

SOLIDWORKS API (.NET VBA C#) — Reference (268/337): ISketchBlockInstance-ISketchContour

SOLIDWORKS API Documentation (converted from CHM)

ISketchBlockInstance (Type)

SOLIDWORKS API Help

[Send comments](#) on this topic.

ISketchBlockInstance Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) : ISketchBlockInstance Interface

Allows access to block instances.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface ISketchBlockInstance
```

Visual Basic (Usage)



```
Dim instance As ISketchBlockInstance
```

C#

```
public interface ISketchBlockInstance
```

C++/CLI

```
public interface class ISketchBlockInstance
```

Visual Basic for Applications (VBA) Syntax

See [SketchBlockInstance](#).

Example

[Get and Set Blocks Data in Any Document \(VBA\)](#)

[Get Block Instance in Part or Assembly \(VBA\)](#)

[Get Blocks in Drawing \(VBA\)](#)

[Create Block Definition and Insert Block Instance \(C#\)](#)

[Create Block Definition and Insert Block Instance \(VBA\)](#)

[Create Block Definition and Insert Block Instance \(VB.NET\)](#)

Remarks

Using this interface, you can:

- get the block instance's [block definition](#)
 - get the sketch in which the block instance is present
 - Get or set the block instance's:
 - Angle
 - Attributes (notes that have tag names and that are not read-only)
 - Layer
 - Leader styles
 - Name
 - Position
 - Scale
 - Text display state
 - Get block instances on a drawing sheet format and edit the sheet format using [IDrawingDoc2::EditTempate](#) and [IModelDoc2::GetActiveSketch2](#) or [IModelDoc2::IGetActiveSketch2](#), which gains access to the [sketch](#) that contains the block instances.
- See [Block Definitions and Block Instances](#) for details.

Accessors

[ILayer::GetItems](#)
[ISketch::GetSketchBlockInstances](#) and [ISketch::!GetSketchBlockInstances](#)
[ISketchBlockDefinition::GetInstances](#) and [ISketchBlockDefinition::!GetInstances](#)
[ISketchManager::ExplodeSketchBlockInstance](#)
[ISketchManager::InsertSketchBlockInstance](#)

 Access Diagram

[SketchBlockInstance](#)

 See Also

[ISketchBlockInstance Members](#)
[SolidWorks.Interop.sldworks Namespace](#)
[ISketchBlockDefinition Interface](#)
[ISketchManager Interface](#)

ISketchBlockInstance Interface Members

[See Also](#) [Properties](#) [Methods](#)

 [SolidWorks.Interop.sldworks Namespace](#) : ISketchBlockInstance Interface

The following tables list the members exposed by [ISketchBlockInstance](#).

 Public Properties

Name	Description
 Angle	Gets or sets the angle around the insertion point which to rotate this block instance.
 BlockToSketchTransform	Gets the MathTransform required to transform coordinates from the sketch block space to the host sketch space.
 Definition	Gets or sets the block definition for this block instance.
 DimensionDisplay	Gets whether dimensions are displayed.
 InstancePosition	Gets or sets the position for this block instance.
 Layer	Gets or sets the name of the layer where this block is located.
 LockAngle	Gets or sets whether the angle around the insertion point which to rotate this block instance is locked.
 Name	Gets or sets the name of this block instance.
 Scale	Obsolete. Superseded by ISketchBlockInstance::Scale2.
 Scale2	Sets the scale for this block instance.
 TextDisplay	Gets or sets whether to display text for this block instance.
 Visible	Gets or sets the visibility of this block instance.

[Top](#)

 Public Methods

Name	Description
 GetArrowHeadStyle	Gets the arrowHead style of the leader on this block instance.
 GetAttachedEntities	Gets the entities to which this block instance is attached.
 GetAttributeCount	Gets the number of attributes for this block instance.
 GetAttributes	Gets the attributes for this block instance.
 GetAttributeValue	Gets the value of the specified attribute for this block instance.
 GetLeaderPoints	Gets the coordinate information for the leader on this block instance.
 GetLeaderStyle	Gets the leader style of this block instance.
 GetScale3	Gets the scale for this block instance.
 GetSketch	Gets the sketch in which this block instance is present.

	IGetAttributes	Gets the attributes for this block instance.
	IGetLeaderPoints	Gets the coordinate information for the leader on this block instance.
	IsNested	Gets whether this sketch block instance is nested within another block definition.
	Select	Selects and marks the block instance.
	SetAttributeValue	Sets the value of the specified attribute for this block instance.
	SetLeader	Sets the leader style for this block instance.

[Top](#)

See Also

[ISketchBlockInstance Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[ISketchBlockDefinition Interface](#)
[ISketchManager Interface](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

ISketchBlockInstance Interface Methods

[See Also](#)

	SolidWorks.Interop.sldworks Namespace : ISketchBlockInstance Interface
---	--

For a list of all members of this type, see [ISketchBlockInstance members](#).

Public Methods

Name	Description
	GetArrowHeadStyle Gets the arrowHead style of the leader on this block instance.
	GetAttachedEntities Gets the entities to which this block instance is attached.
	GetAttributeCount Gets the number of attributes for this block instance.
	GetAttributes Gets the attributes for this block instance.
	GetAttributeValue Gets the value of the specified attribute for this block instance.
	GetLeaderPoints Gets the coordinate information for the leader on this block instance.
	GetLeaderStyle Gets the leader style of this block instance.
	GetScale3 Gets the scale for this block instance.
	GetSketch Gets the sketch in which this block instance is present.
	IGetAttributes Gets the attributes for this block instance.
	IGetLeaderPoints Gets the coordinate information for the leader on this block instance.
	IsNested Gets whether this sketch block instance is nested within another block definition.
	Select Selects and marks the block instance.
	SetAttributeValue Sets the value of the specified attribute for this block instance.
	SetLeader Sets the leader style for this block instance.

[Top](#)

See Also

[ISketchBlockInstance Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[ISketchBlockDefinition Interface](#)
[ISketchManager Interface](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

ISketchBlockInstance Interface Properties

[See Also](#)

	SolidWorks.Interop.sldworks Namespace : ISketchBlockInstance Interface
---	--

For a list of all members of this type, see [ISketchBlockInstance members](#).

Public Properties

Name	Description
 Angle	Gets or sets the angle around the insertion point which to rotate this block instance.
 BlockToSketchTransform	Gets the MathTransform required to transform coordinates from the sketch block space to the host sketch space.
 Definition	Gets or sets the block definition for this block instance.
 DimensionDisplay	Gets whether dimensions are displayed.
 InstancePosition	Gets or sets the position for this block instance.
 Layer	Gets or sets the name of the layer where this block is located.
 LockAngle	Gets or sets whether the angle around the insertion point which to rotate this block instance is locked.
 Name	Gets or sets the name of this block instance.
 Scale	Obsolete. Superseded by ISketchBlockInstance.Scale2 .
 Scale2	Sets the scale for this block instance.
 TextDisplay	Gets or sets whether to display text for this block instance.
 Visible	Gets or sets the visibility of this block instance.

[Top](#)

See Also

[ISketchBlockInstance Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[ISketchBlockDefinition Interface](#)
[ISketchManager Interface](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

Angle Property (ISketchBlockInstance)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchBlockInstance Interface](#) : Angle Property (ISketchBlockInstance)

Gets or sets the angle around the insertion point which to rotate this block instance.

.NET Syntax

Visual Basic (Declaration)

Property Angle As System.Double

Visual Basic (Usage)



```
Dim instance As ISketchBlockInstance  
Dim value As System.Double
```

```
instance.Angle = value
```

```
value = instance.Angle
```

C#

```
System.double Angle {get; set;}
```

C++/CLI

```
property System.double Angle {  
    System.double get();  
    void set ( & System.double value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Angle in radians

Visual Basic for Applications (VBA) Syntax

See [SketchBlockInstance::Angle](#).

Example

[Get and Set Blocks Data in Any Document \(VBA\)](#)
[Get Block Information \(VBA\)](#)

Remarks

You must be editing the block's sketch to change the angle.

See Also

[ISketchBlockInstance Interface](#)
[ISketchBlockInstance Members](#)
[ISketchBlockInstance::LockAngle Property](#)
[ISketchBlockInstance::InstancePosition Property](#)
[ISketchBlockDefinition::InsertionPoint Property](#)

Availability

SOLIDWORKS 2007 FCS, Revision Number 15.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

BlockToSketchTransform Property (ISketchBlockInstance)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchBlockInstance Interface](#) : BlockToSketchTransform Property (ISketchBlockInstance)

Gets the MathTransform required to transform coordinates from the sketch block space to the host sketch space.

.NET Syntax

Visual Basic (Declaration)

ReadOnly Property BlockToSketchTransform As MathTransform

Visual Basic (Usage)



```
Dim instance As ISketchBlockInstance
Dim value As MathTransform

value = instance.BlockToSketchTransform
```

C#

```
MathTransform BlockToSketchTransform {get;}
```

C++/CLI

```
property MathTransform^ BlockToSketchTransform {
    MathTransform^ get();
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

[Math transform](#)

Visual Basic for Applications (VBA) Syntax

See [SketchBlockInstance::BlockToSketchTransform](#).

See Also

[ISketchBlockInstance Interface](#)
[ISketchBlockInstance Members](#)
[ISketchBlockInstance::GetSketch Method](#)

Availability

SOLIDWORKS 2007 FCS, Revision Number 15.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

Definition Property (ISketchBlockInstance)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchBlockInstance Interface](#) : Definition Property (ISketchBlockInstance)

Gets or sets the block definition for this block instance.

.NET Syntax

Visual Basic (Declaration)

Property Definition As SketchBlockDefinition

Visual Basic (Usage)



```
Dim instance As ISketchBlockInstance  
Dim value As SketchBlockDefinition
```

```
instance.Definition = value
```

```
value = instance.Definition
```

C#

```
SketchBlockDefinition Definition {get; set;}
```

C++/CLI

```
property SketchBlockDefinition^ Definition {  
    SketchBlockDefinition^ get();  
    void set ( & SketchBlockDefinition^ value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

[Block definition](#) for this block instance

Visual Basic for Applications (VBA) Syntax

See [SketchBlockInstance::Definition](#).

Example

[Get Block Instance in Part or Assembly \(VBA\)](#)

See Also

[ISketchBlockInstance Interface](#)
[ISketchBlockInstance Members](#)

Availability

SOLIDWORKS 2007 FCS, Revision Number 15.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

DimensionDisplay Property (ISketchBlockInstance)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchBlockInstance Interface](#) : DimensionDisplay Property (ISketchBlockInstance)

Gets whether dimensions are displayed.

.NET Syntax

Visual Basic (Declaration)

```
Property DimensionDisplay As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISketchBlockInstance
Dim value As System.Boolean

instance.DimensionDisplay = value
value = instance.DimensionDisplay
```

C#

```
System.bool DimensionDisplay {get; set;}
```

C++/CLI

```
property System.bool DimensionDisplay {
    System.bool get();
    void set ( & System.bool value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True if dimensions are displayed, false if not

Visual Basic for Applications (VBA) Syntax

See [SketchBlockInstance::DimensionDisplay](#).

See Also

[ISketchBlockInstance Interface](#)
[ISketchBlockInstance Members](#)
[ISketchBlockDefinition::GetDisplayDimensions Method](#)
[ISketchBlockDefinition::IGetDisplayDimensions Method](#)
[ISketchBlockDefinition::GetDisplayDimensionCount Method](#)

Availability

SOLIDWORKS 2007 FCS, Revision Number 15.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetArrowHeadStyle Method (ISketchBlockInstance)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchBlockInstance Interface](#) : GetArrowHeadStyle Method (ISketchBlockInstance)

Gets the arrowhead style of the leader on this block instance.

.NET Syntax

Visual Basic (Declaration)

```
Function GetArrowHeadStyle() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ISketchBlockInstance
Dim value As System.Integer

value = instance.GetArrowHeadStyle()
```

C#

```
System.int GetArrowHeadStyle()
```

C++/CLI

```
System.int GetArrowHeadStyle();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Arrowhead style as defined in [swArrowStyle_e](#)

Visual Basic for Applications (VBA) Syntax

See [SketchBlockInstance::GetArrowHeadStyle](#).

See Also

[ISketchBlockInstance Interface](#)
[ISketchBlockInstance Members](#)
[ISketchBlockInstance::GetLeaderStyle Method](#)
[ISketchBlockInstance::SetLeader Method](#)

Availability

SOLIDWORKS 2007 FCS, Revision Number 15.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetAttachedEntities Method (ISketchBlockInstance)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchBlockInstance Interface](#) : GetAttachedEntities Method (ISketchBlockInstance)

Gets the entities to which this block instance is attached.

.NET Syntax

Visual Basic (Declaration)

```
Function GetAttachedEntities( _  
    ByRef Entities As System.Object, _  
    ByRef EntityType As System.Object _  
    ) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISketchBlockInstance  
Dim Entities As System.Object  
Dim EntityType As System.Object  
Dim value As System.Boolean  
  
value = instance.GetAttachedEntities(Entities, EntityType)
```

C#

```
System.bool GetAttachedEntities(  
    out System.object Entities,  
    out System.object EntityType  
)
```

C++/CLI

```
System.bool GetAttachedEntities(  
& [Out] System.Object^ Entities,  
& [Out] System.Object^ EntityType  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Entities
Array of attached entities
EntityTypes
Array of longs or integers (see [Long vs. Integer](#)) of the types of attached entities (see **Remarks**)

Return Value

True if the entities are retrieved, false if not

Visual Basic for Applications (VBA) Syntax

See [SketchBlockInstance::GetAttachedEntities](#).

Remarks

The arrays returned by this method can contain one or more different object and type.

Possible returned Entities	Possible returned EntityTypes
IFace2	swSelFACES
IEdge	swSelEDGES
IVertex	swSelVERTICES
ISketchSegment	swSelSKETCHSEGS
ISketchPoint	swSelSKETCHPOINTS

A block instance that was inserted with a leader attached to an entity remains attached to that entity even if the leader is hidden. If the leader is shown again later on, the leader still points to the entity and the block instance is still properly associated with the entity.

See Also

[ISketchBlockInstance Interface](#)
[ISketchBlockInstance Members](#)

Availability

SOLIDWORKS 2007 SP2, Revision Number 15.2

GetAttributeCount Method (ISketchBlockInstance)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchBlockInstance Interface](#) : GetAttributeCount Method (ISketchBlockInstance)

Gets the number of attributes for this block instance.

.NET Syntax

Visual Basic (Declaration)

Function GetAttributeCount() As System.Integer

Visual Basic (Usage)



```
Dim instance As ISketchBlockInstance  
Dim value As System.Integer  
  
value = instance.GetAttributeCount()
```

C#

```
System.int GetAttributeCount()
```

C++/CLI

```
System.int GetAttributeCount();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Number of attributes

Visual Basic for Applications (VBA) Syntax

See [SketchBlockInstance::GetAttributeCount](#).

Remarks

Attributes are notes that have tag names and are not read-only.

Call this method before before calling [ISketchBlockInstance::IGetAttributes](#) to get the size of the array for that method.

See Also

[ISketchBlockInstance Interface](#)
[ISketchBlockInstance Members](#)
[ISketchBlockInstance::GetAttributes Method](#)
[ISketchBlockInstance::GetAttributeValue Method](#)
[ISketchBlockInstance::SetAttributeValue Method](#)

Availability

SOLIDWORKS 2007 FCS, Revision Number 15.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetAttributes Method (ISketchBlockInstance)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchBlockInstance Interface](#) : GetAttributes Method (ISketchBlockInstance)

Gets the attributes for this block instance.

.NET Syntax

Visual Basic (Declaration)

```
Function GetAttributes() As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISketchBlockInstance  
Dim value As System.Object  
  
value = instance.GetAttributes()
```

C#

```
System.object GetAttributes()
```

C++/CLI

```
System.Object^ GetAttributes();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Array of attributes (see **Remarks**)

Visual Basic for Applications (VBA) Syntax

See [SketchBlockInstance::GetAttributes](#).

Example

[Get Block Information \(VBA\)](#)

Remarks

Attributes are string notes that have tag names and are not read-only.

Use [ISketchBlockInstance::GetAttributeValue](#) to get attribute's value, or use [ISketchBlockInstance::SetAttributeValue](#) to set an attribute's value.

See Also

[ISketchBlockInstance Interface](#)
[ISketchBlockInstance Members](#)
[ISketchBlockInstance::GetAttributeCount Method](#)
[ISketchBlockInstance::IGetAttributes Method](#)

Availability

SOLIDWORKS 2007 FCS, Revision Number 15.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetAttributeValue Method (ISketchBlockInstance)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchBlockInstance Interface](#) : GetAttributeValue Method (ISketchBlockInstance)

Gets the value of the specified attribute for this block instance.

.NET Syntax

Visual Basic (Declaration)

```
Function GetAttributeValue( _  
    ByVal TagName As System.String _  
) As System.String
```

Visual Basic (Usage)



```
Dim instance As ISketchBlockInstance  
Dim TagName As System.String  
Dim value As System.String  
  
value = instance.GetAttributeValue(TagName)
```

C#

```
System.string GetAttributeValue(  
    System.string TagName  
)
```

C++/CLI

```
System.String^ GetAttributeValue(  
& System.String^ TagName  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

TagName
Tag name of this attribute

Return Value

Value of this attribute

Visual Basic for Applications (VBA) Syntax

See [SketchBlockInstance::GetAttributeValue](#).

Remarks

Attributes are notes that have tag names and are not read-only.

Use [ISketchBlockInstance::SetAttributeValue](#) to set an attribute.

See Also

[ISketchBlockInstance Interface](#)
[ISketchBlockInstance Members](#)
[ISketchBlockInstance::GetAttributeCount Method](#)
[ISketchBlockInstance::GetAttributes Method](#)
[ISketchBlockInstance::IGetAttributes Method](#)

Availability

SOLIDWORKS 2007 FCS, Revision Number 15.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetLeaderPoints Method (ISketchBlockInstance)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchBlockInstance Interface](#) : GetLeaderPoints Method (ISketchBlockInstance)

Gets the coordinate information for the leader on this block instance.

.NET Syntax

Visual Basic (Declaration)

```
Function GetLeaderPoints() As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISketchBlockInstance  
Dim value As System.Object  
  
value = instance.GetLeaderPoints()
```

C#

```
System.object GetLeaderPoints()
```

C++/CLI

```
System.Object^ GetLeaderPoints();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Array containing leader point information (see [Remarks](#))

Visual Basic for Applications (VBA) Syntax

See [SketchBlockInstance::GetLeaderPoints](#).

Remarks

For the COM interface, you must specify an array size of 9. Depending on the number of points in the leader, this array might only be partially filled upon return from the API. For the OLE Automation interface, the returned SafeArray is sized appropriately for the number of points returned.

You must determine the number of points in the leader to use the data returned by this method. The number of points is a function of the number of segments in the leader. The leader line can have one or two segments depending on whether it is straight or bent. Use [ISketchBlockInstance::GetLeaderStyle](#) to determine the number of points in the leader.

If [SketchBlockInstance::GetLeaderStyle](#) returns...

Then the number of points equals...

swNO_LEADER	0
swSTRAIGHT	2
swBENT	3

The format of the return array is:

- *retval*[0] = X-coordinate of first leader point
- *retval*[1] = Y-coordinate of first leader point
- *retval*[2] = Z-coordinate of first leader point
- *retval*[3] = X-coordinate of second leader point
- *retval*[4] = Y-coordinate of second leader point
- *retval*[5] = Z-coordinate of second leader point
- *retval*[6] = X-coordinate of third leader point
- *retval*[7] = Y-coordinate of third leader point
- *retval*[8] = Z-coordinate of third leader point

See Also

[ISketchBlockInstance Interface](#)
[ISketchBlockInstance Members](#)
[ISketchBlockInstance::IGetLeaderPoints Method](#)
[ISketchBlockInstance::SetLeader Method](#)

Availability

SOLIDWORKS 2007 FCS, Revision Number 15.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetLeaderStyle Method (ISketchBlockInstance)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchBlockInstance Interface](#) : GetLeaderStyle Method (ISketchBlockInstance)

Gets the leader style of this block instance.

.NET Syntax

Visual Basic (Declaration)

```
Function GetLeaderStyle() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ISketchBlockInstance
Dim value As System.Integer

value = instance.GetLeaderStyle()
```

C#

```
System.int GetLeaderStyle()
```

C++/CLI

```
System.int GetLeaderStyle();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Leader style as defined in [swLeaderStyle_e](#)

Visual Basic for Applications (VBA) Syntax

See [SketchBlockInstance::GetLeaderStyle](#).

Remarks

Use [ISketchBlockInstance::SetLeader](#) to set the leader style.

See Also

[ISketchBlockInstance Interface](#)
[ISketchBlockInstance Members](#)
[ISketchBlockInstance::GetLeaderPoints Method](#)
[ISketchBlockInstance::!GetLeaderPoints Method](#)

Availability

SOLIDWORKS 2007 FCS, Revision Number 15.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetScale3 Method (ISketchBlockInstance)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchBlockInstance Interface](#) : GetScale3 Method (ISketchBlockInstance)

Gets the scale for this block instance.

.NET Syntax

Visual Basic (Declaration)

```
Function GetScale3( _  
    ByVal Ignoreparentscale As System.Boolean _  
) As System.Double
```

Visual Basic (Usage)



```
Dim instance As ISketchBlockInstance  
Dim Ignoreparentscale As System.Boolean  
Dim value As System.Double  
  
value = instance.GetScale3(Ignoreparentscale)
```

C#

```
System.double GetScale3(  
    System.bool Ignoreparentscale  
)
```

C++/CLI

```
System.double GetScale3(  
& System.bool Ignoreparentscale  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Ignoreparentscale
True to ignore the parent scale, false to not

Return Value

Scale: 0.0000001 to 500000

Visual Basic for Applications (VBA) Syntax

See [SketchBlockInstance::GetScale3](#).

Remarks

Use [ISketchBlockInstance::Scale2](#) to set the scale.

See Also

[ISketchBlockInstance Interface](#)
[ISketchBlockInstance Members](#)

Availability

SOLIDWORKS 2024 SP01, Revision Number 32.1

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetSketch Method (ISketchBlockInstance)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchBlockInstance Interface](#) : GetSketch Method (ISketchBlockInstance)

Gets the sketch in which this block instance is present.

.NET Syntax

Visual Basic (Declaration)

```
Function GetSketch() As Sketch
```

Visual Basic (Usage)



```
Dim instance As ISketchBlockInstance  
Dim value As Sketch
```

```
value = instance.GetSketch()
```

C#

```
Sketch GetSketch()
```

C++/CLI

```
Sketch^ GetSketch();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

[Sketch](#)

Visual Basic for Applications (VBA) Syntax

See [SketchBlockInstance::GetSketch](#).

Example

[Get and Set Blocks Data in Any Document \(VBA\)](#)

See Also

[ISketchBlockInstance Interface](#)
[ISketchBlockInstance Members](#)
[ISketchBlockInstance::BlockToSketchTransform Property](#)

Availability

SOLIDWORKS 2007 FCS, Revision Number 15.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

IGetAttributes Method (ISketchBlockInstance)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchBlockInstance Interface](#) : IGetAttributes Method (ISketchBlockInstance)

Gets the attributes for this block instance.

Visual Basic Syntax

Visual Basic (Declaration)

```
Function IGetAttributes( _  
    ByVal Count As System.Integer _  
) As Note
```

Visual Basic (Usage)



```
Dim instance As ISketchBlockInstance  
Dim Count As System.Integer  
Dim value As Note  
  
value = instance.IGetAttributes(Count)
```

C#

```
Note IGetAttributes(  
    System.int Count  
)
```

C++/CLI

```
Note^ IGetAttributes(  
&    System.int Count  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Count

Number of attributes

Return Value

- in-process, unmanaged C++: Pointer to an array of [notes](#)
- VBA, VB.NET, C#, and C++/CLI: Not supported

See [In-process Methods](#) for details about this type of method.

Remarks

Attributes are notes that have tag names and are not read-only.

Before calling this method, call [ISketchBlockInstance::GetAttributeCount](#) to get the value for Count.

Use [ISketchBlockInstance::GetAttributeValue](#) to get attribute's value, or use [ISketchBlockInstance::SetAttributeValue](#) to set an attribute's value.

See Also

[ISketchBlockInstance Interface](#)
[ISketchBlockInstance Members](#)
[ISketchBlockInstance::GetAttributes Method](#)
[ISketchBlockInstance::GetAttributeValue Method](#)
[ISketchBlockInstance::SetAttributeValue Method](#)

Availability

SOLIDWORKS 2007 FCS, Revision Number 15.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

IGetLeaderPoints Method (ISketchBlockInstance)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchBlockInstance Interface](#) : IGetLeaderPoints Method (ISketchBlockInstance)

Gets the coordinate information for the leader on this block instance.

Visual Basic Syntax

Visual Basic (Declaration)

Function IGetLeaderPoints() As System.Double

Visual Basic (Usage)



```
Dim instance As ISketchBlockInstance
Dim value As System.Double
```

```
value = instance.IGetLeaderPoints()
```

C#

```
System.double IGetLeaderPoints()
```

C++/CLI

```
System.double IGetLeaderPoints();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

- in-process, unmanaged C++: Pointer to an array containing leader point information (see **Remarks**)
 - VBA, VB.NET, C#, and C++/CLI: Not supported
- See [In-process Methods](#) for details about this type of method.

Remarks

For the COM interface, you must specify an array size of 9. Depending on the number of points in the leader, this array might only be partially filled upon return from the API. For the OLE Automation interface, the returned SafeArray is sized appropriately for the number of points returned.

You must determine the number of points in the leader to use the data returned by this method. The number of points is a function of the number of segments in the leader. The leader line can have one or two segments depending on whether it is straight or bent. Use [ISketchBlockInstance::GetLeaderStyle](#) to determine the number of points in the leader.

If SketchBlockInstance::GetLeaderStyle returns...	Then the number of points equals...
swNO_LEADER	0
swSTRAIGHT	2
swBENT	3

The format of the return array is:

- *retval*[0] = X-coordinate of first leader point
- *retval*[1] = Y-coordinate of first leader point
- *retval*[2] = Z-coordinate of first leader point
- *retval*[3] = X-coordinate of second leader point
- *retval*[4] = Y-coordinate of second leader point
- *retval*[5] = Z-coordinate of second leader point
- *retval*[6] = X-coordinate of third leader point
- *retval*[7] = Y-coordinate of third leader point
- *retval*[8] = Z-coordinate of third leader point

See Also

[ISketchBlockInstance Interface](#)
[ISketchBlockInstance Members](#)
[ISketchBlockInstance::GetLeaderPoints Method](#)
[ISketchBlockInstance::SetLeader Method](#)

Availability

SOLIDWORKS 2007 FCS, Revision Number 15.0



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchBlockInstance Interface](#) : InstancePosition Property (ISketchBlockInstance)

Gets or sets the position for this block instance.

.NET Syntax

Visual Basic (Declaration)

```
Property InstancePosition As MathPoint
```

Visual Basic (Usage)



```
Dim instance As ISketchBlockInstance  
Dim value As MathPoint
```

```
instance.InstancePosition = value
```

```
value = instance.InstancePosition
```

C#

```
MathPoint InstancePosition {get; set;}
```

C++/CLI

```
property MathPoint^ InstancePosition {  
    MathPoint^ get();  
    void set ( & MathPoint^ value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

[Position](#) of this block instance

Visual Basic for Applications (VBA) Syntax

See [SketchBlockInstance::InstancePosition](#).

Example

[Get and Set Blocks Data in Any Document \(VBA\)](#)

See Also

[ISketchBlockInstance Interface](#)
[ISketchBlockInstance Members](#)
[ISketchBlockDefinition::InsertionPoint Property](#)
[ISketchBlockInstance::Angle Property](#)
[ISketchBlockInstance::LockAngle Property](#)

Availability

SOLIDWORKS 2007 FCS, Revision Number 15.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

IsNested Method (ISketchBlockInstance)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchBlockInstance Interface](#) : IsNested Method (ISketchBlockInstance)

Gets whether this sketch block instance is nested within another block definition.

.NET Syntax

Visual Basic (Declaration)

```
Function IsNested() As System.Boolean
```

```
Dim instance As ISketchBlockInstance
Dim value As System.Boolean

value = instance.IsNested()
```

C#

```
System.bool IsNested()
```

C++/CLI

```
System.bool IsNested();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

True if nested within another block definition, false if not

Visual Basic for Applications (VBA) Syntax

See [SketchBlockInstance::IsNested](#).

See Also

[ISketchBlockInstance Interface](#)
[ISketchBlockInstance Members](#)

Availability

SOLIDWORKS 2024 SP01, Revision Number 32.1

SOLIDWORKS API Help

[Send comments](#) on this topic.

Layer Property (ISketchBlockInstance)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchBlockInstance Interface](#) : Layer Property (ISketchBlockInstance)

Gets or sets the name of the layer where this block is located.

.NET Syntax

Visual Basic (Declaration)

```
Property Layer As System.String
```

Visual Basic (Usage)

```
Dim instance As ISketchBlockInstance
Dim value As System.String
```

```
instance.Layer = value
```

```
value = instance.Layer
```

C#

```
System.string Layer {get; set;}
```

C++/CLI

```
property System.String^ Layer {
    System.String^ get();
    void set ( & System.String^ value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Name of layer

Visual Basic for Applications (VBA) Syntax

See [SketchBlockInstance::Layer](#).

See Also

[ISketchBlockInstance Interface](#)
[ISketchBlockInstance Members](#)

Availability

SOLIDWORKS 2007 FCS, Revision Number 15.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

LockAngle Property (ISketchBlockInstance)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchBlockInstance Interface](#) : LockAngle Property (ISketchBlockInstance)

Gets or sets whether the angle around the insertion point which to rotate this block instance is locked.

.NET Syntax

Visual Basic (Declaration)

Property LockAngle As System.Boolean

Visual Basic (Usage)



```
Dim instance As ISketchBlockInstance  
Dim value As System.Boolean
```

```
instance.LockAngle = value
```

```
value = instance.LockAngle
```

C#

```
System.bool LockAngle {get; set;}
```

C++/CLI

```
property System.bool LockAngle {  
    System.bool get();  
    void set ( & System.bool value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True to lock the angle of this block instance, false to not

Visual Basic for Applications (VBA) Syntax

See [SketchBlockInstance::LockAngle](#).

See Also

[ISketchBlockInstance Interface](#)
[ISketchBlockInstance Members](#)
[ISketchBlockInstance::Angle Property](#)
[ISketchBlockInstance::InstancePosition Property](#)
[ISketchBlockDefinition::InsertionPoint Property](#)

Availability

Name Property (ISketchBlockInstance)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchBlockInstance Interface](#) : Name Property (ISketchBlockInstance)

Gets or sets the name of this block instance.

.NET Syntax

Visual Basic (Declaration)

```
Property Name As System.String
```

Visual Basic (Usage)



```
Dim instance As ISketchBlockInstance  
Dim value As System.String
```

```
instance.Name = value
```

```
value = instance.Name
```

C#

```
System.string Name {get; set;}
```

C++/CLI

```
property System.String^ Name {  
    System.String^ get();  
    void set ( & System.String^ value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Name of this block instance

Visual Basic for Applications (VBA) Syntax

See [SketchBlockInstance::Name](#).

Example

[Get and Set Blocks Data in Any Document \(VBA\)](#)
[Get Block Information \(VBA\)](#)
[Get Blocks in Drawing \(VBA\)](#)

Remarks

After setting the name of a block instance, use [IFeatureManager::UpdateFeatureTree](#) to see its name in the FeatureManager design tree.

See Also

[ISketchBlockInstance Interface](#)
[ISketchBlockInstance Members](#)

Availability

Scale Property (ISketchBlockInstance)

[See Also](#)



Obsolete. Superseded by [ISketchBlockInstance::Scale2](#).

.NET Syntax

Visual Basic (Declaration)

Property Scale As System.Double

Visual Basic (Usage)



```
Dim instance As ISketchBlockInstance  
Dim value As System.Double
```

```
instance.Scale = value
```

```
value = instance.Scale
```

C#

```
System.double Scale {get; set;}
```

C++/CLI

```
property System.double Scale {  
    System.double get();  
    void set ( & System.double value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [SketchBlockInstance::Scale](#).

See Also

[ISketchBlockInstance Interface](#)
[ISketchBlockInstance Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

Scale2 Property (ISketchBlockInstance)

[See Also](#)



SolidWorks.Interop.sldworks Namespace > [ISketchBlockInstance Interface](#) : Scale2 Property (ISketchBlockInstance)

Sets the scale for this block instance.

.NET Syntax

Visual Basic (Declaration)

Property Scale2 As System.Double

Visual Basic (Usage)



```
Dim instance As ISketchBlockInstance  
Dim value As System.Double
```

```
instance.Scale2 = value
```

```
value = instance.Scale2
```

C#

```
System.double Scale2 {get; set;}
```

C++/CLI

```
property System.double Scale2 {
    System.double get();
    void set ( & System.double value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Scale: 0.0000001 to 500000 (see **Remarks**)

Visual Basic for Applications (VBA) Syntax

See [SketchBlockInstance::Scale2](#).

Remarks

The getter of this property is obsolete. It has been superseded by [ISketchBlockInstance::GetScale3](#).

See Also

[ISketchBlockInstance Interface](#)
[ISketchBlockInstance Members](#)

Availability

SOLIDWORKS 2007 SP2, Revision Number 15.2

SOLIDWORKS API Help

[Send comments on this topic.](#)

Select Method (ISketchBlockInstance)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchBlockInstance Interface](#) : Select Method (ISketchBlockInstance)

Selects and marks the block instance.

.NET Syntax

Visual Basic (Declaration)

```
Function Select( _
    ByVal Append As System.Boolean, _
    ByVal Data As SelectData _
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISketchBlockInstance
Dim Append As System.Boolean
Dim Data As SelectData
Dim value As System.Boolean
```

```
value = instance.Select(Append, Data)
```

C#

```
System.bool Select(
    System.bool Append,
    SelectData Data
)
```

C++/CLI

```
System.bool Select(
    & System.bool Append,
    & SelectData^ Data
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Append

True appends the detail circle to the selection list, false replaces the selection list with this block instance

Data

[ISelectData](#) object

Return Value

True if the block instance is selected, false if not

Visual Basic for Applications (VBA) Syntax

See [SketchBlockInstance::Select](#).

Example

[Get Block Definitions in Part or Assembly \(VBA\)](#)

See Also

[ISketchBlockInstance Interface](#)

[ISketchBlockInstance Members](#)

Availability

SOLIDWORKS 2007 FCS, Revision Number 15.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

SetAttributeValue Method (ISketchBlockInstance)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchBlockInstance Interface](#) : SetAttributeValue Method (ISketchBlockInstance)

Sets the value of the specified attribute for this block instance.

.NET Syntax

Visual Basic (Declaration)

```
Function SetAttributeValue( _  
    ByVal TagName As System.String, _  
    ByVal Value As System.String _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISketchBlockInstance  
Dim TagName As System.String  
Dim Value As System.String  
Dim value As System.Boolean  
  
value = instance.SetAttributeValue(TagName, Value)
```

C#

```
System.bool SetAttributeValue(  
    System.string TagName,  
    System.string Value  
)
```

C++/CLI

```
System.bool SetAttributeValue(  
& System.String^ TagName,  
& System.String^ Value  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

TagName
Tag name of this attribute
Value
Value for this attribute

Return Value

True if the attribute's value is set, false if not

Visual Basic for Applications (VBA) Syntax

See [ISketchBlockInstance::SetAttributeValue](#).

Remarks

Attributes are string notes that have tag names and are not read-only.

Use [ISketchBlockInstance::GetAttributes](#) or [ISketchBlockInstance::IGetAttributes](#) to get the attributes for this block instance. Use [ISketchBlockInstance::GetAttributeValue](#) to get an attribute's value.

See Also

[ISketchBlockInstance Interface](#)
[ISketchBlockInstance Members](#)

Availability

SOLIDWORKS 2007 FCS, Revision Number 15.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

SetLeader Method (ISketchBlockInstance)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchBlockInstance Interface](#) : SetLeader Method (ISketchBlockInstance)

Sets the leader style for this block instance.

.NET Syntax

Visual Basic (Declaration)

```
Function SetLeader( _  
    ByVal LeaderStyle As System.Integer, _  
    ByVal ArrowHeadStyle As System.Integer _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISketchBlockInstance  
Dim LeaderStyle As System.Integer  
Dim ArrowHeadStyle As System.Integer  
Dim value As System.Boolean
```

```
value = instance.SetLeader(LeaderStyle, ArrowHeadStyle)
```

C#

```
System.bool SetLeader(  
    System.int LeaderStyle,  
    System.int ArrowHeadStyle  
)
```

C++/CLI

```
System.bool SetLeader(  
& System.int LeaderStyle,  
& System.int ArrowHeadStyle  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

LeaderStyle

Leader style as defined in [swLeaderStyle_e](#)

ArrowHeadStyle

Arrowhead style as defined in [swArrowStyle_e](#)

Return Value

True if the leader style is set, false if not

Visual Basic for Applications (VBA) Syntax

See [SketchBlockInstance::SetLeader](#).

See Also

[ISketchBlockInstance Interface](#)

[ISketchBlockInstance Members](#)

[ISketchBlockInstance::GetArrowHeadStyle Method](#)

[ISketchBlockInstance::GetLeaderPoints Method](#)

[ISketchBlockInstance::GetLeaderStyle Method](#)

[ISketchBlockInstance::IGetLeaderPoints Method](#)

Availability

SOLIDWORKS 2007 FCS, Revision Number 15.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

TextDisplay Property (ISketchBlockInstance)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchBlockInstance Interface](#) : TextDisplay Property (ISketchBlockInstance)

Gets or sets whether to display text for this block instance.

.NET Syntax

Visual Basic (Declaration)

```
Property TextDisplay As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ISketchBlockInstance  
Dim value As System.Integer
```

```
instance.TextDisplay = value
```

```
value = instance.TextDisplay
```

C#

```
System.int TextDisplay {get; set;}
```

C++/CLI

```
property System.int TextDisplay {  
    System.int get();  
    void set ( & System.int value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Display state as defined in [swBlockInstanceTextDisplay_e](#)

Visual Basic for Applications (VBA) Syntax

See [SketchBlockInstance::TextDisplay](#).

Example

[Get Block Information \(VBA\)](#)

See Also

[ISketchBlockInstance Interface](#)
[ISketchBlockInstance Members](#)

Availability

SOLIDWORKS 2007 FCS, Revision Number 15.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

Visible Property (ISketchBlockInstance)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchBlockInstance Interface](#) : Visible Property (ISketchBlockInstance)

Gets or sets the visibility of this block instance.

.NET Syntax

Visual Basic (Declaration)

Property Visible As System.Integer

Visual Basic (Usage)



```
Dim instance As ISketchBlockInstance  
Dim value As System.Integer
```

```
instance.Visible = value
```

```
value = instance.Visible
```

C#

```
System.int Visible {get; set;}
```

C++/CLI

```
property System.int Visible {  
    System.int get();  
    void set ( & System.int value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Block instance's visibility as defined by [swAnnotationVisibilityState_e](#)

Visual Basic for Applications (VBA) Syntax

See [SketchBlockInstance::Visible](#).

Example

[Change Visibility of Sketch Block Instances \(C#\)](#)
[Change Visibility of Sketch Block Instances \(VB.NET\)](#)
[Change Visibility of Sketch Block Instances \(VBA\)](#)

See Also

[ISketchBlockInstance Interface](#)
[ISketchBlockInstance Members](#)

ISketchContour (Type)

ISketchContour Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) : ISketchContour Interface

Provides access to sketch contours.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface ISketchContour
```

Visual Basic (Usage)

```
Dim instance As ISketchContour
```

C#

```
public interface ISketchContour
```

C++/CLI

```
public interface class ISketchContour
```

Visual Basic for Applications (VBA) Syntax

See [SketchContour](#).

Example

[Get Sketch Contours \(VBA\)](#)
[Create Extrude Feature Using Sketch Contours \(C#\)](#)
[Create Extrude Feature Using Sketch Contours \(VB.NET\)](#)
[Create Extrude Feature Using Sketch Contours \(VBA\)](#)

Remarks

Sketch contours are a collection of end-point connected sketch segments that might, or might not, form a face depending on whether the sketch segments form a closed area.

Accessors

[IExtrudeFeatureData2::Contours](#)
[IExtrudeFeatureData2::IGetContours](#)
[IRvolveFeatureData2::Contours](#)
[IRvolveFeatureData2::IGetContours](#)
[ISketch::GetSketchContours](#) and [ISketch::IGetSketchContours](#)
[ISplitLineFeatureData::Contours](#)
[ISplitLineFeatureData::IGetContours](#)

Access Diagram

[SketchContour](#)

See Also

[ISketchContour Members](#)
[SolidWorks.Interop.sldworks Namespace](#)

ISketchContour Interface Methods

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) : ISketchContour Interface

For a list of all members of this type, see [ISketchContour members](#).

Public Methods

Name	Description
 DeSelect	Deselects the sketch contour.
 GetEdges	Gets the edges in this sketch contour.
 GetEdgesCount	Gets the number of edges in this sketch contour.
 GetSketchSegments	Gets the sketch segments for this sketch contour.
 GetSketchSegmentsCount	Gets the number of sketch segments for this sketch contour.
 IGetEdges	Gets the edges in this sketch contour.
 IGetSketchSegments	Gets the sketch segments for this sketch contour.
 IsClosed	Gets whether this sketch contour is open or closed.
 Select	Obsolete. Superseded by ISketchContour.Select2
 Select2	Selects the sketch contour and marks it.

[Top](#)

See Also

[ISketchContour Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

ISketchContour Interface Members

[See Also](#) [Properties](#) [Methods](#)



[SolidWorks.Interop.sldworks Namespace](#) : ISketchContour Interface

The following tables list the members exposed by [ISketchContour](#).

Public Properties

Name	Description
 Sketch	Gets the sketch for this sketch contour.

[Top](#)

Public Methods

Name	Description
 DeSelect	Deselects the sketch contour.
 GetEdges	Gets the edges in this sketch contour.
 GetEdgesCount	Gets the number of edges in this sketch contour.
 GetSketchSegments	Gets the sketch segments for this sketch contour.
 GetSketchSegmentsCount	Gets the number of sketch segments for this sketch contour.
 IGetEdges	Gets the edges in this sketch contour.
 IGetSketchSegments	Gets the sketch segments for this sketch contour.
 IsClosed	Gets whether this sketch contour is open or closed.
 Select	Obsolete. Superseded by ISketchContour.Select2
 Select2	Selects the sketch contour and marks it.

[Top](#)

See Also

[ISketchContour Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

ISketchContour Interface Properties

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) : ISketchContour Interface

For a list of all members of this type, see [ISketchContour members](#).

Public Properties

Name	Description
 Sketch	Gets the sketch for this sketch contour.

[Top](#)

See Also

[ISketchContour Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

DeSelect Method (ISketchContour)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchContour Interface](#) : DeSelect Method (ISketchContour)

Deselects the sketch contour.

.NET Syntax

Visual Basic (Declaration)

```
Function DeSelect() As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISketchContour  
Dim value As System.Boolean  
  
value = instance.DeSelect()
```

C#

```
System.bool DeSelect()
```

C++/CLI

```
System.bool DeSelect();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

True if the sketch contour is deselected, false if not

Visual Basic for Applications (VBA) Syntax

See [SketchContour::DeSelect](#).

See Also

[ISketchContour Interface](#)
[ISketchContour Members](#)
[ISketchContour::Select2 Method](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetEdges Method (ISketchContour)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchContour Interface](#) : GetEdges Method (ISketchContour)

Gets the edges in this sketch contour.

.NET Syntax

Visual Basic (Declaration)

```
Function GetEdges() As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISketchContour  
Dim value As System.Object  
  
value = instance.GetEdges()
```

C#

```
System.object GetEdges()
```

C++/CLI

```
System.Object^ GetEdges();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Array of the [edges](#)

Visual Basic for Applications (VBA) Syntax

See [SketchContour::GetEdges](#).

Example

[Get Sketch Contours \(VBA\)](#)

See Also

[ISketchContour Interface](#)
[ISketchContour Members](#)
[ISketchContour::GetEdgesCount Method](#)
[ISketchContour::!GetEdges Method](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetEdgesCount Method (ISketchContour)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchContour Interface](#) : GetEdgesCount Method (ISketchContour)

Gets the number of edges in this sketch contour.

.NET Syntax

Visual Basic (Declaration)

```
Function GetEdgesCount() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ISketchContour  
Dim value As System.Integer
```

```
value = instance.GetEdgesCount()
```

C#

```
System.int GetEdgesCount()
```

C++/CLI

```
System.int GetEdgesCount();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Number of edges

Visual Basic for Applications (VBA) Syntax

See [SketchContour::GetEdgesCount](#).

Remarks

Call this method before calling [ISketchContour::IGetEdges](#) to get the size of the array for that method.

See Also

[ISketchContour Interface](#)
[ISketchContour Members](#)
[ISketchContour::GetEdges Method](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetSketchSegments Method (ISketchContour)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchContour Interface](#) : GetSketchSegments Method (ISketchContour)

Gets the sketch segments for this sketch contour.

.NET Syntax

Visual Basic (Declaration)

```
Function GetSketchSegments() As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISketchContour  
Dim value As System.Object
```

```
value = instance.GetSketchSegments()
```

C#

```
System.object GetSketchSegments()
```

C++/CLI

```
System.Object^ GetSketchSegments();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Array of [sketch segments](#)

Visual Basic for Applications (VBA) Syntax

See [SketchContour::GetSketchSegments](#).

Example

[Get Sketch Contours \(VBA\)](#)
[Get Corresponding Objects in Assembly Component \(C#\)](#)
[Get Corresponding Objects in Assembly Component \(VB.NET\)](#)
[Get Corresponding Objects in Assembly Component \(VBA\)](#)

See Also

[ISketchContour Interface](#)
[ISketchContour Members](#)
[ISketchContour::GetSketchSegmentsCount Method](#)
[ISketchContour::IGetSketchSegments Method](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetSketchSegmentsCount Method (ISketchContour)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchContour Interface](#) : GetSketchSegmentsCount Method (ISketchContour)

Gets the number of sketch segments for this sketch contour.

.NET Syntax

Visual Basic (Declaration)

```
Function GetSketchSegmentsCount() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ISketchContour  
Dim value As System.Integer  
  
value = instance.GetSketchSegmentsCount()
```

C#

```
System.int GetSketchSegmentsCount()
```

C++/CLI

```
System.int GetSketchSegmentsCount();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Number of sketch segments

Visual Basic for Applications (VBA) Syntax

See [SketchContour::GetSketchSegmentsCount](#).

Remarks

Call this method before calling [ISketchContour::IGetSketchSegments](#) to get the size of the array for that method.

See Also

[ISketchContour Interface](#)
[ISketchContour Members](#)
[ISketchContour::GetSketchSegments Method](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

IGetEdges Method (ISketchContour)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchContour Interface](#) : IGetEdges Method (ISketchContour)

Gets the edges in this sketch contour.

.NET Syntax

Visual Basic (Declaration)

```
Function IGetEdges( _  
    ByVal Count As System.Integer _  
) As Edge
```

Visual Basic (Usage)



```
Dim instance As ISketchContour  
Dim Count As System.Integer  
Dim value As Edge
```

```
value = instance.IGetEdges(Count)
```

C#

```
Edge IGetEdges(  
    System.int Count  
)
```

C++/CLI

```
Edge^ IGetEdges(  
& System.int Count  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Count
Number of edges

Return Value

- in-process, unmanaged C++: Pointer to an array of the [edges](#)
 - VBA, VB.NET, C#, and C++/CLI: Not supported
- See [In-process Methods](#) for details about this type of method.

Remarks

Before calling this method, call [ISketchContour::GetEdgesCount](#) to get the value for Count.

See Also

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

IGetSketchSegments Method (ISketchContour)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchContour Interface](#) : IGetSketchSegments Method (ISketchContour)

Gets the sketch segments for this sketch contour.

.NET Syntax

Visual Basic (Declaration)

```
Function IGetSketchSegments( _  
    ByVal Count As System.Integer _  
) As SketchSegment
```

Visual Basic (Usage)



```
Dim instance As ISketchContour  
Dim Count As System.Integer  
Dim value As SketchSegment  
  
value = instance.IGetSketchSegments(Count)
```

C#

```
SketchSegment IGetSketchSegments(  
    System.int Count  
)
```

C++/CLI

```
SketchSegment^ IGetSketchSegments(  
    & System.int Count  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Count
Number of sketch segments

Return Value

- in-process, unmanaged C++: Pointer to an array of [sketch segments](#)
 - VBA, VB.NET, C#, and C++/CLI: Not supported
- See [In-process Methods](#) for details about this type of method.

Remarks

Before calling this method, call [ISketchContour::GetSketchSegmentsCount](#) to get the value for Count.

See Also

[ISketchContour Interface](#)
[ISketchContour Members](#)
[ISketchContour::GetSketchSegments Method](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

IsClosed Method (ISketchContour)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchContour Interface](#) : IsClosed Method (ISketchContour)

Gets whether this sketch contour is open or closed.

.NET Syntax

Visual Basic (Declaration)

```
Function IsClosed() As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISketchContour  
Dim value As System.Boolean  
  
value = instance.IsClosed()
```

C#

```
System.bool IsClosed()
```

C++/CLI

```
System.bool IsClosed();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

True if the sketch contour is open, false if closed

Visual Basic for Applications (VBA) Syntax

See [SketchContour::IsClosed](#).

Example

[Get Sketch Contours \(VBA\)](#)
[Create Extrude Feature Using Sketch Contours \(C#\)](#)
[Create Extrude Feature Using Sketch Contours \(VB.NET\)](#)
[Create Extrude Feature Using Sketch Contours \(VBA\)](#)

Remarks

This method works even if the sketch is suppressed.

See Also

[ISketchContour Interface](#)
[ISketchContour Members](#)

Availability

SOLIDWORKS 2009 FCS, Revision Number 17.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

Select Method (ISketchContour)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchContour Interface](#) : Select Method (ISketchContour)

Obsolete. Superseded by [ISketchContour::Select2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function Select( _  
    ByVal Append As System.Boolean, _  
    ByVal Mark As System.Integer _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISketchContour  
Dim Append As System.Boolean  
Dim Mark As System.Integer  
Dim value As System.Boolean  
  
value = instance.Select(Append, Mark)
```

C#

```
System.bool Select(  
    System.bool Append,  
    System.int Mark  
)
```

C++/CLI

```
System.bool Select(  
& System.bool Append,  
& System.int Mark  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Append

Mark

Visual Basic for Applications (VBA) Syntax

See [SketchContour::Select](#).

See Also

[ISketchContour Interface](#)
[ISketchContour Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

Select2 Method (ISketchContour)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchContour Interface](#) : Select2 Method (ISketchContour)

Selects the sketch contour and marks it.

.NET Syntax

Visual Basic (Declaration)

```
Function Select2( _  
    ByVal Append As System.Boolean, _  
    ByVal Data As SelectData _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISketchContour  
Dim Append As System.Boolean  
Dim Data As SelectData  
Dim value As System.Boolean
```

```
value = instance.Select2(Append, Data)
```

C#

```
System.bool Select2(  
    System.bool Append,  
    SelectData Data  
)
```

C++/CLI

```
System.bool Select2(  
& System.bool Append,  
& SelectData^ Data  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Append

True appends the selection to the selection list, false replaces the selection list with this selection

Data

[ISelectData](#) object

Return Value

True if sketch contour selected, false if not

Visual Basic for Applications (VBA) Syntax

See [SketchContour::Select2](#).

Example

[Get Sketch Contours \(VBA\)](#)

[Get Sketch Contours \(VB.NET\)](#)

[Get Sketch Contours \(C#\)](#)

[Get Corresponding Objects in Assembly Component \(C#\)](#)

[Get Corresponding Objects in Assembly Component \(VB.NET\)](#)

[Get Corresponding Objects in Assembly Component \(VBA\)](#)

See Also

[ISketchContour Interface](#)

[ISketchContour Members](#)

[ISketchContour::DeSelect Method](#)

Availability

SOLIDWORKS 2004 FCS, Revision Number 12.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

Sketch Property (ISketchContour)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISketchContour Interface](#) : Sketch Property (ISketchContour)

Gets the sketch for this sketch contour.

.NET Syntax

Visual Basic (Declaration)

ReadOnly Property Sketch As Sketch

Visual Basic (Usage)



Copy Code

```
Dim instance As ISketchContour  
Dim value As Sketch
```

```
value = instance.Sketch
```

C#

```
Sketch Sketch {get;}
```

C++/CLI

```
property Sketch^ Sketch {  
    Sketch^ get();  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

[Sketch](#)

Visual Basic for Applications (VBA) Syntax

See [SketchContour::Sketch](#).

See Also

[ISketchContour Interface](#)
[ISketchContour Members](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0