

SOLIDWORKS API (.NET, VBA, C#) — Reference

(301/337): ISurfaceKnitFeatureData- ISurfaceParameterizationData

SOLIDWORKS API Documentation (converted from CHM)

ISurfaceKnitFeatureData (Type)

ISurfaceKnitFeatureData Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) : ISurfaceKnitFeatureData Interface

Allows access to a Surface-Knit feature.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface ISurfaceKnitFeatureData
```

Visual Basic (Usage)



```
Dim instance As ISurfaceKnitFeatureData
```

C#

```
public interface ISurfaceKnitFeatureData
```

C++/CLI

```
public interface class ISurfaceKnitFeatureData
```

Visual Basic for Applications (VBA) Syntax

See [SurfaceKnitFeatureData](#).

Example

[Create Surface Knit Feature \(VB.NET\)](#)
[Create Surface Knit Feature \(VBA\)](#)
[Create Surface Knit Feature \(C#\)](#)

Accessors

[IFeature::GetDefinition](#) and [IFeature::!GetDefinition](#)

Access Diagram

[SurfaceKnitFeatureData](#)

See Also

[ISurfaceKnitFeatureData Members](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IFeatureManager::InsertSewRefSurface Method](#)

ISurfaceKnitFeatureData Interface Methods

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) : ISurfaceKnitFeatureData Interface

For a list of all members of this type, see [ISurfaceKnitFeatureData members](#).

Public Methods

Name	Description
 AccessSelections	Accesses the selections that define this Surface-Knit feature.
 GetEntitiesCount	Gets the number of knit faces and surfaces for this Surface-Knit feature.

 IAccessSelections	Accesses the selections that define this Surface-Knit feature.
 IGetEntities	Gets the knitted faces and surfaces for this Surface-Knit feature.
 ISetEntities	Sets the faces and surfaces to knit.
 ReleaseSelectionAccess	Releases access to the selections for this Surface-Knit feature.

[Top](#)

See Also

[ISurfaceKnitFeatureData Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IFeatureManager::InsertSewRefSurface Method](#)

SOLIDWORKS API Help [Send comments on this topic.](#)

ISurfaceKnitFeatureData Interface Members

[See Also](#) [Properties](#) [Methods](#)



[SolidWorks.Interop.sldworks Namespace](#) : ISurfaceKnitFeatureData Interface

The following tables list the members exposed by [ISurfaceKnitFeatureData](#).

Public Properties

Name	Description
 Entities	Gets or sets the knitted faces and surfaces.
 KnitTolerance	Gets or sets the knit tolerance for this Surface-Knit feature.
 MaxValueForGapRange	Gets or sets the maximum gap range for this Surface-Knit feature.
 MinValueForGapRange	Gets or sets the minimum gap range for this Surface-Knit feature.
 SeedFace	Gets or sets the seed face for this surface knit feature.
 UseGapFilters	Gets or sets whether to use gap filters for this Surface-Knit feature.
 UseMergeEntities	Get or sets whether to merge edges and faces by removing redundant vertices and edges when creating the Surface-Knit feature.
 UseTryToFormSolid	Gets or sets whether to try to form a solid body when creating the Surface-Knit feature.

[Top](#)

Public Methods

Name	Description
 AccessSelections	Accesses the selections that define this Surface-Knit feature.
 GetEntitiesCount	Gets the number of knit faces and surfaces for this Surface-Knit feature.
 IAccessSelections	Accesses the selections that define this Surface-Knit feature.
 IGetEntities	Gets the knitted faces and surfaces for this Surface-Knit feature.
 ISetEntities	Sets the faces and surfaces to knit.
 ReleaseSelectionAccess	Releases access to the selections for this Surface-Knit feature.

[Top](#)

See Also

[ISurfaceKnitFeatureData Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IFeatureManager::InsertSewRefSurface Method](#)

SOLIDWORKS API Help [Send comments on this topic.](#)

ISurfaceKnitFeatureData Interface Properties

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) : ISurfaceKnitFeatureData Interface

For a list of all members of this type, see [ISurfaceKnitFeatureData members](#).

Public Properties

Name	Description
 Entities	Gets or sets the knitted faces and surfaces.
 KnitTolerance	Gets or sets the knit tolerance for this Surface-Knit feature.
 MaxValueForGapRange	Gets or sets the maximum gap range for this Surface-Knit feature.
 MinValueForGapRange	Gets or sets the minimum gap range for this Surface-Knit feature.
 SeedFace	Gets or sets the seed face for this surface knit feature.
 UseGapFilters	Gets or sets whether to use gap filters for this Surface-Knit feature.
 UseMergeEntities	Get or sets whether to merge edges and faces by removing redundant vertices and edges when creating the Surface-Knit feature.
 UseTryToFormSolid	Gets or sets whether to try to form a solid body when creating the Surface-Knit feature.

[Top](#)

See Also

[ISurfaceKnitFeatureData Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IFeatureManager::InsertSewRefSurface Method](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

AccessSelections Method (ISurfaceKnitFeatureData)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISurfaceKnitFeatureData Interface](#) : AccessSelections Method (ISurfaceKnitFeatureData)

Accesses the selections that define this Surface-Knit feature.

.NET Syntax

Visual Basic (Declaration)

```
Function AccessSelections(  
    ByVal TopDoc As System.Object, _  
    ByVal Component As System.Object _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISurfaceKnitFeatureData  
Dim TopDoc As System.Object  
Dim Component As System.Object  
Dim value As System.Boolean  
  
value = instance.AccessSelections(TopDoc, Component)
```

C#

```
System.bool AccessSelections(  
    System.object TopDoc,  
    System.object Component  
)
```

C++/CLI

```
System.bool AccessSelections(  
& System.Object^ TopDoc,  
& System.Object^ Component  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

TopDoc
Top-level document

Component
Component in which the feature is to be modified

Return Value

True if the selections are successfully accessed, false if not

Visual Basic for Applications (VBA) Syntax

See [SurfaceKnitFeatureData::AccessSelections](#).

Example

[Get Knit Surface Data \(VBA\)](#)

Remarks

To modify a feature in a...	Then...
Part	- TopDoc argument is the IModelDoc2 for the part - Component argument is <code>NULL</code>
Assembly	- TopDoc is the IModelDoc2 object for the assembly - Component argument is the IComponent2 object in which the feature is to be modified

This method puts the model into a rollback state to allow access to the selections that define this feature. You must use either of the following methods to restore the rollback state:

- [IFeature::ModifyDefinition](#) or [IFeature::IModifyDefinition2](#) if you modified the feature
- [ISurfaceKnitFeatureData::ReleaseSelectionAccess](#) if you did not

See [Accessing Selections that Define Features](#) for additional details.

See Also

[ISurfaceKnitFeatureData Interface](#)
[ISurfaceKnitFeatureData Members](#)
[ISurfaceKnitFeatureData::IAccessSelections Method](#)

Availability

SOLIDWORKS 2001Plus SP1, Revision Number 10.1

SOLIDWORKS API Help

[Send comments on this topic.](#)

Entities Property (ISurfaceKnitFeatureData)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISurfaceKnitFeatureData Interface](#) : Entities Property (ISurfaceKnitFeatureData)

Gets or sets the knitted faces and surfaces.

.NET Syntax

Visual Basic (Declaration)

Property Entities As System.Object

Visual Basic (Usage)



```
Dim instance As ISurfaceKnitFeatureData  
Dim value As System.Object  
  
instance.Entities = value  
  
value = instance.Entities
```

C#

```
System.object Entities {get; set;}
```

C++/CLI

```
property System.Object^ Entities {  
    System.Object^ get();
```

```
void set ( & System.Object^ value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Array of knit entities ([faces](#) and [surfaces](#))

Visual Basic for Applications (VBA) Syntax

See [SurfaceKnitFeatureData::Entities](#).

Example

[Get Knit Surface Data \(VBA\)](#)

Remarks

See [Accessing Selections that Define Features](#) for additional details.

See Also

[ISurfaceKnitFeatureData Interface](#)
[ISurfaceKnitFeatureData Members](#)
[ISurfaceKnitFeatureData::GetEntitiesCount Method](#)
[ISurfaceKnitFeatureData::IGetEntities Method](#)
[ISurfaceKnitFeatureData::ISetEntities Method](#)

Availability

SOLIDWORKS 2001Plus SP1, Revision Number 10.1

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetEntitiesCount Method (ISurfaceKnitFeatureData)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISurfaceKnitFeatureData Interface](#) : GetEntitiesCount Method (ISurfaceKnitFeatureData)

Gets the number of knit faces and surfaces for this Surface-Knit feature.

.NET Syntax

Visual Basic (Declaration)

```
Function GetEntitiesCount() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ISurfaceKnitFeatureData  
Dim value As System.Integer  
  
value = instance.GetEntitiesCount()
```

C#

```
System.int GetEntitiesCount()
```

C++/CLI

```
System.int GetEntitiesCount();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Number of knit entities

Visual Basic for Applications (VBA) Syntax

See [SurfaceKnitFeatureData::GetEntitiesCount](#).

Example

[Get Knit Surface \(VBA\)](#)

Remarks

Call this method before calling [ISurfaceKnitFeatureData::IGetEntities](#).

See [Accessing Selections that Define Features](#) for additional details.

See Also

[ISurfaceKnitFeatureData Interface](#)
[ISurfaceKnitFeatureData Members](#)
[ISurfaceKnitFeatureData::IGetEntities Method](#)
[ISurfaceKnitFeatureData::Entities Property](#)

Availability

SOLIDWORKS 2001Plus SP1, Revision Number 10.1

SOLIDWORKS API Help

[Send comments on this topic.](#)

IAccessSelections Method (ISurfaceKnitFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISurfaceKnitFeatureData Interface](#) : IAccessSelections Method (ISurfaceKnitFeatureData)

Accesses the selections that define this Surface-Knit feature.

.NET Syntax

Visual Basic (Declaration)

```
Function IAccessSelections( _  
    ByVal TopDoc As ModelDoc2, _  
    ByVal Component As Component2 _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISurfaceKnitFeatureData  
Dim TopDoc As ModelDoc2  
Dim Component As Component2  
Dim value As System.Boolean  
  
value = instance.IAccessSelections(TopDoc, Component)
```

C#

```
System.bool IAccessSelections(  
    ModelDoc2 TopDoc,  
    Component2 Component  
)
```

C++/CLI

```
System.bool IAccessSelections(  
& ModelDoc2^ TopDoc,  
& Component2^ Component  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

TopDoc
Top-level document

Component
Component in which the feature is to be modified

Return Value

True if the selections are successfully accessed, false if not

Visual Basic for Applications (VBA) Syntax

See [SurfaceKnitFeatureData::IAccessSelections](#).

Remarks

To modify a feature in a...	Then...
Part	- TopDoc argument is the IModelDoc2 for the part - Component argument is NULL
Assembly	- TopDoc is the IModelDoc2 object for the assembly - Component argument is the IComponent2 object in which the feature is to be modified

This method puts the model into a rollback state to allow access to the selections that define this feature. You must use either of the following methods to restore the rollback state:

- [IFeature::ModifyDefinition](#) or [IFeature::IModifyDefinition2](#) if you modified the feature
- [ISurfaceKnitFeatureData::ReleaseSelectionAccess](#) if you did not

See [Accessing Selections that Define Features](#) for additional details.

See Also

[ISurfaceKnitFeatureData Interface](#)
[ISurfaceKnitFeatureData Members](#)
[ISurfaceKnitFeatureData::AccessSelections Method](#)

Availability

SOLIDWORKS 2001Plus SP1, Revision Number 10.1

SOLIDWORKS API Help

[Send comments on this topic.](#)

IGetEntities Method (ISurfaceKnitFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISurfaceKnitFeatureData Interface](#) : IGetEntities Method (ISurfaceKnitFeatureData)

Gets the knitted faces and surfaces for this Surface-Knit feature.

.NET Syntax

Visual Basic (Declaration)

```
Function IGetEntities( _  
    ByVal Count As System.Integer _  
) As System.Object
```

Visual Basic (Usage)

```
Dim instance As ISurfaceKnitFeatureData  
Dim Count As System.Integer  
Dim value As System.Object  
  
value = instance.IGetEntities(Count)
```

C#

```
System.object IGetEntities(  
    System.int Count  
)
```

C++/CLI

```
System.Object^ IGetEntities(  
& System.int Count  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Count

Number of knit entities

Return Value

- in-process, unmanaged C++: Pointer to an array of knit entities ([faces](#) and [surfaces](#)) of size Count
- VBA, VB.NET, C#, and C++/CLI: Not supported
- See [In-process Methods](#) for details about this type of method.

Remarks

Call [ISurfaceKnitFeatureData::GetEntitiesCount](#) before calling this method.

See [Accessing Selections that Define Features](#) for additional details.

See Also

[ISurfaceKnitFeatureData Interface](#)
[ISurfaceKnitFeatureData Members](#)
[ISurfaceKnitFeatureData::ISetEntities Method](#)
[ISurfaceKnitFeatureData::Entities Property](#)

Availability

SOLIDWORKS 2001Plus SP1, Revision Number 10.1

SOLIDWORKS API Help

[Send comments on this topic.](#)

ISetEntities Method (ISurfaceKnitFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISurfaceKnitFeatureData Interface](#) : ISetEntities Method (ISurfaceKnitFeatureData)

Sets the faces and surfaces to knit.

.NET Syntax

Visual Basic (Declaration)

```
Sub ISetEntities( _  
    ByVal Count As System.Integer, _  
    ByRef FaceArr As System.Object _  
)
```

Visual Basic (Usage)



```
Dim instance As ISurfaceKnitFeatureData  
Dim Count As System.Integer  
Dim FaceArr As System.Object  
  
instance.ISetEntities(Count, FaceArr)
```

C#

```
void ISetEntities(  
    System.int Count,  
    ref System.object FaceArr  
)
```

C++/CLI

```
void ISetEntities(  
& System.int Count,  
& System.Object^% FaceArr  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Count

Number of faces

FaceArr

- in-process, unmanaged C++: Pointer to an array of knit entities ([faces](#) and [surfaces](#)) of size Count
 - VBA, VB.NET, C#, and C++/CLI: Not supported
- See [In-process Methods](#) for details about this type of method.

Visual Basic for Applications (VBA) Syntax

See [SurfaceKnitFeatureData::ISetEntities](#).

Remarks

See [Accessing Selections that Define Features](#) for additional details.

See Also

[ISurfaceKnitFeatureData Interface](#)
[ISurfaceKnitFeatureData Members](#)
[ISurfaceKnitFeatureData::Entities Property](#)
[ISurfaceKnitFeatureData::IGetEntities Method](#)
[ISurfaceKnitFeatureData::GetEntitiesCount Method](#)

Availability

SOLIDWORKS 2001Plus SP1, Revision Number 10.1

SOLIDWORKS API Help

[Send comments on this topic.](#)

KnitTolerance Property (ISurfaceKnitFeatureData)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISurfaceKnitFeatureData Interface](#) : KnitTolerance Property (ISurfaceKnitFeatureData)

Gets or sets the knit tolerance for this Surface-Knit feature.

.NET Syntax

Visual Basic (Declaration)

Property KnitTolerance As System.Double

Visual Basic (Usage)



```
Dim instance As ISurfaceKnitFeatureData
Dim value As System.Double

instance.KnitTolerance = value

value = instance.KnitTolerance
```

C#

```
System.double KnitTolerance {get; set;}
```

C++/CLI

```
property System.double KnitTolerance {
    System.double get();
    void set ( & System.double value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Knit tolerance (see **Remarks**)

Visual Basic for Applications (VBA) Syntax

See [SurfaceKnitFeatureData::KnitTolerance](#).

Example

[Create Knit Surface Feature \(VB.NET\)](#)
[Create Knit Surface Feature \(VBA\)](#)
[Create Knit Surface Feature \(C#\)](#)

Remarks

[ISurfaceKnitFeatureData::UseGapFilters](#) must be true for this property to have an effect.

A knit tolerance's:

- lower limit is 0.0001 mm
- upper limit is 0.1 mm

The knit tolerance value should be in a gap range such that:

([Minimum gap](#)) <= (Knit tolerance) <= MIN(0.1 mm, [Maximum gap](#))

See [Accessing Selections that Define Features](#) for additional details.

See Also

[ISurfaceKnitFeatureData Interface](#)
[ISurfaceKnitFeatureData Members](#)

Availability

SOLIDWORKS 2010 FCS, Revision Number 18.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

MaxValueForGapRange Property (ISurfaceKnitFeatureData)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISurfaceKnitFeatureData Interface](#) : MaxValueForGapRange Property (ISurfaceKnitFeatureData)

Gets or sets the maximum gap range for this Surface-Knit feature.

.NET Syntax

Visual Basic (Declaration)

Property MaxValueForGapRange As System.Double

Visual Basic (Usage)



```
Dim instance As ISurfaceKnitFeatureData  
Dim value As System.Double
```

```
instance.MaxValueForGapRange = value
```

```
value = instance.MaxValueForGapRange
```

C#

```
System.double MaxValueForGapRange {get; set;}
```

C++/CLI

```
property System.double MaxValueForGapRange {  
    System.double get();  
    void set ( & System.double value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Maximum gap range; valid values are from 0.01 mm to 1 mm

Visual Basic for Applications (VBA) Syntax

See [SurfaceKnitFeatureData::MaxValueForGapRange](#).

Example

[Create Knit Surface Feature \(VB.NET\)](#)
[Create Knit Surface Feature \(VBA\)](#)
[Create Knit Surface Feature \(C#\)](#)

Remarks

[ISurfaceKnitFeatureData::UseGapFilters](#) must be true for this property to have an effect.

Maximum gap should be in the range of [ISurfaceKnitFeatureData::KnitTolerance](#) to 1 mm.

See [Accessing Selections that Define Features](#) for additional details.

See Also

[ISurfaceKnitFeatureData Interface](#)
[ISurfaceKnitFeatureData Members](#)
[ISurfaceKnitFeatureData::MinValueForGapRange Property](#)

Availability

SOLIDWORKS 2010 FCS, Revision Number 18.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

MinValueForGapRange Property (ISurfaceKnitFeatureData)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISurfaceKnitFeatureData Interface](#) : MinValueForGapRange Property (ISurfaceKnitFeatureData)

Gets or sets the minimum gap range for this Surface-Knit feature.

.NET Syntax

Visual Basic (Declaration)

```
Property MinValueForGapRange As System.Double
```

Visual Basic (Usage)



```
Dim instance As ISurfaceKnitFeatureData  
Dim value As System.Double
```

```
instance.MinValueForGapRange = value
```

```
value = instance.MinValueForGapRange
```

C#

```
System.double MinValueForGapRange {get; set;}
```

C++/CLI

```
property System.double MinValueForGapRange {  
    System.double get();  
    void set ( & System.double value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Minimum gap range; valid values are from 0.0001 mm to 0.01 mm

Visual Basic for Applications (VBA) Syntax

See [SurfaceKnitFeatureData::MinValueForGapRange](#).

Example

[Create Knit Surface Feature \(VB.NET\)](#)
[Create Knit Surface Feature \(VBA\)](#)
[Create Knit Surface Feature \(C#\)](#)

Remarks

[ISurfaceKnitFeatureData::UseGapFilters](#) must be true for this property to have an effect.

The minimum gap should be in the range of 0.0001 mm to [ISurfaceKnitFeatureData::KnitTolerance](#).

See [Accessing Selections that Define Features](#) for additional details.

See Also

[ISurfaceKnitFeatureData Interface](#)

[ISurfaceKnitFeatureData Members](#)

[ISurfaceKnitFeatureData::MaxValueForGapRange Property](#)

Availability

SOLIDWORKS 2010 FCS, Revision Number 18.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

ReleaseSelectionAccess Method (ISurfaceKnitFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISurfaceKnitFeatureData Interface](#) : ReleaseSelectionAccess Method (ISurfaceKnitFeatureData)

Releases access to the selections for this Surface-Knit feature.

.NET Syntax

Visual Basic (Declaration)

```
Sub ReleaseSelectionAccess()
```

Visual Basic (Usage)



```
Dim instance As ISurfaceKnitFeatureData
```

```
instance.ReleaseSelectionAccess()
```

C#

```
void ReleaseSelectionAccess()
```

C++/CLI

```
void ReleaseSelectionAccess();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [SurfaceKnitFeatureData::ReleaseSelectionAccess](#).

Remarks

[ISurfaceKnitFeatureData::AccessSelections](#) and [ISurfaceKnitFeatureData::IAccessSelections](#) put the model in a rollback state to allow access to the selections that define the feature.

Use this method to restore the rollback state if you did not modify the feature, or use [IFeature::ModifyDefinition](#) or [IFeature::IModifyDefinition2](#) if you did modify the feature.

See [Accessing Selections that Define Features](#) for additional details.

See Also

[ISurfaceKnitFeatureData Interface](#)

[ISurfaceKnitFeatureData Members](#)

Availability

SeedFace Property (ISurfaceKnitFeatureData)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISurfaceKnitFeatureData Interface](#) : SeedFace Property (ISurfaceKnitFeatureData)

Gets or sets the seed face for this surface knit feature.

.NET Syntax

Visual Basic (Declaration)

Property SeedFace As System.Object

Visual Basic (Usage)



```
Dim instance As ISurfaceKnitFeatureData
Dim value As System.Object

instance.SeedFace = value

value = instance.SeedFace
```

C#

```
System.Object SeedFace {get; set;}
```

C++/CLI

```
property System.Object^ SeedFace {
    System.Object^ get();
    void set ( & System.Object^ value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Seed [face](#)

Visual Basic for Applications (VBA) Syntax

See [SurfaceKnitFeatureData::SeedFace](#).

Example

[Get Knit Surface \(VBA\)](#)

Remarks

See [Accessing Selections that Define Features](#) for additional details.

See Also

[ISurfaceKnitFeatureData Interface](#)
[ISurfaceKnitFeatureData Members](#)

Availability

SOLIDWORKS 2001Plus SP1, Revision Number 10.1

UseGapFilters Property (ISurfaceKnitFeatureData)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISurfaceKnitFeatureData Interface](#) : UseGapFilters Property (ISurfaceKnitFeatureData)

Gets or sets whether to use gap filters for this Surface-Knit feature.

.NET Syntax

Visual Basic (Declaration)

Property UseGapFilters As System.Boolean

Visual Basic (Usage)



```
Dim instance As ISurfaceKnitFeatureData  
Dim value As System.Boolean  
  
instance.UseGapFilters = value  
value = instance.UseGapFilters
```

C#

```
System.bool UseGapFilters {get; set;}
```

C++/CLI

```
property System.bool UseGapFilters {  
    System.bool get();  
    void set ( & System.bool value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True to use gap filters, false to not

Visual Basic for Applications (VBA) Syntax

See [SurfaceKnitFeatureData::UseGapFilters](#).

Example

[Create Knit Surface Feature \(VB.NET\)](#)
[Create Knit Surface Feature \(VBA\)](#)
[Create Knit Surface Feature \(C#\)](#)

Remarks

See [Accessing Selections that Define Features](#) for additional details.

See Also

[ISurfaceKnitFeatureData Interface](#)
[ISurfaceKnitFeatureData Members](#)
[ISurfaceKnitFeatureData::KnitTolerance Property](#)
[ISurfaceKnitFeatureData::MaxValueForGapRange Property](#)
[ISurfaceKnitFeatureData::MinValueForGapRange Property](#)

Availability

SOLIDWORKS 2010 FCS, Revision Number 18.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

UseMergeEntities Property (ISurfaceKnitFeatureData)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISurfaceKnitFeatureData Interface](#) : UseMergeEntities Property (ISurfaceKnitFeatureData)

Get or sets whether to merge edges and faces by removing redundant vertices and edges when creating the Surface-Knit feature.

.NET Syntax

Visual Basic (Declaration)

Property UseMergeEntities As System.Boolean

Visual Basic (Usage)



```
Dim instance As ISurfaceKnitFeatureData  
Dim value As System.Boolean
```

```
instance.UseMergeEntities = value
```

```
value = instance.UseMergeEntities
```

C#

```
System.bool UseMergeEntities {get; set;}
```

C++/CLI

```
property System.bool UseMergeEntities {  
    System.bool get();  
    void set ( & System.bool value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True to merge edges and faces, false to not

Visual Basic for Applications (VBA) Syntax

See [SurfaceKnitFeatureData::UseMergeEntities](#).

Example

[Create Knit Surface Feature \(VB.NET\)](#)
[Create Knit Surface Feature \(VBA\)](#)
[Create Knit Surface Feature \(C#\)](#)

Remarks

See [Accessing Selections that Define Features](#) for additional details.

See Also

[ISurfaceKnitFeatureData Interface](#)
[ISurfaceKnitFeatureData Members](#)

Availability

SOLIDWORKS 2010 FCS, Revision Number 18.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

UseTryToFormSolid Property (ISurfaceKnitFeatureData)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISurfaceKnitFeatureData Interface](#) : UseTryToFormSolid Property (ISurfaceKnitFeatureData)

Gets or sets whether to try to form a solid body when creating the Surface-Knit feature.

.NET Syntax

Visual Basic (Declaration)

```
Property UseTryToFormSolid As System.Boolean
```

Visual Basic (Usage)




```
Dim instance As ISurfaceKnitFeatureData
Dim value As System.Boolean

instance.UseTryToFormSolid = value

value = instance.UseTryToFormSolid
```

C#

```
System.bool UseTryToFormSolid {get; set;}
```

C++/CLI

```
property System.bool UseTryToFormSolid {
    System.bool get();
    void set ( & System.bool value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True to true to form a solid body, false to not

Visual Basic for Applications (VBA) Syntax

See [SurfaceKnitFeatureData::UseTryToFormSolid](#).

Example

[Create Knit Surface Feature \(VB.NET\)](#)
[Create Knit Surface Feature \(VBA\)](#)
[Create Knit Surface Feature \(C#\)](#)

Remarks

If [ISurfaceKnitFeatureData::UseGapFilters](#) is true, then this property is automatically enabled or disabled depending on whether a solid body can be created from the input bodies.

If you set this property to true, then [knit tolerance](#) is automatically updated so that the Surface-Knit feature can be created as a solid body.

See [Accessing Selections that Define Features](#) for additional details.

See Also

[ISurfaceKnitFeatureData Interface](#)
[ISurfaceKnitFeatureData Members](#)

Availability

SOLIDWORKS 2010 FCS, Revision Number 18.0

ISurfaceOffsetFeatureData (Type)

ISurfaceOffsetFeatureData Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) : ISurfaceOffsetFeatureData Interface

Allows access to a surface offset feature.
NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface ISurfaceOffsetFeatureData
```

Visual Basic (Usage)



```
Dim instance As ISurfaceOffsetFeatureData
```

C#

```
public interface ISurfaceOffsetFeatureData
```

C++/CLI

```
public interface class ISurfaceOffsetFeatureData
```

Visual Basic for Applications (VBA) Syntax

See [SurfaceOffsetFeatureData](#).

Example

[Get Offset Surface Data \(VBA\)](#)
[Get Offset Surface Data \(VB.NET\)](#)
[Get Offset Surface Data \(C#\)](#)

Accessors

[IFeature::GetDefinition](#) and [IFeature::IGetDefinition](#)

Access Diagram

[SurfaceOffsetFeatureData](#)

See Also

[ISurfaceOffsetFeatureData Members](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IModelDoc2::InsertOffsetSurface Method](#)

ISurfaceOffsetFeatureData Interface Methods

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) : ISurfaceOffsetFeatureData Interface

For a list of all members of this type, see [ISurfaceOffsetFeatureData members](#).

Public Methods

Name	Description
 AccessSelections	Accesses the selections that define this surface offset feature.
 GetEntitiesCount	Gets the number of offset surfaces and faces for this surface offset feature.

	GetFacesCount	Obsolete. Superseded by ISurfaceOffsetFeatureData.GetEntitiesCount
	IAccessSelections	Accesses the selections that define this surface offset feature.
	IGetEntities	Gets the offset surfaces or faces of this surface offset feature.
	IGetFaces	Obsolete. Superseded by ISurfaceOffsetFeatureData.IGetEntities
	ISetEntities	Sets the offset surfaces or faces for this surface offset feature.
	ISetFaces	Obsolete. Superseded by ISurfaceOffsetFeatureData.ISetEntities
	ReleaseSelectionAccess	Releases access to the selections for this surface offset feature.

[Top](#)

See Also

[ISurfaceOffsetFeatureData Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IModelDoc2::InsertOffsetSurface Method](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

ISurfaceOffsetFeatureData Interface Members

[See Also](#) [Properties](#) [Methods](#)



[SolidWorks.Interop.sldworks Namespace](#) : ISurfaceOffsetFeatureData Interface

The following tables list the members exposed by [ISurfaceOffsetFeatureData](#).

Public Properties

Name	Description
 Distance	Gets or sets the offset distance for this surface offset feature.
 Entities	Gets or sets the offset surfaces and faces of this surface offset feature.
 Faces	Obsolete. Superseded by ISurfaceOffsetFeatureData.Entities
 Flip	Gets or sets the offset flip setting for this surface offset feature.

[Top](#)

Public Methods

Name	Description
 AccessSelections	Accesses the selections that define this surface offset feature.
 GetEntitiesCount	Gets the number of offset surfaces and faces for this surface offset feature.
 GetFacesCount	Obsolete. Superseded by ISurfaceOffsetFeatureData.GetEntitiesCount
 IAccessSelections	Accesses the selections that define this surface offset feature.
 IGetEntities	Gets the offset surfaces or faces of this surface offset feature.
 IGetFaces	Obsolete. Superseded by ISurfaceOffsetFeatureData.IGetEntities
 ISetEntities	Sets the offset surfaces or faces for this surface offset feature.
 ISetFaces	Obsolete. Superseded by ISurfaceOffsetFeatureData.ISetEntities
 ReleaseSelectionAccess	Releases access to the selections for this surface offset feature.

[Top](#)

See Also

[ISurfaceOffsetFeatureData Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IModelDoc2::InsertOffsetSurface Method](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

ISurfaceOffsetFeatureData Interface Properties

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) : ISurfaceOffsetFeatureData Interface

For a list of all members of this type, see [ISurfaceOffsetFeatureData members](#).

Public Properties

Name	Description
 Distance	Gets or sets the offset distance for this surface offset feature.
 Entities	Gets or sets the offset surfaces and faces of this surface offset feature.
 Faces	Obsolete. Superseded by ISurfaceOffsetFeatureData.Entities
 Flip	Gets or sets the offset flip setting for this surface offset feature.

[Top](#)

See Also

[ISurfaceOffsetFeatureData Interface](#)
[SolidWorks.Interop.sldworks.Namespace](#)
[IModelDoc2::InsertOffsetSurface Method](#)

[Send comments on this topic.](#)

SOLIDWORKS API Help

AccessSelections Method (ISurfaceOffsetFeatureData)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISurfaceOffsetFeatureData Interface](#) : AccessSelections Method (ISurfaceOffsetFeatureData)

Accesses the selections that define this surface offset feature.

.NET Syntax

Visual Basic (Declaration)

```
Function AccessSelections(  
    ByVal TopDoc As System.Object, _  
    ByVal Component As System.Object _  
) As System.Boolean
```

Visual Basic (Usage)

Copy Code

```
Dim instance As ISurfaceOffsetFeatureData  
Dim TopDoc As System.Object  
Dim Component As System.Object  
Dim value As System.Boolean  
  
value = instance.AccessSelections(TopDoc, Component)
```

C#

```
System.bool AccessSelections(  
    System.object TopDoc,  
    System.object Component  
)
```

C++/CLI

```
System.bool AccessSelections(  
& System.Object^ TopDoc,  
& System.Object^ Component  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

TopDoc
Top-level [document](#)

Component
[Component](#) in which the feature is to be modified

Return Value

True if the selections are successfully accessed, false if not

Visual Basic for Applications (VBA) Syntax

See [SurfaceOffsetFeatureData::AccessSelections](#).

Example

[Get Offset Surface Data \(VBA\)](#)
[Get Offset Surface Data \(VB.NET\)](#)
[Get Offset Surface Data \(C#\)](#)

Remarks

To modify a feature in a...	Then...
Part	- TopDoc argument is the IModelDoc2 for the part - Component argument is NULL
Assembly	- TopDoc is the IModelDoc2 object for the assembly - Component argument is the IComponent2 object in which the feature is to be modified

This method puts the model into a rollback state to allow access to the selections that define this feature. You must use either of the following methods to restore the rollback state:

- [IFeature::ModifyDefinition](#) or [IFeature::IModifyDefinition2](#) if you modified the feature
- [ISurfaceOffsetFeatureData::ReleaseSelectionAccess](#) if you did not

See Also

[ISurfaceOffsetFeatureData Interface](#)
[ISurfaceOffsetFeatureData Members](#)
[ISurfaceOffsetFeatureData::AccessSelections Method](#)

Availability

SOLIDWORKS 2001Plus SP1, Revision Number 10.1

SOLIDWORKS API Help

[Send comments on this topic.](#)

Distance Property (ISurfaceOffsetFeatureData)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISurfaceOffsetFeatureData Interface](#) : Distance Property (ISurfaceOffsetFeatureData)

Gets or sets the offset distance for this surface offset feature.

.NET Syntax

Visual Basic (Declaration)

Property Distance As System.Double

Visual Basic (Usage)



```
Dim instance As ISurfaceOffsetFeatureData  
Dim value As System.Double
```

```
instance.Distance = value
```

```
value = instance.Distance
```

C#

```
System.double Distance {get; set;}
```

C++/CLI

```
property System.double Distance {  
    System.double get();  
    void set ( & System.double value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Offset distance

Visual Basic for Applications (VBA) Syntax

See [SurfaceOffsetFeatureData::Distance](#).

Example

[Get Offset Surface Data \(VBA\)](#)
[Get Offset Surface Data \(VB.NET\)](#)
[Get Offset Surface Data \(C#\)](#)

Remarks

See [Accessing Selections that Define Features](#) for additional details.

See Also

[ISurfaceOffsetFeatureData Interface](#)
[ISurfaceOffsetFeatureData Members](#)

Availability

SOLIDWORKS 2001Plus SP1, Revision number 10.1

SOLIDWORKS API Help

[Send comments](#) on this topic.

Entities Property (ISurfaceOffsetFeatureData)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISurfaceOffsetFeatureData Interface](#) : Entities Property (ISurfaceOffsetFeatureData)

Gets or sets the offset surfaces and faces of this surface offset feature.

.NET Syntax

Visual Basic (Declaration)

Property Entities As System.Object

Visual Basic (Usage)



```
Dim instance As ISurfaceOffsetFeatureData  
Dim value As System.Object
```

```
instance.Entities = value
```

```
value = instance.Entities
```

C#

```
System.object Entities {get; set;}
```

C++/CLI

```
property System.Object^ Entities {  
    System.Object^ get();  
    void set ( & System.Object^ value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Array of offset surface or face feature [entities](#)

Visual Basic for Applications (VBA) Syntax

See [SurfaceOffsetFeatureData::Entities](#).

Example

[Get Offset Surface Data \(VBA\)](#)
[Get Offset Surface Data \(VB.NET\)](#)
[Get Offset Surface Data \(C#\)](#)

Remarks

See [Accessing Selections that Define Features](#) for additional details.

See Also

[ISurfaceOffsetFeatureData Interface](#)
[ISurfaceOffsetFeatureData Members](#)
[ISurfaceOffsetFeatureData::GetEntitiesCount Method](#)
[ISurfaceOffsetFeatureData::IGetEntities Method](#)
[ISurfaceOffsetFeatureData::ISetEntities Method](#)

Availability

SOLIDWORKS 2012 SP04, Revision Number 20.4

SOLIDWORKS API Help

[Send comments on this topic.](#)

Faces Property (ISurfaceOffsetFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISurfaceOffsetFeatureData Interface](#) : Faces Property (ISurfaceOffsetFeatureData)

Obsolete. Superseded by [ISurfaceOffsetFeatureData::Entities](#).

.NET Syntax

Visual Basic (Declaration)

Property Faces As System.Object

Visual Basic (Usage)



```
Dim instance As ISurfaceOffsetFeatureData  
Dim value As System.Object
```

```
instance.Faces = value
```

```
value = instance.Faces
```

C#

```
System.Object Faces {get; set;}
```

C++/CLI

```
property System.Object^ Faces {  
    System.Object^ get();  
    void set ( & System.Object^ value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Array of [faces](#)

Visual Basic for Applications (VBA) Syntax

See [SurfaceOffsetFeatureData::Faces](#).

Remarks

See [Accessing Selections that Define Features](#) for additional details.

See Also

[ISurfaceOffsetFeatureData Interface](#)
[ISurfaceOffsetFeatureData Members](#)
[ISurfaceOffsetFeatureData::GetFacesCount Method](#)
[ISurfaceOffsetFeatureData::!GetFaces Method](#)
[ISurfaceOffsetFeatureData::!SetFaces Method](#)

Availability

SOLIDWORKS 2001Plus SP1, Revision Number 10.1

SOLIDWORKS API Help

[Send comments on this topic.](#)

Flip Property (ISurfaceOffsetFeatureData)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISurfaceOffsetFeatureData Interface](#) : Flip Property (ISurfaceOffsetFeatureData)

Gets or sets the offset flip setting for this surface offset feature.

.NET Syntax

Visual Basic (Declaration)

Property Flip As System.Boolean

Visual Basic (Usage)



```
Dim instance As ISurfaceOffsetFeatureData  
Dim value As System.Boolean
```

```
instance.Flip = value
```

```
value = instance.Flip
```

C#

```
System.bool Flip {get; set;}
```

C++/CLI

```
property System.bool Flip {  
    System.bool get();  
    void set ( & System.bool value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True flips the offset, false does not

Visual Basic for Applications (VBA) Syntax

See [SurfaceOffsetFeatureData::Flip](#).

Example

[Get Offset Surface Data \(VBA\)](#)
[Get Offset Surface Data \(VB.NET\)](#)
[Get Offset Surface Data \(C#\)](#)

Remarks

See [Accessing Selections that Define Features](#) for additional details.

See Also

[ISurfaceOffsetFeatureData Interface](#)
[ISurfaceOffsetFeatureData Members](#)

Availability

SOLIDWORKS 2001Plus SP1, Revision number 10.1

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetEntitiesCount Method (ISurfaceOffsetFeatureData)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISurfaceOffsetFeatureData Interface](#) : GetEntitiesCount Method (ISurfaceOffsetFeatureData)

Gets the number of offset surfaces and faces for this surface offset feature.

.NET Syntax

Visual Basic (Declaration)

```
Function GetEntitiesCount() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ISurfaceOffsetFeatureData  
Dim value As System.Integer
```

```
value = instance.GetEntitiesCount()
```

C#

```
System.int GetEntitiesCount()
```

C++/CLI

```
System.int GetEntitiesCount();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Number of offset surfaces and faces

Visual Basic for Applications (VBA) Syntax

See [SurfaceOffsetFeatureData::GetEntitiesCount](#).

Example

[Get Offset Surface Data \(VBA\)](#)
[Get Offset Surface Data \(VB.NET\)](#)
[Get Offset Surface Data \(C#\)](#)

See Also

[ISurfaceOffsetFeatureData Interface](#)
[ISurfaceOffsetFeatureData Members](#)
[ISurfaceOffsetFeatureData::ISetEntities Method](#)
[ISurfaceOffsetFeatureData::Entities Property](#)
[ISurfaceOffsetFeatureData::!GetEntities Method](#)

Availability

SOLIDWORKS 2012 SP04, Revision Number 20.4

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetFacesCount Method (ISurfaceOffsetFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISurfaceOffsetFeatureData Interface](#) : GetFacesCount Method (ISurfaceOffsetFeatureData)

Obsolete. Superseded by [ISurfaceOffsetFeatureData::GetEntitiesCount](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetFacesCount() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ISurfaceOffsetFeatureData  
Dim value As System.Integer  
  
value = instance.GetFacesCount()
```

C#

```
System.int GetFacesCount()
```

C++/CLI

```
System.int GetFacesCount();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Number of offset faces

Visual Basic for Applications (VBA) Syntax

See [SurfaceOffsetFeatureData::GetFacesCount](#).

Remarks

Call this method before calling [ISurfaceOffsetFeatureData::IGetFaces](#).

See Also

[ISurfaceOffsetFeatureData Interface](#)
[ISurfaceOffsetFeatureData Members](#)
[ISurfaceOffsetFeatureData::ISetFaces Method](#)
[ISurfaceOffsetFeatureData::Faces Property](#)

Availability

SOLIDWORKS 2001Plus SP1, Revision Number 10.1

SOLIDWORKS API Help

[Send comments](#) on this topic.

IAccessSelections Method (ISurfaceOffsetFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISurfaceOffsetFeatureData Interface](#) : IAccessSelections Method (ISurfaceOffsetFeatureData)

Accesses the selections that define this surface offset feature.

.NET Syntax

Visual Basic (Declaration)

```
Function IAccessSelections( _  
    ByVal TopDoc As ModelDoc2, _  
    ByVal Component As Component2 _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISurfaceOffsetFeatureData  
Dim TopDoc As ModelDoc2  
Dim Component As Component2  
Dim value As System.Boolean  
  
value = instance.IAccessSelections(TopDoc, Component)
```

C#

```
System.bool IAccessSelections(  
    ModelDoc2 TopDoc,  
    Component2 Component  
)
```

C++/CLI

```
System.bool IAccessSelections(  
& ModelDoc2^ TopDoc,  
& Component2^ Component  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

TopDoc

Top-level document

Component

Component in which the feature is to be modified

Return Value

True if the selections are successfully accessed, false if not

Visual Basic for Applications (VBA) Syntax

See [SurfaceOffsetFeatureData::IAccessSelections](#).

Remarks

To modify a feature in a...	Then...
Part	- TopDoc argument is the IModelDoc2 for the part - Component argument is NULL
Assembly	- TopDoc is the IModelDoc2 object for the assembly - Component argument is the IComponent2 object in which the feature is to be modified

This method puts the model into a rollback state to allow access to the selections that define this feature. You must use either of the following methods to restore the rollback state:

- [IFeature::ModifyDefinition](#) or [IFeature::IModifyDefinition2](#) if you modified the feature
- [ISurfaceOffsetFeatureData::ReleaseSelectionAccess](#) if you did not

See Also

[ISurfaceOffsetFeatureData Interface](#)

[ISurfaceOffsetFeatureData Members](#)

[ISurfaceOffsetFeatureData::AccessSelections Method](#)

Availability

SOLIDWORKS 2001Plus SP1, Revision Number 10.1

SOLIDWORKS API Help

[Send comments on this topic.](#)

IGetEntities Method (ISurfaceOffsetFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISurfaceOffsetFeatureData Interface](#) : IGetEntities Method (ISurfaceOffsetFeatureData)

Gets the offset surfaces or faces of this surface offset feature.

.NET Syntax

Visual Basic (Declaration)

```
Function IGetEntities( _  
    ByVal Count As System.Integer _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISurfaceOffsetFeatureData
Dim Count As System.Integer
Dim value As System.Object

value = instance.IGetEntities(Count)
```

C#

```
System.Object IGetEntities(
    System.int Count
)
```

C++/CLI

```
System.Object^ IGetEntities(
    & System.int Count
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Count

Number of offset surfaces or faces

Return Value

- in-process, unmanaged C++: Pointer to an array of offset surface or face feature [entities](#) of size Count
- VBA, VB.NET, C#, and C++/CLI: Not supported

See [In-process Methods](#) for details about this type of method.

Remarks

Call [ISurfaceOffsetFeatureData::GetEntitiesCount](#) before calling this method to get the value for Count.

See [Accessing Selections that Define Features](#) for additional details.

See Also

[ISurfaceOffsetFeatureData Interface](#)
[ISurfaceOffsetFeatureData Members](#)
[ISurfaceOffsetFeatureData::ISetEntities Method](#)
[ISurfaceOffsetFeatureData::Entities Property](#)

Availability

SOLIDWORKS 2012 SP04, Revision Number 20.4

SOLIDWORKS API Help

[Send comments on this topic.](#)

IGetFaces Method (ISurfaceOffsetFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISurfaceOffsetFeatureData Interface](#) : IGetFaces Method (ISurfaceOffsetFeatureData)

Obsolete. Superseded by [ISurfaceOffsetFeatureData::IGetEntities](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IGetFaces( _
    ByVal Count As System.Integer _
) As Face2
```

Visual Basic (Usage)



```
Dim instance As ISurfaceOffsetFeatureData
Dim Count As System.Integer
Dim value As Face2
```

```
value = instance.IGetFaces(Count)
```

C#

```
Face2 IGetFaces(  
    System.int Count  
)
```

C++/CLI

```
Face2^ IGetFaces(  
& System.int Count  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Count

Number of offset faces

Return Value

- in-process, unmanaged C++: Pointer to an array of [faces](#) of size Count
 - VBA, VB.NET, C#, and C++/CLI: Not supported
- See [In-process Methods](#) for details about this type of method.

Remarks

Call [ISurfaceOffsetFeatureData::GetFacesCount](#) before calling this method to get the value for Count.

See [Accessing Selections that Define Features](#) for additional details.

See Also

[ISurfaceOffsetFeatureData Interface](#)
[ISurfaceOffsetFeatureData Members](#)
[ISurfaceOffsetFeatureData::ISetFaces Method](#)
[ISurfaceOffsetFeatureData::Faces Property](#)

Availability

SOLIDWORKS 2001Plus SP1, Revision Number 10.1

SOLIDWORKS API Help

[Send comments on this topic.](#)

ISetEntities Method (ISurfaceOffsetFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISurfaceOffsetFeatureData Interface](#) : ISetEntities Method (ISurfaceOffsetFeatureData)

Sets the offset surfaces or faces for this surface offset feature.

.NET Syntax

Visual Basic (Declaration)

```
Sub ISetEntities( _  
    ByVal Count As System.Integer, _  
    ByRef EntityArray As System.Object _  
)
```

Visual Basic (Usage)



```
Dim instance As ISurfaceOffsetFeatureData  
Dim Count As System.Integer  
Dim EntityArray As System.Object  
  
instance.ISetEntities(Count, EntityArray)
```

C#

```
void ISetEntities(  
    System.int Count,  
    ref System.object EntityArray  
)
```

C++/CLI

```
void ISetEntities(  
& System.int Count,  
& System.Object^% EntityArray  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Count

Number of offset surfaces or faces

EntityArray

- in-process, unmanaged C++: Pointer to an array of offset surface or face feature [entities](#) of size Count

- VBA, VB.NET, C#, and C++/CLI: Not supported

See [In-process Methods](#) for details about this type of method.

Remarks

See [Accessing Selections that Define Features](#) for additional details.

See Also

[ISurfaceOffsetFeatureData Interface](#)
[ISurfaceOffsetFeatureData Members](#)
[ISurfaceOffsetFeatureData.Entities Property](#)
[ISurfaceOffsetFeatureData.IGetEntities Method](#)
[ISurfaceOffsetFeatureData.GetEntitiesCount Method](#)

Availability

SOLIDWORKS 2012 SP04, Revision Number 20.4

SOLIDWORKS API Help

[Send comments](#) on this topic.

ISetFaces Method (ISurfaceOffsetFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISurfaceOffsetFeatureData Interface](#) : ISetFaces Method (ISurfaceOffsetFeatureData)

Obsolete. Superseded by [ISurfaceOffsetFeatureData.ISetEntities](#).

.NET Syntax

Visual Basic (Declaration)

```
Sub ISetFaces( _  
    ByVal Count As System.Integer, _  
    ByRef FaceArr As Face2 _  
)
```

Visual Basic (Usage)

```
Dim instance As ISurfaceOffsetFeatureData  
Dim Count As System.Integer  
Dim FaceArr As Face2
```

```
instance.ISetFaces(Count, FaceArr)
```

C#

```
void ISetFaces(  
    System.int Count,
```

```
    ref Face2 FaceArr
)
```

C++/CLI

```
void ISetFaces(
&    System.int Count,
&    Face2^% FaceArr
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Count

Number of offset faces

FaceArr

- in-process, unmanaged C++: Pointer to an array of [faces](#) of size Count
 - VBA, VB.NET, C#, and C++/CLI: Not supported
- See [In-process Methods](#) for details about this type of method.

Visual Basic for Applications (VBA) Syntax

See [SurfaceOffsetFeatureData::ISetFaces](#).

Remarks

See [Accessing Selections that Define Features](#) for additional details.

See Also

[ISurfaceOffsetFeatureData Interface](#)
[ISurfaceOffsetFeatureData Members](#)
[ISurfaceOffsetFeatureData::GetFacesCount Method](#)
[ISurfaceOffsetFeatureData::!GetFaces Method](#)
[ISurfaceOffsetFeatureData::Faces Property](#)

Availability

SOLIDWORKS 2001Plus SP1, Revision Number 10.1

SOLIDWORKS API Help

[Send comments](#) on this topic.

ReleaseSelectionAccess Method (ISurfaceOffsetFeatureData)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISurfaceOffsetFeatureData Interface](#) : ReleaseSelectionAccess Method (ISurfaceOffsetFeatureData)

Releases access to the selections for this surface offset feature.

.NET Syntax

Visual Basic (Declaration)

```
Sub ReleaseSelectionAccess()
```

Visual Basic (Usage)



```
Dim instance As ISurfaceOffsetFeatureData
instance.ReleaseSelectionAccess()
```

C#

```
void ReleaseSelectionAccess()
```

C++/CLI

```
void ReleaseSelectionAccess();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [SurfaceOffsetFeatureData::ReleaseSelectionAccess](#).

Example

[Get Offset Surface Data \(VBA\)](#)
[Get Offset Surface Data \(VB.NET\)](#)
[Get Offset Surface Data \(C#\)](#)

Remarks

[ISurfaceOffsetFeatureData::AccessSelections](#) and [ISurfaceOffsetFeatureData::IAccessSelections](#) put the model in a rollback state to allow access to the selections that define the feature.

Use this method to restore the rollback state if you did not modify the feature, or use [IFeature::ModifyDefinition](#) or [IFeature::IModifyDefinition2](#) if you did modify the feature.

See Also

[ISurfaceOffsetFeatureData Interface](#)
[ISurfaceOffsetFeatureData Members](#)

Availability

SOLIDWORKS 2001Plus SP1, Revision Number 10.1

ISurfaceParameterizationData (Type)

ISurfaceParameterizationData Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) : ISurfaceParameterizationData Interface

Allows access to the parameterization data of a surface.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface ISurfaceParameterizationData
```

Visual Basic (Usage)

```
Dim instance As ISurfaceParameterizationData
```

C#

```
public interface ISurfaceParameterizationData
```

C++/CLI

```
public interface class ISurfaceParameterizationData
```

Visual Basic for Applications (VBA) Syntax

See [SurfaceParameterizationData](#).

Example

[Get B-Spline Surface Parameterization Data \(C#\)](#)
[Get B-Spline Surface Parameterization Data \(VB.NET\)](#)
[Get B-Spline Surface Parameterization Data \(VBA\)](#)

Remarks

If a surface is periodic in one direction (cylinder, cone, torus, sphere), then U is the periodic direction.

The -10000 to 10000 parameter range is the modeling limit for the modeler. This means that the values are effectively infinite in size. To get the parameter range from a given face, use [IFace2::GetBox](#) or [IFace2::IGetBox](#), [ISurface::GetClosestPointOn](#) or [ISurface::IGetClosestPointOn](#), and [ISurface::ReverseEvaluate](#) or [ISurface::IReverseEvaluate](#). These methods provide a true parameter range that the face is using on the surface.

Accessors

[ISurface::Parameterization2](#)

Access Diagram

[SurfaceParameterizationData](#)

See Also

[ISurfaceParameterizationData Members](#)
[SolidWorks.Interop.sldworks Namespace](#)
[ISurfParamData Interface](#)
[ISurface::GetBSurfParams3 Method](#)

ISurfaceParameterizationData Interface Members

[See Also](#) [Properties](#)



[SolidWorks.Interop.sldworks Namespace](#) : ISurfaceParameterizationData Interface

The following tables list the members exposed by [ISurfaceParameterizationData](#).

Public Properties

Name	Description
 UMax	Gets the highest value in the U parameter range.
 UMaxBoundType	Gets the behavior at the end of the U range.
 UMin	Gets the lowest value in the U parameter range.
 UMinBoundType	Gets the behavior at the start of the U range.
 UProperties	Gets the U parameterization properties.
 UPropertyNumber	Gets the number of U properties.
 VMax	Gets the highest value in the V parameter range.
 VMaxBoundType	Gets the behavior at the end of the V range.
 VMin	Gets the lowest value in the V parameter range.
 VMinBoundType	Gets the behavior at the start of the V range.
 VProperties	Gets the V parameterization properties.
 VPropertyNumber	Gets the number of V properties.

[Top](#)

See Also

[ISurfaceParameterizationData Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[ISurfParamData Interface](#)
[ISurface.GetBSurfParams3 Method](#)

ISurfaceParameterizationData Interface Properties

[See Also](#)

 [SolidWorks.Interop.sldworks Namespace](#) : ISurfaceParameterizationData Interface

For a list of all members of this type, see [ISurfaceParameterizationData members](#).

Public Properties

Name	Description
 UMax	Gets the highest value in the U parameter range.
 UMaxBoundType	Gets the behavior at the end of the U range.
 UMin	Gets the lowest value in the U parameter range.
 UMinBoundType	Gets the behavior at the start of the U range.
 UProperties	Gets the U parameterization properties.
 UPropertyNumber	Gets the number of U properties.
 VMax	Gets the highest value in the V parameter range.
 VMaxBoundType	Gets the behavior at the end of the V range.
 VMin	Gets the lowest value in the V parameter range.
 VMinBoundType	Gets the behavior at the start of the V range.
 VProperties	Gets the V parameterization properties.
 VPropertyNumber	Gets the number of V properties.

[Top](#)

See Also

UMax Property (ISurfaceParameterizationData)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISurfaceParameterizationData Interface](#) : UMax Property (ISurfaceParameterizationData)

Gets the highest value in the U parameter range.

.NET Syntax

Visual Basic (Declaration)

ReadOnly Property UMax As System.Double

Visual Basic (Usage)



```
Dim instance As ISurfaceParameterizationData  
Dim value As System.Double  
  
value = instance.UMax
```

C#

```
System.double UMax {get;}
```

C++/CLI

```
property System.double UMax {  
    System.double get();  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Highest U parameter value

Visual Basic for Applications (VBA) Syntax

See [SurfaceParameterizationData::UMax](#).

Example

[Get B-Spline Surface Parameterization Data \(C#\)](#)
[Get B-Spline Surface Parameterization Data \(VB.NET\)](#)
[Get B-Spline Surface Parameterization Data \(VBA\)](#)

See Also

[ISurfaceParameterizationData Interface](#)
[ISurfaceParameterizationData Members](#)
[ISurfaceParameterizationData::UMaxBoundType Property](#)
[ISurfaceParameterizationData::UMin Property](#)
[ISurfaceParameterizationData::UProperties Property](#)

Availability

SOLIDWORKS 2011 FCS, Revision Number 19.0

UMaxBoundType Property (ISurfaceParameterizationData)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISurfaceParameterizationData Interface](#) : UMaxBoundType Property (ISurfaceParameterizationData)

Gets the behavior at the end of the U range.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property UMaxBoundType As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ISurfaceParameterizationData  
Dim value As System.Integer  
  
value = instance.UMaxBoundType
```

C#

```
System.int UMaxBoundType {get;}
```

C++/CLI

```
property System.int UMaxBoundType {  
    System.int get();  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Type of behavior as defined in [swBoundType_e](#)

Visual Basic for Applications (VBA) Syntax

See [SurfaceParameterizationData::UMaxBoundType](#).

Example

[Get B-Spline Surface Parameterization Data \(C#\)](#)
[Get B-Spline Surface Parameterization Data \(VB.NET\)](#)
[Get B-Spline Surface Parameterization Data \(VBA\)](#)

See Also

[ISurfaceParameterizationData Interface](#)
[ISurfaceParameterizationData Members](#)
[ISurfaceParameterizationData::UMax Property](#)

Availability

SOLIDWORKS 2011 FCS, Revision Number 19.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

UMin Property (ISurfaceParameterizationData)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISurfaceParameterizationData Interface](#) : UMin Property (ISurfaceParameterizationData)

Gets the lowest value in the U parameter range.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property UMin As System.Double
```

Visual Basic (Usage)



```
Dim instance As ISurfaceParameterizationData  
Dim value As System.Double  
  
value = instance.UMin
```

C#

```
System.double UMin {get;}
```

C++/CLI

```
property System.double UMin {  
    System.double get();  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Lowest U parameter value

Visual Basic for Applications (VBA) Syntax

See [SurfaceParameterizationData::UMin](#).

Example

[Get B-Spline Surface Parameterization Data \(C#\)](#)
[Get B-Spline Surface Parameterization Data \(VB.NET\)](#)
[Get B-Spline Surface Parameterization Data \(VBA\)](#)

See Also

[ISurfaceParameterizationData Interface](#)
[ISurfaceParameterizationData Members](#)
[ISurfaceParameterizationData::UMinBoundType Property](#)
[ISurfaceParameterizationData::UProperties Property](#)
[ISurfaceParameterizationData::UMax Property](#)

Availability

SOLIDWORKS 2011 FCS, Revision Number 19.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

UMinBoundType Property (ISurfaceParameterizationData)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISurfaceParameterizationData Interface](#) : UMinBoundType Property (ISurfaceParameterizationData)

Gets the behavior at the start of the U range.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property UMinBoundType As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ISurfaceParameterizationData  
Dim value As System.Integer
```

```
value = instance.UMinBoundType
```

C#

```
System.int UMinBoundType {get;}
```

C++/CLI

```
property System.int UMinBoundType {  
    System.int get();  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Type of behavior as defined in [swBoundType_e](#)

Visual Basic for Applications (VBA) Syntax

See [SurfaceParameterizationData::UMinBoundType](#).

Example

[Get B-Spline Surface Parameterization Data \(C#\)](#)
[Get B-Spline Surface Parameterization Data \(VB.NET\)](#)
[Get B-Spline Surface Parameterization Data \(VBA\)](#)

See Also

[ISurfaceParameterizationData Interface](#)
[ISurfaceParameterizationData Members](#)
[ISurfaceParameterizationData::UMin Property](#)

Availability

SOLIDWORKS 2011 FCS, Revision Number 19.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

UProperties Property (ISurfaceParameterizationData)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISurfaceParameterizationData Interface](#) : UProperties Property (ISurfaceParameterizationData)

Gets the U parameterization properties.

.NET Syntax

Visual Basic (Declaration)

ReadOnly Property UProperties As System.Object

Visual Basic (Usage)



```
Dim instance As ISurfaceParameterizationData  
Dim value As System.Object  
  
value = instance.UProperties
```

C#

```
System.object UProperties {get;}
```

C++/CLI

```
property System.Object^ UProperties {  
    System.Object^ get();  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Array of properties as defined in [swParameterizationPropertyType_e](#)

Visual Basic for Applications (VBA) Syntax

See [SurfaceParameterizationData::UProperties](#).

Example

[Get B-Spline Surface Parameterization Data \(C#\)](#)
[Get B-Spline Surface Parameterization Data \(VB.NET\)](#)
[Get B-Spline Surface Parameterization Data \(VBA\)](#)

See Also

[ISurfaceParameterizationData Interface](#)
[ISurfaceParameterizationData Members](#)
[ISurfaceParameterizationData::UPROPERTYNUMBER Property](#)

Availability

SOLIDWORKS 2011 FCS, Revision Number 19.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

UPROPERTYNUMBER Property (ISurfaceParameterizationData)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISurfaceParameterizationData Interface](#) : UPROPERTYNUMBER Property (ISurfaceParameterizationData)

Gets the number of U properties.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property UPROPERTYNUMBER As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ISurfaceParameterizationData  
Dim value As System.Integer
```

```
value = instance.UPROPERTYNUMBER
```

C#

```
System.int UPROPERTYNUMBER {get;}
```

C++/CLI

```
property System.int UPROPERTYNUMBER {  
    System.int get();  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Number of properties returned by [ISurfaceParameterizationData::UPROPERTIES](#)

Visual Basic for Applications (VBA) Syntax

See [SurfaceParameterizationData::UPROPERTYNUMBER](#).

Example

[Get B-Spline Surface Parameterization Data \(C#\)](#)
[Get B-Spline Surface Parameterization Data \(VB.NET\)](#)
[Get B-Spline Surface Parameterization Data \(VBA\)](#)

See Also

[ISurfaceParameterizationData Interface](#)
[ISurfaceParameterizationData Members](#)

Availability

SOLIDWORKS 2011 FCS, Revision Number 19.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

VMax Property (ISurfaceParameterizationData)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISurfaceParameterizationData Interface](#) : VMax Property (ISurfaceParameterizationData)

Gets the highest value in the V parameter range.

.NET Syntax

Visual Basic (Declaration)

ReadOnly Property VMax As System.Double

Visual Basic (Usage)



```
Dim instance As ISurfaceParameterizationData  
Dim value As System.Double  
  
value = instance.VMax
```

C#

```
System.double VMax {get;}
```

C++/CLI

```
property System.double VMax {  
    System.double get();  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Highest V parameter value

Visual Basic for Applications (VBA) Syntax

See [SurfaceParameterizationData::VMax](#).

Example

[Get B-Spline Surface Parameterization Data \(C#\)](#)
[Get B-Spline Surface Parameterization Data \(VB.NET\)](#)
[Get B-Spline Surface Parameterization Data \(VBA\)](#)

See Also

[ISurfaceParameterizationData Interface](#)
[ISurfaceParameterizationData Members](#)
[ISurfaceParameterizationData::VMaxBoundType Property](#)
[ISurfaceParameterizationData::VMin Property](#)
[ISurfaceParameterizationData::VProperties Property](#)

Availability

SOLIDWORKS 2011 FCS, Revision Number 19.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

VMaxBoundType Property (ISurfaceParameterizationData)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISurfaceParameterizationData Interface](#) : VMaxBoundType Property (ISurfaceParameterizationData)

Gets the behavior at the end of the V range.

.NET Syntax

Visual Basic (Declaration)

ReadOnly Property VMaxBoundType As System.Integer

Visual Basic (Usage)



```
Dim instance As ISurfaceParameterizationData  
Dim value As System.Integer
```



```
value = instance.VMaxBoundType
```

C#

```
System.int VMaxBoundType {get;}
```

C++/CLI

```
property System.int VMaxBoundType {  
    System.int get();  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Type of behavior as defined in [swBoundType_e](#)

Visual Basic for Applications (VBA) Syntax

See [SurfaceParameterizationData::VMaxBoundType](#).

Example

[Get B-Spline Surface Parameterization Data \(C#\)](#)
[Get B-Spline Surface Parameterization Data \(VB.NET\)](#)
[Get B-Spline Surface Parameterization Data \(VBA\)](#)

See Also

[ISurfaceParameterizationData Interface](#)
[ISurfaceParameterizationData Members](#)
[ISurfaceParameterizationData::VMax Property](#)

Availability

SOLIDWORKS 2011 FCS, Revision Number 19.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

VMin Property (ISurfaceParameterizationData)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISurfaceParameterizationData Interface](#) : VMin Property (ISurfaceParameterizationData)

Gets the lowest value in the V parameter range.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property VMin As System.Double
```

Visual Basic (Usage)



```
Dim instance As ISurfaceParameterizationData  
Dim value As System.Double
```

```
value = instance.VMin
```

C#

```
System.double VMin {get;}
```

C++/CLI

```
property System.double VMin {  
    System.double get();  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Lowest V parameter value

Visual Basic for Applications (VBA) Syntax

See [SurfaceParameterizationData::VMin](#).

Example

[Get B-Spline Surface Parameterization Data \(C#\)](#)
[Get B-Spline Surface Parameterization Data \(VB.NET\)](#)
[Get B-Spline Surface Parameterization Data \(VBA\)](#)

See Also

[ISurfaceParameterizationData Interface](#)
[ISurfaceParameterizationData Members](#)
[ISurfaceParameterizationData::VMinBoundType Property](#)
[ISurfaceParameterizationData::VMax Property](#)
[ISurfaceParameterizationData::VProperties Property](#)

Availability

SOLIDWORKS 2011 FCS, Revision Number 19.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

VMinBoundType Property (ISurfaceParameterizationData)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISurfaceParameterizationData Interface](#) : VMinBoundType Property (ISurfaceParameterizationData)

Gets the behavior at the start of the V range.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property VMinBoundType As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ISurfaceParameterizationData  
Dim value As System.Integer  
  
value = instance.VMinBoundType
```

C#

```
System.int VMinBoundType {get;}
```

C++/CLI

```
property System.int VMinBoundType {  
    System.int get();  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Type of behavior as defined in [swBoundType_e](#)

Visual Basic for Applications (VBA) Syntax

See [SurfaceParameterizationData::VMinBoundType](#).

Example

[Get B-Spline Surface Parameterization Data \(C#\)](#)
[Get B-Spline Surface Parameterization Data \(VB.NET\)](#)
[Get B-Spline Surface Parameterization Data \(VBA\)](#)

See Also

[ISurfaceParameterizationData Interface](#)
[ISurfaceParameterizationData Members](#)
[ISurfaceParameterizationData::VMin Property](#)

Availability

SOLIDWORKS 2011 FCS, Revision Number 19.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

VProperties Property (ISurfaceParameterizationData)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISurfaceParameterizationData Interface](#) : VProperties Property (ISurfaceParameterizationData)

Gets the V parameterization properties.

.NET Syntax

Visual Basic (Declaration)

ReadOnly Property VProperties As System.Object

Visual Basic (Usage)



```
Dim instance As ISurfaceParameterizationData  
Dim value As System.Object  
  
value = instance.VProperties
```

C#

```
System.Object VProperties {get;}
```

C++/CLI

```
property System.Object^ VProperties {  
    System.Object^ get();  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Array of properties as defined in [swParameterizationPropertyType_e](#)

Visual Basic for Applications (VBA) Syntax

See [SurfaceParameterizationData::VProperties](#).

Example

[Get B-Spline Surface Parameterization Data \(C#\)](#)
[Get B-Spline Surface Parameterization Data \(VB.NET\)](#)
[Get B-Spline Surface Parameterization Data \(VBA\)](#)

See Also

[ISurfaceParameterizationData Interface](#)
[ISurfaceParameterizationData Members](#)
[ISurfaceParameterizationData::VPropertyNumber Property](#)

Availability

SOLIDWORKS 2011 FCS, Revision Number 19.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

VPropertyNumber Property (ISurfaceParameterizationData)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISurfaceParameterizationData Interface](#) : VPropertyNumber Property (ISurfaceParameterizationData)

Gets the number of V properties.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property VPropertyNumber As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ISurfaceParameterizationData  
Dim value As System.Integer
```

```
value = instance.VPropertyNumber
```

C#

```
System.int VPropertyNumber {get;}
```

C++/CLI

```
property System.int VPropertyNumber {  
    System.int get();  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Number of properties returned by [ISurfaceParameterizationData::VProperties](#)

Visual Basic for Applications (VBA) Syntax

See [SurfaceParameterizationData::VPropertyNumber](#).

Example

[Get B-Spline Surface Parameterization Data \(C#\)](#)
[Get B-Spline Surface Parameterization Data \(VB.NET\)](#)
[Get B-Spline Surface Parameterization Data \(VBA\)](#)

See Also

[ISurfaceParameterizationData Interface](#)
[ISurfaceParameterizationData Members](#)

Availability

SOLIDWORKS 2011 FCS, Revision Number 19.0