

SOLIDWORKS Document Manager API (.NET) — Reference (13/19): ISwDMDocument10- ISwDMDocument17

SOLIDWORKS API Documentation (converted from CHM)

ISwDMDocument10 (Type)

SOLIDWORKS Document Manager API Help

[Send comments](#) on this topic.

ISwDMDocument10 Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.swdocumentmgr.Namespace](#) : ISwDMDocument10 Interface

Accesses the document.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface ISwDMDocument10
    Inherits
    ISwDMDocument, ISwDMDocument3, ISwDMDocument4, ISwDMDocument5, ISwDMDocument6, ISwDMDocument7, ISwDMDocument8
```

Visual Basic (Usage)



```
Dim instance As ISwDMDocument10
```

C#

```
public interface ISwDMDocument10 :
    ISwDMDocument, ISwDMDocument3, ISwDMDocument4, ISwDMDocument5, ISwDMDocument6, ISwDMDocument7, ISwDMDocument8
```

C++/CLI

```
public interface class ISwDMDocument10 : public
    ISwDMDocument, ISwDMDocument3, ISwDMDocument4, ISwDMDocument5, ISwDMDocument6, ISwDMDocument7, ISwDMDocument8
```

Visual Basic for Applications (VBA) Syntax

See [SwDMDocument10](#).

Example

[Get Preview Bitmap of Drawing Sheet \(VB.NET\)](#)
[Get Preview Bitmap of Drawing Sheet \(C#\)](#)

Remarks

Before you can access this object, you must call [ISwDMApplication::GetDocument](#).

NOTES:

- You can access an ISwDMDocument10 object by calling QueryInterface on an [ISwDMDocument](#) object in C++ or by direct assignment in Visual Basic.
- The SwDMDocument object can be assigned to an ISwDMDocument10 variable, just like the SOLIDWORKS [IModelDoc2](#) object can be assigned to a SOLIDWORKS [IPartDoc](#) variable.

Accessors

[ISwDMApplication::GetDocument](#)
[ISwDMConfiguration::Document](#)
[ISwDMConfigurationMgr::Document](#)

See Also

[ISwDMDocument10 Members](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)
[ISwDMDocument3 Interface](#)
[ISwDMDocument4 Interface](#)
[ISwDMDocument5 Interface](#)
[ISwDMDocument6 Interface](#)
[ISwDMDocument7 Interface](#)
[ISwDMDocument8 Interface](#)
[ISwDMDocument13 Interface](#)
[ISwDMDocument14 Interface](#)
[ISwDMDocument15 Interface](#)
[ISwDMDocument16 Interface](#)
[ISwDMDocument17 Interface](#)
[ISwDMDocument18 Interface](#)
[ISwDMDocument19 Interface](#)
[ISwDMDocument20 Interface](#)
[ISwDMDocument21 Interface](#)
[ISwDMDocument22 Interface](#)
[ISwDMDocument23 Interface](#)
[ISwDMDocument24 Interface](#)
[ISwDMDocument25 Interface](#)
[ISwDMDocument26 Interface](#)
[ISwDMDocument27 Interface](#)
[ISwDMDocument28 Interface](#)
[ISwDMDocument29 Interface](#)
[ISwDMDocument30 Interface](#)

ISwDMDocument10 Interface Methods

[See Also](#)


SolidWorks.Interop.swdocumentmgr Namespace : ISwDMDocument10 Interface

For a list of all members of this type, see [ISwDMDocument10 members](#).

Public Methods

Name	Description
 GetPreviewBitmap	Gets the preview bitmap (.bmp) for this document.
 GetPreviewPNGBitmap	Gets the PNG preview bitmap (.png) for this document.
 GetSheets	Gets the sheets in a drawing document.
 GetTable	Gets the specified table.
 GetTableNames	Gets the names of the tables in this document.
 GetViews	Gets the views in this document.

[Top](#)

See Also

[ISwDMDocument10 Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)
[ISwDMDocument3 Interface](#)
[ISwDMDocument4 Interface](#)
[ISwDMDocument5 Interface](#)
[ISwDMDocument6 Interface](#)
[ISwDMDocument7 Interface](#)
[ISwDMDocument8 Interface](#)
[ISwDMDocument13 Interface](#)
[ISwDMDocument14 Interface](#)
[ISwDMDocument15 Interface](#)
[ISwDMDocument16 Interface](#)
[ISwDMDocument17 Interface](#)
[ISwDMDocument18 Interface](#)
[ISwDMDocument19 Interface](#)
[ISwDMDocument20 Interface](#)
[ISwDMDocument21 Interface](#)
[ISwDMDocument22 Interface](#)
[ISwDMDocument23 Interface](#)
[ISwDMDocument24 Interface](#)
[ISwDMDocument25 Interface](#)
[ISwDMDocument26 Interface](#)
[ISwDMDocument27 Interface](#)
[ISwDMDocument28 Interface](#)
[ISwDMDocument29 Interface](#)
[ISwDMDocument30 Interface](#)

ISwDMDocument10 Interface Members

[See Also](#) [Properties](#) [Methods](#)


SolidWorks.Interop.swdocumentmgr Namespace : ISwDMDocument10 Interface

The following tables list the members exposed by [ISwDMDocument10](#).

Public Properties

Name	Description
 PreviewPNGStreamName	Gets the name of the stream for the preview bitmap (.png) of this document.
 PreviewStreamName	Gets the name of the stream for the preview bitmap (.bmp) of this configuration.

[Top](#)

Public Methods

Name	Description
 GetPreviewBitmap	Gets the preview bitmap (.bmp) for this document.
 GetPreviewPNGBitmap	Gets the PNG preview bitmap (.png) for this document.
 GetSheets	Gets the sheets in a drawing document.
 GetTable	Gets the specified table.
 GetTableNames	Gets the names of the tables in this document.
 GetViews	Gets the views in this document.

[Top](#)

See Also

[ISwDMDocument10 Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)
[ISwDMDocument3 Interface](#)
[ISwDMDocument4 Interface](#)
[ISwDMDocument5 Interface](#)
[ISwDMDocument6 Interface](#)
[ISwDMDocument7 Interface](#)
[ISwDMDocument8 Interface](#)
[ISwDMDocument13 Interface](#)
[ISwDMDocument14 Interface](#)
[ISwDMDocument15 Interface](#)
[ISwDMDocument16 Interface](#)
[ISwDMDocument17 Interface](#)
[ISwDMDocument18 Interface](#)
[ISwDMDocument19 Interface](#)
[ISwDMDocument20 Interface](#)
[ISwDMDocument21 Interface](#)
[ISwDMDocument22 Interface](#)
[ISwDMDocument23 Interface](#)
[ISwDMDocument24 Interface](#)
[ISwDMDocument25 Interface](#)
[ISwDMDocument26 Interface](#)
[ISwDMDocument27 Interface](#)
[ISwDMDocument28 Interface](#)
[ISwDMDocument29 Interface](#)
[ISwDMDocument30 Interface](#)

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

ISwDMDocument10 Interface Properties

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMDocument10 Interface

For a list of all members of this type, see [ISwDMDocument10 members](#).

Public Properties

Name	Description
 PreviewPNGStreamName	Gets the name of the stream for the preview bitmap (.png) of this document.
 PreviewStreamName	Gets the name of the stream for the preview bitmap (.bmp) of this configuration.

[Top](#)

See Also

[ISwDMDocument10 Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)
[ISwDMDocument3 Interface](#)
[ISwDMDocument4 Interface](#)
[ISwDMDocument5 Interface](#)
[ISwDMDocument6 Interface](#)
[ISwDMDocument7 Interface](#)
[ISwDMDocument8 Interface](#)
[ISwDMDocument13 Interface](#)
[ISwDMDocument14 Interface](#)
[ISwDMDocument15 Interface](#)
[ISwDMDocument16 Interface](#)
[ISwDMDocument17 Interface](#)

[ISwDMDocument18 Interface](#)
[ISwDMDocument19 Interface](#)
[ISwDMDocument20 Interface](#)
[ISwDMDocument21 Interface](#)
[ISwDMDocument22 Interface](#)
[ISwDMDocument23 Interface](#)
[ISwDMDocument24 Interface](#)
[ISwDMDocument25 Interface](#)
[ISwDMDocument26 Interface](#)
[ISwDMDocument27 Interface](#)
[ISwDMDocument28 Interface](#)
[ISwDMDocument29 Interface](#)
[ISwDMDocument30 Interface](#)

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

GetPreviewBitmap Method (ISwDMDocument10)

[See Also](#) [Example](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMDocument10 Interface](#) : GetPreviewBitmap Method (ISwDMDocument10)

Gets the preview bitmap (.bmp) for this document.

.NET Syntax

Visual Basic (Declaration)

```
Function GetPreviewBitmap( _  
    ByRef result As SwDmPreviewError _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISwDMDocument10  
Dim result As SwDmPreviewError  
Dim value As System.Object  
  
value = instance.GetPreviewBitmap(result)
```

C#

```
System.object GetPreviewBitmap(  
    out SwDmPreviewError result  
)
```

C++/CLI

```
System.Object^ GetPreviewBitmap(  
& [Out] SwDmPreviewError result  
)
```

Parameters

result

Success or error code as defined by [SwDmPreviewError](#)

Return Value

Pointer to the preview bitmap (.bmp) (an IPictureDisp*)

Visual Basic for Applications (VBA) Syntax

See [SwDMDocument10::GetPreviewBitmap](#).

Example

[Get Preview Bitmap of Drawing Sheet \(VB.NET\)](#)
[Get Preview Bitmap of Drawing Sheet \(C#\)](#)

Remarks

If a drawing has multiple sheets, then a preview bitmap is created only for the drawing sheet that was active when the drawing was last saved. If you want previews for all sheets in a multiple sheet drawing, then use [ISwDMSheet2::GetPreviewPNGBitmap](#).

If a part or assembly has multiple configurations, then a preview bitmap is created only for the configuration that was active when the part or assembly was last saved. If you want previews for all configurations in a multiple configuration part or assembly, then use

[ISwDMConfiguration7::GetPreviewPNGBitmap.](#)

This method does not work in out-of-process and some ASP.NET/IIS web applications.

See Also

[ISwDMDocument10 Interface](#)
[ISwDMDocument10 Members](#)
[ISwDMDocument10::GetPreviewPNGBitmap Method](#)
[ISwDMDocument10::PreviewPNGStreamName Property](#)
[ISwDMDocument10::PreviewStreamName Property](#)
[ISwDMConfiguration::GetPreviewBitmap Method](#)
[ISwDMConfiguration::PreviewStreamName Property](#)
[ISwDMConfiguration7::GetPreviewPNGBitmap Method](#)
[ISwDMConfiguration7::PreviewPNGStreamName Property](#)
[ISwDMConfiguration9::GetPreviewBitmapBytes Method](#)
[ISwDMConfiguration9::GetPreviewPNGBitmapBytes Method](#)
[ISwDMSheet2::GetPreviewPNGBitmap Method](#)
[ISwDMSheet2::GetPreviewPNGBitmapBytes Method](#)
[ISwDMSheet2::PreviewPNGStreamName Property](#)
[ISwDMApplication5::GetPreviewBitmapForAnnotationFiles Method \(\)](#)

Availability

SOLIDWORKS Document Manager API 2008 FCS

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

GetPreviewPNGBitmap Method (ISwDMDocument10)

[See Also](#) [Example](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMDocument10 Interface](#) : GetPreviewPNGBitmap Method (ISwDMDocument10)

Gets the PNG preview bitmap (.png) for this document.

.NET Syntax

Visual Basic (Declaration)

```
Function GetPreviewPNGBitmap( _  
    ByRef result As SwDmPreviewError _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISwDMDocument10  
Dim result As SwDmPreviewError  
Dim value As System.Object  
  
value = instance.GetPreviewPNGBitmap(result)
```

C#

```
System.Object GetPreviewPNGBitmap(  
    out SwDmPreviewError result  
)
```

C++/CLI

```
System.Object^ GetPreviewPNGBitmap(  
& [Out] SwDmPreviewError result  
)
```

Parameters

result

Success or error code as defined by [swDmPreviewError](#)

Return Value

Pointer to the preview bitmap (.png) (an IPictureDisp*)

Visual Basic for Applications (VBA) Syntax

See [SwDMDocument10::GetPreviewPNGBitmap.](#)

Example

[Get Preview Bitmap of Drawing Sheet \(VB.NET\)](#)
[Get Preview Bitmap of Drawing Sheet \(C#\)](#)

Remarks

This method does not work in out-of-process and some ASP.NET/IIS web applications.

See Also

[ISwDMDocument10 Interface](#)
[ISwDMDocument10 Members](#)
[ISwDMDocument10::GetPreviewBitmap Method](#)
[ISwDMDocument10::PreviewPNGStreamName Property](#)
[ISwDMDocument10::PreviewStreamName Property](#)
[ISwDMConfiguration::GetPreviewBitmap Method](#)
[ISwDMConfiguration::PreviewStreamName Property](#)
[ISwDMConfiguration7::GetPreviewPNGBitmap Method](#)
[ISwDMConfiguration7::PreviewPNGStreamName Property](#)
[ISwDMConfiguration9::GetPreviewBitmapBytes Method](#)
[ISwDMConfiguration9::GetPreviewPNGBitmapBytes Method](#)
[ISwDMSheet2::GetPreviewPNGBitmap Method](#)
[ISwDMSheet2::GetPreviewPNGBitmapBytes Method](#)
[ISwDMSheet2::PreviewPNGStreamName Property](#)
[ISwDMAApplication5::GetPreviewBitmapForAnnotationFiles Method\(\)](#)

Availability

SOLIDWORKS Document Manager API 2008 FCS

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

GetSheets Method (ISwDMDocument10)

[See Also](#) [Example](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMDocument10 Interface](#) : GetSheets Method (ISwDMDocument10)

Gets the sheets in a drawing document.

.NET Syntax

Visual Basic (Declaration)

```
Function GetSheets() As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISwDMDocument10  
Dim value As System.Object
```

```
value = instance.GetSheets()
```

C#

```
System.Object GetSheets()
```

C++/CLI

```
System.Object^ GetSheets();
```

Return Value

Array of [sheets](#)

Visual Basic for Applications (VBA) Syntax

See [SwDMDocument10::GetSheets](#).

Example

[Get Preview Bitmaps of Drawing Sheets \(C#\)](#)
[Get Preview Bitmaps of Drawing Sheets \(VB.NET\)](#)

Remarks

This method only supports documents saved in SOLIDWORKS 2008 and later.

See Also

[ISwDMDocument10 Interface](#)
[ISwDMDocument10 Members](#)

Availability

SOLIDWORKS Document Manager API 2009 SP0

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

GetTable Method (ISwDMDocument10)

[See Also](#) [Example](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMDocument10 Interface](#) : GetTable Method (ISwDMDocument10)

Gets the specified table.

.NET Syntax

Visual Basic (Declaration)

```
Function GetTable( _  
    ByVal NameIn As System.String _  
) As SwDMTable
```

Visual Basic (Usage)



```
Dim instance As ISwDMDocument10  
Dim NameIn As System.String  
Dim value As SwDMTable
```

```
value = instance.GetTable(NameIn)
```

C#

```
SwDMTable GetTable(  
    System.string NameIn  
)
```

C++/CLI

```
SwDMTable^ GetTable(  
& System.String^ NameIn  
)
```

Parameters

NameIn
Name of table

Return Value

[Table](#)

Visual Basic for Applications (VBA) Syntax

See [SwDMDocument10::GetTable](#).

Example

[Get BOM Tables \(C#\)](#)
[Get BOM Tables \(VB.NET\)](#)

Remarks

Only revision and bill of materials (BOM) tables are supported.

Before calling this method, call [ISwDMDocument10::GetTableNames](#) to get the names of the tables in this document.

See Also

[ISwDMDocument10 Interface](#)
[ISwDMDocument10 Members](#)
[ISwDMTable Interface](#)
[ISwDMTable2 Interface](#)

Availability

SOLIDWORKS Document Manager API 2009 SP0

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

GetTableNames Method (ISwDMDocument10)

[See Also](#) [Example](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMDocument10 Interface](#) : GetTableNames Method (ISwDMDocument10)

Gets the names of the tables in this document.

.NET Syntax

Visual Basic (Declaration)

```
Function GetTableNames( _  
    ByVal TableType As SwDmTableType _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISwDMDocument10  
Dim TableType As SwDmTableType  
Dim value As System.Object  
  
value = instance.GetTableNames(TableType)
```

C#

```
System.object GetTableNames(  
    SwDmTableType TableType  
)
```

C++/CLI

```
System.Object^ GetTableNames(  
& SwDmTableType TableType  
)
```

Parameters

TableType

Type of table as defined by [swDmTableType](#)

Return Value

Array of table names

Visual Basic for Applications (VBA) Syntax

See [SwDMDocument10::GetTableNames](#).

Example

[Get BOM Tables \(C#\)](#)
[Get BOM Tables \(VB.NET\)](#)

See Also

[ISwDMDocument10 Interface](#)
[ISwDMDocument10 Members](#)
[ISwDMDocument10::GetTable Method](#)
[ISwDMTable Interface](#)
[ISwDMTable2 Interface](#)

Availability

SOLIDWORKS Document Manager API 2009 SP0

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

GetViews Method (ISwDMDocument10)

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMDocument10 Interface](#) : GetViews Method (ISwDMDocument10)

Gets the views in this document.

.NET Syntax

Visual Basic (Declaration)

```
Function GetViews() As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISwDMDocument10  
Dim value As System.Object
```

```
value = instance.GetViews()
```

C#

```
System.Object GetViews()
```

C++/CLI

```
System.Object^ GetViews();
```

Return Value

Array of [views](#)

Visual Basic for Applications (VBA) Syntax

See [SwDMDocument10::GetViews](#).

Remarks

This method only supports documents saved in SOLIDWORKS 2008 and later.

See Also

[ISwDMDocument10 Interface](#)
[ISwDMDocument10 Members](#)

Availability

SOLIDWORKS Document Manager API 2009 SP0

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

PreviewPNGStreamName Property (ISwDMDocument10)

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMDocument10 Interface](#) : PreviewPNGStreamName Property (ISwDMDocument10)

Gets the name of the stream for the preview bitmap (.png) of this document.

Visual Basic Syntax

Visual Basic (Declaration)

```
ReadOnly Property PreviewPNGStreamName As System.String
```

Visual Basic (Usage)



```
Dim instance As ISwDMDocument10
Dim value As System.String

value = instance.PreviewPNGStreamName
```

C#

```
System.string PreviewPNGStreamName {get;}
```

C++/CLI

```
property System.String^ PreviewPNGStreamName {
    System.String^ get();
}
```

Property Value

Name of the stream for the preview bitmap (.png) or an empty string if preview bitmap (.png) does not exist

Visual Basic for Applications (VBA) Syntax

See [SwDMDocument10::PreviewPNGStreamName](#).

See Also

[ISwDMDocument10 Interface](#)
[ISwDMDocument10 Members](#)
[ISwDMDocument10::PreviewStreamName Property](#)
[ISwDMDocument10::GetPreviewBitmap Method](#)
[ISwDMDocument10::GetPreviewPNGBitmap Method](#)
[ISwDMConfiguration::GetPreviewBitmap Method](#)
[ISwDMConfiguration::PreviewStreamName Property](#)
[ISwDMConfiguration7::GetPreviewPNGBitmap Method](#)
[ISwDMConfiguration7::PreviewPNGStreamName Property](#)
[ISwDMConfiguration9::GetPreviewBitmapBytes Method](#)
[ISwDMConfiguration9::GetPreviewPNGBitmapBytes Method](#)
[ISwDMSheet2::GetPreviewPNGBitmap Method](#)
[ISwDMSheet2::GetPreviewPNGBitmapBytes Method](#)
[ISwDMSheet2::PreviewPNGStreamName Property](#)

Availability

SOLIDWORKS Document Manager API 2008 FCS

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

PreviewStreamName Property (ISwDMDocument10)

[See Also](#) [Example](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMDocument10 Interface](#) : PreviewStreamName Property (ISwDMDocument10)

Gets the name of the stream for the preview bitmap (.bmp) of this configuration.

Visual Basic Syntax

Visual Basic (Declaration)

```
ReadOnly Property PreviewStreamName As System.String
```

Visual Basic (Usage)



```
Dim instance As ISwDMDocument10
Dim value As System.String

value = instance.PreviewStreamName
```

C#

```
System.string PreviewStreamName {get;}
```

C++/CLI

```
property System.String^ PreviewStreamName {  
    System.String^ get();  
}
```

Property Value

Name of the stream for the preview bitmap (.bmp) or an empty string if preview bitmap (.bmp) does not exist

Visual Basic for Applications (VBA) Syntax

See [SwDMDocument10::PreviewStreamName](#).

Example

[Get Preview Bitmap of Drawing Sheet \(VB.NET\)](#)
[Get Preview Bitmap of Drawing Sheet \(C#\)](#)

See Also

[ISwDMDocument10 Interface](#)
[ISwDMDocument10 Members](#)
[ISwDMDocument10::GetPreviewBitmap Method](#)
[ISwDMDocument10::GetPreviewPNGBitmap Method](#)
[ISwDMDocument10::PreviewPNGStreamName Property](#)
[ISwDMConfiguration::GetPreviewBitmap Method](#)
[ISwDMConfiguration::PreviewStreamName Property](#)
[ISwDMConfiguration7::GetPreviewPNGBitmap Method](#)
[ISwDMConfiguration7::PreviewPNGStreamName Property](#)
[ISwDMConfiguration9::GetPreviewBitmapBytes Method](#)
[ISwDMConfiguration9::GetPreviewPNGBitmapBytes Method](#)
[ISwDMSheet2::GetPreviewPNGBitmap Method](#)
[ISwDMSheet2::GetPreviewPNGBitmapBytes Method](#)
[ISwDMSheet2::PreviewPNGStreamName Property](#)

Availability

SOLIDWORKS Document Manager API 2008 FCS

ISwDMDocument11 (Type)

ISwDMDocument11 Interface

[See Also](#) [Members](#)



[SolidWorks.Interop.swdocumentmgr.Namespace](#) : ISwDMDocument11 Interface

Obsolete.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface ISwDMDocument11
```

Visual Basic (Usage)



```
Dim instance As ISwDMDocument11
```

C#

```
public interface ISwDMDocument11
```

C++/CLI

```
public interface class ISwDMDocument11
```

Visual Basic for Applications (VBA) Syntax

See [SwDMDocument11](#).

Remarks

Before you can access this object, you must call [ISwDMApplication::GetDocument](#).

NOTES:

- You can access an ISwDMDocument11 object by calling QueryInterface on an [ISwDMDocument](#) object in C++ or by direct assignment in Visual Basic.
- The SwDMDocument object can be assigned to an ISwDMDocument11 variable, just like the SOLIDWORKS [IModelDoc2](#) object can be assigned to a SOLIDWORKS [IPartDoc](#) variable.

Accessors

[ISwDMApplication::GetDocument](#)

[ISwDMConfiguration::Document](#)

[ISwDMConfigurationMgr::Document](#)

See Also

[ISwDMDocument11 Members](#)
[SolidWorks.Interop.swdocumentmgr.Namespace](#)

ISwDMDocument11 Interface Members

[See Also](#) [Methods](#)



[SolidWorks.Interop.swdocumentmgr.Namespace](#) : ISwDMDocument11 Interface

The following tables list the members exposed by [ISwDMDocument11](#).

Public Methods

Name	Description
------	-------------

 GetPreviewBitmapBytes	Obsolete. Superseded by ISwDMConfiguration9::GetPreviewBitmapBytes .
 GetPreviewPNGBitmapBytes	Obsolete. Superseded by ISwDMConfiguration9::GetPreviewPNGBitmapBytes .

[Top](#)

See Also

[ISwDMDocument11 Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

ISwDMDocument11 Interface Methods

[See Also](#)

	SolidWorks.Interop.swdocumentmgr Namespace : ISwDMDocument11 Interface
---	--

For a list of all members of this type, see [ISwDMDocument11 members](#).

Public Methods

Name	Description
 GetPreviewBitmapBytes	Obsolete. Superseded by ISwDMConfiguration9::GetPreviewBitmapBytes .
 GetPreviewPNGBitmapBytes	Obsolete. Superseded by ISwDMConfiguration9::GetPreviewPNGBitmapBytes .

[Top](#)

See Also

[ISwDMDocument11 Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

GetPreviewBitmapBytes Method (ISwDMDocument11)

[See Also](#)

 	SolidWorks.Interop.swdocumentmgr Namespace > ISwDMDocument11 Interface : GetPreviewBitmapBytes Method (ISwDMDocument11)
Obsolete. Superseded by ISwDMConfiguration9::GetPreviewBitmapBytes .	

.NET Syntax

Visual Basic (Declaration)

```
Function GetPreviewBitmapBytes( _  
    ByRef result As SwDmPreviewError _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISwDMDocument11  
Dim result As SwDmPreviewError  
Dim value As System.Object  
  
value = instance.GetPreviewBitmapBytes(result)
```

C#

```
System.object GetPreviewBitmapBytes(  
    out SwDmPreviewError result  
)
```

C++/CLI

```
System.Object^ GetPreviewBitmapBytes(  
& [Out] SwDmPreviewError result  
)
```

Parameters

result

Success or error code as defined by [swDmPreviewError](#)

Return Value

Preview byte array

Visual Basic for Applications (VBA) Syntax

See [SwDMDocument11::GetPreviewBitmapBytes](#).

See Also

[ISwDMDocument11 Interface](#)
[ISwDMDocument11 Members](#)

Availability

SOLIDWORKS Document Manager API 2007 SP5

SOLIDWORKS Document Manager API Help

[Send comments](#) on this topic.

GetPreviewPNGBitmapBytes Method (ISwDMDocument11)

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMDocument11 Interface](#) : GetPreviewPNGBitmapBytes Method (ISwDMDocument11)

Obsolete. Superseded by [ISwDMConfiguration9::GetPreviewPNGBitmapBytes](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetPreviewPNGBitmapBytes( _  
    ByRef result As SwDmPreviewError _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISwDMDocument11  
Dim result As SwDmPreviewError  
Dim value As System.Object
```

```
value = instance.GetPreviewPNGBitmapBytes(result)
```

C#

```
System.Object GetPreviewPNGBitmapBytes(  
    out SwDmPreviewError result  
)
```

C++/CLI

```
System.Object^ GetPreviewPNGBitmapBytes(  
& [Out] SwDmPreviewError result  
)
```

Parameters

result

Success or error code as defined by [swDmPreviewError](#)

Return Value

Preview PNG byte array

Visual Basic for Applications (VBA) Syntax

See [SwDMDocument11::GetPreviewPNGBitmapBytes](#).

Example

See Also

[ISwDMDocument11 Interface](#)
[ISwDMDocument11 Members](#)

Availability

SOLIDWORKS Document Manager API 2007 SP5

ISwDMDocument12 (Type)

SOLIDWORKS Document Manager API Help

[Send comments](#) on this topic.

ISwDMDocument12 Interface

[See Also](#) [Members](#)



[SolidWorks.Interop.swdocumentmgr.Namespace](#) : ISwDMDocument12 Interface

Obsolete.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface ISwDMDocument12
    Inherits
    ISwDMDocument, ISwDMDocument10, ISwDMDocument3, ISwDMDocument4, ISwDMDocument5, ISwDMDocument6, ISwDMDocument7, ISwDMDocument8
```

Visual Basic (Usage)



```
Dim instance As ISwDMDocument12
```

C#

```
public interface ISwDMDocument12 :
    ISwDMDocument, ISwDMDocument10, ISwDMDocument3, ISwDMDocument4, ISwDMDocument5, ISwDMDocument6, ISwDMDocument7, ISwDMDocument8
```

C++/CLI

```
public interface class ISwDMDocument12 : public
    ISwDMDocument, ISwDMDocument10, ISwDMDocument3, ISwDMDocument4, ISwDMDocument5, ISwDMDocument6, ISwDMDocument7, ISwDMDocument8
```

Visual Basic for Applications (VBA) Syntax

See [SwDMDocument12](#).

Remarks

Before you can access this object, you must call [ISwDMAApplication::GetDocument](#).

NOTES:

- You can access an ISwDMDocument12 object by calling QueryInterface on an [ISwDMDocument](#) object in C++ or by direct assignment in Visual Basic.
- The SwDMDocument object can be assigned to an ISwDMDocument12 variable, just like the SOLIDWORKS [IModelDoc2](#) object can be assigned to a SOLIDWORKS [IPartDoc](#) variable.

Accessors

[ISwDMAApplication::GetDocument](#)

[ISwDMConfiguration::Document](#)

[ISwDMConfigurationMgr::Document](#)

See Also

[ISwDMDocument12 Members](#)

[SolidWorks.Interop.swdocumentmgr.Namespace](#)

SOLIDWORKS Document Manager API Help

[Send comments](#) on this topic.

ISwDMDocument12 Interface Methods

[See Also](#)



For a list of all members of this type, see [ISwDMDocument12 members](#).

Public Methods

Name	Description
 GetAllExternalReferences3	Obsolete. Superseded by ISwDMDocument13::GetAllExternalReferences4 .

[Top](#)

See Also

[ISwDMDocument12 Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)

ISwDMDocument12 Interface Members

[See Also](#) [Methods](#)



The following tables list the members exposed by [ISwDMDocument12](#).

Public Methods

Name	Description
 GetAllExternalReferences3	Obsolete. Superseded by ISwDMDocument13::GetAllExternalReferences4 .

[Top](#)

See Also

[ISwDMDocument12 Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)

GetAllExternalReferences3 Method (ISwDMDocument12)

[See Also](#)



Obsolete. Superseded by [ISwDMDocument13::GetAllExternalReferences4](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetAllExternalReferences3( _  
    ByVal pSrcOption As SwDMSearchOption, _  
    ByRef brokenRefVar As System.Object, _  
    ByRef IsVirtual As System.Object _  
) As System.Object
```

Visual Basic (Usage)

```
Dim instance As ISwDMDocument12  
Dim pSrcOption As SwDMSearchOption  
Dim brokenRefVar As System.Object  
Dim IsVirtual As System.Object  
Dim value As System.Object  
  
value = instance.GetAllExternalReferences3(pSrcOption, brokenRefVar, IsVirtual)
```

C#

```
System.object GetAllExternalReferences3(  
    SwDMSearchOption pSrcOption,  
    out System.object brokenRefVar,
```



```
        out System.object IsVirtual  
    )
```

C++/CLI

```
System.Object^ GetAllExternalReferences3(  
&    SwDMSearchOption^ pSrcOption,  
&    [Out] System.Object^ brokenRefVar,  
&    [Out] System.Object^ IsVirtual  
)
```

Parameters

pSrcOption

brokenRefVar

IsVirtual

Visual Basic for Applications (VBA) Syntax

See [SwDMDocument12::GetAllExternalReferences3](#).

See Also

[ISwDMDocument12 Interface](#)
[ISwDMDocument12 Members](#)

ISwDMDocument13 (Type)

SOLIDWORKS Document Manager API Help

[Send comments](#) on this topic.

ISwDMDocument13 Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.swdocumentmgr.Namespace](#) : ISwDMDocument13 Interface

Accesses the document.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

Public Interface ISwDMDocument13

Inherits

[ISwDMDocument](#), [ISwDMDocument10](#), [ISwDMDocument12](#), [ISwDMDocument3](#), [ISwDMDocument4](#), [ISwDMDocument5](#), [ISwDMDocument6](#), [ISwDMDocument7](#), [ISwDMDocument8](#)

Visual Basic (Usage)



Dim instance As [ISwDMDocument13](#)

C#

public interface ISwDMDocument13 :

[ISwDMDocument](#), [ISwDMDocument10](#), [ISwDMDocument12](#), [ISwDMDocument3](#), [ISwDMDocument4](#), [ISwDMDocument5](#), [ISwDMDocument6](#), [ISwDMDocument7](#), [ISwDMDocument8](#)

C++/CLI

public interface class ISwDMDocument13 : public

[ISwDMDocument](#), [ISwDMDocument10](#), [ISwDMDocument12](#), [ISwDMDocument3](#), [ISwDMDocument4](#), [ISwDMDocument5](#), [ISwDMDocument6](#), [ISwDMDocument7](#), [ISwDMDocument8](#)

Visual Basic for Applications (VBA) Syntax

See [SwDMDocument13](#).

Example

[Get, Add, Change, and Delete Cut-List Custom Properties \(C#\)](#)

[Get, Add, Change, and Delete Cut-List Custom Properties \(VB.NET\)](#)

Remarks

Before you can access this object, you must call [ISwDMApplication::GetDocument](#).

NOTES:

- You can access an ISwDMDocument13 object by calling QueryInterface on an [ISwDMDocument](#) object in C++ or by direct assignment in Visual Basic.
- The SwDMDocument object can be assigned to an ISwDMDocument13 variable, just like the SOLIDWORKS [IModelDoc2](#) object can be assigned to a SOLIDWORKS [IPartDoc](#) variable.

Accessors

[ISwDMApplication::GetDocument](#)

[ISwDMConfiguration::Document](#)

[ISwDMConfigurationMgr::Document](#)

See Also

[ISwDMDocument13 Members](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)
[ISwDMDocument3 Interface](#)
[ISwDMDocument4 Interface](#)
[ISwDMDocument5 Interface](#)
[ISwDMDocument6 Interface](#)
[ISwDMDocument7 Interface](#)
[ISwDMDocument8 Interface](#)
[ISwDMDocument10 Interface](#)
[ISwDMDocument14 Interface](#)
[ISwDMDocument15 Interface](#)
[ISwDMDocument16 Interface](#)
[ISwDMDocument17 Interface](#)
[ISwDMDocument18 Interface](#)
[ISwDMDocument19 Interface](#)
[ISwDMDocument20 Interface](#)
[ISwDMDocument21 Interface](#)
[ISwDMDocument22 Interface](#)
[ISwDMDocument23 Interface](#)
[ISwDMDocument24 Interface](#)
[ISwDMDocument25 Interface](#)
[ISwDMDocument26 Interface](#)
[ISwDMDocument27 Interface](#)
[ISwDMDocument28 Interface](#)
[ISwDMDocument29 Interface](#)
[ISwDMDocument30 Interface](#)

ISwDMDocument13 Interface Members

[See Also](#) [Methods](#)


SolidWorks.Interop.swdocumentmgr Namespace : ISwDMDocument13 Interface

The following tables list the members exposed by [ISwDMDocument13](#).

 Public Methods

Name	Description
 GetAllExternalReferences4	Obsolete. Superseded by ISwDMDocument13.GetAllExternalReferences5 .
 GetCutListItems2	Obsolete. Superseded by ISwDMConfiguration16.GetCutListItems .
 GetExternalDesignTable	Gets the path to an external (i.e., linked) design table, if one exists.
 GetLastUpdateTimeStamp	Gets the last update stamp for this document.
 GetSheetFormatPath	Gets the path and filename of the sheet format used for the specified sheet.
 GetSheetProperties	Gets the specified sheet's properties.

[Top](#)

 See Also

[ISwDMDocument13 Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)
[ISwDMDocument3 Interface](#)
[ISwDMDocument4 Interface](#)
[ISwDMDocument5 Interface](#)
[ISwDMDocument6 Interface](#)
[ISwDMDocument7 Interface](#)
[ISwDMDocument8 Interface](#)
[ISwDMDocument10 Interface](#)
[ISwDMDocument14 Interface](#)
[ISwDMDocument15 Interface](#)
[ISwDMDocument16 Interface](#)
[ISwDMDocument17 Interface](#)
[ISwDMDocument18 Interface](#)
[ISwDMDocument19 Interface](#)
[ISwDMDocument20 Interface](#)
[ISwDMDocument21 Interface](#)
[ISwDMDocument22 Interface](#)
[ISwDMDocument23 Interface](#)
[ISwDMDocument24 Interface](#)
[ISwDMDocument25 Interface](#)
[ISwDMDocument26 Interface](#)
[ISwDMDocument27 Interface](#)
[ISwDMDocument28 Interface](#)
[ISwDMDocument29 Interface](#)
[ISwDMDocument30 Interface](#)

ISwDMDocument13 Interface Methods

[See Also](#)


SolidWorks.Interop.swdocumentmgr Namespace : ISwDMDocument13 Interface

For a list of all members of this type, see [ISwDMDocument13 members](#).

 Public Methods

Name	Description
 GetAllExternalReferences4	Obsolete. Superseded by ISwDMDocument13::GetAllExternalReferences5 .
 GetCutListItems2	Obsolete. Superseded by ISwDMConfiguration16::GetCutListItems .
 GetExternalDesignTable	Gets the path to an external (i.e., linked) design table, if one exists.
 GetLastUpdateTimeStamp	Gets the last update stamp for this document.
 GetSheetFormatPath	Gets the path and filename of the sheet format used for the specified sheet.
 GetSheetProperties	Gets the specified sheet's properties.

[Top](#)

See Also

[ISwDMDocument13 Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)
[ISwDMDocument3 Interface](#)
[ISwDMDocument4 Interface](#)
[ISwDMDocument5 Interface](#)
[ISwDMDocument6 Interface](#)
[ISwDMDocument7 Interface](#)
[ISwDMDocument8 Interface](#)
[ISwDMDocument10 Interface](#)
[ISwDMDocument14 Interface](#)
[ISwDMDocument15 Interface](#)
[ISwDMDocument16 Interface](#)
[ISwDMDocument17 Interface](#)
[ISwDMDocument18 Interface](#)
[ISwDMDocument19 Interface](#)
[ISwDMDocument20 Interface](#)
[ISwDMDocument21 Interface](#)
[ISwDMDocument22 Interface](#)
[ISwDMDocument23 Interface](#)
[ISwDMDocument24 Interface](#)
[ISwDMDocument25 Interface](#)
[ISwDMDocument26 Interface](#)
[ISwDMDocument27 Interface](#)
[ISwDMDocument28 Interface](#)
[ISwDMDocument29 Interface](#)
[ISwDMDocument30 Interface](#)

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

GetAllExternalReferences4 Method (ISwDMDocument13)

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMDocument13 Interface](#) : GetAllExternalReferences4 Method (ISwDMDocument13)

Obsolete. Superseded by [ISwDMDocument13::GetAllExternalReferences5](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetAllExternalReferences4( _
    ByVal pSrcOption As SwDMSearchOption, _
    ByRef brokenRefVar As System.Object, _
    ByRef IsVirtual As System.Object, _
    ByRef TimeStamp As System.Object _
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISwDMDocument13
Dim pSrcOption As SwDMSearchOption
Dim brokenRefVar As System.Object
Dim IsVirtual As System.Object
Dim TimeStamp As System.Object
Dim value As System.Object
```

```
value = instance.GetAllExternalReferences4(pSrcOption, brokenRefVar, IsVirtual, TimeStamp)
```

C#

```
System.object GetAllExternalReferences4(
    SwDMSearchOption pSrcOption,
    out System.object brokenRefVar,
    out System.object IsVirtual,
```

```
    out System.Object TimeStamp
)
```

C++/CLI

```
System.Object^ GetAllExternalReferences4(
& SwDMSearchOption^ pSrcOption,
& [Out] System.Object^ brokenRefVar,
& [Out] System.Object^ IsVirtual,
& [Out] System.Object^ TimeStamp
)
```

Parameters

pSrcOption

Pointer to the [ISwDMSearchOption](#) object

brokenRefVar

Array of the statuses of any broken external references as defined in [swDmReferenceStatus](#) (see **Remarks**)

IsVirtual

Array of Booleans that indicate whether each reference corresponds to a virtual component

TimeStamp

Array of time stamps in time_t format

Return Value

Array of the names of the external references used in this document

Visual Basic for Applications (VBA) Syntax

See [SwDMDocument13::GetAllExternalReferences4](#).

Remarks

Use this method for drawings; use [ISwDMDocument15::GetExternalFeatureReferences](#) for parts and assemblies.

This method only supports model documents saved in SOLIDWORKS 2009 and later.

Although this method returns valid data for files created in SOLIDWORKS 2005 and earlier, this method only returns valid data for the brokenRefVar argument for files created in SOLIDWORKS 2005 files and later. For files created in versions of SOLIDWORKS earlier than SOLIDWORKS 2005, it returns swDmReferenceStatusUnknown for brokenRefVar.

Call this method before calling [ISwDMDocument::ReplaceReference](#).

The SOLIDWORKS Document Manager API applies the same rules when searching for a reference as described in the SOLIDWORKS Help. The mix-and-match of sub-folder combinations is applied to the current document, which for the SOLIDWORKS Document Manager is the document attached using [ISwDMApplication::GetDocument](#) and the reference being searched for. You can set up the list of folders to be searched using [ISwDMSearchOption::AddSearchPath](#), which is equivalent to using the SOLIDWORKS user-interface commands **Tools, Option > System Options > File Locations > Referenced Documents**.

Two differences between SOLIDWORKS and the SOLIDWORKS Document Manager API searches are:

- the path of the last opened visible top-level document (drawing or assembly) is not tried directly.
- the last user path is not tried directly.

as these concepts have little meaning when SOLIDWORKS is not running.

SOLIDWORKS does not open suppressed components of assemblies in memory. Thus, information, such as a suppressed component's time stamp, is not updated when the assembly is rebuilt. You can call [ISwDMComponent6::PathName](#) to compare the path returned by [ISwDMDocument13::GetAllExternalReferences4](#) and call [ISwDMComponent::IsSuppressed](#) to find out if the component is suppressed.

Because the search routine is shared between SOLIDWORKS and the SOLIDWORKS Document Manager API, most of the same changes apply going from SOLIDWORKS 2006 to SOLIDWORKS 2007 and later. However, one significant change related to caching of resolved paths for references being searched for in SOLIDWORKS does not apply to the SOLIDWORKS Document Manager API. In SOLIDWORKS 2007 and later, the next time these references are needed, a simple lookup suffices instead of a potentially lengthy search. However, because this caching mechanism was not applied to the SOLIDWORKS Document Manager API, the SOLIDWORKS Document Manager API in 2006 and 2007, and later, exhibit similar behavior.

The array of time stamps are in time_t format, which Microsoft defines "as time as seconds elapsed since midnight, January 1, 1970 or -1 in the case of error". You must either have built-in functions to convert these values to something more accessible or write your own functions.

See Also

[ISwDMDocument13 Interface](#)

[ISwDMDocument13 Members](#)

[ISwDMDocument13::GetLastUpdateTimeStamp Method](#)

Availability

GetCutListItems2 Method (ISwDMDocument13)

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMDocument13 Interface](#) : GetCutListItems2 Method (ISwDMDocument13)

Obsolete. Superseded by [ISwDMConfiguration16::GetCutListItems](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetCutListItems2() As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISwDMDocument13  
Dim value As System.Object  
  
value = instance.GetCutListItems2()
```

C#

```
System.object GetCutListItems2()
```

C++/CLI

```
System.Object^ GetCutListItems2();
```

Return Value

Array of [cut-list items](#)

Visual Basic for Applications (VBA) Syntax

See [SwDMDocument13::GetCutListItems2](#).

Remarks

This property only supports documents saved in SOLIDWORKS 2009 or later.

See Also

[ISwDMDocument13 Interface](#)
[ISwDMDocument13 Members](#)

Availability

SOLIDWORKS Document Manager API 2009 SP0

GetExternalDesignTable Method (ISwDMDocument13)

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMDocument13 Interface](#) : GetExternalDesignTable Method (ISwDMDocument13)

Gets the path to an external (i.e., linked) design table, if one exists.

.NET Syntax

Visual Basic (Declaration)

```
Function GetExternalDesignTable( _  
    ByVal pSrcOption As SwDMSearchOption, _  
    ByRef Status As SwDmDesignTableDataError _  
) As System.String
```

Visual Basic (Usage)



```
Dim instance As ISwDMDocument13  
Dim pSrcOption As SwDMSearchOption  
Dim Status As SwDmDesignTableDataError  
Dim value As System.String  
  
value = instance.GetExternalDesignTable(pSrcOption, Status)
```

C#

```
System.string GetExternalDesignTable(  
    SwDMSearchOption pSrcOption,  
    out SwDmDesignTableDataError Status  
)
```

C++/CLI

```
System.String^ GetExternalDesignTable(  
    & SwDMSearchOption^ pSrcOption,  
    & [Out] SwDmDesignTableDataError Status  
)
```

Parameters

pSrcOption

Pointer to an [ISwDMSearchOption](#) object

Status

Error status as defined by [SwDmDesignTableDataError](#)

Visual Basic for Applications (VBA) Syntax

See [SwDMDocument13::GetExternalDesignTable](#).

See Also

[ISwDMDocument13 Interface](#)
[ISwDMDocument13 Members](#)

Availability

SOLIDWORKS Document Manager API 2009 SP0

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

GetLastUpdateTimeStamp Method (ISwDMDocument13)

[See Also](#) [Example](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMDocument13 Interface](#) : GetLastUpdateTimeStamp Method (ISwDMDocument13)

Gets the last update stamp for this document.

.NET Syntax

Visual Basic (Declaration)

```
Function GetLastUpdateTimeStamp() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ISwDMDocument13
Dim value As System.Integer

value = instance.GetLastUpdateTimeStamp()
```

C#

```
System.int GetLastUpdateTimeStamp()
```

C++/CLI

```
System.int GetLastUpdateTimeStamp();
```

Return Value

Last update stamp in time_t format

Visual Basic for Applications (VBA) Syntax

See [SwDMDocument13::GetLastUpdateTimeStamp](#).

Example

[Get, Add, Change, and Delete Cut-List Custom Properties \(C#\)](#)
[Get, Add, Change, and Delete Cut-List Custom Properties \(VB.NET\)](#)

Remarks

The return value is in time_t format, which Microsoft defines "as time as seconds elapsed since midnight, January 1, 1970 or -1 in the case of error". You must either have built-in functions to convert this value to something more accessible or write your own functions.

See Also

[ISwDMDocument13 Interface](#)
[ISwDMDocument13 Members](#)

Availability

SOLIDWORKS Document Manager API 2009 SP0

SOLIDWORKS Document Manager API Help

[Send comments](#) on this topic.

GetSheetFormatPath Method (ISwDMDocument13)

[See Also](#) [Example](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMDocument13 Interface](#) : GetSheetFormatPath Method (ISwDMDocument13)

Gets the path and filename of the sheet format used for the specified sheet.

.NET Syntax

Visual Basic (Declaration)

```
Function GetSheetFormatPath( _
    ByVal SheetName As System.String, _
    ByRef FormatPath As System.String _
) As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ISwDMDocument13
Dim SheetName As System.String
Dim FormatPath As System.String
Dim value As System.Integer
```

```
value = instance.GetSheetFormatPath(SheetName, FormatPath)
```

C#

```
System.int GetSheetFormatPath(  
    System.string SheetName,  
    out System.string FormatPath  
)
```

C++/CLI

```
System.int GetSheetFormatPath(  
& System.String^ SheetName,  
[Out] System.String^ FormatPath  
)
```

Parameters

SheetName
Sheet name
FormatPath
Path and filename of the sheet format

Return Value

Result as defined in [swSheetFormatPathResult](#)

Visual Basic for Applications (VBA) Syntax

See [SwDMDocument13::GetSheetFormatPath](#).

Example

[Get Drawing Sheets' Properties \(C#\)](#)
[Get Drawing Sheets' Properties \(VB.NET\)](#)

Remarks

This method only supports documents saved in SOLIDWORKS 2009 and later. An empty string is returned for documents saved in earlier versions of SOLIDWORKS.

Before calling this method, call [ISwDMDocument4::GetActiveSheetName](#) or [ISwDMDocument6::GetSheetNames](#).

See Also

[ISwDMDocument13 Interface](#)
[ISwDMDocument13 Members](#)
[ISwDMDocument13::GetSheetProperties Method](#)

Availability

SOLIDWORKS Document Manager 2009 SP0

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

GetSheetProperties Method (ISwDMDocument13)

[See Also](#) [Example](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMDocument13 Interface](#) : GetSheetProperties Method (ISwDMDocument13)

Gets the specified sheet's properties.

.NET Syntax

Visual Basic (Declaration)

```
Function GetSheetProperties(  
    ByVal SheetName As System.String, _  
    ByRef Properties As System.Object _  
) As System.Integer
```

Visual Basic (Usage)

 Copy Code

```
Dim instance As ISwDMDocument13
Dim SheetName As System.String
Dim Properties As System.Object
Dim value As System.Integer
```

```
value = instance.GetSheetProperties(SheetName, Properties)
```

C#

```
System.int GetSheetProperties(
    System.string SheetName,
    out System.object Properties
)
```

C++/CLI

```
System.int GetSheetProperties(
    & System.String^ SheetName,
    & [Out] System.Object^ Properties
)
```

Parameters

SheetName
Sheet name
Properties
Array of 8 doubles (see **Remarks**)

Return Value

Result as defined in [swSheetPropertiesResult](#)

Visual Basic for Applications (VBA) Syntax

See [SwDMDocument13::GetSheetProperties](#).

Example

[Get Drawing Sheets' Properties \(C#\)](#)
[Get Drawing Sheets' Properties \(VB.NET\)](#)

Remarks

Before calling this method, call [ISwDMDocument4::GetActiveSheetName](#) or [ISwDMDocument6::GetSheetNames](#).

The return value is an array of 8 doubles:

[*sheetPaperSize*, *sheetWidth*, *sheetHeight*, *sheetScale1*, *sheetScale2*, *firstAngle*, *templateSize*, *templateVisible*]

where:

1. *sheetPaperSize*: long packed into a double represented by [swDwgPaperSizes_e](#)
2. *sheetWidth*: sheet width
3. *sheetHeight*: sheet height
4. *sheetScale1*: sheet scale1
5. *sheetScale2*: sheet scale2
6. *firstAngle*: Boolean packed into a double; true if sheet is using first angle project, false if not
7. *templateSize*: long packed into a double represented by [swDwgTemplates_e](#)
8. *templateVisible*: Boolean packed into a double; true if template is visible, false if not

See Also

[ISwDMDocument13 Interface](#)
[ISwDMDocument13 Members](#)
[ISwDMDocument13::GetSheetFormatPath](#)

Availability

SOLIDWORKS Document Manager API 2009 SP0

ISwDMDocument14 (Type)

SOLIDWORKS Document Manager API Help

[Send comments](#) on this topic.

ISwDMDocument14 Interface

[See Also](#) [Members](#)



[SolidWorks.Interop.swdocumentmgr.Namespace](#) : ISwDMDocument14 Interface

Accesses the document.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

Public Interface ISwDMDocument14

Inherits

[ISwDMDocument](#), [ISwDMDocument10](#), [ISwDMDocument12](#), [ISwDMDocument13](#), [ISwDMDocument3](#), [ISwDMDocument4](#), [ISwDMDocument5](#), [ISwDMDocument6](#), [ISwDMDocument7](#), [ISwDMDocument8](#)

Visual Basic (Usage)



Dim instance As [ISwDMDocument14](#)

C#

public interface ISwDMDocument14 :

[ISwDMDocument](#), [ISwDMDocument10](#), [ISwDMDocument12](#), [ISwDMDocument13](#), [ISwDMDocument3](#), [ISwDMDocument4](#), [ISwDMDocument5](#), [ISwDMDocument6](#), [ISwDMDocument7](#), [ISwDMDocument8](#)

C++/CLI

public interface class ISwDMDocument14 : public

[ISwDMDocument](#), [ISwDMDocument10](#), [ISwDMDocument12](#), [ISwDMDocument13](#), [ISwDMDocument3](#), [ISwDMDocument4](#), [ISwDMDocument5](#), [ISwDMDocument6](#), [ISwDMDocument7](#), [ISwDMDocument8](#)

Visual Basic for Applications (VBA) Syntax

See [SwDMDocument14](#).

Remarks

Before you can access this object, you must call [ISwDMApplication::GetDocument](#).

NOTES:

- You can access an ISwDMDocument14 object by calling QueryInterface on an [ISwDMDocument](#) object in C++ or by direct assignment in Visual Basic.
- The SwDMDocument object can be assigned to an ISwDMDocument14 variable, just like the SOLIDWORKS [IModelDoc2](#) object can be assigned to a SOLIDWORKS [IPartDoc](#) variable.

Accessors

[ISwDMApplication::GetDocument](#)

[ISwDMConfiguration::Document](#)

[ISwDMConfigurationMgr::Document](#)

See Also

[ISwDMDocument14 Members](#)
[SolidWorks.Interop.swdocumentmgr.Namespace](#)
[ISwDMDocument3 Interface](#)
[ISwDMDocument4 Interface](#)
[ISwDMDocument5 Interface](#)
[ISwDMDocument6 Interface](#)
[ISwDMDocument7 Interface](#)
[ISwDMDocument8 Interface](#)
[ISwDMDocument10 Interface](#)

[ISwDMDocument13 Interface](#)
[ISwDMDocument15 Interface](#)
[ISwDMDocument16 Interface](#)
[ISwDMDocument17 Interface](#)
[ISwDMDocument18 Interface](#)
[ISwDMDocument19 Interface](#)
[ISwDMDocument20 Interface](#)
[ISwDMDocument21 Interface](#)
[ISwDMDocument22 Interface](#)
[ISwDMDocument23 Interface](#)
[ISwDMDocument24 Interface](#)
[ISwDMDocument25 Interface](#)
[ISwDMDocument26 Interface](#)
[ISwDMDocument27 Interface](#)
[ISwDMDocument28 Interface](#)
[ISwDMDocument29 Interface](#)
[ISwDMDocument30 Interface](#)

ISwDMDocument14 Interface Methods

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMDocument14 Interface

For a list of all members of this type, see [ISwDMDocument14 members](#).

Public Methods

Name	Description
Get3DCCGenericStreamFile	Exports an XML file with the 3D Content Central (3DCC) generic format configuration rules that were built into this document by the SOLIDWORKS Configuration Publisher.
Get3DCCStreamFile	Exports an XML file with the 3D Content Central (3DCC) original format configuration rules built into this document by the SOLIDWORKS Configuration Publisher.

[Top](#)

See Also

[ISwDMDocument14 Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)
[ISwDMDocument3 Interface](#)
[ISwDMDocument4 Interface](#)
[ISwDMDocument5 Interface](#)
[ISwDMDocument6 Interface](#)
[ISwDMDocument7 Interface](#)
[ISwDMDocument8 Interface](#)
[ISwDMDocument10 Interface](#)
[ISwDMDocument13 Interface](#)
[ISwDMDocument15 Interface](#)
[ISwDMDocument16 Interface](#)
[ISwDMDocument17 Interface](#)
[ISwDMDocument18 Interface](#)
[ISwDMDocument19 Interface](#)
[ISwDMDocument20 Interface](#)
[ISwDMDocument21 Interface](#)
[ISwDMDocument22 Interface](#)
[ISwDMDocument23 Interface](#)
[ISwDMDocument24 Interface](#)
[ISwDMDocument25 Interface](#)
[ISwDMDocument26 Interface](#)
[ISwDMDocument27 Interface](#)
[ISwDMDocument28 Interface](#)
[ISwDMDocument29 Interface](#)
[ISwDMDocument30 Interface](#)

ISwDMDocument14 Interface Members

[See Also](#) [Methods](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMDocument14 Interface

The following tables list the members exposed by [ISwDMDocument14](#).

Public Methods

Name	Description
Get3DCCGenericStreamFile	Exports an XML file with the 3D Content Central (3DCC) generic format configuration rules that were built into this document by the SOLIDWORKS Configuration Publisher.
Get3DCCStreamFile	Exports an XML file with the 3D Content Central (3DCC) original format configuration rules built into this document by the SOLIDWORKS Configuration Publisher.

[Top](#)

See Also

[ISwDMDocument14 Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)
[ISwDMDocument3 Interface](#)
[ISwDMDocument4 Interface](#)

[ISwMDocument5 Interface](#)
[ISwMDocument6 Interface](#)
[ISwMDocument7 Interface](#)
[ISwMDocument8 Interface](#)
[ISwMDocument10 Interface](#)
[ISwMDocument13 Interface](#)
[ISwMDocument15 Interface](#)
[ISwMDocument16 Interface](#)
[ISwMDocument17 Interface](#)
[ISwMDocument18 Interface](#)
[ISwMDocument19 Interface](#)
[ISwMDocument20 Interface](#)
[ISwMDocument21 Interface](#)
[ISwMDocument22 Interface](#)
[ISwMDocument23 Interface](#)
[ISwMDocument24 Interface](#)
[ISwMDocument25 Interface](#)
[ISwMDocument26 Interface](#)
[ISwMDocument27 Interface](#)
[ISwMDocument28 Interface](#)
[ISwMDocument29 Interface](#)
[ISwMDocument30 Interface](#)

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

Get3DCCGenericStreamFile Method (ISwMDocument14)

[See Also](#) [Example](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwMDocument14 Interface](#) : Get3DCCGenericStreamFile Method (ISwMDocument14)

Exports an XML file with the 3D Content Central (3DCC) generic format configuration rules that were built into this document by the SOLIDWORKS Configuration Publisher.

.NET Syntax

Visual Basic (Declaration)

```
Function Get3DCCGenericStreamFile( _  
    ByVal xmlFileName As System.String _  
) As SwDmXmlDataError
```

Visual Basic (Usage)



```
Dim instance As ISwMDocument14  
Dim xmlFileName As System.String  
Dim value As SwDmXmlDataError
```

```
value = instance.Get3DCCGenericStreamFile(xmlFileName)
```

C#

```
SwDmXmlDataError Get3DCCGenericStreamFile(  
    System.string xmlFileName  
)
```

C++/CLI

```
SwDmXmlDataError Get3DCCGenericStreamFile(  
& System.String^ xmlFileName  
)
```

Parameters

xmlFileName
Name of file to which to save the configuration rules data

Return Value

Status as defined in [swDmXmlDataError](#)

Visual Basic for Applications (VBA) Syntax

See [SwDMDocument14::Get3DCCGenericStreamFile](#).

Example

[Get 3D Content Central Stream Files \(VB.NET\)](#)
[Get 3D Content Central Stream Files \(C#\)](#)

Remarks

Designers use the SOLIDWORKS Configuration Publisher to build configuration rules into their documents to constrain how the documents are seen by users who download them from [3D Content Central](#). (To open the Configuration Publisher in SOLIDWORKS, open a document, right-click on the top-level configuration name in the ConfigurationManager, and click **Configuration Publisher**).

Configuration rules are typically functions of the document's design table parameters. These rules specify how to display the document in different configurations. The Configuration Publisher inserts into the document the configuration rules in two formats: [original](#) and generic.

This method allows user-interface developers to extract configuration rule information in the generic, multi-use format. Developers can then modify the extracted XML file to display the document in a format that differs from this multi-use format.

The Configuration Publisher can also upload documents along with their configuration rules to 3D Content Central. See the 3D Content Central web site to learn more.

See Also

[ISwDMDocument14 Interface](#)
[ISwDMDocument14 Members](#)
[ISwDMDocument15::GetPartNumberStreamFile Method](#)

Availability

SOLIDWORKS Document Manager API 2010 SP0

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

Get3DCCStreamFile Method (ISwDMDocument14)

[See Also](#) [Example](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMDocument14 Interface](#) : Get3DCCStreamFile Method (ISwDMDocument14)

Exports an XML file with the 3D Content Central (3DCC) original format configuration rules built into this document by the SOLIDWORKS Configuration Publisher.

.NET Syntax

Visual Basic (Declaration)

```
Function Get3DCCStreamFile( _  
    ByVal xmlFileName As System.String _  
) As SwDmXmlDataError
```

Visual Basic (Usage)



```
Dim instance As ISwDMDocument14  
Dim xmlFileName As System.String  
Dim value As SwDmXmlDataError  
  
value = instance.Get3DCCStreamFile(xmlFileName)
```

C#

```
SwDmXmlDataError Get3DCCStreamFile(  
    System.string xmlFileName  
)
```

C++/CLI

```
SwDmXmlDataError Get3DCCStreamFile(  
& System.String^ xmlFileName  
)
```

Parameters

xmlFileName
Name of file to which to save the configuration rules data

Return Value

Status as defined in [swDmXmlDataError](#)

Visual Basic for Applications (VBA) Syntax

See [SwDMDocument14::Get3DCCStreamFile](#).

Example

[Get 3D Content Central Stream Files \(VB.NET\)](#)
[Get 3D Content Central Stream Files \(C#\)](#)

Remarks

Designers use the SOLIDWORKS Configuration Publisher to build configuration rules into their documents to constrain how the documents are seen by users who download them from [3D Content Central](#). (To open the Configuration Publisher in SOLIDWORKS, open a document, right-click on the top-level configuration name in the ConfigurationManager, and click **Configuration Publisher**).

Configuration rules are typically functions of the document's design table parameters. These rules specify how to display the document in different configurations. The Configuration Publisher inserts into the document the configuration rules in two formats: original and [generic](#).

This method allows user-interface developers to extract configuration rule information in the original format. Developers can then modify the extracted XML file to display the document in a format that differs from the 3D Content Central format.

The Configuration Publisher can also upload documents along with their configuration rules to 3D Content Central. See the 3D Content Central web site to learn more.

See Also

[ISwDMDocument14 Interface](#)
[ISwDMDocument14 Members](#)
[ISwDMDocument15::GetPartNumberStreamFile Method](#)

Availability

SOLIDWORKS Document Manager API 2010 SP0

ISwDMDocument15 (Type)

SOLIDWORKS Document Manager API Help

[Send comments](#) on this topic.

ISwDMDocument15 Interface

[See Also](#) [Members](#)



[SolidWorks.Interop.swdocumentmgr.Namespace](#) : ISwDMDocument15 Interface

Accesses the document.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

Public Interface ISwDMDocument15

Inherits

[ISwDMDocument](#), [ISwDMDocument10](#), [ISwDMDocument12](#), [ISwDMDocument13](#), [ISwDMDocument14](#), [ISwDMDocument3](#), [ISwDMDocument4](#), [ISwDMDocument5](#), [ISwDMDocument6](#), [ISwDMDocument7](#), [ISwDMDocument8](#)

Visual Basic (Usage)



Dim instance As [ISwDMDocument15](#)

C#

public interface ISwDMDocument15 :

[ISwDMDocument](#), [ISwDMDocument10](#), [ISwDMDocument12](#), [ISwDMDocument13](#), [ISwDMDocument14](#), [ISwDMDocument3](#), [ISwDMDocument4](#), [ISwDMDocument5](#), [ISwDMDocument6](#), [ISwDMDocument7](#), [ISwDMDocument8](#)

C++/CLI

public interface class ISwDMDocument15 : public

[ISwDMDocument](#), [ISwDMDocument10](#), [ISwDMDocument12](#), [ISwDMDocument13](#), [ISwDMDocument14](#), [ISwDMDocument3](#), [ISwDMDocument4](#), [ISwDMDocument5](#), [ISwDMDocument6](#), [ISwDMDocument7](#), [ISwDMDocument8](#)

Visual Basic for Applications (VBA) Syntax

See [SwDMDocument15](#).

Remarks

Before you can access this object, you must call [ISwDMApplication::GetDocument](#).

NOTES:

- You can access an ISwDMDocument15 object by calling QueryInterface on an [ISwDMDocument](#) object in C++ or by direct assignment in Visual Basic.
- The SwDMDocument object can be assigned to an ISwDMDocument15 variable, just like the SOLIDWORKS [IModelDoc2](#) object can be assigned to a SOLIDWORKS [IPartDoc](#) variable.

Accessors

[ISwDMApplication::GetDocument](#)

[ISwDMConfiguration::Document](#)

[ISwDMConfigurationMgr::Document](#)

See Also

[ISwDMDocument15 Members](#)
[SolidWorks.Interop.swdocumentmgr.Namespace](#)
[ISwDMDocument3 Interface](#)
[ISwDMDocument4 Interface](#)
[ISwDMDocument5 Interface](#)
[ISwDMDocument6 Interface](#)
[ISwDMDocument7 Interface](#)
[ISwDMDocument8 Interface](#)
[ISwDMDocument10 Interface](#)

[ISwDMDocument13 Interface](#)
[ISwDMDocument14 Interface](#)
[ISwDMDocument16 Interface](#)
[ISwDMDocument17 Interface](#)
[ISwDMDocument18 Interface](#)
[ISwDMDocument19 Interface](#)
[ISwDMDocument20 Interface](#)
[ISwDMDocument21 Interface](#)
[ISwDMDocument22 Interface](#)
[ISwDMDocument23 Interface](#)
[ISwDMDocument24 Interface](#)
[ISwDMDocument25 Interface](#)
[ISwDMDocument26 Interface](#)
[ISwDMDocument27 Interface](#)
[ISwDMDocument28 Interface](#)
[ISwDMDocument29 Interface](#)
[ISwDMDocument30 Interface](#)

ISwDMDocument15 Interface Members

[See Also](#) [Methods](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMDocument15 Interface

The following tables list the members exposed by [ISwDMDocument15](#).

Public Methods

Name	Description
GetExternalFeatureReferences	Obsolete. Superseded by ISwDMDocument18::GetExternalFeatureReferences2 .
GetPartNumberStreamFile	Gets the name of the XML file generated when uploading a model to 3D Content Central . The XML file is only generated if the model has a design table with a part number column.

[Top](#)

See Also

[ISwDMDocument15 Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)
[ISwDMDocument3 Interface](#)
[ISwDMDocument4 Interface](#)
[ISwDMDocument5 Interface](#)
[ISwDMDocument6 Interface](#)
[ISwDMDocument7 Interface](#)
[ISwDMDocument8 Interface](#)
[ISwDMDocument10 Interface](#)
[ISwDMDocument13 Interface](#)
[ISwDMDocument14 Interface](#)
[ISwDMDocument16 Interface](#)
[ISwDMDocument17 Interface](#)
[ISwDMDocument18 Interface](#)
[ISwDMDocument19 Interface](#)
[ISwDMDocument20 Interface](#)
[ISwDMDocument21 Interface](#)
[ISwDMDocument22 Interface](#)
[ISwDMDocument23 Interface](#)
[ISwDMDocument24 Interface](#)
[ISwDMDocument25 Interface](#)
[ISwDMDocument26 Interface](#)
[ISwDMDocument27 Interface](#)
[ISwDMDocument28 Interface](#)
[ISwDMDocument29 Interface](#)
[ISwDMDocument30 Interface](#)

ISwDMDocument15 Interface Methods

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMDocument15 Interface

For a list of all members of this type, see [ISwDMDocument15 members](#).

Public Methods

Name	Description
GetExternalFeatureReferences	Obsolete. Superseded by ISwDMDocument18::GetExternalFeatureReferences2 .
GetPartNumberStreamFile	Gets the name of the XML file generated when uploading a model to 3D Content Central . The XML file is only generated if the model has a design table with a part number column.

[Top](#)

See Also

[ISwDMDocument15 Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)
[ISwDMDocument3 Interface](#)
[ISwDMDocument4 Interface](#)

[ISwDMDocument5 Interface](#)
[ISwDMDocument6 Interface](#)
[ISwDMDocument7 Interface](#)
[ISwDMDocument8 Interface](#)
[ISwDMDocument10 Interface](#)
[ISwDMDocument13 Interface](#)
[ISwDMDocument14 Interface](#)
[ISwDMDocument16 Interface](#)
[ISwDMDocument17 Interface](#)
[ISwDMDocument18 Interface](#)
[ISwDMDocument19 Interface](#)
[ISwDMDocument20 Interface](#)
[ISwDMDocument21 Interface](#)
[ISwDMDocument22 Interface](#)
[ISwDMDocument23 Interface](#)
[ISwDMDocument24 Interface](#)
[ISwDMDocument25 Interface](#)
[ISwDMDocument26 Interface](#)
[ISwDMDocument27 Interface](#)
[ISwDMDocument28 Interface](#)
[ISwDMDocument29 Interface](#)
[ISwDMDocument30 Interface](#)

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

GetExternalFeatureReferences Method (ISwDMDocument15)

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMDocument15 Interface](#) : GetExternalFeatureReferences Method (ISwDMDocument15)

Obsolete. Superseded by [ISwDMDocument18::GetExternalFeatureReferences2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetExternalFeatureReferences( _  
    ByRef ExtRefOption As SwDMExternalReferenceOption _  
) As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ISwDMDocument15  
Dim ExtRefOption As SwDMExternalReferenceOption  
Dim value As System.Integer  
  
value = instance.GetExternalFeatureReferences(ExtRefOption)
```

C#

```
System.int GetExternalFeatureReferences(  
    out SwDMExternalReferenceOption ExtRefOption  
)
```

C++/CLI

```
System.int GetExternalFeatureReferences(  
& [Out] SwDMExternalReferenceOption^ ExtRefOption  
)
```

Parameters

ExtRefOption

An [ISwDMExternalReferenceOption](#) object (see **Remarks**)

Return Value

Number of external references used in this document

Visual Basic for Applications (VBA) Syntax

See [SwDMDocument15::GetExternalFeatureReferences](#).

Remarks

Use this method with parts and assemblies; use [ISwDMDocument13::GetAllExternalReferences4](#) with drawings.

This method only works in documents saved in SOLIDWORKS 2011 SP0 or later.

Before calling this method:

1. Call [ISwDMAApplication3::GetExternalReferenceOptionObject](#) to obtain an [ISwDMExternalReferenceOption](#) object.
2. Set [ISwDMExternalReferenceOption::Configuration](#).
3. Set [ISwDMExternalReferenceOption::NeedSuppress](#).
4. Set [ISwDMExternalReferenceOption::SearchOption](#).
5. Assign this method's ExtRefOption parameter to the [ISwDMExternalReferenceOption](#) object.

After calling this method, call [ISwDMExternalReferenceOption::ExternalReferences](#) and [ISwDMExternalReferenceOption::ReferencedConfigurations](#) to obtain the external feature references and their configurations.

To find out if an external feature reference is suppressed:

1. Call [ISwDMComponent6::PathName](#) to set one of the external components returned by [ISwDMDocument15::GetExternalFeatureReferences](#).
2. Call [ISwDMComponent::IsSuppressed](#).

The suppression states and other information of all of the external references are also embedded in the parent document. To obtain this information in XML format, call [ISwDMDocument::GetXMLStream](#).

Call this method before calling [ISwDMDocument::ReplaceReference](#).

The SOLIDWORKS Document Manager API applies the same rules when searching for a reference as described in the SOLIDWORKS Help. The mix-and-match of sub-folder combinations is applied to the current document, which for the SOLIDWORKS Document Manager API is the document attached using [ISwDMAApplication::GetDocument](#) and the reference being searched for. You can set up the list of folders to be searched using [ISwDMSearchOption::AddSearchPath](#), which is equivalent to using the SOLIDWORKS user-interface commands **Tools > Options > System Options > File Locations > Referenced Documents**.

Two differences between SOLIDWORKS and the SOLIDWORKS Document Manager API searches are:

- the path of the last opened visible top-level document (drawing or assembly) is not tried directly.
- the last user path is not tried directly.

These concepts have little meaning when SOLIDWORKS is not running.

Because the search routine is shared between SOLIDWORKS and the SOLIDWORKS Document Manager API, most of the same changes apply going from SOLIDWORKS 2006 to SOLIDWORKS 2007 and later. However, one significant change related to caching of resolved paths for references being searched for in SOLIDWORKS does not apply to the SOLIDWORKS Document Manager API. In SOLIDWORKS 2007 and later, the next time these references are needed, a simple lookup suffices instead of a potentially lengthy search. However, because this caching mechanism was not applied to the SOLIDWORKS Document Manager API, the SOLIDWORKS Document Manager API in 2006 and 2007, and later, exhibit similar behavior.

See Also

[ISwDMDocument15 Interface](#)
[ISwDMDocument15 Members](#)

Availability

SOLIDWORKS Document Manager API 2011 SP0

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

GetPartNumberStreamFile Method (ISwDMDocument15)

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMDocument15 Interface](#) : GetPartNumberStreamFile Method (ISwDMDocument15)

Gets the name of the XML file generated when uploading a model to [3D Content Central](#). The XML file is only generated if the model has a design table with a part number column.

.NET Syntax

Visual Basic (Declaration)

```
Function GetPartNumberStreamFile( _  
    ByVal xmlFileName As System.String _  
) As SwDmXmlDataError
```

Visual Basic (Usage)

```
Dim instance As ISwDMDocument15  
Dim xmlFileName As System.String  
Dim value As SwDmXmlDataError
```

```
value = instance.GetPartNumberStreamFile(xmlFileName)
```

C#

```
SwDmXmlDataError GetPartNumberStreamFile(  
    System.string xmlFileName  
)
```

C++/CLI



```
SwDmXmlDataError GetPartNumberStreamFile(  
& System.String^ xmlFileName  
)
```

Parameters

xmlFileName
Name of XML file

Return Value

Status as defined in [swDmXmlDataError](#)

Visual Basic for Applications (VBA) Syntax

See [SwDMDocument15::GetPartNumberStreamFile](#).

Remarks

Use the SOLIDWORKS Configuration Publisher to upload a model that has a design table with a part number column and other control values. (To open the Configuration Publisher in SOLIDWORKS, open a model document, right-click the top-level configuration name in the ConfigurationManager, and select **Configuration Publisher**.)

See Also

[ISwDMDocument15 Interface](#)
[ISwDMDocument15 Members](#)
[ISwDMDocumentManager14::Get3DCCGenericStreamFile Method](#)
[ISwDMDocumentManager14::Get3DCCStreamFile Method](#)

Availability

SOLIDWORKS Document Manager API 2011 SP0

ISwDMDocument16 (Type)

SOLIDWORKS Document Manager API Help

[Send comments](#) on this topic.

ISwDMDocument16 Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.swdocumentmgr.Namespace](#) : ISwDMDocument16 Interface

Accesses the document.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

Public Interface ISwDMDocument16

Inherits

[ISwDMDocument](#), [ISwDMDocument10](#), [ISwDMDocument12](#), [ISwDMDocument13](#), [ISwDMDocument14](#), [ISwDMDocument15](#), [ISwDMDocument3](#), [ISwDMDocument4](#), [ISwDMDocument5](#), [ISwDMDocument6](#), [ISwDMDocument7](#), [ISwDMDocument8](#)

Visual Basic (Usage)



Dim instance As [ISwDMDocument16](#)

C#

public interface ISwDMDocument16 :

[ISwDMDocument](#), [ISwDMDocument10](#), [ISwDMDocument12](#), [ISwDMDocument13](#), [ISwDMDocument14](#), [ISwDMDocument15](#), [ISwDMDocument3](#), [ISwDMDocument4](#), [ISwDMDocument5](#), [ISwDMDocument6](#), [ISwDMDocument7](#), [ISwDMDocument8](#)

C++/CLI

public interface class ISwDMDocument16 : public

[ISwDMDocument](#), [ISwDMDocument10](#), [ISwDMDocument12](#), [ISwDMDocument13](#), [ISwDMDocument14](#), [ISwDMDocument15](#), [ISwDMDocument3](#), [ISwDMDocument4](#), [ISwDMDocument5](#), [ISwDMDocument6](#), [ISwDMDocument7](#), [ISwDMDocument8](#)

Visual Basic for Applications (VBA) Syntax

See [SwDMDocument16](#).

Example

[Get Whether Part Has Frozen Features \(C#\)](#)

[Get Whether Part Has Frozen Features \(VB.NET\)](#)

Remarks

Before you can access this object, you must call [ISwDMApplication::GetDocument](#).

NOTES:

- You can access an ISwDMDocument16 object by calling QueryInterface on an [ISwDMDocument](#) object in C++ or by direct assignment in Visual Basic.
- The SwDMDocument object can be assigned to an ISwDMDocument16 variable, just like the SOLIDWORKS [IModelDoc2](#) object can be assigned to a SOLIDWORKS [IPartDoc](#) variable.

Accessors

[ISwDMApplication::GetDocument](#)

[ISwDMConfiguration::Document](#)

[ISwDMConfigurationMgr::Document](#)

See Also

[ISwDMDocument16 Members](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)
[ISwDMDocument3 Interface](#)
[ISwDMDocument4 Interface](#)
[ISwDMDocument5 Interface](#)
[ISwDMDocument6 Interface](#)
[ISwDMDocument7 Interface](#)
[ISwDMDocument8 Interface](#)
[ISwDMDocument10 Interface](#)
[ISwDMDocument13 Interface](#)
[ISwDMDocument14 Interface](#)
[ISwDMDocument15 Interface](#)
[ISwDMDocument17 Interface](#)
[ISwDMDocument18 Interface](#)
[ISwDMDocument19 Interface](#)
[ISwDMDocument20 Interface](#)
[ISwDMDocument21 Interface](#)
[ISwDMDocument22 Interface](#)
[ISwDMDocument23 Interface](#)
[ISwDMDocument24 Interface](#)
[ISwDMDocument25 Interface](#)
[ISwDMDocument26 Interface](#)
[ISwDMDocument27 Interface](#)
[ISwDMDocument28 Interface](#)
[ISwDMDocument29 Interface](#)
[ISwDMDocument30 Interface](#)

ISwDMDocument16 Interface Members

[See Also](#) [Methods](#)

| [SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMDocument16 Interface | |

The following tables list the members exposed by [ISwDMDocument16](#).

Public Methods

Name	Description
 HasFrozenFeatures	Gets whether the document has frozen features and whether those features need to be updated.

[Top](#)

See Also

[ISwDMDocument16 Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)
[ISwDMDocument3 Interface](#)
[ISwDMDocument4 Interface](#)
[ISwDMDocument5 Interface](#)
[ISwDMDocument6 Interface](#)
[ISwDMDocument7 Interface](#)
[ISwDMDocument8 Interface](#)
[ISwDMDocument10 Interface](#)
[ISwDMDocument13 Interface](#)
[ISwDMDocument14 Interface](#)
[ISwDMDocument15 Interface](#)
[ISwDMDocument17 Interface](#)
[ISwDMDocument18 Interface](#)
[ISwDMDocument19 Interface](#)
[ISwDMDocument20 Interface](#)
[ISwDMDocument21 Interface](#)
[ISwDMDocument22 Interface](#)
[ISwDMDocument23 Interface](#)
[ISwDMDocument24 Interface](#)
[ISwDMDocument25 Interface](#)
[ISwDMDocument26 Interface](#)
[ISwDMDocument27 Interface](#)
[ISwDMDocument28 Interface](#)
[ISwDMDocument29 Interface](#)
[ISwDMDocument30 Interface](#)

ISwDMDocument16 Interface Methods

[See Also](#)

| [SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMDocument16 Interface |

For a list of all members of this type, see [ISwDMDocument16 members](#).

Public Methods

Name	Description
 HasFrozenFeatures	Gets whether the document has frozen features and whether those features need to be updated.

[Top](#)

See Also

[ISwDMDocument16 Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)
[ISwDMDocument3 Interface](#)
[ISwDMDocument4 Interface](#)
[ISwDMDocument5 Interface](#)
[ISwDMDocument6 Interface](#)
[ISwDMDocument7 Interface](#)
[ISwDMDocument8 Interface](#)
[ISwDMDocument10 Interface](#)
[ISwDMDocument13 Interface](#)
[ISwDMDocument14 Interface](#)
[ISwDMDocument15 Interface](#)
[ISwDMDocument17 Interface](#)
[ISwDMDocument18 Interface](#)
[ISwDMDocument19 Interface](#)
[ISwDMDocument20 Interface](#)
[ISwDMDocument21 Interface](#)
[ISwDMDocument22 Interface](#)
[ISwDMDocument23 Interface](#)
[ISwDMDocument24 Interface](#)
[ISwDMDocument25 Interface](#)
[ISwDMDocument26 Interface](#)
[ISwDMDocument27 Interface](#)
[ISwDMDocument28 Interface](#)
[ISwDMDocument29 Interface](#)
[ISwDMDocument30 Interface](#)

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

HasFrozenFeatures Method (ISwDMDocument16)

[See Also](#) [Example](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMDocument16 Interface](#) : HasFrozenFeatures Method (ISwDMDocument16)

Gets whether the document has frozen features and whether those features need to be updated.

.NET Syntax

Visual Basic (Declaration)

```
Function HasFrozenFeatures(  
    ByRef FrozenFeatureNeedsUpdate As System.Boolean _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISwDMDocument16  
Dim FrozenFeatureNeedsUpdate As System.Boolean  
Dim value As System.Boolean  
  
value = instance.HasFrozenFeatures(FrozenFeatureNeedsUpdate)
```

C#

```
System.bool HasFrozenFeatures(  
    out System.bool FrozenFeatureNeedsUpdate  
)
```

C++/CLI

```
System.bool HasFrozenFeatures(  
& [Out] System.bool FrozenFeatureNeedsUpdate  
)
```

Parameters

FrozenFeatureNeedsUpdate

True if the document has frozen features that need to be updated, false if not (see **Remarks**)

Return Value

True if the document has frozen features, false if not

Visual Basic for Applications (VBA) Syntax

See [SwDMDocument16::HasFrozenFeatures](#).

Example

[Get Whether Part Has Frozen Features \(C#\)](#)
[Get Whether Part Has Frozen Features \(VB.NET\)](#)

Remarks

The FrozenFeatureNeedsUpdate return value is only valid if the document has frozen features.

See Also

[ISwDMDocument16 Interface](#)
[ISwDMDocument16 Members](#)

Availability

SOLIDWORKS Document Manager API 2012 SP0

ISwDMDocument17 (Type)

SOLIDWORKS Document Manager API Help

[Send comments](#) on this topic.

ISwDMDocument17 Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.swdocumentmgr.Namespace](#) : ISwDMDocument17 Interface

Accesses the document.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface ISwDMDocument17
    Inherits
    ISwDMDocument, ISwDMDocument10, ISwDMDocument12, ISwDMDocument13, ISwDMDocument14, ISwDMDocument15,
    ISwDMDocument16, ISwDMDocument3, ISwDMDocument4, ISwDMDocument5, ISwDMDocument6, ISwDMDocument7,
    ISwDMDocument8
```

Visual Basic (Usage)



```
Dim instance As ISwDMDocument17
```

C#

```
public interface ISwDMDocument17 :
    ISwDMDocument, ISwDMDocument10, ISwDMDocument12, ISwDMDocument13, ISwDMDocument14, ISwDMDocument15,
    ISwDMDocument16, ISwDMDocument3, ISwDMDocument4, ISwDMDocument5, ISwDMDocument6, ISwDMDocument7,
    ISwDMDocument8
```

C++/CLI

```
public interface class ISwDMDocument17 : public
    ISwDMDocument, ISwDMDocument10, ISwDMDocument12, ISwDMDocument13, ISwDMDocument14, ISwDMDocument15,
    ISwDMDocument16, ISwDMDocument3, ISwDMDocument4, ISwDMDocument5, ISwDMDocument6, ISwDMDocument7,
    ISwDMDocument8
```

Visual Basic for Applications (VBA) Syntax

See [SwDMDocument17](#).

Example

[Get Configuration Information \(C#\)](#)
[Get Configuration Information \(VB.NET\)](#)

Remarks

Before you can access this object, you must call [ISwDMApplication::GetDocument](#).

NOTES:

- You can access an ISwDMDocument17 object by calling QueryInterface on an [ISwDMDocument](#) object in C++ or by direct assignment in Visual Basic.
- The SwDMDocument object can be assigned to an ISwDMDocument17 variable, just like the SOLIDWORKS [IModelDoc2](#) object can be assigned to a SOLIDWORKS [IPartDoc](#) variable.

Accessors

[ISwDMApplication::GetDocument](#)
[ISwDMConfiguration::Document](#)
[ISwDMConfigurationMgr::Document](#)

See Also

[ISwDMDocument17 Members](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)
[ISwDMDocument3 Interface](#)
[ISwDMDocument4 Interface](#)
[ISwDMDocument5 Interface](#)
[ISwDMDocument6 Interface](#)
[ISwDMDocument7 Interface](#)
[ISwDMDocument8 Interface](#)
[ISwDMDocument10 Interface](#)
[ISwDMDocument13 Interface](#)
[ISwDMDocument14 Interface](#)
[ISwDMDocument15 Interface](#)
[ISwDMDocument16 Interface](#)
[ISwDMDocument18 Interface](#)
[ISwDMDocument19 Interface](#)
[ISwDMDocument20 Interface](#)
[ISwDMDocument21 Interface](#)
[ISwDMDocument22 Interface](#)
[ISwDMDocument23 Interface](#)
[ISwDMDocument24 Interface](#)
[ISwDMDocument25 Interface](#)
[ISwDMDocument26 Interface](#)
[ISwDMDocument27 Interface](#)
[ISwDMDocument28 Interface](#)
[ISwDMDocument29 Interface](#)
[ISwDMDocument30 Interface](#)

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

ISwDMDocument17 Interface Members

[See Also](#) [Methods](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMDocument17 Interface

The following tables list the members exposed by [ISwDMDocument17](#).

Public Methods

Name	Description
 GetCustomProperty2	Gets the specified custom property for this document.

[Top](#)

See Also

[ISwDMDocument17 Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)
[ISwDMDocument3 Interface](#)
[ISwDMDocument4 Interface](#)
[ISwDMDocument5 Interface](#)
[ISwDMDocument6 Interface](#)
[ISwDMDocument7 Interface](#)
[ISwDMDocument8 Interface](#)
[ISwDMDocument10 Interface](#)
[ISwDMDocument13 Interface](#)
[ISwDMDocument14 Interface](#)
[ISwDMDocument15 Interface](#)
[ISwDMDocument16 Interface](#)
[ISwDMDocument18 Interface](#)
[ISwDMDocument19 Interface](#)
[ISwDMDocument20 Interface](#)
[ISwDMDocument21 Interface](#)
[ISwDMDocument22 Interface](#)
[ISwDMDocument23 Interface](#)
[ISwDMDocument24 Interface](#)
[ISwDMDocument25 Interface](#)
[ISwDMDocument26 Interface](#)
[ISwDMDocument27 Interface](#)
[ISwDMDocument28 Interface](#)
[ISwDMDocument29 Interface](#)
[ISwDMDocument30 Interface](#)

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

ISwDMDocument17 Interface Methods

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMDocument17 Interface

For a list of all members of this type, see [ISwDMDocument17 members](#).

Public Methods

Name	Description
 GetCustomProperty2	Gets the specified custom property for this document.

[Top](#)

See Also

[ISwDMDocument17 Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)
[ISwDMDocument3 Interface](#)
[ISwDMDocument4 Interface](#)
[ISwDMDocument5 Interface](#)
[ISwDMDocument6 Interface](#)
[ISwDMDocument7 Interface](#)
[ISwDMDocument8 Interface](#)
[ISwDMDocument10 Interface](#)
[ISwDMDocument13 Interface](#)
[ISwDMDocument14 Interface](#)
[ISwDMDocument15 Interface](#)
[ISwDMDocument16 Interface](#)
[ISwDMDocument18 Interface](#)
[ISwDMDocument19 Interface](#)
[ISwDMDocument20 Interface](#)
[ISwDMDocument21 Interface](#)
[ISwDMDocument22 Interface](#)
[ISwDMDocument23 Interface](#)
[ISwDMDocument24 Interface](#)
[ISwDMDocument25 Interface](#)
[ISwDMDocument26 Interface](#)
[ISwDMDocument27 Interface](#)
[ISwDMDocument28 Interface](#)
[ISwDMDocument29 Interface](#)
[ISwDMDocument30 Interface](#)

SOLIDWORKS Document Manager API Help

[Send comments](#) on this topic.

GetCustomProperty2 Method (ISwDMDocument17)

[See Also](#) [Example](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMDocument17 Interface](#) : GetCustomProperty2 Method (ISwDMDocument17)

Gets the specified custom property for this document.

.NET Syntax

Visual Basic (Declaration)

```
Function GetCustomProperty2( _  
    ByVal FieldName As System.String, _  
    ByRef type As SwDmCustomInfoType _  
) As System.String
```

Visual Basic (Usage)



```
Dim instance As ISwDMDocument17  
Dim FieldName As System.String  
Dim type As SwDmCustomInfoType  
Dim value As System.String  
  
value = instance.GetCustomProperty2(FieldName, type)
```

C#

```
System.string GetCustomProperty2(  
    System.string FieldName,  
    out SwDmCustomInfoType type  
)
```

C++/CLI

```
System.String^ GetCustomProperty2(  
& System.String^ FieldName,  
& [Out] SwDmCustomInfoType type  
)
```

Parameters

FieldName

Name of custom property (see **Remarks**)

type

Type of custom property as defined by [SwDmCustomInfoType](#)

Return Value

Value of custom property

Visual Basic for Applications (VBA) Syntax

See [SwDMDocument17::GetCustomProperty2](#).

Example

[Get Configuration Information \(C#\)](#)
[Get Configuration Information \(VB.NET\)](#)

Remarks

To populate FieldName, use [ISwDMDocument::GetCustomPropertyNames](#) to get the names of all of the custom properties.

This method returns an evaluated value:

- from when the document was last saved in SOLIDWORKS.
If you called [ISwDMDocument::SetCustomProperty](#) to set a linked custom property, then you must open and save the file in SOLIDWORKS before calling this method. SOLIDWORKS must process the linked custom property before your DocumentMgr application can retrieve its evaluated value.
- without the **fromparent+** preface for externally referenced documents. Use [ISwDMDocument::GetCustomProperty](#) to return resolved evaluated values prefaced with **fromparent+**.

See Also

[ISwDMDocument17 Interface](#)
[ISwDMDocument17 Members](#)
[ISwDMDocument::AddCustomProperty Method \(\)](#)
[ISwDMDocument::DeleteCustomProperty Method \(\)](#)
[ISwDMDocument::GetCustomPropertyCount Method \(\)](#)
[ISwDMDocument5::GetCustomPropertyValues Method \(\)](#)
[ISwDMConfiguration::GetCustomProperty Method \(\)](#)
[ISwDMConfiguration14::GetCustomProperty2 Method \(\)](#)

Availability

SOLIDWORKS Document Manager API 2013 FCS