» cloudscale server

Provides a cloud scale.ch Server resource. This can be used to create, modify, and delete servers.

» Example Usage

» Argument Reference

The following arguments are supported when creating new servers:

- name (Required) Name of the new server. The name has to be a valid host name or a fully qualified domain name (FQDN).
- flavor_slug (Required) The slug (name) of the flavor to use for the new server. Possible values can be found in our API documentation.
- image_slug (Required) The slug (name) of the image to use for the new server. Possible values can be found in our API documentation.
- ssh_keys (Required) A list of SSH public keys. Use the full content of your *.pub file here.
- volume_size_gb (Optional) The size in GB of the SSD root volume of the new server. If this parameter is not specified, the value will be set to 10. Valid values are either 10 or multiples of 50.
- bulk_volume_size_gb (Optional) The size in GB of the bulk storage volume of the new server. If this parameter is not specified, no bulk storage volume will be attached to the server. Valid values are multiples of 100.
- use_public_network (Optional) Attach/detach the public network interface to/from the new server. Can be true (default) or false.
- use_private_network (Optional) Attach/detach the private network interface to/from the new server. Can be true or false (default).
- use_ipv6 (Optional) Enable/disable IPv6 on the public network interface of the new server. Can be true (default) or false.

- anti_affinity_uuid (Optional) Pass the UUID of another server to either create a new anti-affinity group with that server or add the new server to the same (existing) group as the other server.
- user_data (Optional) User data (custom cloud-config settings) to use for the new server. Needs to be valid YAML. A default configuration will be used if this parameter is not specified or set to null. Use only if you are an advanced user with knowledge of cloud-config and cloud-init.
- status (Optional) The desired state of a server. Can be running (default) or stopped.

The following arguments are supported when updating servers:

• status - (Optional) The desired state of a server. Can be running (default) or stopped.

» Attributes Reference

In addition to the arguments listed above, the following computed attributes are exported:

- id The UUID of this server.
- href The cloudscale.ch API URL of the current resource.
- ssh_fingerprints A list of SSH host key fingerprints (strings) of this server.
- ssh_host_keys A list of SSH host keys (strings) of this server.
- anti_affinity_with A list of server UUIDs that belong to the same anti-affinity group as this server.
- volumes A list of volume objects attached to this server. Each volume object has three attributes:
 - device_path The path (string) to the volume on your server (e.g. /dev/vda)
 - size_gb The size (int) of the volume in GB. Typically matches volume_size_gb or bulk_volume_size_gb.
 - type A string. Either ssd or bulk.
- interfaces A list of interface objects attached to this server. Each interface object has two attributes:
 - type Either public or private. Public interfaces are connected to the Internet, while private interfaces are not.
 - addresses A list of address objects:
 - * address An IPv4 or IPv6 address that has been assigned to this server.
 - * gateway An IPv4 or IPv6 address that represents the default gateway for this interface.
 - * prefix_length The prefix length for this IP address, typically 24 for IPv4 and 128 for IPv6.
 - * reverse ptr The PTR record (reverse DNS pointer) for this

IP address. If you use an FQDN as your server name it will automatically be used here.

* version - The IP version, either 4 or 6.

» cloudscale_floating_ip

Provides a cloud scale.ch Floating IP to represent a publicly-accessible static IP address or IP network that can be assigned to one of your cloud scale.ch servers. Floating IPs can be moved between servers. Possible use cases include: High-availability, non-disruptive maintenance, multiple IPs per server, or re-using the same IP after replacing a server.

» Example Usage

```
# Create a new Server
resource "cloudscale server" "web-worker01" {
             = "web-worker01"
 flavor slug = "flex-4"
  image_slug = "debian-9"
              = ["ssh-ed25519 AAAAC3NzaC11ZDI1NTE5AAAAIL2jzgla23DfRVLQr3KT20QQYovqCCN3c1Hrjn
  ssh_keys
}
# Add a Floating IPv4 address to web-worker01
resource "cloudscale_floating_ip" "web-worker01-vip" {
              = "${cloudscale_server.web-worker01.id}"
  server
  ip\_version = 4
  reverse_ptr = "vip.web-worker01.example.com"
# Add a Floating IPv6 network to web-worker01
resource "cloudscale floating ip" "web-worker01-net" {
  server
                = "${cloudscale_server.web-worker01.id}"
  ip_version
 prefix_length = 56
```

» Argument Reference

The following arguments are supported when adding Floating IPs:

- server (Required) Assign the Floating IP to this server (UUID).
- ip_version (Required) 4 or 6, for an IPv4 or IPv6 address or network respectively.

- prefix_length (Optional) If you want to assign an entire network instead of a single IP address to your server, you must specify the prefix length. Currently, there is only support for ip_version=6 and prefix_length=56.
- reverse_ptr (Optional) You can specify the PTR record (reverse DNS pointer) in case of a single Floating IP address.

The following arguments are supported when updating Floating IPs:

• server - (Required) (Re-)Assign the Floating IP to this server (UUID).

» Attributes Reference

In addition to the arguments listed above, the following computed attributes are exported:

- href The cloudscale.ch API URL of the current resource.
- network The CIDR notation of the Floating IP address or network, e.g. 192.0.2.123/32.
- next_hop The IP address of the server that your Floating IP is currently assigned to.