Crowdcoin Masternode Setup Guide on UBUNTU VPS Server

We need at least 1GHz and 500MB of Ram

Before anything set up initial server using this guide <u>here</u> List of things that are essential:

- 1. 1000CRC (+1 CRC to cover any TX fees)
- 2. IP address
- 3. VPS server

Now we are Ready to Install the Node

Step 1: Install the dependancies

sudo apt-get install libzmq3-dev libminiupnpc-dev libssl-dev libevent-dev -y

sudo apt-get install build-essential libtool autotools-dev automake pkg-config -y sudo apt-get install libssl-dev libevent-dev bsdmainutils software-properties-common -y sudo apt-get install libboost-all-dev -y

and apage and an analysis and an

Berkley 4.8:

sudo add-apt-repository ppa:bitcoin/ bitcoin sudo apt-get update sudo apt-get install libdb4.8-dev libdb4.8++-dev wget -y

Step 2: download the wallet and extract from the archive

wget https://github.com/crowdcoinChain/Crowdcoin/releases/download/1.0.0/ Crowdcoin command line binaries linux 1.0.tar.gz

tar -xf Crowdcoin_command_line_binaries_linux_1.0.tar.gz
cd Crowdcoin_command_line_binaries_linux_1.0

Step 3: Start Headless Client

./crowdcoind -daemon

watch ./crowdcoin-cli info

This command allow you to see the progression of the sync, once no more blocks are added the wallet is in sync

Step 4: Open a note and keep it open so that you can save for later account adress and genkey

RUN

./crowdcoin-cli getaccountaddress 0

this address is the one you have to send to the exact amount of 1000 CRC

./crowdcoin-cli masternode genkey

this is the adress we need later to steup the crowdcoin.conf

Step 5: Send 1000CRC to the address generated in the previous step

Step 6: Prepare the masternode conf file

./crowdcoin-cli masternode outputs

save the two parameters the first is <u>the trasaction id</u> and the second the <u>txcount</u> copy those in your opened note. Run:

./crowdcoin-cli stop

Step 7: Set Configuration

now go in you \$HOME directory eg. /home/name_of_the_user/

cd .crowdcoincore vi crowdcoin.conf

press **1** to get the permission to insert data now copy and paste those settings into your .conf file

rpcuser=user
rpcpassword=pass
rpcallowip=127.0.0.1
listen=1
server=1
daemon=1
staking=0
externalip=IPV4: 12875
masternode=1
masternodeprivkey=masternodeprivkey

change <u>user</u> and <u>pass</u> with any random string with 10 characters or more add your <u>externalip</u> and <u>masternode</u> key that you saved from before

Press ESC

Write:wg

Hit Enter

now crowdcoin.conf has been saved

Step 8: Set Masternode

Open masternode.conf

vi masternode.conf

MN1 < Vps IP>:12875 masternodeprivkey tx_id tx_count

Those 3 information are those previously saved in note

The VPS IP is the IP of the vps that is running this masternode

pres ESC Writer :wq Hit ENTER

now masternode.conf has been saved

Step 9: Set restart the wallet and start masternode

using cd command get back to the folder of the wallet

./crowdcoind -daemon

wait 20 min

Now runn:

./crowdcoin masternode start

expect

Masternode successfully started //in case you don't get this message redo the previous command after 5 minutes

Then sentinel is required you can find the explanation on how to set it up here

https://github.com/crowdcoinChain/sentinelLinux