Get Access

To use SoCLaaS, you will need:

- SoCLaaS API base URL (https://soclaas-api.comp.nus.edu.sg [https://soclaas-api.comp.nus.edu.sg])
- An API key
- One or more approved model names

Get API Key

The easiest way to get your API key is to login to https://soclaas-portal.comp.nus.edu.sg [https://soclaas-portal.comp.nus.edu.sg] and issue/rotate your API key.

The instructions below are for CLI/programmatic access.

Login to SoC login servers like stf.comp.nus.edu.sg (for staff) or stu.comp.nus.edu.sg (for students) and run:

```
soclaas-portal issue
```
Copy

You will need to enter your SOC account password. This will generate an API key. Preferably, let the script update ~/.bashrc for you so that environment variables are setup for you automatically.

If you already have an API key issued before, you can get a new replacement key by running:

```
soclaas-portal issue --rotate
```
Copy

The old key will be replaced and will not work anymore.)

Treat the API key like a password:

- Store it in environment variables or a secret manager
- Do not commit it to git
- Do not embed it in frontend code or mobile apps
- Rotate it if you think it has been exposed

You can run `soclaas-portal -h` to get information on other commands, such as to revoke your key, get usage summary, usage records, and buget controls that apply to your key.

API Usage

Please refer to the API Reference for details. The Quick Start Guide provides a tutorial on using the API.

Web/Chat Access

SoCLaaS is meant to be an LLM API gateway service. The primary usage method is through API access (see quickstart). However, a user-friendly web chat interface using Open WebUI is also available at https://aichat.comp.nus.edu.sg [https://aichat.comp.nus.edu.sg]. Note that getting an API Key is mandatory to use the Open WebUI.

Using with Codex

Make sure you have Codex installed first (refer to https://openai.com/codex/ [https://openai.com/codex/]). Then, configure Codex by running:

```
soclaas-setup-codex
```
Copy

This will create a separate profile from the regular Codex/OpenAI one. To use Codex with SoCLaaS, run:

```
codex --profile soclaas
```
Copy

Installing outside of stf.comp.nus.edu.sg / stu.comp.nus.edu.sg

a) Set Up a Virtual Environment (Optional)

It is recommended to use a virtual environment to avoid dependency conflicts.

```
# 1. Create a virtual environment
python3 -m venv .venv

# 2. Activate the virtual environment
source .venv/bin/activate
```
Copy

b) Install required Python package

```
pip install tomlkit
```
Copy

c) Configure Environment Variables

```
export SOCLAAS_API_KEY="<your_api_key_here>"
export SOCLAAS_MODEL="<your_model_identifier>"
export SOCLAAS_BASE_URL=https://soclaas-api.comp.nus.edu.sg/v1
```
Copy

You may also input the above codes into your `~/.bashrc`. Remember to do a `source ~/.bashrc` to refresh the changes.

d) Install Codex CLI

```
curl -fsSL https://chatgpt.com/codex/install.sh | sh
```
Copy

e) Transfer SoCLaaS Set up file (from stf or stu server)

To view the SoCLaaS file:

```
cat /usr/local/bin/soclaas-setup-codex
```
Copy

Copy the SoCLaaS set up file to your local directory on your server and execute.

```
scp /usr/local/bin/soclaas-setup-codex id@yourserver:
chmod +x ~/soclaas-setup-codex
./soclaas-setup-codex
```
Copy

f) Verification

After completing the above steps, verify that SoCLaaS is correctly installed by running:

```
codex --profile soclaas
```
Copy

Related

- Get Access
- API Reference
- Quick Start Guide
- Using with a GUI