

Kassa

User guide


Cashier quick guide

Print this page and keep it next to the till

The Download PDF page has the "Cashier quick guide" — one A4 sheet.


1. Opening the program

Green **Kassa** icon on the desktop → **choose your name** → **password** → **Log in**.



2. Selling


1. **Scan the product's barcode** — the product goes into the cart (a "beep"). Scan the same product again and the quantity goes up.
2. No barcode? **Type the name** in the box at the top and choose it from the list.
3. Products sold by weight (kg) — enter the weight, e.g. `0.750`.
4. Change the quantity: **−** / **+**. Remove a wrong product with ×.



3. Payment

Button	When
Cash or **F2**	Enter the money the customer gave you (or press 5 ₼, 10 ₼...). The program shows the **change due**. If the amount is exact, leave it empty.
Card or **F3**	First check that the payment went through on the bank terminal, then confirm.

Then **Complete sale** or **Enter**.



4. Receipt

- If a receipt printer is connected, the receipt **prints by itself**.
- If not, press the **"Receipt"** button in the green message after the sale.

5. Sounds

Sound	Meaning
Short "beep"	Product found
Low tone	Product not found — the **admin** must add the product to the system

6. Closing

The ✕ in the top right corner of the window. The program makes a backup and closes. If nobody touches it for a while, the program logs you out — enter your password again.

If something goes wrong

- Blank white screen / "error" — **Reload**, or close the window and open it again. Sales are not lost.
- Forgot your password — the **admin** sets a new one in "Users".
- Anything else — If something goes wrong.

Installation and first launch

This page is for the person who installs the program (usually the shop owner). It is done once.


1. Download the program

Latest version: **Kassa-Setup — download** (the `Kassa-Setup-….exe` file).

2. Install

1. Open the `Kassa-Setup-….exe` file.
2. If Windows says "unrecognized app": **"More info"** → **"Run anyway"**.
3. Choose the language (Azərbaycanca, Русский, English).
4. Choose the installation mode:
   - **"Install for all users" (recommended for a shop)** — Windows asks for the administrator password. The program runs in protected mode: the cashier cannot remove the program or the data. See **Windows accounts**.
   - **"Install for me only"** — no administrator password needed. For trying it out or a home computer.
5. **Next** → **Install** → **Finish**. A green **Kassa** icon appears on the desktop.

3. First launch



1. **Installation password** — get it from the person who gave you the program. It is asked only the first time.
2. Choose the language, enter the **shop name**, **your name** and **your password** (at least 8 characters, letters and digits). You become the shop's **admin**.
3. **Set up**.

4. Recovery code — write it on paper

After setup, a **recovery code** appears on the screen.

- **Write it on paper** and keep it at home or in a safe. Do not store it as a file on the computer.
- If the computer breaks or is stolen, the data can be brought back **only with this code**.
- You can see it later too: **Backup** → **Recovery code** → your password.

Tick **"I have written down the code..."** → **Continue**.

5. Windows accounts: a separate account for the cashier

The safest setup (when installed "for all users"):

1. For the **owner**: a Windows **administrator account with a password** — they install and update Kassa from it.

2. For the **cashier**: a **standard** (non-administrator) account: Settings → Accounts → Other users → **Add account** → account type **"Standard User"**.
3. Every day the computer is used in the **cashier's account**. Kassa works there too, but the cashier cannot delete or change the program or the data files.
4. Everyone logs in to Kassa with their own **Kassa name and password** (separate from the Windows password).

In this mode closing the window does not stop the program completely — it keeps running in the background (Telegram report, backup). This is normal.

6. What to do next

Step	Where
Shop details (address, phone, tax ID (VÖEN) — shown on the receipt)	Settings
Cashier account	Users
Entering products	Products, Receiving goods
Receipt and label printer	Printer
Daily report and backup to your phone	Telegram
Weekly USB backup	Backup


Keyboard shortcuts

Key	Where	What it does
Scanner	Sale, Receiving, Products	Reads the barcode — no need to click any field
F2	Sale	Cash payment
F3	Sale	Card payment
Enter	Search box	Adds the typed barcode or name to the cart
Enter	Payment window	Completes the sale
Esc	Any window	Closes the window (changes are not saved)
Ctrl + P	Any page	Prints the page (or the "Print" button)

How the scanner works

A barcode scanner works like a keyboard: it "types" the digits very fast and presses Enter at the end. The program tells it apart from a person by the speed, so you don't need to click any field when scanning.

Selling



Adding a product to the cart

- **Scan it** — the product goes into the cart with a short "beep". Scan the same product again and the quantity goes up.
- **No barcode** — type the name in the box at the top and choose it from the list.
- **Products sold by weight (kg)** — the program asks for the weight: e.g. `0.750` (750 grams).


A low tone and **"Product not found"** — this product is not in the system. The admin must **add it**. If the admin is scanning, the "New product" window opens right away.

Fixing the cart

- Change the quantity: **−** / **+** or click the number.
- Remove a wrong product: the ✕ at the end of the line.
- Remove everything: **Clear cart**.

Payment

Cash (F2)	Enter the money the customer gave you or pick a ready button. The program shows the **change due**. If the amount is exact, leave the box empty.
Card (F3)	First check that the payment went through on the bank terminal, then confirm.



Complete sale or **Enter**. The message "Sale #... — ... ₼" appears on the screen.

Receipt


- If a **receipt printer** is selected and "Print the receipt automatically after a sale" is on, the receipt **prints by itself**.
- If not, use the **"Receipt"** button in the green message.
- Receipt for an old sale: **Sales** → the sale → **Print receipt**.
- For cash sales the cash drawer (if connected) opens by itself.

If stock goes negative

If more was sold than the system has, the sale still goes through, but a warning appears — it means the goods receiving was not entered. The admin must do the goods receiving.

Products, barcodes and labels


Admin only.



New product

Products → New product:

Field	What to enter
Barcode	Scan the product's barcode
Name	The name the cashier and the receipt will show
Unit	**Piece** or **Kilogram (by weight)**
Sale price	The price the customer pays
Cost price	The price you paid (for profit calculation; the cashier does not see it)
Minimum stock	Below this, the "Low" warning appears



If a barcode that is not in the system is scanned during a sale or receiving, this window opens by itself.

Products without a barcode


Bread, herbs, your own products: the **Generate barcode** button → the program gives an in-store barcode (starts with 29). Then print its label and stick it on the product.

Changing the price

🖍️ on the product's line → new price → **Save**. The change is written to the log. To stop selling a product: untick **Active** (the product is not deleted, its history stays).

Printing labels

1. **Products** → tick the products you need (or 🏷️ on a single product's line).
2. **Print labels** → type:
   - **A4 sheet** — 24 labels (70×37 mm) or 40 labels;
   - **label printer roll** — 58×40, 50×30, 40×30 or 30×20 mm (the size of the label on the roll).
3. How many of each product: **+**.
4. **Print**. If a **label printer** is selected, the button shows the printer's name — labels print without a print dialog.




With the print dialog (no printer selected), the first time

Choose **Scale: 100% (Actual size)** and **Margins: None**. Do a test print on plain paper first.

After the label prints, check its barcode with the scanner — you should hear a "beep".

Receiving goods

Admin only. To increase stock when goods arrive.



1. The **Receiving** section → **scan** the incoming goods (or type the name).
2. Enter the **quantity** and **cost price** for each product.
3. Optionally enter the **supplier's name** and a note.
4. **Confirm receiving** → **Confirm**.

Stock goes up immediately. If a product that is not in the system is scanned, the "New product" window opens.

Receiving note

Open the receiving in the "Receivings in the last 30 days" list below → **Print document** (with signature lines for the supplier and the person receiving).


If you made a mistake in a receiving

A receiving is not deleted (so the stock history stays intact). To fix a wrong quantity, add the difference with a new receiving; if too much was entered, contact your technical person.

Stock and reports


Stock

How much of each product is left. The **Low** tab — print it as an order list.



Report (admin)

For the selected days: revenue, **profit**, cash and card, best sellers, products running low.



"Cash" — the money that should be in the till. At the end of the day, count the till and compare.


Printing and Excel

On every page:

- **Print** — to a printer or "Save as PDF";
- **Excel** — the file goes to the "Downloads" folder.

If the list is very long, the screen shows the first 300 lines — **"Show ... more"** at the bottom. Printing and Excel include everything.

Sales and voiding



- **Sales** → choose the date → click a sale → details.
- **Print receipt** — receipt for an old sale.
- A cashier sees only **their own** sales.


Voiding a sale (admin only)

Wrong sale → **Void sale** → enter the **reason** (required).

- The sale is **not deleted** — it stays as "Voided", with who voided it and when.
- The products go back into stock.
- The daily **Telegram report** lists voids separately.

Users

Admin only.



New user

New user → name, role, password.

Role	What they can do	Password
Cashier	Sell, view stock and their own sales	at least 4 characters (e.g. 4 digits)
Admin	Everything: products, prices, receiving, voids, reports, users, settings	at least 8 characters, letters and digits

Password

- If someone forgets their password, the admin sets a new one with the **Password** button.
- Everyone can change their own password: click your name at the bottom left → **Change password**.

Lock

If someone enters a wrong password **10 times**, they must wait 1 minute (after the 3rd mistake they see how many attempts are left). The admin can unlock them right away with **Unlock**. The number and the time can be changed in **Settings**.

An employee leaves

Deactivate — the user is not deleted and their past sales stay, but they cannot log in.


Training mode: teaching a new cashier

Help → **Training mode (cashier practice)** → duration (15 min–2 hours) → **Start training**.

- The sale screen works fully: scanning, cash/card, change. But sales are **not recorded** and stock does not change.
- An orange **"TRAINING MODE"** bar with the remaining time shows on every screen.
- **Real sales are not possible** meanwhile — train when there are no customers.
- The mode turns itself off when the time is up; to finish earlier — **End training**.
- Only an **admin** can turn it on (not a cashier). Turning it on and off is recorded in the log and the daily Telegram report.

Settings and language

Admin only. After making changes, press the **Save** button at the top (except the Telegram token and chat — they save by themselves). Every change is written to the log.



Section	What is there
Shop	Name, address, phone, tax ID (VÖEN), text at the bottom of the receipt — shown on the receipt
Appearance	Shop language, theme (light / dark / follow Windows), **text size**
Sales and printing	Scan beep, minimum stock for new products, label size, receipt width (80 / 58 mm)
Security	Automatic logout time, wrong passwords before lock, maximum lock time
Backup	How many automatic backups to keep, every how many hours
Internet	Check for new versions; check the computer clock
Printers	See **Receipt and label printer**
Telegram	See **Telegram**
Update	See **Updates**
Database	Database location, size, free space; **Move** — move it to another disk (e.g. `D:\Kassa`; not USB)

All settings are stored inside the database: if you restore the database on another computer, the settings come back too.

Everyone has their own language


Click your name at the bottom left → **Language** → Azərbaycanca / Русский / English (or "Shop language"). It changes only for you — the cashier can choose their own language separately.

Receipt and label printer

One thermal printer (e.g. **Xprinter XP-365B**) can print both receipts and barcode labels.

Connecting

1. Connect the printer by USB and install its **Windows driver** (the disc in the box or the manufacturer's website). It must appear in the Windows "Printers" list.
2. Kassa → **Settings** → **Printers**:
   - **Receipt printer** and **Label (barcode) printer** — choose the device from the list (it can be the same device);
   - **Label size** (in the Sales and printing card) — the size of the label on the roll (e.g. 40×30);
   - optionally: **Print the receipt automatically after a sale**, **Open the cash drawer on cash payment**.
3. **Save** → **Test receipt** and **Test label**.
4. Scan the barcode of the test label — you should hear a "beep".



How it works

- If a printer is selected, receipts and labels go **directly, without a print dialog**.
- If no printer is selected ("Print dialog"), the Windows print dialog opens every time; it works with any printer.
- If the printer is off or out of paper, an error appears and **"Use print dialog"** is offered. The receipt is not lost.

Problems

Symptom	What to do
"Selected printer not found"	Is the printer connected and switched on? Select it again in Settings.
A label is split across two labels / blank space is left	"Label size" must match the roll. Calibrate the printer's sensor (Xprinter: hold the FEED button while switching it on).
Barcode does not scan	Clean the thermal head; on a 30×20 label the barcode is small — 40×30 works better.
Cash drawer does not open	The drawer must be connected to the RJ11 port of the receipt printer (some label printers don't have this port). Try the "Open drawer" test.


Telegram: daily report and backup

Every evening a short **report** (sales, revenue, cash and card, voids — who did them, products running low) and an **encrypted backup** arrive on the owner's phone. Even if the computer is stolen or breaks, the copy in Telegram stays.

If no message arrives, that itself is a warning: something is wrong.

Connecting (once, internet needed)

1. On your phone, find **@BotFather** in Telegram → `/newbot` → give the bot a name (e.g. "Shop Kassa") and a username (it must end with `bot`).
2. BotFather gives you a long **token** (`123456789:AA…`). Copy it.
3. Kassa → **Settings** → **Telegram** → paste it into the **Bot token** field.
4. Find your bot in Telegram and send it `/start`.
   - **To send to a group:** add the bot to the group and send `/start@your_bot_name` in the group (e.g. `/start@magaza_kassa_bot`). An ordinary message is not enough — Telegram does not show ordinary group messages to bots.
5. In Kassa, press **Find chat**. If several chats are found (private and group), choose one from the list. The choice is **saved by itself**.
6. Choose the report time (e.g. 21:00) → **Test message**. A message should arrive on your phone.



After that


- The report comes every day at the chosen time. If the program was closed before that time, a "late report" comes the next day.

- Backup once a day. With a large database the file is split into parts (`.001`, `.002`...).
- If there is no internet, it tries again every 15 minutes. The time and result of the last send are shown in Settings.
- A saved token is not shown on the screen (the field is empty and says "Saved"). If someone learns the token — `/revoke` in BotFather.

> **Yellow warning "Backups are not reaching Telegram"**
>
> Nothing has been sent for more than 2 days. The reason is written in the warning. Check: is there internet? Was the bot deleted? Settings → Telegram → **Test message**.

How to restore a backup from Telegram: **Backup and restore**.

Backup and restore



The program backs up by itself

- Regularly (usually every 20 hours) and **when it closes**.
- A separate backup before an update and before a restore.
- If Telegram is connected — once a day to your phone.

Once a week: USB

Insert a USB stick → **Backup** → **Copy the latest backup to …**. Do not keep the USB stick next to the computer.

Recovery code

Backup → **Recovery code** → your password. It must be written on paper — if the computer breaks, the data cannot be brought back without it.

Restoring a backup

If something got messed up by mistake:

- in the list, **Restore** next to the backup → admin password.

Restore from file

A file from USB or downloaded from Telegram: **Restore from file** → choose the file → admin password.

- **If Telegram sent parts (`.001`, `.002`...)** — download all of them and select **all together** (hold Ctrl).
- If the file is from another computer, also enter that installation's **recovery code**.

After a restore everyone logs in again. The state before the restore is kept as a "Before restore" backup — nothing is lost.

Recovery screen

If the database is deleted or damaged, the key is lost, or an old version of the program is installed, the **Recovery** screen opens instead of the normal one. The reason is written at the top.

1. Enter the **recovery code** (from the paper).
2. Choose: **Restore this backup**, **Restore from file** (USB, Telegram), **Recover key** or **Check again**.
3. **Start with an empty database** — only if there are no backups at all.

Nothing can be done on this screen without the recovery code — the data is protected. If it says "Old program version", just install the latest version.

"WARNING: the database was replaced with an old copy!"

While the program was closed, someone replaced the data file with an old copy — sales made in between may be missing. Check the backups in Telegram and on USB, restore a newer one if needed, then press **Got it**.

The computer broke

Install Kassa on the new computer → create a temporary admin on first launch → **Backup** → **Restore from file** (USB or Telegram file) + the old installation's **recovery code**. The old users, products and settings come back.


Updates

The program accepts only **official (signed)** Kassa updates — a fake or modified file will not be installed.

From the internet

When a new version is out, the admin sees **"A new version of Kassa is available"** → **View** (or Settings → Update) → **Update** → admin password.

The program first makes a backup, closes, and a few seconds later reopens by itself with the new version. Nothing installs by itself in the middle of a sale — only when you press "Update".



From a file (no internet)

Copy the `Kassa-Update-….kassa` file sent by the developer to the computer (USB, WhatsApp) → **Settings** → **Update** → **Update from file (.kassa)** → choose the file → "File verified: official Kassa ..." → **Update**.

After that

A **"What's new"** window appears once. All changes: **What's new**.

Data is **not lost** during an update. An older version cannot be installed over a newer one.

If something goes wrong

Situation	What to do
Blank white screen / "A screen error occurred"	**Reload**, or close the window and open it again. Sales are not lost.
"Product not found"	This product is not in the system — the admin should **add it**.
The scanner does not read	Check the scanner cable. Scan into Notepad: digits should appear. If the barcode is torn or worn — type the name to search.
The printer does not print	**Printer** → **Problems**.
I forgot my password	The admin should set a new one in **Users**. If the admin forgot theirs — contact your technical person.
"Too many failed attempts"	Wait 1 minute or ask the admin to press **Unlock**.
The program does not open, shows an error	Take a photo of the message and send it to your technical person.
The **Recovery** screen opened	**Backup and restore** → **Recovery screen**. The recovery code is needed.
Red "Database damage detected"	You can keep selling. Tell your technical person soon — a restore from the latest backup may be needed.
Yellow "Backups are not reaching Telegram"	**Telegram**.
"The computer clock is wrong"	Fix the date and time in Windows (so sales don't get the wrong date).
Uninstall/update says "Kassa is currently running"	Close the Kassa window, wait 2 seconds, **OK**.
The computer broke	**Backup** → **The computer broke**.

Showing the problem to the developer

Click your name at the bottom left → **Report a problem** → **Download file** (or **Send to Telegram**) → send the file via WhatsApp/Telegram. The file does **not** contain sales or prices.