

How to download an elevation file using WindNinja




Introduction

This document describes the functionality built into WindNinja to download elevation files for wind modeling. We call this utility the "elevation file grabber". It allows you to use a custom Google MapsTMinterface to zoom into and select a desired area for wind modeling. The elevation data for this area is downloaded by WindNinja from a USGS server and saved to a file on your computer. There is also a command line version of the elevation file grabber that is described here. The specific options available and work flow are described below.

To open the elevation file grabber window, start WindNinja and click *Surface Input* in the navigation tree at the top of WindNinja, then click the *Download File* button as shown below.



The *Download Elevation File* window will open. This window is divided into two areas as highlighted in red in the image below. These areas are discussed in the next two sections.



Graphics Window

The graphics window is an interactive mapping display used to navigate into the desired wind simulation area. This window uses a customized version of the popular Google MapsTMsoftware. Various different base maps are available using the *Map* and *Satellite* buttons in the upper right corner. There are a couple of ways to pan and zoom the map. Using a mouse, you can pan with the left button and zoom using a mouse scroll wheel. The keyboard can also be used to pan (arrow keys) and zoom (plus and minus keys).

Input Panel

Selection Method

The Selection Method section of the input panel allows you to define the area that you want to download. This download area is a rectangular box that will be drawn over the map in

the graphics window. There are four different ways to define this rectangular box that can be chosen from the drop-down box. They are:

1. Drag Box On Map

By clicking the *Drag Box On Map* button, you can then left-click and drag on the graphics window to define a box of the desired size.

2. Enter Bounding Box

This option allows you to enter the latitude and longitude bounds for the box.

3. Click Center Point

This option allows you to click a center point on the map to define the center of the box and then enter the size of the box.

4. Enter Center Point

With this method, you enter the center point coordinates of the box and the box size.

After using any of the methods above, a transparent red box will be drawn in the graphics window showing the area you've defined. If you want, you can enlarge or shrink this box in the graphics window by dragging the sides or corners. You can also move the box by dragging the center icon. The *Zoom To Extents* button in the graphics window will zoom the view to fit the box. The *Clear Map* button will clear the box.

Elevation Data Source

There are 4 possible on-line data sets to download elevation data from. These are listed in the *Select Elevation Source* drop-down box. The main difference between these data sets is the spatial resolution and extent. The table below briefly describes these differences. You should be sure to choose a data set that covers your simulation area.

Data set name	Resolution	Spatial Extent	Description
US SRTM	30 meters	Contiguous US, Hawaii,	Data from the Shuttle
		PR, Southern Alaska	Radar Tomography Mis-
			sion (SRTM)
WORLD SRTM	90 meters	Between approximately -	Data from the Shuttle
		60 and +60 latitude	Radar Tomography Mis-
			sion (SRTM)
WORLD GMTED	250 meters	Between approximately -	Global Multi-resolution
		60 and +85 latitude	Terrain Elevation Data
			2010 (GMTED 2010)
Landscape (LCP)	30 meters	Contiguous US, Hawaii,	FARSITE Landscape files
		PR, Southern Alaska	including vegetation in-
			formation

You can check the *Show Available Data* check-box to display a blue polygon on the map outlining the chosen data set's extents.

Download The File

Once you have defined your download area and selected the elevation data source, click the Download File button at the bottom to download the elevation file. A window will open to allow you to specify a file name and location. If you chose the option **US SRTM**, **WORLD SRTM**, or **WORLD GMTED**, the downloaded file will be a GeoTIFF (*.tif). **Landscape** files are downloaded as a .lcp file. After the file is successfully downloaded, you can close the Download elevation file window and the downloaded file will be automatically loaded into the main WindNinja window.