ONSCREEN V2.6

User Guide

Watching, listening and reading with OnScreen on the web, your TV and your phone

This guide is for the people who **watch and listen**. It covers signing in, finding things, the players, music, audiobooks, books, photos, live TV, downloads and your account, plus notes for each app.

Setting up the server, adding libraries and managing users is covered in the separate **OnScreen Install & Administration Guide**. When something in this guide depends on a server setting, it says *ask your server's admin*.

Covers OnScreen server v2.6 and the apps released with it: web, Android TV / Google TV, Fire TV, Android phone, Samsung (Tizen), LG (webOS), Xbox and Roku.

Screens in this guide come from a test server. Your server's libraries, titles and some buttons will differ.

Contents

1 Welcome to OnScreen

1.1 What OnScreen is
1.2 The apps and where to get them
1.3 Signing in on the web
1.4 Signing in on a TV with a code
1.5 Signing in on your phone
1.6 Profiles and PINs
1.7 Signing out

2 Finding things

2.1 Getting around the web app
2.2 The Home screen
2.3 Browsing a library
2.4 Title pages
2.5 Search
2.6 Collections and film series
2.7 People, studios and networks
2.8 Favorites, watch status and history
2.9 Asking for something new
2.10 Notifications

3 Watching

3.1 Starting and resuming
3.2 The web player
3.3 Versions, editions and multi-part movies
3.4 Audio tracks
3.5 Subtitles
3.6 Skip Intro, Credits and Ad
3.7 Up Next
3.8 Quality and direct play
3.9 Play on another device and casting
3.10 Sleep timer
3.11 Messages you might see
3.12 Reporting a problem

4 Music

4.1 Browsing music
4.2 Artists and albums
4.3 The music player
4.4 Track details, lyrics and quality
4.5 ReplayGain and gapless playback
4.6 Playlists and M3U files

5 Audiobooks, podcasts and books

5.1 Audiobooks
5.2 Podcasts
5.3 Reading books and comics
5.4 Reading in an e-reader app (OPDS)

6 Photos

6.1 Browsing photos
6.2 The photo viewer
6.3 Albums
6.4 The map
6.5 Faces and people
6.6 Memories

7 Live TV and recordings

7.1 The guide and channels
7.2 Recording
7.3 Watching recordings and skipping ads

8 Downloads

8.1 Downloading in the web app
8.2 Your downloads list
8.3 Downloads on your phone

9 Your account

9.1 The Account page
9.2 Playback quality
9.3 Signed-in devices
9.4 API keys
9.5 Digest email, stats and your data
9.6 Password, two-factor sign-in, languages and scrobbling

10 App-by-app notes

10.1 Android TV, Google TV and Fire TV
10.2 Android phone
10.3 Samsung, LG and Xbox
10.4 Roku
10.5 Which app does what

11 Troubleshooting and FAQ

1 Welcome to OnScreen

1.1 What OnScreen is

OnScreen is a media server. One computer keeps your household's movies, TV shows, anime, music, audiobooks, podcasts, books, comics and photos, and you watch, listen and read on your own devices.

The person who runs the server, **your admin**, decides which libraries you can open and can set limits on your account (for example a content-rating limit or how many streams you can play at once). Everything else in this guide you can do yourself.

Your progress follows you. Start a film on the TV, finish it on your laptop: every app reads the same watch history, resume points, favorites and ratings from the server.

1.2 The apps and where to get them

All the apps talk to the same server. You need your server's address (for example `https://media.example.com` or `192.168.1.10:7070`) and an account. Your admin gives you both.

App	Runs on	How to get it
Web app	Any up-to-date browser on a computer, tablet or phone	Open your server's address in the browser. Nothing to install.
Fire TV	Amazon Fire TV sticks and boxes	The Amazon Appstore.
Android TV / Google TV	TVs and streaming boxes running Android TV or Google TV	Being tested on Google Play; not yet public. Ask your admin.
Android phone	Android 7.0 or later	Being tested on Google Play; not yet public. Ask your admin.
Samsung TV (Tizen)	Samsung smart TVs from 2020 on	Submitted to Samsung's store and waiting for review. Ask your admin.
LG TV (webOS)	LG 4K (UHD) TVs with webOS 6 or later	Submitted to the LG Content Store and waiting for review. Ask your admin.
Xbox	Xbox consoles	Not in the Microsoft Store yet. Ask your admin.
Roku	Roku devices	Not in the Roku store. Ask your admin.
Desktop	Windows and Linux	Installers are published with each OnScreen release. Ask your admin.

Store availability is as of October 2026. The desktop app shows the web app in its own window and adds a high-quality music engine (see 4.5).

1.3 Signing in on the web

1. Open your server's address in your browser.
2. Enter your **Username** and **Password**, then click **Sign In**.
3. If your account uses two-factor sign-in, the next screen asks for an **Authentication code**. Open your authenticator app and enter the 6-digit code, then click **Verify**. Lost your phone? Click **Use a recovery code instead** and enter one of the recovery codes you saved.

Depending on how your server is set up, you might also see:

- **Single sign-on buttons** under **or continue with**. They sign you in with your organisation's account instead of an OnScreen password.
- A **Sign in with …** link for a directory (LDAP) account. Click it to use your directory password; **Use local account** switches back.
- A **Forgot password?** link next to the password label. It only appears when your admin has set up email. Enter your email address and click **Send Reset Link**; the email takes you to **Choose a New Password**.


Accepting an invitation

If your admin sent you an invite link, open it to reach **Set Up Your Account**. Choose a username and a password of at least 8 characters, click **Create Account**, then **Sign In**.


1.4 Signing in on a TV with a code

Typing a password with a remote is slow, so most TV apps let you sign in from your phone or computer instead. This is called **pairing**.

1. The first time you open the TV app, enter your server's address when it asks.
2. On the sign-in screen, choose **Sign in with another device**. The TV shows an address ending in `/pair` and a 6-digit code.
3. On your phone or computer, open that address. Sign in to the web app if it asks.
4. Type the code into **Pairing code**. You can also give the TV a name under **Device name (optional)**, such as "Living Room TV".
5. Check the box headed **You are about to authorise:**, then click **Authorise device**. The TV signs in within a few seconds.




On the TV. The address to open and the code to enter. The code renews itself if it expires.



On your phone or computer. The **Pair a device** page.

> **NOTE**
>
> Only enter a code that is showing on a device you own. Whoever started that code gets access to your account, which is why the page warns you before you click **Authorise device**.

If your server uses single sign-on, pairing is how you sign in on a TV: you sign in on the web page with your organisation's account, and the TV follows. To type a username and password on the TV instead, choose **Use password instead** (LG, Samsung, Xbox, Roku) or simply stay on the **Sign In** screen (Android TV and Fire TV).



Sign in on the LG, Samsung and Xbox apps. Type with the on-screen keyboard, or choose **Sign in with another device**.

1.5 Signing in on your phone

1. Open the OnScreen phone app and type your server's address under **Connect to your server**. You don't need to type `http://` or `https://`. Tap **Continue**.

2. Sign in in one of three ways:
   - Type your **Username** and **Password** and tap **Sign in with password**.
   - If your server uses single sign-on, tap **Sign in with …**. The phone opens your server's sign-in page and signs in by itself when you finish.
   - Tap **Pair this phone** to get a code, then enter it on the `/pair` page from a computer, as in 1.4.
3. If your account uses two-factor sign-in, enter the 6-digit code (or a recovery code) and tap **Verify**.

1.6 Profiles and PINs

A household can share one account and still keep things apart with **managed profiles**. Each profile has its own watch history and progress, and can have its own 4-digit PIN and content-rating limit. Profiles are created by your server's admin.

Switching profile in the web app

1. Click your name at the bottom of the sidebar. The **Switch User** panel lists your profiles.
2. Click a profile and type its PIN under **Enter 4-digit PIN**. OnScreen switches as soon as the fourth digit is in and reloads the Home screen.

- A profile marked **No PIN set** can't be switched to. Ask your admin to give it a PIN.
- From a profile you can't switch straight to another one. Sign out and sign in with your account first.
- Too many wrong PINs locks switching for a while ("too many failed attempts; try again later").
- The TV and phone apps have no profile switcher; they use the account you signed in with.

1.7 Signing out

App	Where
Web	**Sign out** at the bottom of the sidebar.
LG, Samsung, Xbox	Settings ▸ **Sign out** (keeps the server address) or **Forget server** (start over with a new address).
Android TV, Fire TV	Settings ▸ Account ▸ **Log out** or **Change server**.
Android phone	⋮ ▸ Settings ▸ Account ▸ **Sign out** or **Forget server**. Both also remove the downloads saved on the phone.
Roku	There is no sign-out on Roku. Sign the Roku out from another device's Signed-in devices list.

You can sign any device out remotely from **Account ▸ Signed-in devices** in the web app (see 9.3).

2 Finding things


2.1 Getting around the web app

The sidebar on the left is the web app's main menu.

Item	What it opens
Home	Your rows of things to watch and the list of libraries (2.2).
Search	Search across everything you can open (2.5).
Collections	Collections, your playlists, film series and genres (2.6).
History	Everything you've played, newest first (2.8).
My stats	Your own viewing and listening numbers and Year in review (9.5).
Requests	Things you've asked the admin to add. Only shown when your server takes requests and your account may make them (2.9).
Favorites	Titles you've marked with the heart.
Live TV	The TV guide. Only shown when your server has a TV tuner (chapter 7).
Audio	ReplayGain loudness settings for music in this browser (4.5).
Account	Your account settings (chapter 9).

At the bottom of the sidebar are the **notification bell**, a **Dark mode** / **Light mode** switch, your name (which opens **Switch User**) and **Sign out**. Admins see a few more items, such as Settings; this guide doesn't cover them.

2.2 The Home screen



Home in the web app. Rows of titles, with **Customize rows** at the top right.

Home shows rows of titles. A row only appears when it has something in it.

Row	What's in it
Continue Watching TV Shows	Shows you're part-way through, one tile per show, with a progress bar.
Next Up	The next unwatched episode of each show you're watching, such as "S2 · E5 — Title".
Continue Watching Movies	Movies you've started.
Continue Watching	Anything else you've started, such as home videos.
Memories	Photos taken on this day in earlier years (only if you can open a photo library; see 6.6).
Plan to Watch	Titles you've set to Plan to Watch (2.8), until you've watched them.
Collection rows	Collections your admin has chosen to show on everyone's Home screen.
Trending this week	What's being watched most on the server.
Recently Added to *library*	The newest titles in each library. Click the row's title to open the library sorted newest first.


Libraries	A tile for each library you can open. This is how you get into a library.

Removing something from Continue Watching

Point at the tile and click the × that appears (**Remove from Continue Watching**). The title leaves the Continue Watching rows and Next Up until you watch it again. On a TV app, hold `OK` on the tile (the row says **Hold OK for options**); on the phone, press and hold the card.

Choosing and ordering your rows

1. Click **Customize rows** at the top right of Home.
2. In **Hub rows**, use ↑ and ↓ to move a row, and untick **Show** to hide it. The Libraries grid is in the list too.
3. Click **Save**. **Reset to default** puts everything back.




Hub rows. Rows marked "(empty right now)" are hidden until they have something in them.

Your layout is saved to your account, so the Android TV, Fire TV, phone, LG, Samsung and Xbox apps use the same order. It only affects you.

2.3 Browsing a library

Open a library from the **Libraries** row on Home.



A movie library. Sorting, filters and **Surprise me** sit above the grid.

- **Filter…** narrows the titles on the page by name.
- **Sort** with **Title**, **Year**, **Rating** or **Added**. Click the highlighted one again to flip the order.
- **All Genres** picks one genre.
- The watch filter shows **All items**, **Unwatched**, **In progress** or **Watched**.
- **Surprise me** opens a random title that matches your filters.
- **Browse genres** and **Browse years** open lists by genre and by decade or year. Movie libraries add **Browse studios**; TV libraries add **Browse networks**.
- Movie and TV libraries have a **Collections** tab with the film series and collections in that library. Music libraries have **Artists** and **Albums** tabs instead (chapter 4).


On each tile:

- A **check mark** means watched, a **number** counts unwatched episodes, and a bar shows how far you've got.
- The ⋯ menu has **Mark watched** / **Mark unwatched**.
- The + button adds the title to a playlist (movie and TV libraries).

The TV apps offer the same sorting and filters: **Sort** (Title A–Z / Z–A, Recently added, Newest year, Oldest year, Highest rated), **Genre**, the watch filter and **Surprise me**.

2.4 Title pages

Clicking a movie or show opens its page. (Clicking an episode starts it straight away.)




A movie page, with the **Download** menu open.

Buttons on a movie page

- **Play**, or **Resume · 0:23** if you've started it.
- **Play on…** sends it to another of your devices (3.9).
- **Mark watched** / **Mark unwatched**.
- **Download**, if your admin allows downloads (chapter 8).
- **Report a problem** (3.12).

Buttons on a show page

- One play button that knows where you are: **Resume S1 · E2**, **Play S3 · E5**, **Play S1 · E1** or **Watch again**.
- **Mark all watched** and **Mark all unwatched**.
- **Request more seasons**, when seasons are missing and you're allowed to request.
- Season tabs (**Season 1**, **Season 2**, …) and the episode list. Each episode has its own watched toggle.




A show page. The play button picks up where you left off.

What else is on the page

- **Ratings:** the year and content rating, then scores such as ★ (critics), 👥 (audience) and OnScreen (other users on your server). Where your admin has set it up, you'll also see IMDb, Rotten Tomatoes (RT) and Metacritic scores; the IMDb score links to IMDb.
- **Your rating:** click a star to rate the title for yourself. Click your current star (or **clear**) to remove it.
- **Studio or network** names link to a page of everything from that studio (2.7).
- **Chapters**: for movies with chapter pictures, a strip of chapters. Click one to play from there.
- **Cast & Crew**: click a person to see what else they're in.
- **Part of the …**: other films in the same series, with **See all**. Films you don't have show **Not in library**.
- **Status**: your watch status for the title (2.8).
- For anime, links to **AniList** and **MyAnimeList**.

2.5 Search

Click **Search** in the sidebar and start typing.



Search. Tick the boxes to choose what kinds of results you see.

- Results **In your library** can be narrowed with **Movies**, **Shows**, **Episodes** and **Tracks**. Movies and Shows are on to start with; tick Tracks to find music (artists and albums come with it). Your choice is remembered in that browser.
- If some results are hidden by the boxes, a line tells you how many.
- If your account can make requests, a second section, **Ask your admin to add**, lists titles that aren't on the server yet (2.9).

On the LG, Samsung and Xbox apps, Search has an on-screen keyboard and a **Search in:** choice of library. The Android TV and Google TV app also has voice search when the device supports it.

2.6 Collections and film series

The **Collections** page groups things in four sections:

- **Collections** made by your admin. A **Smart** collection fills itself from rules (for example "80s horror") and updates as the libraries change.
- **Playlists** you've made. Click **+ New Playlist** to start one (more in 4.6).
- **Film series** such as the Alien or Toy Story films. A series appears once two of its films are on the server. Its page shows every film in the series; the ones you don't have are greyed out and may have a **Request** button.
- **Genres**.

2.7 People, studios and networks

- **People:** click a face under **Cast & Crew** to see the person's photo, biography and everything of theirs on the server, grouped as **Acting**, **Directing**, **Writing**, **Created** and **Produced**.
- **Studios and networks** NEW: click a studio or network name on a title page, or use **Browse studios** / **Browse networks** in a library. A studio page lists its titles and can be sorted by **Title**, **Year**, **Rating** or **Date added**.

2.8 Favorites, watch status and history

Favorites

In the web app, click the **heart** at the top right of the player (**Add to favorites**). On the TV apps press ♥ **Favorite** (LG, Samsung, Xbox) or the heart (Android TV, Fire TV) on the title's page; on the phone, tap the heart on the title's page. Everything you've favorited is on the **Favorites** page.

Watch status

Movie and show pages have a **Status** list: **Plan to Watch**, **Watching**, **On Hold**, **Completed** or **Dropped** (— **None** — clears it). Titles set to Plan to Watch appear in the Plan to Watch row on Home. The phone app has the same choice as **Watching status**.

Watched and unwatched

OnScreen marks a title watched when you finish it. To change it yourself, use **Mark watched** / **Mark unwatched** on the title page, a tile's ⋯ menu, or the check mark at the top of the player. Shows and seasons have **Mark all watched** / **Mark all unwatched**. Marking something unwatched also clears its resume point.

History

History (**Watch History**) lists what you've played, with the app you used, how long and when. Entries can't be deleted.

2.9 Asking for something new

If your server takes requests, you can ask your admin to get a movie or show. This works in the web app (and as **Discover** on the LG, Samsung and Xbox apps). The Android apps don't take requests.

1. Search for the title. Under **Ask your admin to add**, click **Request for admin to acquire** for a movie, or **Request** for a show.
2. For a show, choose the seasons in **Choose seasons** (or tick **All seasons**) and click the request button.
3. Follow progress on the **Requests** page under **My Requests**. You can **Cancel** a request while it's pending, and **Watch** it once it's available.

Your account may have a limit, shown as for example "2 movie requests left this week". Over the limit, a request still goes in but needs the admin's approval. If your server is connected to download tools, the **Upcoming** tab shows a calendar of expected releases.

2.10 Notifications

The bell at the bottom of the sidebar shows a count of unread notifications. Click it to see them; click one to open it, or **Mark all read**. You're told when:

- a library scan adds new titles (**Library scan complete**) or a new title arrives;
- a request of yours is submitted, approved, declined, fails to download, or becomes available (including **Season N now available**);
- a problem you reported is resolved or closed.

3 Watching

3.1 Starting and resuming

- **Movies:** press **Play** on the movie's page, or **Resume · time** to carry on.
- **Episodes** start as soon as you open them, from where you left off.
- **Shows:** the show page's play button resumes or starts the right episode.

To start a movie from the beginning in the web app, use the **Chapters** strip, drag the seek bar back, or mark the movie unwatched. On the Android TV, Fire TV, LG, Samsung and Xbox apps the title page has **Play from Beginning**.

Your position is saved as you watch, on every app. If you watch on another device while the web player is paused, the position and the Resume button update to match.

3.2 The web player



The web player. Pointing at the seek bar shows a preview picture of that moment.

Move the mouse to show the controls; they hide again after a few seconds. Click the picture to pause or play.

Top bar

Back (to the show page for an episode), the title (and episode number and chapter), a check mark (**Mark watched**) and a heart (**Add to favorites**).

Bottom bar

Control	What it does
Seek bar	Drag or click to jump. Ticks mark chapters; pointing at it shows a preview picture when the server has made them.
Volume and time	Mute, volume slider, and the time played / total.
⏮ −10s ▶ +10s ⏭	Previous episode, back 10 seconds, play/pause, forward 10 seconds, next episode. Movies have only the middle three.
Ch 1/19	The chapter menu, with pictures when available. Only shown when the file has chapters.
+	Add to playlist.
Subtitles	Shows the subtitle language, or Off (3.5).
Audio track	Only when there's more than one (3.4).
Play on another device	See 3.9.
Report a problem	The flag icon (3.12).
Cast to TV	Chromecast, in Chrome and Edge, when the file can be cast (3.9).
Version	Only when the title has more than one version (3.3).
Quality	See 3.8.
Sleep timer	The moon icon (3.10).
Fullscreen	Fill the screen.

Keyboard shortcuts

Key	Action
`Space` or `K`	Play / pause
`←` `→`	Back / forward 10 seconds
`↑` `↓`	Volume up / down
`F`	Fullscreen on / off
`M`	Mute on / off
`S`	Skip the intro, credits or ad that's playing

`Esc`	Close the Quality, Version, Subtitles, Audio or Sleep timer menu

On a phone or tablet

- Double-tap the left or right third of the picture to go back or forward 10 seconds; double-tap the middle to pause.
- Swipe sideways to seek, up or down on the right half for volume, and on the left half for brightness.
- Swipe down to leave the player.
- Quality, Subtitles and Audio open as panels from the bottom of the screen. Going fullscreen turns the screen sideways.

The TV apps work with the remote's arrows and `OK`. Their buttons are listed in chapter 10.

3.3 Versions, editions and multi-part movies NEW

A title can have more than one version, for example a Director's Cut and the theatrical cut, or a 4K and a 1080p copy. When it does:

- the web player has a **Version** menu, and the movie page shows which version is chosen;
- the TV apps have a **Version:** button on the title page;
- the phone shows **Version** choices on the title page.


Versions are named after the edition (such as "Director's Cut") or described, such as "4K · HDR10 · HEVC · MKV". A version marked **DAMAGED** (or "⚠ file may be damaged" on the page) failed the server's file check and may not play properly.

Multi-part movies (a film stored as two or more files, such as CD1 and CD2) play as one movie on every app, with one seek bar and one running time. The version menu shows them as "· 2 parts". They can't be cast.

Multi-episode files (one file holding two episodes) show as "E1–E2" or "S1 · E1–E2", count as both episodes, and are followed by the next episode after the range (E3).

3.4 Audio tracks

When a file has more than one audio track (another language, or a commentary), the web player shows an **Audio track** button. Each track is listed by its name and language, with the channel count. OnScreen picks your preferred audio language automatically if one is set (9.6).




Audio track menu in the web player.

Switching to a track that isn't the file's default may restart the stream for a moment while the server prepares it. On the TV apps open **Audio** from the player's button row (press ↓) or press the **yellow** button (LG, Samsung) or Y (Xbox).

3.5 Subtitles

Choosing subtitles

Click the **Subtitles** button. The list starts with **Off**, then the file's tracks (marked *forced* or *SDH* where that applies), then subtitles downloaded for the title (marked · *online*). If you've set a preferred subtitle language, OnScreen picks it for you.



The Subtitles menu with a track chosen: size, color, background, outline and sync. (Admins also see a **Server** row for saving timing for everyone.)

Size, color and outline

With a text subtitle chosen, the menu adds **Size** (Small, Medium, Large), **Color** (White, Yellow, Black, Red), **Background** (None, Translucent, Opaque) and **Outline** (None, Light, Heavy). These are remembered in that browser. The phone app has the same choices under **Subtitle style**.

Subtitles out of sync

Use the **Sync** row: **−1s** and **−0.1** show subtitles earlier, **+0.1** and **+1s** later, and **Reset** puts them back. This lasts for the current viewing only. If a file is always out of step, use **Report a problem ▸ Subtitles problem**: an admin can fix the timing on the server, and the fix then applies in every app.

Finding subtitles online

If your server is connected to OpenSubtitles, the menu has **Search online…**. Choose a language, click **Search**, and pick a result; it downloads and is turned on. The Android TV and Google TV app (**Find more online…**), the phone app and the LG, Samsung and Xbox apps have the same search. Fire TV and Roku don't.

Picture-based subtitles (Blu-ray and DVD) NEW

Subtitles copied from Blu-rays and DVDs (PGS and VobSub) are pictures, not text, so a player can't simply draw them over the video. In v2.6, when the server is preparing the stream for you (rather than sending the file as it is), these tracks appear in the Subtitles menu like any other, in one of two ways:

- **"· text"**: the track has already been converted to text. Choosing it works like any other subtitle, with no restart.
- **"(burned in)"**: choosing it restarts the video at the same moment with the subtitles drawn into the picture. You'll see the loading circle briefly. Size, color and Sync don't apply to burned-in subtitles.

Choose **Off** (or a text track) to remove burned-in subtitles; the video restarts without them. Switching audio track or quality keeps the burned-in subtitles on. If a track can't be burned in (for example on a multi-part movie), a message says so and your video carries on.

This works on the web, Android TV, Fire TV, phone, LG, Samsung, Xbox and Roku apps. On Roku, picture-based subtitles are always burned in.

In the web player the menu may also offer **Convert … to text (OCR)**, which turns a picture-based track into text so it can be styled and synced. It takes a few minutes; the text track is turned on when it's ready. If OCR isn't installed on the server, it says so.

3.6 Skip Intro, Credits and Ad

When an episode's intro or end credits are marked on the server, a button appears while they play: **Skip Intro** → or **Skip Credits** →. Click it, or press `S`.

- During an intro, **Always skip intros** turns on automatic skipping in that browser. Each intro is skipped once, so you can seek back into it to watch it.
- Recordings from live TV can show **Skip Ad** → during a detected ad break, with **Always skip ads** (7.3).
- On TV apps, the skip button is selected for you: press `OK` (LG, Samsung and Xbox show **Press OK to skip Intro**). `Back` dismisses it. On Roku press `★`.

3.7 Up Next

Near the end of an episode, an **Up Next** card shows the next episode.

App	What happens
Web	Appears in the last minute. **Up Next · 10s** counts down, then plays the next episode. **Play** → goes now; **Cancel** stops the countdown. Only within the same season.
LG, Samsung, Xbox	Appears 25 seconds before the end with a 10-second countdown: ▶ **Play now** or **Cancel**. Pausing holds the countdown.
Android TV, Fire TV	Appears about 25 seconds before the end with a 10-second countdown: **Play Now** or **Cancel**.
Phone	Appears in the last 25 seconds with **Play now** and **Dismiss**; no countdown.
Roku	Appears 25 seconds before the end; `OK` plays now, and the next episode starts when this one ends.


Music tracks and audiobook chapters simply follow on, with no card.

3.8 Quality and direct play

When your device can play a file exactly as it is stored, OnScreen sends it unchanged. This is called **direct play** and gives the best picture. When it can't (an unusual format, a slow connection, or a limit on your account), the server converts the video as you watch.

The Quality menu (web)

The **Quality** button offers **Auto (Direct Play)**, **4K (2160p)**, **1080p**, **720p**, **480p** and **360p**. Choices higher than the file itself are left out, and Auto (Direct Play) is left out when the file can't be played as it is. Pick a lower setting if playback keeps pausing to load.



Quality menu for a 1080p file.

Playback quality for your account NEW

To set limits for every device at once, use **Account** ▸ **Playback quality** in the web app, or **Settings** ▸ **Playback quality** in the Android TV, Fire TV, phone, LG, Samsung and Xbox apps. Details are in 9.2. The

TV apps have no quality menu in the player; this setting is how you choose quality there.


> **NOTE**
> Your admin can also set a bitrate limit for watching from outside your home network. Anything above it is converted too, so playback away from home may look softer than at home.

3.9 Play on another device and casting

Play on…

Send what you're watching in the web app to one of your other devices, such as your TV:

1. Open OnScreen on the TV first, so the server has seen it recently.
2. In the web app, click **Play on…** on the movie page, or the **Play on another device** icon in the player.
3. Pick the device. The web player pauses and the TV carries on from the same moment.



Play on. When no other device has been seen recently, the menu says so.

The list shows your own devices that have played something in the last 30 days. The LG, Samsung, Xbox, Android TV and Fire TV apps can receive. The phone and Roku can't.

Chromecast

- **Web:** in Chrome or Edge, a **Cast to TV** button appears for files that can play directly on a Chromecast (MP4, M4V, MOV or WebM with H.264 or HEVC video). Casting starts where you are and pauses the browser.
- **Phone:** the player has a Cast button. It sends the original file (H.264 or HEVC video in MP4, M4V, MOV or WebM, and common music formats). Subtitles aren't sent.

> **NOTE**
> Casting sends the original file, so a video above your playback quality limit can't be cast. Multi-part movies can't be cast either.

3.10 Sleep timer

The moon icon in the web player stops playback after **15 minutes**, **30 minutes**, **45 minutes**, **1 hour** or at the **End of episode**. **Off** cancels it. The music player has the same timer, with **End of track** (or **End of chapter** for audiobooks). The phone app has a sleep timer too.

3.11 Messages you might see

Message	What it means and what to do
Too many streams	Your account may only play a set number of streams at once, and that many are already playing on other devices. Stop one, then try again. The limit is set by your admin; since v2.6 it counts every stream, not only converted ones.
Watch limit reached	Your account has viewing hours or a daily time limit. Try again in the allowed hours or tomorrow.
Playback stopped	The admin stopped your stream, sometimes with a reason.
This file appears to be damaged	The server's file check found broken parts. Use **Report a problem** so the admin can replace it.
Dolby Vision is not supported	This copy uses a kind of Dolby Vision that OnScreen can't play. Another version (HDR10 or SDR) will play normally; ask your admin.
This content is restricted by your profile's content rating	It's above your account's rating limit.
Playback keeps stalling	The web player restarted three times and gave up. The file may be damaged or the server busy; try a lower quality or report it.
Downloads are turned off on this server.	Your admin hasn't enabled downloads.

3.12 Reporting a problem

If something's wrong with a title, tell your admin from inside OnScreen. Click **Report a problem** (the flag icon in the player, or the button on the title page), choose what's wrong and add a note if you like:

- **Video won't play or looks wrong**
- **Audio problem**
- **Subtitles problem**
- **Wrong movie/show**
- **Something else**

Click **Send report**. The admin is notified, and you get a notification when the report is resolved. The same option is on the Android TV, Fire TV, phone, LG, Samsung, Xbox and Roku apps.


4 Music

4.1 Browsing music

A music library has two tabs, **Artists** and **Albums**. Sort artists by **Title**, **Year**, **Rating** or **Added**, and albums by **Title**, **Artist**, **Year** or **Added**. **All Genres**, **Browse genres** and **Browse years** narrow the albums. Music videos appear on a shelf at the top of the Artists tab.

To find a particular song, use Search with **Tracks** ticked.

4.2 Artists and albums



An artist page with **Instant mix**.


An **artist page** has these sections:

- **Albums**, newest first.
- **Appears on** NEW: albums by others that the artist features on, with the matching tracks.
- **Similar artists** NEW: artists on your server with a similar sound.
- **Music Videos**.

Instant mix NEW plays a mix of the artist and similar music on your server, replacing what's playing. It's also on album pages and in a track's details. The TV apps have Instant mix too, plus **Play All** and **Shuffle** on artist pages.

An **album page** shows the year, track count and length, with ▶ **Play** and **Instant mix**. Albums on more than one disc are split under **Disc 1**, **Disc 2** and so on. Click a track number to play from that track.

4.3 The music player



Playing an album. The player bar stays at the bottom of the screen while you browse.

Music plays in a bar at the bottom of the web app, so you can keep browsing. From left to right:


- × (**Close player**) stops and clears what's playing.
- The cover, title and artist (links to the artist and album).
- **Shuffle**, **Previous**, **Play/Pause**, **Next** and **Repeat** (off → all → one). Previous restarts the track if you're more than 3 seconds in.
- The seek bar, then the sleep timer, **RG** (ReplayGain, 4.5) and volume.

On the phone and Android TV, music keeps playing after you leave the app, with controls on the lock screen and in the notification area (phone) or the system's media controls (TV).

4.4 Track details, lyrics and quality

Each track on an album page has a quality badge: **Hi-Res** (lossless, better than CD) or **Lossless**. Point at a track and click ⓘ (**File details**) to see:

- the format, bit depth, sample rate, channels and bitrate;
- ReplayGain values, and whether they came from the file's tags or the server measured them;
- **Lyrics**, when the server has them;
- MusicBrainz links for the recording, release and artist.




File details for a 24-bit, 192 kHz FLAC track.

The phone app shows lyrics from a **Lyrics** button in the player.

4.5 ReplayGain and gapless playback

ReplayGain evens out loudness so one track doesn't blast after a quiet one. It's off unless you turn it on, and it's set per browser or device.

- Click **RG** in the music player, or open **Audio** in the sidebar.
- Choose **Off**, **Track** (each track at the same loudness) or **Album** (whole albums at the same loudness, keeping the differences between their tracks).
- **Preamp** raises or lowers everything by up to 15 dB. The gain never pushes a track past its peak, so it doesn't distort.



ReplayGain in the music player.

Tracks without ReplayGain tags play at their own level, unless your server has measured them (shown as **Analyzed** in the track's details). The phone app has the same choice in **Settings ▸ ReplayGain**.

Gapless playback: the web player loads the next track before the current one ends, so live albums and continuous mixes play without a gap. The phone plays queues gaplessly too.

The OnScreen desktop app adds a native audio engine for bit-perfect playback, with its options on the **Audio** page. The web music player always plays the original files.

4.6 Playlists and M3U files

Making a playlist

- On the **Collections** page, click **+ New Playlist**.
- Add a movie or episode with the **+** button (**Add to playlist**) in the player or on a library tile, then choose a playlist or **+ New Playlist**.
- Your playlists are listed under **Playlists** on the Collections page; open one to edit it or remove items.

Importing and exporting M3U playlists NEW

Import and export live on the **My Playlists** page: click **Playlists** in the sidebar.

1. Click **Import playlist** and choose an `.m3u` or `.m3u8` file (up to 1 MB) exported from another player.
2. Give it a name (or leave the file name) and click **Import**.
3. OnScreen matches each line to something on the server by path, folder and file name, or artist and title, and says how many it matched. Lines it couldn't match are listed. Web addresses in the file are never opened.

To export, open a playlist there and click **Export .m3u8**. Tick **Full server paths** if the other player needs the files' full paths on the server.

The My Playlists page also makes **smart playlists** (tick **Smart playlist (rule-based)**), which fill themselves from rules such as type, genre, year and rating.

5 Audiobooks, podcasts and books


5.1 Audiobooks

Audiobook libraries are organised by author and series. A book's page shows its chapters and a play button:

- ▶ **Play** for a new book, or ▶ **Resume · ch 3 · 12:40** to carry on. You resume at the start of the chapter you were in.
- **Start over** goes back to chapter 1.
- Click a chapter to play from it.

Audiobooks play in the music player bar, which adds two buttons:

- **Speed** (shows e.g. **1×**): **0.75×** to **3×**. The voice keeps its normal pitch, and the speed is saved for that book on the server, so it follows you to other devices.
- **Add bookmark**: saves the current moment, with an optional note.



Playback speed for an audiobook, next to the bookmark and sleep timer buttons.

Bookmarks are listed on the book's page under **Bookmarks**. Click a bookmark's time to play from there, or use **Add note** / **Edit note** and **Delete**. The sleep timer can stop at the **End of chapter**.


Other apps: the phone has speed, bookmarks and a sleep timer. Android TV, Fire TV, LG, Samsung and Xbox have speed (on LG, Samsung and Xbox press ↓ during an audiobook). Roku plays audiobooks at normal speed only.

5.2 Podcasts

Podcast libraries list shows; open one to see its **Episodes**, newest first, with the date and length. Click an episode to play it. Your admin chooses which podcasts the server follows and how many episodes it keeps; new episodes download automatically. To suggest a podcast, ask your admin.

5.3 Reading books and comics

OnScreen reads EPUB books and CBZ and CBR comics in the web app and the phone app. Open a book to start reading.



Reading a comic. Reading direction and page layout are at the top right; the slider at the bottom jumps to a page.

Turning pages

- Click ‹ or › at the sides, or drag the slider at the bottom.
- Keys: `←` `→`, `PgUp` `PgDn` or `Space` to turn pages, `Home` and `End` to jump to the first or last page.
- EPUB books show **Section 3 of 144** at the top; comics show **Page 1 of 36**.

Comic options

- **Reading direction: Left → Right**, **Right → Left** (manga) or **Vertical (webtoon)**. Manga usually opens right-to-left by itself. The arrow keys follow the direction.
- **Layout: Single page**, **Two-page spread** or **Long scroll**.

Picking up where you left off NEW

Your page is saved to the server as you read. If you've read further on another device, the web reader offers **You're further along on …** with **Continue from page 40 on …** or **Stay here**. This works for EPUB, CBZ and CBR in the web app; the phone app syncs comic pages (CBZ and CBR).

The TV apps don't read books ("Book reading isn't available on TV. Open this book in the web or phone app.").

5.4 Reading in an e-reader app (OPDS) NEW

E-reader apps that support OPDS catalogs, such as KOReader, Moon+ Reader, Panels, Chunky and Thorium, can browse, search and download your books.

1. **Make a key.** In the web app go to **Account** ▸ **API keys** ▸ **Create API key**. Name it after the device (for example "Kobo"), set **Access** to **Read-only (GET requests only)**, and click **Create key**. Copy the key (it starts with `osk_`); it's shown only once.
2. **Add the catalog in the app.** The address is shown on the Account page under **Read your books in an e-reader app** (with a **Copy** button). It's your server's address followed by `/opds/`.
3. **Sign in with the key.** Enter anything as the user name (your username is fine) and paste the key as the **password**.

- **KOReader:** Search ▸ OPDS catalog ▸ +.
- **Moon+ Reader:** Net Library ▸ Add.
- **Panels / Chunky:** add an OPDS source with the address, then the user name and key.

The catalog shows **Recently added**, one entry per book library you can open, and search. You see exactly the books you'd see in the web app.

> **NOTE**
> Your account password doesn't work here, on purpose. If a device is lost, revoke its key in **Account** ▸ **API keys**. The catalog needs downloads to be allowed on the server; if they're not, the Account page says so.

6 Photos

6.1 Browsing photos

A photo library opens as a grid sorted by **Taken** (newest first), which works as a timeline. You can also sort by **Added** or **Title**. Links at the top open the **Map**, **Albums**, **People** and **Memories**.

Camera RAW files NEW (CR2, CR3, NEF, ARW, DNG, RAF, ORF, RW2 and PEF) show like any other photo. When you shoot RAW + JPEG, the pair appears as one photo, and **Download original** gives you the RAW file.

Select lets you tick photos and **Add to album…**.

6.2 The photo viewer

Key or button	Action
`←` `→` **or swipe**	Previous / next photo
`+` `-`**, wheel, pinch**	Zoom in / out (double-click zooms to 2×); `0` resets. Drag to move around.
`Space`	Start or stop a slideshow (4 seconds a photo)
`I`	Info: when it was taken, camera, lens, exposure, size, location and people
`F`	Show the faces found in the photo
`Esc`	Stop the slideshow, close the info panel, then close the viewer

The top bar also has **Download original** (when downloads are allowed), **Add to album…** and, inside an album, **Remove from this album**. The location in the info panel links to OpenStreetMap.

6.3 Albums

Albums are private: only you see yours. Open **Albums** (**Photo albums**) and click **+ New album**, or add photos from the viewer or with **Select**. Each album's ⋯ menu has **Rename** and **Delete**; deleting an album leaves the photos in the library.

6.4 The map

Photo map places photos that have GPS coordinates. Click a spot to see its photos in a side panel; zoom in to split busy spots. The phone app has a map too, under the library's **Photo timeline / map** button, with **Timeline** and **Geotagged** tabs.

6.5 Faces and people NEW

If your admin has turned on face detection, OnScreen finds faces in your photos. It doesn't recognise who they are: you name them, and OnScreen gathers each person's photos.

- In the viewer, press F and click a face box. Type a name under **Who is this?** and click **Save**, or **Not a face**. Typing an existing name adds the face to that person.
- The **People** page lists named people and a **Who is this?** section of unnamed faces to name.
- A person's page can suggest more faces (**Is this …?**); answer **Yes** or **No**.

Naming is available unless your account has viewing restrictions. If there are no faces yet, face detection may be off; ask your admin.

6.6 Memories NEW

Memories shows photos taken on this day in earlier years (or this week, when a year has none that day). Each group has a **Play** button that starts a slideshow. The same memories appear as a row on Home.

On the TV apps, photos open in a viewer: ← → move between photos and OK starts a slideshow.

7 Live TV and recordings

If your server has a TV tuner, the web app shows **Live TV** in the sidebar, and the LG, Samsung, Xbox and Android TV / Google TV apps show **Live TV** and **Recordings**. Fire TV, the phone and Roku don't have live TV.

7.1 The guide and channels

- **Guide** shows four hours at a time. ← **Earlier**, **Now** and **Later** → move through the day; a red line marks the current time.
- Click a programme for its details, then **Watch channel** or **Record**.
- **Channels** shows a tile per channel with what's on now and next. Click one to watch.
- A channel starts muted; unmute with the volume control. ↑ **Prev** and ↓ **Next** (or the `P` and `N` keys) change channel, and **All channels** goes back.

On the LG, Samsung and Xbox apps, change channel with `▲` `▼` or `CH ▲▼`; `Back` returns to the channel list.

7.2 Recording

1. In the guide, click the programme.
2. Click **Record**. "Recording scheduled" confirms it.

The **Recordings** page has tabs for **Upcoming**, **Recording now**, **Completed** and **Rules**. You can **Cancel** a recording that's scheduled or in progress. Statuses include **Scheduled**, **Recording now**, **Done** and **Failed**.

7.3 Watching recordings and skipping ads

Click **Watch** on a completed recording to open it in the normal player. If the server has found the ad breaks NEW, a **Skip Ad** → button appears during each break; click it or press `S`. Turn on **Always skip ads** to skip them automatically in that browser.

8 Downloads

Downloads let you keep a copy of a movie or episode to watch without a connection. They only appear when your admin allows downloads. Otherwise the button is hidden, or you'll see "Downloads are turned off on this server."

8.1 Downloading in the web app


1. On a movie or episode page, click **Download**.
2. Choose a size:
   - **Original**: the file exactly as it's stored ("the file as it is"). It starts straight away.
   - A smaller copy NEW: **1080p · 8 Mbps**, **720p · 4 Mbps**, **720p · 2 Mbps** or **480p · 1 Mbps**. These are MP4 files the server prepares first.
3. For a smaller copy, the button shows **Waiting…** and then **Preparing 40%**. The download starts by itself when the copy is ready. You can leave the page; the server keeps working.

- Sizes above your account's limit are greyed out and marked "above your limit".
- If a file can't be converted, the menu says **No smaller copies for this file**.
- "You already have downloads being prepared" means wait for one of them to finish before asking for another.

8.2 Your downloads list

Account ▸ **Downloads** lists the smaller copies you've asked for, with their size and status: **Waiting to start**, **Preparing · N%**, **Ready**, **Failed** or **Expired**.

- **Download** saves a ready copy again; **Cancel** stops one being prepared; **Remove** deletes it from the list.
- The server keeps each copy for a while after you last downloaded it (a week unless your admin changed it), then removes it to save space. An expired copy can simply be asked for again.



Account ▸ **Downloads** before anything has been downloaded.

8.3 Downloads on your phone

The phone app keeps downloads inside the app for watching offline.

1. On a movie, episode, track or book page, tap **Download**.
2. For video, choose **Original** or a smaller copy (the same sizes as the web). If nothing smaller is offered, the original downloads straight away.
3. The button shows the progress (**Queued**, **Preparing N%**, then a percentage) and finally **Downloaded**. Tap **Downloaded** to remove it.

- All your downloads are under ⋮ ▸ **Downloads**, with the space they use. Tap one to play it; the trash icon removes it.
- If the phone has no connection when you open the app, it goes straight to Downloads and shows **Offline — showing your downloaded items**.
- **Settings** ▸ **Download only over Wi-Fi** (on by default) waits for Wi-Fi before downloading.

> **NOTE**
> Signing out of the phone app, or choosing **Forget server**, deletes every download on the phone.

The TV apps don't download.

9 Your account


9.1 The Account page

Click **Account** in the sidebar. The page has these sections:

Section	What it's for
My stats	A link to your statistics and Year in review (9.5).
Email me a digest	A weekly or monthly email of what's new (9.5).
Playback quality	Quality limits for all your devices (9.2).
Languages	Preferred audio and subtitle language (9.6).
Scrobbling	Link Last.fm, ListenBrainz or Trakt (9.6).
Password	Change your password (9.6).
Two-factor authentication	A code from an authenticator app at sign-in (9.6).
Signed-in devices	See and sign out your devices (9.3).
Downloads	Smaller copies you've asked for (8.2).
API keys	Keys for e-reader apps and home automation (9.4).
Your data	Download a copy of everything the server keeps about you (9.5).

9.2 Playback quality NEW

These limits apply to your account on every device, at home and away. Anything above them is converted by the server before it plays.



Account ▸ Playback quality. The defaults set no limit.

Setting	Choices
Maximum resolution	Original, 4K, 1080p, 720p, 480p
Maximum video bitrate	No limit, 40, 20, 12, 8, 4, 2 or 1 Mbps
Maximum audio bitrate	Original, 320, 256, 192, 128 or 96 kbps
Video format when converting	Automatic, H.264 (plays everywhere), HEVC (smaller, where supported)


Click **Save**. The same four settings are in the Android TV, Fire TV, phone, LG, Samsung and Xbox apps' Settings, and they all change the one setting on your account.

> **TIP**
> Lower the limits if you often watch over a slow connection or want to save mobile data. Leave them at **Original / No limit** for the best picture at home. The audio limit also applies to music in the apps that check with the server first; the web music player always plays the original files.

9.3 Signed-in devices NEW

This lists the browsers and apps signed in to your account, with when each was last used. The one you're using is marked **This device**.

- **Sign out** next to a device signs it out at once.
- **Sign out everywhere else** signs out every device except this browser.




Signed-in devices. "Last used" updates about every hour while a device is in use.

> **TIP**
> Lost a phone, or sold a TV? Sign it out here. If someone may know your password, change it too (9.6).

9.4 API keys NEW

An API key lets an e-reader app, Home Assistant, Kometa or a script use OnScreen as you, without your password.

1. Click **Create API key**.
2. Give it a **Name** you'll recognise.
3. Choose **Access**: **Full access**, or **Read-only (GET requests only)** for anything that only reads (e-readers, sensors).
4. Choose when it **Expires**: **Never**, **30 days**, **90 days** or **1 year**.
5. Click **Create key**, then **Copy**. The key is shown only once.



Create API key.

A key can do what you can, with your library access and limits, but it can never sign in, change your password or two-factor settings, or manage keys and devices. **Revoke** a key to stop it working at once. The section also shows your OPDS catalog address (5.4).


9.5 Digest email, stats and your data

Email me a digest NEW


Choose **Off**, **Weekly** or **Monthly** for an email of what was added, what you're in the middle of and your numbers for the period. It needs an email address on your account and email set up on the server; the section tells you if either is missing.

My stats and Year in review NEW

My stats shows what you've watched, listened to and read. Only you can see it. Pick **30 days**, **90 days**, **12 months**, **All time** or a year. You'll see hours watched and listened, plays, titles finished, books read and your longest streak, then activity by month, a chart of when you play, top genres, top movies, shows, artists and albums, and your devices. Plays show up a few minutes after they finish.



My stats.



Year in review.

Your 2026 in review → opens a summary of the year: total hours, top titles, **Where it started**, highlights such as your busiest day and longest streak, and your year month by month. **Print** prints it.

Your data NEW

Download my data saves a ZIP of what the server keeps about your account: profile and preferences, watch history and progress, ratings, favorites, playlists, reading positions, requests and signed-in devices. Passwords, two-factor secrets and keys are never included.

9.6 Password, two-factor sign-in, languages and scrobbling NEW

These are on the Account page too. Before v2.6 they were only in the admin's Settings.

Changing your password

1. Under **Password**, enter your **Current password**, then the **New password** twice. It must be at least 12 characters.
2. Click **Change password**.

Your other devices are signed out and need the new password; this browser stays signed in. After five wrong current passwords within 15 minutes, the form refuses further tries for a while. If you sign in through your organisation's sign-in (single sign-on) or LDAP, there's no OnScreen password to change and the section says so. Forgotten your password? Use **Forgot password?** on the sign-in page if your server sends email, or ask your admin.

Two-factor sign-in

1. Under **Two-factor authentication**, click **Enable 2FA**.
2. Scan the QR code with an authenticator app (Google Authenticator, Authy, 1Password and others), or type in the secret shown under it.
3. Enter the 6-digit code the app shows.

4. Save the recovery codes: **Copy** or **Download** them, then click **I've saved them**. Each recovery code works once, in place of a code from the app.

To turn it off, enter a current code or a recovery code and click **Disable 2FA**. The phone app has the same setting (**Settings** ▸ **Security**). Two-factor sign-in protects password sign-in, so it isn't offered to accounts that use single sign-on or LDAP.

Languages

Choose a **Preferred Audio Language** and a **Preferred Subtitle Language**, then click **Save Preferences**. They're saved to your account, so every app uses them; the TV apps also have them in their own Settings. **Use the series poster for episodes** shows a show's poster instead of an episode still on Continue Watching, History and Search.

Scrobbling

Click **Link your accounts** → under **Scrobbling** to send what you play to other services:

- **ListenBrainz**: paste your user token and click **Link account**.
- **Last.fm** and **Trakt** (if your server is set up for them): click **Connect Last.fm** or **Connect Trakt**, approve OnScreen on that site, then come back. The page finishes linking on its own.

The phone, Android TV and Fire TV apps can link ListenBrainz too (**Settings** ▸ **Scrobbling**).

Things only your admin can change

Setting	Who changes it
Profile PINs, content-rating limit	Your admin. The TV apps show your rating limit as "Managed by the server administrator".
Display name, email	Your admin.
Deleting your account	Your admin.

Light and dark theme

The web app follows your computer's light or dark setting. Click **Dark mode** / **Light mode** at the bottom of the sidebar to choose.

10 App-by-app notes

10.1 Android TV, Google TV and Fire TV

One app, in two editions. The Google TV / Android TV edition adds live TV and online subtitle search; the Fire TV edition leaves those out.

Getting around

- Home has the same rows as the web, a row per library, and a **Browse** row with **Favorites**, **History**, **Live TV** and **Recordings** (Google TV edition) and **Settings**.
- In a library, the search orb opens **Sort and filter**. The remote's `Menu` button opens sorting too.
- Search has voice input when your device supports it.
- Hold `OK` on an episode for **Mark as watched**; on a Continue Watching card for **Remove from Continue Watching**.

Remote in the player

Button	Action
`←` / `→`	Back 10 s / forward 30 s (when the controls are hidden)
`OK`	Show the controls; then press the selected button
`Play/Pause`	Play / pause
`Fast-forward` / `Rewind`	Forward 30 s / back 10 s
`Next`	Next episode, track or chapter
`Back`	Close a Skip or Up Next card, or leave the player

The player's buttons open **Audio**, **Subtitles** and **Chapters** (and **Playback speed** for audiobooks). Pick a version with **Version:** on the title page, and set quality in **Settings ▸ Playback quality**.

Settings

- **Language Preferences**: preferred audio and subtitle language (saved to your account).
- **Match frame rate** (on by default) switches the TV to the film's frame rate so motion is smooth; the screen goes dark for a moment. On Fire TV, also turn on the Fire TV's own Match Original Frame Rate setting. On Android 12 and later, the TV's Match content frame rate setting decides.
- **Playback quality** (9.2).
- **Scrobbling** (ListenBrainz) and **Account**.


Surround sound (Dolby, DTS, TrueHD/Atmos), 4K and HDR are used automatically when your TV or receiver supports them. Music and audiobooks keep playing after you press Home. This app doesn't download or cast.

10.2 Android phone


- **Home:** the ⋮ menu has **Favorites**, **History**, **Collections**, **Playlists**, **Downloads** and **Settings**. Pull down to refresh.
- **Libraries:** filter chips **All**, **Unwatched**, **In progress**, **Watched**, and a shuffle button for **Surprise me**. Press and hold a card to mark it watched or unwatched.
- **Player:** buttons for audio, Cast, subtitles, subtitle style, chapters, lyrics, sleep timer and picture-in-picture (plus speed and bookmarks for audiobooks). Video shrinks into a small window when you press Home (Android 12 and later).
- **Mobile data: Warn before streaming on cellular** (on by default) asks **Stream over cellular?** before video plays on mobile data.
- **Downloads and offline viewing:** see 8.3.
- **Books:** CBZ and CBR comics (swipe to turn pages; right-to-left and top-to-bottom supported) and EPUB. Comic pages sync with your other devices.
- **Photos:** a swipe viewer with **Photo info**, and a map.
- **Settings: Playback quality**, **ReplayGain**, **Two-factor authentication**, ListenBrainz scrobbling and Wi-Fi-only downloads.

10.3 Samsung, LG and Xbox


These three apps share the same screens. The top bar has **Home**, **Libraries**, **Search**, **Favorites**, **History**, and when your server offers them **Discover** (requests), **Live TV** and **Recordings**, then **Settings**.



Home on the LG, Samsung and Xbox apps. Hold OK on a Continue Watching tile for options.



A title page: Resume, Play from Beginning, Mark watched, Favorite and Report a problem.



Settings: Playback (languages) and Playback quality.

Remote in the player

Button	Action
`OK` **or** `Play/Pause`	Play / pause
`←` / `→`	Back / forward 10 seconds (presses add up; the jump happens a moment after the last one)
`Rewind` / `Fast-forward`	Back / forward 30 seconds (previous / next track for music)
`CH ▲▼`	Previous / next chapter, track or episode
Red / green	Previous / next chapter
Yellow / blue	Audio / subtitles menu
`↑` `↓`	Show the controls; `↓` again reaches **Audio**, **Subtitles** and **Chapters**
`Stop`	Pause
`Back`	Close a menu, cancel Up Next, dismiss Skip, or leave the player

- **Samsung:** the slim Smart Remote has no colour, rewind or fast-forward buttons; use `↓` for the menus and `CH ▲▼` for chapters. `Back` on Home closes the app.
- **LG:** the Magic Remote pointer also shows on-screen buttons (−10s, play, +10s, previous, next) and lets you click the seek bar. `Back` on Home asks **Exit OnScreen?**.
- **Xbox controller:** `A` = OK (hold for options), `B` = Back, `X` = subtitles, `Y` = audio, `LB` / `RB` = previous/next chapter or track, `LT` / `RT` = back/forward 30 seconds. The on-screen hints use TV-remote names. The Xbox app first asks for your server address (**Add your OnScreen server**), then shows the TV app your server provides.

These apps have no quality menu in the player (use **Settings** ▸ **Playback quality**) and no book reader. There is no profile switcher; to change account, use **Settings** ▸ **Sign out**.

10.4 Roku

- **Getting started:** enter the server address including `http://` or `https://`, then sign in or choose **Sign in with another device**.
- **Home** rows: Continue Watching, Next Up, Plan to Watch, Trending and Recently Added. Press `↑` from the top row for **Libraries**, **Favorites**, **History** and **Search**.
- **In the player:** `★` opens the audio menu, `★` again the subtitles menu, and skips an intro or credits when the skip button shows. `Back` stops playback and returns to Home. Seeking uses the Roku's own controls.

> **NOTE**
> Roku limits:
>
> - Only subtitles inside the video file are offered; downloaded or online subtitles and subtitle styling aren't. Picture-based subtitles are burned in (3.5).
> - No Settings screen: no Playback quality, no sign-out, no Favorite button (add favorites from another app).
> - No live TV, recordings, requests, book reader or audiobook speed.
> - The Roku app hasn't yet been tested on a Roku device for this release.

10.5 Which app does what

Feature	Web	Android TV / Fire TV	Phone	LG / Samsung / Xbox	Roku
Pair with a code	(approves)	Yes	Yes	Yes	Yes
Profile switching	Yes	No	No	No	No
Playback quality setting	Account	Settings	Settings	Settings	No
Quality menu in player	Yes	No	No	No	No
Version picker	Player	Title page	Title page	Title page	Title page
Online subtitle search	Yes	Google TV only	Yes	Yes	No
Subtitle sync	Yes	No	No	No	No
Downloads	Yes	No	Yes, offline	No	No
Casting / Play on	Both	Receives	Chromecast	Receives	No
Book reader	Yes	No	Yes	No	No
Live TV	Yes	Google TV only	No	Yes	No
Requests	Yes	No	No	Discover	No

11 Troubleshooting and FAQ

The video keeps stopping to load (buffering).

- Choose a lower setting in the web player's **Quality** menu, or lower Playback quality for your account (it's the only quality control in the TV apps).
- Watching away from home? Your admin may have a lower limit for viewers outside the home network.
- If the web player says "Playback keeps stalling", the file may be damaged or the server busy. Report it.

A title won't play.

- Read the message (3.11). "Too many streams" means stop playback on another device first.
- "Dolby Vision is not supported" or "This file appears to be damaged": ask your admin for another copy, using **Report a problem**.
- Try another app or a browser. If it fails everywhere, report it.

Subtitles are out of sync.

In the web player, use the **Sync** row in the Subtitles menu (3.5). It only lasts for that viewing, so also send **Report a problem ▸ Subtitles problem**: an admin can save the right timing on the server for every app. Or try a different track, or **Search online…** for another one.

I can't see the subtitles I chose.

- Picture-based (Blu-ray/DVD) tracks marked "(burned in)" take a moment to appear, because the video restarts.
- On Roku, only subtitles inside the video file are offered.
- On Fire TV, the Subtitles button only appears when the title has a subtitle track.

I was signed out.

- Someone may have signed the device out from **Signed-in devices**, or your admin may have. Sign in again. If you didn't do it and don't know who did, ask your admin to change your password.
- A device that hasn't been used for a long time has to sign in again.

The TV pairing code doesn't work.

- Make sure you're signed in on the `/pair` page with the right account, and you typed all 6 digits.
- Codes expire. The TV shows a new one by itself (Android TV says "The previous code expired — enter the NEW code shown above"); type the new code.
- If the TV says it can't reach the server, check the server address on the TV (**Change server**).
- Still stuck? Choose **Use password instead**, or use the Sign In screen.

Something is missing from my library.

Your admin decides which libraries you can open, and may have a content-rating limit or label restrictions on your account. If you can make requests, search for the title and ask for it (2.9).

I can't find the Download button.

Downloads are off on your server. Ask your admin. The same setting controls the e-reader catalog and photo **Download original**.

Can I watch on two devices at once?

Usually yes, up to your account's stream limit. Opening the same title on a second device takes over from the first.

Can I cast to a Chromecast?

From the web app in Chrome or Edge, or from the phone app, when the file can play directly on the Chromecast and is within your Playback quality limit (3.9). Otherwise use **Play on…** to send it to an OnScreen TV app.

My music is louder or quieter from track to track.

Turn on ReplayGain (4.5). It's set separately in each browser and on the phone.

Where are the settings for my profile's PIN or rating limit?

Your admin manages those.

How do I change my password?

On the Account page, under **Password** (9.6). If you've forgotten it, use **Forgot password?** on the sign-in page if it's there, or ask your admin.