

Commodore 264 Series Emulator User Guide

C16, C116 AND PLUS/4 STARTUP OPTIONS AND
COMMAND CONSOLE REFERENCE

IGNACIO CEA FORNIÉS

Contents

CONTENTS 1

/O 6

/P 6

/H 6

/F 7

/K 7

/C 7

/L 8

/A 8

/D 8

/S 9

/I 9

/R 9

/G 10

/N 10

/W 10

/B 11

/M 12

/H 13

/F 13

/K 13

/C 14

/L	14
/A	14
/D	15
/S	15
/I	15
/R	16
/P	16
/G	16
/N	17
/W	17
/B	17
/M	19
3.1 STANDARD FRAMEWORK COMMANDS	20
HELP	20
AUTHOR	20
STATUS	20
PC	21
REGISTERS	21
CHANGereg	21
STACK	22
CPUSTATUS	22
CPUSSTATUS	22
CPUSTATE	23
CPUINFO	23
MEMORY	23
MEMORYDUMP	24
MEMORYSTR	24
SETMEMORY	24
MEMORYANALYSIS	25
STOP	25
RUN	26
SETPC	26
NEXT	26
NEXTSTACK	27
SHOWNEXT	27
INST	27
BREAKS	28
SETBREAK	28

REMOVEBREAK	28
REMOVEBREAKS	29
SPEED	29
LOADBIN	29
SAVEBIN	30
DEBUGON	30
DEBUGOFF	30
IDEBUGON	31
IDEBUGOFF	31
RESTART	31
DEVICES	32
PERIPHERALS	32
PERCOMMAND	32
ASSIGNJOY	33
CLOCKFACTOR	33
SOUNDON	33
SOUNDOFF	34
INTERRUPTS	34
INTSET	34
CHIPS	35
CRTON	35
CRTOFF	35
DATASETTE	36
GRIDON	36
GRIDOFF	36
PICTURE	37
SETHOOK	37
REMOVEHOOK	37
HOOKS	38
HOOKSHELP	38
CMOVEPARAMS	38

3.2 INHERITED COMMODORE COMMANDS 39

VICII	39
VICIIEVENTS	39
SID	40
SIDW	40
VICI	40
TED	41
TEDEVENTS	41
VIA	41
CIA	42

3.3 C264-SPECIFIC COMMANDS 42

SCREENDUMP	42
ATTRIBUTEDUMP	42
BITMAPDUMP	43
CHARSDRAW	43

3.4 LOCAL-CONSOLE-ONLY COMMANDS 43

LOADPRG	43
---------------	----

LOADBINARY	44
LOADBLOCKS	44
DECOMPILE	44
POSSIBLEPERS	45
CONNECTPER.....	45
DISCONNECTPERS	46
LOADPERDATA	46
EMPTYPERDATA.....	46
SAVEPERDATA	47
CLEARPERDATA.....	47
 APPENDIX A. COMMAND AVAILABILITY SUMMARY	 48
 APPENDIX B. SOURCE-OF-TRUTH MAINTENANCE RULE	 48
 ILLUSTRATIONS	 49
 EQUATIONS	 50

Foreword

This guide describes the startup and command interfaces implemented by the two Commodore 264-series executables in EMULATORS: C264Emulator (without a local command console) and C264EmulatorC (with a local command console). It covers the Commodore 16, Commodore 116 and Commodore Plus/4 models and is based on both executable entry points, the C264::C264Emulator inheritance chain, LocalConsole, and the complete C264 -> COMMODORE -> StandardCommandBuilder responsibility chain.

Command and parameter names are shown exactly as accepted by the current code. Startup options use /XVALUE with no space between the one-letter option and its value. Command names are matched as written by the builders; use uppercase names for reliable operation. Positional command parameters are separated by spaces; examples use paths without embedded spaces.

The non-console executable does not expose an interactive prompt. When started with /o it creates a remote communication system using the same C264 series, Commodore and standard command builders. Commands marked Local console only are intercepted by LocalConsole and therefore cannot be sent to the non-console executable.

1. Startup Parameters: Version Without a Local Console

Executable: C264Emulator.exe. It accepts the framework and C264-specific options below, plus /o and the communication-port option. Option letters are case-sensitive because the command-line parser stores the character exactly as supplied.

/o

Meaning: Controls creation of the remote command communication system.

General form:

```
/o[YES|NO]
```

- YES or an empty value: open remote communications.
- NO (and any other non-YES non-empty value): do not open it.
- Omitted: remote communications disabled.

Examples:

```
C264Emulator.exe /o  
C264Emulator.exe /oYES /p60000
```

Consequence: When enabled, remote clients can execute C264 series, Commodore and standard builder commands. LocalConsole-only commands remain unavailable.

/p

Meaning: Selects the TCP listening port used when /o enables remote communications.

General form:

```
/pPORT
```

- PORT: decimal port number; default 60000 when /p is omitted.

Examples:

```
C264Emulator.exe /o /p60000  
C264Emulator.exe /o /p61000
```

Consequence: The communication system attempts to listen on the converted port.

Important: Current-code collision: the inherited Emulator also interprets the same /p value as a comma-separated peripheral ID list. A normal port value can therefore trigger an unintended peripheral connection attempt. Avoid combining startup peripheral attachment with the non-console executable until the option letters are separated in code.

/h

Meaning: Prints the executable help and prevents the emulation from starting.

General form:

```
/h
```

- No value.

Examples:

```
C264Emulator.exe /h
```

Consequence: Initialization returns failure after printing the help; the current main program therefore exits with code 1.

/f

Meaning: Loads a binary file whose header contains the destination address.

General form:

```
/fFILE
```

- FILE: path to the header-addressed binary file; attach it directly to /f.

Examples:

```
C264Emulator.exe /fprogram.prg
C264Emulator.exe /fgames\demo.prg /a$080d
```

Consequence: The file is loaded before execution. An unreadable or invalid file aborts initialization.

/k

Meaning: Loads a block-structured memory file.

General form:

```
/kFILE
```

- FILE: path to a block file understood by the framework.

Examples:

```
C264Emulator.exe /ksnapshot.blocks
```

Consequence: Every encoded block is placed at its stored address. A load error aborts initialization.

/c

Meaning: Parses, assembles and loads an assembler source file.

General form:

```
/cFILE
```

- FILE: assembler source path.

Examples:

```
C264Emulator.exe /cstartup.asm /s
```

Consequence: The assembled bytes are installed before the main loop. Syntax or load errors are logged and initialization stops.

/l

Meaning: Selects the framework diagnostic level.

General form:

```
/lLEVEL
```

- 0: no diagnostics.
- 1: errors (default).
- 2: dump at exit.
- 3: errors and warnings.
- 4: all regular diagnostics.
- 5: internal trace diagnostics.

Examples:

```
C264Emulator.exe /l0  
C264Emulator.exe /l4
```

Consequence: Higher values produce progressively more diagnostic output and may reduce performance.

/a

Meaning: Overrides the address at which execution begins.

General form:

```
/aADDRESS
```

- ADDRESS: C264 series address in the framework number syntax, for example decimal or hexadecimal with \$.

Examples:

```
C264Emulator.exe /a$080d  
C264Emulator.exe /fprogram.prg /a2061
```

Consequence: A non-zero, valid address replaces the normal reset/program entry address.

/d

Meaning: Creates startup stop points at one or more addresses.

General form:

```
/dADDRESS1,ADDRESS2,...
```

- ADDRESSn: comma-separated address. Each entry accepts the framework number syntax.

Examples:

```
C264Emulator.exe /d$080d  
C264Emulator.exe /d$080d,$ffd2 /s
```

Consequence: Execution stops when the CPU reaches any listed address, allowing later inspection or continuation.

/s

Meaning: Controls whether the emulated computer starts stopped.

General form:

```
/s[YES|NO]
```

- YES or an empty value: start stopped.
- NO (and any non-YES non-empty value): start running.
- Omitted: start running.

Examples:

```
C264Emulator.exe /s  
C264Emulator.exe /sNO
```

Consequence: When enabled, the machine is initialized but the CPU does not run until a RUN/NEXT command or the equivalent UI action is issued.

/i

Meaning: Selects the C264-series language and KERNAL-ROM variant.

General form:

```
/iLANG
```

- ENG: English (default).
- FRA: French.
- SWE: Swedish.
- HUN: Hungarian.

Examples:

```
C264Emulator.exe /iENG  
C264Emulator.exe /iFRA
```

Consequence: The selected language is used when loading the KERNAL ROM for the selected C16, C116 or Plus/4 model.

/r

Meaning: Controls sound at startup.

General form:

```
/r[YES|NO]
```

- YES or an empty value: sound enabled.
- NO (and any non-YES non-empty value): sound disabled.
- Omitted: sound enabled.

Examples:

```
C264Emulator.exe /r  
C264Emulator.exe /rNO
```

Consequence: The audio subsystem begins enabled or disabled. The state can later be changed with SOUNDON/SOUNDOFF.

/g

Meaning: Controls the CRT post-processing effect at startup.

General form:

```
/g[YES|NO]
```

- YES or an empty value: CRT effect enabled.
- NO (and any non-YES non-empty value): disabled.
- Omitted: disabled.

Examples:

```
C264Emulator.exe /g  
C264Emulator.exe /gNO
```

Consequence: The screen starts with or without CRT emulation. CRTON and CRTOFF can change it later.

/n

Meaning: Selects NTSC timing instead of PAL.

General form:

```
/n
```

- No value; presence selects NTSC.

Examples:

```
C264Emulator.exe /n
```

Consequence: The emulator creates an NTSC C264 series. Without /n it creates the PAL model.

/w

Meaning: Selects the startup RAM configuration for the requested C264-series model.

General form:

```
/w[CONF]
```

- C16 or C116, 0 or omitted: 16 KiB configuration (default).
- C16 or C116, 1: 32 KiB configuration.
- C16 or C116, 2 or any greater numeric value: 64 KiB configuration; values above 2 are clamped to 2.
- Plus/4: whenever /w is present, the emulator forces configuration 2 (64 KiB with the internal 3+1 ROM available), regardless of the numeric value supplied.

Examples:

```
C264Emulator.exe /mC16 /w0  
C264Emulator.exe /mC16 /w1  
C264Emulator.exe /mC116 /w2  
C264Emulator.exe /mCP4 /w2
```

Consequence: The selected RAM map is installed before machine initialization. For reliable Plus/4 startup, specify /w2: when /w is omitted, the current configuration selector returns 0 even though Plus/4 memory accepts only mode 2 and logs other modes as invalid.

/b

Meaning: Draws the C264 series screen grid/border using the requested color.

General form:

```
/bCOLOR
```

- COLOR: numeric color value. If /b is present without a valid number, conversion yields 0.

Examples:

```
C264Emulator.exe /b1  
C264Emulator.exe /b14 /s
```

Consequence: The screen grid is enabled at startup with the converted color value.

/m

Meaning: Selects the member of the Commodore 264 series to emulate.

General form:

/mMACHINE

- C16: Commodore 16 implementation (default).
- C116: accepted as Commodore 116, but the current factory constructs the same Commodore16_116 implementation and C16/116 screen as C16.
- CP4: Commodore Plus/4 with 64 KiB RAM, ACIA, a second 6529B interface and the internal 3+1 ROM images.
- Any other value: falls back to C16.

Examples:

```
C264Emulator.exe /mC16
C264Emulator.exe /mC116 /w2
C264Emulator.exe /mCP4 /w2
```

Consequence: The model choice determines the computer class, ROM set, memory implementation, screen label and model-specific chips created before initialization.

2. Startup Parameters: Version With a Local Console

Executable: C264EmulatorC.exe. Its main program delegates the complete command line to C264::C264Emulator, so all inherited framework options and C264-specific options are active even though the short main-level help banner only advertises /h. It has no /o listener option; commands are entered in its local console.

/h

Meaning: Prints the executable help and prevents the emulation from starting.

General form:

```
/h
```

- No value.

Examples:

```
C264Emulator.exe /h
```

Consequence: Initialization returns failure after printing the help; the current main program therefore exits with code 1.

/f

Meaning: Loads a binary file whose header contains the destination address.

General form:

```
/fFILE
```

- FILE: path to the header-addressed binary file; attach it directly to /f.

Examples:

```
C264Emulator.exe /fprogram.prg  
C264Emulator.exe /fgames\demo.prg /a$080d
```

Consequence: The file is loaded before execution. An unreadable or invalid file aborts initialization.

/k

Meaning: Loads a block-structured memory file.

General form:

```
/kFILE
```

- FILE: path to a block file understood by the framework.

Examples:

```
C264Emulator.exe /ksnapshot.blocks
```

Consequence: Every encoded block is placed at its stored address. A load error aborts initialization.

/c

Meaning: Parses, assembles and loads an assembler source file.

General form:

```
/cFILE
```

- FILE: assembler source path.

Examples:

```
C264Emulator.exe /cstartup.asm /s
```

Consequence: The assembled bytes are installed before the main loop. Syntax or load errors are logged and initialization stops.

/l

Meaning: Selects the framework diagnostic level.

General form:

```
/lLEVEL
```

- 0: no diagnostics.
- 1: errors (default).
- 2: dump at exit.
- 3: errors and warnings.
- 4: all regular diagnostics.
- 5: internal trace diagnostics.

Examples:

```
C264Emulator.exe /l0  
C264Emulator.exe /l4
```

Consequence: Higher values produce progressively more diagnostic output and may reduce performance.

/a

Meaning: Overrides the address at which execution begins.

General form:

```
/aADDRESS
```

- ADDRESS: C264 series address in the framework number syntax, for example decimal or hexadecimal with \$.

Examples:

```
C264Emulator.exe /a$080d  
C264Emulator.exe /fprogram.prg /a2061
```

Consequence: A non-zero, valid address replaces the normal reset/program entry address.

/d

Meaning: Creates startup stop points at one or more addresses.

General form:

```
/dADDRESS1,ADDRESS2,...
```

- ADDRESSn: comma-separated address. Each entry accepts the framework number syntax.

Examples:

```
C264Emulator.exe /d$080d  
C264Emulator.exe /d$080d,$ffd2 /s
```

Consequence: Execution stops when the CPU reaches any listed address, allowing later inspection or continuation.

/s

Meaning: Controls whether the emulated computer starts stopped.

General form:

```
/s[YES|NO]
```

- YES or an empty value: start stopped.
- NO (and any non-YES non-empty value): start running.
- Omitted: start running.

Examples:

```
C264Emulator.exe /s  
C264Emulator.exe /sNO
```

Consequence: When enabled, the machine is initialized but the CPU does not run until a RUN/NEXT command or the equivalent UI action is issued.

/i

Meaning: Selects the C264-series language and KERNAL-ROM variant.

General form:

```
/iLANG
```

- ENG: English (default).
- FRA: French.
- SWE: Swedish.
- HUN: Hungarian.

Examples:

```
C264EmulatorC.exe /iENG  
C264EmulatorC.exe /iFRA
```

Consequence: The selected language is used when loading the KERNAL ROM for the selected C16, C116 or Plus/4 model.

/r

Meaning: Controls sound at startup.

General form:

```
/r[YES|NO]
```

- YES or an empty value: sound enabled.
- NO (and any non-YES non-empty value): sound disabled.
- Omitted: sound enabled.

Examples:

```
C264Emulator.exe /r  
C264Emulator.exe /rNO
```

Consequence: The audio subsystem begins enabled or disabled. The state can later be changed with SOUNDON/SOUNDOFF.

/p

Meaning: Connects framework peripherals during initialization.

General form:

```
/pID1, ID2, ...
```

- 10: typewriter input.
- 100: 1530 datasette.
- 101: injected/fast 1530 datasette.
- 203: cartridge.
- 205 or 206: serial printer instances.
- 215, 216, 217 or 218: 1541 disk-drive instances.

Examples:

```
C264EmulatorC.exe /p100  
C264EmulatorC.exe /p100,101
```

Consequence: Each recognized ID is built and connected before execution; unsupported IDs are not connected.

Important: Use POSSIBLEPERS in the local console to obtain the IDs supported by the current build.

/g

Meaning: Controls the CRT post-processing effect at startup.

General form:

```
/g[YES|NO]
```

- YES or an empty value: CRT effect enabled.
- NO (and any non-YES non-empty value): disabled.
- Omitted: disabled.

Examples:

```
C264Emulator.exe /g
```

```
C264Emulator.exe /gNO
```

Consequence: The screen starts with or without CRT emulation. CRTON and CRTOFF can change it later.

/n

Meaning: Selects NTSC timing instead of PAL.

General form:

```
/n
```

- No value; presence selects NTSC.

Examples:

```
C264Emulator.exe /n
```

Consequence: The emulator creates an NTSC C264 series. Without /n it creates the PAL model.

/w

Meaning: Selects the startup RAM configuration for the requested C264-series model.

General form:

```
/w[CONF]
```

- C16 or C116, 0 or omitted: 16 KiB configuration (default).
- C16 or C116, 1: 32 KiB configuration.
- C16 or C116, 2 or any greater numeric value: 64 KiB configuration; values above 2 are clamped to 2.
- Plus/4: whenever /w is present, the emulator forces configuration 2 (64 KiB with the internal 3+1 ROM available), regardless of the numeric value supplied.

Examples:

```
C264EmulatorC.exe /mC16 /w0  
C264EmulatorC.exe /mC16 /w1  
C264EmulatorC.exe /mC116 /w2  
C264EmulatorC.exe /mCP4 /w2
```

Consequence: The selected RAM map is installed before machine initialization. For reliable Plus/4 startup, specify /w2: when /w is omitted, the current configuration selector returns 0 even though Plus/4 memory accepts only mode 2 and logs other modes as invalid.

/b

Meaning: Draws the C264 series screen grid/border using the requested color.

General form:

```
/bCOLOR
```

- COLOR: numeric color value. If /b is present without a valid number, conversion yields 0.

Examples:

```
C264Emulator.exe /b1
```

Consequence: The screen grid is enabled at startup with the converted color value.

IGNACIO CEA FORNIÉS

/m

Meaning: Selects the member of the Commodore 264 series to emulate.

General form:

/mMACHINE

- C16: Commodore 16 implementation (default).
- C116: accepted as Commodore 116, but the current factory constructs the same Commodore16_116 implementation and C16/116 screen as C16.
- CP4: Commodore Plus/4 with 64 KiB RAM, ACIA, a second 6529B interface and the internal 3+1 ROM images.
- Any other value: falls back to C16.

Examples:

```
C264EmulatorC.exe /mC16
C264EmulatorC.exe /mC116 /w2
C264EmulatorC.exe /mCP4 /w2
```

Consequence: The model choice determines the computer class, ROM set, memory implementation, screen label and model-specific chips created before initialization.

3. Command Console Reference

The local console checks its eleven emulator-level commands first. All remaining text is delegated through C264::CommandBuilder, then COMMODORE::CommandBuilder, and finally MCHEmul::StandardCommandBuilder. The remote /o channel in C264Emulator.exe uses only that three-builder chain. The availability line in each entry makes this boundary explicit.

3.1 Standard Framework Commands

HELP

Availability: Local console and remote /o channel.

Accepted aliases: CHELP.

Meaning: Displays the C264 series console help assembled from the C264 series, Commodore, local-console and standard help files.

General syntax:

```
HELP
```

Parameters:

- No parameters.

Examples:

```
HELP
```

Result and consequences: Displays the C264 series console help assembled from the C264 series, Commodore, local-console and standard help files.

AUTHOR

Availability: Local console and remote /o channel.

Accepted aliases: CAUTHOR.

Meaning: Returns framework author information.

General syntax:

```
AUTHOR
```

Parameters:

- No parameters.

Examples:

```
AUTHOR
```

Result and consequences: Returns framework author information.

STATUS

Availability: Local console and remote /o channel.

Accepted aliases: CSTATUS.

Meaning: Shows the 7501 status register.

General syntax:

```
STATUS
```

Parameters:

- No parameters.

Examples:

```
STATUS
```

Result and consequences: Shows the 7501 status register.

PC

Availability: Local console and remote /o channel.

Accepted aliases: CPC.

Meaning: Shows the current program counter.

General syntax:

```
PC
```

Parameters:

- No parameters.

Examples:

```
PC
```

Result and consequences: Shows the current program counter.

REGISTERS

Availability: Local console and remote /o channel.

Accepted aliases: CREGISTERS.

Meaning: Shows all CPU registers.

General syntax:

```
REGISTERS
```

Parameters:

- No parameters.

Examples:

```
REGISTERS
```

Result and consequences: Shows all CPU registers.

CHANGereg

Availability: Local console and remote /o channel.

Accepted aliases: CCHANGereg.

Meaning: Changes one CPU internal register.

General syntax:

```
CHANGereg REGNAME VALUE
```

Parameters:

- REGNAME: registered 7501 register name.
- VALUE: new decimal, z-prefixed binary, o-prefixed octal or \$-prefixed hexadecimal value.

Examples:

```
CHANGereg A $41
```

Result and consequences: The register changes only if it exists and accepts the supplied byte width; otherwise an error is returned.

STACK

Availability: Local console and remote /o channel.

Accepted aliases: CSTACK.

Meaning: Shows stack state.

General syntax:

```
STACK [ALL]
```

Parameters:

- ALL: optional; includes stack contents in addition to basic state.

Examples:

```
STACK  
STACK ALL
```

Result and consequences: Shows stack state.

CPUSTATUS

Availability: Local console and remote /o channel.

Accepted aliases: CCPUSTATUS.

Meaning: Shows registers, status, program counter and stack.

General syntax:

```
CPUSTATUS
```

Parameters:

- No parameters.

Examples:

```
CPUSTATUS
```

Result and consequences: Shows registers, status, program counter and stack.

CPUSSTATUS

Availability: Local console and remote /o channel.

Accepted aliases: CCPUSSTATUS.

Meaning: Shows the compact CPU status without stack detail.

General syntax:

```
CPUSSTATUS
```

Parameters:

- No parameters.

Examples:

```
CPUSSTATUS
```

Result and consequences: Shows the compact CPU status without stack detail.

CPUSTATE

Availability: Local console and remote /o channel.

Accepted aliases: CCPUSTATE.

Meaning: Shows the CPU execution state and state-specific data.

General syntax:

```
CPUSTATE
```

Parameters:

- No parameters.

Examples:

```
CPUSTATE
```

Result and consequences: Shows the CPU execution state and state-specific data.

CPUINFO

Availability: Local console and remote /o channel.

Accepted aliases: CCPUINFO.

Meaning: Returns the complete CPU information structure.

General syntax:

```
CPUINFO
```

Parameters:

- No parameters.

Examples:

```
CPUINFO
```

Result and consequences: Returns the complete CPU information structure.

MEMORY

Availability: Local console and remote /o channel.

Accepted aliases: CMEMORY.

Meaning: Reads the active CPU-visible memory range.

General syntax:


```
MEMORY INITIAL [FINAL]
```

Parameters:

- INITIAL: first address.
- FINAL: optional last address; with no final address only the initial location is reported.

Examples:

```
MEMORY $0400  
MEMORY $0400 $0427
```

Result and consequences: Reads the active CPU-visible memory range.

MEMORYDUMP

Availability: Local console and remote /o channel.

Accepted aliases: CMEMORYDUMP.

Meaning: Dumps every memory view between two addresses, including inactive RAM/ROM views.

General syntax:

```
MEMORYDUMP INITIAL FINAL
```

Parameters:

- INITIAL: first address.
- FINAL: last address.

Examples:

```
MEMORYDUMP $a000 $a03f
```

Result and consequences: Dumps every memory view between two addresses, including inactive RAM/ROM views.

MEMORYSTR

Availability: Local console and remote /o channel.

Accepted aliases: CMEMORYSTR.

Meaning: Shows the configured memory structure.

General syntax:

```
MEMORYSTR [ALL]
```

Parameters:

- ALL: optional; includes inactive regions. Without it only active regions are shown.

Examples:

```
MEMORYSTR  
MEMORYSTR ALL
```

Result and consequences: Shows the configured memory structure.

SETMEMORY

Availability: Local console and remote /o channel.

Accepted aliases: CSETMEMORY.

Meaning: Writes a value to one address or repeatedly across a range.

General syntax:

```
SETMEMORY INITIAL [FINAL] VALUE
```

Parameters:

- INITIAL: first address.
- FINAL: optional last address.
- VALUE: byte sequence in framework numeric syntax; multi-byte values advance by their own length.

Examples:

```
SETMEMORY $0400 $41  
SETMEMORY $0400 $0427 $20
```

Result and consequences: The active memory view is modified immediately; unsafe writes can corrupt state or crash the emulated program.

MEMORYANALYSIS

Availability: Local console and remote /o channel.

Accepted aliases: CMEMORYANALYSIS.

Meaning: Analyzes the current memory configuration.

General syntax:

```
MEMORYANALYSIS
```

Parameters:

- No parameters.

Examples:

```
MEMORYANALYSIS
```

Result and consequences: Analyzes the current memory configuration.

STOP

Availability: Local console and remote /o channel.

Accepted aliases: CSTOP.

Meaning: Stops CPU execution.

General syntax:

```
STOP
```

Parameters:

- No parameters.

Examples:

```
STOP
```

Result and consequences: Stops CPU execution.

RUN

Availability: Local console and remote /o channel.

Accepted aliases: R, CRUN.

Meaning: Starts or resumes CPU execution; alias R.

General syntax:

```
RUN [ADDRESS]
```

Parameters:

- ADDRESS: optional new program counter before running.

Examples:

```
RUN  
R $080d
```

Result and consequences: The CPU resumes immediately, optionally after changing PC.

SETPC

Availability: Local console and remote /o channel.

Accepted aliases: CSETPC.

Meaning: Sets the program counter without starting execution.

General syntax:

```
SETPC ADDRESS
```

Parameters:

- ADDRESS: new CPU address.

Examples:

```
SETPC $080d
```

Result and consequences: Subsequent execution continues from the new address; an unsafe address can break the program.

NEXT

Availability: Local console and remote /o channel.

Accepted aliases: N, CNEXT.

Meaning: Executes the next instruction; alias N.

General syntax:

```
NEXT
```

Parameters:

- No parameters.

Examples:

```
NEXT  
N
```

Result and consequences: Executes the next instruction; alias N.

NEXTSTACK

Availability: Local console and remote /o channel.

Accepted aliases: NS, CNEXTSTACK.

Meaning: Runs until the stack pointer returns to its initial value; alias NS.

General syntax:

```
NEXTSTACK
```

Parameters:

- No parameters.

Examples:

```
NS
```

Result and consequences: Useful for stepping over a routine, although behavior depends on the routine's stack discipline.

SHOWNEXT

Availability: Local console and remote /o channel.

Accepted aliases: SN, CSHOWNEXT.

Meaning: Disassembles upcoming instruction(s); alias SN.

General syntax:

```
SHOWNEXT [NUMBER]
```

Parameters:

- NUMBER: optional count; one instruction by default.

Examples:

```
SHOWNEXT  
SN 8
```

Result and consequences: Disassembles upcoming instruction(s); alias SN.

INST

Availability: Local console and remote /o channel.

Accepted aliases: CINST.

Meaning: Shows the last instruction executed.

General syntax:

```
INST
```

Parameters:

- No parameters.

Examples:

```
INST
```

Result and consequences: Shows the last instruction executed.

BREAKS

Availability: Local console and remote /o channel.

Accepted aliases: CBREAKS.

Meaning: Lists all stop-point addresses.

General syntax:

```
BREAKS
```

Parameters:

- No parameters.

Examples:

```
BREAKS
```

Result and consequences: Lists all stop-point addresses.

SETBREAK

Availability: Local console and remote /o channel.

Accepted aliases: CSETBREAK.

Meaning: Adds one or more breakpoints.

General syntax:

```
SETBREAK ADDRESS1 [ADDRESS2 ...]
```

Parameters:

- ADDRESSn: one or more addresses in framework numeric syntax.

Examples:

```
SETBREAK $080d $ffd2
```

Result and consequences: Adds one or more breakpoints.

REMOVEBREAK

Availability: Local console and remote /o channel.

Accepted aliases: CREMOVEBREAK.

Meaning: Removes selected breakpoints.

General syntax:

```
REMOVEBREAK ADDRESS1 [ADDRESS2 ...]
```

Parameters:

- ADDRESSn: one or more existing breakpoint addresses.

Examples:

```
REMOVEBREAK $ffd2
```

Result and consequences: Removes selected breakpoints.

REMOVEBREAKS

Availability: Local console and remote /o channel.

Accepted aliases: CREMOVEBREAKS.

Meaning: Removes every breakpoint.

General syntax:

```
REMOVEBREAKS
```

Parameters:

- No parameters.

Examples:

```
REMOVEBREAKS
```

Result and consequences: Removes every breakpoint.

SPEED

Availability: Local console and remote /o channel.

Accepted aliases: CSPEED.

Meaning: Shows measured CPU and screen-I/O execution speed.

General syntax:

```
SPEED
```

Parameters:

- No parameters.

Examples:

```
SPEED
```

Result and consequences: Shows measured CPU and screen-I/O execution speed.

LOADBIN

Availability: Local console and remote /o channel.

Accepted aliases: CLOADBIN.

Meaning: Loads a raw binary file at an explicit address.

General syntax:

```
LOADBIN FILE ADDRESS
```

Parameters:

- FILE: raw binary path.
- ADDRESS: first destination address.

Examples:

```
LOADBIN charset.bin $2000
```

Result and consequences: Bytes are copied into memory without an embedded load-address header.

SAVEBIN

Availability: Local console and remote /o channel.

Accepted aliases: CSAVEBIN.

Meaning: Saves a memory range as raw binary.

General syntax:

```
SAVEBIN FILE SIZE ADDRESS
```

Parameters:

- FILE: output path.
- SIZE: byte count.
- ADDRESS: first source address.

Examples:

```
SAVEBIN screen.bin 1000 $0400
```

Result and consequences: Saves a memory range as raw binary.

DEBUGON

Availability: Local console and remote /o channel.

Accepted aliases: CACTIVATEDEEPDEBUG.

Meaning: Enables deep execution debugging.

General syntax:

```
DEBUGON FILE CPU [APPEND] [FILTERS...]
```

Parameters:

- FILE: output log.
- CPU: YES includes CPU execution; NO omits it.
- APPEND: optional YES appends, NO overwrites (default).
- D:START-END or ALLDIR: address filter.
- C:IDs or ALLCHIP: chip filter.
- I:IDs or ALLIO: device filter.
- M:IDs or ALLMEM: memory filter.

Examples:

```
DEBUGON c264.log YES NO D:$0800-$0fff ALLCHIP ALLIO ALLMEM
```

Result and consequences: Tracing begins with the selected sources and can substantially slow emulation. It cannot coexist with interrupt-only debugging.

DEBUGOFF

Availability: Local console and remote /o channel.

Accepted aliases: CDESACTIVATEDEEPDEBUG.

Meaning: Stops deep execution debugging.

General syntax:

```
DEBUGOFF
```

Parameters:

- No parameters.

Examples:

```
DEBUGOFF
```

Result and consequences: Stops deep execution debugging.

IDEBUGON

Availability: Local console and remote /o channel.

Accepted aliases: CIDEBUGON.

Meaning: Enables interrupt-only debugging.

General syntax:

```
IDEBUGON FILE [APPEND]
```

Parameters:

- FILE: output log.
- APPEND: optional YES appends; NO overwrites (default).

Examples:

```
IDEBUGON interrupts.log NO
```

Result and consequences: Interrupt tracing begins and cannot coexist with deep debugging.

IDEBUGOFF

Availability: Local console and remote /o channel.

Accepted aliases: CIDEBUGOFF.

Meaning: Stops interrupt-only debugging.

General syntax:

```
IDEBUGOFF
```

Parameters:

- No parameters.

Examples:

```
IDEBUGOFF
```

Result and consequences: Stops interrupt-only debugging.

RESTART

Availability: Local console and remote /o channel.

Accepted aliases: CRESTART.

Meaning: Requests a restart and exits the current computer loop so it can be rebuilt.

General syntax:

```
RESTART STOPPED [LEVEL]
```

Parameters:

- STOPPED: YES restarts stopped; NO restarts running.

- LEVEL: optional 0 CPU-only/mild restart (default), 1 computer restart preserving memory, greater than 1 full restart.

Examples:

```
RESTART YES 0
RESTART NO 2
```

Result and consequences: Requests a restart and exits the current computer loop so it can be rebuilt.

DEVICES

Availability: Local console and remote /o channel.

Accepted aliases: CDEVICES.

Meaning: Shows all or selected I/O devices.

General syntax:

```
DEVICES [ID1 ID2 ...]
```

Parameters:

- IDn: optional device identifiers; with none, all devices are returned.

Examples:

```
DEVICES
DEVICES 1 2
```

Result and consequences: Shows all or selected I/O devices.

PERIPHERALS

Availability: Local console and remote /o channel.

Accepted aliases: CPERIPHERALS.

Meaning: Shows all or selected connected peripherals.

General syntax:

```
PERIPHERALS [ID1 ID2 ...]
```

Parameters:

- IDn: optional peripheral identifiers; with none, all are returned.

Examples:

```
PERIPHERALS
PERIPHERALS 100
```

Result and consequences: Shows all or selected connected peripherals.

PERCOMMAND

Availability: Local console and remote /o channel.

Accepted aliases: CPERCMD.

Meaning: Sends a device-specific command to a connected peripheral.

General syntax:

```
PERCOMMAND PERID CMDID [ATTRS...]
```

Parameters:

- PERID: connected peripheral ID.
- CMDID: command ID implemented by that peripheral.
- ATTRS: optional positional attributes forwarded unchanged.

Examples:

```
PERCOMMAND 100 0
```

Result and consequences: The peripheral executes the request if both IDs and its parameter contract are valid; otherwise the answer reports an error.

ASSIGNJOY

Availability: Local console and remote /o channel.

Accepted aliases: CASSIGNJ.

Meaning: Remaps a joystick identifier.

General syntax:

```
ASSIGNJOY ID NEWID
```

Parameters:

- ID: current joystick ID.
- NEWID: required target ID; using the same ID removes an existing assignment.

Examples:

```
ASSIGNJOY 0 1
```

Result and consequences: Remaps a joystick identifier.

CLOCKFACTOR

Availability: Local console and remote /o channel.

Accepted aliases: CCLOCKFACTOR.

Meaning: Changes the CPU clock multiplier.

General syntax:

```
CLOCKFACTOR VALUE
```

Parameters:

- VALUE: numeric factor; 1 means normal speed.

Examples:

```
CLOCKFACTOR 2
```

Result and consequences: The emulation pacing target changes; values above one request faster execution.

SOUNDON

Availability: Local console and remote /o channel.

Accepted aliases: CSOUNDON.

Meaning: Enables audio output.

General syntax:

```
SOUNDON
```

Parameters:

- No parameters.

Examples:

```
SOUNDON
```

Result and consequences: Enables audio output.

SOUNDOFF

Availability: Local console and remote /o channel.

Accepted aliases: CSOUNDOFF.

Meaning: Disables audio output.

General syntax:

```
SOUNDOFF
```

Parameters:

- No parameters.

Examples:

```
SOUNDOFF
```

Result and consequences: Disables audio output.

INTERRUPTS

Availability: Local console and remote /o channel.

Accepted aliases: CINTERRUPTS.

Meaning: Shows all interrupts known by the computer.

General syntax:

```
INTERRUPTS
```

Parameters:

- No parameters.

Examples:

```
INTERRUPTS
```

Result and consequences: Shows all interrupts known by the computer.

INTSET

Availability: Local console and remote /o channel.

Accepted aliases: CINTSET.

Meaning: Enables or disables one interrupt or every interrupt.

General syntax:

```
INTSET ID|ALL ON|OFF
```

Parameters:

- ID or ALL: target interrupt.
- ON or OFF: requested state.

Examples:

```
INTSET ALL ON
```

Result and consequences: An unknown interrupt ID produces an error.

CHIPS

Availability: Local console and remote /o channel.

Accepted aliases: CCHIPS.

Meaning: Lists the emulated chips and their identifying attributes.

General syntax:

```
CHIPS
```

Parameters:

- No parameters.

Examples:

```
CHIPS
```

Result and consequences: Lists the emulated chips and their identifying attributes.

CRTON

Availability: Local console and remote /o channel.

Accepted aliases: CCRTON.

Meaning: Enables the CRT screen effect.

General syntax:

```
CRTON
```

Parameters:

- No parameters.

Examples:

```
CRTON
```

Result and consequences: Enables the CRT screen effect.

CRTOFF

Availability: Local console and remote /o channel.

Accepted aliases: CCRTOFF.

Meaning: Disables the CRT screen effect.

General syntax:

```
CRTOFF
```

Parameters:

- No parameters.

Examples:

```
CRTOFF
```

Result and consequences: Disables the CRT screen effect.

DATASETTE

Availability: Local console and remote /o channel.

Accepted aliases: CDATASETTE.

Meaning: Shows datasette state when a supported datasette is connected.

General syntax:

```
DATASETTE
```

Parameters:

- No parameters.

Examples:

```
DATASETTE
```

Result and consequences: Shows datasette state when a supported datasette is connected.

GRIDON

Availability: Local console and remote /o channel.

Accepted aliases: CGRIDON.

Meaning: Enables the C264-specific screen grid and optionally TED raster-interrupt markers.

General syntax:

```
GRIDON COLOR [ON]
```

Parameters:

- COLOR: mandatory numeric grid color.
- ON: optional second token; its presence enables TED raster-interrupt-position markers.

Examples:

```
GRIDON 14  
GRIDON 14 ON
```

Result and consequences: The C264-specific implementation shadows the standard GRIDON command. It enables the grid and, when a second token is supplied, TED raster-interrupt markers.

GRIDOFF

Availability: Local console and remote /o channel.

Accepted aliases: CGRIDOFF.

Meaning: Disables the C264-specific screen grid and TED raster-interrupt markers.

General syntax:

```
GRIDOFF
```

Parameters:

- No parameters.

Examples:

```
GRIDOFF
```

Result and consequences: The C264-specific implementation shadows the standard GRIDOFF command and disables both the grid and TED raster-interrupt markers.

PICTURE

Availability: Local console and remote /o channel.

Accepted aliases: CPICTURE.

Meaning: Saves a screenshot of the emulator screen.

General syntax:

```
PICTURE FILE
```

Parameters:

- FILE: output PNG, JPG or BMP filename.

Examples:

```
PICTURE c264-screen.png
```

Result and consequences: A supported extension writes the current screen; unsupported formats fail.

SETHOOK

Availability: Local console and remote /o channel.

Accepted aliases: CSETHOOK.

Meaning: Creates an execution hook.

General syntax:

```
SETHOOK ID TYPE [PARAMS...]
```

Parameters:

- ID: unique hook identifier.
- TYPE: hook kind; currently 0 stops on memory read/write.
- For TYPE 0, PARAMS are mandatory INITIAL and optional FINAL addresses.

Examples:

```
SETHOOK 1 0 $d000 $d3ff
```

Result and consequences: Creates an execution hook.

REMOVEHOOK

Availability: Local console and remote /o channel.

Accepted aliases: CREMOVEHOOK.

Meaning: Removes a hook by identifier.

General syntax:

```
REMOVEHOOK ID
```

Parameters:

- ID: hook identifier.

Examples:

```
REMOVEHOOK 1
```

Result and consequences: If the hook does not exist, no state changes.

HOOKS

Availability: Local console and remote /o channel.

Accepted aliases: CHOOKS.

Meaning: Lists active hooks.

General syntax:

```
HOOKS
```

Parameters:

- No parameters.

Examples:

```
HOOKS
```

Result and consequences: Lists active hooks.

HOOKSHELP

Availability: Local console and remote /o channel.

Accepted aliases: CHOOKSHELP.

Meaning: Shows help for supported hook types.

General syntax:

```
HOOKSHELP
```

Parameters:

- No parameters.

Examples:

```
HOOKSHELP
```

Result and consequences: Shows help for supported hook types.

CMOVEPARAMS

Availability: Local console and remote /o channel.

Accepted aliases: No public alias.

Meaning: Builds the framework's internal MoveParametersToAnswerCommand.

General syntax:

```
CMOVEPARAMS
```

Parameters:

- No parameters are executable under the current command contract.

Examples:

```
CMOVEPARAMS
```

Result and consequences: The command returns an empty answer when invoked directly; it is an internal response helper and is not advertised in the help file.

3.2 Inherited Commodore Commands

VICII

Availability: Local console and remote /o channel.

Accepted aliases: CVICII.

Meaning: Requests VIC-II state.

General syntax:

```
VICII
```

Parameters:

- No parameters.

Examples:

```
VICII
```

Result and consequences: Accepted by the inherited builder, but C264-series machines have no VIC-II, so no chip data is returned.

VICIIEVENTS

Availability: Local console and remote /o channel.

Accepted aliases: None in the current internal-name registration.

Meaning: Enables or disables VIC-II event visualization.

General syntax:

```
VICIIEVENTS ON|OFF
```

Parameters:

- ON: enable event display.
- OFF: disable it.

Examples:

```
VICIIEVENTS ON
```

Result and consequences: Accepted by the inherited builder, but C264-series machines have no VIC-II, so the command has no effect.

SID

Availability: Local console and remote /o channel.

Accepted aliases: CSID.

Meaning: Requests SID state.

General syntax:

```
SID
```

Parameters:

- No parameters.

Examples:

```
SID
```

Result and consequences: Accepted by the inherited builder, but C264-series sound is provided by TED rather than a SID chip, so no SID data is returned.

SIDW

Availability: Local console and remote /o channel.

Accepted aliases: CSIDW.

Meaning: Changes the active SID sound wrapper.

General syntax:

```
SIDW LIBID
```

Parameters:

- 0: reSID wrapper.
- 1: ICF/simple wrapper.

Examples:

```
SIDW 0  
SIDW 1
```

Result and consequences: Accepted by the inherited builder, but C264-series machines have no SID chip; the TED sound implementation is unchanged.

VICI

Availability: Local console and remote /o channel.

Accepted aliases: CVICI.

Meaning: Requests VIC-I state.

General syntax:

```
VICI
```

Parameters:

- No parameters.

Examples:

```
VICI
```

Result and consequences: Accepted by the inherited builder, but C264-series machines have no VIC-I, so no chip data is returned.

TED

Availability: Local console and remote /o channel.

Accepted aliases: CTED.

Meaning: Shows TED video, raster, interrupt and sound state.

General syntax:

```
TED
```

Parameters:

- No parameters.

Examples:

```
TED
```

Result and consequences: Returns the TED state used by the selected C16, C116 or Plus/4 model.

TEDEVENTS

Availability: Local console and remote /o channel.

Accepted aliases: None in the current internal-name registration.

Meaning: Enables or disables TED event visualization.

General syntax:

```
TEDEVENTS ON|OFF
```

Parameters:

- ON or OFF: requested event-display state.

Examples:

```
TEDEVENTS ON
```

Result and consequences: Changes TED event visualization for the selected C264-series model.

VIA

Availability: Local console and remote /o channel.

Accepted aliases: CVIA.

Meaning: Requests generic Commodore VIA state.

General syntax:

```
VIA
```

Parameters:

- No parameters.

Examples:

```
VIA
```

Result and consequences: Accepted by the inherited builder, but the implemented C264-series machines have no VIA, so no VIA data is returned.

CIA

Availability: Local console and remote /o channel.

Accepted aliases: CCIA.

Meaning: Requests generic Commodore CIA state.

General syntax:

```
CIA
```

Parameters:

- No parameters.

Examples:

```
CIA
```

Result and consequences: Accepted by the inherited builder, but C264-series machines have no CIA. The Plus/4 ACIA is a different chip and is not exposed by this command.

3.3 C264-Specific Commands

SCREENDUMP

Availability: Local console and remote /o channel.

Accepted aliases: CSCREENDUMP.

Meaning: Returns the current TED text-screen memory in hexadecimal.

General syntax:

```
SCREENDUMP
```

Parameters:

- No parameters.

Examples:

```
SCREENDUMP
```

Result and consequences: Returns the screen-memory snapshot selected by TED and visible to the active CPU.

ATTRIBUTEDUMP

Availability: Local console and remote /o channel.

Accepted aliases: CATTRIBUTEDUMP.

Meaning: Returns the current TED attribute memory in hexadecimal.

General syntax:

```
ATTRIBUTEDUMP
```

Parameters:

- No parameters.

Examples:

```
ATTRIBUTEDUMP
```

Result and consequences: Returns the attribute-memory snapshot used by the active TED display mode.

BITMAPDUMP

Availability: Local console and remote /o channel.

Accepted aliases: CBITMAPDUMP.

Meaning: Returns the current TED bitmap memory in hexadecimal.

General syntax:

```
BITMAPDUMP
```

Parameters:

- No parameters.

Examples:

```
BITMAPDUMP
```

Result and consequences: Returns the bitmap-memory snapshot selected by TED and visible to the active CPU.

CHARSDRAW

Availability: Local console and remote /o channel.

Accepted aliases: CCHARSDRAW.

Meaning: Renders textual drawings of all or selected character glyphs.

General syntax:

```
CHARSDRAW [0..255 ...]
```

Parameters:

- Character codes: optional values from 0 through 255; invalid values are ignored and duplicates are coalesced. With none, all characters are rendered.

Examples:

```
CHARSDRAW  
CHARSDRAW 1 2 65
```

Result and consequences: Returns textual drawings generated from the character data selected by TED.

3.4 Local-Console-Only Commands

LOADPRG

Availability: Local console only.

Accepted aliases: None.

Meaning: Loads, assembles and installs an assembler source through the emulator object.

General syntax:

```
LOADPRG FILE
```

Parameters:

- FILE: assembler source path.

Examples:

```
LOADPRG demo.asm
```

Result and consequences: Compilation or loading errors are reported by the local console.

LOADBINARY

Availability: Local console only.

Accepted aliases: None.

Meaning: Loads a binary containing its destination address in the file header.

General syntax:

```
LOADBINARY FILE
```

Parameters:

- FILE: header-addressed binary path.

Examples:

```
LOADBINARY demo.prg
```

Result and consequences: Loads a binary containing its destination address in the file header.

LOADBLOCKS

Availability: Local console only.

Accepted aliases: None.

Meaning: Loads a block-structured memory file.

General syntax:

```
LOADBLOCKS FILE
```

Parameters:

- FILE: block file path.

Examples:

```
LOADBLOCKS state.blocks
```

Result and consequences: Loads a block-structured memory file.

DECOMPILE

Availability: Local console only.

Accepted aliases: None.

Meaning: Disassembles a memory region.

General syntax:

```
DECOMPILE ADDRESS BYTES
```

Parameters:

- ADDRESS: first address.
- BYTES: approximate byte count; output rounds to complete instructions.

Examples:

```
DECOMPILE $080d 64
```

Result and consequences: Disassembles a memory region.

POSSIBLEPERS

Availability: Local console only.

Accepted aliases: None.

Meaning: Lists peripheral IDs and required attributes supported by the active I/O peripheral builder.

General syntax:

```
POSSIBLEPERS
```

Parameters:

- No parameters.

Examples:

```
POSSIBLEPERS
```

Result and consequences: Lists peripheral IDs and required attributes supported by the active I/O peripheral builder.

CONNECTPER

Availability: Local console only.

Accepted aliases: None.

Meaning: Builds and connects a peripheral to the first compatible device.

General syntax:

```
CONNECTPER ID [ATTRS...]
```

Parameters:

- ID: peripheral-emulation ID from POSSIBLEPERS.
- ATTRS: optional device-specific positional attributes, such as d:8 for a 1541 or d:4 f:printer.ps p:MPS801-PS for a printer.

Examples:

```
CONNECTPER 100  
CONNECTPER 215 d:8
```

Result and consequences: Connection succeeds only when the ID and attributes are valid and a compatible device is available.

DISCONNECTPERS

Availability: Local console only.

Accepted aliases: None.

Meaning: Disconnects one or more peripherals.

General syntax:

```
DISCONNECTPERS ID1 [ID2 ...]
```

Parameters:

- IDn: connected peripheral IDs.

Examples:

```
DISCONNECTPERS 100 101
```

Result and consequences: Disconnects one or more peripherals.

LOADPERDATA

Availability: Local console only.

Accepted aliases: None.

Meaning: Loads media/data into a connected peripheral.

General syntax:

```
LOADPERDATA ID FILE [DEBUGFILE]
```

Parameters:

- ID: connected peripheral ID.
- FILE: supported media/data file.
- DEBUGFILE: optional file used to start format-related debugging.

Examples:

```
LOADPERDATA 215 disk.d64
```

Result and consequences: The operation fails if the peripheral does not support the supplied format.

EMPTYPERDATA

Availability: Local console only.

Accepted aliases: None.

Meaning: Creates empty media/data in a peripheral.

General syntax:

```
EMPTYPERDATA ID FILE
```

Parameters:

- ID: connected peripheral ID.
- FILE: path whose extension selects a supported creatable format.

Examples:

```
EMPTYPERDATA 215 blank.d64
```

Result and consequences: Only peripherals and formats that implement empty-media creation can succeed.

SAVEPERDATA

Availability: Local console only.

Accepted aliases: None.

Meaning: Saves a peripheral's current media/data.

General syntax:

```
SAVEPERDATA ID [FILE]
```

Parameters:

- ID: connected peripheral ID.
- FILE: optional output path; may be omitted when LOADPERDATA or EMPTYPERDATA established the current filename.

Examples:

```
SAVEPERDATA 215  
SAVEPERDATA 215 copy.d64
```

Result and consequences: Saves a peripheral's current media/data.

CLEARPERDATA

Availability: Local console only.

Accepted aliases: None.

Meaning: Clears all data currently loaded into peripherals.

General syntax:

```
CLEARPERDATA
```

Parameters:

- No parameters.

Examples:

```
CLEARPERDATA
```

Result and consequences: Commonly used to force a subsequent program/media reload.

Appendices

Appendix A. Command Availability Summary

The table distinguishes the interactive console from the command channel of the non-console executable. Remote availability assumes C264Emulator.exe was started with /o and that the client is connected.

Command family	C264EmulatorC local console	C264Emulator remote /o
Standard builder	Yes	Yes
Inherited Commodore builder	Yes	Yes
C264 builder	Yes	Yes
LocalConsole emulator/media operations	Yes	No

Appendix B. Source-of-Truth Maintenance Rule

This file is a maintained repository artifact. Every change that adds, removes, renames or changes a C264 startup option, a command-builder registration, a LocalConsole-only command, command syntax, parameter meaning, command consequences or user-visible formatted output must include a review and, when applicable, an update of docs/C264Data/C264Emulator_UserGuide.docx. The corresponding canonical .fmt source must be updated whenever the command's InfoStructure contract changes.

Audit the complete chain, not only the edited class: the C264Emulator entry point and C264::C264Emulator hierarchy for startup options; LocalConsole for local-only commands; and C264::CommandBuilder -> COMMODORE::CommandBuilder -> MCHEmul::StandardCommandBuilder for builder commands.

Illustrations

NO ILLUSTRATIONS ARE INCLUDED IN THIS EDITION.

IGNACIO CEA FORNIÉS

Equations

NO EQUATIONS ARE INCLUDED IN THIS EDITION.

IGNACIO CEA FORNIÉS