

CC41 USER MANUAL

Version 0.46.05 Alpha

Copyright (C) 2026 Craig Bladow. All rights reserved.

Table of Contents

1. Introduction
2. Installation
3. Starting and Exiting CC41
4. Differences from HP 41CX commands
5. Numeric Functions
6. Alpha Register
7. Stack, Data and Alpha Register Functions
8. Display and Information Functions
9. Interactive Functions
10. Program and Flag Operations
11. Extended Functions Memory and File Operations
12. Flags
13. Error Numbers

Introduction

Why CC41?

CC41 is a re-creation of many of the functions of Hewlett Packard's HP-41CX calculator in software. Most calculator programs recreate a graphical interface resembling a calculator requiring the user to either use a mouse to enter commands and numbers or use a somewhat non-intuitive keyboard mapping where one key on the PC's keyboard maps to a key on the graphical calculator. With CC41 you can quickly type a function such as "1/x" rather than having to memorize which keyboard key the function is mapped to.

CC41 contains 1000 data memory registers, numbered 0 to 999, and 65535 program memory registers as well as 64 flags, numbered 0 to 63.

Using PATH to navigate your computer's filesystem CC41 can read programs using GETP and GETSUB and remove them with PCLPS. CC41 can automatically load a program on launch and optionally begin running it.

The VIEW and AVIEW commands can output results to the command window as the program runs and the TRACE, WATCH, and SST commands enable program debugging.

While CC41 can be a touch typist's calculator the two best features are that programs can be written in your favorite text editor which then run incredibly fast on your computer compared to the original HP-41CX.

Additional Reference Material

The Hewlett-Packard HP-41 CX Owner's Manual, volumes 1 and 2, is the recommended reference for most of the commands supported by CC41. Differences, if any, between the HP-41CX commands and CC41 will be explained in this manual.

Installation

There is no installer needed for CC41. Download the .zip file from GitHub.com. Uncompress the file and copy the executable corresponding to your computer's operating system, as well as the file beep41.wav to where you desire to run the program from.

Software Updates

Download the latest release: <https://github.com/CraigBladow/cc41/releases>

Starting and Exiting CC41

Pressing the CTRL and C keys simultaneously will exit an interactive CC41 session or, if a program is running, stop the running program. The program can be resumed by entering the RUN command.

Enabling and Disabling Continuous Memory

To enable continuous memory, which preserves the memory and state of the calculator between uses, clear flag 59 by issuing the command, "cf 59". This creates or updates the file "cc41.mem" upon exiting CC41. If this file is present on startup, CC41 will prompt the user to choose to restore, keep without restoring, or delete the previous saved session's state.

Note that if the default path has been modified, cc41.mem will be written to the modified path and won't be found automatically. A cc41.mem file can be loaded anytime using READA.

Windows

Open a console by pressing the Windows key located to the left of the spacebar and typing (without quotes) "cmd". To leave CC41 type "exit" or "off" and press the return key.

Mac OS

Open the Terminal application by pressing the 'command' and 'space' keys to open Spotlight search, type 'terminal' and hit return. To leave CC41 type "exit" or "off" and press the return key or press the key combination CTRL + d .

Linux

In many Linux distributions the key combination CTRL + ALT + T will open the terminal. Otherwise use the graphical menu system. To leave CC41 type "exit" or "off" and press the return key or press the key combination CTRL + d .

After Opening a Console Window

Navigate to the location where you copied CC41. In Windows type "cc41.exe" and press the return key.

In MacOS and Linux type "./cc41" and press the return key. CC41 starts by displaying version information and some tips to get started. This is followed by a "Memory Cleared" message and a display of the current stack values, last x value, and the contents of the alpha register.

To see the list of supported commands, enter “cat 3” and press the return key.

Commands are entered in upper or lower case with a space between each command and number or followed by pressing the return key.

Interactive mode is where you input commands from the keyboard, press the return key and CC41 outputs the resultant stack and alpha registers. When you type RUN and press the return key, CC41 will begin executing the current program, at the current program step. If you type XEQ followed by a program label, CC41 will begin running that program at the program label location. You can also GTO a program label before typing RUN.

Input is limited to 256 characters at a time. This limit includes commands, number, operations, alpha strings, and filenames. Input continues on the next entry line. Commands that always expect a following parameter, such as SF, can be continued after the return key is pressed. Commands that have optional following parameters, such as CLP and LIST, must be completed before pressing the return key.

Numbers must also be completed before pressing the return key. A number followed by a space or return key will cause the stack to lift and the new number to be placed in X with stack lift enabled. This differs from ENTER which lifts the stack, duplicating the value in X and disabling stack lift. Numbers can be entered using keyboard keys for ‘+’, ‘-’, ‘.’, ‘0-9’, ‘e’, and ‘E’. If more than 16 number digits are entered the 16th digit will be rounded. Hexadecimal numbers are recognized by prefixing with ‘0x’ or ‘0X’ followed by 0 to 16 hexadecimal characters. Prefixing is not necessary when working hexadecimal numbers in the alpha register.

Text surrounded by double quotes, such as “Alphabet” will be placed in the Alpha Register. Text following a command that expects text does not need to be quoted. For example, GTO MYLABEL does not need double quotes.

Command Line Options

The default mode of operation is interactive mode if no options are provided.

Option	Description
-i or -I	Start CC41 in interactive mode.
-l or -L [filename]	Load a program into memory.

Option	Description
-x or -X [filename]	Load a program into memory and begin running it.
-r or -R [filename]	Restore entire memory from a file, equivalent to READA command.
-s or -S	Suppress the startup messages except for MEMORY LOST.
-v or -V	Output the software version and exit.

Command Line History

A very nice feature available is the ability to press the up and down arrows to navigate through previous commands issued to CC41. In the Windows version of CC41 this feature works with no additional software installation needed. For Linux and MacOS a utility called “rlwrap” needs to be installed. Once the utility is installed then launch cc41 as follows: rlwrap ./cc41 .

Differences from HP 41CX commands

CC41 Additional Commands

CC41	Description
astol	Extended version of ASTO that stores 8 characters from the Alpha register in a memory instead of 6.
aversion	Appends the CC41 software version to the Alpha register.
arcl	Extended version of ARCL that recalls 8 characters from a memory to the Alpha register instead of 6.
ashfl	Extended version of ASHF that shifts 8 characters instead of 6 in the Alpha register.
changes	Displays list of CC41 software changes.
clerr	Set the error number to 0 indicating no error (see ERRNO).
clall	Clears all memories and resets CC41 to the initial state. Not programmable.
dec	Input greater than 7,777,777,777,777,777 returns DATA ERROR.

CC41	Description
dejavu	Clears the calculator and reloads the last program loaded.
drop	Deletes current X contents and moves stack contents down. L not affected.
dropl	Deletes current L contents and moves stack down. X contents moved to L.
errno	Recalls the last error number to the X register. See Error Numbers.
exit	Exits CC41, similar to turning the HP-41CX off, however memory contents and status are not retained.
exeq	Executes the system command, shell script, or batch file named in the alpha register using the current specified path.
fview	Displays the flags register as a hexadecimal number.
getpr	Loads and then runs a program starting at the first line. See GETP.
gto.	Go to the following program line number. Replaces 'GTO .'
gto..	Go to the end of Program Memory, create an END if the last program does not have one. Replaces 'GTO ..'
oct	Input greater than 281,474,976,710,655 returns DATA ERROR.
os?	Returns the name of the OS to the alpha register.
path	Sets the filesystem path to the contents of the alpha register.
path?	Displays the current filesystem path, if set.
path+	Appends the contents of the alpha register to the current path. Maximum path characters limited to 233.
pdir	Lists contents of the directory that PATH points to. Defaults to the current directory.
rand	Generates a psuedo-random number based on Mersenne Twister MT19937. Numbers range from 0 to $2^{32} - 1$ with a uniform distribution.
reada	Read calculator status, program and memory contents from PATH + filename In a program ,filename length is limited to 8 characters.
reads filename	Reads calculator status, written by WRTS, from PATH + filename.

CC41	Description
rclst	Recall stack registers X,Y,Z,T, and L from the given memory location and 4 subsequent memories.
run	Begins running the current program at the current step. Clears the last error (see ERRNO).
sst	Must be followed by RETURN key or an optional number N, executing one or N number of steps respectively.
stost	Store stack registers X,Y,Z,T, and L in the given memory location and 4 subsequent memories.
trace	Display program step information as a program runs.
usage	Prints how to call the CC41 executable.
user	Toggles flag 27 which enables USER Mode.
version	Outputs software build, library, and operating system information.
wrta	Write calculator status, program and memory contents to PATH + filename. In a program filename length is limited to 8 characters.
wrts filename	Write calculator status to PATH + filename. In a program filename length is limited to 8 characters. Saves registers, x, y, z, t, and l. Saves flags 0-63 and the Alpha register. Saves Statistics registers base register and data memory size allocation.
xail	Executes one or more commands contained in the Alpha register in line. All instructions in the Alpha register are executed. Branching due to a conditional in the Alpha register is delayed until xail completes. If any single conditional fails then the instruction following XAIL is skipped. The following commands are not allowed to be executed by XAIL: LBL, GTO, XEQ, EXEQ, RTN, STOP, PCLPS, PSE, PROMPT, END, XAIL and non-programmable commands. If an error is detected in the string of commands execution of the commands in the alpha register ceases. If a program is running, the program is stopped unless flag 25 is set.
xtoa	Doesn't replicate the special characters displayed for some codes on HP-41CX.

Hexadecimal Commands

CC41	Description
and	Logical AND of two hexadecimal (flag data) numbers.
ad-h	Performs full 64 bit decimal to hexadecimal conversion in the alpha register
ah-d	Performs full 64 bit hexadecimal to decimal conversion in the alpha register
d-h	Convert decimal (0-9999999999999999) number in X to hexadecimal (flag data).
h-d	Convert hexadecimal (flag data) number (0x0-0x2386F26FC0FFFF) in X to decimal number in X.
h-	Subtract the hexadecimal (flag data) number in X from Y.
h+	Add the two hexadecimal (flag data) numbers in X and Y.
harcl	Recall hexadecimal (flag data) numbers from stack or memory to the alpha register.
hasto	Store hexadecimal (flag data) numbers from the alpha register to stack or memory.
not	Logical NOT of the hexadecimal (flag data) number in X.
or	Logical OR of two hexadecimal (flag data) numbers.
shfl	Shift hexadecimal (flag data) number left 0 to 64 bits.
shfr	Shift hexadecimal (flag data) number right 0 to 64 bits.
xor	Logical XOR of two hexadecimal (flag data) numbers.

Different Command Behavior

All memory, registers 0 through 999, may be directly referenced by STO, RCL, and other commands. Indirect access works also.

SIZE and PSIZE have no affect as data memory size is fixed to 1000.

SIZE? always returns 1000.

User Flags number 0-63.

Stack indirection, STO IND ST X and STO IND X will both work exactly the same. CC41 will list commands referencing stack registers without 'ST'.

There is no need for ALPHA or PRGM mode with CC41. Alpha text is entered directly between double quotes and programs are edited in your favorite text editor.

The functions of the R/S key are replaced by the commands RUN and STOP.

There are no key assignments in CC41.

PRSTK prints x, y, z, and t registers as well as the l and Alpha register.

Beep prints "BEEP!" and uses the PC speaker to make the classic beep sound. Output can be suppressed by clearing flag 26.

RCLFLAG recalls status of flags 0-63 to x register.

STOFLAG Saves flag data in x register to flags 0-63. Viewing flag data is indicated by "Flag Data" in the display.

Numeric operations on flag data result in a "FLAG DATA" instead of an "ALPHA DATA" error.

TIME displays current time to millisecond resolution.

FIX, SCI and ENG will accept values from 0 to 15.

SIN, COS and TAN return 0.0 for $|X| \geq 1e300$.

CC41 uses 16 decimal digits internally however only 15 can normally be displayed using FIX, SCI and ENG. Setting flag 60 will display all sixteen digits in the current FIX, SCI or ENG formats regardless of the last FIX, SCI or ENG setting.

CLD is present for compatibility but does not clear what has been output to the console.

CC41 will not give an OUT OF RANGE error for: mdy 10.161582 -1 date+, while the HP 41CX will. 10.151582 is a valid date per the HP 41CX manual.

Labels

CC41 supports global labels up to 8 characters in length while HP-41CX supports 7 characters. Global labels are case sensitive. Valid local alpha labels for CC41 are labels a-z and A-Z except for l,x,y,z,t and L,X,Y,Z,T. Valid numeric labels are 0 through 999.

Comments

Comments in programs may start anywhere and are prefaced by a '@' or a ';' character. All text on a line following a comment character will be ignored.

Entry Using Upper and Lower Case

Command entry and command short cuts are case insensitive. File name and paths depend on your operating system settings. Program labels are case sensitive.

Short Cut Commands

s for SST. b for BST. Prefacing a global label with '.' is a shortcut for XEQ. No intervening space is required. For example, instead of XEQ TVM, typing .TVM will execute the label. This shortcut works with both local and global labels. This shortcut works in programs as well, but is expanded by LIST or SAVEP.

User Mode

User mode is toggled by the USER command which sets flag 27 when in user mode. When in user mode XEQ is not required to execute a global label, just type in a valid global label and it will be treated as a built-in command.

Text Entry

Text entered between " and " will overwrite the contents of the Alpha register. Adding a '>', '+', or '|-' before the first " will append the text to the contents of the Alpha Register (note 3). Alpha program labels following LBL, GTO, and XEQ work with and without double quotes.

Filenames following READS, WRTS, WRTA, and READA must not be double quoted.

A program label following CLP must not be double quoted otherwise it is treated as an alpha register text entry.

CC41 uses the more easily typed "alpha" version of the HP-41CX command set as opposed to the symbols appearing on the HP-41CX keyboard. Some of the alpha commands contain symbols that do not

commonly appear on computer keyboards. The following is a list of those commands and the text equivalent. Either command will be accepted in a program file. Numerous other symbols produced by online RAW file decoders will also be translated or ignored.

Notes:

1. "x<>y" is the CC41 command to swap the contents of the X and Y registers.
2. Exponentiation is denoted by the '^' character e.g., x^2 , y^x , e^x , 10^x , e^{x-1} .
3. HP-41CX printed program listings include the append character inside the double quotes. For CC41 these characters will be placed in the Alpha register so editing of these lines is necessary.

HP-41CX	CC41
CLΣ	cls
ENTER↑	enter, space or return key
R↑	rup
Σ+	s+
Σ-	s-
ΣREG	sreg
ΣREG?	sreg?
X≠0?	x<>0? or x!=0?
X≠Y?	x<>y? or x!=y?

Unimplemented Commands

A number of commands do not make sense in the context of CC41 vs. a handheld calculator. There are also commands that are planned to be implemented in the future and are described as such.

Numeric Functions

Unless noted these commands function as described in [Additional Reference Material Numeric] (#additional-reference-material) Because CC41 uses 16 digit decimal math, which is more digits than the HP-41CX calculator uses, the outputs of arithmetic operations may be slightly different.

Name	Description
+	$y + x$
-	$y - x$
*	$y * x$
/	y / x
1/x	Reciprocal
10^x	Common exponential
abs	Absolute value
acos	Arc cosine
asin	Arc sine
atan	Arc tangent
chs	Change sign
cos	Cosine
d-r	Degrees to radians conversion
dec	Octal to decimal conversion
e^x	Natural exponential
e^x-1	Natural exponential for arguments close to zero
fact	Factorial
frc	Fractional part
hms	Decimal hours to hours-minutes-seconds conversion
hms+	Hours-minutes-seconds addition
hms-	Hours-minutes-seconds subtraction
hr	Hours-minutes-seconds to decimal hours conversion
int	Integer part
ln	Natural logarithm
ln1+x	Natural logarithm for arguments close to 1
log	Common logarithm
mean	Means of accumulated x and y values
mod	$y \bmod x$
oct	Decimal to octal conversion
p-r	Polar to rectangular conversion
%	x percent of y
%ch	Percent change from y to x
pi	Pi
r-d	Radians to degrees conversion
r-p	Rectangular to polar conversion
rnd	Round
sdev	Standard deviations of accumulated x and y values
sum+	Accumulations for statistics
sum-	Accumulations correction
sin	Sine
sign	Sign of x
sqrt	Square root
tan	Tangent
x^2	Square

Name	Description
y ^x	y raised to the x power

Alpha Register

The Alpha register can hold up to 24 alpha-numeric characters.

Text surrounded by double quotes, i.e. "example" will be placed in the Alpha register, overwriting any text previously there. If the text in double quotes is prefixed by '-' or '+', i.e. |- "pangolin" or + "anteater" then it is appended onto the existing text, if any, in the Alpha register. A maximum of 24 characters is allowed between double quotes in interactive mode and 16 characters are allowed between double quotes in a program.

Stack, Data and Alpha Register Functions

Name	Description
adate	Append date in X register to Alpha register.
aleng	Loads x with the number of characters in the Alpha register.
anum	Constructs a number from the first string of number characters in the Alpha register. Sets flag 22 if a number is found.
arcl	Appends 6 characters from memory to Alpha register.
arcll	Appends 8 characters from memory to Alpha register.
arot	Rotates alpha register contents by X, left if X is positive, right if X is negative.
ashf	Shift Alpha register left 6 characters.
ashfl	Shift Alpha register left 8 characters.
asto	Copies the left 6 characters from the Alpha register to memory.
astol	Copies the left 6 characters from the Alpha register to memory.
atime	Append time in X register to Alpha register.
atime24	Append time in X register to Alpha register in 24 hour format.
atox	The value of the left most character in the Alpha register is placed in X and the Alpha register contents are shifted left one character. A 0 is placed in X if the Alpha register is empty.

Name	Description
cla	Clear the Alpha register.
cld	Clear the display. Has no effect in CC41
clrg	Clear all numbered memory registers
clrgx	Clear registers starting at bbb, through eee incrementing by ii as specified in X by bbb.eeeeii.
cls	Clear statistics registers.
clst	Clear the stack registers x, y, z, and t.
clx	Clear the x register.
date	Loads number for current date into the x register.
date+	Adds days in x register to date in y register.
ddays	Difference in days between dates in the y and x registers.
dow	Returns the day of the week.
dse	Decrement the referenced register and skip the next program instruction if the counter and the end value are equal.
enter	Will lift the stack, duplicating x on the stack and disabling stack lift.
isg	Increment the referenced register and skip the next program instruction if the counter is greater than the end value.
lastx	Recall register l to x, lifting the stack.
posa	Finds the position of the character byte code or alpha character string in X, and returns the position of the first character to the X register. -1 indicates that the target was not found.
psize	Set number of data registers from program. Has no effect in CC41 as there are 1000 memory registers numbered 0 to 999.
rup	rotate the stack up, bringing t into x.
rcl	Recall a memory value to the x register.
rc+	Add the referenced memory location to the x register.
rc-	Subtract the referenced memory location from the x register.
rc*	Multiply the x register by the referenced memory location by x and store the result in the x register.
rc/	Divide the x register by the referenced memory location and store the result in the x register.
rdn	rotate the stack down, putting x into t.
regmove	The value sss.dddn in X specifies copying the contents of nnn registers, starting at register sss to registers beginning with ddd.

Name	Description
regswap	The value sss.dddnnn in X specifies swapping the contents of nnn registers, starting at register sss with registers beginning with ddd.
sumreg	Set the base memory register for the statistics registers.
sumreg?	Recall the base memory register value for the statistics registers to the x register.
size	Sets the number of data memory registers. Has no effect in CC41 as there are 1000 memory registers numbered 0 to 999.
size?	Always returns 1000. See SIZE.
st+	Add the x register to the referenced memory location.
st-	Subtract the x register from the referenced memory location.
st*	Multiply the referenced memory location by x and store the result there.
st/	Divide the referenced memory location by x and store the result there.
sto	Store x in the referenced memory location.
time	Load the current time into the x register.
xtoa	Appends the character represented by the value in X, or the string of alpha characters in X, to the right end of the contents of the Alpha register.
x<>	Swap the x register with the referenced memory register.
x<>f	Swap the first 8 flags, 0-7 with the x register.
x<>y	Swap the x and y registers.

Display and Information Functions

Name	Description
about	Displays information about CC41 and a short summary to get started.
adv	Outputs a blank line. Unaffected by flags 21 or 55.
aview	View the Alpha register.
cat	CAT 1 lists global labels in memory. CAT 3 lists all CC41 commands. CAT 4 lists the files in the current directory. Cat 6 lists global labels if USER mode is enabled. CAT 9 is CAT 3 with the output commands in one column. These are the only CAT commands implemented.
changes	Displays recent software change information.
clk12	12 hour clock display.

Name	Description
clk24	24 hour clock display.
clkt	Only display clock time.
clkt d	Set clock to display time and date.
clock	View clock.
deg	Set the angle units to degrees.
dmy	Set Day Month Year date format.
eng	Set the display format to engineering.
exit	Exit CC41
fix	Set the display format to fixed.
grad	Set the angle units to grads.
mdy	Set Month Day Year date format.
os?	Returns the name of the OS to the alpha register.
prstk	Print the stack, l and Alpha register.
rad	Set the angle units to radians
sci	Set the display format to scientific.
trace	Display program step information as a program runs.
usage	Displays command line parameters for loading and running programs.
version	Outputs software build, library, and operating system information.
view	View the contents of the referenced memory.

Interactive Functions

Name	Description
beep	Prints "BEEP!" and makes the classic beep sound. Output can be suppressed by clearing flag 26.
exit	Exit CC41 program. Memory and status are not saved.
off	Exit CC41 program. Memory and status are not saved.
prompt	Stops a running program and displays Alpha register prompt. User enters the needed data and types RUN followed by pressing the return key.
pse	Pauses running program for 2 seconds.
tone	CC41 does not accept input during a pause. Not yet implemented.

Program and Flag Operations

Flag test operations will print 'yes' or 'no' when commanded in interactive mode. See 11. Flags for flag definitions.

Name	Description
bst	Step back one program line.
cf	Clear flag.
clp	Clear program. If followed by a program label, ex. CLP labelname (no quotes) deletes the program containing that label. If not followed by a program label deletes the current program.
end	End of program.
fc?	Test if flag is clear.
fc?c	Test if flag is clear. Then clear the flag.
fs?	Test if flag is set.
fs?c	Test if flag is set. Then clear the flag.
gto	Go to a program label.
gto.	Go to a program line number.
gto..	Go to the end of program memory and append and END statement to the last program if none is present.
lbl	Program label. Valid numeric labels are 0 through 999. Alpha-numeric labels can be up to 8 characters in length. Invalid labels are x, y, z, t, l, X, Y, Z, T, and L. Numeric only and single alpha labels are local in scope to the current program, all other labels are globally accessible from any program in memory.
list	list the program from the current step. Must be followed by RETURN key or an optional number N. If followed by a number N, list N program lines from the current program step.
pclps	Programmable version of CLP. Clears a program with the label as identified in the Alpha register.
rclflag	Recalls status of flags 0-63 to x register.
rtn	Directs program to return to the calling program or exit.
run	Start running the program at the current program step.

Name	Description
sst	Execute one step of the program. When followed by an optional number N, executes N number of steps.
stoflag	Saves flag data in x register to flags 0-63.
stop	Command in the running program to stop.
x=0?	Test if x is equal to 0.
x<>0?	Test if x is not equal to 0.
x<0?	Test if x is less than 0.
x<=0?	Test if x is less than or equal to 0.
x>0?	Test if x is greater than 0.
x=y?	Test if x is equal to y.
x<>y?	Test if x is not equal to y.
x<=y?	Test if x is less than or equal to y.
x<y?	Test if x is less than y.
x>y?	Test if x is greater than y.
x=nn?	Test if x is equal to the contents of register NN in y.
x<>nn?	Test if x is not equal to the contents of register NN in y.
x<nn?	Test if x is less than to the contents of register NN in y.
x<=nn?	Test if x is less than or equal to the contents of register NN in y.
x>nn?	Test if x is greater than to the contents of register NN in y.
x>=nn?	Test if x is greater than or equal to the contents of register NN in y.
xeq	Execute a program starting at the given program label. XEQ does not clear errors (see ERRNO).

Program Development Functions

These features help in developing and debugging programs. A list of up to 25 registers may be monitored. The contents of the registers will be displayed everytime the statck is displayed. Registers can be added and removed one at a time using WATCH and UNWATCH respectively. WATCH and UNWATCH take the same arguments as VIEW.

Name	Description
clwatch	Clear the list of watch registers.
unwatch (0 to 999, ind, st)	Unwatch the referenced storage register
watch (0 to 999, ind, st)	Watch the referenced storage register.
check labelname	Is followed by a subroutine label and enables CHECK mode where the subroutine label is called after every program step. If the subroutine determines that the CHECK condition is met it uses the BREAK labelname command to jump to a label and the program will stop following a RTN to the program being debugged. Using STOST and RCLST to save and recall the stack and lastx values enables the break subroutine to not affect the state of the program being debugged. CHECK labelname may be used to change the labelname at any time. CHECK is not programmable.
clcheck	Disables CHECK mode.
break labelname	BREAK lablename jumps to the labelname and stops the program after the next RTN if CHECK lablename was set previously and the program identified by CHECK is running. If CHECK mode is not set it does nothing.

Extended Functions Memory and File Operations

Data and text file operations are not currently supported in CC41.

Name	Description
curfl	Makes the file named in the alpha register the current file.
curfl?	Places the current file name in the Alpha register.
pdir	List files in the directory pointed to by PATH.
emdir	List files in the default directory.
emdirx	Retrieve file information for Nth file in directory. N is provided by emdir.
emroom	Always returns 600 for the amount of extended memory registers available.

Name	Description
flsize	Returns the size of the file in the default directory named in the alpha register.
getp	Reads a program into memory, replacing the last program in memory. Uses PATH plus the filename stored in the Alpha Register. If getsub is commanded from a running program, execution resumes after the getsub command. If the program has line numbers, every line must have a number, the line numbers do not have to be in any order and can be duplicated. This is useful if you add comments to an existing program with line numbers.
getr	Copies registers from the file named in the Alpha register plus PATH into main memory.
getrx	Copies registers from the file named in the Alpha register plus PATH into main memory starting at sss and ending at eee where sss.ee is a number in the x register.
getsub	Reads a program into memory after all other programs. Uses PATH plus the filename stored in the Alpha Register and PATH. If getsub is commanded from a running program, execution resumes after the getsub command.
path	Sets the filesystem path to the contents of the alpha register. Initializes to the current directory.
path?	Displays the current filesystem path.
path+	Appends the contents of the alpha register to the current path. Maximum path length is limited to 233 characters.
reada	Read calculator status, program and memory contents from PATH + filename In a program ,filename length is limited to 8 characters.
reads filename	Reads calculator status, written by WRTS, from PATH plus filename.
saver	Saves all registers in main memory to the file named in the Alpha register plus PATH

Name	Description
savep	Saves a program with the designated global label to the named file. For example "label, filename" savep will save the program containing 'label' to file 'filename' at the current path. If 'label' is omitted then the current program is saved. Line numbers are included and may be turned off by setting flag 58. Output of SAVEP should be compatible with RAW file converter utilities comp41 from lifutils and also 41uc.
saverx	Copies registers to the file named in the Alpha register plus PATH from main memory starting at sss and ending at eee where sss.ee is a number in the x register.
wrta	Write calculator status, program and memory contents to PATH + filename. In a program filename length is limited to 8 characters.
wrts filename	Write calculator status to PATH + filename. In a program filename length is limited to 8 characters. Saves registers, x, y, z, t, and l. Saves flags 0-63 and the Alpha register. Saves Statistics registers base register and data memory size allocation.

Flags

Flags typically follow the HP-41CX conventions with flags 0-29 being user modifiable. System flags are 30-63, where HP-41CX stops at flag 55. Currently all flags are user modifiable, this may change in the future.

Flag Overview

Flag No.	Description
0-10	User Flags
11-29	Control Flags
30-61	System Flags
62-63	Console Output Flags

Control Flags

Flags identified as “Reserved” are not currently implemented but may be used in a future version of CC41. They can currently be set, cleared and tested by the user.

Flag No.	Description
11	Reserved (Automatic Execution)
12-20	Reserved (External Device Control)
21	Reserved (Printer Enable)
22-23	Reserved (Data Input)
24	RangeError Ignore
25	Error Ignore
26	Audio Enable, when set enables output to console from BEEP command.
27	User Mode enabled when set.
28-29	Display Punctuation

System Flags

Flags identified as “Reserved” are not currently implemented but may be used in a future version of CC41. They can currently be set, cleared and tested by the user.

Flag No.	Description
31	Date Format page 242
36-39	Number of displayed digits page 160-161
42-43	Angular Mode page 186
44	Reserved (Continuous On)
48	Reserved (Alpha Keyboard active)
49	Reserved (Low Battery)
50	Reserved (Message Displayed)
55	Reserved (Printer present)

Miscellaneous CC41 System Flags

These flags are not present in the HP-41CX and are used to affect the operation and or output of some commands

Flag No.	Description
56	Reserved CC41 system flag
57	Setting this flag When BREAK mode is active causes the program to stop. See BREAK and CLBREAK commands for more information.
58	Setting this flag disables line numbers being output by the LIST and SAVEP commands
59	When cleared enables continuous memory functionality. This flag is set on startup.

Console Display Flags

Console display flags determine what is displayed as console output as a result of user interaction. These flags can be set, cleared and tested by the user.

Flag No.	Description
60	When set will display the 16th digit in the number regardless of the current FIX, ENG and SCI setting. This flag is clear on startup.
61	When set suppresses "Reading/Writing filename.ext" messages when reading or writing files. This flag is clear on startup.
62	Displays just the X register contents instead of the entire stack when set. This flag is clear on startup.
63	Display stack and alpha register contents when set. This flag is set on startup. Clearing this flag results in no output.

Error Number Table

The following table lists the error number generated by CC41. It is useful for testing error conditions with flag 25 set which allows

the test program to run, detect that an error occur and then identify which error it was using the ERRNO command.

Error No.	Description
0	No Error
1	Data Error
2	Out of Range Error
3	Nonexistent
4	Alpha Data
5	Flag Data
6	Memory Lost
7	Xail Error
99	Unknown Error