CrewmateA300 — User Manual

Contents

Getting Started

- Requirements
- Voice Modes
- PTT and Mic On/Off Buttons
- Voice Settings

Tutorial

- Assumptions
- Typical preflight timeline (example)
- Pushback and Engine Start
- Taxi
- Line-up & Takeoff
- Acceleration
- Climb to 10,000 ft
- Descent Preparation
- 10k Descent
- Approach
- Landing
- After Landing
- Parking
- Securing the Aircraft


Voice Commands

- Preflight Timer
- Ground Engineer
- Gear
- Flaps
- Engine Anti-Ice
- Wing Anti-Ice
- Lights (Landing / Taxi / Nose / Strobe)
- Flight Director
- Autopilot
- Flight Controls Check
- Launching Flows by Voice
- Launching Checklists by Voice

Tips & Troubleshooting

CrewmateA300 — User Manual

CrewmateA300 is a virtual First Officer companion for the **Airbus A300** in Microsoft Flight Simulator. It listens to your voice, responds with audio callouts, runs automated cockpit flows, and guides you through interactive checklists — just like a real crew member.



Getting Started

Requirements

- Install **an English** Windows speech recognition language pack (Settings → Time & language → Speech). Regional variants (e.g. US, UK, Australia, India) are supported — whichever English recognizer Windows exposes. If several English packs are installed, the active engine follows Windows' installed-recognizer order.
- **Set up Windows Speech Recognition once** before using the Voice Trainer. The trainer teaches Windows your voice, and Windows needs an existing speech profile to train. If the setup has never been run, there is no profile and training cannot start.
- To use the trainer app, set your Display Language to EN-US while training (you can change it back afterward).

Voice Modes

CrewmateA300 supports two voice recognition modes, chosen with **Voice Mode** in Settings:

Mode	How it works
Always listening	The microphone is always listening. Speak naturally.
Push-to-talk	The FO only listens while you hold the **PTT button**. Keep holding until you finish the command, then release.

The mic button on the toolbar is the master switch in both modes. When it is off the FO hears nothing, even with PTT held. The icon shows what the FO can hear:

Toolbar mic	Meaning
Crossed out	Off. The FO hears nothing.
Red	Always listening. The FO hears everything.
Faded red	Push-to-talk, ready. Hold the PTT button to speak.
Green	Push-to-talk, PTT held. The FO is listening.

PTT and Mic On/Off Buttons

Both buttons can be a keyboard key, mouse button 4 or 5, or a button or hat on a joystick, yoke, throttle or game controller. They work while MSFS has focus, including in fullscreen.

- **PTT Button**: hold to talk in Push-to-talk mode.
- **Mic On/Off**: works like clicking the toolbar mic, in either mode. It only works while the sim is connected.

To set one, open **Settings** → **Microphone**, click **Set** and press the key or button. Press **Esc** or click **Cancel** to stop without changing it, and click **×** to clear it.

CrewMate does not take the key or button away from MSFS, so pick one that is not bound to anything in the sim. Analog triggers and axes cannot be bound.

Voice Settings

Setting	What it does
Input Device	Which microphone the speech engine listens to.
Sound Volume	How loud the FO's audio is (0–200; above 100 amplifies).
Voice Sensitivity	How confident the engine must be before accepting a command (50–100). Lower is more tolerant and may accept the wrong command; higher is stricter.
Voice Mode	**Always listening** or **Push-to-talk**. See Voice Modes.
PTT Button	The key or button held to talk in Push-to-talk mode.
Mic On/Off	A key or button that switches the mic on and off, like the toolbar mic.

Tutorial

Assumptions

This tutorial assumes you are parked at the gate with engines off. You are the Captain and PF (Pilot Flying); CrewMate acts as PM (Pilot Monitoring).

Typical preflight timeline (example)

- 45 min: Crew arrives at aircraft and PM takes their seat.
- 43 min: PM starts preliminary cockpit preparation.
- 42 min: PM departs for external walkaround. PF starts cockpit preparation on their side.

COCKPIT PREPARATION

PF	PNF
GEAR PINS + COVERS . . . . . CHECK	
OVHD PANEL	
* ALL WHITE LIGHTS . . . . . EXTINGUISH	
* IRS . . . . . NAV	
FMS LAT/LONG . . . . . CHECK/CORRECT	
ALIGN IRS PROMPT . . . . . PRESS	
* SIGNS . . . . . SET	
* CALLS . . . . . CHECK	
HYD quantities . . . . . NORMAL RANGE	
* FLT RCDR GND CTL . . . . . ON	
ISDU (if installed) . . . . . OFF	
* EXT LTS . . . . . AS REQ	
* PITCH TRIM/YAW DAMPER/ATS . . . . . ON	
ENG 1 FIRE PROTECTION . . . . . CHECK/TEST	
EVAC SIGNAL . . . . . AS REQ	
L/G ANN . . . . . CHECK	
* FUEL panel . . . . . CHECK	
* FUEL X-FEED (if ER flight) . . . . . TEST	
* CVR . . . . . TEST	
CABIN PRESS . . . . . CHECK	
* CREW OXY . . . . . CHECK	
ENG 2 FIRE PROTECTION . . . . . CHECK/TEST	
* EMER EXIT LT . . . . . ARM	
COMPT TEMP . . . . . CHECK/AS REQ	
* COM . . . . . SET	
* AIRFIELD DATA . . . . . OBTAIN	

* FMS INITIALIZATION	
DATA BASE VALIDITY . . . . . CHECK	
NAVAID DESELECTION . . . . . AS REQ	
F-PLN INITIALIZATION . . . . . COMPLETE	
F-PLN A . . . . . CHECK/COMPLETE	
F-PLN B . . . . . CHECK	
SEC F-PLN . . . . . AS REQ	
* FMS DATA INSERTION	
ZFW/CG or ZFCG/BLOCK FUEL . . . . . INSERT	
T. O. DATA . . . . . INSERT	
THR RED/ACC ALT . . . . . SET/CHECK	
. When both pilots seated :	
GLARESHIELD :	
* PFD/ND BRIGHTNESS . . . . . AS REQ	* PFD/ND BRIGHTNESS . . . . . AS REQ
* FPV/FD . . . . . ON FD	* FPV/FD . . . . . ON FD
* VOR/NAV/ILS . . . . . AS REQ	* VOR/NAV/ILS . . . . . AS REQ
* EFIS cont panel . . . . . AS REQ	* EFIS cont panel . . . . . AS REQ
* ND mode/range . . . . . AS REQ	* ND mode/range . . . . . AS REQ
* FCU . . . . . CHECK/SET	* FCU . . . . . CHECK/SET
LATERAL CONSOLE :	
RAT . . . . . CHECK OFF	RAT . . . . . CHECK OFF
OXYGEN MASK . . . . . TEST	OXYGEN MASK . . . . . TEST
GND SVS INTPH . . . . . OFF	

- 30 min: PM returns and starts cockpit preparation on their side.

R	CM1/CM2 INST PANELS :	
	GPWS . . . . . NORM	
	PFD/ND . . . . . CHECK	PFD/ND . . . . . CHECK
	STBY ASI . . . . . CHECK	STBY ASI . . . . . CHECK
	VSI . . . . . CHECK	VSI . . . . . CHECK
	ALTIMETER . . . . . CHECK	ALTIMETER . . . . . CHECK
	* BARO REF . . . . . SET	* BARO REF . . . . . SET
	CLOCK . . . . . CHECK/ADJUST	CLOCK . . . . . CHECK/ADJUST
	CTR INST PANEL	
	STBY ALT . . . . . CHECK	
	* BARO REF . . . . . SET	
	STBY HORIZON . . . . . CHECK	
	* ECAM . . . . . RCL	
	BRK-A/SKID . . . . . NORM/ON	
	* ENGINE INST . . . . . CHECK	
	* OIL QUANTITY . . . . . CHECK	
	* REV and REV UNLK lts . . . . . CHECK	
	* TRP . . . . . CHECK	
	L/G WARN TEST . . . . . PRESS	
	L/G POSITION DET SYS . . . . . AS REQ	
	LDG ELEV . . . . . SET DEPARTURE FIELD ELEV	

PEDESTAL : ADF . . . . . CHECK * RADIOS . . . . . CHECK * WX RADAR . . . . . CHECK OFF * PARK BRK . . . . . CHECK OFF/AS REQ * ATC TRANSPONDER . . . . . STBY/OFF * TCAS (if installed) . . . . . OFF VOR/ILS . . . . . AS REQ * FMS DATA CONFIRMATION	IRS ALIGN . . . . . CHECK INIT PAGE A/B . . . . . CHECK T.O. DATA . . . . . CALCULATE/CONFIRM F-PLN . . . . . CHECK AIRFIELD DATA . . . . . CONFIRM DFDR fault lights . . . . . CHECK EXTINGUISHED
FUEL	* FUEL QUANTITY . . . . . CHECK * FUEL PUMPS . . . . . ON
* TAKE-OFF BRIEFING . . . . . PERFORM	

- 25 min: PF conducts the departure briefing (enter takeoff data in the Takeoff Performance window).
- 10 min: PF calls for the BEFORE START checklist to the line.
- 1 min: CrewMate closes the cockpit door. PF and PM perform before start flow, after that PF calls for the BEFORE START checklist below the line.

BEFORE PUSH BACK or START	
PF	PNF
LOADSHEET ..... CHECK (CM1)	
T. O. DATA . . . . . PREPARE/REVISE	T. O. DATA . . . . . PREPARE/REVISE
SEAT . . . . . ADJUST	SEAT . . . . . ADJUST
CDU . . . . . TAKE-OFF (PF)	CDU . . . . . F-PLN (PNF)
	EXT PWR . . . . . OFF/DISCONNECTED
BEFORE START C/L DOWN TO THE LINE	
PUSHBACK/START CLEARANCE . . . . . OBTAIN	
WINDOW/DOORS . . . . . CLOSED	WINDOW . . . . . CLOSED
PARK BRK . . . . . AS REQ	BEACON . . . . . ON/AUTO
BEFORE START C/L BELOW THE LINE	

Before Start flow pattern

Pushback and Engine Start

- Command PM to start engines (e.g., “Start engine 2). PM will set ignition knob to Start A or B and press the starter.
- When ignition is set to OFF, PF and PM will start the AFTER START flow pattern. If anti-ice will be used, flaps may be left as required.
- On hand signal from ground personnel, call for the AFTER START checklist.

AFTER START	
PF	PNF
IGNITION . . . . . OFF	APU BLEED . . . . . OFF APU . . . . . OFF ENG ANTI ICE . . . . . AS REQ WING ANTI ICE . . . . . AS REQ SLATS/FLAPS . . . . . SET GND SPOILERS . . . . . ARM AIL/RUD TRIM . . . . . ZERO PITCH TRIM . . . . . SET
ECAM . . . . . CHECK STS ECAM DOOR PAGE . . . . . CHECK CLEAR To disconnect . . . . . ANNOUNCE **AFTER START C/L**	

After Start flow pattern

Taxi

- PM announces when the cabin is ready.
- Check flight controls at a convenient time before or during taxi (this is done before arming the autobrake).
- Control check sequence: Full Up, Full Down, Full Left, Full Right, Rudder Full Left, Rudder Full Right.
- After the controls check, PM performs the 2nd part of the TAXI flow pattern.
- After T.O. CONFIG pushbutton is pressed and a cabin report is received, PF calls for the BEFORE TAKEOFF to the line checklist.

TAXI	
PF	PNF
NOSE LIGHT . . . . . TAXI PARK BRK . . . . . OFF EXT LTS . . . . . AS REQ THRUST . . . . . AS REQ BRAKES . . . . . CHECK FLT CTL . . . . . CHECK T. O. DATA/CONDITIONS . . . . . CHECK/REVISE FD . . . . . CHECK ON FMA . . . . . CHECK FLT INST . . . . . CHECK TAKE-OFF BRIEFING . . . . . CONFIRM **BEFORE TO C/L DOWN TO THE LINE**	TAXI CLEARANCE . . . . . OBTAIN ELAPSED TIME . . . . . START ANNOUNCE . . . . . "PRESSURE ZERO" FLT CTL . . . . . CHECK ATC CLEARANCE . . . . . OBTAIN/CONFIRM T.O. DATA/CONDITIONS . . . . . CHECK/REVISE FMS F-PLN . . . . . CHECK FCU ALT/HDG/SPD . . . . . CHECK PROF . . . . . ARM NAV . . . . . ARM FD . . . . . CHECK ON FMA . . . . . CHECK FLT INST . . . . . CHECK RADAR . . . . . AS REQ ATC CODE . . . . . CONFIRM/SET CABIN REPORT ..... OBTAIN (CM1) T.O. CONFIG TEST . . . . . PRESS ECAM . . . . . NORM FOR T. O.

Taxi flow pattern

Line-up & Takeoff

- PF calls for the Line-up flow.

- When line-up clearance is received and the Line-up flow pattern is complete, PF calls for the BEFORE TAKEOFF below the line checklist.
- When cleared for takeoff, announce “TAKEOFF.”

BEFORE TAKE OFF	
PF	PNF
APPROACH PATH . . . . . CLEAR OF TRAFFIC EXT LTS . . . . . SET QFU & THRESHOLD . . . . . CONFIRM **BEFORE TO C/L BELOW THE LINE**	TAKE OFF/LINE UP CLEARANCE . . . . . OBTAIN CABIN CREW . . . . . ADVISE BRAKE PRESSURE . . . . . CHECK BRAKE TEMP (if BRK FAN on) . . . . . CHECK BRAKE FAN (if installed) . . . . . OFF AUTO BRK . . . . . MAX IGNITION . . . . . CONT RELIGHT/AS REQ PACK VALVE . . . . . AS REQ ATC TRANSPONDER . . . . . ON/ALT REP TCAS (if installed) . . . . . TA/RA/AS REQ QFU & THRESHOLD . . . . . CONFIRM

Line-up flow pattern

Acceleration

- The First part of the After-Takeoff flow is triggered when you are above thrust reduction altitude.
- The Second part of the After-Takeoff flow is triggered when the aircraft is clean.
- When the aircraft is clean call for the AFTER TAKEOFF CLIMB checklist to the line.
- When the aircraft is above transition altitude and altimeters are standard call for the AFTER TAKEOFF CLIMB checklist below the line.

TAKE OFF	
PF	PNF
ANNOUNCE . . . . . "TAKE OFF" CLOCK . . . . . START BRAKES . . . . . RELEASE GO LEVERS . . . . . TRIGGERS (CM1)	CLOCK . . . . . START
CM1 keeps his hand on throttles until V1 is reached.	
PFD/ND . . . . . SCAN FMA INDICATION . . . . . ANNOUNCE	PFD/ND . . . . . SCAN N1 (EPR) . . . . . CHECK
• **Below 80 Kts :**	THRUST SET . . . . . ANNOUNCE AIRSPEED/ENG INST . . . . . SCAN
• **At 100 Kts :**	ANNOUNCE . . . . . "100 KTS"
• **At V1 :**	ANNOUNCE . . . . . "V1"
• **At VR :**	ANNOUNCE . . . . . "ROTATE"
• **At VSI positive :**	ANNOUNCE . . . . . "POSITIVE CLIMB"
ORDER . . . . . "GEAR UP"	L/G . . . . . UP GND SPOILERS . . . . . DISARM EXT LTS . . . . . SET
AP . . . . . ON/AS REQ	L/G LEVER . . . . . NEUTRAL ANNOUNCE . . . . . "GEAR UP/NEUTRAL"
• **At thrust red alt** FMA/TRP . . . . . CHECK	ONE PACK . . . . . ON
• **At F speed** ORDER . . . . . "FLAPS ZERO"	FLAPS 0 . . . . . SELECT ANNOUNCE . . . . . "FLAPS ZERO"
• **At S speed** ORDER . . . . . "SLATS RETRACT"	SLATS 0 . . . . . SELECT ANNOUNCE . . . . . "SLATS RETRACTED" 2ND PACK . . . . . ON

AFTER TAKE OFF	
PF	PNF
	APU BLEED . . . . . AS REQ APU . . . . . AS REQ IGNITION . . . . . AS REQ FUEL CTR TK PUMPS . . . . . ON
ANTI ICE . . . . . AS REQ	SIGNS . . . . . AS REQ TCAS (if installed) . . . . . TA/RA
AFTER TO/CLIMB C/L DOWN TO THE LINE	

Climb to 10,000 ft

CLIMB	
PF	PNF
	LAND LTS . . . . . OFF/RETRACT
FMA . . . MONITOR/ANNOUNCE ANY CHANGES	FMA . . . . . MONITOR ANY CHANGES
PF CDU . . . . . PROG	PNF CDU . . . . . F-PLN
FCU/FMS . . . . . SET (IF AP ON)	FCU/FMS . . . . . SET (IF AP OFF)
• **At transition altitude**	
ALTIMETER . . . . . STD	ALTIMETER . . . . . STD
CRZ FL . . . . . CHECK/MODIFY	
AFTER TO/CLIMB C/L BELOW THE LINE	
RADAR . . . . . AS REQ	RADAR . . . . . AS REQ

Climb/10,000 ft flow pattern

Descent Preparation

- PF should insert landing data in the Landing Performance window.

DESCENT PREPARATION	
PF	PNF
	ECAM MEMO/STS . . . . . CHECK
	WEATHER/LANDING INFO . . . . . OBTAIN
	LANDING ELEV . . . . . SET
	FUEL . . . . . CHECK
	LANDING DATA . . . . . PREPARE
FMS . . . . . PREPARE	FMS . . . . . PREPARE
APPROACH BRIEFING . . . . . PERFORM	
	DESCENT CLEARANCE . . . . . OBTAIN
FCU ALT . . . . . CLEARED ALT	
	ANTI ICE . . . . . AS REQ
	IGNITION . . . . . AS REQ

Descent preparation items

10k Descent

INITIAL APPROACH	
PF	PNF
	IGNITION . . . . . CONT RELIGHT/AS REQ
	SIGNS . . . . . SET
	EXT LTS . . . . . AS REQ
POSITIONING . . . . . MONITOR	POSITIONING . . . . . MONITOR
	NAV/COM . . . . . CHECK/SET
ILS . . . . . SELECT/AS REQ	
NAV ACCURACY . . . . . CHECK	
RADAR TILT . . . . . ADJUST	
R TERR ON ND . . . . . AS RQRD	TERR ON ND . . . . . AS RQRD
ND . . . . . RANGE 15NM	ND . . . . . RANGE 15 NM
ND . . MAP FOR ILS (OTHERWISE ROSE OR ARC)	ND . . . . . MAP/AS REQ
• **For CAT II OR CAT III :**	
DH . . . . . CHECK/SET	DH . . . . . CHECK/SET
APPROACH C/L	

10k descent flow pattern

Approach

- After passing the transition level and/or setting the barometric reference, complete the APPROACH checklist.

Landing

- When LDG CONF is set and a cabin report is received, call for the LANDING checklist.
- PF announces “Continue” at minima or “Go-around - flaps” as appropriate.

After Landing

- Disarming the ground spoilers will trigger the After-Landing flow.
- If anti-ice is used, flaps may remain at LDG CONF per procedure.
- Once flows done call for the AFTER LANDING checklist.

AFTER LANDING	
PF	PNF
LANDING LTS . . . . . OFF/RETRACT	ICE PROTECTION . . . . . AS REQ
GND SPOILERS . . . . . DISARM	IGNITION . . . . . OFF
	APU . . . . . START
	TRANSPONDER . . . . . STBY/OFF
	TCAS (if installed) . . . . . STBY OFF
	RADAR . . . . . OFF/TEST
	PITCH TRIM . . . . . 1° NOSE UP
	SLATS/FLAPS . . . . . RETRACT
	BRAKE TEMP . . . . . CHECK
	BRAKE FANS (if installed) . . . . . AS REQ
AFTER LANDING C/L	

After landing flow pattern

Parking

- Turn off taxi lights when turning into the gate, or ask the PM to confirm.
- Shutting down the engines will trigger the Parking flow.
- After the Parking flow pattern completes, PM calls for the PARKING checklist.

PARKING	
PF	PNF
NOSE LIGHT . . . . . OFF/AS REQ	
R PARKING BRAKE ACCU PRESS . . . . . CHECK	
PARKING BRAKE . . . . . ON	APU BLEED . . . . . ON
ENG FUEL LEVERS . . . . . OFF	ELAPSED TIME . . . . . STOP
EXT LTS . . . . . AS REQ	SLIDES DISARMED . . . . . CHECK
	CABIN PRESS . . . . . CHECK
	FUEL PUMPS . . . . . OFF
SEAT BELTS . . . . . OFF	WINDOW HEAT . . . . . OFF
GROUND CONTACT . . . . . ESTABLISH	PROBE HEAT . . . . . OFF
PARKING BRAKE . . . . . OFF/AS REQ	IRS DRIFT . . . . . CHECK
	IRS MSU, 1, 2, 3 . . . . . OFF/AS REQ
	BRAKE TEMP . . . . . CHECK
	BRAKE FANS (if installed) . . . . . AS REQ
CRT's . . . . . DIM	CRT's . . . . . DIM
PARKING C/L	

Parking flow pattern

Securing the Aircraft

- After the last passenger leaves (if securing the aircraft), call for the SECURE AIRCRAFT checklist.

Voice Commands

Speak these phrases clearly during flight. The FO uses partial matching — you don't need to be word-perfect, but include the key phrase.

Preflight Timer

Say	What happens
"Let's prepare the aircraft"	Starts the preflight countdown timer to help you track preparation time.

Ground Engineer

Say	What happens
"Ground from cockpit"	Ground Engineer will ask whats your request
"Cockpit to ground"	Ground Engineer will ask whats your request

Gear

Say	What happens
"gear down"	Lowers the landing gear. **Speed must be at or below 270 knots.**
"gear up"	Raises the landing gear.

Flaps

The FO will confirm speed limits before moving flaps while airborne.

Say	Flap Setting	Max Speed
"slats retract"	Flaps 0/0 (retracted)	—
"slats extend" or "flaps 0"	Flaps 15/0	250 kts
"flaps fifteen"	Flaps 15/15	215 kts
"flaps twenty"	Flaps 15/20	205 kts
"flaps fourty"	Flaps 40	175 kts

Engine Anti-Ice

Say	What happens
"Engine anti ice on"	Turns on engine anti-ice for both engines.
"Engine anti ice off"	Turns off engine anti-ice.

Wing Anti-Ice

Say	What happens
"Wing anti ice on"	Turns on wing anti-ice.
"Wing anti ice off"	Turns off wing anti-ice.

Lights (Landing / Taxi / Nose / Strobe)

Say	What happens
"Landing lights on"	Turns on landing lights.
"Landing lights off"	Turns off landing lights.
"Taxi lights on"	Turns on nose taxi light.
"Taxi lights off"	Turns off nose taxi light.
"Takeoff light on"	Turns on nose takeoff light.
"Strobe lights on"	Turns on strobes.
"Strobe lights auto"	Sets strobes to AUTO.
"Strobe lights off"	Turns off strobes.

Flight Director

Say	What happens
"Flight Director on"	Activates the Flight Director.
"Flight Director off"	Deactivates the Flight Director.

Autopilot

Say	What happens
"Autopilot on"	Engages Autopilot 1.
"Set speed ***or speed select*** "	Sets commanded speed.
"Set heading _ **or heading select** __"	Sets commanded heading.
"Set altitude _ or altitude select _ or set flight level ***or flight level select*** "	Sets commanded altitude.
"Pull speed"	Pulls speed knob to select selected speed.
"Pull speed ___"	Pulls speed knob and sets the commanded speed.
"Pull heading"	Pulls heading knob to select selected heading.
"Pull heading ___"	Pulls heading knob and sets the commanded heading.
"Heading push"	Pushes heading knob to synchronize FCU heading with aircraft heading
"Engage nav"	Selects NAV mode.
"Arm land"	Selects LAND mode.

Say	What happens
"Arm loc"	Selects V/L mode.
"Altitude _ pull or Flight level ___ pull"	Sets commanded altitude and pulls altitude knob.
"Altitude pull or Flight level pull"	Pulls altitude knob.

Flight Controls Check

Say	What happens
"Flight controls check"	Starts the flight controls flow: Up, Down, Left, Right, Rudder Left, Rudder Right

Launching Flows by Voice

Say	Flow launched
"Clear left" or "Left side clear"	Clear Left flow
"Runway entry procedure" or "Clear to line up"	Before Takeoff flow
"Before start procedure"	Before Start flow

Launching Checklists by Voice

Say	Checklist launched
"Before start checklist to the line"	Before start to the line
"Before start checklist below the line"	Before start below the line
"After start checklist"	After Start
"Before takeoff checklist to the line"	Before takeoff to the line
"Before takeoff checklist below the line"	Before takeoff below the line
"After takeoff climb checklist to the line"	Climb to the line
"After takeoff climb checklist below the line"	Climb below the line
"Approach checklist"	Approach
"Landing checklist"	Landing
"After landing checklist"	After Landing
"Parking checklist"	Parking
"Secure aircraft checklist"	Secure Aircraft
"Stop checklist" or "Abort checklist" or "Cancel checklist"	Aborts the active checklist

Tips & Troubleshooting

The FO isn't hearing me

- Check that your microphone is selected and working.
- Adjust the **Voice Sensitivity** setting.
- In Push-to-talk mode, check that a **PTT Button** is set and that the toolbar mic turns green while you hold it.

My PTT or Mic On/Off key does nothing while MSFS has focus

- MSFS is probably running as administrator. Run CrewMate as administrator too.

The FO ignores everything I say before departure

- Between T-42 and T-32 on the preflight timer the FO is outside on the walkaround and does not answer. The **FO outside** indicator is shown while this is the case. Ground engineer calls still work.

The FO keeps repeating the challenge

- Your response didn't match the expected phrase. Listen to the challenge and use one of the phrases listed in this manual (voice matching can be tuned in settings).
- If a physical switch must be set first (e.g., parking brake), set it in the cockpit before responding.

The Voice Trainer says training failed

- "Value does not fall within the expected range" means Windows has no speech profile for your account. Run Windows Speech Recognition setup once, then start the trainer again.
- The trainer also needs the Windows Display Language set to EN-US while it runs.

How do I stop a checklist mid-way?

- Say **"Stop checklist"**, **"Abort checklist"**, or **"Cancel checklist"** at any time.

Can I run flows and checklists manually without voice?

- Yes. Both can be triggered from the **Flows** and **Checklist** panels in the app UI.