


Steps to Create EC2 Instance in AWS (Amazon)

Follow the below steps to create an EC2 instance in AWS (Amazon):

Step 1: Login and Navigate to EC2 Dashboard


- Log in to your AWS Management Console.
- From the Services menu, choose EC2 under the Compute section.
- Under Resources, click Instances (Running) to view running instances (if any).



Under Resources >> Click on "Instances running" -- It will show if any [EC2 instances](#) are running or not.

Step 2: Launch a New Instance

- Click Launch Instance.
- On the "Launch an Instance" page, enter a name for your instance (e.g., my-first-ec2-server).
- You'll now configure your server settings.



Naming instance

Step 3: Choose Amazon Machine Image

- Select an Amazon Machine Image (AMI), which is the OS for your server.

- For beginners, choose Amazon Linux 2, Ubuntu, or Windows, depending on your needs.
- AMIs come preconfigured with OS and some software like templates.

▼ Application and OS Images (Amazon Machine Image) [Info](#)

An AMI is a template that contains the software configuration (operating system, application server, and applications) required to launch your instance. Search or Browse for AMIs if you don't see what you are looking for below

Quick Start

Amazon Linux

macOS

Ubuntu

Windows

Red Hat

Browse more AMIs

Including AMIs from AWS, Marketplace and the Community

Amazon Machine Image (AMI)

Amazon Linux 2 AMI (HVM) - Kernel 5.10, SSD Volume Type

ami-0a606d8395a538502 (64-bit (x86)) / ami-0f822d3c9e0532335 (64-bit (Arm))

Virtualization: hvm ENA enabled: true Root device type: ebs

Free tier eligible

Selecting AMI

Step 4: Select Instance Type

- Select the [instance type](#) (defines CPU and memory).
- For Free Tier, choose t2.micro — 1 vCPU and 1 GB RAM.
- Avoid selecting higher types like t2.small, t3.medium, etc., unless needed, as they may incur charges.

64-bit (x86)

ami-000125ea030277031

Amazon Linux 2 AMI

▼ Instance type [Info](#)

Instance type

t2.micro

Family: t2 1 vCPU 1 GiB Memory

On-Demand Linux pricing: 0.0116 USD per Hour

On-Demand Windows pricing: 0.0162 USD per Hour


Free tier eligible

[Compare instance types](#)

Select instance type

Step 5: Configure Key Pair

1. EC2 instances use SSH key pairs for secure access.
2. Click Create new key pair:
 - Enter a name.
 - Choose file format: .pem for [Linux](#)/macOS or .ppk for Windows (for PuTTY).
 - Download the key file and save it securely (you won't be able to download it again).
3. Select the created key pair from the dropdown.



The screenshot shows the 'Create key pair' dialog box in the AWS Management Console. The dialog has a title bar with a close button (X). Below the title bar, there is a heading 'Create key pair' and a sub-heading 'Key pairs allow you to connect to your instance securely.' followed by instructions: 'Enter the name of the key pair below. When prompted, store the private key in a secure and accessible location on your computer. **You will need it later to connect to your instance.** [Learn more](#) [external link icon]'. Below this is a text input field labeled 'Key pair name' with a placeholder 'Enter key pair name'. A note below the field states: 'The name can include upto 255 ASCII characters. It can't include leading or trailing spaces.' Underneath is the 'Private key file format' section with two radio button options: '.pem' (selected) with the description 'For use with OpenSSH' and '.ppk' with the description 'For use with PuTTY'. At the bottom right are two buttons: 'Cancel' and 'Create key pair' (highlighted in orange).

Creating key pair

Step 6: Network and Storage Configuration

1. **Network Settings:** Use the default VPC and subnet unless you have specific networking needs.
2. **Firewall (Security Group):** Allow SSH (port 22) for Linux or RDP (port 3389) for Windows.
3. **Storage Settings:**

- Free Tier allows up to 30 GB of General Purpose SSD (gp2).
- Keep default (8 GB) or increase as needed.

▼ **Configure storage**
[Info](#)
Advanced

1x GiB ▼ Root volume (Not encrypted)

Free tier eligible customers can get up to 30 GB of EBS General Purpose (SSD) or Magnetic storage

Add new volume

The selected AMI contains more instance store volumes than the instance allows. Only the first 0 instance store volumes from the AMI will be accessible from the instance

0 x File systems Edit

Step 7: Review and Launch

- Review all configurations to ensure they are Free Tier eligible.
- Click Launch Instance.
- You will see a confirmation page. Click View Instances to see your new server being initialized.

▼ Root volume (Not encrypted)

p to 30 GB of EBS General Purpose (SSD) or Magnetic storage

re volumes than the instance allows. Only the first 0 instance store
n the instance

Edit

New security group

Storage (volumes)

1 volume(s) - 30 GiB

Free tier: In your first year includes 750 hours of t2.micro (or t3.micro in the Regions in which t2.micro is unavailable) instance usage on free tier AMIs per month, 30 GiB of EBS storage, 2 million IOs, 1 GB of snapshots, and 100 GB of bandwidth to the internet.

Cancel

Launch Instance