### **CLI VLAN Commands**

## Creating a VLAN

Task	IOS Command
Create a VLAN with a valid ID number (1 – 4095)	S1(config)# vlan vlan-id
Specify a unique name to identify the VLAN	S1(config-vlan)# name vlan-name
Return to the privileged EXEC mode	S1(config-vlan)# end

## **VLAN Port Assignment Commands**

Once a VLAN is created, we can then assign it to the correct interfaces

Task	IOS Command
Enter interface configuration mode	S1(config)# interface interface-id
Set the port to access mode	S1(config-if)# switchport mode access
Assign the port to a VLAN	S1(config-if)# switchport access vlan vlan-id
Return to the privileged EXEC mode	S1(config-vlan)# end

# Verify VLAN information

Show vlan [brief | id vlan-id | name vlan-name | summary ]

Task	IOS Command
Display VLAN name, status, and its ports, one	S1# show vlan brief
VLAN per line	
Display information about the identified VLAN ID	S1# show vlan vlan-id
number	
Display information about the identified VLAN	S1# show vlan vlan-name
name.	
Display VLAN summary information.	S1# show vlan summary

#### Delete VLANs

Task	IOS Command
Delete a specific VLAN	S1(config)# no vlan vlan-id
Delete all VLANS	delete flash:vlan.dat or delete vlan.dat
Reload the switch when deleting all VLANs	

# **Trunking Configuration Commands**

Task	IOS Command
Enter the interface configuration mode.	S1(config)# interface interface-id
Set the port to permanent trunking mode	S1(config-if)# switchport mode trunk
Sets the native VLAN to something other than	S1(config-if)# switchport trunk native vlan
VLAN 1	vlan-id
Specifiy the list of VLANs to be allowed on the	S1(config-if)# switchport trunk allowed vlan
trunk link.	vlan-list (eg vlan-list 10,20,30, 42)
For a STATIC trunk use the command	S1(config-if)#switchport nonegotiate
For DYNAMIC trunk see the table below for	S1(config-if)#switchport mode option
option	

		One end of the cable			
		Dynamic Auto	Dynamic Desirable	Trunk	Access
The other end	Dynamic Auto	Access	Trunk	Trunk	Access
of the cable	Dynamic Desirable	Trunk	Trunk	Trunk	Access
	Trunk	Trunk	Trunk	Trunk	Limited Connectivity
	Access	Access	Access	Limited Connectivity	Access

# Verify Trunk Configuration

Task	IOS Command
Show the trunk configuration	S1# show int int-id switchport

# Reset the Trunk to the Default State

Task	IOS Command
Enter the configuration for the interface	S1(config)# int int-id
Reset the trunk settings with the NO command	S1(config-if)# no switchport trunk allowed
	S1(config-if)# no switchport trunk native vlan
Reset the trunk to an access mode	S1(config-if)# switchport mode access