


1 Start directly in the editor

In the launcher, choose **Editor** (map icon), below **Sessions** and above **Mods**.



Original screenshot: German launcher. The visible folder path and launcher version label are not installation instructions.

Create a new blank map

Kartenname (map name): required; also determines the folder name. Existing names are rejected.

Autor / Beschreibung (author / description): optional; saved in the map description.

Speicherort (destination): shown below the fields. Maps are created in the active openOMSI content folder's maps directory, outside the original OMSI 2 installation.

Karte erstellen und bearbeiten (create and edit): creates one flat 300 × 300 m tile with a base texture and opens the editor. No bus or driving duty is needed.

2 Maps and camera position

Open an existing map

Select a map under **Vorhandene Karte bearbeiten**, then click **Im Editor öffnen**. End any running session first. The map opens with a free camera and the editor already active.

Start above the terrain

With no saved editor position, the standard is the same elevated view as on a new map: **35 m above the terrain** at the start location, looking **30° downward**. If the map's initial location lies outside existing tiles, the nearest tile is used.

Return to the last editor location

Position, direction and zoom are remembered per map when you **save, switch off the editor or end the session normally**. The next direct editor start restores that location. Height is raised to at least 35 m above the current terrain when needed; higher saved positions are retained.

Save and reopen

Fly to a recognisable location, make a desired edit and press **Ctrl+S**. Close the session and reopen the same map through **Editor**. Check the edit and camera position. Other maps retain their own positions.

What the camera bookmark saves

Camera data is stored locally under `~/.openomsi/editor-views`, not in the map. It does not save unsaved map edits. A crash may lose the latest location that has not yet been recorded. Normal driving starts are unchanged.

Language and available tools

The editor does not yet fully follow in-game language changes; some labels remain German. The German and English follow the language selected in the game. Other languages are not fully translated yet. Junction and roundabout builders are included. New features are covered on pages 13-16 .

3 Open the editor during play

Edit the currently loaded map directly during gameplay.


New: direct editor start and blank maps - see pages 1-2.

Press **F4** to switch to camera mode. Then press **Esc** to open the pause menu.


World options → Tools → Objekteditor → Open

This opens the Object Editor. Press T to switch to the Spline Editor for roads (page 10). Screenshots use German or mixed-language labels; this guide includes the relevant German names.


PAUSE MENU




WORLD OPTIONS



TOOLS: OPEN THE OBJECT EDITOR



4 Interface and objects



Current screenshot with German labels; lower panel area is cropped.

Tool panel

Catalogue, Build junction and Roundabout open the object tools. Below are new tiles, terrain editing, map reload and spline connection checks.

Panel and commands

Drag the panel by its header. “All commands” expands the shortcuts; “Fewer commands” collapses them. Scroll to see more commands.

Selection and information

The information bar shows the editing mode and selected object. Click or Enter selects; Tab cycles through hits.

Copy and place

Ctrl+C copies and Ctrl+V starts placement. Ctrl+R uses the last placed object. Multi-place allows repeated placement; Esc stops placement.

Rotation and tilt

N/M rotates, U/O changes height. Home/End changes builder object pitch; Page Up/Down changes bank. Hold Shift for finer adjustments. See page 15.

Save

Ctrl+S saves the map. Save desired changes before reloading.

5 Adding map tiles

“Neues Tile” opens the map expansion window. Each tile measures 300 × 300 m.

Karte erweitern

Blickrichtung: Nord · Raster: 300 × 300 m

Nord ↑ · West ← · Ost → · Süd ↓

-20, 14 —	-19, 14 —	-18, 14 —	-17, 14 —	-16, 14 —
-20, 13 —	-19, 13 —	-18, 13 —	-17, 13 —	-16, 13 —
-20, 12 —	-19, 12 —	-18, 12 frei	-17, 12 frei	-16, 12 —
-20, 11 frei	-19, 11 frei	-18, 11 vorhanden	-17, 11 vorhanden	-16, 11 frei
-20, 10 vorhanden	-19, 10 vorhanden	-18, 10 vorhanden	-17, 10 vorhanden	-16, 10 vorhanden

← West

Nord ↑

Süd ↓

Ost →

Grün: eingetragen · Blau: Auswahl · Grau: frei

Pfeiltasten: Kartenausschnitt · Enter: anlegen · Esc: schließen

Neues Tile (-18, 12)

Randhöhen übernehmen

Eigene Höhe

Gelände übernimmt die Nachbar-Randhöhen
Randprofil weich über das neue Feld fortführen

Freies Nachbarfeld wählen. Grün = vorhanden, Blau = Auswahl.

Tile anlegen

Schließen

Choose a free neighbouring tile

Green marks existing tiles; “frei” marks free positions. Your selection is dark grey with an orange side marker. The on-screen legend still says “blue”. Each cell shows its coordinates. Use the direction buttons or arrow keys to move the map area.

Set the terrain height

“**Randhöhen übernehmen**” takes the edge heights of neighbouring tiles and smoothly extends their profiles across the new tile. “**Eigene Höhe**” lets you specify a height yourself.

Create the tile

Click “**Tile anlegen**” or press **Enter**. “Schließen” or **Esc** closes the window.

Choose a free position beside the existing map to add a connected area for building.

6 Editing the terrain

Change the ground shape or switch between heights and textures.



Height tools

Open “Gelände bearbeiten”. The “Höhen” tab provides tools to raise, lower, level and smooth the ground. “Texturen” switches to textures.

Brush settings

Radius: size of the affected area.

Stärke / Sek.: strength per second.

Weicher Rand: soft edge falloff.

Zielhöhe: target height for applicable tools.

Tile-Schritt: step size for whole tiles.

Pick a height or tile

“Höhe aufnehmen” samples an existing terrain height.

“Tile auswählen” selects a map tile for the tile tools; its coordinates appear below.

Edit entire tiles

Raise or lower the tile, or set it to the target height.

“Übergang zu Nachbarn” controls the transition width towards neighbouring tiles.

Paint and save

Hold the **left mouse button** to paint. Hold **Shift** for finer adjustments. “Rückgängig” and “Wiederholen” undo and redo changes. Save with **Ctrl+S**.

“Zurück zum Bauen” returns to building mode.

The “Texturen” tab is explained in detail on page 7.

7 Painting terrain textures

Open "Gelände bearbeiten", then select "Texturen".



Choose a texture and layer

The arrows switch terrain texture layers. "Texturkatalog ..." opens texture selection. The current layer and texture name appear above these controls.

Paint or erase

Select "Malen" and hold the left mouse button over the terrain. "Radierer" removes the selected overlay layer. It is disabled on layer 0: painting the base texture removes overlaid paint instead.

Brush settings

"Radius (m)" sets brush size; the mouse wheel also changes it. "Stärke / Sek." controls how quickly paint is applied or erased. "Weicher Rand (%)" controls the soft transition at the edge.

Pick an existing texture

Click "Pipette: Textur aufnehmen", then click the terrain. The editor selects the sampled terrain texture layer.


Undo and save

Use "Rückgängig" / "Wiederholen" to revise brush strokes. Save with "Speichern (Strg+S)". "Zurück zum Bauen" returns to the building tools.

Tip: begin with a small brush and low strength. Terrain textures change the ground surface; they do not select the asphalt texture of a spline or junction.

8 The asset catalogue

Open “Katalog (P)” in the tool panel, or press P.



Search and filter

The top tabs switch between **Splines & Junctions** (“Splines & Kreuzungen”), **Objects** (“Objekte”) and **Textures** (“Texturen”). Categories narrow the results. Search by name or file path; “Leeren” clears the search.

Preview and selection

Results appear as thumbnails on the left. Click an item to see a larger preview, its name and file path on the right. The buttons below the preview rotate it.


Select and browse

Click **“Auswählen”** (Select) or press **Enter** to use the highlighted item. “Zurück” and “Weiter” move between result pages. **Esc** closes the catalogue.

“Kreuzung bauen” opens the junction builder. “Alle Vorschauen prüfen” starts a check of the catalogue previews.

9 Splines in the catalogue

Use "Splines & Kreuzungen" to find road profiles and junction components.



Filter and search

Choose categories such as "Spline-Profile", "Kreuzungen" or "Verkehrslogik". Search by name or file path and use the sorting controls to narrow the list.

Understand the preview


A traffic-logic preview represents paths, not necessarily a visible road model. Blue means road, green footpath, violet rail and yellow flight path. Read the preview description on the right.

Use the selection

Click "Auswählen" or press Enter. "Kreuzung bauen" opens the junction builder; its texture controls are explained on page 12.

10 Switching to the Spline Editor

Edit roads and other splines instead of individual objects.



Press T to switch modes

In the Object Editor, press **T**. The information bar now reads “Spline-Editor”. “Keine Straße ausgewählt” means no road is selected.

Select a road

Click the road you want to edit. The information bar shows details of your selection. Basic controls and shared tools remain largely the same.

Additional road tools

The lower panel includes:

- Smooth edge: Rand glätten (F8)
- Smooth wider: Breiter glätten (Shift+F8)
- Fit to ground: An Boden anpassen (F6)
- Objects along the road: Objekte entlang der Straße
- Sidewalk along the road: Gehweg entlang der Straße

Press **T** again to return to the Object Editor.

A simple workflow


Select → Edit → Save → Check connections

Save the changes you want to keep with **Ctrl+S**. After reloading the map, inspect the edited areas. After changing roads, refresh the connection check using “Erneut prüfen”.

This quick guide covers getting started and the windows shown. Detailed instructions for the sidewalk, connection and road tools are outside the scope of this overview.

11 Building a junction

Design a junction, save it and place it on the map.



Shape and arms

Choose **“T-Kreuzung”** (T-junction) or **“Vierarmkreuzung”** (four-arm junction). Select **Arm A to D** to edit it; D is disabled for a T-junction. Adjust width, length, direction, bend and sidewalk width.

Textures and preview

“Asphalt wählen ...” and “Gehweg wählen ...” select road and sidewalk textures. If you selected a road in Spline mode first, “Breite / Textur vom gewählten Spline” copies its width and texture. The 3D preview is on the right; AI paths are shown in blue.

Toggle centre lines with “Mittellinien”. “Rückgängig” and “Wiederholen” undo and redo changes. “Projekt laden ...” opens an existing project. Click **“Speichern & einsetzen”** (Save & place) to save the junction and then place it on the map.

Texture crop controls: [page 12](#). Terrain texture painting: [page 7](#).

12 Adjusting junction textures

Editor 0.7.10-pre on openOMSI 0.2.20. These controls affect the road texture across all junction arms.

Control diagram in the current style (not a screenshot)

Ausschnitt U von

-

0.25

+

Step: 0.01

Ausschnitt U bis

-

0.75

+

Step: 0.01

Texturbreite (m)

-

6.52

+

Step: 0.01

Choose the step size

Click the value and type a number; comma and decimal point are accepted. Enter applies it. Plus/minus also applies a valid entry before changing it. The number of typed decimal places sets the step: 6.5 → 0.1; 6.52 → 0.01; 6 → 1. Up to four decimal places are supported.

Click a digit to select its place: in 6.52, clicking 6 selects steps of 1, clicking 5 selects 0.1, and clicking 2 selects 0.01. The selected digit is underlined. Use + or - to change the value. Each field remembers its own step.

What the fields do

Ausschnitt U von

Start of the horizontal texture crop. $U = 0$ is the left edge; $U = 1$ is one full image width.

Ausschnitt U bis

End of the crop. Example: 0.25 to 0.75 uses the middle half. A smaller end than start mirrors the crop; values outside 0 to 1 repeat the texture.


Texturbreite (m)

Width in metres covered by one repetition of the selected crop. Larger values stretch it wider; smaller values repeat it more often. The road width stays unchanged.

Limits: U from/to -16 to 16; the values must differ by at least 0.0001. Texture width: 0.25 to 100 m. Undo/Redo also covers these changes. Esc cancels a pending text entry; use Undo for changes already applied with +/- . Inspect the preview, then save or update the placed junction.

13 Build a roundabout

Open “Roundabout” in the tool panel. To use a road’s width and texture, select that road in spline mode before opening the builder.



Roundabout builder 0.7.10-pre: new object with four approaches. Screenshot labels are German.

From design to map

Choose 3 or 4 approaches, enter a name and select arm A/B/C/D. Set dimensions and textures; page 14 explains the controls. Check the 3D preview and, if needed, the AI paths.

Save and edit again

“Save & place” creates the object for placement. Place it and save the map with Ctrl+S. Select a placed object and reopen the builder to edit it. Road connections: page 16. Reload the map to refresh AI paths.

14 Roundabout: fields and controls

3 / 4 approaches; Arm A-D	Choose the number of approaches and the arm to edit. Road width, length and direction apply to that arm.
Name	Name of your custom roundabout project.
Road width (m)	Width of the selected approach, not the circulating lane.
Length from centre (m)	Distance from the roundabout centre to the outer end of the selected approach.
Direction (°)	Orientation of the selected approach around the centre.
Island radius (m)	Radius of the central island. Larger values enlarge the island and roundabout.
Ring road width (m)	Width of the circulating roadway around the island.
Island height (m)	Height of the island above the roadway.
Texture length (m)	Length of one texture repeat along the roadway. Larger values stretch the pattern.
Width / texture from selected spline	Uses the previously selected road's width and texture. Select a road in spline mode first.
Choose asphalt / island texture	Select textures for the roadway and central island.
Island edge line	Turns the visible island edge marking on or off.
Show AI paths / Rotate preview	Shows traffic paths or rotates the preview view. Rotate a placed object separately with N/M.
Load project; Undo / Redo	Load a saved builder project or undo/redo changes within the builder.
Crop U from / to; Texture width	Image crop and repeat width across the road. Click a digit and use +/-; see page 12 for details.

Input: click a numeric value, type and press Enter. The +/- buttons change dimensions. Limits: single circulating lane, no turbo roundabouts; direction follows the map's left-/right-hand traffic. Check AI traffic after reloading.

15 Rotation, height and tilt

Select a placed object in **object mode**. Tilt controls support builder junctions and roundabouts. Keep the companion **junction.junction.json** beside the object.

Keys	Action	Normal / Shift
N / M	Rotate	5° / 0.5°
U / O	Lower / Raise	0.5 m / 0.05 m
Home / End	Pitch + / -	0.5° / 0.05°
Page Up / Down	Bank + / -	0.5° / 0.05°
I / J / K / L	Move	0.5 m / 0.05 m
Delete	Delete / Restore	
Ctrl+S	Save map	

Check the angles

The information bar shows pitch and bank. Axes follow the object, not the camera. Copying and placement preserve the angles. Each angle is limited to -89°...+89°; road connections may reach geometric limits earlier.

Backspace and saving

For connected builder objects, Backspace restores the combined pose and road edits. Without connected approaches it first resets changed tilt. Restore deleted objects with Delete first. Save and reload the map to refresh traffic paths.

Spline mode: comma/period still adjust curvature and Home/End adjust gradient. Keyboard rotation in object mode uses N/M only.

16 Connect roads and follow changes

Applies to builder junctions and roundabouts. A road that merely touches the object is **not yet an explicit connection**.

1. Select the approach road in spline mode.
2. Switch to object mode and select the placed builder object.
3. Open the appropriate builder and choose approach A/B/C/D.
4. Choose “Connect road to selected arm” to prepare the preview.
5. Check the preview and update the placed object to apply it. Closing the builder discards the preparation.
6. Save with Ctrl+S and reload the map to refresh traffic paths.

What follows automatically

Explicitly connected approaches follow moving, rotating, raising and tilting the object. Their far endpoints stay fixed. New connections to tilted objects are also supported. Backspace restores combined pose and approach edits together.

If a connection cannot be fitted

All approaches are checked before applying a pose change. If one fit fails, object and road geometry remain unchanged. Smaller changes, longer approaches or a matching transition spline may help. Repair an old broken link by selecting its road and reconnecting the correct arm.

Limits: standard OMSI maps; at most 50 m gap and 30° direction mismatch, compatible profiles and sufficient transition length. Reset protects separately edited roads. Non-editable Chrono or old-format roads are not changed.

17 Checking spline connections

Find open ends and suspicious connections across the whole map.

Spline-Verbindungen · ganze Karte

Erneut prüfen
Marker: AN
Nur offene / auffällige Enden
Schließen

Rot: Fehler
Gelb: offen
Grau: ungeprüft
Grün: verbunden

102221 Splines · Enden: 116991 Fehler / 42292 offen / 0 ungeprüft / 45159 verbunden

Stand der letzten Prüfung – nach Änderungen erneut prüfen

FEHLER · ID 812251 · Start · Tile (-43, 0)

Eigene ID mehrfach vergeben

FEHLER · ID 812251 · Ende · Tile (-43, 0)

Eigene ID mehrfach vergeben

FEHLER · ID 812254 · Start · Tile (-43, 0)

Eigene ID mehrfach vergeben

FEHLER · ID 812254 · Ende · Tile (-43, 0)

Eigene ID mehrfach vergeben

FEHLER · ID 812255 · Start · Tile (-43, 0)

Eigene ID mehrfach vergeben

FEHLER · ID 812255 · Ende · Tile (-43, 0)

Eigene ID mehrfach vergeben

FEHLER · ID 812256 · Start · Tile (-43, 0)

Eigene ID mehrfach vergeben

FEHLER · ID 812256 · Ende · Tile (-43, 0)

Eigene ID mehrfach vergeben

Zurück
Seite 1 / 19911 · Zeile anklicken: zur Stelle
Weiter

Gelb kann ein absichtliches Ende sein. Es wird nichts automatisch verändert.

15 cm Endpunktteranz · Marker in der 3D-Ansicht · Esc schließt diese Liste

Red: an error, such as a duplicate ID. **Yellow:** an open end, which may be intentional. **Grey:** unchecked. **Green:** recognised as connected.

Each entry lists the spline ID, start or end, tile coordinates and the finding. **Click an entry to jump to that location.** “Zurück” and “Weiter” move between result pages.


“**Erneut prüfen**” runs the check again after edits. “**Marker: AN/AUS**” toggles markers in the 3D view. The filter “Nur offene / auffällige Enden” limits results to open or suspicious ends.

Endpoint tolerance: **15 cm**. The check does not change anything automatically. “Schließen” or **Esc** closes the list.

18 Design, cursor and updates

Guide: Editor 0.7.10-pre on openOMSI 0.2.20. Direct editor start: pages 1-2. Roundabouts, tilt and road connections: pages 13-16 .

Style diagram - not an in-game screenshot



One bright cursor

Since 0.7.3-pre, a white system crosshair with a dark edge replaces the additional software marker. Mouse steering is suspended while the editor is open. This is intended to prevent overlapping pointers when selecting objects or opening panels.

Updates and current status

Close the editor and game before updating. Follow the instructions included with that package and back up maps. Source updates and ready-to-run downloads are different packages.

Launch the Linux download with:

```
bash start-editor.sh "/path/to/openOMSI-game-folder"
```

The game folder must be configured and contain OMSI 2 content. Game content is not included with the editor.

Uploading source changes does not update the public download. A new package must be published as a GitHub release.

For 0.7.10-pre, the project owner reported successful GitHub checks on Linux and Windows and manual testing on Linux. This does not establish an interactive Windows test; this package targets Linux x64.

Existing screenshots may show older version labels and German text. The added pages describe the current features. Languages other than DE/EN remain incomplete.