# 1 Welcome to the openOMSI Editor

Editor 0.8.2-pre | Windows / Linux | 14.10.2026

Build maps directly in the game
This operating guide covers openOMSI Editor 0.8.2-pre, based on openOMSI 0.2.38. Preview packages are available for Windows x64 and Linux x64.

Requirements
An original OMSI 2 installation and its content are required. The editor package does not include third-party maps, vehicles or OMSI 2 content.

Choose a workspace
Use Objects, Splines and AI paths at the top of the toolbox. Switching replaces the current toolbox with the selected workspace. General map tools are in Objects, road tools in Splines and traffic-path tools in AI paths.

Using this guide
Objects: page 6. Splines: page 12. Road and terrain: page 13. AI paths: from page 23. Save and test: page 32. Startup and updates: pages 33-34.


Before editing
Back up the map, save deliberately and check your changes. Older detail screenshots may show earlier versions or layouts. Current workspace overviews are on pages 6, 12 and 27.

# 2 Contents


01 Welcome to the openOMSI Editor 1
02 Contents 2
03 Start directly in the editor 3
04 Maps and camera position 4
05 Open the editor during play 5
06 Interface and objects 6
07 Adding map tiles 7
08 Editing the terrain 8
09 Painting terrain textures 9
10 The asset catalogue 10
11 Splines in the catalogue 11
12 Select and move spline groups 12
13 Fit road and terrain 13
14 Bridge / tunnel / underground 14
15 Building bridges and tunnels 15
16 Junction builder 16
17 Adjusting junction textures 17
18 Roundabout builder 18
19 Roundabout: fields and controls 19
20 Rotation, height and tilt 20
21 Connect roads and follow changes 21
22 Checking spline connections 22
23 Working with AI paths 23
24 Create AI driving paths 24
25 AI paths along a road 25
26 Shape AI paths with the mouse 26
27 Select and edit AI paths 27
28 Edit existing paths 28
29 Connections and opposing traffic 29
30 Additional AI connection 30
31 AI paths: help and diagnostics 31
32 Save and test with traffic 32
33 Version, startup and updates 33
34 Check and install updates 34

# 3 Start directly in the editor

In the launcher, choose Editor below Sessions and above Mods.




## Create a new blank map

**Map name:** required; it also determines the folder name. Existing names are rejected. **Author (optional)** and **Description:** saved in the map description.

**Save location:** maps are created in the active content folder's maps directory, outside the original OMSI 2 installation. The folder shown in the screenshot is an example, not an installation requirement.

**Create and edit map:** creates one flat 300 × 300 m tile with a base texture and opens the editor. No bus or driving duty is needed. Use **Edit existing map** to choose an existing map, then **Open in editor**.

# 4 Maps and camera position

## Open an existing map

Choose a map under **Edit existing map**, then click **Open in editor**. End any running session first. The map opens with a free camera and the editor already active.

## Start above the terrain

Without a saved editor position, the default is 35 m above the terrain at the start location, looking 30° downward. If the initial location is outside existing tiles, the nearest tile is used.

## Return to the last editor location

Position, direction and zoom are remembered per map when you save, switch off the editor or end the session normally. The next direct editor start restores that location. Height is raised to at least 35 m above the current terrain when needed; higher saved positions are retained.

## Save and reopen

Fly to a recognisable location, make an edit and press Ctrl+S. Close the session and reopen the same map through Editor. Check the edit and camera position. Other maps retain their own positions.

## What the camera bookmark saves

Camera data is stored locally under ~/.openomsi/editor-views, not in the map. It does not save unsaved map edits. A crash may lose a location not yet recorded. Normal driving starts are unchanged.

## Language and available tools

The tools described here support German and English. Select English in the game settings for the interface shown in this guide. Other translations remain incomplete. Junction and roundabout builders are included; see pages 16-19


# 5 Open the editor during play

Edit the currently loaded map directly during gameplay.


Press **F4** to switch to camera mode. Press **Esc** to open the pause menu.

Choose **World options → Tools → Object editor → Open**. This opens the Object Editor. Press **T** to switch to the Spline Editor for roads (page 12). Direct editor startup and blank maps are explained on pages 3-4.


## PAUSE MENU




## WORLD OPTIONS





## TOOLS: OPEN THE OBJECT EDITOR



# 6 Interface and objects

Editor 0.8.2-pre | Windows / Linux | 14.10.2026




Switch workspace
Click Objects, Splines or AI paths at the top. The current toolbox is replaced by the selected editing workspace. T switches between object and spline mode.

General tools
Object catalogue (P) opens the object browser. New tile expands the map. Edit terrain opens height and texture tools. Reload map loads saved changes.


Selection and camera
Click / Enter selects; Tab cycles through hits. WASD / Q E moves the camera. I J K L moves an object, U / O changes height and N / M rotates it.

Copy and edit text
Ctrl+C copies and Ctrl+V starts placement. Ctrl+R places the last object again. Repeat placement allows more copies; Esc finishes. Edit text opens the object text fields.

Windows and saving
Drag the title bar with the left mouse button held. Left returns the toolbox to the left side. Ctrl+S saves the map.

# 7 Adding map tiles

New tile opens the map expansion window. Each tile measures 300 × 300 m.




## Choose a free neighbouring tile

Green marks existing tiles; **free** marks unused positions. The selection is dark grey with an orange side marker; the legend still calls it blue. Each cell shows coordinates. Use the direction buttons or arrow keys to move the map view.

## Set the terrain height

**Use edge heights:** take neighbouring edge heights and smoothly extend their profiles across the new tile. **Custom height:** specify a height yourself.

## Create the tile

Click **Create tile** or press Enter. **Close** or Esc closes the window. Choose a free neighbouring position to add a connected area for building.

# 8 Editing the terrain

Use Edit terrain to change the ground shape or switch between Heights and Textures.




English interface

## Height tools

**Raise hill**, **Lower hollow**, **Level** and **Smooth** shape the ground. **Paint height** uses the target height; **Fine smoothing** provides gentler smoothing.

## Brush settings

**Radius (m):** affected area. **Strength / sec.:** amount per second. **Soft edge (%):** edge falloff. **Target height (m):** height for applicable tools. **Tile step (m):** step size for whole tiles.

## Pick a height or tile

**Sample height** picks an existing ground height. **Select tile** selects a map tile; its coordinates appear below.

## Edit entire tiles

**Lower tile** and **Raise tile** change the whole tile. **Set entire tile to target height** uses the target value. **Blend with neighbours** controls the transition width.


## Paint and save

Hold the left mouse button to sculpt; hold Shift for finer adjustments. The mouse wheel changes brush size. **Undo / Redo** revises changes. **Save (Ctrl+S)** saves the map.

**Back to building** returns to building tools. **New tile**, **Reload map …** and **Check spline connections …** open the related map tools.

# 9 Painting terrain textures

Open Edit terrain, then select Textures.




English interface

## Choose a texture and layer

The arrows switch terrain texture layers. **Texture catalogue …** opens texture selection. The current layer and texture name appear above these controls.

## Paint or erase

Select **Paint** and hold the left mouse button over the terrain. **Eraser** removes the selected overlay layer. It is disabled on layer 0: painting the base texture removes overlaid paint instead.

## Brush settings

**Radius (m)** sets brush size; the mouse wheel also changes it. **Strength / sec.** controls how quickly paint is applied or erased. **Soft edge (%)** controls the transition at the edge.

## Pick an existing texture

Click **Eyedropper: pick texture**, then click the terrain. The editor selects the sampled terrain texture layer.


## Undo and save

Use **Undo** / **Redo** to revise brush strokes. **Save (Ctrl+S)** saves; **Back to building** returns to the building tools.

Begin with a small brush and low strength. Terrain textures change the ground; they do not select the asphalt texture of a spline or junction.

# 10 The asset catalogue

Open Catalogue (P) in the tool panel, or press P.




## Search and filter

The top tabs select **Splines & junctions**, **Objects** or **Textures**. Categories narrow results. Search by name or file path; **Clear** clears the search. Sorting by name, category or path changes the order.

## Preview and selection


Results appear as thumbnails on the left. Click an item for a larger preview, its name and file path on the right. The buttons below the preview rotate it.

## Select and browse

Click **Select** or press Enter to use the highlighted item. **Back / Next** changes result pages; Esc closes the catalogue. **Build junction** opens the builder. **Check all previews** checks catalogue previews.

# 11 Splines in the catalogue

Splines & junctions contains road profiles, junction components and related path assets.




## Filter and search

Choose **Spline profiles**, **Junctions**, **Traffic logic** or another category. The AI-path category is still labelled **KI-Pfade** in this original screenshot. Search by a profile name or part of its file path.

## Preview the profile

The right panel shows the highlighted asset and its path. Spline previews show the road cross-section and available paths. **Blue:** road. **Green:** footpath. **Purple:** railway. **Yellow:** flight path. A traffic-logic object can show paths without a road model.

## Select and continue

Click **Select** or press Enter, then use the selected asset in the editor. **Back / Next** browses results. Asset names and file paths retain their original language; they identify installed content.

# 12 Select and move spline groups

Editor 0.8.2-pre | Windows / Linux | 14.10.2026

Workspace and catalogue
Choose Splines at the top or press T in object mode. P opens the spline catalogue. Build junction and Build roundabout open the construction tools.

Selection filter
Cycle the filter button through all splines, roads, sidewalks, markings and other assets. It applies to new clicks. Choose All if an asset cannot be found. Tab cycles overlapping hits and returns to single selection.

Create a group
Ctrl+click adds or removes splines. A normal click on a selected member keeps the group for dragging. Clicking another spline replaces the selection; clicking empty space clears it. Check the count and markers.

Move together
Drag or use I/J/K/L to move the group; U/O changes its height. Ctrl+Z undoes the whole movement. One continuous drag produces one undo step.

Tile boundaries and connections
Each spline must stay inside its original tile. If a move is invalid, none of the members move. Afterwards check connections to neighbours that were not moved.

Edit one spline
Select a single spline for length, curve, gradient, connections and terrain tools. + / - changes length, comma / period the curve, Home / End the gradient. C extends; G connects. Ctrl+S saves; reload after AI changes.

# 13 Fit road and terrain

Editor 0.8.2-pre | Windows / Linux | 14.10.2026

1 Select the correct road
In Splines, click the road surface and check its ID. A marking, sidewalk or terrain profile may be a separate spline. The new tool affects only the selected road section.

2 Road to terrain - F6
The existing tool fits the road to ground height. Check its shape and connections afterwards.

3 Terrain to road - Shift+F6
The road remains in place. Terrain grid samples inside its surface footprint are fitted to road height. Samples outside remain unchanged; no wide shoulder smoothing is applied.


4 Terrain-grid limitation
Triangles span the grid samples. At the road edge, their visible shape may extend to the next sample. A very narrow road may cover no samples at all; the tool then reports that nothing needs changing.

5 Smooth a shoulder if required
F8 and Shift+F8 are separate tools with a lateral transition area. Use them only when the road edge or a wider surrounding area should also change.

6 Undo and save
In spline mode, Ctrl+Z undoes the terrain fit. For height and texture brushes in terrain mode: Ctrl+Z undoes; Ctrl+Y or Ctrl+Shift+Z redoes. Ctrl+S saves. Undo does not replace a map backup; do not rely on the previous history after reloading.

# 14 Bridge / tunnel / underground

Editor 0.8.2-pre | Linux prerelease | 13.10.2026




1 Select the road
In spline mode, click the actual road surface and check its ID. Open Bridge / tunnel / underground (Bridge / tunnel / underground). A marking may be a separate spline.

2 Set heights and gradients
Start height and End height are absolute map heights in metres. Set the gradient at each end separately in percent. Click a number, type a value and press Enter; a decimal comma is accepted.

3 Check and apply the preset
Bridge: +5 m and Tunnel: -5 m suggest heights relative to the terrain at both road ends. Apply road heights applies the change. Gradients above 20% within a ramp are rejected.

4 Check connections
Neighbouring roads are not automatically moved to matching heights. Check transitions and ramps. The road retains its profile, textures and AI paths; terrain-height adaptation is disabled.

Important
The tool changes road height. It does not create a terrain opening or a complete bridge or tunnel tube.

Screenshot: English interface.

# 15 Building bridges and tunnels

Editor 0.8.2-pre | Linux prerelease | 13.10.2026

Work plane
Set Work plane height and enable Work plane: ON. Placement of new objects and splines, and dragging, use this plane even below ground. It stays active after closing the window. Disable it in the same window to resume normal terrain-based placement.

See below ground
Terrain: visible toggles terrain visibility in the editor. Hiding terrain does not change saved ground or collisions. Terrain becomes visible again when leaving the editor or opening the game menu.

Build a bridge
Raise the road and connect suitable ramps. Choose and place a deck, railings and supports from the catalogue. The +5 m preset is a starting point; check clearance and connections.


Build a tunnel
Lower the road and connect entrance ramps. Place a suitable tube, walls and portals from the catalogue. A portal alone does not cut an opening in the ground. An opening requires suitable terrainhole-enabled assets or an open approach shaped with the terrain tools. Lowering the ground does not create an enclosed tube.

Road surface or marking?
A surface invisible from below may be rendered on one side only. If the road seems transparent, also check whether only a marking spline was selected. Verify its name, profile and ID.

Back up and test
Copy the map before extensive terrain edits. Ctrl+Z undoes road-height changes; Ctrl+S saves. Reload and check the approach, collisions, road height and AI connections. Work-plane settings and hidden terrain are not saved map changes.

# 16 Junction builder

Design a junction, save it and place it on the map.




## Shape and arms

Choose **T-junction** or **Four-way junction**. Select **Arm A/B/C/D**; D is disabled for a T-junction. Set road width, length, direction, bend, sidewalk width and corner radius. Labels identify the arms; **Arm A** is selected in this screenshot.

## Textures and preview


**Choose asphalt … / Choose sidewalk …** select textures. **Width / texture from selected spline** copies a previously selected road's width and texture. **Show AI paths** toggles blue paths; **Centre lines** toggles markings. **Rotate preview** changes the view.

## Save and continue editing

**Load project …** opens a saved project. **Undo / Redo** correct changes. **Save & place** prepares placement; then save the map with Ctrl+S. Texture crop: page 17 Road connections: page 21 AI connections: page 29

# 17 Adjusting junction textures

These controls affect the road texture across all junction arms.




## Choose the step size

Click a value and type a number; comma and decimal point are accepted. Enter applies it. Plus/minus also applies a valid entry before changing it. Typed decimal places set the step: 6.5 → 0.1; 6.52 → 0.01; 6 → 1. Up to four decimal places are supported.

Click a digit to select its place. In 6.52, clicking 6 selects steps of 1, clicking 5 selects 0.1 and clicking 2 selects 0.01. The digit is underlined; use + / - to change the value. Each field remembers its own step. The screenshot shows a step of 0.0001.

## Crop U from

Start of the horizontal texture crop. U = 0 is the left edge; U = 1 is one full image width.

## Crop U to

End of the crop. Example: 0.25 to 0.75 uses the middle half. A smaller end than start mirrors the crop; values outside 0 to 1 repeat the texture.


## Texture width (m)

Width covered by one repetition of the selected crop. Larger values stretch it wider; smaller values repeat it more often. The road width stays unchanged.

Limits: U from/to -16 to 16; values must differ by at least 0.0001. Texture width: 0.25 to 100 m. Undo/Redo covers these changes. Esc cancels pending text input; use Undo for applied +/- changes. Inspect the preview, then save or update the placed junction.

# 18 Roundabout builder

Choose approaches, identify them in the preview and place the roundabout.




## Entrances and arm selection

Open **Build roundabout** in the tool panel. Choose **3 entrances** or **4 entrances**, then edit **Arm A/B/C/D**. Preview labels identify the entrances; **Arm A** is selected here.

## Dimensions, textures and saving

Controls are explained on page 19 A previously selected road can supply width and texture. Use **Save & place**, place the object, then press Ctrl+S. Select a placed object and reopen the builder to edit it.

## Check connections

Road connections: page 21 AI endpoints: page 29 Save and reload the map so AI traffic uses the updated network.

# 19 Roundabout: fields and controls

| | |
|---|---|
| 3 / 4 approaches; Arm A-D | Choose the number of approaches and the arm to edit. Road width, length and direction apply to that arm. |
| Name | Name of your custom roundabout project. |
| Road width (m) | Width of the selected approach, not the circulating lane. |
| Length from centre (m) | Distance from the roundabout centre to the outer end of the selected approach. |
| Direction (°) | Orientation of the selected approach around the centre. |
| Island radius (m) | Radius of the central island. Larger values enlarge the island and roundabout. |
| Ring road width (m) | Width of the circulating roadway around the island. |
| Island height (m) | Height of the island above the roadway. |
| Texture length (m) | Length of one texture repeat along the roadway. Larger values stretch the pattern. |
| Width / texture from selected spline | Uses the previously selected road’s width and texture. Select a road in spline mode first. |
| Choose asphalt / island texture | Select textures for the roadway and central island. |
| Island edge line | Turns the visible island edge marking on or off. |
| Show AI paths / Rotate preview | Shows traffic paths or rotates the preview view. Rotate a placed object separately with N/M. |
| Load project; Undo / Redo | Load a saved builder project or undo/redo changes within the builder. |
| Crop U from / to; Texture width | Image crop and repeat width across the road. Click a digit and use +/-; see page 17 for details. |

Input: click a numeric value, type and press Enter. The +/- buttons change dimensions. Limits: single circulating lane, no turbo roundabouts; direction follows the map’s left-/right-hand traffic. Check AI traffic after reloading.

# 20 Rotation, height and tilt

Select a placed object in **object mode**. Tilt controls support builder junctions and roundabouts. Keep the companion **junction.junction.json** beside the object.

| Keys | Action | Normal / Shift |
|---|---|---|
| N / M | Rotate | 5° / 0.5° |
| U / O | Lower / Raise | 0.5 m / 0.05 m |
| Home / End | Pitch + / - | 0.5° / 0.05° |
| Page Up / Down | Bank + / - | 0.5° / 0.05° |
| I / J / K / L | Move | 0.5 m / 0.05 m |
| Delete | Delete / Restore | |
| Ctrl+S | Save map | |

## Check the angles

The information bar shows pitch and bank. Axes follow the object, not the camera. Copying and placement preserve the angles. Each angle is limited to -89°…+89°; road connections may reach geometric limits earlier.

## Backspace and saving

For connected builder objects, Backspace restores the combined pose and road edits. Without connected approaches it first resets changed tilt. Restore deleted objects with Delete first. Save and reload the map to refresh traffic paths.

**Spline mode:** comma/period still adjust curvature and Home/End adjust gradient. Keyboard rotation in object mode uses N/M only.

# 21 Connect roads and follow changes

Applies to builder junctions and roundabouts. A road that merely touches the object is **not yet an explicit connection**.

**1.** Select the approach road in spline mode.

**2.** Switch to object mode and select the placed builder object.

**3.** Open the appropriate builder and choose approach A/B/C/D.

**4.** Choose “Connect road to selected arm” to prepare the preview.

**5.** Check the preview and update the placed object to apply it. Closing the builder discards the preparation.

**6.** Save with Ctrl+S and reload the map to refresh traffic paths.

## What follows automatically

Explicitly connected approaches follow moving, rotating, raising and tilting the object. Their far endpoints stay fixed. New connections to tilted objects are also supported. Backspace restores combined pose and approach edits together.


## If a connection cannot be fitted

All approaches are checked before applying a pose change. If one fit fails, object and road geometry remain unchanged. Smaller changes, longer approaches or a matching transition spline may help. Repair an old broken link by selecting its road and reconnecting the correct arm.

**Limits:** standard OMSI maps; at most 50 m gap and 30° direction mismatch, compatible profiles and sufficient transition length. Reset protects separately edited roads. Non-editable Chrono or old-format roads are not changed.

# 22 Checking spline connections

Find open ends and suspicious connections across the whole map.




**Red:** errors, such as duplicate IDs. **Yellow:** open ends, which may be intentional. **Grey:** unchecked. **Green:** recognised as connected. The screenshot shows results from this map, not a requirement for every map.


Each entry lists the spline ID, start or end, tile coordinates and the finding. Click a row to go there. **Back / Next** changes result pages.

**Check again** refreshes results after edits. **Markers: ON/OFF** toggles markers in 3D. **Only open / suspect ends** filters results.

Endpoint tolerance: 15 cm. Nothing is changed automatically. Close or Esc closes the list.

# 23 Working with AI paths

Editor 0.8.2-pre | Windows / Linux | 14.10.2026




Switch to AI editing
Click AI paths at the top or press F9. The object or spline toolbox is replaced. Objects and Splines return to those workspaces.

Edit an existing path
Click a blue or orange traffic path. Selecting the road first is unnecessary. Paths inside junction objects can also be selected. See pages 27-28.

Create paths along a road
Select the road in Splines first, then open AI paths. AI paths along the selected road opens the generator. Check scope, direction and lane width; see pages 24-26.

Create an additional connection
Create additional AI connection opens a connection preview directly. Connect an existing path end to an onward path start; see page 30.

Colours and completion
Blue: all vehicles. Orange: buses only. Arrows: travel direction. Apply, save and reload for traffic simulation. Add a pending connection before switching workspace, or deliberately close its preview.

# 24 Create AI driving paths

First select the actual road, not an island, kerb or sidewalk.




English interface

## Scope

**Scope: selected spline** edits one section. **Scope: connected spline chain** follows connected reference splines; junctions or gaps may limit the chain.

## Lane count and direction

Cycle between **Two opposing lanes**, **One lane / one-way road** and **Two lanes in the same direction**. Arrows show travel direction. Separately created one-way splines are edited individually.

## Vehicles

Choose **All vehicles** or **Buses only** per lane. Bus schedules are separate; this permission does not create a bus service.

## Width, offset and height

Lane width and lateral offset define the starting layout. Height above spline lifts the path relative to the road reference. Check that it follows the lane centre. This does not reshape the visible road.

## Add or replace

**Mode: add missing AI paths** keeps existing paths. **Mode: replace existing AI paths** updates editor-generated paths. Do not add another path when you intend to correct one.

## About this screenshot

Two opposing lanes are selected. **Select lane 2** switches the edited lane. The status shows **0 new sections, 6 already with paths and 0 open endpoints**. These values depend on the selection.

# 25 AI paths along a road

Editor 0.8.0-pre | 13 October 2026




English interface

## Scope, lanes and direction

**Scope:** switch between a selected spline and its connected chain. The lane-mode button cycles through **Two opposing lanes**, **One lane / one-way road** and **Two lanes in the same direction**. **Direction:** choose the reference direction or its opposite.

**Lane 1 / Lane 2:** choose **All vehicles** or **Buses only** per lane. Blue means all vehicles; orange means buses only. Arrows show travel direction.

## Placement and freeform points

**Lane width:** set the width of a lane. **Lateral offset:** move the layout sideways. **Height above spline:** set its vertical offset. Use + / - to change values.

**Edit freeform points:** toggle point editing. **Select lane:** switch the edited lane. Click and drag a point. **Reset point:** remove its individual offset. **Lower point / Raise point:** lower / raise it by 0.1 m.

## Apply the preview

**Mode: add missing AI paths:** add missing paths and retain existing ones. Switch to “replace existing AI paths” to replace existing paths in the selected scope; inspect the preview before applying.

**AI paths: visible - hide:** toggle the overlay. **Create AI paths (Enter):** apply the preview. **Refresh preview:** recalculate it. The status line reports new sections and open endpoints.

The bottom buttons open additional connections or direct path selection. **Close (Esc)** closes the tool. Save afterwards, then reload the map.

This tool generates paths from a road. Use direct path selection to move an original individual path.

A bus-only path does not create a timetable. Scheduled buses need a route and timetable. A connection does not force every ordinary car to turn.

# 26 Shape AI paths with the mouse

Freeform editing works on one selected section at a time.

## 1. Open the existing path

Select the road or generated AI spline and open **AI paths along the road**. Choose replacement mode when correcting an existing path.

## 2. Enable freeform editing

Click **Edit freeform points**. The tool switches to the selected section. Each lane starts with nine green points, including its start and end.

## 3. Choose the lane

With two lanes, use **Select lane 1 / Select lane 2**. The button names the lane you can switch to. Dragging does not move the other lane.

## 4. Drag points

Hold the left mouse button on a green point and drag. The selected point turns yellow: this means selected, not connected. Intermediate points shape a smooth curve. Keep the path in the centre of its lane.

## 5. Adjust height or reset a point

Dragging moves points horizontally. **Raise point / Lower point** changes height in 0.1 m steps. **Reset point** resets the point’s displacement. Displacement is limited to 50 m in each local direction.

## 6. Apply, save and reload


Apply with **Create AI paths / Replace AI paths** or Enter. Ctrl+Z undoes the applied change. Save with Ctrl+S and reload the map for running traffic. Close or Esc discards the unapplied preview.

## Longer routes and smooth dragging

Edit connected sections individually and join their endpoints. Chain mode does not overwrite individual freeform shapes as one uniform layout. Mouse movements are combined per frame; release uses the latest position.

# 27 Select and edit AI paths

Editor 0.8.2-pre | Windows / Linux | 14.10.2026




Select
Choose AI paths at the top or press F9, then click a traffic path. Next overlapping path (Tab) cycles through hits.

Edit curve
Edit curve enables the handles. Green shapes the bend, purple moves the start and yellow moves the end. Drag with the left mouse button held, then check direction and connections.

Delete and reset
Delete AI path (Del) removes the selected path, not the road. A deleted path can be restored. Restore original curve resets the shape, endpoints and height adjustment.

Undo and save
Ctrl+Z undoes an individual path edit; Ctrl+Y redoes it. Save map (Ctrl+S) saves changes.

Other tools
AI paths along the selected road generates lanes. Create additional AI connection adds links. Show / hide AI paths controls visibility. Objects or Splines switches workspace.

# 28 Edit existing paths

## 3. Select a path and reshape it

**1.** Open F9. Click a blue or orange path and check its purple highlight. The panel identifies road/object, instance ID, path number and direction.

**2.** Use Tab or “Next overlapping path” when paths overlap. After cycling, enable “Edit curve” if necessary.

**3.** Hold a green handle with the left mouse button and drag. A top-down or oblique view makes lateral placement easier to judge. Short paths with only two original samples can also be edited.

**4.** Dragging captures height from loaded road surfaces when the entire interior lies above a road. Otherwise, the geometric road-profile correction is used. A curve outside the road is not automatically moved back onto it.

## 4. Extend a path

Drag the **yellow end handle** to the desired position. The **purple start handle** moves the start. Adjust the green handles afterwards to keep the route within the intended lane.

Releasing an endpoint near a unique compatible connection may snap it to that position. Moving an endpoint clears its previous explicit link on that side. Check direction and continuity afterwards: identical endpoint coordinates alone do not guarantee a suitable AI route.

## 5. Delete, reset and undo

**Delete / “Delete AI path”:** removes only the selected path direction on that instance. The junction object and other routes remain. Removing an entire junction arm may require deleting several paths individually.

**Ctrl+Z:** undo. **Ctrl+Y:** redo. “Restore AI path” restores the currently selected deleted route. “Restore original curve” resets shape, endpoint offsets and saved height correction.

Reloading starts a new editing session; the previous undo history is not carried over. Saving and reloading are explained on page 32

# 29 Connections and opposing traffic

Paths touching visually are not yet an explicitly selected connection.

### Connect endpoints explicitly

In freeform mode, select the green start or end point. Matching opposite endpoints within 50 m appear purple. A path end connects to another path start, and vice versa. Drag the selected point onto the desired purple target and release; it snaps within 1.5 m.

### Check the result

The panel counts fixed connections and open ends. Check the assignment and arrow direction, then apply and save. Moving that endpoint freely again removes its fixed assignment. Nearly overlapping targets may be ambiguous.

### Separate straight and right-turn lanes

Connect the straight-ahead lane to the crossing's appropriate straight path and the turning lane to its right-turn path. Merely straightening the visible line does not select the connection. Use two same-direction lanes for adjacent lanes travelling the same way.

### Route around a central island

Keep each direction in the centre of its own lane. With right-hand traffic, pass to the right of the island in the direction of travel. Edit opposing lanes separately. With two separate one-way splines, the opposite direction is lane 1 of its own spline.

### Arm labels A/B/C/D in the preview

The junction and roundabout builders label their arms in the preview. Match the label to the selected approach. This assists the road connections in chapter 19; AI endpoints are connected in the AI-path tool.


### Limits and compatibility

Original paths in standard spline profiles or crossing objects are not overwritten. Custom paths can connect to suitable original endpoints. Free bridges across a crossing do not create traffic-light control or priority rules. Freeform points and fixed connections require this modified openOMSI runtime; an unmodified upstream version does not interpret these extensions.

New in 0.7.22-pre: create an additional AI connection - step-by-step guide on page 30

# 30 Additional AI connection

Editor 0.8.0-pre | 13 October 2026




English interface

## 1. Choose source and destination

**Select start:** click the incoming lane's yellow end. **Select destination:** click the outgoing lane's purple start. Check arrow direction. Connections use path endpoints, not the middle of a path.

## 2. Shape the connection

Drag both **green curve handles** freely with the left mouse button. Keep the curve in the intended lane. It follows loaded road surfaces; check height from a second camera angle.

**Vehicles:** all vehicles or buses only. **Lane width:** adjust with + / -. **Select start and destination again:** reset endpoint selection and preview.

## 3. Add and save

**Add connection (Enter):** apply the preview. Existing straight-through routes remain. Until you apply it, the curve is only a preview.

**Save map (Ctrl+S):** save the map. Once source and destination are selected, the button reads **"Add connection + save (Ctrl+S)"**. A complete valid preview is applied before saving; invalid previews stay editable.

## Return and continue

**Back to AI paths along the road:** switch tools. **Close (Esc):** leave the preview; apply it first if you want to keep it. F9 no longer discards a pending connection.

Check the save message, then use "Reload map ...". AI uses the new route after reloading. The bus location and active duty are retained.

If no loaded road surface is found beneath the curve, move it back over the road and let the area load. The entire curve needs a valid road surface before it can be added.

# 31 AI paths: help and diagnostics

Check the selection and preview before applying and saving.

### No paths or control points visible

Show AI paths. Enable freeform mode to see green control points. Background loading may take a moment after enabling the display. Check the information bar: did you select the road or the traffic island? An error can prevent a valid preview.

### Cannot select lane 2

One lane / one-way road has only one editable lane, although the second button may still be visible. If the opposite direction belongs to another AI spline, select it separately. Avoid creating a duplicate path over an existing one.

### Curve too tight for this lane offset

A section does not fit the configured lateral offset. In chain mode, another section may be responsible. Select the correct road individually and check width, offset and curvature; do not use the narrow island edge as the reference.

### Yellow point will not snap

Yellow means selected. Hold the left mouse button and drag the endpoint onto the matching purple target, then release. Check direction, distance and the 50 m displacement limit. Interior control points are not connection endpoints.

### Another prolonged freeze?

Launch with start-editor-diagnose.sh. Note the time and action: dragging, releasing, applying or moving the camera. Save game.log before the next launch. EDITOR-DIAG reports slow operations; 0.7.20 also reports excessive waiting of combined mouse movements.

### What has been observed

Normal dragging without freezes was confirmed on Linux with 0.7.20. The path display builds in the background. A brief map-update delay can still occur; diagnostics do not prove smooth operation on every map under all conditions.

### Finish safely

Apply the preview, save with Ctrl+S, then reload the map for AI traffic. After troubleshooting, return to normal startup with start-editor.sh. Diagnostics stop; the improvements stay active.

# 32 Save and test with traffic

Editor 0.8.2-pre | Linux prerelease | 13.10.2026

### Reloading during a duty - local development build

Single-player map reload retains the bus position, duty, technical bus state, passengers in the player bus and selected camera view, provided the same bus can be restored. An ongoing ticket sale is retained. Waiting people are retained at still-loaded stops moved by up to 30 m; deleted stops or larger moves are excluded. Other pedestrians and AI-bus passengers are regenerated. Move waiting-point objects and shelters as well when permanently relocating a stop. This continuation applies to map reload within the current session, not loading a saved situation or LAN.

### While editing

Terrain painting updates the ground display without rebuilding simulation tiles. Expensive updates while moving objects and splines are deferred until the key or mouse button is released. Allow the update to finish after releasing it.

### Save and reload

Ctrl+S saves edits. Use Reload map after changing AI connections. Wait for reload to finish, then continue driving. Reloading a map does not save a driving situation.

### Move bus stops

Keep the stop marker, waiting points and shelter aligned. Deleted stops, moves over 30 m and unloaded areas cannot retain all waiting passengers.

### Check AI traffic

Moving only the camera does not move the traffic area around the player bus. Drive to the edited location to test it. Check endpoints, directions and heights; a visible path alone does not prove a usable connection.

### Camera and backup

Press F1 if the interior camera appears offset after reload. Back up the map before major edits. Normal game saving rules apply when leaving the session.

# 33 Version, startup and updates

Editor 0.8.2-pre | Windows / Linux | 14.10.2026

Version and content
Editor 0.8.2-pre uses openOMSI 0.2.38. OMSI 2 content is required separately. End the driving session, close the program and back up edited maps before updating.

Start on Windows
Extract the complete Windows x64 ZIP into a new folder. Run start-editor.cmd and complete the OMSI 2 content setup. Do not mix old and new program files.

Start on Linux
Extract the Linux x64 package. From the editor folder, run bash start-editor.sh "/path/to/content" --launcher. The supplied package requires glibc 2.39 or newer.


Separate update checks
Settings - General - Updates checks the separate game and editor package independently. Check now installs nothing. Updating the normal game does not replace the bundled editor engine.

Manual package update
Extract the matching new package into a new folder. Back up and transfer required content and your own maps, or reuse the existing content folder. Then use the new starter.

Checksums and backups
The SHA-256 checksum verifies the downloaded package. A program backup does not replace a map backup. When using the integrated Linux updater, check its displayed destination and backup folders.

# 34 Check and install updates

Editor 0.8.2-pre | Linux prerelease | 13.10.2026




1 Open the update section
Open Settings → General → Updates. The two buttons check different programs.

2 Choose the correct check
openOMSI · separate game installation checks the normal game in the selected content folder. openOMSI Editor · editor package checks the editor, including prereleases. Check now does not install anything.

3 Review the offer
If a newer version is found, check the release notes, version and target folder. End the driving session and back up maps before installation. Download and install starts installation.

4 After updating
An editor update restarts the editor. A game update does not replace the bundled editor engine. Both programs can use the same maps and mods. Backup and compatibility details: page 33.

State shown in the screenshot
The image shows the buttons before a check. Download and installation controls appear only when an update is available. Reset all settings affects settings and is not an update tool.