1 Welcome to the openOMSI Editor

Editor 0.7.23-pre | Local development build | 12.10.2026

With the openOMSI Editor, you can create and edit your map - from the layout of roads and placement of objects to the paths used by AI traffic. You can also use the editor while playing. This lets you make changes directly at the place you are visiting. When you reload the map afterwards, your current bus position and an active duty are retained, allowing you to continue your journey from the same location. This guide explains the main tools and how to use them step by step. You will learn what the individual buttons do, how to make changes and how to save your work. The AI path tools help you adjust existing paths and create additional connections. Read the guide in order, or use the contents to go straight to the topic you need. Back up your map before making major changes. Save your edits and then reload the map so that changes to the AI path network take effect in the game. Enjoy building, experimenting and developing your map!

Guide scope
The additions for bridges, tunnels, movable windows, passenger retention and separate updates describe the local development build after the published 0.7.23-pre release. An older download with the same version number may not include them yet.


2 Contents

Editor 0.7.23-pre | Local development build | 12.10.2026

Start directly in the editor	3
Maps and camera position	4
Open the editor during play	5
Interface and objects	6
Adding map tiles	7
Editing the terrain	8
Painting terrain textures	9
The asset catalogue	10
Splines in the catalogue	11
The Spline Editor	12
Spline editor: tools	13
Bridge / tunnel / underground	14
Building bridges and tunnels	15
Junction builder	16
Adjusting junction textures	17
Roundabout builder	18
Roundabout: fields and controls	19
Rotation, height and tilt	20
Connect roads and follow changes	21
Checking spline connections	22
Working with AI paths	23
Create AI driving paths	24
AI paths along a road	25
Shape AI paths with the mouse	26
Select and edit AI paths	27
Edit existing paths	28
Connections and opposing traffic	29
Additional AI connection	30
AI paths: help and diagnostics	31
Save and test with traffic	32
Version, startup and updates	33
Check and install updates	34

3 Start directly in the editor

In the launcher, choose Editor below Sessions and above Mods.



Create a new blank map

Map name: required; it also determines the folder name. Existing names are rejected. **Author (optional)** and **Description:** saved in the map description.

Save location: maps are created in the active content folder's maps directory, outside the original OMSI 2 installation. The folder shown in the screenshot is an example, not an installation requirement.

Create and edit map: creates one flat 300 × 300 m tile with a base texture and opens the editor. No bus or driving duty is needed. Use **Edit existing map** to choose an existing map, then **Open in editor**.

4 Maps and camera position

Open an existing map

Choose a map under **Edit existing map**, then click **Open in editor**. End any running session first. The map opens with a free camera and the editor already active.

Start above the terrain

Without a saved editor position, the default is 35 m above the terrain at the start location, looking 30° downward. If the initial location is outside existing tiles, the nearest tile is used.

Return to the last editor location

Position, direction and zoom are remembered per map when you save, switch off the editor or end the session normally. The next direct editor start restores that location. Height is raised to at least 35 m above the current terrain when needed; higher saved positions are retained.

Save and reopen

Fly to a recognisable location, make an edit and press Ctrl+S. Close the session and reopen the same map through Editor. Check the edit and camera position. Other maps retain their own positions.

What the camera bookmark saves

Camera data is stored locally under ~/.openomsi/editor-views, not in the map. It does not save unsaved map edits. A crash may lose a location not yet recorded. Normal driving starts are unchanged.

Language and available tools

The tools described here support German and English. Select English in the game settings for the interface shown in this guide. Other translations remain incomplete. Junction and roundabout builders are included; see pages 16-19


5 Open the editor during play

Edit the currently loaded map directly during gameplay.


Press **F4** to switch to camera mode. Press **Esc** to open the pause menu.

Choose **World options → Tools → Object editor → Open**. This opens the Object Editor. Press **T** to switch to the Spline Editor for roads (page 12). Direct editor startup and blank maps are explained on pages 3-4.


PAUSE MENU



WORLD OPTIONS




TOOLS: OPEN THE OBJECT EDITOR



6 Interface and objects

Editor 0.7.23-pre | Local development build | 12.10.2026



Find the tools
Catalogue (P), Build junction and Roundabout open the building tools. New tile expands the map. Edit terrain opens height and texture tools.

Move editor windows
Drag a window by its title bar with the left mouse button held. The catalogue, builders and other editor windows can also be moved. Left and docks the toolbar to the left.

Select and move
Click / Enter selects; Tab cycles through hits. WASD / Q E moves the free camera. I J K L moves an object, U / O changes height and N / M rotates it.

Copy and place
Ctrl+C copies; Ctrl+V starts placement. Ctrl+R places the last object again. Repeat placement enables repeated placement; Esc finishes.


More tools
Edit text and Select / edit AI paths are near the bottom. Bridge / tunnel / underground opens Bridge / tunnel / underground; see pages 14-15.

Save and check
Ctrl+S saves. Reload map loads the saved state. Check spline connections checks road connections. Driving-session details: page 32.

Screenshot: English interface.

7 Adding map tiles

New tile opens the map expansion window. Each tile measures 300 × 300 m.



Choose a free neighbouring tile

Green marks existing tiles; **free** marks unused positions. The selection is dark grey with an orange side marker; the legend still calls it blue. Each cell shows coordinates. Use the direction buttons or arrow keys to move the map view.

Set the terrain height

Use edge heights: take neighbouring edge heights and smoothly extend their profiles across the new tile. **Custom height:** specify a height yourself.

Create the tile

Click **Create tile** or press Enter. **Close** or Esc closes the window. Choose a free neighbouring position to add a connected area for building.

8 Editing the terrain

Use Edit terrain to change the ground shape or switch between Heights and Textures.



English interface

Height tools

Raise hill, **Lower hollow**, **Level** and **Smooth** shape the ground. **Paint height** uses the target height; **Fine smoothing** provides gentler smoothing.

Brush settings

Radius (m): affected area. **Strength / sec.:** amount per second. **Soft edge (%):** edge falloff. **Target height (m):** height for applicable tools. **Tile step (m):** step size for whole tiles.

Pick a height or tile

Sample height picks an existing ground height. **Select tile** selects a map tile; its coordinates appear below.

Edit entire tiles

Lower tile and **Raise tile** change the whole tile. **Set entire tile to target height** uses the target value. **Blend with neighbours** controls the transition width.


Paint and save

Hold the left mouse button to sculpt; hold Shift for finer adjustments. The mouse wheel changes brush size. **Undo / Redo** revises changes. **Save (Ctrl+S)** saves the map.

Back to building returns to building tools. **New tile**, **Reload map …** and **Check spline connections …** open the related map tools.

9 Painting terrain textures

Open Edit terrain, then select Textures.



English interface

Choose a texture and layer

The arrows switch terrain texture layers. **Texture catalogue …** opens texture selection. The current layer and texture name appear above these controls.

Paint or erase

Select **Paint** and hold the left mouse button over the terrain. **Eraser** removes the selected overlay layer. It is disabled on layer 0: painting the base texture removes overlaid paint instead.

Brush settings

Radius (m) sets brush size; the mouse wheel also changes it. **Strength / sec.** controls how quickly paint is applied or erased. **Soft edge (%)** controls the transition at the edge.

Pick an existing texture

Click **Eyedropper: pick texture**, then click the terrain. The editor selects the sampled terrain texture layer.


Undo and save

Use **Undo** / **Redo** to revise brush strokes. **Save (Ctrl+S)** saves; **Back to building** returns to the building tools.

Begin with a small brush and low strength. Terrain textures change the ground; they do not select the asphalt texture of a spline or junction.

10 The asset catalogue

Open Catalogue (P) in the tool panel, or press P.



Search and filter

The top tabs select **Splines & junctions**, **Objects** or **Textures**. Categories narrow results. Search by name or file path; **Clear** clears the search. Sorting by name, category or path changes the order.

Preview and selection


Results appear as thumbnails on the left. Click an item for a larger preview, its name and file path on the right. The buttons below the preview rotate it.

Select and browse

Click **Select** or press Enter to use the highlighted item. **Back / Next** changes result pages; Esc closes the catalogue. **Build junction** opens the builder. **Check all previews** checks catalogue previews.

11 Splines in the catalogue

Splines & junctions contains road profiles, junction components and related path assets.



Filter and search

Choose **Spline profiles**, **Junctions**, **Traffic logic** or another category. The AI-path category is still labelled **KI-Pfade** in this original screenshot. Search by a profile name or part of its file path.

Preview the profile


The right panel shows the highlighted asset and its path. Spline previews show the road cross-section and available paths. **Blue:** road. **Green:** footpath. **Purple:** railway. **Yellow:** flight path. A traffic-logic object can show paths without a road model.

Select and continue

Click **Select** or press Enter, then use the selected asset in the editor. **Back / Next** browses results. Asset names and file paths retain their original language; they identify installed content.

12 The Spline Editor

Editor 0.7.23-pre | Local development build | 12.10.2026



Mode and selection
Press T in object mode to switch to splines. Click the road; Tab cycles through overlapping hits. Check its name and ID in the information bar.

Edit a road
+ / - changes length; comma / period changes the curve; Home / End changes the gradient. C extends and G connects. Hold Shift for smaller steps.

Road and terrain
F6 fits the road to the ground. F8 smooths its edge; Shift+F8 smooths a wider area. These tools require a selected road.

AI paths
AI paths along the road creates driving lanes along the road. Select / edit AI paths opens existing paths. Show / hide toggles visibility. A road does not automatically include an AI path.


Bridge and tunnel
Open the bottom entry Bridge / tunnel / underground. Select the actual road surface first, rather than a marking or terrain profile. See pages 14-15.

Apply and test
AI paths: pages 24-25; drag points: page 26; connections: page 29. Apply changes, save and reload.

Screenshot: English interface.

13 Spline editor tools

Editor 0.7.23-pre | Local development build | 12.10.2026



Camera and selection
WASD / Q E moves the free camera. Hold the right or middle mouse button to look around. Click / Enter selects. I J K L moves, U / O changes height, N / M rotates. T switches to objects.

Map maintenance
Catalogue (P), Build junction, Roundabout, New tile and Edit terrain open their tools. Reload map and Check spline connections help verify edits.

Tools for a road
Select the road first. Smooth shoulder (F8) smooths the edge, Smooth wider (Shift+F8) smooths a wider area and Fit to ground (F6) fits the road to the ground.

Objects, sidewalks and AI
Objects along the road and Sidewalk along the road open separate tools. Direct AI path selection does not require a selected road. Generating AI paths along a road does.


Heights and input focus
Bridge / tunnel / underground opens the height tools. Camera movement remains available with a road selected. While editing a number, movement keys are blocked. Enter confirms; Esc ends the input.

Save
Ctrl+S saves. Check connections after changing heights. The next pages explain bridges and tunnels.

Screenshot: English interface.

14 Bridge / tunnel / underground

Editor 0.7.23-pre | Local development build | 12.10.2026



1 Select the road
In spline mode, click the actual road surface and check its ID. Open Bridge / tunnel / underground (Bridge / tunnel / underground). A marking may be a separate spline.

2 Set heights and gradients
Start height and End height are absolute map heights in metres. Set the gradient at each end separately in percent. Click a number, type a value and press Enter; a decimal comma is accepted.

3 Check and apply the preset
Bridge: +5 m and Tunnel: -5 m suggest heights relative to the terrain at both road ends. Apply road heights applies the change. Gradients above 20% within a ramp are rejected.

4 Check connections
Neighbouring roads are not automatically moved to matching heights. Check transitions and ramps. The road retains its profile, textures and AI paths; terrain-height adaptation is disabled.

Important
The tool changes road height. It does not create a terrain opening or a complete bridge or tunnel tube.

Screenshot: English interface.

15 Building bridges and tunnels

Editor 0.7.23-pre | Local development build | 12.10.2026

Work plane
Set Work plane height and enable Work plane: ON. Placement of new objects and splines, and dragging, use this plane even below ground. It stays active after closing the window. Disable it in the same window to resume normal terrain-based placement.

See below ground
Terrain: visible toggles terrain visibility in the editor. Hiding terrain does not change saved ground or collisions. Terrain becomes visible again when leaving the editor or opening the game menu.

Build a bridge
Raise the road and connect suitable ramps. Choose and place a deck, railings and supports from the catalogue. The +5 m preset is a starting point; check clearance and connections.


Build a tunnel
Lower the road and connect entrance ramps. Place a suitable tube, walls and portals from the catalogue. A portal alone does not cut an opening in the ground. An opening requires suitable terrainhole-enabled assets or an open approach shaped with the terrain tools. Lowering the ground does not create an enclosed tube.

Road surface or marking?
A surface invisible from below may be rendered on one side only. If the road seems transparent, also check whether only a marking spline was selected. Verify its name, profile and ID.

Back up and test
Copy the map before extensive terrain edits. Ctrl+Z undoes road-height changes; Ctrl+S saves. Reload and check the approach, collisions, road height and AI connections. Work-plane settings and hidden terrain are not saved map changes.

16 Junction builder

Design a junction, save it and place it on the map.



Shape and arms

Choose **T-junction** or **Four-way junction**. Select **Arm A/B/C/D**; D is disabled for a T-junction. Set road width, length, direction, bend, sidewalk width and corner radius. Labels identify the arms; **Arm A** is selected in this screenshot.

Textures and preview


Choose asphalt … / Choose sidewalk … select textures. **Width / texture from selected spline** copies a previously selected road's width and texture. **Show AI paths** toggles blue paths; **Centre lines** toggles markings. **Rotate preview** changes the view.

Save and continue editing

Load project … opens a saved project. **Undo / Redo** correct changes. **Save & place** prepares placement; then save the map with Ctrl+S. Texture crop: page 17 Road connections: page 21 AI connections: page 29

17 Adjusting junction textures

These controls affect the road texture across all junction arms.



Choose the step size

Click a value and type a number; comma and decimal point are accepted. Enter applies it. Plus/minus also applies a valid entry before changing it. Typed decimal places set the step: 6.5 → 0.1; 6.52 → 0.01; 6 → 1. Up to four decimal places are supported.

Click a digit to select its place. In 6.52, clicking 6 selects steps of 1, clicking 5 selects 0.1 and clicking 2 selects 0.01. The digit is underlined; use + / - to change the value. Each field remembers its own step. The screenshot shows a step of 0.0001.

Crop U from

Start of the horizontal texture crop. U = 0 is the left edge; U = 1 is one full image width.

Crop U to

End of the crop. Example: 0.25 to 0.75 uses the middle half. A smaller end than start mirrors the crop; values outside 0 to 1 repeat the texture.


Texture width (m)

Width covered by one repetition of the selected crop. Larger values stretch it wider; smaller values repeat it more often. The road width stays unchanged.

Limits: U from/to -16 to 16; values must differ by at least 0.0001. Texture width: 0.25 to 100 m. Undo/Redo covers these changes. Esc cancels pending text input; use Undo for applied +/- changes. Inspect the preview, then save or update the placed junction.

18 Roundabout builder

Choose approaches, identify them in the preview and place the roundabout.



Entrances and arm selection

Open **Build roundabout** in the tool panel. Choose **3 entrances** or **4 entrances**, then edit **Arm A/B/C/D**. Preview labels identify the entrances; **Arm A** is selected here.

Dimensions, textures and saving

Controls are explained on page 19 A previously selected road can supply width and texture. Use **Save & place**, place the object, then press Ctrl+S. Select a placed object and reopen the builder to edit it.

Check connections

Road connections: page 21 AI endpoints: page 29 Save and reload the map so AI traffic uses the updated network.

19 Roundabout: fields and controls

3 / 4 approaches; Arm A-D	Choose the number of approaches and the arm to edit. Road width, length and direction apply to that arm.
Name	Name of your custom roundabout project.
Road width (m)	Width of the selected approach, not the circulating lane.
Length from centre (m)	Distance from the roundabout centre to the outer end of the selected approach.
Direction (°)	Orientation of the selected approach around the centre.
Island radius (m)	Radius of the central island. Larger values enlarge the island and roundabout.
Ring road width (m)	Width of the circulating roadway around the island.
Island height (m)	Height of the island above the roadway.
Texture length (m)	Length of one texture repeat along the roadway. Larger values stretch the pattern.
Width / texture from selected spline	Uses the previously selected road’s width and texture. Select a road in spline mode first.
Choose asphalt / island texture	Select textures for the roadway and central island.
Island edge line	Turns the visible island edge marking on or off.
Show AI paths / Rotate preview	Shows traffic paths or rotates the preview view. Rotate a placed object separately with N/M.
Load project; Undo / Redo	Load a saved builder project or undo/redo changes within the builder.
Crop U from / to; Texture width	Image crop and repeat width across the road. Click a digit and use +/-; see page 17 for details.

Input: click a numeric value, type and press Enter. The +/- buttons change dimensions. Limits: single circulating lane, no turbo roundabouts; direction follows the map’s left-/right-hand traffic. Check AI traffic after reloading.

20 Rotation, height and tilt

Select a placed object in **object mode**. Tilt controls support builder junctions and roundabouts. Keep the companion **junction.junction.json** beside the object.

Keys	Action	Normal / Shift
N / M	Rotate	5° / 0.5°
U / O	Lower / Raise	0.5 m / 0.05 m
Home / End	Pitch + / -	0.5° / 0.05°
Page Up / Down	Bank + / -	0.5° / 0.05°
I / J / K / L	Move	0.5 m / 0.05 m
Delete	Delete / Restore	
Ctrl+S	Save map	

Check the angles

The information bar shows pitch and bank. Axes follow the object, not the camera. Copying and placement preserve the angles. Each angle is limited to -89°…+89°; road connections may reach geometric limits earlier.

Backspace and saving

For connected builder objects, Backspace restores the combined pose and road edits. Without connected approaches it first resets changed tilt. Restore deleted objects with Delete first. Save and reload the map to refresh traffic paths.

Spline mode: comma/period still adjust curvature and Home/End adjust gradient. Keyboard rotation in object mode uses N/M only.

21 Connect roads and follow changes

Applies to builder junctions and roundabouts. A road that merely touches the object is **not yet an explicit connection**.

1. Select the approach road in spline mode.

2. Switch to object mode and select the placed builder object.

3. Open the appropriate builder and choose approach A/B/C/D.

4. Choose “Connect road to selected arm” to prepare the preview.

5. Check the preview and update the placed object to apply it. Closing the builder discards the preparation.

6. Save with Ctrl+S and reload the map to refresh traffic paths.

What follows automatically

Explicitly connected approaches follow moving, rotating, raising and tilting the object. Their far endpoints stay fixed. New connections to tilted objects are also supported. Backspace restores combined pose and approach edits together.


If a connection cannot be fitted

All approaches are checked before applying a pose change. If one fit fails, object and road geometry remain unchanged. Smaller changes, longer approaches or a matching transition spline may help. Repair an old broken link by selecting its road and reconnecting the correct arm.

Limits: standard OMSI maps; at most 50 m gap and 30° direction mismatch, compatible profiles and sufficient transition length. Reset protects separately edited roads. Non-editable Chrono or old-format roads are not changed.

22 Checking spline connections

Find open ends and suspicious connections across the whole map.



Red: errors, such as duplicate IDs. **Yellow:** open ends, which may be intentional. **Grey:** unchecked. **Green:** recognised as connected. The screenshot shows results from this map, not a requirement for every map.

Each entry lists the spline ID, start or end, tile coordinates and the finding. Click a row to go there. **Back / Next** changes result pages.

Check again refreshes results after edits. **Markers: ON/OFF** toggles markers in 3D. **Only open / suspect ends** filters results.

Endpoint tolerance: 15 cm. Nothing is changed automatically. Close or Esc closes the list.

23 Working with AI paths

openOMSI Editor 0.7.23-pre | Updated: 11 October 2026

This guide covers existing AI paths, additional connections and testing with traffic. The current tools extend the path and height features introduced in earlier editor releases.

1. Choose the right tool

Edit or delete an existing path: press F9 in the editor or choose **Select / edit AI paths**, then click the path directly. No preceding road-spline selection is required. Paths inside junction objects can also be selected.

Add a turning route: choose **Create additional AI connection**. Connect two existing endpoints. Existing straight-through paths are preserved.

Create lanes along a road: select the road and open **AI paths along the road**. This works on a selected spline or a connected spline chain.

2. Understand the colours

Blue: all vehicles. **Orange:** buses only. Arrows show travel direction. A selected path is highlighted purple.

Editing a selected path: green handles reshape the curve. Purple at the start moves the start; yellow at the end moves the end.

Creating a connection: choose the incoming lane’s yellow end as the start, then the outgoing lane’s purple start as the destination. Green handles shape the connecting curve.

Glowing markers are drawn slightly above the path for visibility. A small display offset is intentional; a clearly floating driving path is not.

24 Create AI driving paths

First select the actual road, not an island, kerb or sidewalk.



English interface

Scope

Scope: selected spline edits one section. **Scope: connected spline chain** follows connected reference splines; junctions or gaps may limit the chain.

Lane count and direction

Cycle between **Two opposing lanes**, **One lane / one-way road** and **Two lanes in the same direction**. Arrows show travel direction. Separately created one-way splines are edited individually.

Vehicles

Choose **All vehicles** or **Buses only** per lane. Bus schedules are separate; this permission does not create a bus service.

Width, offset and height

Lane width and lateral offset define the starting layout. Height above spline lifts the path relative to the road reference. Check that it follows the lane centre. This does not reshape the visible road.

Add or replace

Mode: add missing AI paths keeps existing paths. **Mode: replace existing AI paths** updates editor-generated paths. Do not add another path when you intend to correct one.

About this screenshot

Two opposing lanes are selected. **Select lane 2** switches the edited lane. The status shows **0 new sections, 6 already with paths and 0 open endpoints**. These values depend on the selection.

25 AI paths along a road

Editor 0.7.23-pre | 11 October 2026



English interface

Scope, lanes and direction

Scope: switch between a selected spline and its connected chain. The lane-mode button cycles through **Two opposing lanes**, **One lane / one-way road** and **Two lanes in the same direction**. **Direction:** choose the reference direction or its opposite.

Lane 1 / Lane 2: choose **All vehicles** or **Buses only** per lane. Blue means all vehicles; orange means buses only. Arrows show travel direction.

Placement and freeform points

Lane width: set the width of a lane. **Lateral offset:** move the layout sideways. **Height above spline:** set its vertical offset. Use + / - to change values.

Edit freeform points: toggle point editing. **Select lane:** switch the edited lane. Click and drag a point. **Reset point:** remove its individual offset. **Lower point / Raise point:** lower / raise it by 0.1 m.

Apply the preview

Mode: add missing AI paths: add missing paths and retain existing ones. Switch to “replace existing AI paths” to replace existing paths in the selected scope; inspect the preview before applying.

AI paths: visible - hide: toggle the overlay. **Create AI paths (Enter):** apply the preview. **Refresh preview:** recalculate it. The status line reports new sections and open endpoints.

The bottom buttons open additional connections or direct path selection. **Close (Esc)** closes the tool. Save afterwards, then reload the map.

This tool generates paths from a road. Use direct path selection to move an original individual path.

A bus-only path does not create a timetable. Scheduled buses need a route and timetable. A connection does not force every ordinary car to turn.

26 Shape AI paths with the mouse

Freeform editing works on one selected section at a time.

1. Open the existing path

Select the road or generated AI spline and open **AI paths along the road**. Choose replacement mode when correcting an existing path.

2. Enable freeform editing

Click **Edit freeform points**. The tool switches to the selected section. Each lane starts with nine green points, including its start and end.

3. Choose the lane

With two lanes, use **Select lane 1 / Select lane 2**. The button names the lane you can switch to. Dragging does not move the other lane.

4. Drag points

Hold the left mouse button on a green point and drag. The selected point turns yellow: this means selected, not connected. Intermediate points shape a smooth curve. Keep the path in the centre of its lane.

5. Adjust height or reset a point

Dragging moves points horizontally. **Raise point / Lower point** changes height in 0.1 m steps. **Reset point** resets the point’s displacement. Displacement is limited to 50 m in each local direction.

6. Apply, save and reload


Apply with **Create AI paths / Replace AI paths** or Enter. Ctrl+Z undoes the applied change. Save with Ctrl+S and reload the map for running traffic. Close or Esc discards the unapplied preview.

Longer routes and smooth dragging

Edit connected sections individually and join their endpoints. Chain mode does not overwrite individual freeform shapes as one uniform layout. Mouse movements are combined per frame; release uses the latest position.

27 Select and edit AI paths

Editor 0.7.23-pre | 11 October 2026



English interface

Click the path directly

Press F9 or open “Select / edit AI paths”, then click a blue or orange path. Paths inside junction objects can also be selected. You do not have to select the road first.

Selection and curve handles

Next overlapping path (Tab): cycle through overlapping paths. **Edit curve:** enable or disable editing handles.

Green: shape the curve. **Purple:** move the start. **Yellow:** move the end. Hold a handle with the left mouse button and drag. Check connections and travel direction afterwards.

Delete and reset

Delete AI path (Del): remove only the selected path direction on this instance. The road or junction object remains. A selected deleted path can be restored.

Restore original curve: reset curve shape, endpoint offsets and height correction. **Undo (Ctrl+Z) / Redo (Ctrl+Y):** undo or redo the last individual-path edit.

Save and switch tools

Save map (Ctrl+S): save changes. **AI paths along the selected road:** switch to the road tool when an appropriate road is selected. **Close (Esc):** return to the normal editor view.

Save, then reload the map for AI to use the changed network. Purple selection markers on additional connections follow their actual curve.

Edit existing paths

3. Select a path and reshape it

1. Open F9. Click a blue or orange path and check its purple highlight. The panel identifies road/object, instance ID, path number and direction.

2. Use Tab or “Next overlapping path” when paths overlap. After cycling, enable “Edit curve” if necessary.

3. Hold a green handle with the left mouse button and drag. A top-down or oblique view makes lateral placement easier to judge. Short paths with only two original samples can also be edited.

4. Dragging captures height from loaded road surfaces when the entire interior lies above a road. Otherwise, the geometric road-profile correction is used. A curve outside the road is not automatically moved back onto it.

4. Extend a path

Drag the **yellow end handle** to the desired position. The **purple start handle** moves the start. Adjust the green handles afterwards to keep the route within the intended lane.

Releasing an endpoint near a unique compatible connection may snap it to that position. Moving an endpoint clears its previous explicit link on that side. Check direction and continuity afterwards: identical endpoint coordinates alone do not guarantee a suitable AI route.

5. Delete, reset and undo

Delete / “Delete AI path”: removes only the selected path direction on that instance. The junction object and other routes remain. Removing an entire junction arm may require deleting several paths individually.

Ctrl+Z: undo. **Ctrl+Y:** redo. “Restore AI path” restores the currently selected deleted route. “Restore original curve” resets shape, endpoint offsets and saved height correction.

Reloading starts a new editing session; the previous undo history is not carried over. Saving and reloading are explained on page 32

29 Connections and opposing traffic

Paths touching visually are not yet an explicitly selected connection.

Connect endpoints explicitly

In freeform mode, select the green start or end point. Matching opposite endpoints within 50 m appear purple. A path end connects to another path start, and vice versa. Drag the selected point onto the desired purple target and release; it snaps within 1.5 m.

Check the result

The panel counts fixed connections and open ends. Check the assignment and arrow direction, then apply and save. Moving that endpoint freely again removes its fixed assignment. Nearly overlapping targets may be ambiguous.

Separate straight and right-turn lanes

Connect the straight-ahead lane to the crossing's appropriate straight path and the turning lane to its right-turn path. Merely straightening the visible line does not select the connection. Use two same-direction lanes for adjacent lanes travelling the same way.

Route around a central island

Keep each direction in the centre of its own lane. With right-hand traffic, pass to the right of the island in the direction of travel. Edit opposing lanes separately. With two separate one-way splines, the opposite direction is lane 1 of its own spline.

Arm labels A/B/C/D in the preview

The junction and roundabout builders label their arms in the preview. Match the label to the selected approach. This assists the road connections in chapter 19; AI endpoints are connected in the AI-path tool.


Limits and compatibility

Original paths in standard spline profiles or crossing objects are not overwritten. Custom paths can connect to suitable original endpoints. Free bridges across a crossing do not create traffic-light control or priority rules. Freeform points and fixed connections require this modified openOMSI runtime; an unmodified upstream version does not interpret these extensions.

New in 0.7.22-pre: create an additional AI connection - step-by-step guide on page 30

30 Additional AI connection

Editor 0.7.23-pre | 11 October 2026



English interface

1. Choose source and destination

Select start: click the incoming lane's yellow end. **Select destination:** click the outgoing lane's purple start. Check arrow direction. Connections use path endpoints, not the middle of a path.

2. Shape the connection

Drag both **green curve handles** freely with the left mouse button. Keep the curve in the intended lane. It follows loaded road surfaces; check height from a second camera angle.

Vehicles: all vehicles or buses only. **Lane width:** adjust with + / -. **Select start and destination again:** reset endpoint selection and preview.

3. Add and save

Add connection (Enter): apply the preview. Existing straight-through routes remain. Until you apply it, the curve is only a preview.

Save map (Ctrl+S): save the map. Once source and destination are selected, the button reads **"Add connection + save (Ctrl+S)"**. A complete valid preview is applied before saving; invalid previews stay editable.

Return and continue

Back to AI paths along the road: switch tools. **Close (Esc):** leave the preview; apply it first if you want to keep it. F9 no longer discards a pending connection.

Check the save message, then use "Reload map ...". AI uses the new route after reloading. The bus location and active duty are retained.

If no loaded road surface is found beneath the curve, move it back over the road and let the area load. The entire curve needs a valid road surface before it can be added.

31 AI paths: help and diagnostics

Check the selection and preview before applying and saving.

No paths or control points visible

Show AI paths. Enable freeform mode to see green control points. Background loading may take a moment after enabling the display. Check the information bar: did you select the road or the traffic island? An error can prevent a valid preview.

Cannot select lane 2

One lane / one-way road has only one editable lane, although the second button may still be visible. If the opposite direction belongs to another AI spline, select it separately. Avoid creating a duplicate path over an existing one.

Curve too tight for this lane offset

A section does not fit the configured lateral offset. In chain mode, another section may be responsible. Select the correct road individually and check width, offset and curvature; do not use the narrow island edge as the reference.

Yellow point will not snap

Yellow means selected. Hold the left mouse button and drag the endpoint onto the matching purple target, then release. Check direction, distance and the 50 m displacement limit. Interior control points are not connection endpoints.

Another prolonged freeze?

Launch with start-editor-diagnose.sh. Note the time and action: dragging, releasing, applying or moving the camera. Save game.log before the next launch. EDITOR-DIAG reports slow operations; 0.7.20 also reports excessive waiting of combined mouse movements.

What has been observed

Normal dragging without freezes was confirmed on Linux with 0.7.20. The path display builds in the background. A brief map-update delay can still occur; diagnostics do not prove smooth operation on every map under all conditions.

Finish safely

Apply the preview, save with Ctrl+S, then reload the map for AI traffic. After troubleshooting, return to normal startup with start-editor.sh. Diagnostics stop; the improvements stay active.

32 Save and test with traffic

Editor 0.7.23-pre | Local development build | 12.10.2026

Reloading during a duty - local development build
Single-player map reload retains the bus position, duty, technical bus state, passengers in the player bus and selected camera view, provided the same bus can be restored. An ongoing ticket sale is retained. Waiting people are retained at still-loaded stops moved by up to 30 m; deleted stops or larger moves are excluded. Other pedestrians and AI-bus passengers are regenerated. Move waiting-point objects and shelters as well when permanently relocating a stop. This continuation applies to map reload within the current session, not loading a saved situation or LAN.

6. A reliable test workflow 1. Save with Ctrl+S and check the save message. Close the tool with Esc. Use “Reload map …” or reopen the map.

3. Unpause: P toggles pause. Close menus and check that time advances. Wait several simulation seconds; if needed, drive a short distance and observe the approach. 4. With a player bus present, ordinary street traffic is populated around the bus. Flying to a distant junction with the free camera alone does not move that population area. Without a player bus, the camera is used as the centre. 5. Observe vehicles on the approach: do they follow the lane, stay at road height and cross the joins? Wait for several vehicles. Seeing a path overlay alone does not prove a driveable connection.

7. If you cannot see cars At a distant camera location: first bring the bus to the test area. Everywhere: check traffic at session start and its amount in settings. Random street traffic and scheduled services are separate; a timetable bus does not prove that cars spawn on every road. Only at the edited route: check map copy, version, saving and reloading. Endpoints and travel direction must match. Gaps, deleted adjacent routes, bus-only permissions and map traffic-density rules may prevent traffic there. Inspect the log: “traffic:” reports loaded network and vehicle types; “AI vehicles” reports active vehicles. This is a session count, not a count restricted to the visible junction. Assess missing vehicle files separately from texture warnings.

8. Files and compatibility Individual path edits are stored as editor_lane_* rules in the map tile. Shared SCO/SLI definitions are preserved. New connections have their own AI spline files; these belong with the map. The extensions require a compatible openOMSI version and are not fully applied by original OMSI 2 or older editors. Path editing supports ordinary single-player maps and version 14 tiles. Active Chrono changes may be protected. Use a map copy before extensive edits. AI traffic and passengers are rebuilt when reloading. Check connections after editing.

33 Version, startup and updates

Editor 0.7.23-pre | Local development build | 12.10.2026

Version and installation
This guide covers Editor 0.7.23-pre, openOMSI base 0.2.27 and local additions dated 12 October 2026. Already published downloads are not changed by these edits. OMSI 2 content is not included. End the driving session and back up maps before installing or updating.

Normal startup
In the installed editor folder, run bash start-editor.sh "/path/to/content". An existing start.sh can also be used. The source package and installed editor folder are different. Follow the installation instructions included with source packages.

Two separate update checks
Settings → General → Updates provides Check now for the separate openOMSI game installation and for the editor package. Checking alone installs nothing. A newer version shows the target folder, release notes and Download and install. Editor updates currently support Linux x64, including prereleases.


Game and editor remain separate
The editor package contains its own engine. Updating the separate game installation does not replace it. Both programs can use the same content folder. The check does not create a separate game installation if none exists. A newer game does not guarantee that new content formats work with an older editor engine.

Backups and recovery
Update packages are verified using SHA-256. Replaced program files are saved under .editor-update-backups/ in the installation folder. RECOVERY.txt identifies the target folder. Restore only after fully closing the program. A program backup does not replace a map backup.

Controls and screenshots
Drag windows by their title bars. Camera movement works in the height tool; finish numeric input with Enter or Esc first. Older screenshots may show earlier versions. New screenshots use the English interface.

34 Check and install updates

Editor 0.7.23-pre | Local development build | 12.10.2026



1 Open the update section
Open Settings → General → Updates. The two buttons check different programs.

2 Choose the correct check
openOMSI · separate game installation checks the normal game in the selected content folder. openOMSI Editor · editor package checks the editor, including prereleases. Check now does not install anything.

3 Review the offer
If a newer version is found, check the release notes, version and target folder. End the driving session and back up maps before installation. Download and install starts installation.

4 After updating
An editor update restarts the editor. A game update does not replace the bundled editor engine. Both programs can use the same maps and mods. Backup and compatibility details: page 33.

State shown in the screenshot
The image shows the buttons before a check. Download and installation controls appear only when an update is available. Reset all settings affects settings and is not an update tool.