


Consumables Floor Map

How to use it • GXO Sherburn

The floor map is an Excel file (**Consumables_Map.xlsx**) that shows every pallet space in the consumables area. It shows what's in each space, what's free, and what's running low.



Example map with a few test pallets. The loading bay is at the top, the fire exit at the bottom, and the main walkway runs up the middle.

The sheets (tabs at the bottom)

Sheet	What it's for
Map	The floor plan. Look here first.
Dashboard	Totals for each item, space used in each zone, the low-stock list and the next free space.
Items	Your list of products. You fill this in.
Locations	One row for every pallet space. This is where the map gets its information.
Config	Aisle sizes, zones, colours and settings.
MoveLog	Every move, with the time and who did it. Written automatically.

What the map shows

You see	It means
Solid colour	A pallet is there. Hover over it to see the details.
Stripes	A free space, kept for that zone.
Grey "NOT OURS"	Someone else's space. Don't use it.
Thick red border	The pallet is in the wrong zone .

You see	It means
Red line along the bottom	That item is low on stock .
Thick black border	The pallet you've picked up to move.

Zone	Colour and what goes there	Zone	Colour and what goes there
BOX	Brown: all box types	FLM	Teal: pallet wrap, films, bubble wrap
BAG	Blue: packing bags	LBL	Amber: labels, void fill, tape, other packing

Reading a location code: **L2-05-C** means aisle **L2**, **5** pallets in from the walkway, row **C**. Row letters go A, B, C, D from the top of each aisle on the map.

1. First-time setup (do once)

Check the aisles

1. Open the **Config** sheet.
2. In the **Aisles** table, check each aisle. **PalletsAcross** is how many pallets wide it is, and **PalletsDeep** is how many deep. **Zone** is what goes there.
3. **Active** is **Yes** for your aisles, **Blocked** for someone else's space, and **No** to hide one.

The starting sizes come from your floor sketch. Please check that **R1** (the narrow aisle) is 2 across and that **R2–R4** are 4 × 16. Also check which zone each aisle is for. After changing any sizes, press **Rebuild Layout** on the Map (needs macros, see section 3).

Add your items

1. Open the **Items** sheet.
2. Type over the two rows marked **EXAMPLE**, then keep adding items in the row under the table. The table grows by itself.
3. Fill in **ItemCode** (short, like BX-S), **Description**, **Zone**, **UnitsPerPallet** and **OnHandUnits**.
4. Leave **ReorderPallets** blank to use the normal low-stock level (2 pallets), or type a number for that item.
5. Don't type in the grey columns on the right. They work themselves out.

2. Everyday use: no macros needed

This always works, even if your PC blocks macros.

Put a pallet away

1. Open the **Locations** sheet.
2. Find the space, for example **R3-01-B**.
3. Click its **ItemCode** cell and pick the item from the dropdown. The list only shows items for that zone.
4. Optional: type the number of units in **UnitsOnPallet** if it's not a full pallet.

Take a pallet out

1. Find its space on **Locations** and delete the **ItemCode** (and **UnitsOnPallet**).

Move a pallet

1. Delete it from the old space and pick it in the new space.

The **Map** and **Dashboard** update straight away. When stock is used, update **OnHandUnits** on the **Items** sheet.

3. Click-to-move: turning on the macros (once)

If your PC allows macros, you can move pallets by clicking the map. You'll need the file **FloorMap_VBA.txt**.

1. In Excel, click **File** → **Save As**. Choose **Excel Macro-Enabled Workbook (.xlsm)** and save. Use this .xlsm file from now on.
2. Press **Alt + F11** to open the code window.
3. Click **Insert** → **Module**. Open FloorMap_VBA.txt in Notepad, copy everything between **PART 1 START** and **PART 1 END**, and paste it in.
4. On the left, double-click the sheet marked **(Map)** and paste **PART 2**.
5. Double-click the sheet marked **(Locations)** and paste **PART 3**.
6. Optional: double-click **ThisWorkbook** and paste **PART 4**, so the file opens on the map.
7. Click **Debug** → **Compile VBAProject**. If nothing pops up, it's fine.
8. Close the code window. Press **Alt + F8**, choose **SetupButtons** and click **Run**. Five pink buttons appear on the Map.
9. Press **Ctrl + S** to save. Next time you open it, click **Enable Content** if you see a yellow bar.

If Excel says macros are blocked, close the file. Right-click it in File Explorer, choose **Properties**, tick **Unblock**, then click **OK**. If IT blocks macros completely, just use section 2. Everything else still works.

4. Everyday use with the buttons

To do this	Do this
Move a pallet	Click the pallet (it gets a black border), then click an empty square.
Swap two pallets	Click one pallet, then click the other.
Cancel a move	Click the same pallet again, press Esc , or press Cancel Move .
Put a delivery away	Press Find Space . Type the item code, then the number of units. It works out how many pallets and picks free spaces in the right zone, nearest the loading bay. Click Yes to put them in.
Zone full?	Find Space offers spaces in other zones, marked OUT OF ZONE . It's your choice.
Colours look wrong	Press Refresh .
Changed aisle sizes on Config	Press Rebuild Layout . Pallets stay where they are. Any that no longer fit are listed and saved in MoveLog.
Map too big or small	Press Fit to Screen .

- If you move a pallet into the wrong zone, Excel asks you to confirm. You can say Yes if you need to.
- Every move is recorded on **MoveLog** with the time and your login name.

5. Something not right?

Problem	Fix
Clicking the map does nothing	Macros are off or not set up. Use the Locations sheet (section 2), or set up the macros (section 3).
"Compile error"	A part went in the wrong place, or a banner line was copied. Paste each part again.
Item not in the dropdown	Check the item's Zone on the Items sheet matches the aisle's zone.
A pallet vanished after Rebuild Layout	Look at the bottom of MoveLog for "removed by Rebuild Layout".
Item shows LOW but you have stock	Check that the pallets are placed on Locations , and check ReorderPallets on Items.