Университет ИТМО

Факультет программной инженерии и компьютерной техники

Лабораторная работа №7 по Администрированию систем и сетей «Создание сети IPv6»


Работу выполнили студенты группы Р34101:Патутин Владимир Крюков Андрей

> Преподаватель: Афанасьев Дмитрий Борисович Желаемая оценка: 3

Оглавление

Топология:
Шаг 1. Настройте основные параметры устройств
Шаг 2. Настройте функции IPv6 на устройствах и интерфейсах 3
Шаг 3. Настройте локальный адрес канала (link-local address) для интерфейса и проверьте конфигурацию
Шаг 4. Настройте статические IPv6-адреса на R2 6
Шаг 5 Настройте функцию сервера DHCPv6 на R2 и настройте R3 для получения IPv6-адресов через DHCPv6
Шаг 6. Настройте R1 для получения IPv6-адреса в режиме без отслеживания состояния
Шаг 7. Настройте статический маршрут IPv6 8
Выводы:

Топология:



Шаг 1. Настройте основные параметры устройств

Задайте имена устройствам.

<Huawei>system-view
Enter system view, return user view with Ctrl+Z.
[Huawei]sysname R1
[R1]

<Huawei>system-view
Enter system view, return user view with Ctrl+Z.
[Huawei]sysname R2
[R2]

<Huawei>system-view
Enter system view, return user view with Ctrl+Z.
[Huawei]sysname R3
[R3]

Шаг 2. Настройте функции IPv6 на устройствах и интерфейсах.

Включите IPv6 глобально.

[R1]ipv6
[R2]ipv6
[R3]ipv6

Включите IPv6 на интерфейсе.

[R1]interface GigabitEthernet 0/0/0
[R1-GigabitEthernet0/0/0]ipv6 enable
[R1-GigabitEthernet0/0/0]quit
[R1]

```
[R2]interface GigabitEthernet 0/0/0
[R2-GigabitEthernet0/0/0]ipv6 enable
[R2-GigabitEthernet0/0/0]quit
[R2]interface GigabitEthernet 0/0/1
[R2-GigabitEthernet0/0/1]ipv6 enable
[R2-GigabitEthernet0/0/1]quit
[R2]
[R3]interface GigabitEthernet 0/0/0
[R3-GigabitEthernet0/0/0]ipv6 enable
[R3-GigabitEthernet0/0/0]quit
[R3]
```

Шаг 3. Настройте локальный адрес канала (link-local address) для интерфейса и проверьте конфигурацию.

```
Настройте на интерфейсе автоматическое генерирование локального адреса канала
[R1]interface GigabitEthernet 0/0/0
[R1-GigabitEthernet0/0/0]ipv6 address auto link-local
[R1-GigabitEthernet0/0/0]quit
[R1]
[R2]interface GigabitEthernet 0/0/0
[R2-GigabitEthernet0/0/0]ipv6 address auto link-local
[R2-GigabitEthernet0/0/0]quit
[R2]interface GigabitEthernet 0/0/1
[R2-GigabitEthernet0/0/1]ipv6 address auto link-local
[R2-GigabitEthernet0/0/1]quit
[R2]
[R3]interface GigabitEthernet 0/0/0
[R3-GigabitEthernet0/0/0]ipv6 address auto link-local
[R3-GigabitEthernet0/0/0]quit
[R3]
Выведите на экран IPv6-статус интерфейса и проверьте возможность подключения
<R1>display ipv6 interface GigabitEthernet 0/0/0
GigabitEthernet0/0/0 current state : UP
IPv6 protocol current state : UP
IPv6 is enabled, link-local address is FE80::2E0:FCFF:FE90:4B3E
 No global unicast address configured
 Joined group address(es):
    FF02::1:FF90:4B3E
    FF02::2
   FF02::1
 MTU is 1500 bytes
 ND DAD is enabled, number of DAD attempts: 1
 ND reachable time is 30000 milliseconds
 ND retransmit interval is 1000 milliseconds
 Hosts use stateless autoconfig for addresses
<R1>
<R2>display ipv6 interface GigabitEthernet 0/0/0
GigabitEthernet0/0/0 current state : UP
IPv6 protocol current state : UP
IPv6 is enabled, link-local address is FE80::2E0:FCFF:FEF2:4174
 No global unicast address configured
 Joined group address(es):
   FF02::1:FFF2:4174
    FF02::2
```

```
FF02::1
 MTU is 1500 bytes
 ND DAD is enabled, number of DAD attempts: 1
 ND reachable time is 30000 milliseconds
 ND retransmit interval is 1000 milliseconds
 Hosts use stateless autoconfig for addresses
<R2>display ipv6 interface GigabitEthernet 0/0/1
GigabitEthernet0/0/1 current state : UP
IPv6 protocol current state : UP
IPv6 is enabled, link-local address is FE80::2E0:FCFF:FEF2:4175
 No global unicast address configured
 Joined group address(es):
   FF02::1:FFF2:4175
   FF02::2
   FF02::1
 MTU is 1500 bytes
 ND DAD is enabled, number of DAD attempts: 1
 ND reachable time is 30000 milliseconds
 ND retransmit interval is 1000 milliseconds
 Hosts use stateless autoconfig for addresses
<R2>
<R3>display ipv6 interface GigabitEthernet 0/0/0
GigabitEthernet0/0/0 current state : UP
IPv6 protocol current state : UP
IPv6 is enabled, link-local address is FE80::2E0:FCFF:FEBB:77AF
 No global unicast address configured
 Joined group address(es):
   FF02::1:FFBB:77AF
   FF02::2
   FF02::1
 MTU is 1500 bytes
 ND DAD is enabled, number of DAD attempts: 1
 ND reachable time is 30000 milliseconds
 ND retransmit interval is 1000 milliseconds
 Hosts use stateless autoconfig for addresses
<R3>
Проверьте сетевое соединение между маршрутизаторами R1 и R2
<R1>ping ipv6 FE80::2E0:FCFF:FEF2:4174 -i GigabitEthernet 0/0/0
  PING FE80::2E0:FCFF:FEF2:4174 : 56 data bytes, press CTRL C to break
    Reply from FE80::2E0:FCFF:FEF2:4174
    bytes=56 Sequence=1 hop limit=64
                                     time = 120 ms
    Reply from FE80::2E0:FCFF:FEF2:4174
    bytes=56 Sequence=2 hop limit=64
                                     time = 20 ms
    Reply from FE80::2E0:FCFF:FEF2:4174
    bytes=56 Sequence=3 hop limit=64
                                     time = 20 ms
    Reply from FE80::2E0:FCFF:FEF2:4174
    bytes=56 Sequence=4 hop limit=64 time = 20 ms
    Reply from FE80::2E0:FCFF:FEF2:4174
   bytes=56 Sequence=5 hop limit=64 time = 20 ms
  --- FE80::2E0:FCFF:FEF2:4174 ping statistics ---
    5 packet(s) transmitted
    5 packet(s) received
    0.00% packet loss
    round-trip min/avg/max = 20/40/120 ms
```

Шаг 4. Настройте статические IPv6-адреса на R2.

```
[R2]interface GigabitEthernet 0/0/0
[R2-GigabitEthernet0/0/0]ipv6 address 2000:0012::2 64
[R2-GigabitEthernet0/0/0]quit
[R2]interface GigabitEthernet 0/0/1
[R2-GigabitEthernet0/0/1]ipv6 address 2000:0023::2 64
[R2-GigabitEthernet0/0/1]quit
[R2]
```

Шаг 5 Настройте функцию сервера DHCPv6 на R2 и настройте R3 для получения IPv6-адресов через DHCPv6.

Настройте функцию сервера DHCPv6.

```
[R2]dhcp enable
Info: The operation may take a few seconds. Please wait for a moment.done.
[R2]dhcpv6 pool pool1
[R2-dhcpv6-pool-pool1]address prefix 2000:0023::/64
[R2-dhcpv6-pool-pool1]dns-server 2000:0023::2
[R2-dhcpv6-pool-pool1]quit
[R2]interface GigabitEthernet 0/0/1
[R2-GigabitEthernet0/0/1]dhcpv6 server pool1
[R2-GigabitEthernet0/0/1]quit
[R2]
```

Настройте функцию клиента DHCPv6.

```
[R3]dhcp enable
Info: The operation may take a few seconds. Please wait for a moment.done.
[R3]interface GigabitEthernet 0/0/0
[R3-GigabitEthernet0/0/0]ipv6 address auto dhcp
[R3-GigabitEthernet0/0/0]quit
[R3]
```

Выведите на экран адрес клиента и информацию о DNS-сервере.

```
[R3]display ipv6 interface brief
*down: administratively down
(1): loopback
(s): spoofing
Interface
                            Physical
                                                  Protocol
GigabitEthernet0/0/0
                            up
                                                  up
[IPv6 Address] 2000:23::1
[R3]display dns serve
Type:
D:Dynamic S:Static
No configured ip dns servers.
No. Type IPv6 Address
                                                   Interface Name
         2000:23::2
    D
[R3]
```

Настройте сервер DHCPv6 для передачи адресов шлюза клиентам

```
[R2]interface GigabitEthernet 0/0/1
[R2-GigabitEthernet0/0/1]undo ipv6 nd ra halt
[R2-GigabitEthernet0/0/1]ipv6 nd autoconfig managed-address-flag
[R2-GigabitEthernet0/0/1]ipv6 nd autoconfig other-flag
```

```
[R2-GigabitEthernet0/0/1]quit
[R2]
Настройте клиент на получение маршрута по умолчанию посредством сообщений RA.
[R3]interface GigabitEthernet 0/0/0
[R3-GigabitEthernet0/0/0]ipv6 address auto global default
[R3-GigabitEthernet0/0/0]quit
[R3]
Выведите на экран маршруты R3.
[R3]display ipv6 routing-table
Routing Table : Public
     Destinations : 4 Routes : 4
Destination : ::
                                             PrefixLength: 0
NextHop : FE80::2E0:FCFF:FEF2:4175
                                            Preference : 64
            : 0
                                             Protocol : Unr
RelayNextHop : ::
                                             TunnelID
                                                         : 0x0
Interface : GigabitEthernet0/0/0
                                             Flags
Destination : ::1
                                             PrefixLength: 128
NextHop :::1
                                             Preference : 0
Cost
            : 0
                                             Protocol : Direct
RelayNextHop : ::
                                             TunnelID
                                                         : 0x0
Interface : InLoopBack0
                                             Flags
Destination : 2000:23::1
                                             PrefixLength: 128
NextHop :::1
Cost : 0
                                             Preference : 0
                                             Protocol : Direct TunnelID : 0x0
Cost
            : 0
RelayNextHop : ::
Interface : GigabitEthernet0/0/0
                                                         : D
                                             Flags
Destination : FE80::
                                             PrefixLength: 10
NextHop :::
                                             Preference : 0
                                             Protocol : Direct
TunnelID : 0x0
Flags : D
            : 0
Cost
```

[R3]

RelayNextHop : ::

Interface : NULL0

Шаг 6. Настройте R1 для получения IPv6-адреса в режиме без отслеживания состояния.

: D

Включите RA на GigabitEthernet0/0/0 маршрутизатора R2.

```
[R2]
[R2]interface GigabitEthernet 0/0/0
[R2-GigabitEthernet0/0/0]undo ipv6 nd ra halt
```

Включите функцию автоконфигурации адреса без отслеживания состояния на GigabitEthernet0/0/3 маршрутизатора R1.

```
[R1]interface GigabitEthernet 0/0/0
[R1-GigabitEthernet0/0/0] ipv6 address auto global
[R1-GigabitEthernet0/0/0]
```

Выведите на экран конфигурацию IP-адреса маршрутизатора R1.

```
[R1] display ipv6 interface brief
*down: administratively down
```

```
(1): loopback
(s): spoofing
Interface Physical GigabitEthernet0/0/0 up
                                                    Protocol
                                                     up
[IPv6 Address] 2000:12::2E0:FCFF:FE90:4B3E
[R1]
```

Шаг 7. Настройте статический маршрут IPv6.

Настройте статический маршрут на маршрутизаторе R1, чтобы обеспечить соединение между GigabitEthernet0/0/3 на маршрутизаторе R1 и GigabitEthernet0/0/3 на маршрутизаторе R3.

```
[R1]ipv6 route-static 2000:23:: 64 2000:12::2
```

Проверьте возможность установления связи.

```
[R1]ping ipv6 2000:23::1
 PING 2000:23::1 : 56 data bytes, press CTRL C to break
   Reply from 2000:23::1
   bytes=56 Sequence=1 hop limit=63 time = 40 ms
   Reply from 2000:23::1
   bytes=56 Sequence=2 hop limit=63 time = 50 ms
   Reply from 2000:23::1
   bytes=56 Sequence=3 hop limit=63 time = 30 ms
   Reply from 2000:23::1
   bytes=56 Sequence=4 hop limit=63 time = 40 ms
   Reply from 2000:23::1
   bytes=56 Sequence=5 hop limit=63 time = 20 ms
  --- 2000:23::1 ping statistics ---
   5 packet(s) transmitted
   5 packet(s) received
   0.00% packet loss
   round-trip min/avg/max = 20/36/50 ms
```

[R1]

Выведите на экран информацию о соседях IPv6

```
[R1]display ipv6 neighbors
```

```
IPv6 Address : 2000:12::2
Link-layer : 00e0-fcf2-4174
Interface : GE0/0/0
                                                      State : STALE
                                                      Age : 1
             : -
VLAN
                                                       CEVLAN: -
VLAN :
VPN name :
                                                       Is Router: TRUE
```

Secure FLAG : UN-SECURE

IPv6 Address : FE80::2E0:FCFF:FEF2:4174

Link-layer : 00e0-fcf2-4174
Interface : GE0/0/0
VLAN : VPN name : State : STALE Age : 0 CEVLAN: -

Is Router: TRUE

Secure FLAG : UN-SECURE

Total: 2 Dynamic: 2 Static: 0

[R1]

Выводы:

Таким образом, мы научились создавать сети IPv6.