Valhalla VM spec

Instruction set

- rd = destination register,
- rs = source register,
- im = immediate value,
- ad = memory address (label)

Value	Opcode	Description
oxoo	NOP	Do nothing.
OXO1	HCF	Halt and catch fire. Stops execution of instructions.
0x02	MOV rd rs	Sets rd to the value of rs.
oxo3	SET rd im	Sets rd to im.
0x04	GET rd rs	Sets rd to the value of memory at location rs.
oxo5	STR rd rs	Sets the memory at location rd to the value of rs.
0x06	ADD rd rs	Adds the values of rd and rs and stores the result in rd.
0x07	SUB rd rs	Subtracts rs from rd and stores the result in rd.
oxo8	MUL rd rs	Multiplies the values of rd and rs and stores the result in rd.
0x09	DIV rd rs	Divides rd by rs and stores the result in rd.
oxoA	MOD rd rs	Divides rd by rs and stores the modulo in rd.
oxoB	OR rd rs	Sets rd to bitwise or of rd and rs.
oxoC	AND rd rs	Sets rd to bitwise and of rd and rs.
oxoD	XOR rd rs	Sets rd to bitwise xor of rd and rs.
oxoE	NOT rd	Negates rd.
oxoF	SHL rd rs	Left shifts bits stored in rd by rs positions.
0x10	SHR rd rs	Right shifts bits stored in rd by rs positions.
OX11	PRI rd	Reads the value stored in rd as integer and prints it on the screen.
0x12	PRS ad	Prints characters starting from location ad until null byte (0x00).

Value	Opcode	Description
0x13	CMP rd rs	Compares numbers stored in rd and rs.
0x14	JMP ad	Jumps to address ad.
0x15	JEQ ad	Jumps to address ad when last comparison was equal.
ox16	JLT ad	Jumps to address ad when last comparison was less than.
0x17	JGT ad	Jumps to address ad when last comparison was greater than.
ox18	JLE ad	Jumps to address ad when last comparison was less or equal.
0x19	JGE ad	Jumps to address ad when last comparison was greater or equal.
ox1A	JNE ad	Jumps to address ad when last comparison was not equal.
ox1B	RED rd	Blocks; Reads integer from stdin to rd.
0x1C	RND rd	Draws random number from 0 to 255 and saves it in rd.