

Routers

HQ-Router

enable

configure terminal

hostname HQ-Router

interface GigabitEthernet0/0

ip address 1.2.0.1 255.255.248.0

no shutdown

interface GigabitEthernet0/1

ip address 1.2.24.129 255.255.255.252

no shutdown

interface GigabitEthernet0/2

ip address 1.2.24.133 255.255.255.252

no shutdown

ip route 1.2.24.0 255.255.255.128 1.2.24.130

ip route 1.2.8.0 255.255.252.0 1.2.24.134

ip route 1.2.12.0 255.255.252.0 1.2.24.134

ip route 1.2.16.0 255.255.254.0 1.2.24.134

ip route 1.2.18.0 255.255.254.0 1.2.24.134

ip route 1.2.20.0 255.255.254.0 1.2.24.134

ip route 1.2.22.0 255.255.254.0 1.2.24.134

ip route 1.2.24.148 255.255.255.252 1.2.24.134

ip route 1.2.24.140 255.255.255.252 1.2.24.134

ip route 1.2.24.152 255.255.255.252 1.2.24.134

end

write memory

EMRG-Router

enable

configure terminal

hostname EMRG-Router

interface GigabitEthernet0/0

ip address 1.2.24.1 255.255.255.128

no shutdown

```
interface GigabitEthernet0/1
ip address 1.2.24.130 255.255.255.252
no shutdown

ip route 1.2.0.0 255.255.248.0 GigabitEthernet0/1

end
write memory
```

SimCore-Router

```
enable
configure terminal
hostname SimCore-Router

interface GigabitEthernet0/0
ip address 1.2.8.1 255.255.252.0
no shutdown

interface GigabitEthernet0/1
ip address 1.2.24.134 255.255.255.252
no shutdown

interface GigabitEthernet0/2
ip address 1.2.24.138 255.255.255.252
no shutdown

interface Serial0/3/0
ip address 1.2.24.149 255.255.255.252
clock rate 64000
no shutdown

interface Serial0/3/1
ip address 1.2.24.142 255.255.255.252
clock rate 64000
no shutdown

ip route 1.2.0.0 255.255.248.0 1.2.24.133
ip route 1.2.24.0 255.255.255.128 1.2.24.133
ip route 1.2.24.144 255.255.255.252 1.2.24.150
ip route 1.2.24.152 255.255.255.252 1.2.24.141

router rip
version 2
```

```
network 1.2.8.0
network 1.2.24.0
no auto-summary
```

```
end
write memory
```

Sandbox-Router

```
enable
configure terminal
hostname Sandbox-Router
```

```
interface GigabitEthernet0/0
ip address 1.2.12.1 255.255.252.0
no shutdown
```

```
interface Serial0/3/0
ip address 1.2.24.150 255.255.255.252
no shutdown
```

```
interface Serial0/3/1
ip address 1.2.24.146 255.255.255.252
no shutdown
```

```
ip route 1.2.0.0 255.255.248.0 1.2.24.149
```

```
router rip
version 2
network 1.2.12.0
network 1.2.24.0
no auto-summary
```

```
end
write memory
```

AI-Router

```
enable
configure terminal
hostname AI-Router
```

```
interface GigabitEthernet0/0
ip address 1.2.16.1 255.255.254.0
no shutdown
```

```
interface GigabitEthernet0/1
ip address 1.2.18.1 255.255.254.0
no shutdown

interface GigabitEthernet0/2
ip address 1.2.24.137 255.255.255.252
no shutdown

interface Serial0/3/0
ip address 1.2.24.145 255.255.255.252
no shutdown

ip dhcp excluded-address 1.2.16.1 1.2.16.10
ip dhcp excluded-address 1.2.18.1 1.2.18.10

ip dhcp pool ML-ENGINE
network 1.2.16.0 255.255.254.0
default-router 1.2.16.1
dns-server 1.2.0.2
lease 1

ip dhcp pool DATA-CELL
network 1.2.18.0 255.255.254.0
default-router 1.2.18.1
dns-server 1.2.0.2
lease 1

ip route 1.2.0.0 255.255.248.0 1.2.24.138
ip route 1.2.0.0 255.255.248.0 1.2.24.146 88
ip route 1.2.24.0 255.255.255.128 1.2.24.138

router rip
version 2
network 1.2.16.0
network 1.2.18.0
network 1.2.24.0
no auto-summary

end
write memory
```

Diag-Router

```
enable
configure terminal
hostname Diag-Router

interface GigabitEthernet0/0
ip address 1.2.20.1 255.255.254.0
no shutdown

interface GigabitEthernet0/1
ip address 1.2.24.153 255.255.255.252
no shutdown

interface Serial0/3/0
ip address 1.2.24.141 255.255.255.252
no shutdown

ip dhcp excluded-address 1.2.20.1 1.2.20.10

ip dhcp pool DIAG-BAY
network 1.2.20.0 255.255.254.0
default-router 1.2.20.1
dns-server 1.2.0.2
lease 1

ip route 1.2.0.0 255.255.248.0 1.2.24.142
ip route 1.2.24.0 255.255.255.128 1.2.24.142

router rip
version 2
network 1.2.20.0
network 1.2.22.0
network 1.2.24.0
no auto-summary

end
write memory
```

Repair-Router

```
enable
configure terminal
hostname Repair-Router

interface GigabitEthernet0/0
```

```
ip address 1.2.22.1 255.255.254.0
no shutdown

interface GigabitEthernet0/1
ip address 1.2.24.154 255.255.255.252
no shutdown

ip dhcp excluded-address 1.2.22.1 1.2.22.10

ip dhcp pool REPAIR-UNIT
network 1.2.22.0 255.255.254.0
default-router 1.2.22.1
dns-server 1.2.0.2
lease 1

ip route 1.2.0.0 255.255.248.0 1.2.24.153
ip route 1.2.8.0 255.255.252.0 1.2.24.153
ip route 1.2.12.0 255.255.252.0 1.2.24.153
ip route 1.2.16.0 255.255.254.0 1.2.24.153
ip route 1.2.18.0 255.255.254.0 1.2.24.153
ip route 1.2.20.0 255.255.254.0 1.2.24.153
ip route 1.2.24.0 255.255.255.128 1.2.24.153

router rip
version 2
network 1.2.22.0
network 1.2.24.0
no auto-summary

end
write memory
```

Servers

HQ-DNS-WEB Server

IP Address: 1.2.0.2
Subnet Mask: 255.255.248.0
Gateway: 1.2.0.1
DNS Server: 1.2.0.2

HQ-Mail Server

IP Address: 1.2.0.3

Subnet Mask: 255.255.248.0
Gateway: 1.2.0.1
DNS Server: 1.2.0.2

AI-Mail Server

IP Address: 1.2.16.2
Subnet Mask: 255.255.254.0
Gateway: 1.2.16.1
DNS Server: 1.2.0.2

DHCP-Server in SimCore

IP Address: 1.2.8.2
Subnet Mask: 255.255.252.0
Gateway: 1.2.8.1
DNS Server: 1.2.0.2

Pool 1:

Name: SimCore-Pool
Default Gateway: 1.2.8.1
DNS: 1.2.0.2
Start IP: 1.2.8.11
Subnet Mask: 255.255.252.0
Max Users: 600

Pool 2:

Name: Sandbox-Pool
Default Gateway: 1.2.12.1
DNS: 1.2.0.2
Start IP: 1.2.12.11
Subnet Mask: 255.255.252.0
Max Users: 600