DJBILBOX BEATS / HUMPIRE

CHINTZWAZ

Retro floral synthesizer: sitar, flower-power keys, tape strings, flutes, kalimba, pads and psychedelic organ, from eight synthesis engines.

Version 1.0 - Windows (VST3) and macOS (VST3 / Audio Unit) - Royalty-free license

Contents

CHINTZWAZ

- Overview
- Quick start in FL Studio
- Interface
- Parameters
- Factory presets
- Production tips
- MIDI, automation and performance
- FAQ

CHINTZWAZ

Retro floral synthesizer: sitar, flower-power keys, tape strings, flutes, kalimba, pads and psychedelic organ, from eight synthesis engines.

Type	Synthesizer (instrument)
Format	VST3 64-bit (Windows); VST3 + Audio Unit, universal (macOS)
Brand / developer	HUMPIRE by DJBILBOX BEATS
Version	1.0
Factory presets	70
Latency	0 samples

Overview

CHINTZWAZ is a retro, bohemian synthesizer sold under the HUMPIRE brand by DJBILBOX BEATS. It uses no samples. Every sound is generated in real time by one of eight engines: Sitar Bloom (a plucked string with a buzzing bridge), Flower EP (an electric piano with a bell-like tine), Mellotron (five detuned saws with tape flutter and breath), Hippie Flute (a sine with harmonics, vibrato and breath noise), Kalimba (short metallic tines), Daisy Pad (detuned saws with a sub octave and a slowly breathing filter), Bloom Bass (a filtered triangle/saw with a round sub) and Psyche Organ (a drawbar organ with tremolo).

Five character controls (TONE, BODY, BRIGHT, WIDTH, TEXTURE) reshape each engine. The sound then goes through a multimode filter with its own envelope, an amplitude envelope, an LFO and an effects chain: distortion, chorus, ping-pong delay and reverb. The look is a pink brushed-metal faceplate on floral wallpaper.

CHINTZWAZ fits Lo-fi Hip-Hop and Boom Bap loops, psychedelic Soul and Funk, Oriental-flavored melodies (sitar, flute), Afrobeats and Amapiano (kalimba, pads), dreamy pads and retro keys. Most presets load in Poly mode (up to 16 voices). Twelve presets load in Mono mode: one flute-and-tape lead and the bass and organ voices.

Quick start in FL Studio

1. In the **Channel rack**, click **+** and choose **CHINTZWAZ** (vendor **DJBILBOX BEATS**). You can also drag it from the **Plugin database > Generators** browser.
2. The plugin opens on **CHINTZWAZ - Init Patch**: the Sitar Bloom engine in Poly mode.
3. Click the **folder icon** at the left of the preset display. Pick a bank, then a preset. You can also step through all 70 presets with the **<** and **>** arrows.
4. Play from your MIDI keyboard or draw notes in the **Piano roll**. The on-screen keyboard covers MIDI notes 48 to 96 (C4 to C8 in FL Studio naming, where middle C is C5). Keys, pads and plucks work well in the middle of that range; the Bloom Bass presets sit lower, so play them from a MIDI keyboard or the Piano roll.
5. Shape the sound with the three main controls:
   - **TONE**: the main character of the engine (pluck brightness, tape color, breath pitch, organ sub drawbar…).
   - **CUTOFF**: the cutoff of the filter. Turn it down for a darker, vintage tone.
   - **WIDTH**: jawari buzz, tape detune and wobble, flute vibrato, pad detune or organ tremolo, depending on the engine.
6. Adjust **VOLUME** to set the level, then click the **disk icon** to save your own version.

Interface

The window opens at 1000 x 746 pixels. Drag the bottom-right corner to resize it from 50% to 200%. The proportions stay fixed.

Preset display (top center). From left to right: the folder icon (preset menu), the **<** arrow, the current preset name, the **>** arrow and the disk icon (save). The arrows wrap around from the last preset to the first.

EXPANSION cassette (top left). Clicking the cassette opens an information message about upcoming expansion packs. No expansion content is included with version 1.0.

Logo (top right). The DB logo and the DJBILBOXBEATS name.

Center. The camel artwork, the CHINTZWAZ title and “By Humpire”. The two perforated speaker grilles on each side of the artwork carry the small character knobs (see below).

LFO section (left). RATE and **AMOUNT** set the LFO speed and depth. **TRANSPOSE**, also under this header, is the global transposition (-12 to +12 semitones). It is not an LFO control.

Left speaker grille. Four small knobs stacked vertically: **TONE, BODY, BRIGHT, WIDTH**.

Right speaker grille. Three small knobs stacked vertically: **TEXTURE** (the fifth character control), **RES** (filter resonance) and **ENV AMT** (filter envelope depth).

AMP ENVELOPE (lower left). Four sliders: **ATTACK, DECAY, SUSTAIN, RELEASE**.

GLIDE and CUTOFF. The **GLIDE** knob sits at the left of the title and the **CUTOFF** knob at the right.

FILTER ENVELOPE (upper right). Four sliders: **ATTACK, DECAY, SUSTAIN** (filter envelope) and **VELOCITY** (how much note velocity changes the level).

MASTER and EFFECTS (right). VOLUME is the large knob in the top right corner. Under the **EFFECTS** header, first row: **REVERB, CHORUS, DISTORTION**. Second row: **DELAY** (delay level), **DLY TIME** (delay time) and **FEEDBACK** (delay repeats).

Menu row. Five drop-down menus, each with a caption below it: **ENGINE**, **LFO SHAPE**, **LFO DESTINATION**, **FILTER TYPE** and **VOICE MODE**. Each menu shows its current value.

Wheels (bottom left). PITCH BEND springs back to the center when you release it. **MOD WHEEL** stays where you leave it.

On-screen keyboard (bottom). Click a key to play it. The keyboard covers MIDI notes 48 to 96 (four octaves plus one key). The key labels on screen run from C2 to C6, with middle C labeled C3; in FL Studio naming, where middle C is C5, the same range is C4 to C8. It does not scroll. For notes outside this range, use a MIDI controller or the Piano roll.

Mouse gestures. Drag a knob up or right to increase it. Drag sliders and wheels vertically. Double-click any knob or slider to return it to its default value. The mouse wheel also adjusts controls. A value bubble appears while you drag.

Parameters

Signal flow: engine, then filter, then amplitude envelope (per voice). The voices are summed, then processed by Distortion, Chorus, Delay and Reverb. A DC blocker and a soft limiter protect the output.

CHINTZWAZ exposes 34 automatable parameters. The host name is shown in parentheses when it differs from the panel label.

Control	Range	Default	What it does
ENGINE (Waveform)	Sitar Bloom, Flower EP, Mellotron, Hippie Flute, Kalimba, Daisy Pad, Bloom Bass, Psyche Organ	Sitar Bloom	Selects the synthesis engine.
TONE (Tone)	0 to 1	0.5	Character control 1. Its effect depends on the engine (see the table below).
BODY (Body)	0 to 1	0.5	Character control 2. Engine-dependent.
BRIGHT (Brightness)	0 to 1	0.5	Character control 3. Engine-dependent.
WIDTH (Width)	0 to 1	0.3	Character control 4. Engine-dependent (detune, buzz, vibrato, tremolo…). It is not a stereo width control.
TEXTURE (Texture)	0 to 1	0.2	Character control 5. Engine-dependent (noise, click, saturation…).
CUTOFF (Filter)	40 to 18,000 Hz	9,000 Hz	Filter cutoff. The cutoff follows the keyboard by 25% around middle C.
RES (Resonance)	0 to 1	0.15	Filter resonance.
FILTER TYPE (Filter Type)	Low Pass, High Pass, Band Pass	Low Pass	Filter mode.
ENV AMT (Filter Env Amount)	0 to 1	0	Filter envelope depth. At 1 the envelope opens the cutoff up to 5 octaves. At 0 the filter envelope has no effect.
FILTER ENVELOPE ATTACK (Filter Attack)	0.002 to 3 s	0.002 s	Filter envelope attack time.
FILTER ENVELOPE DECAY (Filter Decay)	0.02 to 4 s	0.3 s	Filter envelope decay time. It also sets the filter release time after the key is released.
FILTER ENVELOPE SUSTAIN (Filter Sustain)	0 to 1	0	Filter envelope sustain level.
VELOCITY (Velocity Sensitivity)	0 to 1	0.5	How much note velocity changes the level. 0: all notes at the same level. 1: full velocity response.
AMP ENVELOPE ATTACK (Attack)	0.001 to 5 s	0.01 s	Amplitude envelope attack time.
AMP ENVELOPE DECAY (Decay)	0.01 to 5 s	0.4 s	Amplitude envelope decay time.
AMP ENVELOPE SUSTAIN (Sustain)	0 to 1	0.7	Amplitude envelope sustain level.

Control	Range	Default	What it does
AMP ENVELOPE RELEASE (Release)	0.02 to 8 s	0.4 s	Amplitude envelope release time.
VOLUME (Volume)	0 to 1	0.7	Output level of each voice, before the effects. Shown in dB.
GLIDE (Glide)	0 to 2 s	0	Portamento: the value is roughly the slide time in seconds. Each new note slides from the pitch of the previous note, in Mono and in Poly mode. 0 turns glide off.
TRANSPOSE (Transpose)	-12 to +12 semitones	0	Global transposition in whole semitones.
RATE (LFO Rate)	0.05 to 20 Hz	4 Hz	LFO speed. Not tempo-synced.
AMOUNT (LFO Amount)	0 to 1	0	LFO depth. The mod wheel adds to this value.
LFO SHAPE (LFO Source)	Sine, Triangle, Saw, Square, Sample&Hold	Sine	LFO shape. The LFO restarts at every new note. Sample&Hold picks a new random value once per cycle.
LFO DESTINATION (Destination)	Pitch, Filter, Amp, Timbre	Pitch	LFO target. Pitch: up to +/-1 semitone (vibrato). Filter: up to +/-3 octaves (wobble). Amp: up to 50% level dip (tremolo). Timbre: moves all five character controls by up to +/-0.5.
VOICE MODE (Mono/Poly)	Poly, Mono	Poly	Poly: up to 16 notes at once. Mono: one note at a time, last-note priority.
DISTORTION (Distortion)	0 to 1	0	Saturation on the summed output, with automatic level compensation.
CHORUS (Chorus)	0 to 1	0	Stereo chorus mix (slow, fixed rate).
DELAY (Delay Mix)	0 to 1	0	Level of the ping-pong delay.
DLY TIME (Delay Time)	0.05 to 1.0 s	0.35 s	Delay time in seconds. Not tempo-synced: for a quarter note, use 60 / BPM (0.5 s at 120 BPM); halve it for an eighth note.
FEEDBACK (Delay Feedback)	0 to 0.9	0.35	Number of delay repeats (0 to 90% feedback).
REVERB (Reverb)	0 to 1	0.25	Reverb amount. Higher values also enlarge the room.

Control	Range	Default	What it does
PITCH BEND wheel (Pitch Bend)	-1 to +1	0	On-screen pitch bend, +/-2 semitones. Adds to MIDI pitch bend.
MOD WHEEL (Mod Wheel)	0 to 1	0	On-screen mod wheel. Adds up to +0.8 to the LFO AMOUNT.

Character controls by engine

Engine	TONE	BODY	BRIGHT	WIDTH	TEXTURE
Sitar Bloom	Brightness of the pluck	String sustain	String brightness (less damping)	Jawari buzz amount	Level of a resonant formant (about 900 to 2,500 Hz)
Flower EP	No effect	Length of the tine decay	Bark (upper partials), stronger with velocity	No effect	Attack noise
Mellotron	Center of a mid band (400 to 1,100 Hz)	Level of that mid band	Low-pass opening	Detune of the five saws and tape wobble depth	Wobble speed and breath noise
Hippie Flute	Pitch of the breath noise	Resonance of the breath noise	Level of the 2nd and 3rd harmonics	Vibrato depth (fades in after the attack)	Breath noise level
Kalimba	Level of the pluck click	Ring length	Level of the upper partials	No effect	Resonance of the kalimba box
Daisy Pad	No effect	Sub-octave level	Filter opening, with a slow built-in breathing	Detune of the five saws	Noise
Bloom Bass	Blend from triangle to saw	Sub level	Opening of a built-in low-pass that closes during the note	How slowly that low-pass closes	Saturation
Psyche Organ	Sub-octave drawbar level	Level of the octave-up drawbar	Level of the upper drawbars	Tremolo speed and depth	Key click

Factory presets

CHINTZWAZ includes 70 factory presets in 7 banks of 10. 58 load in Poly mode and 12 in Mono mode (Violin Tape; Breathy Dawn, Sad Daisy, Flute Echo, Wind In Petals and Whistling Gardener; and the Bloom Bass & Organs presets Bloom Bass, Round Sub, Fuzz Petal, Slide Stem, Pluck Root and Vox Garden).

Sitar & Strings (Sitar Bloom engine): Sitar Bloom, Raga Morning, Patchouli Pluck, Jawari Buzz, Marigold Drone, Soft Tamboura, Hippie Strum, Bazaar Echo, Low Sitar, Glass Sitar.

Flower EP (Flower EP engine): Flower Power EP, Velvet Daisy, Bark Petal, Summer Haze Keys, Tremolo Bloom, Tape Wurly, Bell Blossom, Low Tide EP, Lazy Sunday, Wah Garden.

Mellotron & Choir (Mellotron engine): Chintz Mellotron, Strawberry Tape, Soft Choir Tape, Flute Mellotron, Violin Tape, Slow Wobble, Dream Tape Pad, Low Choir Tape, Eight Track, Kaleidoscope.

Hippie Flutes (Hippie Flute engine): Hippie Flute, Meadow Pipe, Breathy Dawn, Sad Daisy, High Piccolo, Flute Echo, Wind In Petals, Low Flute, Fog Flute, Whistling Gardener.

Kalimba & Bells (Kalimba engine): Daisy Kalimba, Music Box Garden, Thumb Piano, Wind Chimes, Glass Petals, Low Kalimba, Echo Garden, Rain On Leaves, Teacup Bell, Marimba Blush.

Daisy Pads (Daisy Pad engine): Daisy Pad, Petal Mist, Sundress Strings, Slow Bloom, Lavender Haze, Warm Chintz, Breeze Drift, Whisper Field, Pulse Of Spring, Twilight Garden.

Bloom Bass & Organs (Bloom Bass engine for the first five, Psyche Organ engine for the last five): Bloom Bass, Round Sub, Fuzz Petal, Slide Stem, Pluck Root, Psyche Organ, Vox Garden, Soft Flute Stop, Rotary Daisy, Golden Haze Organ.

Loading a preset first resets every parameter to its default value, then applies the preset. The two wheels are not changed.

User presets. Click the disk icon to save the current sound as a `.czpreset` file. The default folder is `DJBILBOX BEATS/CHINTZWAZ/Presets` inside your Documents folder. Files in this folder appear in the **User** submenu of the preset menu. Use **Open a .czpreset file…** in the same menu to load a file from another location. The preset display shows the file name.

The host also sees the 70 factory presets as a program list. Your project saves the full state of the plugin, including the preset name.

Production tips

1. **Lo-fi and Boom Bap loops.** Start from Tape Wurly or Eight Track. Lower CUTOFF and add a little CHORUS for a dusty, vintage color. Raise DISTORTION slightly to glue the sound.
2. **Sitar and Oriental-flavored melodies.** Load Sitar Bloom or Raga Morning. WIDTH sets the jawari buzz and TEXTURE adds a resonant formant. Add DELAY (Bazaar Echo is a starting point) and set DLY TIME to a quarter or eighth note: 60 / BPM seconds, halved for an eighth.
3. **Psychedelic Soul and Funk keys.** Flower Power EP and Bark Petal respond to velocity: BRIGHT adds bark on hard notes. Use the VELOCITY slider around 60 to 80% so the accents of your Piano roll come through. Wah Garden uses the filter envelope; raise ENV AMT for a stronger wah.
4. **Afrobeats and Amapiano.** Daisy Kalimba, Thumb Piano and Music Box Garden give short, bouncy hooks; Daisy Pad and Sundress Strings hold the harmony. Add REVERB for space and a touch of DELAY for movement.
5. **Tape strings and choirs.** On the Mellotron engine, WIDTH detunes the five saws and adds tape wobble, and TEXTURE sets the wobble speed. Raise the AMP ENVELOPE ATTACK for swells (Dream Tape Pad).
6. **Flute leads.** Play Hippie Flute in Mono mode for clean lines, and add GLIDE (about 0.1 s) for smooth slides. WIDTH sets the vibrato depth; TEXTURE sets the breath.
7. **Slow-moving pads.** Slow Bloom and Daisy Pad use long attacks and releases. Automate CUTOFF over 8 or 16 bars, or set LFO DESTINATION to Filter with a slow Sine for gentle movement (Kaleidoscope uses the Timbre destination).
8. **Bass and organ.** The Bloom Bass presets load in Mono mode. Round Sub keeps TONE low for a soft low end; Fuzz Petal adds saturation through TEXTURE. Psyche Organ and Rotary Daisy play chords in Poly mode, or in Mono mode for lead lines like Vox Garden.

MIDI, automation and performance

Notes and channels. CHINTZWAZ responds to all 128 MIDI notes on any MIDI channel. Velocity controls the level according to the VELOCITY slider.

Polyphony. Up to 16 voices in Poly mode. When you play a 17th note, a voice is taken over. In Mono mode, each new note stops the previous one (last-note priority). Releasing the newest note does not bring back an earlier note that you still hold.

Pitch bend. MIDI pitch bend covers +/-2 semitones. The on-screen PITCH BEND wheel adds another +/-2 semitones.

Mod wheel (CC1). CC1 raises the LFO depth, like the on-screen MOD WHEEL (up to +0.8 on top of AMOUNT, capped at 1). When both are used, the higher value wins. A note that starts later begins from the latest CC1 position. For repeatable results in a song, automate the **Mod Wheel** parameter.

Other MIDI. The sustain pedal (CC64) is supported. All Notes Off and All Sound Off messages stop the sound. Aftertouch is ignored.

Automation in FL Studio. All 34 parameters can be automated. Move a control in the plugin, then use **Tools > Last tweaked > Create automation clip**. Use **Tools > Last tweaked > Link to controller** to assign a hardware knob. You can also pick parameters from the plugin wrapper menu (**Browse parameters**). Level, transpose, bend, cutoff, distortion and delay changes are smoothed to avoid clicks. Parameters show units in the host (Hz, ms, s, dB, semitones, %).

Latency and tail. The plugin adds no latency (0 samples), so no delay compensation is needed. It reports a 12-second tail to the host so reverb and delay trails are not cut when rendering.

CPU. Effects set to zero are bypassed. Fewer simultaneous notes and shorter release times keep the voice count low.

FAQ

CHINTZWAZ does not appear in FL Studio. Open **Options > Manage plugins**, check that `C:\Program Files\Common Files\VST3` is in the search paths, then click **Find installed plugins**. The plugin is listed as **CHINTZWAZ** under **DJBILBOX BEATS**. It is an instrument: load it in the Channel rack, not in a Mixer insert slot.

I hear nothing, or almost nothing, when I click the on-screen keyboard. Check VOLUME, and check that CUTOFF is not turned all the way down with FILTER TYPE set to Low Pass. Some presets have a long attack (pads, Slow Bloom), so the sound fades in slowly. For notes outside the on-screen keyboard range (MIDI 48 to 96), play from a MIDI keyboard or the Piano roll.

The sound is slightly different on every note. Each note gets a random starting phase and a slight random stereo offset. This is intended and adds a natural feel.

Every note slides into the next one. GLIDE is above zero. Glide applies to every new note. Set GLIDE to 0, or automate it only where you want slides.

My chord only plays one note. The VOICE MODE menu is set to Mono. Switch it to Poly (up to 16 voices).

Where do I install it on macOS? Copy the VST3 to `/Library/Audio/Plug-Ins/VST3` and the Audio Unit to `/Library/Audio/Plug-Ins/Components`, then rescan plugins in your host. Both are universal builds.