DJBILBOX BEATS / HUMPIRE

HIGHROLLER GOLD

Casino-lounge synthesizer: gold bells, velvet keys, big band brass, organ, mallets, strings, gold sub and smoky pads from eight synthesis engines.

Version 1.0 - Windows (VST3) and macOS (VST3 / Audio Unit) - Royalty-free license

Contents

HIGHROLLER GOLD

- Overview
- Quick start in FL Studio
- Interface
- Parameters
- Factory presets
- Production tips
- MIDI, automation and performance
- FAQ

HIGHROLLER GOLD

Casino-lounge synthesizer: gold bells, velvet keys, big band brass, organ, mallets, strings, gold sub and smoky pads from eight synthesis engines.

Type	Synthesizer (instrument)
Format	VST3 64-bit (Windows); VST3 + Audio Unit, universal (macOS)
Brand / developer	HUMPIRE by DJBILBOX BEATS
Version	1.0
Factory presets	70
Latency	0 samples

Overview

HIGHROLLER GOLD is a synthesizer sold under the HUMPIRE brand by DJBILBOX BEATS. It uses no samples. Every sound is generated in real time by one of eight engines: Gold Bell (FM bell), Velvet Keys (electric-piano style tines with a bell), Big Band Brass (three detuned saws with an opening filter), Vegas Organ (drawbars with percussion and key click), Roulette Mallets (struck bars with tremolo), Silk Strings (five detuned saws with a slow drift), Gold Sub (a sine sub with pitch “knock” and saturation) and Cigar Smoke (a detuned saw pad with breath noise and a filter that slowly breathes).

Five character controls (TONE, BODY, BRIGHT, WIDTH, TEXTURE) reshape each engine. The sound then goes through a multimode filter with its own envelope, an amplitude envelope, an LFO and an effects chain: distortion, chorus, ping-pong delay and reverb.

The sound is built for Hip-Hop, Trap and R&B keys and hooks, lounge and soul chords, brass stabs and pads, bell toplines and 808-style subs. The Gold Sub & Bass bank loads in Mono mode for clean one-note lines. All other banks load in Poly mode, with up to 16 voices.

Quick start in FL Studio

1. In the **Channel rack**, click **+** and choose **HIGHROLLER GOLD** (vendor **DJBILBOX BEATS**). You can also drag it from the **Plugin database > Generators** browser.
2. The plugin opens on **HIGHROLLER GOLD - Init Patch**: the Gold Bell engine in Poly mode.
3. Click the **folder icon** at the left of the preset display. Pick a bank, then a preset. You can also step through all 70 presets with the **<** and **>** arrows.
4. Play from your MIDI keyboard or draw notes in the **Piano roll**. The on-screen keyboard covers MIDI notes 48 to 96. Click a key to hear the sound.
5. Shape the sound with the main controls:
   - **TONE**: the main character of the engine (bell ratio, hardness, drawbar level, string or pad color…).
   - **CUTOFF**: the cutoff of the filter. Turn it down for a darker, rounder sound.
   - **RELEASE** (in AMP ENVELOPE): how long the note rings after you let go.
6. Adjust **VOLUME** to set the level, then click the **disk icon** to save your own version.

Interface

The window opens at 1000 x 746 pixels. Drag the bottom-right corner to resize it from 500 x 373 up to 2000 x 1492 pixels. The proportions stay fixed.

Preset display (top center). From left to right: the folder icon (preset menu), the **<** arrow, the current preset name, the **>** arrow and the disk icon (save). The arrows wrap around from the last preset to the first.

EXPANSION cassette (top left). Clicking the cassette opens a message saying that expansion packs are coming soon. No expansion content is included with version 1.0.

Logo (top right). The DJBILBOXBEATS name and the DB logo.

Center. The camel artwork, the HIGHROLLER GOLD title and “By Humpire”. The dotted grille around the artwork is decorative.

Character knobs (row above the artwork). TONE, BODY, BRIGHT, WIDTH, TEXTURE: the five character controls of the selected engine.

Left side.

- **LFO** section: **RATE** and **AMOUNT** set the LFO speed and depth.
- **TUNING** section: **TRANSPOSE**, the global transposition (-12 to +12 semitones). It is not an LFO control.
- **AMP ENVELOPE**: four sliders, **ATTACK, DECAY, SUSTAIN, RELEASE**.
- Small knobs **RES** (filter resonance) and **FLT ENV** (filter envelope depth).
- **GLIDE** knob.

Right side.

- **FILTER ENVELOPE**: four sliders **ATK, DEC, SUS, REL**, plus the **VELOCITY** slider (velocity sensitivity of the level) just to their right.
- **VOLUME** knob (output level), **CUTOFF** knob (filter cutoff).
- **REVERB, CHORUS, DISTORTION** knobs.
- **DLY MIX** (delay level), **DLY TIME** and **FEEDBACK** knobs.

Menu row. Five drop-down menus, each with a caption below it: **ENGINE**, **LFO SHAPE**, **LFO DESTINATION**, **FILTER TYPE** and **VOICE MODE** (Poly or Mono). Each menu shows its current value.

Wheels (bottom left). Pitch Bend springs back to the center when you release it. **Modulation** stays where you leave it.

On-screen keyboard (bottom). Click a key to play it. The keyboard covers MIDI notes 48 to 96 (four octaves plus one key). The key labels on screen run from C2 to C6, with middle C labeled C3; in FL Studio naming, where middle C is C5, the same range is C4 to C8. It always shows the whole range and does not scroll. For notes outside this range, use a MIDI controller or the Piano roll.

Mouse gestures. Drag a knob up or right to increase it. Drag sliders and wheels vertically. Double-click any knob or slider to return it to its default value. The mouse wheel also adjusts controls. A value bubble appears while you drag.

Parameters

Signal flow: engine, then filter, then amplitude envelope (per voice). The voices are summed, then processed by Distortion, Chorus, Delay and Reverb. A DC blocker and a soft limiter protect the output.

HIGHROLLER GOLD exposes 35 automatable parameters. The host name is shown in parentheses when it differs from the panel label.

Parameter	Range	Default	Function
ENGINE (Waveform menu)	Gold Bell, Velvet Keys, Big Band Brass, Vegas Organ, Roulette Mallets, Silk Strings, Gold Sub, Cigar Smoke	Gold Bell	Selects the synthesis engine.

Parameter	Range	Default	Function
TONE (Tone)	0 to 1	0.5	Character control 1. Its effect depends on the engine (see the table below).
BODY (Body)	0 to 1	0.5	Character control 2. Engine-dependent.
BRIGHT (Brightness)	0 to 1	0.5	Character control 3. Engine-dependent.
WIDTH (Width)	0 to 1	0.3	Character control 4. Engine-dependent (detune, tremolo depth, drift…). It is not a stereo width control.
TEXTURE (Texture)	0 to 1	0.2	Character control 5. Engine-dependent (noise, saturation, speed…).
CUTOFF (Filter)	40 to 18,000 Hz	9,000 Hz	Filter cutoff. The cutoff follows the keyboard by 25% around middle C.
RES (Resonance)	0 to 1	0.15	Filter resonance.
FILTER TYPE (menu)	Low Pass, High Pass, Band Pass	Low Pass	Filter mode.
FLT ENV (Filter Env Amount)	0 to 1	0	Filter envelope depth. At 1 the envelope opens the cutoff up to 5 octaves. At 0 the filter envelope has no effect.
ATK (Filter Attack)	0.002 to 3 s	0.002 s	Filter envelope attack time.
DEC (Filter Decay)	0.02 to 4 s	0.3 s	Filter envelope decay time.
SUS (Filter Sustain)	0 to 1	0	Filter envelope sustain level.
REL (Filter Release)	0.02 to 4 s	0.3 s	Filter envelope release time.
VELOCITY (Velocity Sensitivity)	0 to 1	0.5	How much note velocity changes the level. 0: all notes at the same level. 1: full velocity response.
ATTACK (Attack)	0.001 to 5 s	0.01 s	Amplitude envelope attack time.
DECAY (Decay)	0.01 to 5 s	0.4 s	Amplitude envelope decay time.
SUSTAIN (Sustain)	0 to 1	0.7	Amplitude envelope sustain level.
RELEASE (Release)	0.02 to 8 s	0.4 s	Amplitude envelope release time.
VOLUME (Volume)	0 to 1	0.7	Output level of each voice, before the effects. Shown in dB.

Parameter	Range	Default	Function
GLIDE (Glide)	0 to 2	0	Portamento. Higher values give a slower slide. Each new note slides from the pitch of the previous note, in Mono and in Poly mode. 0 turns glide off.
TRANSPOSE (Transpose)	-12 to +12 semitones	0	Global transposition in whole semitones.
RATE (LFO Rate)	0.05 to 20 Hz	4 Hz	LFO speed. Not tempo-synced.
AMOUNT (LFO Amount)	0 to 1	0	LFO depth. The mod wheel adds to this value.
LFO SHAPE (LFO Source menu)	Sine, Triangle, Saw, Square, Sample&Hold	Sine	LFO shape. The LFO restarts at every new note. Sample&Hold picks a new random value once per cycle.
LFO DESTINATION (Destination menu)	Pitch, Filter, Amp, Timbre	Pitch	LFO target. Pitch: up to +/-1 semitone (vibrato). Filter: up to +/-3 octaves (wobble). Amp: up to 50% level dip (tremolo). Timbre: moves all five character controls by up to +/-0.5.
VOICE MODE (Mono/Poly menu)	Poly, Mono	Poly	Poly: up to 16 notes at once. Mono: one note at a time, last-note priority.
DISTORTION (Distortion)	0 to 1	0	Saturation on the summed output, with automatic level compensation.
CHORUS (Chorus)	0 to 1	0	Stereo chorus mix (slow, fixed rate).
DLY MIX (Delay Mix)	0 to 1	0	Level of the ping-pong delay.
DLY TIME (Delay Time)	0.05 to 1.0 s	0.35 s	Delay time in seconds. Not tempo-synced: for a quarter note, use 60 / BPM (0.5 s at 120 BPM); halve it for an eighth note.
FEEDBACK (Delay Feedback)	0 to 0.9	0.35	Number of delay repeats (0 to 90% feedback).
REVERB (Reverb)	0 to 1	0.25	Reverb amount. Higher values also enlarge the room.
Pitch Bend wheel (Pitch Bend)	-1 to +1	0	On-screen pitch bend, +/-2 semitones. Adds to MIDI pitch bend.
Modulation wheel (Mod Wheel)	0 to 1	0	On-screen mod wheel. Adds up to +0.8 to the LFO AMOUNT.

Character controls by engine

Engine	TONE	BODY	BRIGHT	WIDTH	TEXTURE
Gold Bell	Ratio of the FM modulator (bell color)	Length of the ring	FM depth (brightness of the strike)	Slight detune between the two carriers	Noise click at the attack
Velvet Keys	No effect	Length of the tines	“Bark” (upper partials), stronger with higher velocity	No effect	Attack noise
Big Band Brass	Time the filter takes to open	Output weight	How far the filter opens	Detune of the three saws	Breath noise
Vegas Organ	Level of the sub-octave drawbar	Level of the 2nd harmonic drawbar	Level of the upper drawbars	Percussion at the attack	Key click
Roulette Mallets	Mallet noise at the attack	Length of the ring	Level of the upper partials	Tremolo depth	Tremolo speed
Silk Strings	Position of the body resonance	Level of the body resonance	Filter opening	Detune and drift of the five saws	Speed of the slow drift
Gold Sub	Pitch “knock” at the attack	Adds the octave harmonic	Attack click	No effect	Saturation
Cigar Smoke	No effect	Level of the sub layer	How far the filter opens	Detune of the five saws	Breath noise

Factory presets

HIGHROLLER GOLD includes 70 factory presets in 7 banks of 10. The Gold Sub & Bass bank loads in Mono mode. In the Big Band Brass bank, only Cigar Lounge Horn is in Mono mode. Every other preset loads in Poly mode.

Gold Bells & Jackpot: Jackpot Bell, Gold Coin, Slot Machine, Casino Chimes, Velvet Box, Crystal Chandelier, Low Gong, Ring Of Fortune, Lucky Seven, Winner Echo.

Velvet Keys: Velvet Rhodes, High Stakes Keys, Bark EP, Lounge Keys, Tremolo Velvet, After Dark EP, Wurly Bite, Gilded Bell EP, Penthouse Chords, Tape Velvet.

Big Band Brass: Big Band Brass, High Roller Horns, Brass Stab, Soft Flugel, Slow Swell, Vegas Fanfare, Muted Horn, Sax Section, Disco Hit, Cigar Lounge Horn.

Vegas Organ: Vegas Organ, Smoky Lounge, Full Drawbars, Gospel Gold, Casino Floor, Perc Organ, Soft Flute Stop, Rotary Dream, Tape Organ, Golden Swell.

Mallets & Strings: Roulette Vibes, Gold Marimba, Chip Stack, Slow Motor Vibes, Dealer’s Hand (Roulette Mallets engine), then Silk Strings, Velvet Strings, Slow Rise Strings, Dark Cellos, Pizz Casino (Silk Strings engine).

Gold Sub & Bass: Gold 808, Long Slide Gold, Dirty Gold, Boom Bap Sub, Hard Knock, Deep Vault, Short Gold, Smooth Sub, Pitch Drop Gold, Rumble Royale.

Cigar Smoke Pads: Cigar Smoke, Smoky Backroom, Velvet Curtain, Golden Haze, High Roller Rise, Midnight Casino, Whisper Table, Vault Drone, Pulse Of Luck, Final Hand.

Loading a preset first resets every parameter to its default value, then applies the preset. The two wheels are not changed.

User presets. Click the disk icon to save the current sound as a `.hgpreset` file. The default folder is `DJBILBOX BEATS/HIGHROLLER_GOLD/Presets` inside your Documents folder (Windows and macOS). Files in this folder appear in the **User** submenu of the preset menu. Use **Open a .hgpreset file…** in the same menu to load a file from another location.

The preset display shows the file name.

The host also sees the 70 factory presets as a program list. Your project saves the full state of the plugin, including the preset name.

Production tips

1. **Hooks and toplines.** Start from Jackpot Bell, Gold Coin or Crystal Chandelier. Raise TONE to change the bell color and BODY for a longer ring. Add REVERB and a little DLY MIX with DLY TIME at 0.375 s for a sparkling top layer.
2. **Soul and R&B chords.** The Velvet Keys bank plays chords in Poly mode. Raise BRIGHT for more bite on hard notes, and keep the VELOCITY slider around 60 to 80% so your Piano roll accents come through. Add CHORUS for width.
3. **Brass stabs and swells.** In Big Band Brass, shorten DECAY and SUSTAIN for stabs (Brass Stab, Disco Hit) or raise ATTACK for swells (Slow Swell). TONE sets how fast the filter opens.
4. **Organ beds.** Vegas Organ mixes drawbar levels with TONE, BODY and BRIGHT. WIDTH adds percussion at the attack and TEXTURE adds key click. Set LFO DESTINATION to Amp for a tremolo, as a starting point for rotary-style movement.
5. **Vibes and marimba.** In Roulette Mallets, WIDTH sets the tremolo depth and TEXTURE its speed. Lower RELEASE for dry, tight hits.
6. **Strings and pads.** Silk Strings and Cigar Smoke use detuned saws. Raise ATTACK and RELEASE for slow pads, and WIDTH for a thicker sound. In Cigar Smoke, BRIGHT opens the filter and the filter slowly breathes by itself.
7. **808 subs.** Load a Gold Sub & Bass preset (Gold 808, Long Slide Gold). Raise TONE for a harder knock. Raise TEXTURE or add a little DISTORTION so the sub stays audible on phone and laptop speakers.
8. **Slides.** With GLIDE above zero, every new note slides from the previous one, even if the notes do not overlap. For slides on selected notes only, keep GLIDE at 0 and automate it up just before the notes that should slide.
9. **Filter movement.** Raise FLT ENV and shorten the filter DEC slider for a plucked attack. For a wobble, set LFO DESTINATION to Filter and RATE between 1 and 4 Hz.

MIDI, automation and performance

Notes and channels. HIGHROLLER GOLD responds to all 128 MIDI notes on any MIDI channel. Velocity controls the level according to the VELOCITY slider.

Polyphony. Up to 16 voices in Poly mode. When you play a 17th note, a voice is taken over and cut immediately. In Mono mode, each new note stops the previous one (last-note priority). Releasing the newest note does not bring back an earlier note that you still hold.

Pitch bend. MIDI pitch bend covers +/-2 semitones. The on-screen Pitch Bend wheel adds another +/-2 semitones.

Mod wheel (CC1). CC1 raises the LFO depth, like the on-screen Modulation wheel. When both are used, the higher value wins. A new note starts with the latest CC1 value. For repeatable results in a song, automate the on-screen **Mod Wheel** parameter instead.

Other MIDI. The sustain pedal (CC64) is supported. All Notes Off and All Sound Off messages stop the sound. Aftertouch is ignored.

Automation in FL Studio. All 35 parameters can be automated. Move a control in the plugin, then use **Tools > Last tweaked > Create automation clip**. Use **Tools > Last tweaked > Link to controller** to assign a hardware knob. You can also pick parameters from the plugin wrapper menu (**Browse parameters**). Level, pitch, bend and cutoff changes are smoothed to avoid clicks. Distortion and delay level changes are smoothed too.

Latency and tail. The plugin adds no latency (0 samples), so no delay compensation is needed. It reports a 12-second tail to the host so reverb and delay trails are not cut when rendering.

Output. Stereo output. Each note gets a slight random position in the stereo field.

FAQ

HIGHROLLER GOLD does not appear in FL Studio. Open **Options > Manage plugins**, check that `C:\Program Files\Common Files\VST3` is in the search paths, then click **Find installed plugins**. The plugin is listed as **HIGHROLLER GOLD** under **DJBILBOX BEATS**. It is an instrument: load it in the Channel rack, not in a Mixer insert slot.

I hear nothing, or almost nothing, when I click the on-screen keyboard. Check VOLUME, and check that CUTOFF is not turned all the way down with FILTER TYPE set to Low Pass. Some presets have a very slow ATTACK (pads and swells) or a long fade-in, so hold the note for a moment. For notes outside the on-screen keyboard range (MIDI 48 to 96), play from a MIDI keyboard or the Piano roll.

My sub is not perfectly centered. Each note gets a slight random stereo offset. For a strictly centered sub, reduce the stereo separation of the mixer track in FL Studio, or insert a mono utility after HIGHROLLER GOLD. If the sub is also weak on small speakers, add harmonics with TEXTURE, BODY or DISTORTION.

Every note slides into the next one. GLIDE is above zero. Glide applies to every new note. Set GLIDE to 0, or automate it only where you want slides.

My chord only plays one note. The VOICE MODE menu is set to Mono, which is the default for the Gold Sub & Bass presets. Switch it to Poly (up to 16 voices).

Where do I install it on macOS? Copy the VST3 to `/Library/Audio/Plug-Ins/VST3` and the Audio Unit to `/Library/Audio/Plug-Ins/Components`, then rescan plugins in your host. Both are universal builds.