DJBILBOX BEATS / HUMPIRE

HUMPIRE LAG

Stereo delay with BPM sync, filtered feedback, ducking, ping-pong mode and four snapshots you can morph between.

Version 1.0 - Windows (VST3) and macOS (VST3 / Audio Unit) - Royalty-free license

Contents

HUMPIRE LAG
- Overview
- Quick start in FL Studio
- Interface
- Parameters
- Factory presets
- Production tips
- FAQ

HUMPIRE LAG

Stereo delay with BPM sync, filtered feedback, ducking, ping-pong mode and four snapshots you can morph between.

Type	Audio effect (stereo delay)
Format	VST3 64-bit (Windows); VST3 + Audio Unit, universal (macOS)
Brand / developer	HUMPIRE by DJBILBOX BEATS
Version	1.0
Factory presets	12
Delay time	1 ms to 2 s per side
Reported tail	30 seconds
Latency	0 samples

Overview

HUMPIRE LAG is a stereo delay with separate left and right times. Each side can run in milliseconds (1 ms to 2 s) or be **synced** to the host tempo with eight divisions: 1/16, 1/8, dotted 1/8, triplet 1/8, 1/4, dotted 1/4, 1/2 and 1/1. The feedback (up to 95%) passes through a **low cut** and a **high cut** filter, and a soft saturator in the feedback path keeps long repeats under control. **DUCK** lowers the echoes while the input signal is loud. **PING-PONG** feeds the input into the left delay only and sends the repeats back and forth between the two sides.

Four **snapshots** (slots A to D) store the time, feedback, filter, ducking and mix settings. Picking a slot makes the delay **morph** smoothly to those settings over a time you set with the **MORPH** knob.

Quick start in FL Studio

1. Open the **Mixer**, select a track and click an empty slot in its effects chain. Choose **HUMPIRE LAG** (vendor **HUMPIRE by Djbilbox BEATS**). If it is not listed, open **Options > Manage plugins**, check that `C:\Program Files\Common Files\VST3` is in the search paths and click **Find installed plugins**.
2. Click the **preset name** in the top bar and pick a preset, or step through them with **<** and **>**.
3. Click **SYNC** to follow the host tempo, then use the two division buttons to choose the left and right note values. Click a division button to go to the next value.
4. Set **FEEDBACK** for the number of repeats, and **MIX** for the level of the echoes.
5. Use **DUCK** so the echoes appear in the gaps between words or notes.
6. To store a snapshot: click **STORE**, then click a slot (A to D). To recall it, click the slot.

Interface

Top bar (all HUMPIRE LOADOUT plugins). From left to right: the HUMPIRE logo and the plugin name, the **<** and **>** buttons (previous and next preset), the preset name (click it to open the preset menu, sorted by category), **SAVE**, **A/B**, **UNDO**, **REDO**, **BYPASS**, and the **IN** and **OUT** level meters. At the right end of the bar, the **SIMPLE** and **CLEAN** buttons change the display.

- **SAVE** asks for a name and stores the current settings as a user preset. User presets are listed in the **User** category of the preset menu.
- **A/B** switches between two settings: the first click stores the current settings in slot A and moves to slot B, and each following click swaps between the two.
- **UNDO** and **REDO** step through your recent control changes and preset loads.

- **BYPASS** passes the audio through untouched. The host also sees it as the plugin's bypass parameter.
- **SIMPLE** hides the advanced knobs and keeps the essential ones. **CLEAN** replaces the textured body with a flat, plain panel. These two choices are saved with your project and are not automatable.

The window opens at 820 x 560 pixels. Drag its bottom-right corner to resize it from 50% to 200%; the proportions stay fixed.

Mouse gestures. Drag a knob up or down. Shift + drag for fine control. Right-click a knob to type a value. Double-click to reset to the default (when supported by the host). Hover over a control to see its value.

Screen. Two lanes, **L** (amber) and **R** (violet). Each lane shows the source and its repeats as vertical bars that fade according to the feedback, and a moving light. The screen also shows the time of each side in milliseconds.

Knobs. TIME L, **TIME R**, **FEEDBACK**, **LOW CUT**, **HIGH CUT**, **DUCK**, **MIX** and **MORPH**. In SIMPLE mode, **LOW CUT**, **HIGH CUT**, **DUCK** and **MORPH** are hidden.

Buttons. SYNC, **PING-PONG**, the left division button (shows its current value, default 1/4) and the right division button (default 1/4 D). When SYNC is off, the time knobs set the delay; when SYNC is on, the division buttons do.

Snapshot row (bottom). SLOT A, **SLOT B**, **SLOT C**, **SLOT D** and **STORE**. A LED shows the active slot.

Parameters

Control	Host name	Range	Default	Function
TIME L	Time L	1 to 2000 ms	375 ms	Left delay time when SYNC is off.
TIME R	Time R	1 to 2000 ms	375 ms	Right delay time when SYNC is off.
SYNC	Sync	Off / On	Off	Follows the host tempo. Without a tempo from the host, 120 BPM is assumed.
Left division button	Division L	1/16, 1/8, 1/8 D, 1/8 T, 1/4, 1/4 D, 1/2, 1/1	1/4	Left note value when SYNC is on.
Right division button	Division R	Same	1/4 D	Right note value when SYNC is on.
FEEDBACK	Feedback	0 to 0.95	0.35	Amount of signal sent back into the delay.
LOW CUT	Low Cut	20 Hz to 1 kHz	100 Hz	High-pass filter inside the feedback loop.
HIGH CUT	High Cut	1 kHz to 20 kHz	8 kHz	Low-pass filter inside the feedback loop.
DUCK	Ducking	0 to 1	0.00	Lowers the echoes while the input is loud.
MIX	Mix	0 to 1	0.30	Level of the echoes added to the dry signal.
PING-PONG	Ping-Pong	Off / On	Off	Sends the repeats back and forth between left and right.

Control	Host name	Range	Default	Function
MORPH	Morph	20 ms to 3 s	500 ms	Time taken to move to a snapshot.
BYPASS	Bypass	Off / On	Off	Passes the audio through.

LAG has 13 automatable parameters. The echoes are added to the dry signal, which always passes through unchanged. The delay time changes smoothly, like a tape delay.

Snapshots. A snapshot stores seven values: Time L, Time R, Feedback, Low Cut, High Cut, Duck and Mix. It does not store Sync, the divisions or Ping-Pong. The four slots start with these values (Time L / Time R in ms, Feedback, Low Cut in Hz, High Cut in Hz, Duck, Mix):

Slot	Time L	Time R	Feedback	Low Cut	High Cut	Duck	Mix
A	375	375	0.35	100	8000	0.00	0.30
B	250	375	0.50	200	6000	0.30	0.35
C	90	120	0.20	150	10000	0.00	0.25
D	800	1200	0.70	300	4000	0.50	0.45

Snapshots are saved with your project. While the delay morphs, the knobs move by themselves.

Factory presets

LAG includes 12 factory presets.

Trap Vocals: Trap Vocal 1/8, Ad-Lib Ping-Pong, Dotted Hook.

808: 808 Slap.

Kick: Kick Echo Tight.

Oud: Oud Wide Echo, Oud Desert.

Darbouka: Darbouka Roll.

Bus Drums: Bus Drums Space.

Master: Master Haze, Dub Throw, Infinite Ghost.

User presets. SAVE writes an `.xml` file in `%APPDATA%\HUMPIRE\LAG\Presets` on Windows (the `AppData\Roaming` folder of your user account) and in `~/Library/Application Support/HUMPIRE/LAG/Presets` on macOS. Files in this folder appear in the **User** category. Loading a factory preset first resets every parameter to its default, then applies the preset.

Production tips

- **Hooks and vocals. Trap Vocal 1/8** and **Dotted Hook** use a synced delay with ducking so the words stay clear.
- **Wide echoes.** Use different times on the left and right (**Oud Wide Echo**) or enable ping-pong (**Ad-Lib Ping-Pong**).
- **Slapback. 808 Slap** uses very short times with a low feedback.
- **Dub throws.** Raise FEEDBACK to 0.75 (**Dub Throw**) and automate MIX or the snapshot slots.
- **Transitions.** Store a dry snapshot in slot A and an extreme one in slot D, then switch to D at the end of a bar with a long MORPH.
- **Keep the low end clean.** Raise LOW CUT so that repeats of a bass do not muddy the mix.

FAQ

The delay does not follow my tempo. Click SYNC. If your host does not send a tempo, the plugin uses 120 BPM.

What do the division values mean? D is dotted (1.5 times longer), T is triplet (two thirds as long).

How do I store a snapshot? Click STORE (it lights up), then click the slot. The current settings are stored in that slot.

Does it add latency? No.