# RapidFort Big Bang Helm Chart Keycloak Administrator User Setup

## Goals

Set up a Keycloak administrator username and password via the RapidFort Helm Chart to enable logging into the Keycloak user interface.

## Steps

### Step 1: Set up Keycloak Administrator Username and Password

Update the RapidFort Helm Chart values.yaml file with the Keycloak administrator username and password.

```
global:
 keycloak_service_account_client_secret: ""
 keycloak_admin: "keycloakAdmin" # replace keycloak admin username if needed
 keycloak_admin_passwd: "Dz4HEhDCaEEoDPom" # replace keycloak admin password
```

### Step 2: Install the RapidFort Helm Chart

Install the RapidFort Helm Chart. Wait for the pods to stabilize.

### Step 3: Log into the Keycloak UI

Open a web browser and navigate to the Keycloak UI using `https://<rapidfort_host_uri>/auth/`.

You should see the following UI.

Log in using the credentials configured in Step 1.



### Step 4: Regenerate the Keycloak Service Account Client Secret

Select the `customers` realm from the top left dropdown menu.




Next select `Clients`. Select `admin-cli` from the list of clients.




Select the `Credentials` tab. Click the `Regenerate` button next to the `Client Secret` text box.

Save the client secret value.



### Step 5: Update the Keycloak Service Account Client Secret

Update the `values.yaml` file with the Keycloak service account client secret (`keycloak_service_account_client_secret`).

Save the `values.yaml` file and apply the changes.

```
global:
 keycloak_service_account_client_secret: "" # replace this with the service account client secret
```

### Step 6: Confirm the Keycloak Service Account Client Secret

Confirm that the Keycloak service account client secret was updated.

```
kubectl get secret rapidfort-secret -n rapidfort -o yaml | yq .data.KEYCLOAK_SERVICE_ACCOUNT_CLIENT_SECRET | base64 -d
```

### Step 7: Rollout Restart

Run the rollout restart for the RapidFort services using the following command.

```
kubectl rollout restart deploy fileupload isomaster rfscan backend -n rapidfort
```