

Since the merger starting at PLOT.MANUAL = 3.1, there has been only one regional field guide for all NRS States, the regional [NRS field guide](#). In the database, however, there are attributes named MANUAL_NERS and MANUAL_NCRS. Only one of these attributes is populated; the other is blank (NULL), depending on the State of data collection.

3.1.1 CN

Sequence number. A unique sequence number used to identify a tree record.

3.1.2 PLT_CN

Plot sequence number. Foreign key linking the tree record to the plot record.

3.1.3 PREV_TRE_CN

Previous tree sequence number. Foreign key linking the tree to the previous inventory's tree record for this tree. Only populated on trees remeasured from a previous annual inventory.

3.1.4 INVYR

Inventory year. See SURVEY.[INVYR](#) description for definition.

3.1.5 STATECD

State code. Bureau of the Census Federal Information Processing Standards (FIPS) 2-digit code for each State. Refer to [appendix B](#).

3.1.6 UNITCD

Survey unit code. Forest Inventory and Analysis survey unit identification number. Survey units are usually groups of counties within each State. For periodic inventories, survey units may be made up of lands of particular owners. Refer to [appendix B](#) for codes.

3.1.7 COUNTYCD

County code. The identification number for a county, parish, watershed, borough, or similar governmental unit in a State. FIPS codes from the Bureau of the Census are used. Refer to [appendix B](#) for codes.

Note: Summarizing data by county is not recommended for Alaska datasets. For assistance with analyses for Alaska, please consult the PNWRS analyst contact listed in [table 1-1](#).

3.1.8 PLOT

Plot number. An identifier for a plot. Along with STATECD, INVYR, UNITCD, COUNTYCD and/or some other combinations of variables, PLOT may be used to uniquely identify a plot.

3.1.9 SUBP

Subplot number. The number assigned to the subplot. The national plot design (PLOT.DESIGNCD = 1) has subplot number values of 1 through 4. Other plot designs have various subplot number values. See PLOT.[DESIGNCD](#) and [appendix G](#) for information about plot designs. For more explanation about SUBP, contact the appropriate FIA work unit ([table 1-1](#)).

3.1.10 TREE

Tree number. A number used to uniquely identify a tree on a subplot. Tree numbers can be used to track trees when PLOT.DESIGNCD is the same between inventories.

3.1.11 CONDID

Condition class number. The unique identifying number assigned to a condition on which the tree is located, and is defined in the COND table. See COND.CONDID for details on the attributes which delineate a condition.

3.1.12 AZIMUTH

Azimuth. This attribute now available from the [FIA Spatial Data Services \(SDS\)](https://www.fs.usda.gov/research/programs/fia/sds) group by following the instructions provided at the following web address:
<https://www.fs.usda.gov/research/programs/fia/sds>.

3.1.13 DIST

Horizontal distance. This attribute now available from the [FIA Spatial Data Services \(SDS\)](https://www.fs.usd.gov/research/programs/fia/sds) group by following the instructions provided at the following web address:
<https://www.fs.usd.gov/research/programs/fia/sds>.

3.1.14 PREVCOND

Previous condition class number. This Identifies the condition within the plot on which the tree occurred at the previous inventory.

3.1.15 STATUSCD

Status code. A code indicating whether the sample tree is live, cut, or dead at the time of measurement. Includes dead and cut trees, which are required to estimate aboveground biomass and net annual volume for growth, mortality, and removals. This code is not used when querying data for change estimates.

Note: New and replacement plots use only codes 1 and 2.

Codes: STATUSCD

Code	Description
0	No status - Tree is not presently in the sample (remeasurement plots only). Tree was incorrectly tallied at the previous inventory, currently not tallied due to definition or procedural change, or is not tallied because it is located on a nonsampled condition (e.g., hazardous or denied). RECONCILECD = 5-9 required for remeasured annual inventory data but not for periodic inventory data.
1	Live tree.
2	Dead tree.
3	Retired code - Starting with PLOT.MANUAL = 9.3, this code is only valid for some periodic-to-periodic, periodic-to-annual, and modeled GRM estimates. Only populated by certain FIA work units (SURVEY.RSCD = 23, 24). <i>Removed - Cut and removed by direct human activity related to harvesting, silviculture, or land clearing. This tree is assumed to be utilized.</i>

3.1.16 SPCD

Species code. An FIA tree species code. Refer to [appendix F](#) for codes.

3.1.17 SPGRPCD

Species group code. A code assigned to each tree species to group them for reporting purposes. Codes and their associated names (see REF_SPECIES_GROUP.NAME) are shown in [appendix E](#). Refer to [appendix F](#) for individual tree species and corresponding species group codes.

3.1.18 DIA

Current diameter. The current diameter, in inches, of the sample tree at the point of diameter measurement. For timber species, diameter is measured at breast height (d.b.h.), which is usually measured at 4.5 feet above the ground line on the uphill side of the tree. For woodland species, which are often multi-stemmed, diameter is measured at the ground line or at the stem root collar (d.r.c.), whichever is higher. DIA for woodland species (DRC) is computed using the following formula:

$$\text{DRC} = \text{SQRT} [\text{SUM} (\text{stem diameter}^2)]$$

For additional information about where the tree diameter is measured, see [DIAHTCD](#) or [HTDMP](#). DIA for live trees contains the measured value. DIA for cut and dead trees presents problems associated with uncertainty of when the tree was cut or died as well as structural deterioration of dead trees. Consult individual FIA work units ([table 1-1](#)) for explanations of how DIA is collected for dead and cut trees.

3.1.19 DIAHTCD

Diameter height code. A code indicating the location at which diameter was measured. For trees with code 1 (d.b.h.), the actual measurement point may be found in [HTDMP](#).

Codes: DIAHTCD

Code	Description
1	Breast height (d.b.h.).
2	Root collar (d.r.c.).

3.1.20 HT

Total height. (*All live and standing dead tally trees ≥ 1.0 inch d.b.h./d.r.c.*) The total length (height) of a tree, in feet, from the ground to the tip of the apical meristem beginning in PLOT.MANUAL = 1.1. The total length of a tree is not always its actual length. If the main stem is broken, the actual length is measured or estimated and the missing piece is added to the actual length to estimate total length. The amount added is determined by measuring the broken piece if it can be located on the ground; otherwise it is estimated. The minimum height for timber species is 5 feet and for woodland species is 1 foot. Starting with PLOT.MANUAL = 7.0, the *core* minimum diameter to qualify for a standing dead tree was changed from 5.0 inches to 1.0 inch. For multi-stemmed woodland species, this attribute is based on the length of the longest stem present.

Note: Prior to PLOT.MANUAL = 7.0, this attribute was tallied as follows:

- *Core* Phase 2: ≥ 5.0 -inch d.b.h./d.r.c. live trees.
- *Core optional* Phase 2: 1.0-4.9-inch d.b.h./d.r.c. live trees and ≥ 5.0 -inch d.b.h./d.r.c. standing dead trees.
- *Core* Phase 3: ≥ 1.0 -inch d.b.h./d.r.c. live trees.

- *Core optional* Phase 3: ≥ 5.0 -inch d.b.h./d.r.c. standing dead trees.

3.1.21 HTCD

Height method code. (*All live and standing dead tally trees ≥ 1.0 inch d.b.h./d.r.c.*) A code indicating how length (height) was determined beginning in PLOT.MANUAL = 1.1. Starting with PLOT.MANUAL = 7.0, the *core* minimum diameter to qualify for a standing dead tree was changed from 5.0 inches to 1.0 inch.

Note: Prior to PLOT.MANUAL = 7.0, this attribute was tallied as follows:

- *Core* Phase 2: ≥ 5.0 -inch d.b.h./d.r.c. live trees.
- *Core optional* Phase 2: 1.0-4.9-inch d.b.h./d.r.c. live trees and ≥ 5.0 -inch d.b.h./d.r.c. standing dead trees.
- *Core* Phase 3: ≥ 1.0 -inch d.b.h./d.r.c. live trees.
- *Core optional* Phase 3: ≥ 5.0 -inch d.b.h./d.r.c. standing dead trees.

Codes: HTCD

Code	Description
1	Field measured (total and actual length).
2	Total length visually estimated in the field, actual length measured.
3	Total and actual lengths are visually estimated.
4	Estimated with a model.

3.1.22 ACTUALHT

Actual height. (*All live and standing dead tally trees ≥ 1.0 inch d.b.h./d.r.c.*) The length (height) of the tree to the nearest foot from ground level to the highest remaining portion of the tree still present and attached to the bole. If ACTUALHT = HT, then the tree does not have a broken top. If ACTUALHT < HT, then the tree does have a broken or missing top. The minimum height for timber species is 5 feet and for woodland species is 1 foot. Starting with PLOT.MANUAL = 7.0, the *core* minimum diameter to qualify for a standing dead tree was changed from 5.0 inches to 1.0 inch.

Note: Prior to PLOT.MANUAL = 7.0, this attribute was tallied as follows:

- *Core* Phase 2: live and standing dead trees with broken tops, ≥ 5.0 inches d.b.h./d.r.c.
- *Core optional* Phase 2: live trees 1.0-4.9 inches d.b.h./d.r.c. with broken or missing tops.
- *Core* Phase 3: live trees ≥ 1.0 inch d.b.h./d.r.c. (with broken or missing tops) and standing dead trees ≥ 5.0 inches d.b.h./d.r.c. (with broken or missing tops).

3.1.23 TREECLCD

Tree class code. A code indicating the general quality of the tree. In annual inventory, this is the tree class for both live and dead trees at the time of current measurement. In periodic inventory, for cut and dead trees, this is the tree class of the tree at the time it died or was cut. Therefore, cut and dead trees collected in periodic inventory can be coded as growing-stock trees.