# The Python/C API

**Version 3.11.3** 

Guido van Rossum and the Python development team

mai 08, 2023

Python Software Foundation Email: docs@python.org

# Table des matières

1	Introduction	3
	1.2 Include Files          1.3 Useful macros          1.4 Objects, Types and Reference Counts          1.4.1 Compteurs de références          1.4.2 Types          1.5 Exceptions          1.6 Embarquer Python	3 4 6 7 10 12
2	2.1       ABI stable       1         2.1.1       Porté de l'API restreinte et performance       1         2.1.2       Inconvénients de l'API restreinte       1         2.2       Considérations relatives aux plateformes       1	15 16 16 17
3	The Very High Level Layer	35
4	Reference Counting 4	<b>ļ</b> 1
5	5.1 Printing and clearing       4         5.2 Lever des exceptions       4         5.3 Issuing warnings       4         5.4 Querying the error indicator       4         5.5 Traitement des signaux       5         5.6 Exception Classes       5         5.7 Objets exception       5         5.8 Objets exception Unicode       5         5.9 Contrôle de la récursion       5         5.10 Exceptions standards       5	13 14 14 17 17 17 17 17 17 17 17 17 17 17 17 17
6		5 <b>7</b>

	6.2 6.3	-	Functions       60         Control       60	
	6.4		r des modules	
	6.5	urshalling support		
	6.6		des arguments et construction des valeurs	
		6.6.1	Analyse des arguments	
		6.6.2	Construction des valeurs	
	6.7		ion et formatage de chaînes	
	6.8			
	6.9		egistry and support functions	
	0.7	6.9.1	Codec lookup API	
		6.9.2	Registry API for Unicode encoding error handlers	
		0.7.2	registry in the emocal encoung error naturals.	,
7	Couc	he d'abs	traction des objets 79	9
	7.1		le Objet	9
	7.2		otocol	4
		7.2.1	The <i>tp_call</i> Protocol	4
		7.2.2	The Vectorcall Protocol	4
		7.2.3	Object Calling API	
		7.2.4	Call Support API	
	7.3		Protocol	
	7.4		pe Protocol	
	7.5	-	le de correspondance	
	7.6		le d'itération	
	7.7		le tampon	
		7.7.1	La structure buffer	
		7.7.2	Buffer request types	
		7.7.3	Complex arrays	
		7.7.4	Fonctions relatives aux tampons	
	7.8		Protocole Tampon	
	7.0	1 11101011	Tampon Ta	_
8	Couc	he des ol	bjets concrets 10	5
	8.1	Objets f	ondamentaux	5
		8.1.1	Objets type	5
		8.1.2	L'objet None	9
	8.2	Objets r	numériques	9
		8.2.1	Objets Integer	
		8.2.2	Les objets booléens	
		8.2.3	Objets représentant les nombres à virgule flottante	
		8.2.4	Pack functions	
		8.2.5	Unpack functions	
		8.2.6	Objets représentant des nombres complexes	
	8.3		équences	6
		8.3.1	Objets <i>bytes</i>	6
		8.3.2	Objets tableau d'octets	8
		8.3.3	Objets Unicode et Codecs	
		8.3.4	Tuple Objects	
		8.3.5	Struct Sequence Objects	
		8.3.6	List Objects	
	8.4		conteneurs	
	0.1	8.4.1	Objets dictionnaires	
		8.4.2	Set Objects	
	8.5		onctions	-
	0.0	8.5.1	Objets fonction	_
		0.0.1		J

		8.5.2	Instance Method Objects	147
		8.5.3	Objets méthode	147
		8.5.4	Objets Cellules	148
		8.5.5	Objets code	148
	8.6	Autres o	bjets	
		8.6.1	Objets fichiers	150
		8.6.2	Module Objects	
		8.6.3	Itérateurs	
		8.6.4	Les descripteurs	
		8.6.5	Slice Objects	
		8.6.6	Ellipsis Object	
		8.6.7	Objets de type MemoryView	
		8.6.8		
			Objets à références faibles	
		8.6.9	Capsules	
		8.6.10	Objets décrivant les <i>frames</i>	
		8.6.11	Objets générateur	
		8.6.12	Objets coroutines	
		8.6.13	Context Variables Objects	
		8.6.14	Objets DateTime	
		8.6.15	Objects for Type Hinting	171
0	Ŧ */* :	•		1=0
9				173
	9.1		Python Initialization	
	9.2		configuration variables	
	9.3		ng and finalizing the interpreter	
	9.4		wide parameters	
	9.5		State and the Global Interpreter Lock	
		9.5.1	Releasing the GIL from extension code	
		9.5.2	Non-Python created threads	
		9.5.3	Cautions about fork()	
		9.5.4	High-level API	
		9.5.5	Low-level API	
	9.6	Sub-inte	erpreter support	
		9.6.1	Bugs and caveats	
	9.7	Asynchr	onous Notifications	189
	9.8	Profiling	g and Tracing	190
	9.9	Support	avancé du débogueur	191
	9.10	Thread 1	Local Storage Support	191
		9.10.1	Thread Specific Storage (TSS) API	192
		9.10.2	Thread Local Storage (TLS) API	
10	Pytho	n Initial		195
	10.1	Example	3	195
	10.2	PyWide	StringList	196
	10.3	PyStatus	3	197
	10.4	PyPreCo	onfig	198
				199
	10.6	PyConfi	g	200
				209
				211
			· ·	211
		-		211
		•		212
		-	ArgcArgv()	
	10.12	- 1_000		

	10.13	Multi-Phase Initialization Private Provisional API	213
11		• 8	215
	11.1	Aperçu	215
	11.2	Allocator Domains	
		Raw Memory Interface	
	11.4	Memory Interface	
	11.5	$\mathbf{J}$	219
	11.6	Default Memory Allocators	220
	11.7	Customize Memory Allocators	220
	11.8	Debug hooks on the Python memory allocators	
	11.9		223
	11.9		
		11.9.1 Customize pymalloc Arena Allocator	
	11.10	tracemalloc C API	223
	11.11	Exemples	224
		•	
12	Implé	émentation d'objets	225
	12.1		
	12.2	Common Object Structures	
		12.2.1 Base object types and macros	
		12.2.2 Implementing functions and methods	228
		12.2.3 Accessing attributes of extension types	230
	12.3	Objets type	
	12.0	12.3.1 Quick Reference	
		12.3.2 PyTypeObject Definition	
		12.3.3 PyObject Slots	
		12.3.4 PyVarObject Slots	239
		12.3.5 PyTypeObject Slots	239
		12.3.6 Static Types	
		12.3.7 Heap Types	
	10.4		
	12.4	Number Object Structures	
	12.5	Mapping Object Structures	
	12.6	Sequence Object Structures	259
	12.7	Buffer Object Structures	260
	12.8	Async Object Structures	
	12.9	Slot Type typedefs	
		Exemples	
	12.11	Supporting Cyclic Garbage Collection	266
		12.11.1 Controlling the Garbage Collector State	268
13	Versi	on des API et ABI	269
A	Gloss	saire 2	271
-	01055	-	
R	À pro	opos de ces documents	285
D	_ 7		
	B.1	Contributeurs de la documentation Python	285
~			
C			287
	C.1	Histoire du logiciel	287
	C.2	Conditions générales pour accéder à, ou utiliser, Python	288
			288
			289
		C.2.3 LICENCE D'UTILISATION CNRI POUR PYTHON 1.6.1	
		C.2.4 LICENCE D'UTILISATION CWI POUR PYTHON 0.9.0 à 1.2	291

	C.2.5	LICENCE BSD ZERO-CLAUSE POUR LE CODE DANS LA DOCUMENTATION DE	
		PYTHON 3.11.3	291
C.3	Licence	es et remerciements pour les logiciels tiers	292
	C.3.1	Mersenne twister	292
	C.3.2	Interfaces de connexion (sockets)	293
	C.3.3	Interfaces de connexion asynchrones	293
	C.3.4	Gestion de témoin (cookie)	294
	C.3.5	Traçage d'exécution	294
	C.3.6	Les fonctions UUencode et UUdecode	295
	C.3.7	Appel de procédures distantes en XML (RPC, pour Remote Procedure Call)	295
	C.3.8	test_epoll	296
	C.3.9	Select kqueue	296
	C.3.10	SipHash24	297
	C.3.11	strtod et dtoa	
	C.3.12	OpenSSL	298
	C.3.13	expat	
	C.3.14	libffi	
	C.3.15	zlib	
	C.3.16	cfuhash	302
	C.3.17	libmpdec	303
	C.3.18	Ensemble de tests C14N du W3C	
	C.3.19		
<b>D</b> Сору	right		305
Index			307

C'est la documentation de l'API utilisée par les développeurs C et C++ écrivant des modules d'extension ou intégrant Python. Elle va de pair avec extending-index, qui décrit les principes généraux de l'écriture d'extensions, mais ne rentre pas dans les détails de chaque fonction de l'API.

Table des matières 1

2 Table des matières

# CHAPITRE 1

Introduction

The Application Programmer's Interface to Python gives C and C++ programmers access to the Python interpreter at a variety of levels. The API is equally usable from C++, but for brevity it is generally referred to as the Python/C API. There are two fundamentally different reasons for using the Python/C API. The first reason is to write *extension modules* for specific purposes; these are C modules that extend the Python interpreter. This is probably the most common use. The second reason is to use Python as a component in a larger application; this technique is generally referred to as *embedding* Python in an application.

Writing an extension module is a relatively well-understood process, where a "cookbook" approach works well. There are several tools that automate the process to some extent. While people have embedded Python in other applications since its early existence, the process of embedding Python is less straightforward than writing an extension.

Many API functions are useful independent of whether you're embedding or extending Python; moreover, most applications that embed Python will need to provide a custom extension as well, so it's probably a good idea to become familiar with writing an extension before attempting to embed Python in a real application.

# 1.1 Coding standards

If you're writing C code for inclusion in CPython, you **must** follow the guidelines and standards defined in **PEP 7**. These guidelines apply regardless of the version of Python you are contributing to. Following these conventions is not necessary for your own third party extension modules, unless you eventually expect to contribute them to Python.

#### 1.2 Include Files

All function, type and macro definitions needed to use the Python/C API are included in your code by the following line:

```
#define PY_SSIZE_T_CLEAN
#include <Python.h>
```

This implies inclusion of the following standard headers: <stdio.h>, <string.h>, <errno.h>, imits.h>, <assert.h> and <stdlib.h> (if available).

**Note:** Python pouvant définir certaines définitions pré-processeur qui affectent les têtes standard sur certains systèmes, vous *devez* inclure Python.h avant les en-têtes standards.

It is recommended to always define PY\_SSIZE\_T\_CLEAN before including Python.h. See *Analyse des arguments et construction des valeurs* for a description of this macro.

All user visible names defined by Python.h (except those defined by the included standard headers) have one of the prefixes Py or \_Py. Names beginning with \_Py are for internal use by the Python implementation and should not be used by extension writers. Structure member names do not have a reserved prefix.

**Note:** User code should never define names that begin with Py or \_Py. This confuses the reader, and jeopardizes the portability of the user code to future Python versions, which may define additional names beginning with one of these prefixes.

The header files are typically installed with Python. On Unix, these are located in the directories prefix/include/pythonversion/ and  $exec\_prefix/include/pythonversion/$ , where prefix and  $exec\_prefix$  are defined by the corresponding parameters to Python's **configure** script and *version* is '%d.%d' % sys.  $version\_info[:2]$ . On Windows, the headers are installed in prefix/include, where prefix is the installation directory specified to the installer.

To include the headers, place both directories (if different) on your compiler's search path for includes. Do *not* place the parent directories on the search path and then use #include <pythonX.Y/Python.h>; this will break on multi-platform builds since the platform independent headers under prefix include the platform specific headers from exec\_prefix.

C++ users should note that although the API is defined entirely using C, the header files properly declare the entry points to be extern "C". As a result, there is no need to do anything special to use the API from C++.

### 1.3 Useful macros

Several useful macros are defined in the Python header files. Many are defined closer to where they are useful (e.g.  $Py\_RETURN\_NONE$ ). Others of a more general utility are defined here. This is not necessarily a complete listing.

#### Py\_ABS(x)

Return the absolute value of x.

Nouveau dans la version 3.3.

#### Py\_ALWAYS\_INLINE

Ask the compiler to always inline a static inline function. The compiler can ignore it and decides to not inline the function

It can be used to inline performance critical static inline functions when building Python in debug mode with function inlining disabled. For example, MSC disables function inlining when building in debug mode.

Marking blindly a static inline function with Py\_ALWAYS\_INLINE can result in worse performances (due to increased code size for example). The compiler is usually smarter than the developer for the cost/benefit analysis.

If Python is built in debug mode (if the Py\_DEBUG macro is defined), the  $Py_ALWAYS_INLINE$  macro does nothing.

It must be specified before the function return type. Usage:

```
static inline Py_ALWAYS_INLINE int random(void) { return 4; }
```

Nouveau dans la version 3.11.

#### Py\_CHARMASK (c)

Argument must be a character or an integer in the range [-128, 127] or [0, 255]. This macro returns c cast to an unsigned char.

#### Py\_DEPRECATED (version)

Use this for deprecated declarations. The macro must be placed before the symbol name.

Exemple:

```
Py_DEPRECATED(3.8) PyAPI_FUNC(int) Py_OldFunction(void);
```

Modifié dans la version 3.8 : MSVC support was added.

#### Py\_GETENV(s)

Like getenv(s), but returns NULL if -E was passed on the command line (i.e. if Py\_IgnoreEnvironmentFlag is set).

#### $Py_MAX(x, y)$

Return the maximum value between x and y.

Nouveau dans la version 3.3.

#### Py\_MEMBER\_SIZE (type, member)

Return the size of a structure (type) member in bytes.

Nouveau dans la version 3.6.

#### $Py_MIN(x, y)$

Return the minimum value between x and y.

Nouveau dans la version 3.3.

#### Py\_NO\_INLINE

Disable inlining on a function. For example, it reduces the C stack consumption: useful on LTO+PGO builds which heavily inline code (see bpo-33720).

Usage:

```
Py_NO_INLINE static int random(void) { return 4; }
```

Nouveau dans la version 3.11.

#### Py STRINGIFY(X)

Convert x to a C string. E.g. Py\_STRINGIFY (123) returns "123".

Nouveau dans la version 3.4.

#### Py UNREACHABLE ()

Use this when you have a code path that cannot be reached by design. For example, in the default: clause in a switch statement for which all possible values are covered in case statements. Use this in places where you might be tempted to put an assert (0) or abort () call.

In release mode, the macro helps the compiler to optimize the code, and avoids a warning about unreachable code. For example, the macro is implemented with \_\_builtin\_unreachable() on GCC in release mode.

1.3. Useful macros 5

A use for Py\_UNREACHABLE() is following a call a function that never returns but that is not declared \_Py\_NO\_RETURN.

If a code path is very unlikely code but can be reached under exceptional case, this macro must not be used. For example, under low memory condition or if a system call returns a value out of the expected range. In this case, it's better to report the error to the caller. If the error cannot be reported to caller,  $Py_FatalError()$  can be used. Nouveau dans la version 3.7.

#### Py\_UNUSED (arg)

Use this for unused arguments in a function definition to silence compiler warnings. Example: int func(int a, int  $Py\_UNUSED(b)$ ) { return a; }.

Nouveau dans la version 3.4.

#### PyDoc STRVAR (name, str)

Creates a variable with name name that can be used in docstrings. If Python is built without docstrings, the value will be empty.

Use PyDoc\_STRVAR for docstrings to support building Python without docstrings, as specified in PEP 7.

#### Exemple:

#### PyDoc\_STR (str)

Creates a docstring for the given input string or an empty string if docstrings are disabled.

Use PyDoc\_STR in specifying docstrings to support building Python without docstrings, as specified in PEP 7.

#### Exemple:

# 1.4 Objects, Types and Reference Counts

Most Python/C API functions have one or more arguments as well as a return value of type PyObject\*. This type is a pointer to an opaque data type representing an arbitrary Python object. Since all Python object types are treated the same way by the Python language in most situations (e.g., assignments, scope rules, and argument passing), it is only fitting that they should be represented by a single C type. Almost all Python objects live on the heap: you never declare an automatic or static variable of type PyObject\*, only pointer variables of type PyObject\* can be declared. The sole exception are the type objects; since these must never be deallocated, they are typically static PyTypeObject\* objects.

All Python objects (even Python integers) have a *type* and a *reference count*. An object's type determines what kind of object it is (e.g., an integer, a list, or a user-defined function; there are many more as explained in types). For each of the well-known types there is a macro to check whether an object is of that type; for instance, PyList\_Check (a) is true if (and only if) the object pointed to by *a* is a Python list.

#### 1.4.1 Compteurs de références

The reference count is important because today's computers have a finite (and often severely limited) memory size; it counts how many different places there are that have a reference to an object. Such a place could be another object, or a global (or static) C variable, or a local variable in some C function. When an object's reference count becomes zero, the object is deallocated. If it contains references to other objects, their reference count is decremented. Those other objects may be deallocated in turn, if this decrement makes their reference count become zero, and so on. (There's an obvious problem with objects that reference each other here; for now, the solution is "don't do that.")

Reference counts are always manipulated explicitly. The normal way is to use the macro  $Py\_INCREF()$  to increment an object's reference count by one, and  $Py\_DECREF()$  to decrement it by one. The  $Py\_DECREF()$  macro is considerably more complex than the incref one, since it must check whether the reference count becomes zero and then cause the object's deallocator to be called. The deallocator is a function pointer contained in the object's type structure. The type-specific deallocator takes care of decrementing the reference counts for other objects contained in the object if this is a compound object type, such as a list, as well as performing any additional finalization that's needed. There's no chance that the reference count can overflow; at least as many bits are used to hold the reference count as there are distinct memory locations in virtual memory (assuming sizeof(Py\_ssize\_t) >= sizeof(void\*)). Thus, the reference count increment is a simple operation.

It is not necessary to increment an object's reference count for every local variable that contains a pointer to an object. In theory, the object's reference count goes up by one when the variable is made to point to it and it goes down by one when the variable goes out of scope. However, these two cancel each other out, so at the end the reference count hasn't changed. The only real reason to use the reference count is to prevent the object from being deallocated as long as our variable is pointing to it. If we know that there is at least one other reference to the object that lives at least as long as our variable, there is no need to increment the reference count temporarily. An important situation where this arises is in objects that are passed as arguments to C functions in an extension module that are called from Python; the call mechanism guarantees to hold a reference to every argument for the duration of the call.

However, a common pitfall is to extract an object from a list and hold on to it for a while without incrementing its reference count. Some other operation might conceivably remove the object from the list, decrementing its reference count and possibly deallocating it. The real danger is that innocent-looking operations may invoke arbitrary Python code which could do this; there is a code path which allows control to flow back to the user from a  $Py\_DECREF()$ , so almost any operation is potentially dangerous.

A safe approach is to always use the generic operations (functions whose name begins with PyObject\_, PyNumber\_, PySequence\_ or PyMapping\_). These operations always increment the reference count of the object they return. This leaves the caller with the responsibility to call  $Py_DECREF()$  when they are done with the result; this soon becomes second nature.

#### **Reference Count Details**

The reference count behavior of functions in the Python/C API is best explained in terms of ownership of references. Ownership pertains to references, never to objects (objects are not owned: they are always shared). "Owning a reference" means being responsible for calling Py\_DECREF on it when the reference is no longer needed. Ownership can also be transferred, meaning that the code that receives ownership of the reference then becomes responsible for eventually decref'ing it by calling  $Py_DECREF$  () or  $Py_XDECREF$  () when it's no longer needed---or passing on this responsibility (usually to its caller). When a function passes ownership of a reference on to its caller, the caller is said to receive a new reference. When no ownership is transferred, the caller is said to borrow the reference. Nothing needs to be done for a borrowed reference.

Conversely, when a calling function passes in a reference to an object, there are two possibilities: the function *steals* a reference to the object, or it does not. *Stealing a reference* means that when you pass a reference to a function, that function assumes that it now owns that reference, and you are not responsible for it any longer.

Few functions steal references; the two notable exceptions are PyList\_SetItem() and PyTuple\_SetItem(), which steal a reference to the item (but not to the tuple or list into which the item is put!). These functions were designed

to steal a reference because of a common idiom for populating a tuple or list with newly created objects; for example, the code to create the tuple (1, 2, "three") could look like this (forgetting about error handling for the moment; a better way to code this is shown below):

```
PyObject *t;

t = PyTuple_New(3);
PyTuple_SetItem(t, 0, PyLong_FromLong(1L));
PyTuple_SetItem(t, 1, PyLong_FromLong(2L));
PyTuple_SetItem(t, 2, PyUnicode_FromString("three"));
```

Here,  $PyLong\_FromLong()$  returns a new reference which is immediately stolen by  $PyTuple\_SetItem()$ . When you want to keep using an object although the reference to it will be stolen, use  $Py\_INCREF()$  to grab another reference before calling the reference-stealing function.

Incidentally,  $PyTuple\_SetItem()$  is the *only* way to set tuple items;  $PySequence\_SetItem()$  and  $PyObject\_SetItem()$  refuse to do this since tuples are an immutable data type. You should only use  $PyTuple\_SetItem()$  for tuples that you are creating yourself.

Equivalent code for populating a list can be written using PyList\_New() and PyList\_SetItem().

However, in practice, you will rarely use these ways of creating and populating a tuple or list. There's a generic function,  $Py\_BuildValue()$ , that can create most common objects from C values, directed by a *format string*. For example, the above two blocks of code could be replaced by the following (which also takes care of the error checking):

```
PyObject *tuple, *list;

tuple = Py_BuildValue("(iis)", 1, 2, "three");
list = Py_BuildValue("[iis]", 1, 2, "three");
```

It is much more common to use <code>PyObject\_SetItem()</code> and friends with items whose references you are only borrowing, like arguments that were passed in to the function you are writing. In that case, their behaviour regarding reference counts is much saner, since you don't have to increment a reference count so you can give a reference away ("have it be stolen"). For example, this function sets all items of a list (actually, any mutable sequence) to a given item:

```
int
set_all(PyObject *target, PyObject *item)
{
    Py_ssize_t i, n;
    n = PyObject_Length(target);
    if (n < 0)
        return -1;
    for (i = 0; i < n; i++) {
        PyObject *index = PyLong_FromSsize_t(i);
        if (!index)
            return -1;
        if (PyObject_SetItem(target, index, item) < 0) {
            Py_DECREF(index);
            return -1;
        }
        Py_DECREF(index);
    }
    return 0;
}</pre>
```

The situation is slightly different for function return values. While passing a reference to most functions does not change your ownership responsibilities for that reference, many functions that return a reference to an object give you ownership of the reference. The reason is simple: in many cases, the returned object is created on the fly, and the reference you get is the

only reference to the object. Therefore, the generic functions that return object references, like  $PyObject\_GetItem()$  and  $PySequence\_GetItem()$ , always return a new reference (the caller becomes the owner of the reference).

It is important to realize that whether you own a reference returned by a function depends on which function you call only --- the plumage (the type of the object passed as an argument to the function) doesn't enter into it! Thus, if you extract an item from a list using  $PyList\_GetItem()$ , you don't own the reference --- but if you obtain the same item from the same list using  $PySequence\_GetItem()$  (which happens to take exactly the same arguments), you do own a reference to the returned object.

Here is an example of how you could write a function that computes the sum of the items in a list of integers; once using  $PyList\_GetItem()$ , and once using  $PySequence\_GetItem()$ .

```
sum_list(PyObject *list)
   Py_ssize_t i, n;
   long total = 0, value;
   PyObject *item;
   n = PyList_Size(list);
   if (n < 0)
       return -1; /* Not a list */
    for (i = 0; i < n; i++) {</pre>
        item = PyList_GetItem(list, i); /* Can't fail */
        if (!PyLong_Check(item)) continue; /* Skip non-integers */
        value = PyLong_AsLong(item);
        if (value == -1 && PyErr_Occurred())
            /* Integer too big to fit in a C long, bail out */
            return -1;
       total += value;
   return total;
}
```

```
sum_sequence(PyObject *sequence)
   Py_ssize_t i, n;
    long total = 0, value;
   PyObject *item;
    n = PySequence_Length(sequence);
   if (n < 0)
        return -1; /* Has no length */
    for (i = 0; i < n; i++) {</pre>
        item = PySequence_GetItem(sequence, i);
        if (item == NULL)
            return -1; /* Not a sequence, or other failure */
        if (PyLong_Check(item)) {
            value = PyLong_AsLong(item);
            Py_DECREF (item);
            if (value == -1 && PyErr_Occurred())
                /* Integer too big to fit in a C long, bail out */
                return -1;
            total += value;
        }
        else {
            Py_DECREF(item); /* Discard reference ownership */
        }
```

(suite sur la page suivante)

(suite de la page précédente)

```
return total;
}
```

### **1.4.2 Types**

There are few other data types that play a significant role in the Python/C API; most are simple C types such as int, long, double and char\*. A few structure types are used to describe static tables used to list the functions exported by a module or the data attributes of a new object type, and another is used to describe the value of a complex number. These will be discussed together with the functions that use them.

```
type Py_ssize_t
```

Part of the Stable ABI. A signed integral type such that  $sizeof(Py_size_t) == sizeof(size_t)$ . C99 doesn't define such a thing directly (size\_t is an unsigned integral type). See PEP 353 for details.  $PY_SSIZE_T_MAX$  is the largest positive value of type  $Py_size_t$ .

# 1.5 Exceptions

The Python programmer only needs to deal with exceptions if specific error handling is required; unhandled exceptions are automatically propagated to the caller, then to the caller's caller, and so on, until they reach the top-level interpreter, where they are reported to the user accompanied by a stack traceback.

For C programmers, however, error checking always has to be explicit. All functions in the Python/C API can raise exceptions, unless an explicit claim is made otherwise in a function's documentation. In general, when a function encounters an error, it sets an exception, discards any object references that it owns, and returns an error indicator. If not documented otherwise, this indicator is either NULL or -1, depending on the function's return type. A few functions return a Boolean true/false result, with false indicating an error. Very few functions return no explicit error indicator or have an ambiguous return value, and require explicit testing for errors with  $PyErr\_Occurred()$ . These exceptions are always explicitly documented.

Exception state is maintained in per-thread storage (this is equivalent to using global storage in an unthreaded application). A thread can be in one of two states: an exception has occurred, or not. The function  $PyErr\_Occurred()$  can be used to check for this: it returns a borrowed reference to the exception type object when an exception has occurred, and NULL otherwise. There are a number of functions to set the exception state:  $PyErr\_SetString()$  is the most common (though not the most general) function to set the exception state, and  $PyErr\_Clear()$  clears the exception state.

The full exception state consists of three objects (all of which can be NULL): the exception type, the corresponding exception value, and the traceback. These have the same meanings as the Python result of  $sys.exc\_info()$ ; however, they are not the same: the Python objects represent the last exception being handled by a Python try ... except statement, while the C level exception state only exists while an exception is being passed on between C functions until it reaches the Python bytecode interpreter's main loop, which takes care of transferring it to  $sys.exc\_info()$  and friends.

Note that starting with Python 1.5, the preferred, thread-safe way to access the exception state from Python code is to call the function <code>sys.exc\_info()</code>, which returns the per-thread exception state for Python code. Also, the semantics of both ways to access the exception state have changed so that a function which catches an exception will save and restore its thread's exception state so as to preserve the exception state of its caller. This prevents common bugs in exception handling code caused by an innocent-looking function overwriting the exception being handled; it also reduces the often unwanted lifetime extension for objects that are referenced by the stack frames in the traceback.

As a general principle, a function that calls another function to perform some task should check whether the called function raised an exception, and if so, pass the exception state on to its caller. It should discard any object references that it owns,

and return an error indicator, but it should *not* set another exception --- that would overwrite the exception that was just raised, and lose important information about the exact cause of the error.

A simple example of detecting exceptions and passing them on is shown in the sum\_sequence() example above. It so happens that this example doesn't need to clean up any owned references when it detects an error. The following example function shows some error cleanup. First, to remind you why you like Python, we show the equivalent Python code:

```
def incr_item(dict, key):
    try:
        item = dict[key]
    except KeyError:
        item = 0
    dict[key] = item + 1
```

Here is the corresponding C code, in all its glory:

```
int
incr_item(PyObject *dict, PyObject *key)
    /* Objects all initialized to NULL for Py_XDECREF */
   PyObject *item = NULL, *const_one = NULL, *incremented_item = NULL;
   int rv = -1; /* Return value initialized to -1 (failure) */
    item = PyObject_GetItem(dict, key);
    if (item == NULL) {
        /* Handle KeyError only: */
        if (!PyErr_ExceptionMatches(PyExc_KeyError))
            goto error;
        /* Clear the error and use zero: */
        PyErr_Clear();
        item = PyLong_FromLong(0L);
        if (item == NULL)
            goto error;
    }
    const_one = PyLong_FromLong(1L);
    if (const_one == NULL)
        goto error;
    incremented_item = PyNumber_Add(item, const_one);
   if (incremented_item == NULL)
        goto error;
    if (PyObject_SetItem(dict, key, incremented_item) < 0)</pre>
        goto error;
    rv = 0; /* Success */
    /* Continue with cleanup code */
error:
    /* Cleanup code, shared by success and failure path */
   /* Use Py_XDECREF() to ignore NULL references */
   Pv XDECREF (item);
   Py_XDECREF(const_one);
   Py_XDECREF(incremented_item);
    return rv; /* -1 for error, 0 for success */
```

1.5. Exceptions 11

This example represents an endorsed use of the goto statement in C! It illustrates the use of  $PyErr\_ExceptionMatches()$  and  $PyErr\_Clear()$  to handle specific exceptions, and the use of  $Py\_XDECREF()$  to dispose of owned references that may be NULL (note the 'X' in the name;  $Py\_DECREF()$  would crash when confronted with a NULL reference). It is important that the variables used to hold owned references are initialized to NULL for this to work; likewise, the proposed return value is initialized to -1 (failure) and only set to success after the final call made is successful.

# 1.6 Embarquer Python

The one important task that only embedders (as opposed to extension writers) of the Python interpreter have to worry about is the initialization, and possibly the finalization, of the Python interpreter. Most functionality of the interpreter can only be used after the interpreter has been initialized.

The basic initialization function is  $Py_Initialize()$ . This initializes the table of loaded modules, and creates the fundamental modules builtins, \_\_main\_\_, and sys. It also initializes the module search path (sys.path).

Py\_Initialize() does not set the "script argument list" (sys.argv). If this variable is needed by Python code that will be executed later, setting PyConfig.argv and PyConfig.parse\_argv must be set: see Python Initialization Configuration.

On most systems (in particular, on Unix and Windows, although the details are slightly different),  $Py\_Initialize()$  calculates the module search path based upon its best guess for the location of the standard Python interpreter executable, assuming that the Python library is found in a fixed location relative to the Python interpreter executable. In particular, it looks for a directory named lib/pythonX. Y relative to the parent directory where the executable named python is found on the shell command search path (the environment variable PATH).

For instance, if the Python executable is found in /usr/local/bin/python, it will assume that the libraries are in / usr/local/lib/pythonX. Y. (In fact, this particular path is also the "fallback" location, used when no executable file named python is found along PATH.) The user can override this behavior by setting the environment variable PYTHONHOME, or insert additional directories in front of the standard path by setting PYTHONPATH.

The embedding application can steer the search by calling Py\_SetProgramName(file) before calling  $Py_Initialize()$ . Note that PYTHONHOME still overrides this and PYTHONPATH is still inserted in front of the standard path. An application that requires total control has to provide its own implementation of  $Py_GetPath()$ ,  $Py_GetPrefix()$ ,  $Py_GetExecPrefix()$ , and  $Py_GetProgramFullPath()$  (all defined in Modules/getpath.c).

Sometimes, it is desirable to "uninitialize" Python. For instance, the application may want to start over (make another call to  $Py\_Initialize()$ ) or the application is simply done with its use of Python and wants to free memory allocated by Python. This can be accomplished by calling  $Py\_FinalizeEx()$ . The function  $Py\_IsInitialized()$  returns true if Python is currently in the initialized state. More information about these functions is given in a later chapter. Notice that  $Py\_FinalizeEx()$  does *not* free all memory allocated by the Python interpreter, e.g. memory allocated by extension modules currently cannot be released.

# 1.7 Debugging Builds

Python can be built with several macros to enable extra checks of the interpreter and extension modules. These checks tend to add a large amount of overhead to the runtime so they are not enabled by default.

A full list of the various types of debugging builds is in the file Misc/SpecialBuilds.txt in the Python source distribution. Builds are available that support tracing of reference counts, debugging the memory allocator, or low-level profiling of the main interpreter loop. Only the most frequently used builds will be described in the remainder of this section.

Compiling the interpreter with the Py\_DEBUG macro defined produces what is generally meant by a debug build of Python. Py\_DEBUG is enabled in the Unix build by adding --with-pydebug to the ./configure command. It is also implied by the presence of the not-Python-specific \_DEBUG macro. When Py\_DEBUG is enabled in the Unix build, compiler optimization is disabled.

In addition to the reference count debugging described below, extra checks are performed, see Python Debug Build.

Defining Py\_TRACE\_REFS enables reference tracing (see the configure --with-trace-refs option). When defined, a circular doubly linked list of active objects is maintained by adding two extra fields to every PyObject. Total allocations are tracked as well. Upon exit, all existing references are printed. (In interactive mode this happens after every statement run by the interpreter.)

Please refer to Misc/SpecialBuilds.txt in the Python source distribution for more detailed information.

#### Stabilité de l'API C

L'API C respecte la politique de rétrocompatibilité de Python, **PEP 387**. Malgré la présence d'évolutions dans chaque version mineure (par exemple entre 3.9 et 3.10), la majorité de ces changements n'affecte pas la compatibilité du code source. Typiquement des API sont ajoutées mais pas modifiées ou supprimées, bien que cela puisse arriver après une période de dépréciation ou pour corriger un problème important.

L'interface binaire de CPython (ABI) est entièrement compatible au sein d'une version mineure (à condition que la compilation soit toujours faite de même manière, comme indiqué dans *Considérations relatives aux plateformes* ci-dessous). Ainsi le code compilé pour Python 3.10.0 fonctionnera avec Python 3.10.8 et inversement, mais il devra être compilé séparément pour 3.9.x et 3.10.x.

Les noms commençant par un caractère souligné, comme \_Py\_InternalState, font partie de l'API privée et peuvent changer sans préavis même dans une version de correctif.

#### 2.1 ABI stable

Le concept d'*API restreinte*, un sous-ensemble de l'API C de Python, existe depuis Python 3.2. Les extensions qui utilisent uniquement l'API restreinte peuvent être compilées une seule fois et fonctionner avec plusieurs versions de Python. Les objets faisant partie de l'API restreinte sont *documentés ci-dessous*.

Python a aussi une *ABI stable*: un ensemble de symboles qui sont compatibles avec l'ensemble des versions Python 3.x. L'ABI stable contient les symboles utilisés par l'API restreinte, mais pas seulement — par exemple les fonctions nécessaires pour supporter les versions précédentes de l'API restreinte en font aussi partie.

(Par simplicité ce document parle *d'extensions*, mais l'API restreinte et l'ABI stable fonctionnent de la même manière pour tous les cas d'usages de l'API — par exemple pour embarquer Python.)

#### Py LIMITED API

Définissez cette macro avant d'inclure Python. h pour n'inclure que l'API restreinte et indiquer sa version. Définissez Py\_LIMITED\_API à la valeur de PY\_VERSION\_HEX correspond à la version minimale de Python que votre extension supporte. Cette extension fonctionnera sans re-compilation avec toutes les versions futures de Python 3, et peut utiliser l'ensemble des éléments de l'API restreinte présent dans cette version.

Il est recommandé de renseigner une version mineure minimale (par exemple 0x030A0000 pour Python 3.10) plutôt que d'utiliser directement la macro PY\_VERSION\_HEX pour ne pas dépendre de la version de Python utilisée lors de la compilation.

Vous pouvez aussi définir Py\_LIMITED\_API à 3. Cette valeur est équivalente à 0x03020000 correspondant à Python 3.2, la première version à supporter l'API restreinte.

Sur Windows les extensions qui utilisent l'ABI stable doivent être liées avec python3.dll et non pas avec une bibliothèque spécifique à une version comme python39.dll.

Sur certaines plateformes Python essaiera de charger une bibliothèque partagée dont le nom contient abi3 (par exemple mymodule.abi3.so). Il ne vérifie pas si ces extensions respectent l'ABI stable. L'utilisateur (ou ses outils d'administration) doit s'assurer que les extensions compilées avec une version donnée de l'API restreinte, par exemple 3.10+, ne sont pas utilisées avec des versions plus anciennes de Python.

Toutes les fonctions de l'ABI stable sont présentes dans la bibliothèque dynamique de Python en tant que fonction, et pas uniquement comme macro. Elles peuvent donc être utilisées avec des langages qui n'utilisent pas le pré-processeur C.

#### 2.1.1 Porté de l'API restreinte et performance

L'objectif de l'API restreinte est de permettre l'ensemble des opérations possibles avec l'API C étendue, mais peut avoir un impact sur les performances.

Par exemple la fonction <code>PyList\_GetItem()</code> est disponible, mais la macro « dangereuse » <code>PyList\_GET\_ITEM()</code> ne l'est pas. Cette macro peut être plus rapide car elle dépend de détails d'implémentation spécifique à l'objet list.

Si Py\_LIMITED\_API n'est pas défini certaines fonctions de l'API C seront remplacées par des macros ou une version en-ligne. Définir Py\_LIMITED\_API désactive cette optimisation, permettant de se garantir contre les évolutions des structures de données utilisées par Python, et peut réduire les performances.

En omettant la définition de Py\_LIMITED\_API il est possible de compiler une extension utilisant l'API restreinte avec une version spécifique de l'ABI. Les performances seront meilleures pour cette version de Python, mais la compatibilité sera réduite. Compiler en définissant Py\_LIMITED\_API produira une extension qui peut être utilisée quand une variante spécifique à une version n'est pas disponible — par exemple pour une version alpha de Python.

#### 2.1.2 Inconvénients de l'API restreinte

Compiler avec Py\_LIMITED\_API *n'est pas* une garantie absolue que le code est conforme à l'API restreinte ou à l'ABI stable. Py\_LIMITED\_API ne concerne que la définition des objets, mais une API inclut aussi d'autres spécificités comme le comportement attendu.

Une des limitations est que Py\_LIMITED\_API ne protège pas contre l'appel d'une fonction avec des arguments qui sont invalides pour une version de Python plus ancienne. Par exemple considérons une fonction qui accepte NULL comme argument à partir de 3.9. NULL permet maintenant d'utiliser le comportement par défaut, mais Python 3.8 essayera d'accéder à l'objet pointé et dé-référencera NULL, causant un crash. Des problèmes similaires peuvent se produire avec les attributs des structures.

Un autre problème est que certains attributs ne sont pas encore cachés lorsque Py\_LIMITED\_API est défini, même s'ils ne font pas partie de l'API restreinte.

Pour ces raisons il est recommandé de tester une extension avec *l'ensemble des versions mineures* supportées de Python, et généralement de la compiler avec la plus *ancienne* de ces versions.

Il est aussi recommandé de vérifier la documentation de toutes les API utilisées pour vérifier qu'elles fassent bien partie de l'API restreinte. Même lorsque Py\_LIMITED\_API est défini quelques fonctions privées peuvent être exposées aux utilisateurs pour des raisons techniques, ou par erreur.

Notez aussi que l'API restreinte n'est pas forcément stable : compiler avec Python 3.8 en définissant Py\_LIMITED\_API garanti que l'extension fonctionnera avec Python 3.12, mais pas qu'elle pourra *être compilée* avec Python 3.12. En particulier certaines parties de l'API restreinte peuvent être dépréciées et retirées tant que l'ABI stable n'est pas modifiée.

# 2.2 Considérations relatives aux plateformes

La stabilité de l'ABI ne dépend pas que de Python mais aussi du compilateur utilisé, des bibliothèques systèmes et des options du compilateur. L'ensemble de ces détails correspondent à ce que l'ABI stable appelle une « plateforme ». Ils dépendent généralement du système d'exploitation et de l'architecture du processeur.

Les distributeurs de Python doivent s'assurer que toutes les versions de Python pour une plateforme donnée sont compilées de manière à ne pas rompre la compatibilité de l'ABI stable. C'est le cas des versions produites pour Windows et macOS de python.org et de la plupart des distributions tierces.

## 2.3 Contenu de l'API restreinte

Pour le moment l'API restreinte inclut les éléments suivants :

```
- PyAIter Check()
— PyArg_Parse()
- PyArg ParseTuple()
— PyArg_ParseTupleAndKeywords()
— PyArg_UnpackTuple()
— PyArg_VaParse()
— PyArg_VaParseTupleAndKeywords()
— PyArg_ValidateKeywordArguments()
— PyBaseObject_Type
— PyBool_FromLong()
— PyBool_Type
- PyBuffer_FillContiguousStrides()
— PyBuffer FillInfo()
— PyBuffer_FromContiguous()
- PyBuffer GetPointer()
- PyBuffer_IsContiguous()
- PyBuffer Release()
— PyBuffer_SizeFromFormat()
- PyBuffer ToContiquous()
— PyByteArrayIter_Type
— PyByteArray_AsString()
— PyByteArray_Concat()
— PyByteArray_FromObject()
— PyByteArray_FromStringAndSize()
— PyByteArray_Resize()
— PyByteArray_Size()
— PyByteArray_Type
— PyBytesIter_Type
— PyBytes_AsString()
- PyBytes AsStringAndSize()
- PyBytes Concat()
- PyBytes ConcatAndDel()
```

```
— PyBytes_DecodeEscape()
— PyBytes_FromFormat()
- PyBytes FromFormatV()
- PyBytes_FromObject()
— PyBytes_FromString()
- PyBytes FromStringAndSize()
— PyBytes Repr()
— PyBytes_Size()
- PyBytes_Type
- PyCFunction
— PyCFunctionWithKeywords
— PyCFunction_Call()
— PyCFunction_GetFlags()
— PyCFunction_GetFunction()
— PyCFunction_GetSelf()
— PyCFunction_New()
— PyCFunction_NewEx()
— PyCFunction_Type
— PyCMethod_New()
— PyCallIter_New()
— PyCallIter_Type
- PyCallable_Check()
— PyCapsule_Destructor
- PyCapsule GetContext()
— PyCapsule_GetDestructor()
— PyCapsule_GetName()
— PyCapsule_GetPointer()
— PyCapsule_Import()
— PyCapsule_IsValid()
— PyCapsule_New()
— PyCapsule_SetContext()
— PyCapsule_SetDestructor()
— PyCapsule_SetName()
— PyCapsule_SetPointer()
- PvCapsule Type
— PyClassMethodDescr_Type
— PyCodec_BackslashReplaceErrors()
— PyCodec_Decode()
— PyCodec_Decoder()
— PyCodec_Encode()
- PyCodec Encoder()
— PyCodec_IgnoreErrors()
— PyCodec_IncrementalDecoder()
— PyCodec_IncrementalEncoder()
— PyCodec_KnownEncoding()
— PyCodec_LookupError()
— PyCodec_NameReplaceErrors()
- PyCodec_Register()
— PyCodec_RegisterError()
— PyCodec_ReplaceErrors()
— PyCodec_StreamReader()
— PyCodec_StreamWriter()
— PyCodec_StrictErrors()
— PyCodec_Unregister()
```

```
— PyCodec XMLCharRefReplaceErrors()
— PyComplex_FromDoubles()
— PyComplex ImagAsDouble()
— PyComplex_RealAsDouble()
— PyComplex_Type
— PyDescr NewClassMethod()
- PyDescr NewGetSet()
— PyDescr_NewMember()
— PyDescr_NewMethod()
— PyDictItems_Type
— PyDictIterItem_Type
— PyDictIterKey_Type
— PyDictIterValue_Type
- PyDictKeys_Type
— PyDictProxy_New()
— PyDictProxy_Type
— PyDictRevIterItem_Type
— PyDictRevIterKey_Type
— PyDictRevIterValue_Type
— PyDictValues_Type
— PyDict_Clear()
— PyDict_Contains()
— PyDict_Copy()
- PyDict DelItem()
— PyDict_DelItemString()
- PyDict GetItem()
— PyDict_GetItemString()
— PyDict_GetItemWithError()
— PyDict_Items()
— PyDict_Keys()
— PyDict_Merge()
— PyDict_MergeFromSeq2()
— PyDict_New()
— PyDict_Next()
- PyDict SetItem()
— PyDict_SetItemString()
- PyDict Size()
- PyDict_Type
— PyDict_Update()
— PyDict_Values()
— PyEllipsis_Type
— PyEnum_Type
— PyErr_BadArgument()
— PyErr_BadInternalCall()
— PyErr_CheckSignals()
— PyErr_Clear()
— PyErr_Display()
— PyErr_ExceptionMatches()
— PyErr_Fetch()
— PyErr_Format()
— PyErr_FormatV()
— PyErr_GetExcInfo()
— PyErr_GetHandledException()
— PyErr GivenExceptionMatches()
```

```
- PyErr NewException()
— PyErr_NewExceptionWithDoc()
- PyErr NoMemory()
— PyErr_NormalizeException()
— PyErr_Occurred()
- PyErr Print()
— PyErr PrintEx()
— PyErr_ProgramText()
— PyErr ResourceWarning()
— PyErr_Restore()
— PyErr_SetExcFromWindowsErr()
— PyErr_SetExcFromWindowsErrWithFilename()
— PyErr_SetExcFromWindowsErrWithFilenameObject()
— PyErr_SetExcFromWindowsErrWithFilenameObjects()
— PyErr_SetExcInfo()
— PyErr_SetFromErrno()
— PyErr_SetFromErrnoWithFilename()
— PvErr SetFromErrnoWithFilenameObject()
— PyErr_SetFromErrnoWithFilenameObjects()
— PyErr SetFromWindowsErr()
— PyErr_SetFromWindowsErrWithFilename()
— PyErr_SetHandledException()
— PyErr_SetImportError()
— PyErr SetImportErrorSubclass()
— PyErr_SetInterrupt()
— PyErr_SetInterruptEx()
— PyErr_SetNone()
- PyErr_SetObject()
— PyErr_SetString()
- PyErr_SyntaxLocation()
— PyErr_SyntaxLocationEx()
— PyErr_WarnEx()
— PyErr_WarnExplicit()
— PyErr_WarnFormat()
- PyErr WriteUnraisable()
- PyEval_AcquireLock()
- PyEval AcquireThread()
— PyEval_CallFunction()
— PyEval_CallMethod()
— PyEval_CallObjectWithKeywords()
- PyEval EvalCode()
— PyEval EvalCodeEx()
- PyEval EvalFrame()
— PyEval_EvalFrameEx()
— PyEval_GetBuiltins()
— PyEval_GetFrame()
— PyEval_GetFuncDesc()
— PyEval_GetFuncName()
— PyEval_GetGlobals()
— PyEval_GetLocals()
- PyEval_InitThreads()
— PyEval_ReleaseLock()
— PyEval_ReleaseThread()
- PyEval RestoreThread()
```

- PyEval\_SaveThread()
- PyEval\_ThreadsInitialized()
- PyExc\_ArithmeticError
- PyExc\_AssertionError
- PyExc\_AttributeError
- PyExc\_BaseException
- PyExc\_BaseExceptionGroup
- PyExc\_BlockingIOError
- PyExc\_BrokenPipeError
- PyExc\_BufferError
- PyExc\_BytesWarning
- PyExc\_ChildProcessError
- PyExc\_ConnectionAbortedError
- PyExc\_ConnectionError
- PyExc\_ConnectionRefusedError
- PyExc\_ConnectionResetError
- PyExc\_DeprecationWarning
- PyExc\_EOFError
- PyExc\_EncodingWarning
- PyExc\_EnvironmentError
- PyExc\_Exception
- PyExc\_FileExistsError
- PyExc\_FileNotFoundError
- PyExc FloatingPointError
- PyExc\_FutureWarning
- PyExc\_GeneratorExit
- PyExc\_IOError
- PyExc\_ImportError
- PyExc\_ImportWarning
- PyExc\_IndentationError
- PyExc\_IndexError
- PyExc\_InterruptedError
- PyExc\_IsADirectoryError
- PyExc\_KeyError
- PyExc\_KeyboardInterrupt
- PyExc\_LookupError
- PyExc\_MemoryError
- PyExc\_ModuleNotFoundError
- PyExc\_NameError
- PyExc\_NotADirectoryError
- PyExc NotImplementedError
- PyExc\_OSError
- PyExc\_OverflowError
- PyExc\_PendingDeprecationWarning
- PyExc\_PermissionError
- PyExc\_ProcessLookupError
- PyExc\_RecursionError
- PyExc\_ReferenceError
- PyExc\_ResourceWarning
- PyExc\_RuntimeError
- PyExc\_RuntimeWarning
- PyExc\_StopAsyncIteration
- PyExc\_StopIteration
- PyExc\_SyntaxError

- PyExc\_SyntaxWarning — PyExc\_SystemError - PyExc SystemExit — PyExc\_TabError — PyExc\_TimeoutError — PyExc TypeError - PyExc UnboundLocalError — PyExc\_UnicodeDecodeError - PyExc\_UnicodeEncodeError — PyExc\_UnicodeError — PyExc\_UnicodeTranslateError — PyExc\_UnicodeWarning — PyExc\_UserWarning — PyExc\_ValueError — PyExc\_Warning — PyExc\_WindowsError - PyExc\_ZeroDivisionError — PyExceptionClass\_Name() — PyException\_GetCause() — PyException\_GetContext() — PyException\_GetTraceback() — PyException\_SetCause() — PyException\_SetContext() — PyException\_SetTraceback() — PyFile\_FromFd() — PyFile\_GetLine() — PyFile\_WriteObject() — PyFile\_WriteString() — PyFilter\_Type - PyFloat\_AsDouble() — PyFloat\_FromDouble() — PyFloat\_FromString() — PyFloat\_GetInfo() — PyFloat\_GetMax() — PyFloat\_GetMin() — PyFloat\_Type - PyFrameObject — PyFrame\_GetCode() — PyFrame\_GetLineNumber() — PyFrozenSet\_New() — PyFrozenSet\_Type - PyGC Collect() - PyGC\_Disable() — PyGC\_Enable() — PyGC\_IsEnabled() — PyGILState\_Ensure() — PyGILState\_GetThisThreadState() — PyGILState\_Release() — PyGILState\_STATE - PyGetSetDef — PyGetSetDescr\_Type — PyImport\_AddModule() — PyImport\_AddModuleObject() — PyImport\_AppendInittab()

```
— PyImport_ExecCodeModule()
— PyImport_ExecCodeModuleEx()
— PyImport ExecCodeModuleObject()
— PyImport_ExecCodeModuleWithPathnames()
- PyImport GetImporter()
— PyImport GetMagicNumber()
— PyImport GetMagicTag()
— PyImport_GetModule()
— PyImport_GetModuleDict()
— PyImport_Import()
— PyImport_ImportFrozenModule()
— PyImport_ImportFrozenModuleObject()
— PyImport_ImportModule()
— PyImport_ImportModuleLevel()
— PyImport_ImportModuleLevelObject()
— PyImport_ImportModuleNoBlock()
— PyImport_ReloadModule()
- PyIndex Check()
- PyInterpreterState
- PyInterpreterState Clear()
— PyInterpreterState_Delete()
- PyInterpreterState Get()
— PyInterpreterState_GetDict()
— PyInterpreterState GetID()
— PyInterpreterState_New()
- PyIter Check()
— PyIter_Next()
— PyIter_Send()
— PyListIter_Type
— PyListRevIter_Type
— PyList_Append()
- PyList_AsTuple()
— PyList_GetItem()
— PyList_GetSlice()
- PyList Insert()
— PyList_New()
- PyList Reverse()
— PyList_SetItem()
— PyList_SetSlice()
— PyList_Size()
- PyList Sort()
— PyList_Type
- PyLongObject
— PyLongRangeIter_Type
— PyLong_AsDouble()
— PyLong_AsLong()
— PyLong_AsLongAndOverflow()
— PyLong_AsLongLong()
— PyLong_AsLongLongAndOverflow()
— PyLong_AsSize_t()
- PyLong_AsSsize_t()
— PyLong_AsUnsignedLong()
— PyLong_AsUnsignedLongLong()
```

— PyLong AsUnsignedLongLongMask()

```
— PyLong_AsUnsignedLongMask()
— PyLong_AsVoidPtr()
- PyLong FromDouble()
— PyLong_FromLong()
— PyLong_FromLongLong()
- PyLong FromSize t()
- PyLong FromSsize t()
— PyLong_FromString()
— PyLong_FromUnsignedLong()
— PyLong_FromUnsignedLongLong()
— PyLong_FromVoidPtr()
— PyLong_GetInfo()
- PyLong_Type
- PyMap_Type
— PyMapping_Check()
— PyMapping_GetItemString()
— PyMapping_HasKey()
- PyMapping HasKeyString()
— PyMapping_Items()
- PyMapping Keys()
— PyMapping_Length()
— PyMapping_SetItemString()
— PyMapping_Size()
- PyMapping Values()
— PyMem_Calloc()
- PyMem Free()
— PyMem_Malloc()
— PyMem_Realloc()
— PyMemberDef
— PyMemberDescr_Type
— PyMemoryView_FromBuffer()
— PyMemoryView_FromMemory()
— PyMemoryView_FromObject()
— PyMemoryView_GetContiguous()
— PyMemoryView_Type
— PyMethodDef
- PyMethodDescr_Type
— PyModuleDef
— PyModuleDef_Base
— PyModuleDef_Init()
— PyModuleDef Type
— PyModule_AddFunctions()
— PyModule AddIntConstant()
- PyModule_AddObject()
— PyModule_AddObjectRef()
— PyModule_AddStringConstant()
— PyModule_AddType()
— PyModule_Create2()
— PyModule_ExecDef()
— PyModule_FromDefAndSpec2()
— PyModule_GetDef()
— PyModule_GetDict()
— PyModule_GetFilename()
- PyModule GetFilenameObject()
```

- PyModule GetName() — PyModule\_GetNameObject() - PyModule GetState() — PyModule\_New() - PyModule NewObject() - PyModule SetDocString() - PyModule Type - PyNumber Absolute() — PyNumber Add() — PyNumber\_And() — PyNumber\_AsSsize\_t() — PyNumber\_Check() — PyNumber\_Divmod() — PyNumber\_Float() — PyNumber\_FloorDivide() — PyNumber\_InPlaceAdd() — PyNumber\_InPlaceAnd() - PyNumber InPlaceFloorDivide() — PyNumber\_InPlaceLshift() — PyNumber InPlaceMatrixMultiply() — PyNumber\_InPlaceMultiply() — PyNumber InPlaceOr() — PyNumber\_InPlacePower() — PyNumber InPlaceRemainder() - PyNumber InPlaceRshift() — PyNumber InPlaceSubtract() — PyNumber\_InPlaceTrueDivide() — PyNumber\_InPlaceXor() — PyNumber\_Index() — PyNumber\_Invert() — PyNumber\_Long() — PyNumber\_Lshift() — PyNumber\_MatrixMultiply() — PyNumber\_Multiply() - PyNumber Negative() — PyNumber\_Or() - PyNumber Positive() — PyNumber\_Power() — PyNumber\_Remainder() — PyNumber\_Rshift() - PyNumber Subtract() — PyNumber ToBase() — PyNumber\_TrueDivide() — PyNumber\_Xor() — PyOS\_AfterFork() — PyOS\_AfterFork\_Child() — PyOS\_AfterFork\_Parent() — PyOS\_BeforeFork() — PyOS\_CheckStack() — PyOS\_FSPath() - PyOS\_InputHook — PyOS\_InterruptOccurred() — PyOS\_double\_to\_string() - PyOS getsig()

```
— PyOS_mystricmp()
— PyOS_mystrnicmp()
- PyOS setsig()
- PyOS_sighandler_t
- PyOS snprintf()
- PyOS string to double()
— PyOS strtol()
— PyOS_strtoul()
— PyOS_vsnprintf()
- PyObject
— PyObject.ob_refcnt
- PyObject.ob_type
— PyObject_ASCII()
— PyObject_AsCharBuffer()
— PyObject_AsFileDescriptor()
— PyObject_AsReadBuffer()
— PyObject_AsWriteBuffer()
- PvObject Bytes()
— PyObject_Call()
- PyObject CallFunction()
— PyObject_CallFunctionObjArgs()
— PyObject_CallMethod()
— PyObject_CallMethodObjArgs()
- PyObject CallNoArgs()
- PyObject_CallObject()
— PyObject_Calloc()
— PyObject_CheckBuffer()
— PyObject_CheckReadBuffer()
— PyObject_ClearWeakRefs()
— PyObject_CopyData()
— PyObject_DelItem()
— PyObject_DelItemString()
— PyObject_Dir()
— PyObject_Format()
- PvObject Free()
— PyObject_GC_Del()
- PyObject GC IsFinalized()
— PyObject_GC_IsTracked()
— PyObject_GC_Track()
— PyObject_GC_UnTrack()
- PyObject GenericGetAttr()
- PyObject GenericGetDict()
— PyObject_GenericSetAttr()
— PyObject_GenericSetDict()
— PyObject_GetAIter()
— PyObject_GetAttr()
— PyObject_GetAttrString()
— PyObject_GetBuffer()
— PyObject_GetItem()
— PyObject_GetIter()
— PyObject_HasAttr()
— PyObject_HasAttrString()
— PyObject_Hash()
— PyObject HashNotImplemented()
```

```
- PyObject_Init()
— PyObject_InitVar()
- PyObject IsInstance()
- PyObject_IsSubclass()
— PyObject_IsTrue()
- PyObject Length()
- PyObject Malloc()
— PyObject_Not()
- PyObject Realloc()
— PyObject_Repr()
— PyObject_RichCompare()
— PyObject_RichCompareBool()
— PyObject_SelfIter()
— PyObject_SetAttr()
— PyObject_SetAttrString()
— PyObject_SetItem()
- PyObject_Size()
- PvObject Str()
— PyObject_Type()
— PyProperty_Type
— PyRangeIter_Type
- PyRange Type
— PyReversed_Type
— PySeqIter_New()
— PySeqIter_Type
- PySequence Check()
— PySequence_Concat()
- PySequence_Contains()
— PySequence_Count()
— PySequence_DelItem()
- PySequence_DelSlice()
— PySequence_Fast()
— PySequence_GetItem()
— PySequence_GetSlice()
- PySequence In()
— PySequence_InPlaceConcat()
- PySequence InPlaceRepeat ()
— PySequence_Index()
- PySequence_Length()
— PySequence_List()
- PySequence Repeat ()
- PySequence SetItem()
- PySequence SetSlice()
- PySequence_Size()
— PySequence_Tuple()
— PySetIter_Type
— PySet_Add()
— PySet_Clear()
- PySet_Contains()
— PySet_Discard()
— PySet_New()
— PySet_Pop()
— PySet_Size()
```

- PySet Type

```
- PySlice_AdjustIndices()
— PySlice_GetIndices()
- PySlice GetIndicesEx()
— PySlice_New()
— PySlice_Type
- PySlice Unpack()
- PyState AddModule()
— PyState_FindModule()
— PyState_RemoveModule()
— PyStructSequence_Desc
- PyStructSequence_Field
— PyStructSequence_GetItem()
— PyStructSequence_New()
— PyStructSequence_NewType()
— PyStructSequence_SetItem()
- PyStructSequence_UnnamedField
— PySuper_Type
- PvSvs AddWarnOption()
— PySys_AddWarnOptionUnicode()
- PySys AddXOption()
— PySys_FormatStderr()
— PySys_FormatStdout()
- PySys_GetObject()
- PySys GetXOptions()
— PySys_HasWarnOptions()
— PySys_ResetWarnOptions()
— PySys_SetArgv()
— PySys_SetArgvEx()
- PySys_SetObject()
— PySys_SetPath()
— PySys_WriteStderr()
- PySys_WriteStdout()
- PyThreadState
— PyThreadState_Clear()
- PvThreadState Delete()
— PyThreadState_Get()
- PyThreadState GetDict()
— PyThreadState_GetFrame()
— PyThreadState_GetID()
— PyThreadState_GetInterpreter()
- PyThreadState New()
— PyThreadState_SetAsyncExc()
— PyThreadState_Swap()
— PyThread_GetInfo()
— PyThread_ReInitTLS()
— PyThread_acquire_lock()
— PyThread_acquire_lock_timed()
— PyThread_allocate_lock()
— PyThread_create_key()
— PyThread_delete_key()
— PyThread_delete_key_value()
— PyThread_exit_thread()
— PyThread_free_lock()
— PyThread_get_key_value()
```

```
— PyThread_get_stacksize()
— PyThread_get_thread_ident()
- PyThread get thread native id()
— PyThread_init_thread()
— PyThread_release_lock()
- PyThread set key value()
— PyThread_set_stacksize()
— PyThread_start_new_thread()
— PyThread_tss_alloc()
— PyThread_tss_create()
— PyThread_tss_delete()
— PyThread_tss_free()
— PyThread_tss_get()
— PyThread_tss_is_created()
— PyThread_tss_set()
— PyTraceBack_Here()
— PyTraceBack_Print()
- PyTraceBack Type
— PyTupleIter_Type
- PyTuple GetItem()
— PyTuple_GetSlice()
- PyTuple New()
— PyTuple_Pack()
- PyTuple SetItem()
— PyTuple_Size()
- PyTuple_Type
- PyTypeObject
— PyType_ClearCache()
— PyType_FromModuleAndSpec()
— PyType_FromSpec()
— PyType_FromSpecWithBases()
— PyType_GenericAlloc()
— PyType_GenericNew()
— PyType_GetFlags()
- PvTvpe GetModule()
— PyType_GetModuleState()
— PyType GetName()
— PyType_GetQualName()
— PyType_GetSlot()
— PyType_IsSubtype()
— PyType Modified()
— PyType_Ready()
- PyType Slot
- PyType_Spec
— PyType_Type
— PyUnicodeDecodeError_Create()
— PyUnicodeDecodeError_GetEncoding()
— PyUnicodeDecodeError_GetEnd()
— PyUnicodeDecodeError_GetObject()
— PyUnicodeDecodeError_GetReason()
— PyUnicodeDecodeError_GetStart()
— PyUnicodeDecodeError SetEnd()
— PyUnicodeDecodeError_SetReason()
```

— PyUnicodeDecodeError SetStart()

```
— PyUnicodeEncodeError GetEncoding()
— PyUnicodeEncodeError_GetEnd()
— PyUnicodeEncodeError GetObject()
— PyUnicodeEncodeError_GetReason()
— PyUnicodeEncodeError GetStart()
— PyUnicodeEncodeError SetEnd()
— PyUnicodeEncodeError SetReason()
— PyUnicodeEncodeError_SetStart()
— PyUnicodeIter_Type
— PyUnicodeTranslateError_GetEnd()
— PyUnicodeTranslateError_GetObject()
— PyUnicodeTranslateError_GetReason()
— PyUnicodeTranslateError_GetStart()
— PyUnicodeTranslateError_SetEnd()
— PyUnicodeTranslateError_SetReason()
— PyUnicodeTranslateError_SetStart()
— PyUnicode_Append()
— PyUnicode AppendAndDel()
— PyUnicode_AsASCIIString()
— PyUnicode AsCharmapString()
— PyUnicode_AsDecodedObject()
- PyUnicode AsDecodedUnicode()
— PyUnicode_AsEncodedObject()
— PyUnicode AsEncodedString()
— PyUnicode_AsEncodedUnicode()
- PyUnicode AsLatin1String()
— PyUnicode_AsMBCSString()
— PyUnicode_AsRawUnicodeEscapeString()
- PyUnicode_AsUCS4()
- PyUnicode_AsUCS4Copy()
— PyUnicode_AsUTF16String()
— PyUnicode_AsUTF32String()
- PyUnicode_AsUTF8AndSize()
— PyUnicode_AsUTF8String()
- PyUnicode AsUnicodeEscapeString()
— PyUnicode_AsWideChar()
— PyUnicode AsWideCharString()
— PyUnicode_BuildEncodingMap()
— PyUnicode_Compare()
— PyUnicode_CompareWithASCIIString()
- PyUnicode Concat()
- PyUnicode Contains()
- PyUnicode Count()
- PyUnicode_Decode()
- PyUnicode_DecodeASCII()
— PyUnicode_DecodeCharmap()
— PyUnicode_DecodeCodePageStateful()
— PyUnicode_DecodeFSDefault()
- PyUnicode_DecodeFSDefaultAndSize()
- PyUnicode_DecodeLatin1()
— PyUnicode_DecodeLocale()
- PyUnicode_DecodeLocaleAndSize()
— PyUnicode_DecodeMBCS()
- PyUnicode DecodeMBCSStateful()
```

- PyUnicode DecodeRawUnicodeEscape() - PyUnicode\_DecodeUTF16() - PyUnicode DecodeUTF16Stateful() — PyUnicode\_DecodeUTF32() - PyUnicode DecodeUTF32Stateful() - PyUnicode DecodeUTF7() - PyUnicode DecodeUTF7Stateful() - PyUnicode DecodeUTF8() - PyUnicode DecodeUTF8Stateful() — PyUnicode\_DecodeUnicodeEscape() — PyUnicode\_EncodeCodePage() — PyUnicode\_EncodeFSDefault() — PyUnicode\_EncodeLocale() - PyUnicode\_FSConverter() — PyUnicode\_FSDecoder() — PyUnicode\_Find() — PyUnicode\_FindChar() - PyUnicode Format() — PyUnicode\_FromEncodedObject() — PyUnicode FromFormat() — PyUnicode\_FromFormatV() - PyUnicode FromObject() — PyUnicode\_FromOrdinal() - PyUnicode FromString() — PyUnicode FromStringAndSize() — PyUnicode FromWideChar() — PyUnicode\_GetDefaultEncoding() — PyUnicode\_GetLength() - PyUnicode\_GetSize() — PyUnicode\_InternFromString() — PyUnicode\_InternImmortal() — PyUnicode\_InternInPlace() - PyUnicode\_IsIdentifier() — PyUnicode\_Join() — PyUnicode Partition() — PyUnicode\_RPartition() - PyUnicode RSplit() — PyUnicode\_ReadChar() - PyUnicode\_Replace() — PyUnicode\_Resize() — PyUnicode RichCompare() - PyUnicode Split() - PyUnicode Splitlines() — PyUnicode\_Substring() — PyUnicode\_Tailmatch() - PyUnicode\_Translate() — PyUnicode\_Type — PyUnicode\_WriteChar() - PyVarObject - PyVarObject.ob\_base - PyVarObject.ob\_size — PyWeakReference — PyWeakref\_GetObject() — PyWeakref NewProxy()

```
— PyWeakref_NewRef()
- PyWrapperDescr_Type
— PyWrapper_New()
— PyZip_Type
— Py_AddPendingCall()
- Py_AtExit()
- Py BEGIN ALLOW THREADS
— Py_BLOCK_THREADS
— Py_BuildValue()
— Py_BytesMain()
— Py_CompileString()
— Py_DecRef()
— Py_DecodeLocale()
- Py_END_ALLOW_THREADS
— Py_EncodeLocale()
— Py_EndInterpreter()
- Py_EnterRecursiveCall()
- Pv Exit()
— Py_FatalError()
— Py_FileSystemDefaultEncodeErrors
— Py_FileSystemDefaultEncoding
— Py_Finalize()
— Py_FinalizeEx()
— Py_GenericAlias()
— Py_GenericAliasType
— Py_GetBuildInfo()
— Py_GetCompiler()
— Py_GetCopyright()
— Py_GetExecPrefix()
— Py_GetPath()
— Py_GetPlatform()
— Py_GetPrefix()
— Py_GetProgramFullPath()
— Py_GetProgramName()
— Py_GetPythonHome()
— Py_GetRecursionLimit()
- Py GetVersion()
- Py_HasFileSystemDefaultEncoding
— Py_IncRef()
— Py_Initialize()
— Py_InitializeEx()
— Py_Is()
— Py_IsFalse()
- Py_IsInitialized()
— Py_IsNone()
— Py_IsTrue()
— Py_LeaveRecursiveCall()
— Py_Main()
— Py_MakePendingCalls()
— Py_NewInterpreter()
— Py_NewRef()
— Py_ReprEnter()
— Py_ReprLeave()
— Py_SetPath()
```

- Py\_SetProgramName()
- Py\_SetPythonHome()
- Py\_SetRecursionLimit()
- *Py\_UCS4*
- Py\_UNBLOCK\_THREADS
- Py\_UTF8Mode
- Py\_VaBuildValue()
- Py\_Version
- Py\_XNewRef()
- Py\_buffer
- Py\_intptr\_t
- Py\_ssize\_t
- Py\_uintptr\_t
- allocfunc
- binaryfunc
- descraptfunc
- descrsetfunc
- destructor
- getattrfunc
- getattrofunc
- getiterfunc
- getter
- hashfunc
- initproc
- inquiry
- iternextfunc
- lenfunc
- newfunc
- objobjargproc
- objobjproc
- reprfunc
- richcmpfunc
- setattrfunc
- setattrofunc
- setter
- ssizeargfunc
- ssizeobjargproc
- ssizessizeargfunc
- ssizessizeobjargproc
- symtable
- ternaryfunc
- traverseproc
- unaryfunc
- visitproc

# The Very High Level Layer

The functions in this chapter will let you execute Python source code given in a file or a buffer, but they will not let you interact in a more detailed way with the interpreter.

Several of these functions accept a start symbol from the grammar as a parameter. The available start symbols are Py\_eval\_input, Py\_file\_input, and Py\_single\_input. These are described following the functions which accept them as parameters.

Note also that several of these functions take FILE\* parameters. One particular issue which needs to be handled carefully is that the FILE structure for different C libraries can be different and incompatible. Under Windows (at least), it is possible for dynamically linked extensions to actually use different libraries, so care should be taken that FILE\* parameters are only passed to these functions if it is certain that they were created by the same library that the Python runtime is using.

#### int **Py\_Main** (int argc, wchar\_t \*\*argv)

Part of the Stable ABI. The main program for the standard interpreter. This is made available for programs which embed Python. The argc and argv parameters should be prepared exactly as those which are passed to a C program's main() function (converted to wchar\_t according to the user's locale). It is important to note that the argument list may be modified (but the contents of the strings pointed to by the argument list are not). The return value will be 0 if the interpreter exits normally (i.e., without an exception), 1 if the interpreter exits due to an exception, or 2 if the parameter list does not represent a valid Python command line.

Note that if an otherwise unhandled SystemExit is raised, this function will not return 1, but exit the process, as long as Py\_InspectFlag is not set.

# int **Py\_BytesMain** (int argc, char \*\*argv)

*Part of the* Stable ABI *since version 3.8.* Similar to *Py\_Main()* but *argv* is an array of bytes strings. Nouveau dans la version 3.8.

### int **PyRun\_AnyFile** (FILE \*fp, const char \*filename)

This is a simplified interface to PyRun\_AnyFileExFlags() below, leaving *closeit* set to 0 and *flags* set to NULL.

### int PyRun\_AnyFileFlags (FILE \*fp, const char \*filename, PyCompilerFlags \*flags)

This is a simplified interface to PyRun\_AnyFileExFlags() below, leaving the *closeit* argument set to 0.

### int PyRun\_AnyFileEx (FILE \*fp, const char \*filename, int closeit)

This is a simplified interface to PyRun\_AnyFileExFlags () below, leaving the flags argument set to NULL.

## int PyRun\_AnyFileExFlags (FILE \*fp, const char \*filename, int closeit, PyCompilerFlags \*flags)

If fp refers to a file associated with an interactive device (console or terminal input or Unix pseudo-terminal), return the value of  $PyRun\_InteractiveLoop()$ , otherwise return the result of  $PyRun\_SimpleFile()$ . filename is decoded from the filesystem encoding (sys.getfilesystemencoding()). If filename is NULL, this function uses "???" as the filename. If closeit is true, the file is closed before  $PyRun\_SimpleFileExFlags()$  returns.

### int PyRun\_SimpleString (const char \*command)

This is a simplified interface to PyRun\_SimpleStringFlags() below, leaving the PyCompilerFlags\* argument set to NULL.

## int PyRun\_SimpleStringFlags (const char \*command, PyCompilerFlags \*flags)

Executes the Python source code from *command* in the \_\_main\_\_ module according to the *flags* argument. If \_\_main\_\_ does not already exist, it is created. Returns 0 on success or -1 if an exception was raised. If there was an error, there is no way to get the exception information. For the meaning of *flags*, see below.

Note that if an otherwise unhandled SystemExit is raised, this function will not return -1, but exit the process, as long as Py\_InspectFlag is not set.

## int PyRun\_SimpleFile (FILE \*fp, const char \*filename)

This is a simplified interface to PyRun\_SimpleFileExFlags() below, leaving closeit set to 0 and flags set to NULL.

### int PyRun\_SimpleFileEx (FILE \*fp, const char \*filename, int closeit)

This is a simplified interface to PyRun\_SimpleFileExFlags() below, leaving flags set to NULL.

### int PyRun SimpleFileExFlags (FILE \*fp, const char \*filename, int closeit, PyCompilerFlags \*flags)

Similar to PyRun\_SimpleStringFlags(), but the Python source code is read from fp instead of an inmemory string. filename should be the name of the file, it is decoded from filesystem encoding and error handler. If closeit is true, the file is closed before PyRun\_SimpleFileExFlags() returns.

**Note:** On Windows, fp should be opened as binary mode (e.g. fopen (filename, "rb")). Otherwise, Python may not handle script file with LF line ending correctly.

#### int **PyRun\_InteractiveOne** (FILE \*fp, const char \*filename)

This is a simplified interface to PyRun\_InteractiveOneFlags() below, leaving flags set to NULL.

## int PyRun\_InteractiveOneFlags (FILE \*fp, const char \*filename, PyCompilerFlags \*flags)

Read and execute a single statement from a file associated with an interactive device according to the *flags* argument. The user will be prompted using sys.ps1 and sys.ps2. *filename* is decoded from the *filesystem encoding and* error handler.

Returns 0 when the input was executed successfully, -1 if there was an exception, or an error code from the errorde.h include file distributed as part of Python if there was a parse error. (Note that errorde.h is not included by Python.h, so must be included specifically if needed.)

### int **PyRun\_InteractiveLoop** (FILE \*fp, const char \*filename)

This is a simplified interface to PyRun\_InteractiveLoopFlags() below, leaving flags set to NULL.

## int PyRun\_InteractiveLoopFlags (FILE \*fp, const char \*filename, PyCompilerFlags \*flags)

Read and execute statements from a file associated with an interactive device until EOF is reached. The user will be prompted using sys.ps1 and sys.ps2. *filename* is decoded from the *filesystem encoding and error handler*. Returns 0 at EOF or a negative number upon failure.

#### int (\*PyOS\_InputHook)(void)

Part of the Stable ABI. Can be set to point to a function with the prototype int func (void). The function will be called when Python's interpreter prompt is about to become idle and wait for user input from the terminal. The return value is ignored. Overriding this hook can be used to integrate the interpreter's prompt with other event loops, as done in the Modules/\_tkinter.c in the Python source code.

### char \*(\*PyOS\_ReadlineFunctionPointer)(FILE\*, FILE\*, const char\*)

Can be set to point to a function with the prototype char \*func(FILE \*stdin, FILE \*stdout, char \*prompt), overriding the default function used to read a single line of input at the interpreter's prompt. The function is expected to output the string *prompt* if it's not NULL, and then read a line of input from the provided standard input file, returning the resulting string. For example, The readline module sets this hook to provide line-editing and tab-completion features.

The result must be a string allocated by <code>PyMem\_RawMalloc()</code> or <code>PyMem\_RawRealloc()</code>, or <code>NULL</code> if an error occurred.

Modifié dans la version 3.4 : The result must be allocated by PyMem\_RawMalloc() or PyMem RawRealloc(), instead of being allocated by PyMem Malloc() or PyMem Realloc().

*PyObject* \***PyRun\_String** (const char \*str, int start, *PyObject* \*globals, *PyObject* \*locals)

Return value: New reference. This is a simplified interface to PyRun\_StringFlags() below, leaving flags set to NULL.

PyObject \*PyRun\_StringFlags (const char \*str, int start, PyObject \*globals, PyObject \*locals, PyCompilerFlags \*flags)

Return value: New reference. Execute Python source code from str in the context specified by the objects globals and locals with the compiler flags specified by flags. globals must be a dictionary; locals can be any object that implements the mapping protocol. The parameter start specifies the start token that should be used to parse the source code.

Returns the result of executing the code as a Python object, or NULL if an exception was raised.

- PyObject \*PyRun\_File (FILE \*fp, const char \*filename, int start, PyObject \*globals, PyObject \*locals)

  Return value: New reference. This is a simplified interface to PyRun\_FileExFlags() below, leaving closeit set to 0 and flags set to NULL.
- PyObject \*PyRun\_FileEx (FILE \*fp, const char \*filename, int start, PyObject \*globals, PyObject \*locals, int closeit)

  Return value: New reference. This is a simplified interface to PyRun\_FileExFlags() below, leaving flags set to NULL.
- PyObject \*PyRun\_FileFlags (FILE \*fp, const char \*filename, int start, PyObject \*globals, PyObject \*locals, PyCompilerFlags \*flags)

Return value: New reference. This is a simplified interface to PyRun\_FileExFlags() below, leaving closeit set to 0.

PyObject \*PyRun\_FileExFlags (FILE \*fp, const char \*filename, int start, PyObject \*globals, PyObject \*locals, int closeit, PyCompilerFlags \*flags)

Return value: New reference. Similar to PyRun\_StringFlags(), but the Python source code is read from fp instead of an in-memory string. filename should be the name of the file, it is decoded from the filesystem encoding and error handler. If closeit is true, the file is closed before PyRun FileExFlags() returns.

*PyObject* \***Py\_CompileString** (const char \*str, const char \*filename, int start)

Return value: New reference. Part of the Stable ABI. This is a simplified interface to Py\_CompileStringFlags() below, leaving flags set to NULL.

PyObject \*Py\_CompileStringFlags (const char \*str, const char \*filename, int start, PyCompilerFlags \*flags)

Return value: New reference. This is a simplified interface to Py\_CompileStringExFlags() below, with optimize set to -1.

PyObject \*Py\_CompileStringObject (const char \*str, PyObject \*filename, int start, PyCompilerFlags \*flags, int optimize)

Return value: New reference. Parse and compile the Python source code in str, returning the resulting code object. The start token is given by start; this can be used to constrain the code which can be compiled and should be Py\_eval\_input, Py\_file\_input, or Py\_single\_input. The filename specified by filename is used to construct the code object and may appear in tracebacks or SyntaxError exception messages. This returns NULL if the code cannot be parsed or compiled.

The integer *optimize* specifies the optimization level of the compiler; a value of -1 selects the optimization level of the interpreter as given by -0 options. Explicit levels are 0 (no optimization; \_\_debug\_\_ is true), 1 (asserts are removed, \_\_debug\_\_ is false) or 2 (docstrings are removed too).

Nouveau dans la version 3.4.

PyObject \*Py\_CompileStringExFlags (const char \*str, const char \*filename, int start, PyCompilerFlags \*flags, int optimize)

Return value: New reference. Like Py\_CompileStringObject(), but filename is a byte string decoded from the filesystem encoding and error handler.

Nouveau dans la version 3.2.

```
PyObject *PyEval_EvalCode (PyObject *co, PyObject *globals, PyObject *locals)
```

Return value: New reference. Part of the Stable ABI. This is a simplified interface to PyEval\_EvalCodeEx(), with just the code object, and global and local variables. The other arguments are set to NULL.

PyObject \*PyEval\_EvalCodeEx (PyObject \*co, PyObject \*globals, PyObject \*locals, PyObject \*const \*args, int argcount, PyObject \*const \*kws, int kwcount, PyObject \*const \*defs, int defcount, PyObject \*kwdefs, PyObject \*closure)

Return value: New reference. Part of the Stable ABI. Evaluate a precompiled code object, given a particular environment for its evaluation. This environment consists of a dictionary of global variables, a mapping object of local variables, arrays of arguments, keywords and defaults, a dictionary of default values for keyword-only arguments and a closure tuple of cells.

### PyObject \*PyEval\_EvalFrame (PyFrameObject \*f)

*Return value : New reference. Part of the* Stable ABI. Evaluate an execution frame. This is a simplified interface to *PyEval EvalFrameEx()*, for backward compatibility.

### PyObject \*PyEval\_EvalFrameEx (PyFrameObject \*f, int throwflag)

Return value: New reference. Part of the Stable ABI. This is the main, unvarnished function of Python interpretation. The code object associated with the execution frame f is executed, interpreting bytecode and executing calls as needed. The additional throwflag parameter can mostly be ignored - if true, then it causes an exception to immediately be thrown; this is used for the throw() methods of generator objects.

Modifié dans la version 3.4 : Cette fonction inclut maintenant une assertion de débogage afin d'assurer qu'elle ne passe pas sous silence une exception active.

### int PyEval\_MergeCompilerFlags (PyCompilerFlags \*cf)

This function changes the flags of the current evaluation frame, and returns true on success, false on failure.

### int Py eval input

The start symbol from the Python grammar for isolated expressions; for use with Py\_CompileString().

### int Py\_file\_input

The start symbol from the Python grammar for sequences of statements as read from a file or other source; for use with <code>Py\_CompileString()</code>. This is the symbol to use when compiling arbitrarily long Python source code.

## int Py\_single\_input

The start symbol from the Python grammar for a single statement; for use with Py\_CompileString(). This is the symbol used for the interactive interpreter loop.

### struct PyCompilerFlags

This is the structure used to hold compiler flags. In cases where code is only being compiled, it is passed as int flags, and in cases where code is being executed, it is passed as PyCompilerFlags \*flags. In this case, from \_\_future\_\_ import can modify flags.

Whenever PyCompilerFlags \*flags is NULL, cf\_flags is treated as equal to 0, and any modification due to from \_\_future\_\_ import is discarded.

### int cf\_flags

Compiler flags.

### int cf\_feature\_version

cf\_feature\_version is the minor Python version. It should be initialized to PY\_MINOR\_VERSION.

The field is ignored by default, it is used if and only if PyCF\_ONLY\_AST flag is set in *cf\_flags*.

Modifié dans la version 3.8 : Added *cf\_feature\_version* field.

## int CO\_FUTURE\_DIVISION

This bit can be set in *flags* to cause division operator / to be interpreted as "true division" according to **PEP 238**.

# CHAPITRE 4

# Reference Counting

Les macros dans cette section permettent de gérer le compteur de références des objets Python.

```
void Py_INCREF (PyObject *o)
```

Incrémente le compteur de références de l'objet o.

Cette fonction est souvent utilisée pour convertir une *référence empruntée* en une *référence forte sur place*. La fonction  $Py\_NewRef$  () peut être utilisée pour créer une nouvelle *référence forte*.

L'objet ne doit pas être NULL, la fonction Py\_XINCREF () doit être utilisée s'il est possible qu'il soit NULL.

```
void Py_XINCREF (PyObject *o)
```

Incrémente le compteur de références de l'objet o. La macro n'a pas d'effet si l'objet est NULL.

Voir aussi Py\_XNewRef().

```
PyObject *Py_NewRef (PyObject *o)
```

Part of the Stable ABI since version 3.10. Créer une nouvelle référence forte d'un objet : incrémente le compteur de référence de l'objet o et renvoie l'objet o.

Py\_DECREF () doit être appelée quand la référence forte n'est plus utilisée pour décrémenter le compteur de références de l'objet.

L'objet o ne doit pas être NULL et la fonction  $Py\_XNewRef()$  doit être utilisée si o peut être NULL.

Par exemple:

```
Py_INCREF(obj);
self->attr = obj;
```

### peut s'écrire :

```
self->attr = Py_NewRef(obj);
```

Voir aussi Py\_INCREF().

Nouveau dans la version 3.10.

### PyObject \*Py\_XNewRef (PyObject \*o)

Part of the Stable ABI since version 3.10. Semblable à Py\_NewRef() mais l'objet o peut être NULL.

Cette fonction renvoie NULL si l'objet o est NULL.

Nouveau dans la version 3.10.

### void **Py\_DECREF** (*PyObject* \*o)

Décrémente le compteur de références de l'objet o.

Si le compteur de références atteint zéro, la fonction de dés-allocation du type de l'objet (qui ne doit pas être NULL) est invoquée.

Cette fonction est généralement utilisée pour supprimer une *référence forte* avant qu'elle ne soit plus accessible. L'objet en argument ne doit pas être NULL. Py XDECREF () doit être utilisée si l'objet peut être NULL.

**Avertissement :** La fonction de dés-allocation peut invoquer du code Python arbitraire (par exemple quand une instance d'une classe avec une méthode \_\_\_del\_\_\_() est supprimée). Le code exécuté a accès à toutes les variables Python globales mais les exceptions lors de l'exécution de ce code ne sont pas propagées. Tous les objets qui peuvent être atteints à partir d'une variable globale doivent être dans un état cohérent avant d'appeler  $Py\_DECREF()$ . Par exemple le code pour supprimer un élément d'une liste doit copier une référence à l'objet dans une variable temporaire, mettre à jour la liste, et enfin appeler  $Py\_DECREF()$  avec la variable temporaire.

### void Py\_XDECREF (PyObject \*o)

Décrémente le compteur de références de l'objet o. L'objet peut être NULL, dans ce cas la macro n'a pas d'effet. Dans le cas contraire le comportement est identique à Py\_DECREF () et les mêmes avertissements sont de rigueur.

### void Py\_CLEAR (PyObject \*o)

Décrémente le compteur de références de l'objet o. L'objet peut être NULL, dans ce cas la macro n'a pas d'effet. Dans le cas contraire le comportement est identique à  $Py\_DECREF$  (), puis l'argument est mis à NULL. L'avertissement au sujet de l'objet passé en argument à  $Py\_DECREF$  () ne s'applique pas car la macro utilise une variable temporaire et met l'objet à NULL avant de décrémenter le compteur de références.

Il est recommandé d'utiliser cette macro lorsqu'on décrémente le compteur de référence d'un objet qui peut être parcouru par le ramasse-miette.

### void Py\_IncRef (PyObject \*o)

Part of the Stable ABI. Incrémente le compteur de références de l'objet o. C'est la version fonctionnelle de Py\_XINCREF (). Elle peut être utilisée lorsque Python est embarqué dynamiquement dans une application.

## void Py\_DecRef (PyObject \*o)

Part of the Stable ABI. Décrémente le compteur de références de l'objet o. C'est la version fonctionnelle de Py\_XDECREF (). Elle peut être utilisée lorsque Python est embarqué dynamiquement dans une application.

Les fonctions ou macros suivantes doivent être uniquement utilisées au sein de l'interpréteur et ne font pas partie de l'API publique: \_Py\_Dealloc(), \_Py\_ForgetReference(), \_Py\_NewReference(), ainsi que la variable globale \_Py\_RefTotal.

# CHAPITRE 5

# Gestion des exceptions

The functions described in this chapter will let you handle and raise Python exceptions. It is important to understand some of the basics of Python exception handling. It works somewhat like the POSIX errno variable: there is a global indicator (per thread) of the last error that occurred. Most C API functions don't clear this on success, but will set it to indicate the cause of the error on failure. Most C API functions also return an error indicator, usually NULL if they are supposed to return a pointer, or -1 if they return an integer (exception: the PyArg\_\* functions return 1 for success and 0 for failure).

Concretely, the error indicator consists of three object pointers: the exception's type, the exception's value, and the traceback object. Any of those pointers can be <code>NULL</code> if non-set (although some combinations are forbidden, for example you can't have a non-<code>NULL</code> traceback if the exception type is <code>NULL</code>).

When a function must fail because some function it called failed, it generally doesn't set the error indicator; the function it called already set it. It is responsible for either handling the error and clearing the exception or returning after cleaning up any resources it holds (such as object references or memory allocations); it should *not* continue normally if it is not prepared to handle the error. If returning due to an error, it is important to indicate to the caller that an error has been set. If the error is not handled or carefully propagated, additional calls into the Python/C API may not behave as intended and may fail in mysterious ways.

**Note:** The error indicator is **not** the result of sys.exc\_info(). The former corresponds to an exception that is not yet caught (and is therefore still propagating), while the latter returns an exception after it is caught (and has therefore stopped propagating).

# 5.1 Printing and clearing

```
void PyErr_Clear()
```

Part of the Stable ABI. Clear the error indicator. If the error indicator is not set, there is no effect.

```
void PyErr_PrintEx (int set_sys_last_vars)
```

Part of the Stable ABI. Print a standard traceback to sys.stderr and clear the error indicator. Unless the error is a SystemExit, in that case no traceback is printed and the Python process will exit with the error code specified by the SystemExit instance.

Call this function **only** when the error indicator is set. Otherwise it will cause a fatal error!

If *set\_sys\_last\_vars* is nonzero, the variables sys.last\_type, sys.last\_value and sys.last\_traceback will be set to the type, value and traceback of the printed exception, respectively.

```
void PyErr_Print()
```

Part of the Stable ABI. Alias for PyErr\_PrintEx (1).

```
void PyErr_WriteUnraisable (PyObject *obj)
```

Part of the Stable ABI. Call sys.unraisablehook () using the current exception and obj argument.

This utility function prints a warning message to sys.stderr when an exception has been set but it is impossible for the interpreter to actually raise the exception. It is used, for example, when an exception occurs in an \_\_del\_\_() method.

The function is called with a single argument *obj* that identifies the context in which the unraisable exception occurred. If possible, the repr of *obj* will be printed in the warning message.

An exception must be set when calling this function.

# 5.2 Lever des exceptions

These functions help you set the current thread's error indicator. For convenience, some of these functions will always return a NULL pointer for use in a return statement.

```
void PyErr_SetString (PyObject *type, const char *message)
```

Part of the Stable ABI. This is the most common way to set the error indicator. The first argument specifies the exception type; it is normally one of the standard exceptions, e.g. PyExc\_RuntimeError. You need not increment its reference count. The second argument is an error message; it is decoded from 'utf-8'.

```
void PyErr_SetObject (PyObject *type, PyObject *value)
```

Part of the Stable ABI. This function is similar to  $PyErr\_SetString()$  but lets you specify an arbitrary Python object for the "value" of the exception.

```
PyObject *PyErr_Format (PyObject *exception, const char *format, ...)
```

Return value: Always NULL. Part of the Stable ABI. This function sets the error indicator and returns NULL. exception should be a Python exception class. The format and subsequent parameters help format the error message; they have the same meaning and values as in PyUnicode\_FromFormat(). format is an ASCII-encoded string.

```
PyObject *PyErr_FormatV (PyObject *exception, const char *format, va_list vargs)
```

Return value: Always NULL. Part of the Stable ABI since version 3.5. Same as PyErr\_Format(), but taking a value is targument rather than a variable number of arguments.

Nouveau dans la version 3.5.

```
void PyErr_SetNone (PyObject *type)
```

Part of the Stable ABI. This is a shorthand for PyErr\_SetObject (type, Py\_None).

#### int PyErr BadArgument()

Part of the Stable ABI. This is a shorthand for PyErr\_SetString (PyExc\_TypeError, message), where message indicates that a built-in operation was invoked with an illegal argument. It is mostly for internal use.

### PyObject \*PyErr\_NoMemory()

Return value: Always NULL. Part of the Stable ABI. This is a shorthand for PyErr\_SetNone(PyExc\_MemoryError); it returns NULL so an object allocation function can write return PyErr\_NoMemory(); when it runs out of memory.

### PyObject \*PyErr\_SetFromErrno (PyObject \*type)

Return value: Always NULL. Part of the Stable ABI. This is a convenience function to raise an exception when a C library function has returned an error and set the C variable errno. It constructs a tuple object whose first item is the integer errno value and whose second item is the corresponding error message (gotten from strerror()), and then calls PyErr\_SetObject(type, object). On Unix, when the errno value is EINTR, indicating an interrupted system call, this calls PyErr\_CheckSignals(), and if that set the error indicator, leaves it set to that. The function always returns NULL, so a wrapper function around a system call can write return PyErr\_SetFromErrno(type); when the system call returns an error.

### PyObject \*PyErr\_SetFromErrnoWithFilenameObject (PyObject \*type, PyObject \*filenameObject)

Return value: Always NULL. Part of the Stable ABI. Similar to PyErr\_SetFromErrno(), with the additional behavior that if filenameObject is not NULL, it is passed to the constructor of type as a third parameter. In the case of OSError exception, this is used to define the filename attribute of the exception instance.

# PyObject \*PyErr\_SetFromErrnoWithFilenameObjects (PyObject \*type, PyObject \*filenameObject, PyObject \*filenameObject2)

Return value: Always NULL. Part of the Stable ABI since version 3.7. Similar to PyErr\_SetFromErrnoWithFilenameObject(), but takes a second filename object, for raising errors when a function that takes two filenames fails.

Nouveau dans la version 3.4.

### PyObject \*PyErr\_SetFromErrnoWithFilename (PyObject \*type, const char \*filename)

Return value: Always NULL. Part of the Stable ABI. Similar to PyErr\_SetFromErrnoWithFilenameObject(), but the filename is given as a C string. filename is decoded from the filesystem encoding and error handler.

### PyObject \*PyErr\_SetFromWindowsErr (int ierr)

Return value: Always NULL. Part of the Stable ABI on Windows since version 3.7. This is a convenience function to raise WindowsError. If called with ierr of 0, the error code returned by a call to GetLastError() is used instead. It calls the Win32 function FormatMessage() to retrieve the Windows description of error code given by ierr or GetLastError(), then it constructs a tuple object whose first item is the ierr value and whose second item is the corresponding error message (gotten from FormatMessage()), and then calls PyErr\_SetObject(PyExc\_WindowsError, object). This function always returns NULL.

Disponibilité : Windows.

### PyObject \*PyErr\_SetExcFromWindowsErr (PyObject \*type, int ierr)

Return value: Always NULL. Part of the Stable ABI on Windows since version 3.7. Similar to  $PyErr\_SetFromWindowsErr()$ , with an additional parameter specifying the exception type to be raised.

Disponibilité: Windows.

### PyObject \*PyErr\_SetFromWindowsErrWithFilename (int ierr, const char \*filename)

Return value: Always NULL. Part of the Stable ABI on Windows since version 3.7. Similar to PyErr\_SetFromWindowsErrWithFilenameObject(), but the filename is given as a C string. filename is decoded from the filesystem encoding (os.fsdecode()).

Disponibilité: Windows.

# PyObject \*PyErr\_SetExcFromWindowsErrWithFilenameObject (PyObject \*type, int ierr, PyObject \*filename)

Return value: Always NULL. Part of the Stable ABI on Windows since version 3.7. Similar to PyErr\_SetFromWindowsErrWithFilenameObject(), with an additional parameter specifying the exception type to be raised.

Disponibilité: Windows.

# PyObject \*PyErr\_SetExcFromWindowsErrWithFilenameObjects (PyObject \*type, int ierr, PyObject \*filename, PyObject \*filename2)

Return value: Always NULL. Part of the Stable ABI on Windows since version 3.7. Similar to PyErr\_SetExcFromWindowsErrWithFilenameObject(), but accepts a second filename object.

Disponibilité: Windows.

Nouveau dans la version 3.4.

### PyObject \*PyErr\_SetExcFromWindowsErrWithFilename (PyObject \*type, int ierr, const char \*filename)

Return value: Always NULL. Part of the Stable ABI on Windows since version 3.7. Similar to PyErr\_SetFromWindowsErrWithFilename(), with an additional parameter specifying the exception type to be raised.

Disponibilité: Windows.

## PyObject \*PyErr\_SetImportError (PyObject \*msg, PyObject \*name, PyObject \*path)

Return value: Always NULL. Part of the Stable ABI since version 3.7. This is a convenience function to raise ImportError. msg will be set as the exception's message string. name and path, both of which can be NULL, will be set as the ImportError's respective name and path attributes.

Nouveau dans la version 3.3.

# PyObject \*PyErr\_SetImportErrorSubclass (PyObject \*exception, PyObject \*msg, PyObject \*name, PyObject \*path)

Return value: Always NULL. Part of the Stable ABI since version 3.6. Much like PyErr\_SetImportError() but this function allows for specifying a subclass of ImportError to raise.

Nouveau dans la version 3.6.

### void PyErr\_SyntaxLocationObject (PyObject \*filename, int lineno, int col\_offset)

Set file, line, and offset information for the current exception. If the current exception is not a SyntaxError, then it sets additional attributes, which make the exception printing subsystem think the exception is a SyntaxError. Nouveau dans la version 3.4.

## void PyErr\_SyntaxLocationEx (const char \*filename, int lineno, int col\_offset)

Part of the Stable ABI since version 3.7. Like PyErr\_SyntaxLocationObject(), but filename is a byte string decoded from the filesystem encoding and error handler.

Nouveau dans la version 3.2.

## void PyErr\_SyntaxLocation (const char \*filename, int lineno)

Part of the Stable ABI. Like PyErr\_SyntaxLocationEx(), but the col\_offset parameter is omitted.

### void PyErr\_BadInternalCall()

Part of the Stable ABI. This is a shorthand for PyErr\_SetString (PyExc\_SystemError, message), where message indicates that an internal operation (e.g. a Python/C API function) was invoked with an illegal argument. It is mostly for internal use.

# 5.3 Issuing warnings

Use these functions to issue warnings from C code. They mirror similar functions exported by the Python warnings module. They normally print a warning message to *sys.stderr*; however, it is also possible that the user has specified that warnings are to be turned into errors, and in that case they will raise an exception. It is also possible that the functions raise an exception because of a problem with the warning machinery. The return value is 0 if no exception is raised, or -1 if an exception is raised. (It is not possible to determine whether a warning message is actually printed, nor what the reason is for the exception; this is intentional.) If an exception is raised, the caller should do its normal exception handling (for example,  $P_{Y\_DECREF}()$ ) owned references and return an error value).

```
int PyErr_WarnEx (PyObject *category, const char *message, Py_ssize_t stack_level)
```

Part of the Stable ABI. Issue a warning message. The category argument is a warning category (see below) or NULL; the message argument is a UTF-8 encoded string. stack\_level is a positive number giving a number of stack frames; the warning will be issued from the currently executing line of code in that stack frame. A stack\_level of 1 is the function calling PyErr\_WarnEx(), 2 is the function above that, and so forth.

Warning categories must be subclasses of PyExc\_Warning; PyExc\_Warning is a subclass of PyExc\_Exception; the default warning category is PyExc\_RuntimeWarning. The standard Python warning categories are available as global variables whose names are enumerated at *Standard Warning Categories*.

For information about warning control, see the documentation for the warnings module and the -W option in the command line documentation. There is no C API for warning control.

```
int PyErr_WarnExplicitObject (PyObject *category, PyObject *message, PyObject *filename, int lineno, PyObject *module, PyObject *registry)
```

Issue a warning message with explicit control over all warning attributes. This is a straightforward wrapper around the Python function warnings.warn\_explicit(); see there for more information. The *module* and *registry* arguments may be set to NULL to get the default effect described there.

Nouveau dans la version 3.4.

int **PyErr\_WarnExplicit** (*PyObject* \*category, const char \*message, const char \*filename, int lineno, const char \*module, *PyObject* \*registry)

Part of the Stable ABI. Similar to PyErr\_WarnExplicitObject() except that message and module are UTF-8 encoded strings, and filename is decoded from the filesystem encoding and error handler.

```
int PyErr WarnFormat (PyObject *category, Py ssize t stack level, const char *format, ...)
```

Part of the Stable ABI. Function similar to PyErr\_WarnEx(), but use PyUnicode\_FromFormat() to format the warning message. format is an ASCII-encoded string.

Nouveau dans la version 3.2.

int PyErr\_ResourceWarning (PyObject \*source, Py\_ssize\_t stack\_level, const char \*format, ...)

Part of the Stable ABI since version 3.6. Function similar to PyErr\_WarnFormat(), but category is ResourceWarning and it passes source to warnings.WarningMessage().

Nouveau dans la version 3.6.

# 5.4 Querying the error indicator

```
PyObject *PyErr_Occurred()
```

Return value: Borrowed reference. Part of the Stable ABI. Test whether the error indicator is set. If set, return the exception type (the first argument to the last call to one of the PyErr\_Set\* functions or to  $PyErr_Restore()$ ). If not set, return NULL. You do not own a reference to the return value, so you do not need to  $Py_DECREF()$  it. The caller must hold the GIL.

**Note:** Do not compare the return value to a specific exception; use <code>PyErr\_ExceptionMatches()</code> instead, shown below. (The comparison could easily fail since the exception may be an instance instead of a class, in the case of a class exception, or it may be a subclass of the expected exception.)

### int PyErr\_ExceptionMatches (PyObject \*exc)

Part of the Stable ABI. Equivalent to PyErr\_GivenExceptionMatches (PyErr\_Occurred(), exc). This should only be called when an exception is actually set; a memory access violation will occur if no exception has been raised.

### int PyErr\_GivenExceptionMatches (PyObject \*given, PyObject \*exc)

Part of the Stable ABI. Return true if the given exception matches the exception type in exc. If exc is a class object, this also returns true when given is an instance of a subclass. If exc is a tuple, all exception types in the tuple (and recursively in subtuples) are searched for a match.

```
void PyErr_Fetch (PyObject **ptype, PyObject **pvalue, PyObject **ptraceback)
```

Part of the Stable ABI. Retrieve the error indicator into three variables whose addresses are passed. If the error indicator is not set, set all three variables to NULL. If it is set, it will be cleared and you own a reference to each object retrieved. The value and traceback object may be NULL even when the type object is not.

**Note:** This function is normally only used by code that needs to catch exceptions or by code that needs to save and restore the error indicator temporarily, e.g.:

```
PyObject *type, *value, *traceback;
PyErr_Fetch(&type, &value, &traceback);

/* ... code that might produce other errors ... */
PyErr_Restore(type, value, traceback);
}
```

### void PyErr\_Restore (PyObject \*type, PyObject \*value, PyObject \*traceback)

Part of the Stable ABI. Set the error indicator from the three objects. If the error indicator is already set, it is cleared first. If the objects are NULL, the error indicator is cleared. Do not pass a NULL type and non-NULL value or traceback. The exception type should be a class. Do not pass an invalid exception type or value. (Violating these rules will cause subtle problems later.) This call takes away a reference to each object: you must own a reference to each object before the call and after the call you no longer own these references. (If you don't understand this, don't use this function. I warned you.)

**Note:** This function is normally only used by code that needs to save and restore the error indicator temporarily. Use  $PyErr\_Fetch()$  to save the current error indicator.

```
void PyErr_NormalizeException (PyObject **exc, PyObject **val, PyObject **tb)
```

Part of the Stable ABI. Under certain circumstances, the values returned by <code>PyErr\_Fetch()</code> below can be "unnormalized", meaning that <code>\*exc</code> is a class object but <code>\*val</code> is not an instance of the same class. This function can be used to instantiate the class in that case. If the values are already normalized, nothing happens. The delayed normalization is implemented to improve performance.

**Note:** This function *does not* implicitly set the \_\_traceback\_\_ attribute on the exception value. If setting the traceback appropriately is desired, the following additional snippet is needed:

```
if (tb != NULL) {
   PyException_SetTraceback(val, tb);
}
```

### PyObject \*PyErr\_GetHandledException (void)

Part of the Stable ABI since version 3.11. Retrieve the active exception instance, as would be returned by sys. exception (). This refers to an exception that was *already caught*, not to an exception that was freshly raised. Returns a new reference to the exception or NULL. Does not modify the interpreter's exception state.

**Note:** This function is not normally used by code that wants to handle exceptions. Rather, it can be used when code needs to save and restore the exception state temporarily. Use <code>PyErr\_SetHandledException()</code> to restore or clear the exception state.

Nouveau dans la version 3.11.

### void PyErr\_SetHandledException (PyObject \*exc)

Part of the Stable ABI since version 3.11. Set the active exception, as known from sys.exception(). This refers to an exception that was already caught, not to an exception that was freshly raised. To clear the exception state, pass NULL.

**Note:** This function is not normally used by code that wants to handle exceptions. Rather, it can be used when code needs to save and restore the exception state temporarily. Use <code>PyErr\_GetHandledException()</code> to get the exception state.

Nouveau dans la version 3.11.

```
void PyErr_GetExcInfo (PyObject **ptype, PyObject **pvalue, PyObject **ptraceback)
```

Part of the Stable ABI since version 3.7. Retrieve the old-style representation of the exception info, as known from sys.exc\_info(). This refers to an exception that was already caught, not to an exception that was freshly raised. Returns new references for the three objects, any of which may be NULL. Does not modify the exception info state. This function is kept for backwards compatibility. Prefer using PyErr\_GetHandledException().

**Note:** This function is not normally used by code that wants to handle exceptions. Rather, it can be used when code needs to save and restore the exception state temporarily. Use <code>PyErr\_SetExcInfo()</code> to restore or clear the exception state.

Nouveau dans la version 3.3.

```
void PyErr_SetExcInfo (PyObject *type, PyObject *value, PyObject *traceback)
```

Part of the Stable ABI since version 3.7. Set the exception info, as known from sys.exc\_info(). This refers to an exception that was already caught, not to an exception that was freshly raised. This function steals the references of the arguments. To clear the exception state, pass NULL for all three arguments. This function is kept for backwards compatibility. Prefer using <code>PyErr\_SetHandledException()</code>.

**Note:** This function is not normally used by code that wants to handle exceptions. Rather, it can be used when code needs to save and restore the exception state temporarily. Use  $PyErr\_GetExcInfo()$  to read the exception state.

Nouveau dans la version 3.3.

Modifié dans la version 3.11: The type and traceback arguments are no longer used and can be NULL. The interpreter now derives them from the exception instance (the value argument). The function still steals references of all three arguments.

# 5.5 Traitement des signaux

### int PyErr\_CheckSignals()

Part of the Stable ABI. This function interacts with Python's signal handling.

If the function is called from the main thread and under the main Python interpreter, it checks whether a signal has been sent to the processes and if so, invokes the corresponding signal handler. If the signal module is supported, this can invoke a signal handler written in Python.

The function attempts to handle all pending signals, and then returns 0. However, if a Python signal handler raises an exception, the error indicator is set and the function returns -1 immediately (such that other pending signals may not have been handled yet: they will be on the next <code>PyErr\_CheckSignals()</code> invocation).

If the function is called from a non-main thread, or under a non-main Python interpreter, it does nothing and returns 0.

This function can be called by long-running C code that wants to be interruptible by user requests (such as by pressing Ctrl-C).

Note: The default Python signal handler for SIGINT raises the KeyboardInterrupt exception.

### void PyErr\_SetInterrupt()

Part of the Stable ABI. Simulate the effect of a SIGINT signal arriving. This is equivalent to PyErr SetInterruptEx(SIGINT).

Note: This function is async-signal-safe. It can be called without the GIL and from a C signal handler.

### int PyErr\_SetInterruptEx (int signum)

Part of the Stable ABI since version 3.10. Simulate the effect of a signal arriving. The next time PyErr CheckSignals () is called, the Python signal handler for the given signal number will be called.

This function can be called by C code that sets up its own signal handling and wants Python signal handlers to be invoked as expected when an interruption is requested (for example when the user presses Ctrl-C to interrupt an operation).

If the given signal isn't handled by Python (it was set to signal.SIG\_DFL or signal.SIG\_IGN), it will be ignored.

If signum is outside of the allowed range of signal numbers, -1 is returned. Otherwise, 0 is returned. The error indicator is never changed by this function.

**Note:** This function is async-signal-safe. It can be called without the *GIL* and from a C signal handler.

Nouveau dans la version 3.10.

### int PySignal\_SetWakeupFd (int fd)

This utility function specifies a file descriptor to which the signal number is written as a single byte whenever a signal is received. fd must be non-blocking. It returns the previous such file descriptor.

The value -1 disables the feature; this is the initial state. This is equivalent to signal.set\_wakeup\_fd() in Python, but without any error checking. fd should be a valid file descriptor. The function should only be called from the main thread.

Modifié dans la version 3.5 : On Windows, the function now also supports socket handles.

# 5.6 Exception Classes

### PyObject \*PyErr\_NewException (const char \*name, PyObject \*base, PyObject \*dict)

Return value: New reference. Part of the Stable ABI. This utility function creates and returns a new exception class. The name argument must be the name of the new exception, a C string of the form module.classname. The base and dict arguments are normally NULL. This creates a class object derived from Exception (accessible in C as PyExc Exception).

The \_\_module\_\_ attribute of the new class is set to the first part (up to the last dot) of the *name* argument, and the class name is set to the last part (after the last dot). The *base* argument can be used to specify alternate base classes; it can either be only one class or a tuple of classes. The *dict* argument can be used to specify a dictionary of class variables and methods.

PyObject \*PyErr\_NewExceptionWithDoc (const char \*name, const char \*doc, PyObject \*base, PyObject \*dict)

Return value: New reference. Part of the Stable ABI. Same as PyErr\_NewException(), except that the new exception class can easily be given a docstring: If doc is non-NULL, it will be used as the docstring for the exception class.

Nouveau dans la version 3.2.

# 5.7 Objets exception

### PyObject \*PyException\_GetTraceback (PyObject \*ex)

Return value: New reference. Part of the Stable ABI. Return the traceback associated with the exception as a new reference, as accessible from Python through \_\_traceback\_\_. If there is no traceback associated, this returns NIII.I.

```
int PyException_SetTraceback (PyObject *ex, PyObject *tb)
```

Part of the Stable ABI. Set the traceback associated with the exception to tb. Use Py\_None to clear it.

```
PyObject *PyException_GetContext (PyObject *ex)
```

Return value: New reference. Part of the Stable ABI. Return the context (another exception instance during whose handling ex was raised) associated with the exception as a new reference, as accessible from Python through \_\_context\_\_. If there is no context associated, this returns NULL.

```
void PyException_SetContext (PyObject *ex, PyObject *ctx)
```

*Part of the* Stable ABI. Set the context associated with the exception to *ctx*. Use NULL to clear it. There is no type check to make sure that *ctx* is an exception instance. This steals a reference to *ctx*.

```
PyObject *PyException_GetCause (PyObject *ex)
```

Return value: New reference. Part of the Stable ABI. Return the cause (either an exception instance, or None, set by raise ... from ...) associated with the exception as a new reference, as accessible from Python through \_\_cause\_\_.

```
void PyException_SetCause (PyObject *ex, PyObject *cause)
```

Part of the Stable ABI. Set the cause associated with the exception to cause. Use NULL to clear it. There is no type check to make sure that cause is either an exception instance or None. This steals a reference to cause.

```
__suppress_context__ is implicitly set to True by this function.
```

# 5.8 Objets exception Unicode

```
The following functions are used to create and modify Unicode exceptions from C.
PyObject *PyUnicodeDecodeError Create (const char *encoding, const char *object, Py ssize t length,
                                               Py_ssize_t start, Py_ssize_t end, const char *reason)
     Return value: New reference. Part of the Stable ABI. Create a UnicodeDecodeError object with the attributes
     encoding, object, length, start, end and reason. encoding and reason are UTF-8 encoded strings.
PyObject *PyUnicodeDecodeError_GetEncoding (PyObject *exc)
PyObject *PyUnicodeEncodeError_GetEncoding (PyObject *exc)
     Return value: New reference. Part of the Stable ABI. Return the encoding attribute of the given exception object.
PyObject *PyUnicodeDecodeError_GetObject (PyObject *exc)
PyObject *PyUnicodeEncodeError_GetObject (PyObject *exc)
PyObject *PyUnicodeTranslateError_GetObject (PyObject *exc)
     Return value: New reference. Part of the Stable ABI. Return the object attribute of the given exception object.
int PyUnicodeDecodeError_GetStart (PyObject *exc, Py_ssize_t *start)
int PyUnicodeEncodeError_GetStart (PyObject *exc, Py_ssize_t *start)
int PyUnicodeTranslateError_GetStart (PyObject *exc, Py_ssize_t *start)
     Part of the Stable ABI. Get the start attribute of the given exception object and place it into *start. start must not
     be NULL. Return 0 on success. -1 on failure.
int PyUnicodeDecodeError SetStart (PyObject *exc, Py ssize t start)
int PyUnicodeEncodeError_SetStart (PyObject *exc, Py_ssize_t start)
int PyUnicodeTranslateError_SetStart (PyObject *exc, Py_ssize_t start)
     Part of the Stable ABI. Set the start attribute of the given exception object to start. Return 0 on success, -1 on
     failure.
int PyUnicodeDecodeError_GetEnd (PyObject *exc, Py_ssize_t *end)
int PyUnicodeEncodeError_GetEnd (PyObject *exc, Py_ssize_t *end)
int PyUnicodeTranslateError_GetEnd (PyObject *exc, Py_ssize_t *end)
     Part of the Stable ABI. Get the end attribute of the given exception object and place it into *end. end must not be
     NULL. Return 0 on success, -1 on failure.
int PyUnicodeDecodeError_SetEnd (PyObject *exc, Py_ssize_t end)
int PyUnicodeEncodeError_SetEnd (PyObject *exc, Py_ssize_t end)
int PyUnicodeTranslateError SetEnd (PyObject *exc, Py ssize t end)
     Part of the Stable ABI. Set the end attribute of the given exception object to end. Return 0 on success, -1 on failure.
PyObject *PyUnicodeDecodeError GetReason (PyObject *exc)
PyObject *PyUnicodeEncodeError_GetReason (PyObject *exc)
PyObject *PyUnicodeTranslateError_GetReason (PyObject *exc)
     Return value: New reference. Part of the Stable ABI. Return the reason attribute of the given exception object.
int PyUnicodeDecodeError_SetReason (PyObject *exc, const char *reason)
int PyUnicodeError_SetReason (PyObject *exc, const char *reason)
int PyUnicodeTranslateError_SetReason (PyObject *exc, const char *reason)
     Part of the Stable ABI. Set the reason attribute of the given exception object to reason. Return 0 on success, -1 on
     failure.
```

# 5.9 Contrôle de la récursion

These two functions provide a way to perform safe recursive calls at the C level, both in the core and in extension modules. They are needed if the recursive code does not necessarily invoke Python code (which tracks its recursion depth automatically). They are also not needed for *tp\_call* implementations because the *call protocol* takes care of recursion handling.

### int Py\_EnterRecursiveCall (const char \*where)

Part of the Stable ABI since version 3.9. Marks a point where a recursive C-level call is about to be performed.

If  $USE\_STACKCHECK$  is defined, this function checks if the OS stack overflowed using  $PyOS\_CheckStack$  (). In this is the case, it sets a MemoryError and returns a nonzero value.

The function then checks if the recursion limit is reached. If this is the case, a RecursionError is set and a nonzero value is returned. Otherwise, zero is returned.

where should be a UTF-8 encoded string such as " in instance check" to be concatenated to the RecursionError message caused by the recursion depth limit.

Modifié dans la version 3.9: This function is now also available in the limited API.

#### void Py LeaveRecursiveCall (void)

Part of the Stable ABI since version 3.9. Ends a Py\_EnterRecursiveCall(). Must be called once for each successful invocation of Py\_EnterRecursiveCall().

Modifié dans la version 3.9: This function is now also available in the limited API.

Properly implementing  $tp\_repr$  for container types requires special recursion handling. In addition to protecting the stack,  $tp\_repr$  also needs to track objects to prevent cycles. The following two functions facilitate this functionality. Effectively, these are the C equivalent to reprlib.recursive\\_repr().

#### int Py\_ReprEnter (PyObject \*object)

Part of the Stable ABI. Called at the beginning of the  $tp\_repr$  implementation to detect cycles.

If the object has already been processed, the function returns a positive integer. In that case the  $tp\_repr$  implementation should return a string object indicating a cycle. As examples, dict objects return  $\{\ldots\}$  and list objects return  $[\ldots]$ .

The function will return a negative integer if the recursion limit is reached. In that case the  $tp\_repr$  implementation should typically return NULL.

Otherwise, the function returns zero and the  $tp\_repr$  implementation can continue normally.

### void Py\_ReprLeave (PyObject \*object)

Part of the Stable ABI. Ends a Py\_ReprEnter(). Must be called once for each invocation of Py\_ReprEnter() that returns zero.

# 5.10 Exceptions standards

All standard Python exceptions are available as global variables whose names are PyExc\_ followed by the Python exception name. These have the type PyObject\*; they are all class objects. For completeness, here are all the variables:

Nom C	Nom Python	Notes	
PyExc_BaseException	BaseException	1	
PyExc_Exception	Exception	page 54, 1	
PyExc_ArithmeticError	ArithmeticError	page 54, 1	
PyExc_AssertionError	AssertionError		
PyExc AttributeError	AttributeError		

suite sur la page suivante

Tableau 1 - suite de la page précédente

Nom C	Nom Python	Notes
PyExc_BlockingIOError	BlockingIOError	
PyExc_BrokenPipeError	BrokenPipeError	
PyExc_BufferError	BufferError	
PyExc_ChildProcessError	ChildProcessError	
PyExc_ConnectionAbortedEr	r6pnnectionAbortedError	
PyExc_ConnectionError	ConnectionError	
PyExc_ConnectionRefusedEr	r6pnnectionRefusedError	
PyExc_ConnectionResetErro	rConnectionResetError	
PyExc_EOFError	EOFError	
PyExc_FileExistsError	FileExistsError	
PyExc_FloatingPointError	FileNotFoundError	
PyExc_FloatingPointError	FloatingPointError	
PyExc_GeneratorExit	GeneratorExit	
PyExc_ImportError	ImportError	
PyExc_IndentationError	IndentationError	
PyExc_IndexError	IndexError	
PyExc_InterruptedError	InterruptedError	
PyExc_IsADirectoryError	IsADirectoryError	
PyExc_KeyError	KeyError	
PyExc_KeyboardInterrupt	KeyboardInterrupt	
PyExc_LookupError	LookupError	page 54, 1
PyExc_MemoryError	MemoryError	
PyExc_ModuleNotFoundError	ModuleNotFoundError	
PyExc_NameError	NameError	
PyExc_NotADirectoryError	NotADirectoryError	
PyExc_NotImplementedError	NotImplementedError	
PyExc_OSError	OSError	page 54, 1
PyExc_OverflowError	OverflowError	
PyExc_PermissionError	PermissionError	
PyExc_ProcessLookupError	ProcessLookupError	
PyExc_ReferenceError	RecursionError	
PyExc_ReferenceError	ReferenceError	
PyExc_RuntimeError	RuntimeError	
PyExc_StopAsyncIteration	StopAsyncIteration	
PyExc_StopIteration	StopIteration	
PyExc_SyntaxError	SyntaxError	
PyExc_SystemError	SystemError	
PyExc_SystemExit	SystemExit	
PyExc_TabError	TabError	
PyExc_ImportError	TimeoutError	
PyExc_TypeError	TypeError	
PyExc_UnboundLocalError	UnboundLocalError	
PyExc_UnicodeDecodeError	UnicodeDecodeError	
PyExc_UnicodeEncodeError	UnicodeEncodeError	
PyExc_UnicodeError	UnicodeError	
PyExc_UnicodeTranslateErr		
PyExc_ValueError	ValueError	
PyExc_ZeroDivisionError	ZeroDivisionError	

<sup>1.</sup> C'est la classe de base pour les autres exceptions standards.

Nouveau dans la version 3.3 : PyExc\_BlockingIOError, PyExc\_BrokenPipeError, PyExc\_ChildProcessError, PyExc\_ConnectionError, PyExc\_ConnectionAbortedError, PyExc\_ConnectionRefusedError, PyExc\_ConnectionResetError, PyExc\_FileExistsError, PyExc\_FileNotFoundError, PyExc\_InterruptedError, PyExc\_IsADirectoryError, PyExc\_NotADirectoryError, PyExc\_PermissionError, PyExc\_ProcessLookupError and PyExc\_TimeoutError were introduced following PEP 3151.

Nouveau dans la version 3.5: PyExc\_StopAsyncIteration et PyExc\_RecursionError.

Nouveau dans la version 3.6: PyExc\_ModuleNotFoundError.

These are compatibility aliases to PyExc\_OSError:

Nom C	Notes
PyExc_EnvironmentError	
PyExc_IOError	
PyExc_WindowsError	2

Modifié dans la version 3.3 : These aliases used to be separate exception types.

Notes:

# **5.11 Standard Warning Categories**

All standard Python warning categories are available as global variables whose names are  $PyExc_followed$  by the Python exception name. These have the type PyObject\*; they are all class objects. For completeness, here are all the variables:

Nom C	Nom Python	Notes
PyExc_Warning	Warning	3
PyExc_BytesWarning	BytesWarning	
PyExc_DeprecationWarning	DeprecationWarning	
PyExc_FutureWarning	FutureWarning	
PyExc_ImportWarning	ImportWarning	
PyExc_PendingDeprecationWarning	PendingDeprecationWarning	
PyExc_ResourceWarning	ResourceWarning	
PyExc_RuntimeWarning	RuntimeWarning	
PyExc_SyntaxWarning	SyntaxWarning	
PyExc_UnicodeWarning	UnicodeWarning	
PyExc_UserWarning	UserWarning	

Nouveau dans la version 3.2: PyExc\_ResourceWarning.

Notes:

<sup>2.</sup> Only defined on Windows; protect code that uses this by testing that the preprocessor macro MS\_WINDOWS is defined.

<sup>3.</sup> C'est la classe de base pour les autres catégories de warning.

# CHAPITRE 6

## Utilitaires

Les fonctions de ce chapitre sont utilitaires, certaines aident à rendre le code en C plus portable, d'autres à utiliser des modules Python depuis du C, analyser des arguments de fonctions, ou encore construire des valeurs Python à partir de valeurs C.

# **6.1 Operating System Utilities**

### PyObject \*PyOS\_FSPath (PyObject \*path)

Return value: New reference. Part of the Stable ABI since version 3.6. Return the file system representation for path. If the object is a str or bytes object, then its reference count is incremented. If the object implements the os.PathLike interface, then \_\_fspath\_\_() is returned as long as it is a str or bytes object. Otherwise TypeError is raised and NULL is returned.

Nouveau dans la version 3.6.

### int Py\_FdIsInteractive (FILE \*fp, const char \*filename)

Return true (nonzero) if the standard I/O file fp with name filename is deemed interactive. This is the case for files for which isatty (fileno(fp)) is true. If the global flag  $Py\_InteractiveFlag$  is true, this function also returns true if the filename pointer is NULL or if the name is equal to one of the strings '<stdin>' or '???'.

### void PyOS\_BeforeFork()

Part of the Stable ABI on platforms with fork() since version 3.7. Function to prepare some internal state before a process fork. This should be called before calling fork() or any similar function that clones the current process. Only available on systems where fork() is defined.

**Avertissement:** The C fork () call should only be made from the "main" thread (of the "main" interpreter). The same is true for PyOS\_BeforeFork ().

Nouveau dans la version 3.7.

#### void PyOS\_AfterFork\_Parent()

Part of the Stable ABI on platforms with fork() since version 3.7. Function to update some internal state after a process fork. This should be called from the parent process after calling fork() or any similar function that clones the current process, regardless of whether process cloning was successful. Only available on systems where fork() is defined.

**Avertissement:** The C fork () call should only be made from the "main" thread (of the "main" interpreter). The same is true for  $PyOS\_AfterFork\_Parent$  ().

Nouveau dans la version 3.7.

### void PyOS\_AfterFork\_Child()

Part of the Stable ABI on platforms with fork() since version 3.7. Function to update internal interpreter state after a process fork. This must be called from the child process after calling fork(), or any similar function that clones the current process, if there is any chance the process will call back into the Python interpreter. Only available on systems where fork() is defined.

Avertissement: The C fork () call should only be made from the "main" thread (of the "main" interpreter). The same is true for  $PyOS\_AfterFork\_Child()$ .

Nouveau dans la version 3.7.

#### Voir aussi:

os.register\_at\_fork() allows registering custom Python functions to be called by PyOS\_BeforeFork(), PyOS\_AfterFork\_Parent() and PyOS\_AfterFork\_Child().

#### void PyOS\_AfterFork()

Part of the Stable ABI on platforms with fork(). Function to update some internal state after a process fork; this should be called in the new process if the Python interpreter will continue to be used. If a new executable is loaded into the new process, this function does not need to be called.

Obsolète depuis la version 3.7: This function is superseded by PyOS AfterFork Child().

### int PyOS\_CheckStack()

Part of the Stable ABI on platforms with USE\_STACKCHECK since version 3.7. Return true when the interpreter runs out of stack space. This is a reliable check, but is only available when USE\_STACKCHECK is defined (currently on certain versions of Windows using the Microsoft Visual C++ compiler). USE\_STACKCHECK will be defined automatically; you should never change the definition in your own code.

### PyOS\_sighandler\_t PyOS\_getsig (int i)

Part of the Stable ABI. Return the current signal handler for signal i. This is a thin wrapper around either signation() or signal(). Do not call those functions directly! PyOS\_sighandler\_t is a typedef alias for void (\*)(int).

## PyOS\_sighandler\_t PyOS\_setsig (int i, PyOS\_sighandler\_t h)

Part of the Stable ABI. Set the signal handler for signal i to be h; return the old signal handler. This is a thin wrapper around either signation () or signal (). Do not call those functions directly! PyOS\_sighandler\_t is a typedef alias for void (\*) (int).

### wchar\_t \*Py\_DecodeLocale (const char \*arg, size\_t \*size)

Part of the Stable ABI since version 3.7.

**Avertissement:** This function should not be called directly: use the *PyConfig* API with the *PyConfig\_SetBytesString()* function which ensures that *Python is preinitialized*.

This function must not be called before *Python is preinitialized* and so that the LC\_CTYPE locale is properly configured : see the *Py\_PreInitialize()* function.

Decode a byte string from the *filesystem encoding and error handler*. If the error handler is surrogateescape error handler, undecodable bytes are decoded as characters in range U+DC80..U+DCFF; and if a byte sequence can be decoded as a surrogate character, the bytes are escaped using the surrogateescape error handler instead of decoding them.

Return a pointer to a newly allocated wide character string, use <code>PyMem\_RawFree()</code> to free the memory. If size is not <code>NULL</code>, write the number of wide characters excluding the null character into <code>\*size</code>

Return NULL on decoding error or memory allocation error. If size is not NULL, \*size is set to (size\_t)-1 on memory error or set to (size\_t)-2 on decoding error.

The filesystem encoding and error handler are selected by PyConfig\_Read(): see filesystem\_encoding and filesystem\_errors members of PyConfig.

Decoding errors should never happen, unless there is a bug in the C library.

Use the Py\_EncodeLocale() function to encode the character string back to a byte string.

#### Voir aussi:

 $\begin{tabular}{lll} The & {\it PyUnicode\_DecodeFSDefaultAndSize()} & and & {\it PyUnicode\_DecodeLocaleAndSize()} \\ functions. & \begin{tabular}{lll} And & {\it PyUnicode\_DecodeLocaleAndSize()} \\ \hline \end{tabular} \label{table}$ 

Nouveau dans la version 3.5.

Modifié dans la version 3.7 : The function now uses the UTF-8 encoding in the Python UTF-8 Mode.

Modifié dans la version 3.8 : The function now uses the UTF-8 encoding on Windows if Py\_LegacyWindowsFSEncodingFlag is zero;

### char \*Py\_EncodeLocale (const wchar\_t \*text, size\_t \*error\_pos)

Part of the Stable ABI since version 3.7. Encode a wide character string to the *filesystem encoding and error handler*. If the error handler is surrogateescape error handler, surrogate characters in the range U+DC80..U+DCFF are converted to bytes 0x80..0xFF.

Return a pointer to a newly allocated byte string, use PyMem\_Free() to free the memory. Return NULL on encoding error or memory allocation error.

If error\_pos is not NULL,  $*error_pos$  is set to  $(size_t)-1$  on success, or set to the index of the invalid character on encoding error.

The filesystem encoding and error handler are selected by PyConfig\_Read(): see filesystem\_encoding and filesystem\_errors members of PyConfig.

Use the Py DecodeLocale () function to decode the bytes string back to a wide character string.

**Avertissement :** This function must not be called before *Python is preinitialized* and so that the LC\_CTYPE locale is properly configured : see the *Py\_PreInitialize()* function.

#### Voir aussi:

 $\label{thm:code_encode} \textbf{The } \textit{PyUnicode\_EncodeLocale()} \ \ \textbf{functions.}$ 

Nouveau dans la version 3.5.

Modifié dans la version 3.7: The function now uses the UTF-8 encoding in the Python UTF-8 Mode.

Modifié dans la version 3.8: The function now uses the UTF-8 encoding on Windows if  $Py\_LegacyWindowsFSEncodingFlag$  is zero.

# 6.2 System Functions

These are utility functions that make functionality from the sys module accessible to C code. They all work with the current interpreter thread's sys module's dict, which is contained in the internal thread state structure.

### PyObject \*PySys\_GetObject (const char \*name)

*Return value : Borrowed reference. Part of the* Stable ABI. Return the object *name* from the sys module or NULL if it does not exist, without setting an exception.

### int PySys\_SetObject (const char \*name, PyObject \*v)

*Part of the* Stable ABI. Set *name* in the sys module to v unless v is NULL, in which case *name* is deleted from the sys module. Returns 0 on success, -1 on error.

### void PySys\_ResetWarnOptions()

Part of the Stable ABI. Reset sys.warnoptions to an empty list. This function may be called prior to Py\_Initialize().

### void PySys\_AddWarnOption (const wchar\_t \*s)

Part of the Stable ABI. This API is kept for backward compatibility: setting PyConfig.warnoptions should be used instead, see Python Initialization Configuration.

Append s to sys.warnoptions. This function must be called prior to  $Py\_Initialize()$  in order to affect the warnings filter list.

Obsolète depuis la version 3.11.

### void PySys\_AddWarnOptionUnicode (PyObject \*unicode)

Part of the Stable ABI. This API is kept for backward compatibility: setting PyConfig.warnoptions should be used instead, see Python Initialization Configuration.

Append unicode to sys.warnoptions.

Note: this function is not currently usable from outside the CPython implementation, as it must be called prior to the implicit import of warnings in  $Py\_Initialize()$  to be effective, but can't be called until enough of the runtime has been initialized to permit the creation of Unicode objects.

Obsolète depuis la version 3.11.

### void PySys\_SetPath (const wchar\_t \*path)

Part of the Stable ABI. This API is kept for backward compatibility: setting PyConfig. module\_search\_paths and PyConfig.module\_search\_paths\_set should be used instead, see Python Initialization Configuration.

Set sys.path to a list object of paths found in *path* which should be a list of paths separated with the platform's search path delimiter (: on Unix, ; on Windows).

Obsolète depuis la version 3.11.

### void PySys\_WriteStdout (const char \*format, ...)

Part of the Stable ABI. Write the output string described by format to sys.stdout. No exceptions are raised, even if truncation occurs (see below).

format should limit the total size of the formatted output string to 1000 bytes or less -- after 1000 bytes, the output string is truncated. In particular, this means that no unrestricted "%s" formats should occur; these should be limited using "%.<N>s" where <N> is a decimal number calculated so that <N> plus the maximum size of other formatted text does not exceed 1000 bytes. Also watch out for "%f", which can print hundreds of digits for very large numbers.

If a problem occurs, or sys. stdout is unset, the formatted message is written to the real (C level) stdout.

### void PySys\_WriteStderr (const char \*format, ...)

Part of the Stable ABI. As PySys\_WriteStdout(), but write to sys.stderr or stderr instead.

### void PySys\_FormatStdout (const char \*format, ...)

Part of the Stable ABI. Function similar to PySys\_WriteStdout() but format the message using PyUnicode\_FromFormatV() and don't truncate the message to an arbitrary length.

Nouveau dans la version 3.2.

### void PySys\_FormatStderr (const char \*format, ...)

Part of the Stable ABI. As PySys\_FormatStdout(), but write to sys.stderr or stderr instead. Nouveau dans la version 3.2.

### void PySys\_AddXOption (const wchar\_t \*s)

Part of the Stable ABI since version 3.7. This API is kept for backward compatibility: setting PyConfig. xoptions should be used instead, see Python Initialization Configuration.

Parse s as a set of -X options and add them to the current options mapping as returned by  $PySys\_GetXOptions()$ . This function may be called prior to  $Py\_Initialize()$ .

Nouveau dans la version 3.2.

Obsolète depuis la version 3.11.

### PyObject \*PySys\_GetXOptions()

Return value: Borrowed reference. Part of the Stable ABI since version 3.7. Return the current dictionary of -X options, similarly to sys.\_xoptions. On error, NULL is returned and an exception is set.

Nouveau dans la version 3.2.

## int PySys\_Audit (const char \*event, const char \*format, ...)

Raise an auditing event with any active hooks. Return zero for success and non-zero with an exception set on failure. If any hooks have been added, *format* and other arguments will be used to construct a tuple to pass. Apart from N, the same format characters as used in  $Py\_BuildValue()$  are available. If the built value is not a tuple, it will be added into a single-element tuple. (The N format option consumes a reference, but since there is no way to know whether arguments to this function will be consumed, using it may cause reference leaks.)

Note that # format characters should always be treated as  $Py\_ssize\_t$ , regardless of whether  $PY\_SSIZE\_T\_CLEAN$  was defined.

sys.audit() performs the same function from Python code.

Nouveau dans la version 3.8.

Modifié dans la version 3.8.2: Require  $Py\_ssize\_t$  for # format characters. Previously, an unavoidable deprecation warning was raised.

### int PySys\_AddAuditHook (Py\_AuditHookFunction hook, void \*userData)

Append the callable *hook* to the list of active auditing hooks. Return zero on success and non-zero on failure. If the runtime has been initialized, also set an error on failure. Hooks added through this API are called for all interpreters created by the runtime.

The *userData* pointer is passed into the hook function. Since hook functions may be called from different runtimes, this pointer should not refer directly to Python state.

This function is safe to call before  $Py\_Initialize()$ . When called after runtime initialization, existing audit hooks are notified and may silently abort the operation by raising an error subclassed from Exception (other errors will not be silenced).

The hook function is of type int (\*) (const char \*event, PyObject \*args, void \*userData), where args is guaranteed to be a PyTupleObject. The hook function is always called with the GIL held by the Python interpreter that raised the event.

See PEP 578 for a detailed description of auditing. Functions in the runtime and standard library that raise events are listed in the audit events table. Details are in each function's documentation.

Déclenche un événement d'audit sys. addaudithook sans arguments.

Nouveau dans la version 3.8.

## 6.3 Process Control

### void Py\_FatalError (const char \*message)

Part of the Stable ABI. Print a fatal error message and kill the process. No cleanup is performed. This function should only be invoked when a condition is detected that would make it dangerous to continue using the Python interpreter; e.g., when the object administration appears to be corrupted. On Unix, the standard C library function abort () is called which will attempt to produce a core file.

The Py\_FatalError() function is replaced with a macro which logs automatically the name of the current function, unless the Py\_LIMITED\_API macro is defined.

Modifié dans la version 3.9 : Log the function name automatically.

### void Py\_Exit (int status)

Part of the Stable ABI. Exit the current process. This calls  $Py\_FinalizeEx()$  and then calls the standard C library function exit (status). If  $Py\_FinalizeEx()$  indicates an error, the exit status is set to 120.

Modifié dans la version 3.6 : Errors from finalization no longer ignored.

### int Py\_AtExit (void (\*func)())

Part of the Stable ABI. Register a cleanup function to be called by  $Py\_FinalizeEx()$ . The cleanup function will be called with no arguments and should return no value. At most 32 cleanup functions can be registered. When the registration is successful,  $Py\_AtExit()$  returns 0; on failure, it returns -1. The cleanup function registered last is called first. Each cleanup function will be called at most once. Since Python's internal finalization will have completed before the cleanup function, no Python APIs should be called by *func*.

# 6.4 Importer des modules

#### PyObject \*PyImport ImportModule (const char \*name)

Return value: New reference. Part of the Stable ABI. This is a simplified interface to PyImport\_ImportModuleEx() below, leaving the globals and locals arguments set to NULL and level set to 0. When the name argument contains a dot (when it specifies a submodule of a package), the fromlist argument is set to the list ['\*'] so that the return value is the named module rather than the top-level package containing it as would otherwise be the case. (Unfortunately, this has an additional side effect when name in fact specifies a subpackage instead of a submodule: the submodules specified in the package's \_\_all\_\_\_ variable are loaded.) Return a new reference to the imported module, or NULL with an exception set on failure. A failing import of a module doesn't leave the module in sys.modules.

This function always uses absolute imports.

### PyObject \*PyImport\_ImportModuleNoBlock (const char \*name)

Return value: New reference. Part of the Stable ABI. This function is a deprecated alias of PyImport\_ImportModule().

Modifié dans la version 3.3: This function used to fail immediately when the import lock was held by another thread. In Python 3.3 though, the locking scheme switched to per-module locks for most purposes, so this function's special behaviour isn't needed anymore.

# PyObject \*PyImport\_ImportModuleEx (const char \*name, PyObject \*globals, PyObject \*locals, PyObject \*fromlist)

*Return value : New reference.* Import a module. This is best described by referring to the built-in Python function \_\_import\_\_().

The return value is a new reference to the imported module or top-level package, or NULL with an exception set on failure. Like for \_\_import\_\_ (), the return value when a submodule of a package was requested is normally the top-level package, unless a non-empty *fromlist* was given.

Failing imports remove incomplete module objects, like with PyImport\_ImportModule().

# PyObject \*PyImport\_ImportModuleLevelObject (PyObject \*name, PyObject \*globals, PyObject \*locals, PyObject \*fromlist, int level)

Return value: New reference. Part of the Stable ABI since version 3.7. Import a module. This is best described by referring to the built-in Python function \_\_import\_\_(), as the standard \_\_import\_\_() function calls this function directly.

The return value is a new reference to the imported module or top-level package, or NULL with an exception set on failure. Like for \_\_import\_\_ (), the return value when a submodule of a package was requested is normally the top-level package, unless a non-empty *fromlist* was given.

Nouveau dans la version 3.3.

# PyObject \*PyImport\_ImportModuleLevel (const char \*name, PyObject \*globals, PyObject \*locals, PyObject \*fromlist, int level)

Return value: New reference. Part of the Stable ABI. Similar to PyImport\_ImportModuleLevelObject(), but the name is a UTF-8 encoded string instead of a Unicode object.

Modifié dans la version 3.3 : Negative values for *level* are no longer accepted.

### PyObject \*PyImport\_Import (PyObject \*name)

Return value: New reference. Part of the Stable ABI. This is a higher-level interface that calls the current "import hook function" (with an explicit level of 0, meaning absolute import). It invokes the \_\_import\_\_() function from the \_\_builtins\_\_ of the current globals. This means that the import is done using whatever import hooks are installed in the current environment.

This function always uses absolute imports.

### PyObject \*PyImport\_ReloadModule (PyObject \*m)

*Return value : New reference. Part of the* Stable ABI. Reload a module. Return a new reference to the reloaded module, or NULL with an exception set on failure (the module still exists in this case).

### PyObject \*PyImport\_AddModuleObject (PyObject \*name)

Return value: Borrowed reference. Part of the Stable ABI since version 3.7. Return the module object corresponding to a module name. The name argument may be of the form package.module. First check the modules dictionary if there's one there, and if not, create a new one and insert it in the modules dictionary. Return NULL with an exception set on failure.

**Note:** This function does not load or import the module; if the module wasn't already loaded, you will get an empty module object. Use <code>PyImport\_ImportModule()</code> or one of its variants to import a module. Package structures implied by a dotted name for *name* are not created if not already present.

Nouveau dans la version 3.3.

### PyObject \*PyImport\_AddModule (const char \*name)

Return value: Borrowed reference. Part of the Stable ABI. Similar to PyImport\_AddModuleObject(), but the name is a UTF-8 encoded string instead of a Unicode object.

## PyObject \*PyImport\_ExecCodeModule (const char \*name, PyObject \*co)

Return value: New reference. Part of the Stable ABI. Given a module name (possibly of the form package. module) and a code object read from a Python bytecode file or obtained from the built-in function compile(), load the module. Return a new reference to the module object, or NULL with an exception set if an error occurred. name is removed from sys.modules in error cases, even if name was already in sys.modules on entry to PyImport\_ExecCodeModule(). Leaving incompletely initialized modules in sys.modules is dangerous, as imports of such modules have no way to know that the module object is an unknown (and probably damaged with respect to the module author's intents) state.

The module's \_\_spec\_\_ and \_\_loader\_\_ will be set, if not set already, with the appropriate values. The spec's loader will be set to the module's \_\_loader\_\_ (if set) and to an instance of SourceFileLoader otherwise. The module's \_\_file\_\_ attribute will be set to the code object's co\_filename. If applicable, \_\_cached\_\_ will also be set.

This function will reload the module if it was already imported. See <code>PyImport\_ReloadModule()</code> for the intended way to reload a module.

If name points to a dotted name of the form package. module, any package structures not already created will still not be created.

See also PyImport\_ExecCodeModuleEx() and PyImport\_ExecCodeModuleWithPathnames().

## PyObject \*PyImport\_ExecCodeModuleEx (const char \*name, PyObject \*co, const char \*pathname)

Return value: New reference. Part of the Stable ABI. Like PyImport\_ExecCodeModule(), but the \_\_file\_\_ attribute of the module object is set to pathname if it is non-NULL.

See also PyImport ExecCodeModuleWithPathnames ().

# PyObject \*PyImport\_ExecCodeModuleObject (PyObject \*name, PyObject \*co, PyObject \*pathname, PyObject \*co, PyObject \*pathname)

Return value: New reference. Part of the Stable ABI since version 3.7. Like PyImport\_ExecCodeModuleEx(), but the \_\_cached\_\_ attribute of the module object is set to cpathname if it is non-NULL. Of the three functions, this is the preferred one to use.

Nouveau dans la version 3.3.

# PyObject \*PyImport\_ExecCodeModuleWithPathnames (const char \*name, PyObject \*co, const char \*pathname, const char \*cpathname)

Return value: New reference. Part of the Stable ABI. Like <code>PyImport\_ExecCodeModuleObject()</code>, but name, pathname and cpathname are UTF-8 encoded strings. Attempts are also made to figure out what the value for pathname should be from cpathname if the former is set to <code>NULL</code>.

Nouveau dans la version 3.2.

Modifié dans la version 3.3 : Uses imp.source\_from\_cache() in calculating the source path if only the bytecode path is provided.

#### long PyImport\_GetMagicNumber()

Part of the Stable ABI. Return the magic number for Python bytecode files (a.k.a. .pyc file). The magic number should be present in the first four bytes of the bytecode file, in little-endian byte order. Returns -1 on error.

Modifié dans la version 3.3 : Return value of −1 upon failure.

### const char \*PyImport\_GetMagicTag()

Part of the Stable ABI. Return the magic tag string for PEP 3147 format Python bytecode file names. Keep in mind that the value at sys.implementation.cache\_tag is authoritative and should be used instead of this function.

Nouveau dans la version 3.2.

### PyObject \*PyImport\_GetModuleDict()

*Return value : Borrowed reference. Part of the* Stable ABI. Return the dictionary used for the module administration (a.k.a. sys.modules). Note that this is a per-interpreter variable.

### PyObject \*PyImport\_GetModule (PyObject \*name)

Return value: New reference. Part of the Stable ABI since version 3.8. Return the already imported module with the given name. If the module has not been imported yet then returns NULL but does not set an error. Returns NULL and sets an error if the lookup failed.

Nouveau dans la version 3.7.

#### PyObject \*PyImport\_GetImporter (PyObject \*path)

Return value: New reference. Part of the Stable ABI. Return a finder object for a sys.path/pkg.\_\_path\_item path, possibly by fetching it from the sys.path\_importer\_cache dict. If it wasn't yet cached, traverse sys.path\_hooks until a hook is found that can handle the path item. Return None if no hook could; this tells our caller that the path based finder could not find a finder for this path item. Cache the result in sys.path\_importer\_cache. Return a new reference to the finder object.

#### int PyImport\_ImportFrozenModuleObject (PyObject \*name)

Part of the Stable ABI since version 3.7. Load a frozen module named name. Return 1 for success, 0 if the module is not found, and -1 with an exception set if the initialization failed. To access the imported module on a successful load, use <code>PyImport\_ImportModule()</code>. (Note the misnomer --- this function would reload the module if it was already imported.)

Nouveau dans la version 3.3.

Modifié dans la version 3.4 : The \_\_\_file\_\_ attribute is no longer set on the module.

## int PyImport\_ImportFrozenModule (const char \*name)

Part of the Stable ABI. Similar to PyImport\_ImportFrozenModuleObject(), but the name is a UTF-8 encoded string instead of a Unicode object.

### struct \_frozen

This is the structure type definition for frozen module descriptors, as generated by the **freeze** utility (see Tools/freeze/in the Python source distribution). Its definition, found in Include/import.h, is:

```
struct _frozen {
   const char *name;
   const unsigned char *code;
   int size;
   bool is_package;
};
```

Modifié dans la version 3.11: The new is\_package field indicates whether the module is a package or not. This replaces setting the size field to a negative value.

### const struct \_frozen \*PyImport\_FrozenModules

This pointer is initialized to point to an array of \_frozen records, terminated by one whose members are all NULL or zero. When a frozen module is imported, it is searched in this table. Third-party code could play tricks with this to provide a dynamically created collection of frozen modules.

## int PyImport\_AppendInittab (const char \*name, PyObject \*(\*initfunc)(void))

Part of the Stable ABI. Add a single module to the existing table of built-in modules. This is a convenience wrapper around <code>PyImport\_ExtendInittab()</code>, returning -1 if the table could not be extended. The new module can be imported by the name *name*, and uses the function *initfunc* as the initialization function called on the first attempted import. This should be called before <code>Py\_Initialize()</code>.

#### struct \_inittab

Structure describing a single entry in the list of built-in modules. Each of these structures gives the name and initialization function for a module built into the interpreter. The name is an ASCII encoded string. Programs which embed Python may use an array of these structures in conjunction with <code>PyImport\_ExtendInittab()</code> to provide additional built-in modules. The structure is defined in <code>Include/import.h</code> as:

### int PyImport\_ExtendInittab (struct \_inittab \*newtab)

Add a collection of modules to the table of built-in modules. The *newtab* array must end with a sentinel entry which contains NULL for the name field; failure to provide the sentinel value can result in a memory fault. Returns 0 on success or -1 if insufficient memory could be allocated to extend the internal table. In the event of failure, no modules are added to the internal table. This must be called before  $Py_Initialize()$ .

If Python is initialized multiple times, PyImport\_AppendInittab() or PyImport\_ExtendInittab() must be called before each Python initialization.

# 6.5 Data marshalling support

These routines allow C code to work with serialized objects using the same data format as the marshal module. There are functions to write data into the serialization format, and additional functions that can be used to read the data back. Files used to store marshalled data must be opened in binary mode.

Numeric values are stored with the least significant byte first.

The module supports two versions of the data format: version 0 is the historical version, version 1 shares interned strings in the file, and upon unmarshalling. Version 2 uses a binary format for floating point numbers. Py\_MARSHAL\_VERSION indicates the current file format (currently 2).

### void PyMarshal\_WriteLongToFile (long value, FILE \*file, int version)

Marshal a long integer, *value*, to *file*. This will only write the least-significant 32 bits of *value*; regardless of the size of the native long type. *version* indicates the file format.

### void PyMarshal\_WriteObjectToFile (PyObject \*value, FILE \*file, int version)

Marshal a Python object, value, to file. version indicates the file format.

## PyObject \*PyMarshal\_WriteObjectToString (PyObject \*value, int version)

Return value: New reference. Return a bytes object containing the marshalled representation of value. version indicates the file format.

The following functions allow marshalled values to be read back in.

#### long PyMarshal ReadLongFromFile (FILE \*file)

Return a C long from the data stream in a FILE\* opened for reading. Only a 32-bit value can be read in using this function, regardless of the native size of long.

On error, sets the appropriate exception (EOFError) and returns -1.

#### int PyMarshal ReadShortFromFile (FILE \*file)

Return a C short from the data stream in a FILE\* opened for reading. Only a 16-bit value can be read in using this function, regardless of the native size of short.

On error, sets the appropriate exception (EOFError) and returns -1.

### PyObject \*PyMarshal\_ReadObjectFromFile (FILE \*file)

Return value: New reference. Return a Python object from the data stream in a FILE\* opened for reading.

On error, sets the appropriate exception (EOFError, ValueError or TypeError) and returns NULL.

### PyObject \*PyMarshal\_ReadLastObjectFromFile (FILE \*file)

Return value: New reference. Return a Python object from the data stream in a FILE\* opened for reading. Unlike PyMarshal\_ReadObjectFromFile(), this function assumes that no further objects will be read from the file, allowing it to aggressively load file data into memory so that the de-serialization can operate from data in memory rather than reading a byte at a time from the file. Only use these variant if you are certain that you won't be reading anything else from the file.

On error, sets the appropriate exception (EOFError, ValueError or TypeError) and returns NULL.

### PyObject \*PyMarshal\_ReadObjectFromString (const char \*data, Py\_ssize\_t len)

Return value: New reference. Return a Python object from the data stream in a byte buffer containing len bytes pointed to by data.

On error, sets the appropriate exception (EOFError, ValueError or TypeError) and returns NULL.

# 6.6 Analyse des arguments et construction des valeurs

Ces fonctions sont utiles pour créer vos propres fonctions et méthodes d'extensions. Des informations supplémentaires et des exemples sont disponibles ici : extending-index.

Dans Les trois premières de ces fonctions décrites, <code>PyArg\_ParseTuple()</code>, <code>PyArg\_ParseTupleAndKeywords()</code>, et <code>PyArg\_Parse()</code>, toutes utilisent des chaînes de format qui sont utilisées pour indiquer à la fonction les arguments attendus. Les chaînes de format utilise la même syntaxe pour chacune de ces fonctions.

## 6.6.1 Analyse des arguments

Une chaîne de format se compose de zéro ou plusieurs "unités de format". Une unité de format décrit un objet Python, elle est généralement composée d'un seul caractère ou d'une séquence d'unités de format entre parenthèses. À quelques exceptions près, une unité de format qui n'est pas une séquence entre parenthèses correspond normalement à un argument d'une seule adresse pour ces fonctions. Dans la description qui suit, la forme entre guillemets est l'unité de format, l'entrée entre parenthèses est le type d'objet Python qui correspond à l'unité de format, et l'entrée entre crochets est le type de la variable C (ou des variables) dont l'adresse doit être donnée.

### Chaînes et tampons

Ces formats permettent d'accéder à un objet sous forme d'un fragment de mémoire contiguë. Il n'est pas nécessaire d'allouer la mémoire pour l'*unicode* ou le *bytes* renvoyé.

Sauf indication contraire, les tampons ne se terminent pas par NUL.

There are three ways strings and buffers can be converted to C:

- Formats such as y\* and s\* fill a Py\_buffer structure. This locks the underlying buffer so that the caller can subsequently use the buffer even inside a Py\_BEGIN\_ALLOW\_THREADS block without the risk of mutable data being resized or destroyed. As a result, **you have to call** PyBuffer\_Release() after you have finished processing the data (or in any early abort case).
- The es, es#, et and et# formats allocate the result buffer. You have to call PyMem\_Free () after you have finished processing the data (or in any early abort case).
- Other formats take a str or a read-only bytes-like object, such as bytes, and provide a const char \* pointer to its buffer. In this case the buffer is "borrowed": it is managed by the corresponding Python object, and shares the lifetime of this object. You won't have to release any memory yourself.
  - To ensure that the underlying buffer may be safely borrowed, the object's <code>PyBufferProcs.bf\_releasebuffer</code> field must be <code>NULL</code>. This disallows common mutable objects such as <code>bytearray</code>, but also some read-only objects such as <code>memoryview</code> of <code>bytes</code>.
  - Besides this bf\_releasebuffer requirement, there is no check to verify whether the input object is immutable (e.g. whether it would honor a request for a writable buffer, or whether another thread can mutate the data).

**Note:** For all # variants of formats (s#, y#, etc.), the macro PY\_SSIZE\_T\_CLEAN must be defined before including Python.h. On Python 3.9 and older, the type of the length argument is  $Py\_ssize\_t$  if the PY\_SSIZE\_T\_CLEAN macro is defined, or int otherwise.

s (str) [const char \*] Convertit un objet Unicode en un pointeur vers une chaîne de caractères. S'il s'agit d'un pointeur vers une chaîne de caractères déjà existante, il est stocké dans la variable de type pointeur vers un caractère dont vous avez donné l'adresse. Une chaîne de caractères en C se termine par NULL. La chaîne de caractères Python ne doit donc pas contenir de caractère dont le code est null. Si elle en contient, une exception ValueError est levée. Si la conversion échoue, une UnicodeError est levée.

**Note :** Ce format n'accepte pas les *objets compatibles avec une chaîne d'octets*. Si vous voulez accepter les chemins du système de fichiers et les convertir vers des chaînes de caractères C, il est préférable d'utiliser le format O& avec *PyUnicode\_FSConverter()* en tant que *converter*.

Modifié dans la version 3.5 : Auparavant, une TypeError était levée quand la chaîne de caractères Python contenait des codes NULL.

- s\* (str ou bytes-like object) [Py\_buffer] Ce format accepte les objets Unicode et les bytes-like object. Cela remplit une structure Py\_buffer qui est fournie par l'appelant. Dans ce cas, la chaîne de caractères C qui en résulte peut contenir des octets NULL. Les objets Unicode sont convertis en chaînes de caractères C en utilisant l'encodage 'utf-8'.
- s# (str, read-only bytes-like object) [const char \*, Py\_ssize\_t] Like s\*, except that it provides a borrowed buffer. The result is stored into two C variables, the first one a pointer to a C string, the second one its length. The string may contain embedded null bytes. Unicode objects are converted to C strings using 'utf-8' encoding.
- z (strou None) [const char \*] Like s, but the Python object may also be None, in which case the C pointer is set to NULL.
- z\* (str, bytes-like object ou None) [Py\_buffer] Comme s\*, mais l'objet Python peut aussi être None, auquel cas le membre buf, dont la structure est Py\_buffer est fixée à NULL.
- z# (str, read-only bytes-like object or None) [const char \*, Py\_ssize\_t] Like s#, but the Python object may also be None, in which case the C pointer is set to NULL.
- y (lecture seule *objet compatible avec une chaîne d'octets*) [constante char \*] This format converts a bytes-like object to a C pointer to a *borrowed* character string; it does not accept Unicode objects. The bytes buffer must not contain embedded null bytes; if it does, a ValueError exception is raised.
  - Modifié dans la version 3.5 : Auparavant, TypeError était levée lorsque des octets *null* étaient rencontrés dans le tampon d'octets.
- y\* (bytes-like object) [Py\_buffer] This variant on s\* doesn't accept Unicode objects, only bytes-like objects. This is the recommended way to accept binary data.
- y# (read-only bytes-like object) [const char \*, Py\_ssize\_t] Cette variante de s# n'accepte pas les objets Unicode, uniquement des objets assimilés à des octets.
- **S (bytes)** [**PyBytesObject \***] Requires that the Python object is a bytes object, without attempting any conversion. Raises TypeError if the object is not a bytes object. The C variable may also be declared as PyObject\*.
- Y (bytearray) [PyByteArrayObject \*] Requires that the Python object is a bytearray object, without attempting any conversion. Raises TypeError if the object is not a bytearray object. The C variable may also be declared as PyObject\*.
- u (str) [const Py\_UNICODE \*] Convertit un objet Python Unicode en un pointeur C vers un tampon de caractères Unicode terminé par NULL. Vous devez passer l'adresse d'un pointeur Py\_UNICODE, qui sera rempli avec le pointeur vers un tampon Unicode existant. Veuillez noter que la taille d'un Py\_UNICODE dépend des options de compilation (soit 16, soit 32 bits). La chaîne de caractères Python ne doit pas contenir de code NULL. Si elle en contient, une exception ValueError est levée.
  - Modifié dans la version 3.5 : Auparavant, une TypeError était levée quand la chaîne de caractères Python contenait des codes NULL.
  - Obsolète depuis la version 3.3, sera supprimé dans la version 3.12 : Part of the old-style *Py\_UNICODE* API; please migrate to using *PyUnicode\_AsWideCharString()*.
- u# (str) [const Py\_UNICODE \*, Py\_ssize\_t] This variant on u stores into two C variables, the first one a pointer to a Unicode data buffer, the second one its length. This variant allows null code points.
  - Obsolète depuis la version 3.3, sera supprimé dans la version 3.12 : Part of the old-style *Py\_UNICODE* API; please migrate to using *PyUnicode\_AsWideCharString()*.
- **Z** (str ou None) [const Py\_UNICODE \*] Like u, but the Python object may also be None, in which case the Py\_UNICODE pointer is set to NULL.

- Obsolète depuis la version 3.3, sera supprimé dans la version 3.12 : Part of the old-style *Py\_UNICODE* API; please migrate to using *PyUnicode\_AsWideCharString()*.
- **Z#** (str or None) [const Py\_UNICODE \*, Py\_ssize\_t] Like u#, but the Python object may also be None, in which case the Py\_UNICODE pointer is set to NULL.
  - Obsolète depuis la version 3.3, sera supprimé dans la version 3.12 : Part of the old-style Py\_UNICODE API; please migrate to using PyUnicode\_AsWideCharString().
- **U**(str)[PyObject \*] Requires that the Python object is a Unicode object, without attempting any conversion. Raises TypeError if the object is not a Unicode object. The C variable may also be declared as PyObject\*.
- **w\*** (lecture-écriture bytes-like object) [Py\_buffer] This format accepts any object which implements the readwrite buffer interface. It fills a Py\_buffer structure provided by the caller. The buffer may contain embedded null bytes. The caller have to call PyBuffer Release() when it is done with the buffer.
- **es** (**str**) [const char \*encoding, char \*\*buffer] This variant on s is used for encoding Unicode into a character buffer. It only works for encoded data without embedded NUL bytes.
  - This format requires two arguments. The first is only used as input, and must be a const char\* which points to the name of an encoding as a NUL-terminated string, or NULL, in which case 'utf-8' encoding is used. An exception is raised if the named encoding is not known to Python. The second argument must be a char\*\*; the value of the pointer it references will be set to a buffer with the contents of the argument text. The text will be encoded in the encoding specified by the first argument.
  - PyArg\_ParseTuple() will allocate a buffer of the needed size, copy the encoded data into this buffer and adjust \*buffer to reference the newly allocated storage. The caller is responsible for calling PyMem\_Free() to free the allocated buffer after use.
- et (str, bytes or bytearray) [const char \*encoding, char \*\*buffer] Same as es except that byte string objects are passed through without recoding them. Instead, the implementation assumes that the byte string object uses the encoding passed in as parameter.
- es#(str)[const char \*encoding, char \*\*buffer, Py\_ssize\_t \*buffer\_length] This variant on s# is used for encoding Unicode into a character buffer. Unlike the es format, this variant allows input data which contains NUL characters.
  - It requires three arguments. The first is only used as input, and must be a const char\* which points to the name of an encoding as a NUL-terminated string, or NULL, in which case 'utf-8' encoding is used. An exception is raised if the named encoding is not known to Python. The second argument must be a char\*\*; the value of the pointer it references will be set to a buffer with the contents of the argument text. The text will be encoded in the encoding specified by the first argument. The third argument must be a pointer to an integer; the referenced integer will be set to the number of bytes in the output buffer.

Il existe deux modes de fonctionnement :

- If \*buffer points a NULL pointer, the function will allocate a buffer of the needed size, copy the encoded data into this buffer and set \*buffer to reference the newly allocated storage. The caller is responsible for calling <code>PyMem\_Free()</code> to free the allocated buffer after usage.
- If \*buffer points to a non-NULL pointer (an already allocated buffer),  $PyArg\_ParseTuple()$  will use this location as the buffer and interpret the initial value of \*buffer\_length as the buffer size. It will then copy the encoded data into the buffer and NUL-terminate it. If the buffer is not large enough, a ValueError will be set. Dans les deux cas, \*buffer\_length est la longueur des données encodées, sans l'octet NUL de fin.
- et# (str, bytes or bytearray) [const char \*encoding, char \*\*buffer, Py\_ssize\_t \*buffer\_length]

  Same as es# except that byte string objects are passed through without recoding them. Instead, the implementation assumes that the byte string object uses the encoding passed in as parameter.

#### Les nombres

- **b** (int) [unsigned char] Convert a nonnegative Python integer to an unsigned tiny int, stored in a C unsigned char.
- **B(int)[unsigned char]** Convert a Python integer to a tiny int without overflow checking, stored in a C unsigned char.
- h (int) [short int] Convert a Python integer to a C short int.
- H (int) [unsigned short int] Convert a Python integer to a C unsigned short int, without overflow checking.
- i (int) [int] Convert a Python integer to a plain C int.
- I (int) [unsigned int] Convert a Python integer to a C unsigned int, without overflow checking.
- 1 (int) [long int] Convert a Python integer to a C long int.
- k (int) [unsigned long] Convert a Python integer to a C unsigned long without overflow checking.
- L(int)[long long] Convert a Python integer to a C long long.
- K (int) [unsigned long long] Convert a Python integer to a C unsigned long long without overflow checking.
- **n** (int) [*Py\_ssize\_t*] Convertit un entier Python en un *Py\_ssize\_t*.
- c (bytes ou bytearray de longueur 1) [char] Convert a Python byte, represented as a bytes or bytearray object of length 1, to a C char.
  - Modifié dans la version 3.3 : Allow bytearray objects.
- C (str de longueur 1) [int] Convert a Python character, represented as a str object of length 1, to a C int.
- f (float) [float] Convert a Python floating point number to a C float.
- d (float) [double] Convert a Python floating point number to a C double.
- D (complex) [Py\_complex] Convertit un nombre complexe Python vers une structure Py\_complex C.

### **Autres objets**

- O (objet) [PyObject \*] Store a Python object (without any conversion) in a C object pointer. The C program thus receives the actual object that was passed. The object's reference count is not increased. The pointer stored is not NULL.
- O! (objet) [typeobject, PyObject \*] Store a Python object in a C object pointer. This is similar to 0, but takes two C arguments: the first is the address of a Python type object, the second is the address of the C variable (of type PyObject\*) into which the object pointer is stored. If the Python object does not have the required type, TypeError is raised.
- **O&** (objet) [converter, anything] Convert a Python object to a C variable through a converter function. This takes two arguments: the first is a function, the second is the address of a C variable (of arbitrary type), converted to void\*. The converter function in turn is called as follows:

```
status = converter(object, address);
```

where *object* is the Python object to be converted and *address* is the void\* argument that was passed to the PyArg\_Parse\* function. The returned *status* should be 1 for a successful conversion and 0 if the conversion has failed. When the conversion fails, the *converter* function should raise an exception and leave the content of *address* unmodified.

If the *converter* returns Py\_CLEANUP\_SUPPORTED, it may get called a second time if the argument parsing eventually fails, giving the converter a chance to release any memory that it had already allocated. In this second call, the *object* parameter will be NULL; *address* will have the same value as in the original call.

Modifié dans la version 3.1 : Py\_CLEANUP\_SUPPORTED à été ajouté.

- p (bool) [int] Tests the value passed in for truth (a boolean predicate) and converts the result to its equivalent C true/false integer value. Sets the int to 1 if the expression was true and 0 if it was false. This accepts any valid Python value. See truth for more information about how Python tests values for truth.
  Nouveau dans la version 3.3.
- (items) (tuple) [matching-items] L'objet doit être une séquence Python dont la longueur est le nombre d'unités de formats dans articles. Les arguments C doivent correspondre à chaque unité de format particulière dans articles. Les unités de formats pour les séquences peuvent être imbriquées.

It is possible to pass "long" integers (integers whose value exceeds the platform's LONG\_MAX) however no proper range checking is done --- the most significant bits are silently truncated when the receiving field is too small to receive the value (actually, the semantics are inherited from downcasts in C --- your mileage may vary).

Quelques autres caractères ont un sens dans une chaîne de format. On ne doit pas les trouvées dans des parenthèses imbriquées. Ce sont :

- Indicates that the remaining arguments in the Python argument list are optional. The C variables corresponding to optional arguments should be initialized to their default value --- when an optional argument is not specified,  $PyArg\_ParseTuple()$  does not touch the contents of the corresponding C variable(s).
- \$ PyArg\_ParseTupleAndKeywords () only: Indicates that the remaining arguments in the Python argument list are keyword-only. Currently, all keyword-only arguments must also be optional arguments, so | must always be specified before \$ in the format string.
  - Nouveau dans la version 3.3.
- : The list of format units ends here; the string after the colon is used as the function name in error messages (the "associated value" of the exception that PyArg\_ParseTuple() raises).
- ; La liste des unités de format s'arrête ici ; la chaîne après le point-virgule est utilise comme message d'erreur *au lieu* du message d'erreur par défaut. : et ; sont mutuellement exclusifs.

Notez que n'importe quelles références sur un objet Python qui sont données à l'appelant sont des références *empruntées*; ne décrémentez pas leur compteur de références!

Les arguments additionnels qui sont donnés à ces fonctions doivent être des adresses de variables dont le type est déterminé par la chaîne de format. Elles sont utilisées pour stocker les valeurs du *n*-uplet d'entrée. Il y a quelques cas, comme décrit précédemment dans le liste des unités de formats, où ces paramètres sont utilisés comme valeurs d'entrée. Dans ce cas, ils devraient correspondre à ce qui est spécifié pour l'unité de format correspondante.

For the conversion to succeed, the *arg* object must match the format and the format must be exhausted. On success, the PyArg\_Parse\* functions return true, otherwise they return false and raise an appropriate exception. When the PyArg\_Parse\* functions fail due to conversion failure in one of the format units, the variables at the addresses corresponding to that and the following format units are left untouched.

#### Fonction de l'API

int PyArq ParseTuple (PyObject \*args, const char \*format, ...)

*Part of the* Stable ABI. Parse the parameters of a function that takes only positional parameters into local variables. Returns true on success; on failure, it returns false and raises the appropriate exception.

int PyArg\_VaParse (*PyObject* \*args, const char \*format, va\_list vargs)

Part of the Stable ABI. Identical to  $PyArg\_ParseTuple()$ , except that it accepts a va\_list rather than a variable number of arguments.

int PyArg\_ParseTupleAndKeywords (PyObject \*args, PyObject \*kw, const char \*format, char \*keywords[], ...)

*Part of the* Stable ABI. Parse the parameters of a function that takes both positional and keyword parameters into local variables. The *keywords* argument is a NULL-terminated array of keyword parameter names. Empty names denote *positional-only parameters*. Returns true on success; on failure, it returns false and raises the appropriate exception.

Modifié dans la version 3.6 : Added support for *positional-only parameters*.

int PyArg\_VaParseTupleAndKeywords (*PyObject* \*args, *PyObject* \*kw, const char \*format, char \*keywords[], va list vargs)

Part of the Stable ABI. Identical to PyArg\_ParseTupleAndKeywords(), except that it accepts a va\_list rather than a variable number of arguments.

#### int PyArg\_ValidateKeywordArguments (PyObject\*)

Part of the Stable ABI. Ensure that the keys in the keywords argument dictionary are strings. This is only needed if PyArg\_ParseTupleAndKeywords () is not used, since the latter already does this check.

Nouveau dans la version 3.2.

```
int PyArg_Parse (PyObject *args, const char *format, ...)
```

Part of the Stable ABI. Function used to deconstruct the argument lists of "old-style" functions --- these are functions which use the METH\_OLDARGS parameter parsing method, which has been removed in Python 3. This is not recommended for use in parameter parsing in new code, and most code in the standard interpreter has been modified to no longer use this for that purpose. It does remain a convenient way to decompose other tuples, however, and may continue to be used for that purpose.

```
int PyArg_UnpackTuple (PyObject *args, const char *name, Py_ssize_t min, Py_ssize_t max, ...)
```

Part of the Stable ABI. A simpler form of parameter retrieval which does not use a format string to specify the types of the arguments. Functions which use this method to retrieve their parameters should be declared as METH\_VARARGS in function or method tables. The tuple containing the actual parameters should be passed as args; it must actually be a tuple. The length of the tuple must be at least min and no more than max; min and max may be equal. Additional arguments must be passed to the function, each of which should be a pointer to a PyObject\* variable; these will be filled in with the values from args; they will contain borrowed references. The variables which correspond to optional parameters not given by args will not be filled in; these should be initialized by the caller. This function returns true on success and false if args is not a tuple or contains the wrong number of elements; an exception will be set if there was a failure.

This is an example of the use of this function, taken from the sources for the \_weakref helper module for weak references:

```
static PyObject *
weakref_ref(PyObject *self, PyObject *args)
{
    PyObject *object;
    PyObject *callback = NULL;
    PyObject *result = NULL;

    if (PyArg_UnpackTuple(args, "ref", 1, 2, &object, &callback)) {
        result = PyWeakref_NewRef(object, callback);
    }
    return result;
}
```

The call to  $PyArg\_UnpackTuple()$  in this example is entirely equivalent to this call to  $PyArg\_ParseTuple()$ :

```
PyArg_ParseTuple(args, "0|0:ref", &object, &callback)
```

### 6.6.2 Construction des valeurs

```
PyObject *Py_BuildValue (const char *format, ...)
```

Return value: New reference. Part of the Stable ABI. Create a new value based on a format string similar to those accepted by the PyArg\_Parse\* family of functions and a sequence of values. Returns the value or NULL in the case of an error; an exception will be raised if NULL is returned.

 $Py\_BuildValue()$  does not always build a tuple. It builds a tuple only if its format string contains two or more format units. If the format string is empty, it returns None; if it contains exactly one format unit, it returns whatever object is described by that format unit. To force it to return a tuple of size 0 or one, parenthesize the format string. When memory buffers are passed as parameters to supply data to build objects, as for the s and s# formats, the required data is copied. Buffers provided by the caller are never referenced by the objects created by  $Py\_BuildValue()$ . In other words, if your code invokes malloc() and passes the allocated memory to  $Py\_BuildValue()$ , your code is responsible for calling free() for that memory once  $Py\_BuildValue()$  returns.

In the following description, the quoted form is the format unit; the entry in (round) parentheses is the Python object type that the format unit will return; and the entry in [square] brackets is the type of the C value(s) to be passed.

The characters space, tab, colon and comma are ignored in format strings (but not within format units such as s#). This can be used to make long format strings a tad more readable.

- s (strou None) [const char \*] Convert a null-terminated C string to a Python str object using 'utf-8' encoding. If the C string pointer is NULL, None is used.
- **s#** (**str or None**) [**const char \***, **Py\_ssize\_t**] Convert a C string and its length to a Python str object using 'utf-8' encoding. If the C string pointer is NULL, the length is ignored and None is returned.
- y (bytes) [const char \*] This converts a C string to a Python bytes object. If the C string pointer is NULL, None is returned.
- y# (bytes) [const char \*, Py\_ssize\_t] This converts a C string and its lengths to a Python object. If the C string pointer is NULL, None is returned.
- z (strou None) [const char \*] Same as s.
- **z#** (str or None) [const char \*, Py\_ssize\_t] Same as s#.
- u (str) [const wchar\_t \*] Convert a null-terminated wchar\_t buffer of Unicode (UTF-16 or UCS-4) data to a Python Unicode object. If the Unicode buffer pointer is NULL, None is returned.
- u# (str) [const wchar\_t\*, Py\_ssize\_t] Convert a Unicode (UTF-16 or UCS-4) data buffer and its length to a Python Unicode object. If the Unicode buffer pointer is NULL, the length is ignored and None is returned.
- U(strou None) [const char \*] Same as s.
- U# (str or None) [const char \*, Py\_ssize\_t] Same as s#.
- i (int) [int] Convert a plain C int to a Python integer object.
- **b** (int) [char] Convert a plain C char to a Python integer object.
- h (int) [short int] Convert a plain C short int to a Python integer object.
- 1 (int) [long int] Convert a Clong int to a Python integer object.
- B (int) [unsigned char] Convert a Cunsigned char to a Python integer object.
- H (int) [unsigned short int] Convert a C unsigned short int to a Python integer object.
- I (int) [unsigned int] Convert a C unsigned int to a Python integer object.
- k (int) [unsigned long] Convert a Cunsigned long to a Python integer object.
- L(int)[long long] Convert a Clong long to a Python integer object.
- K (int) [unsigned long long] Convert a C unsigned long long to a Python integer object.
- n (int) [Py\_ssize\_t] Convert a C Py\_ssize\_t to a Python integer.
- c (bytes de taille 1) [char] Convert a C int representing a byte to a Python bytes object of length 1.

- C (str de longueur 1) [int] Convert a C int representing a character to Python str object of length 1.
- d (float) [double] Convert a C double to a Python floating point number.
- **f**(**float**) [**float**] Convert a C float to a Python floating point number.
- D (complex) [Py\_complex \*] Convert a C Py\_complex structure to a Python complex number.
- O (objet) [PyObject \*] Pass a Python object untouched (except for its reference count, which is incremented by one). If the object passed in is a NULL pointer, it is assumed that this was caused because the call producing the argument found an error and set an exception. Therefore, <code>Py\_BuildValue()</code> will return <code>NULL</code> but won't raise an exception. If no exception has been raised yet, <code>SystemError</code> is set.
- S (objet) [PyObject \*] Same as O.
- **N** (objet) [PyObject \*] Same as O, except it doesn't increment the reference count on the object. Useful when the object is created by a call to an object constructor in the argument list.
- **O&** (**objet**) [converter, anything] Convert anything to a Python object through a converter function. The function is called with anything (which should be compatible with void\*) as its argument and should return a "new" Python object, or NULL if an error occurred.
- (items) (tuple) [matching-items] Convert a sequence of C values to a Python tuple with the same number of items.
- [items] (list) [matching-items] Convert a sequence of C values to a Python list with the same number of items.
- **{items}** (dict) [matching-items] Convert a sequence of C values to a Python dictionary. Each pair of consecutive C values adds one item to the dictionary, serving as key and value, respectively.

If there is an error in the format string, the SystemError exception is set and NULL returned.

PyObject \*Py\_VaBuildValue (const char \*format, va\_list vargs)

*Return value : New reference. Part of the* Stable ABI. Identical to *Py\_BuildValue()*, except that it accepts a va\_list rather than a variable number of arguments.

# 6.7 Conversion et formatage de chaînes

Fonctions de conversion pour les nombres et pour la sortie des chaînes formatées.

int **PyOS\_snprintf** (char \*str, size\_t size, const char \*format, ...)

Part of the Stable ABI. Output not more than size bytes to str according to the format string format and the extra arguments. See the Unix man page snprintf(3).

int **PyOS\_vsnprintf** (char \*str, size\_t size, const char \*format, va\_list va)

Part of the Stable ABI. Output not more than size bytes to str according to the format string format and the variable argument list va. Unix man page vsnprintf(3).

 $PyOS\_snprintf()$  and  $PyOS\_vsnprintf()$  wrap the Standard C library functions snprintf() and vsnprintf(). Their purpose is to guarantee consistent behavior in corner cases, which the Standard C functions do not.

The wrappers ensure that str[size-1] is always '\0' upon return. They never write more than size bytes (including the trailing '\0') into str. Both functions require that str != NULL, size > 0, format != NULL and  $size < INT_MAX$ . Note that this means there is no equivalent to the C99 n = snprintf(NULL, 0, ...) which would determine the necessary buffer size.

The return value (rv) for these functions should be interpreted as follows:

- When 0 <= rv < size, the output conversion was successful and rv characters were written to str (excluding the trailing '\0' byte at str[rv]).
- When rv >= size, the output conversion was truncated and a buffer with rv + 1 bytes would have been needed to succeed. str[size-1] is '\0' in this case.

— When rv < 0, "something bad happened." str[size-1] is '\0' in this case too, but the rest of *str* is undefined. The exact cause of the error depends on the underlying platform.

The following functions provide locale-independent string to number conversions.

## double PyOS\_string\_to\_double (const char \*s, char \*\*endptr, PyObject \*overflow\_exception)

Part of the Stable ABI. Convert a string s to a double, raising a Python exception on failure. The set of accepted strings corresponds to the set of strings accepted by Python's float () constructor, except that s must not have leading or trailing whitespace. The conversion is independent of the current locale.

If endptr is NULL, convert the whole string. Raise ValueError and return -1.0 if the string is not a valid representation of a floating-point number.

If endptr is not NULL, convert as much of the string as possible and set \*endptr to point to the first unconverted character. If no initial segment of the string is the valid representation of a floating-point number, set \*endptr to point to the beginning of the string, raise ValueError, and return -1.0.

If s represents a value that is too large to store in a float (for example, "1e500" is such a string on many platforms) then if overflow\_exception is NULL return Py\_HUGE\_VAL (with an appropriate sign) and don't set any exception. Otherwise, overflow\_exception must point to a Python exception object; raise that exception and return -1.0. In both cases, set \*endptr to point to the first character after the converted value.

If any other error occurs during the conversion (for example an out-of-memory error), set the appropriate Python exception and return -1.0.

Nouveau dans la version 3.1.

### char \*PyOS\_double\_to\_string (double val, char format\_code, int precision, int flags, int \*ptype)

Part of the Stable ABI. Convert a double val to a string using supplied format\_code, precision, and flags.

format\_code must be one of 'e', 'E', 'f', 'f', 'g', 'G' or 'r'. For 'r', the supplied precision must be 0 and is ignored. The 'r' format code specifies the standard repr() format.

flags can be zero or more of the values Py\_DTSF\_SIGN, Py\_DTSF\_ADD\_DOT\_0, or Py\_DTSF\_ALT, or-ed together:

- Py\_DTSF\_SIGN means to always precede the returned string with a sign character, even if val is non-negative.
- Py\_DTSF\_ADD\_DOT\_0 means to ensure that the returned string will not look like an integer.
- $Py_DTSF_ALT$  means to apply "alternate" formatting rules. See the documentation for the  $PyOS\_snprintf()$  '#' specifier for details.

If *ptype* is non-NULL, then the value it points to will be set to one of Py\_DTST\_FINITE, Py\_DTST\_INFINITE, or Py\_DTST\_NAN, signifying that *val* is a finite number, an infinite number, or not a number, respectively.

The return value is a pointer to *buffer* with the converted string or NULL if the conversion failed. The caller is responsible for freeing the returned string by calling <code>PyMem\_Free()</code>.

Nouveau dans la version 3.1.

### int PyOS\_stricmp (const char \*s1, const char \*s2)

Case insensitive comparison of strings. The function works almost identically to strcmp () except that it ignores the case.

#### int PyOS\_strnicmp (const char \*s1, const char \*s2, Py\_ssize\_t size)

Case insensitive comparison of strings. The function works almost identically to strncmp () except that it ignores the case.

## 6.8 Réflexion

## PyObject \*PyEval\_GetBuiltins (void)

Return value : Borrowed reference. Part of the Stable ABI. Renvoie un dictionnaire des fonctions natives de la frame en cours d'exécution, ou si aucune frame n'est exécutée, les fonctions natives du thread indiqué par le thread state.

#### PyObject \*PyEval\_GetLocals (void)

*Return value : Borrowed reference. Part of the* Stable ABI. Return a dictionary of the local variables in the current execution frame, or NULL if no frame is currently executing.

### PyObject \*PyEval\_GetGlobals (void)

*Return value : Borrowed reference. Part of the* Stable ABI. Return a dictionary of the global variables in the current execution frame, or NULL if no frame is currently executing.

### PyFrameObject \*PyEval\_GetFrame (void)

*Return value : Borrowed reference. Part of the* Stable ABI. Return the current thread state's frame, which is NULL if no frame is currently executing.

See also PyThreadState\_GetFrame().

### const char \*PyEval\_GetFuncName (PyObject \*func)

Part of the Stable ABI. Renvoie le nom de func s'il s'agit d'une fonction, d'une classe ou d'un objet d'instance, sinon le nom du type de func

## const char \*PyEval\_GetFuncDesc (PyObject \*func)

Part of the Stable ABI. Renvoie une description en chaîne de caractères, en fonction du type de func. Les valeurs renvoyées peuvent être " () " pour les fonction et les méthodes, \" constructor\", \" instance\", \" object\". Concaténé avec le résultat de PyEval\_GetFuncName (), le résultat sera une description de func

# 6.9 Codec registry and support functions

### int PyCodec\_Register (PyObject \*search\_function)

Part of the Stable ABI. Register a new codec search function.

As side effect, this tries to load the encodings package, if not yet done, to make sure that it is always first in the list of search functions.

### int PyCodec\_Unregister (PyObject \*search\_function)

Part of the Stable ABI since version 3.10. Unregister a codec search function and clear the registry's cache. If the search function is not registered, do nothing. Return 0 on success. Raise an exception and return -1 on error. Nouveau dans la version 3.10.

### int PyCodec\_KnownEncoding (const char \*encoding)

*Part of the* Stable ABI. Return 1 or 0 depending on whether there is a registered codec for the given *encoding*. This function always succeeds.

### PyObject \*PyCodec\_Encode (PyObject \*object, const char \*encoding, const char \*errors)

Return value: New reference. Part of the Stable ABI. Generic codec based encoding API.

object is passed through the encoder function found for the given *encoding* using the error handling method defined by *errors*. *errors* may be NULL to use the default method defined for the codec. Raises a LookupError if no encoder can be found.

PyObject \*PyCodec\_Decode (PyObject \*object, const char \*encoding, const char \*errors)

Return value: New reference. Part of the Stable ABI. Generic codec based decoding API.

*object* is passed through the decoder function found for the given *encoding* using the error handling method defined by *errors*. *errors* may be NULL to use the default method defined for the codec. Raises a LookupError if no encoder can be found.

## 6.9.1 Codec lookup API

In the following functions, the *encoding* string is looked up converted to all lower-case characters, which makes encodings looked up through this mechanism effectively case-insensitive. If no codec is found, a KeyError is set and NULL returned.

PyObject \*PyCodec\_Encoder (const char \*encoding)

Return value: New reference. Part of the Stable ABI. Get an encoder function for the given encoding.

PyObject \*PyCodec\_Decoder (const char \*encoding)

Return value: New reference. Part of the Stable ABI. Get a decoder function for the given encoding.

PyObject \*PyCodec\_IncrementalEncoder (const char \*encoding, const char \*errors)

Return value: New reference. Part of the Stable ABI. Get an IncrementalEncoder object for the given encoding.

PyObject \*PyCodec\_IncrementalDecoder (const char \*encoding, const char \*errors)

Return value: New reference. Part of the Stable ABI. Get an IncrementalDecoder object for the given encoding.

PyObject \*PyCodec\_StreamReader (const char \*encoding, PyObject \*stream, const char \*errors)

Return value: New reference. Part of the Stable ABI. Get a StreamReader factory function for the given encoding.

PyObject \*PyCodec\_StreamWriter (const char \*encoding, PyObject \*stream, const char \*errors)

Return value: New reference. Part of the Stable ABI. Get a StreamWriter factory function for the given encoding.

## 6.9.2 Registry API for Unicode encoding error handlers

int PyCodec RegisterError (const char \*name, PyObject \*error)

*Part of the* Stable ABI. Register the error handling callback function *error* under the given *name*. This callback function will be called by a codec when it encounters unencodable characters/undecodable bytes and *name* is specified as the error parameter in the call to the encode/decode function.

The callback gets a single argument, an instance of UnicodeEncodeError, UnicodeDecodeError or UnicodeTranslateError that holds information about the problematic sequence of characters or bytes and their offset in the original string (see *Objets exception Unicode* for functions to extract this information). The callback must either raise the given exception, or return a two-item tuple containing the replacement for the problematic sequence, and an integer giving the offset in the original string at which encoding/decoding should be resumed.

Return 0 on success, -1 on error.

PyObject \*PyCodec\_LookupError (const char \*name)

*Return value : New reference. Part of the* Stable ABI. Lookup the error handling callback function registered under *name.* As a special case NULL can be passed, in which case the error handling callback for "strict" will be returned.

PyObject \*PyCodec\_StrictErrors (PyObject \*exc)

Return value: Always NULL. Part of the Stable ABI. Raise exc as an exception.

### PyObject \*PyCodec\_IgnoreErrors (PyObject \*exc)

Return value: New reference. Part of the Stable ABI. Ignore the unicode error, skipping the faulty input.

## PyObject \*PyCodec\_ReplaceErrors (PyObject \*exc)

Return value: New reference. Part of the Stable ABI. Replace the unicode encode error with? or U+FFFD.

### PyObject \*PyCodec\_XMLCharRefReplaceErrors (PyObject \*exc)

Return value: New reference. Part of the Stable ABI. Replace the unicode encode error with XML character references.

### PyObject \*PyCodec\_BackslashReplaceErrors (PyObject \*exc)

*Return value : New reference. Part of the* Stable ABI. Replace the unicode encode error with backslash escapes ( $\xspace x$ ,  $\astrue u$  and  $\astrue U$ ).

## PyObject \*PyCodec\_NameReplaceErrors (PyObject \*exc)

Return value: New reference. Part of the Stable ABI since version 3.7. Replace the unicode encode error with  $N\{...\}$  escapes.

Nouveau dans la version 3.5.

# Couche d'abstraction des objets

Dans ce chapitre, les fonctions s'appliquent à des objets Python sans tenir compte de leur type, ou des classes d'objets au sens large (par exemple, tous les types numériques, ou tous les types de séquence). Quand ils sont utilisés sur des types d'objets qui ne correspondent pas, ils lèveront une exception Python.

Il n'est pas possible d'utiliser ces fonctions sur des objets qui n'ont pas été correctement initialisés, comme un objet liste qui a été créé avec <code>PyList\_New()</code> mais dont les éléments n'ont pas encore été mis à une valeur non-NULL.

# 7.1 Protocole Objet

### PyObject \*Py\_NotImplemented

Le singleton Not Implemented, utilisé pour signaler qu'une opération n'est pas implémentée pour la combinaison de types en question.

### Py\_RETURN\_NOTIMPLEMENTED

Traite proprement le renvoi de *Py\_NotImplemented* depuis l'intérieur d'une fonction C (c'est-à-dire, incrémente le compteur de référence de NotImplemented et le renvoie).

### int PyObject\_Print (PyObject \*o, FILE \*fp, int flags)

Écrit un objet o, dans le fichier fp. Renvoie -1 en cas d'erreur. L'argument flags est utilisé pour permettre certaines options de rendu. La seule option actuellement gérée est  $Py\_PRINT\_RAW$ ; si cet argument est fourni, le str() de l'objet est utilisé pour le rendu à la place de repr().

### int PyObject\_HasAttr(PyObject \*o, PyObject \*attr\_name)

*Part of the* Stable ABI. Renvoie 1 si *o* a l'attribut *attr\_name*, et 0 sinon. Ceci est équivalent à l'expression Python hasattr(o, attr\_name). Cette fonction réussit toujours.

Note that exceptions which occur while calling \_\_getattr\_\_() and \_\_getattribute\_\_() methods will get suppressed. To get error reporting use PyObject\_GetAttr() instead.

### int PyObject\_HasAttrString (PyObject \*o, const char \*attr\_name)

*Part of the* Stable ABI. Renvoie 1 si *o* a l'attribut *attr\_name*, et 0 sinon. Ceci est équivalent à l'expression Python hasattr(o, attr\_name). Cette fonction réussit toujours.

Note that exceptions which occur while calling \_\_getattr\_\_() and \_\_getattribute\_\_() methods and creating a temporary string object will get suppressed. To get error reporting use PyObject\_GetAttrString() instead.

### PyObject \*PyObject\_GetAttr (PyObject \*o, PyObject \*attr\_name)

*Return value : New reference. Part of the* Stable ABI. Retrieve an attribute named *attr\_name* from object *o*. Returns the attribute value on success, or NULL on failure. This is the equivalent of the Python expression o .attr\_name.

### PyObject \*PyObject\_GetAttrString (PyObject \*o, const char \*attr\_name)

*Return value : New reference. Part of the* Stable ABI. Retrieve an attribute named *attr\_name* from object *o*. Returns the attribute value on success, or NULL on failure. This is the equivalent of the Python expression o .attr\_name.

### PyObject \*PyObject\_GenericGetAttr(PyObject \*o, PyObject \*name)

Return value: New reference. Part of the Stable ABI. Accesseur d'attribut générique destiné à être mis dans le slot tp\_getattro d'un objet type. Recherche un descripteur dans le dictionnaire de classes du MRO de l'objet ainsi qu'un attribut dans le \_\_dict\_\_ de l'objet (si présent). Comme défini dans descriptors, les descripteurs de données sont prioritaires sur les attributs d'instance, contrairement aux autres descripteurs. Sinon, une AttributeError est levée.

#### int PyObject\_SetAttr (PyObject \*o, PyObject \*attr\_name, PyObject \*v)

Part of the Stable ABI. Définit la valeur de l'attribut nommé attr\_name, pour l'objet o, à la valeur v. Lève une exception et renvoie -1 en cas d'échec; renvoie 0 en cas de succès. Ceci est équivalent à l'instruction Python o.attr\_name = v.

If v is NULL, the attribute is deleted. This behaviour is deprecated in favour of using  $PyObject\_DelAttr()$ , but there are currently no plans to remove it.

### int PyObject\_SetAttrString (PyObject \*o, const char \*attr\_name, PyObject \*v)

Part of the Stable ABI. Définit la valeur de l'attribut nommé  $attr_name$ , pour l'objet o, à la valeur v. Lève une exception et renvoie -1 en cas d'échec; renvoie 0 en cas de succès. Ceci est équivalent à l'instruction Python o.attr name = v.

If v is NULL, the attribute is deleted, but this feature is deprecated in favour of using  $PyObject\_DelAttrString()$ .

#### int PyObject GenericSetAttr (PyObject \*o, PyObject \*name, PyObject \*value)

Part of the Stable ABI. Accesseur et suppresseur générique d'attributs qui est fait pour être mis dans le tp\_setattro d'un objet type. Il cherche un descripteur de données dans le dictionnaire de classes dans le MRO de l'objet et, si ce descripteur est trouvé, c'est lui qui est utilisé de préférence pour la suppression et la définition de l'attribut dans le dictionnaire d'instance. Sinon, l'attribut est défini ou supprimé dans le \_\_dict\_\_ de l'objet (si présent). En cas de succès, 0 est renvoyé, sinon une AttributeError est levée et -1 est renvoyé.

### int PyObject\_DelAttr (*PyObject* \*o, *PyObject* \*attr\_name)

Supprime l'attribut nommé *attr\_name*, pour l'objet *o*. Renvoie –1 en cas d'échec. Ceci est l'équivalent de l'expression Python del o.attr\_name.

### int PyObject\_DelAttrString (PyObject \*o, const char \*attr\_name)

Supprime l'attribut nommé *attr\_name*, pour l'objet *o*. Renvoie –1 en cas d'échec. Ceci est l'équivalent de l'expression Python del o.attr\_name.

### PyObject \*PyObject\_GenericGetDict (PyObject \*o, void \*context)

Return value : New reference. Part of the Stable ABI since version 3.10. Une implémentation générique de l'accesseur d'un descripteur d'un \_\_\_dict\_\_\_. Crée le dictionnaire si nécessaire.

This function may also be called to get the  $\__dict\__$  of the object o. Pass NULL for *context* when calling it. Since this function may need to allocate memory for the dictionary, it may be more efficient to call  $PyObject\_GetAttr()$  when accessing an attribute on the object.

On failure, returns NULL with an exception set.

Nouveau dans la version 3.3.

#### int PyObject\_GenericSetDict (PyObject \*o, PyObject \*value, void \*context)

Part of the Stable ABI since version 3.7. Une implémentation générique du mutateur d'un descripteur de \_\_dict\_\_. Cette implémentation n'autorise pas la suppression du dictionnaire.

Nouveau dans la version 3.3.

### PyObject \*\*\_PyObject\_GetDictPtr(PyObject \*obj)

Return a pointer to \_\_dict\_\_ of the object *obj*. If there is no \_\_dict\_\_, return NULL without setting an exception.

This function may need to allocate memory for the dictionary, so it may be more efficient to call <code>PyObject\_GetAttr()</code> when accessing an attribute on the object.

## PyObject \*PyObject\_RichCompare (PyObject \*o1, PyObject \*o2, int opid)

Return value: New reference. Part of the Stable ABI. Compare the values of o1 and o2 using the operation specified by opid, which must be one of Py\_LT, Py\_LE, Py\_EQ, Py\_NE, Py\_GT, or Py\_GE, corresponding to <, <=, ==, !=, >, or >= respectively. This is the equivalent of the Python expression o1 op o2, where op is the operator corresponding to opid. Returns the value of the comparison on success, or NULL on failure.

### int PyObject\_RichCompareBool (PyObject \*o1, PyObject \*o2, int opid)

Part of the Stable ABI. Compare les valeurs de o1 et o2 en utilisant l'opération spécifiée par opid, qui doit être Py\_LT, Py\_LE, Py\_EQ, Py\_NE, Py\_GT, ou Py\_GE, correspondant à <, <=, ==, !=, >, ou >= respectivement. Renvoie -1 en cas d'erreur, 0 si le résultat est faux, et 1 sinon. Ceci est l'équivalent de l'expression Python o1 op o2, où op est l'opérateur correspondant à opid.

**Note:** Si *o1* et *o2* sont le même objet, *PyObject\_RichCompareBool()* renvoie toujours 1 pour *Py\_EQ* et 0 pour *Py\_NE*.

#### PyObject \*PyObject\_Format (PyObject \*obj, PyObject \*format\_spec)

Part of the Stable ABI. Format obj using format\_spec. This is equivalent to the Python expression format (obj, format\_spec).

format\_spec may be NULL. In this case the call is equivalent to format (obj). Returns the formatted string on success, NULL on failure.

#### PyObject \*PyObject\_Repr (PyObject \*o)

Return value: New reference. Part of the Stable ABI. Compute a string representation of object o. Returns the string representation on success, NULL on failure. This is the equivalent of the Python expression repr (o). Called by the repr() built-in function.

Modifié dans la version 3.4 : Cette fonction inclut maintenant une assertion de débogage afin d'assurer qu'elle ne passe pas sous silence une exception active.

### PyObject \*PyObject\_ASCII (PyObject \*o)

Return value : New reference. Part of the Stable ABI. Comme  $PyObject\_Repr()$ , calcule une représentation en chaîne de caractères de l'objet o, mais échappe les caractères non ASCII dans la chaîne de caractères renvoyée par  $PyObject\_Repr()$  avec'  $\xspace x$ ,  $\uspace u$  ou  $\uspace u$ . Cela génère une chaîne de caractères similaire à celle renvoyée par  $PyObject\_Repr()$  en Python 2. Appelée par la fonction native ascii().

### PyObject \*PyObject\_Str (PyObject \*o)

Return value: New reference. Part of the Stable ABI. Compute a string representation of object o. Returns the string representation on success, NULL on failure. This is the equivalent of the Python expression str(o). Called by the str() built-in function and, therefore, by the print() function.

Modifié dans la version 3.4 : Cette fonction inclut maintenant une assertion de débogage afin d'assurer qu'elle ne passe pas sous silence une exception active.

#### PyObject \*PyObject\_Bytes (PyObject \*o)

Return value: New reference. Part of the Stable ABI. Compute a bytes representation of object o. NULL is returned on failure and a bytes object on success. This is equivalent to the Python expression bytes (o), when o is not an integer. Unlike bytes (o), a TypeError is raised when o is an integer instead of a zero-initialized bytes object.

### int PyObject\_IsSubclass (PyObject \*derived, PyObject \*cls)

Part of the Stable ABI. Renvoie 1 si la classe derived est identique à ou dérivée de la classe cls, renvoie 0 sinon. En cas d'erreur, renvoie -1.

Si *cls* est un *n*-uplet, la vérification est menée sur chaque entrée de *cls*. Le résultat sera 1 quand au moins une des vérifications renvoie 1, sinon ce sera 0.

Si *cls* a une méthode \_\_subclasscheck\_\_(), elle est appelée pour déterminer le statut de la sous-classe comme décrit dans PEP 3119. Sinon, *derived* est une sous-classe de *cls* si c'est une sous-classe directe ou indirecte, c'est-à-dire contenue dans cls.\_\_mro\_\_.

Normalement seulement les classes objets, c'est-à-dire les instances de type ou d'une classe dérivée, sont considérées classes. Cependant, les objets peuvent surcharger cela en ayant un attribut \_\_bases\_\_ (qui doit être un n-uplet de classes de bases).

#### int PyObject\_IsInstance (PyObject \*inst, PyObject \*cls)

Part of the Stable ABI. Renvoie 1 si inst est une instance de la classe cls ou une sous-classe de cls, ou 0 sinon. En cas d'erreur, renvoie -1 et initialise une exception.

Si *cls* est un *n*-uplet, la vérification est menée sur chaque entrée de *cls*. Le résultat sera 1 quand au moins une des vérifications renvoie 1, sinon ce sera 0.

Si *cls* a une méthode \_\_subclasscheck\_\_(), elle sera appelée pour déterminer le statut de la sous-classe comme décrit dans PEP 3119. Sinon, *inst* est une instance *cls* si sa classe est une sous-classe de *cls*.

Une instance *inst* peut surcharger ce qui est considéré comme sa classe en ayant un attribut \_\_class\_\_.

Un objet *cls* peut surcharger s'il est considéré comme une classe, et ce que ses classes de bases sont, en ayant un attribut \_\_bases\_\_ (qui doit être un *n*-uplet des classes de base).

### Py\_hash\_t PyObject\_Hash (PyObject \*o)

Part of the Stable ABI. Compute and return the hash value of an object o. On failure, return -1. This is the equivalent of the Python expression hash (o).

Modifié dans la version 3.2 : The return type is now Py\_hash\_t. This is a signed integer the same size as  $Py\_ssize\_t$ .

### Py\_hash\_t PyObject\_HashNotImplemented (PyObject \*o)

Part of the Stable ABI. Set a TypeError indicating that type (0) is not hashable and return -1. This function receives special treatment when stored in a tp\_hash slot, allowing a type to explicitly indicate to the interpreter that it is not hashable.

### int PyObject\_IsTrue (PyObject \*o)

Part of the Stable ABI. Returns 1 if the object o is considered to be true, and 0 otherwise. This is equivalent to the Python expression not not o. On failure, return -1.

### int PyObject\_Not (PyObject \*o)

Part of the Stable ABI. Returns 0 if the object o is considered to be true, and 1 otherwise. This is equivalent to the Python expression not o. On failure, return -1.

## PyObject \*PyObject \*o)

Return value: New reference. Part of the Stable ABI. When o is non-NULL, returns a type object corresponding to the object type of object o. On failure, raises SystemError and returns NULL. This is equivalent to the Python expression type (o). This function increments the reference count of the return value. There's really no reason to use this function instead of the  $Py\_TYPE()$  function, which returns a pointer of type PyTypeObject\*, except when the incremented reference count is needed.

#### int PyObject\_TypeCheck (PyObject \*o, PyTypeObject \*type)

Return non-zero if the object o is of type type or a subtype of type, and 0 otherwise. Both parameters must be non-NULL.

#### Py\_ssize\_t PyObject\_Size (PyObject \*o)

## Py\_ssize\_t PyObject\_Length (PyObject \*0)

*Part of the* Stable ABI. Return the length of object o. If the object o provides either the sequence and mapping protocols, the sequence length is returned. On error, -1 is returned. This is the equivalent to the Python expression len(o).

#### Py\_ssize\_t PyObject\_LengthHint (PyObject \*o, Py\_ssize\_t defaultvalue)

Return an estimated length for the object o. First try to return its actual length, then an estimate using \_\_length\_hint\_\_(), and finally return the default value. On error return -1. This is the equivalent to the Python expression operator.length\_hint(o, defaultvalue).

Nouveau dans la version 3.4.

### PyObject \*PyObject\_GetItem (PyObject \*o, PyObject \*key)

Return value: New reference. Part of the Stable ABI. Return element of o corresponding to the object key or NULL on failure. This is the equivalent of the Python expression o[key].

## int PyObject\_SetItem (PyObject \*o, PyObject \*key, PyObject \*v)

Part of the Stable ABI. Map the object key to the value v. Raise an exception and return -1 on failure; return 0 on success. This is the equivalent of the Python statement o[key] = v. This function *does not* steal a reference to v.

## int PyObject\_DelItem (PyObject \*o, PyObject \*key)

Part of the Stable ABI. Remove the mapping for the object key from the object o. Return -1 on failure. This is equivalent to the Python statement del o[key].

### PyObject \*PyObject\_Dir (PyObject \*o)

Return value: New reference. Part of the Stable ABI. This is equivalent to the Python expression dir(0), returning a (possibly empty) list of strings appropriate for the object argument, or NULL if there was an error. If the argument is NULL, this is like the Python dir(), returning the names of the current locals; in this case, if no execution frame is active then NULL is returned but PyErr\_Occurred() will return false.

### PyObject \*PyObject\_GetIter (PyObject \*o)

Return value: New reference. Part of the Stable ABI. This is equivalent to the Python expression iter(0). It returns a new iterator for the object argument, or the object itself if the object is already an iterator. Raises TypeError and returns NULL if the object cannot be iterated.

### PyObject \*PyObject\_GetAIter (PyObject \*o)

Return value: New reference. Part of the Stable ABI since version 3.10. This is the equivalent to the Python expression aiter(o). Takes an AsyncIterable object and returns an AsyncIterator for it. This is typically a new iterator but if the argument is an AsyncIterator, this returns itself. Raises TypeError and returns NULL if the object cannot be iterated.

Nouveau dans la version 3.10.

## 7.2 Call Protocol

CPython supports two different calling protocols : *tp\_call* and vectorcall.

## 7.2.1 The tp\_call Protocol

Instances of classes that set  $tp\_call$  are callable. The signature of the slot is :

```
PyObject *tp_call(PyObject *callable, PyObject *args, PyObject *kwargs);
```

A call is made using a tuple for the positional arguments and a dict for the keyword arguments, similarly to callable (\*args, \*\*kwargs) in Python code. *args* must be non-NULL (use an empty tuple if there are no arguments) but *kwargs* may be *NULL* if there are no keyword arguments.

This convention is not only used by  $tp\_call$ :  $tp\_new$  and  $tp\_init$  also pass arguments this way.

To call an object, use PyObject\_Call() or another call API.

## 7.2.2 The Vectorcall Protocol

Nouveau dans la version 3.9.

The vectorcall protocol was introduced in PEP 590 as an additional protocol for making calls more efficient.

As rule of thumb, CPython will prefer the vectorcall for internal calls if the callable supports it. However, this is not a hard rule. Additionally, some third-party extensions use  $tp\_call$  directly (rather than using  $PyObject\_Call$  ()). Therefore, a class supporting vectorcall must also implement  $tp\_call$ . Moreover, the callable must behave the same regardless of which protocol is used. The recommended way to achieve this is by setting  $tp\_call$  to  $PyVectorcall\_Call$  (). This bears repeating:

**Avertissement:** A class supporting vectorcall **must** also implement  $tp\_call$  with the same semantics.

A class should not implement vectorcall if that would be slower than *tp\_call*. For example, if the callee needs to convert the arguments to an args tuple and kwargs dict anyway, then there is no point in implementing vectorcall.

Classes can implement the vectorcall protocol by enabling the  $Py\_TPFLAGS\_HAVE\_VECTORCALL$  flag and setting  $tp\_vectorcall\_offset$  to the offset inside the object structure where a vectorcallfunc appears. This is a pointer to a function with the following signature :

typedef *PyObject* \*(\*vectorcallfunc)(*PyObject* \*callable, *PyObject* \*const \*args, size\_t nargsf, *PyObject* \*kwnames)

- *callable* is the object being called.
- *args* is a C array consisting of the positional arguments followed by the values of the keyword arguments.

  This can be *NULL* if there are no arguments.
- *nargsf* is the number of positional arguments plus possibly the PY\_VECTORCALL\_ARGUMENTS\_OFFSET flag. To get the actual number of positional arguments from *nargsf*, use *PyVectorcall\_NARGS()*.
- *kwnames* is a tuple containing the names of the keyword arguments; in other words, the keys of the kwargs dict. These names must be strings (instances of str or a subclass) and they must be unique. If there are no keyword arguments, then *kwnames* can instead be *NULL*.

#### PY VECTORCALL ARGUMENTS OFFSET

If this flag is set in a vectorcall *nargsf* argument, the callee is allowed to temporarily change args[-1]. In other words, *args* points to argument 1 (not 0) in the allocated vector. The callee must restore the value of args[-1] before returning.

For PyObject\_VectorcallMethod(), this flag means instead that args[0] may be changed.

Whenever they can do so cheaply (without additional allocation), callers are encouraged to use PY\_VECTORCALL\_ARGUMENTS\_OFFSET. Doing so will allow callables such as bound methods to make their onward calls (which include a prepended *self* argument) very efficiently.

To call an object that implements vectorcall, use a *call API* function as with any other callable. <code>PyObject\_Vectorcall()</code> will usually be most efficient.

Note: In CPython 3.8, the vectorcall API and related functions were available provisionally under names with a leading underscore: \_PyObject\_Vectorcall, \_Py\_TPFLAGS\_HAVE\_VECTORCALL, \_PyObject\_VectorcallMethod, \_PyVectorcall\_Function, \_PyObject\_CallOneArg, \_PyObject\_CallMethodNoArgs, \_PyObject\_CallMethodOneArg. Additionally, PyObject\_VectorcallDict was available as \_PyObject\_FastCallDict. The old names are still defined as aliases of the new, non-underscored names.

#### Contrôle de la récursion

When using *tp\_call*, callees do not need to worry about *recursion*: CPython uses *Py\_EnterRecursiveCall()* and *Py\_LeaveRecursiveCall()* for calls made using *tp\_call*.

For efficiency, this is not the case for calls done using vectorcall: the callee should use *Py\_EnterRecursiveCall* and *Py\_LeaveRecursiveCall* if needed.

## **Vectorcall Support API**

### Py\_ssize\_t PyVectorcall\_NARGS (size\_t nargsf)

Given a vectorcall nargsf argument, return the actual number of arguments. Currently equivalent to :

```
(Py_ssize_t) (nargsf & ~PY_VECTORCALL_ARGUMENTS_OFFSET)
```

However, the function PyVectorcall\_NARGS should be used to allow for future extensions.

Nouveau dans la version 3.8.

### vectorcallfunc PyVectorcall\_Function (PyObject \*op)

If op does not support the vectorcall protocol (either because the type does not or because the specific instance does not), return NULL. Otherwise, return the vectorcall function pointer stored in op. This function never raises an exception.

This is mostly useful to check whether or not op supports vectorcall, which can be done by checking PyVectorcall\_Function(op) != NULL.

Nouveau dans la version 3.8.

### PyObject \*PyVectorcall\_Call (PyObject \*callable, PyObject \*tuple, PyObject \*dict)

Call callable's vectorcallfunc with positional and keyword arguments given in a tuple and dict, respectively. This is a specialized function, intended to be put in the  $tp\_call$  slot or be used in an implementation of  $tp\_call$ . It does not check the  $Py\_TPFLAGS\_HAVE\_VECTORCALL$  flag and it does not fall back to  $tp\_call$ . Nouveau dans la version 3.8.

7.2. Call Protocol 85

## 7.2.3 Object Calling API

Various functions are available for calling a Python object. Each converts its arguments to a convention supported by the called object – either *tp\_call* or vectorcall. In order to do as little conversion as possible, pick one that best fits the format of data you have available.

The following table summarizes the available functions; please see individual documentation for details.

Fonction	callable	args	kwargs
PyObject_Call()	PyObject *	tuple	dict/NULL
PyObject_CallNoArgs()	PyObject *		
PyObject_CallOneArg()	PyObject *	1 object	
PyObject_CallObject()	PyObject *	tuple/NULL	
PyObject_CallFunction()	PyObject *	format	
PyObject_CallMethod()	obj + char*	format	
PyObject_CallFunctionObjArgs()	PyObject *	variadic	
PyObject_CallMethodObjArgs()	obj + name	variadic	
PyObject_CallMethodNoArgs()	obj + name		
PyObject_CallMethodOneArg()	obj + name	1 object	
PyObject_Vectorcall()	PyObject *	vectorcall	vectorcall
PyObject_VectorcallDict()	PyObject *	vectorcall	dict/NULL
PyObject_VectorcallMethod()	arg + name	vectorcall	vectorcall

### PyObject \*PyObject\_Call (PyObject \*callable, PyObject \*args, PyObject \*kwargs)

*Return value : New reference. Part of the* Stable ABI. Appelle un objet Python appelable *callable*, avec des arguments donnés par le *n*-uplet *args*, et des arguments nommés donnés par le dictionnaire *kwargs*.

args must not be NULL; use an empty tuple if no arguments are needed. If no named arguments are needed, kwargs can be NULL.

Return the result of the call on success, or raise an exception and return NULL on failure.

Ceci est l'équivalent de l'expression Python: callable (\*args, \*\*kwargs).

#### PyObject \*PyObject CallNoArgs (PyObject \*callable)

Part of the Stable ABI since version 3.10. Call a callable Python object callable without any arguments. It is the most efficient way to call a callable Python object without any argument.

Return the result of the call on success, or raise an exception and return NULL on failure.

Nouveau dans la version 3.9.

### PyObject \*PyObject\_CallOneArg (PyObject \*callable, PyObject \*arg)

Call a callable Python object *callable* with exactly 1 positional argument *arg* and no keyword arguments.

Return the result of the call on success, or raise an exception and return NULL on failure.

Nouveau dans la version 3.9.

### PyObject \*PyObject\_CallObject (PyObject \*callable, PyObject \*args)

Return value: New reference. Part of the Stable ABI. Call a callable Python object callable, with arguments given by the tuple args. If no arguments are needed, then args can be NULL.

Return the result of the call on success, or raise an exception and return NULL on failure.

Ceci est l'équivalent de l'expression Python : callable (\*args).

### PyObject \*PyObject\_CallFunction (PyObject \*callable, const char \*format, ...)

Return value: New reference. Part of the Stable ABI. Call a callable Python object callable, with a variable number of C arguments. The C arguments are described using a Py\_BuildValue() style format string. The format can be NULL, indicating that no arguments are provided.

Return the result of the call on success, or raise an exception and return NULL on failure.

Ceci est l'équivalent de l'expression Python : callable (\*args).

Note that if you only pass PyObject\* args, PyObject\_CallFunctionObjArgs() is a faster alternative.

Modifié dans la version 3.4 : The type of *format* was changed from char \*.

```
PyObject *PyObject_CallMethod (PyObject *obj, const char *name, const char *format, ...)
```

Return value: New reference. Part of the Stable ABI. Call the method named name of object obj with a variable number of C arguments. The C arguments are described by a Py\_BuildValue() format string that should produce a tuple.

The format can be *NULL*, indicating that no arguments are provided.

Return the result of the call on success, or raise an exception and return NULL on failure.

This is the equivalent of the Python expression: obj.name(arg1, arg2, ...).

Note that if you only pass PyObject\* args, PyObject\_CallMethodObjArgs() is a faster alternative.

Modifié dans la version 3.4: The types of *name* and *format* were changed from char \*.

```
PyObject *PyObject CallFunctionObjArgs (PyObject *callable, ...)
```

*Return value : New reference. Part of the* Stable ABI. Call a callable Python object *callable*, with a variable number of PyObject\* arguments. The arguments are provided as a variable number of parameters followed by *NULL*.

Return the result of the call on success, or raise an exception and return NULL on failure.

This is the equivalent of the Python expression: callable (arg1, arg2, ...).

```
PyObject *PyObject_CallMethodObjArgs (PyObject *obj, PyObject *name, ...)
```

Return value: New reference. Part of the Stable ABI. Call a method of the Python object obj, where the name of the method is given as a Python string object in name. It is called with a variable number of PyObject\* arguments. The arguments are provided as a variable number of parameters followed by NULL.

Return the result of the call on success, or raise an exception and return NULL on failure.

```
PyObject *PyObject_CallMethodNoArgs (PyObject *obj, PyObject *name)
```

Call a method of the Python object *obj* without arguments, where the name of the method is given as a Python string object in *name*.

Return the result of the call on success, or raise an exception and return NULL on failure.

Nouveau dans la version 3.9.

```
PyObject *PyObject CallMethodOneArg (PyObject *obj, PyObject *name, PyObject *arg)
```

Call a method of the Python object *obj* with a single positional argument *arg*, where the name of the method is given as a Python string object in *name*.

Return the result of the call on success, or raise an exception and return NULL on failure.

Nouveau dans la version 3.9.

```
PyObject *PyObject *PyObject *const *args, size_t nargsf, PyObject *kwnames)
```

Call a callable Python object *callable*. The arguments are the same as for *vectorcallfunc*. If *callable* supports *vectorcall*, this directly calls the vectorcall function stored in *callable*.

Return the result of the call on success, or raise an exception and return NULL on failure.

Nouveau dans la version 3.9.

```
PyObject *PyObject_VectorcallDict (PyObject *callable, PyObject *const *args, size_t nargsf, PyObject *kwdict)
```

Call *callable* with positional arguments passed exactly as in the *vectorcall* protocol, but with keyword arguments passed as a dictionary *kwdict*. The *args* array contains only the positional arguments.

Regardless of which protocol is used internally, a conversion of arguments needs to be done. Therefore, this function should only be used if the caller already has a dictionary ready to use for the keyword arguments, but not a tuple for the positional arguments.

Nouveau dans la version 3.9.

7.2. Call Protocol 87

# PyObject \*PyObject\_VectorcallMethod (PyObject \*name, PyObject \*const \*args, size\_t nargsf, PyObject \*kwnames)

Call a method using the vectorcall calling convention. The name of the method is given as a Python string *name*. The object whose method is called is args[0], and the args array starting at args[1] represents the arguments of the call. There must be at least one positional argument. nargsf is the number of positional arguments including args[0], plus PY\_VECTORCALL\_ARGUMENTS\_OFFSET if the value of args[0] may temporarily be changed. Keyword arguments can be passed just like in  $PyObject_Vectorcall()$ .

If the object has the  $Py\_TPFLAGS\_METHOD\_DESCRIPTOR$  feature, this will call the unbound method object with the full args vector as arguments.

Return the result of the call on success, or raise an exception and return NULL on failure.

Nouveau dans la version 3.9.

## 7.2.4 Call Support API

### int PyCallable\_Check (PyObject \*o)

Part of the Stable ABI. Détermine si l'objet o est appelable. Renvoie 1 si c'est le cas, et 0 sinon. Cette fonction réussit toujours.

## 7.3 Number Protocol

#### int PyNumber\_Check (PyObject \*o)

Part of the Stable ABI. Returns 1 if the object o provides numeric protocols, and false otherwise. This function always succeeds.

Modifié dans la version 3.8 : Returns 1 if o is an index integer.

### PyObject \*PyNumber\_Add (PyObject \*o1, PyObject \*o2)

Return value: New reference. Part of the Stable ABI. Returns the result of adding o1 and o2, or NULL on failure. This is the equivalent of the Python expression o1 + o2.

#### PyObject \*PyNumber\_Subtract (PyObject \*o1, PyObject \*o2)

Return value: New reference. Part of the Stable ABI. Returns the result of subtracting o2 from o1, or NULL on failure. This is the equivalent of the Python expression o1 - o2.

## PyObject \*PyNumber\_Multiply (PyObject \*o1, PyObject \*o2)

Return value: New reference. Part of the Stable ABI. Returns the result of multiplying o1 and o2, or NULL on failure. This is the equivalent of the Python expression o1 \* o2.

## PyObject \*PyNumber\_MatrixMultiply (PyObject \*o1, PyObject \*o2)

Return value: New reference. Part of the Stable ABI since version 3.7. Returns the result of matrix multiplication on o1 and o2, or NULL on failure. This is the equivalent of the Python expression o1 @ o2. Nouveau dans la version 3.5.

### PyObject \*PyNumber\_FloorDivide (PyObject \*o1, PyObject \*o2)

*Return value : New reference. Part of the* Stable ABI. Return the floor of o1 divided by o2, or NULL on failure. This is the equivalent of the Python expression o1 // o2.

### PyObject \*PyNumber\_TrueDivide (PyObject \*o1, PyObject \*o2)

Return value: New reference. Part of the Stable ABI. Return a reasonable approximation for the mathematical value of o1 divided by o2, or NULL on failure. The return value is "approximate" because binary floating point numbers are approximate; it is not possible to represent all real numbers in base two. This function can return a floating point value when passed two integers. This is the equivalent of the Python expression o1 / o2.

#### PyObject \*PyNumber\_Remainder (PyObject \*o1, PyObject \*o2)

Return value: New reference. Part of the Stable ABI. Returns the remainder of dividing o1 by o2, or NULL on failure. This is the equivalent of the Python expression o1 % o2.

#### PyObject \*PyNumber\_Divmod (PyObject \*o1, PyObject \*o2)

Return value: New reference. Part of the Stable ABI. See the built-in function divmod(). Returns NULL on failure. This is the equivalent of the Python expression divmod(o1, o2).

#### PyObject \*PyNumber\_Power (PyObject \*o1, PyObject \*o2, PyObject \*o3)

Return value: New reference. Part of the Stable ABI. See the built-in function pow(). Returns NULL on failure. This is the equivalent of the Python expression pow(o1, o2, o3), where o3 is optional. If o3 is to be ignored, pass  $Py\_None$  in its place (passing NULL for o3 would cause an illegal memory access).

### PyObject \*PyNumber\_Negative (PyObject \*o)

Return value: New reference. Part of the Stable ABI. Returns the negation of o on success, or NULL on failure. This is the equivalent of the Python expression  $-\circ$ .

### PyObject \*PyNumber\_Positive (PyObject \*o)

*Return value : New reference. Part of the* Stable ABI. Returns *o* on success, or NULL on failure. This is the equivalent of the Python expression +0.

## PyObject \*PyNumber\_Absolute (PyObject \*o)

*Return value : New reference. Part of the* Stable ABI. Returns the absolute value of o, or NULL on failure. This is the equivalent of the Python expression abs (o).

#### PyObject \*PyNumber Invert (PyObject \*o)

*Return value : New reference. Part of the* Stable ABI. Returns the bitwise negation of o on success, or NULL on failure. This is the equivalent of the Python expression  $\sim \circ$ .

### PyObject \*PyNumber\_Lshift (PyObject \*o1, PyObject \*o2)

Return value: New reference. Part of the Stable ABI. Returns the result of left shifting o1 by o2 on success, or NULL on failure. This is the equivalent of the Python expression o1 << o2.

#### PyObject \*PyNumber\_Rshift (PyObject \*o1, PyObject \*o2)

Return value: New reference. Part of the Stable ABI. Returns the result of right shifting o1 by o2 on success, or NULL on failure. This is the equivalent of the Python expression o1 >> o2.

#### PyObject \*PyNumber\_And (PyObject \*o1, PyObject \*o2)

Return value: New reference. Part of the Stable ABI. Returns the "bitwise and" of o1 and o2 on success and NULL on failure. This is the equivalent of the Python expression o1 & o2.

### PyObject \*PyNumber\_Xor (PyObject \*o1, PyObject \*o2)

*Return value : New reference. Part of the* Stable ABI. Returns the "bitwise exclusive or" of *o1* by *o2* on success, or NULL on failure. This is the equivalent of the Python expression o1 ^ o2.

## PyObject \*PyNumber\_Or (PyObject \*o1, PyObject \*o2)

Return value: New reference. Part of the Stable ABI. Returns the "bitwise or" of o1 and o2 on success, or NULL on failure. This is the equivalent of the Python expression o1 | o2.

### PyObject \*PyNumber\_InPlaceAdd (PyObject \*o1, PyObject \*o2)

Return value: New reference. Part of the Stable ABI. Returns the result of adding o1 and o2, or NULL on failure. The operation is done in-place when o1 supports it. This is the equivalent of the Python statement o1 += o2.

### PyObject \*PyNumber\_InPlaceSubtract (PyObject \*o1, PyObject \*o2)

Return value: New reference. Part of the Stable ABI. Returns the result of subtracting o2 from o1, or NULL on failure. The operation is done in-place when o1 supports it. This is the equivalent of the Python statement o1 -= o2.

7.3. Number Protocol 89

#### PyObject \*PyNumber\_InPlaceMultiply (PyObject \*o1, PyObject \*o2)

Return value: New reference. Part of the Stable ABI. Returns the result of multiplying o1 and o2, or NULL on failure. The operation is done in-place when o1 supports it. This is the equivalent of the Python statement o1 \*= o2.

## PyObject \*PyNumber\_InPlaceMatrixMultiply (PyObject \*o1, PyObject \*o2)

Return value: New reference. Part of the Stable ABI since version 3.7. Returns the result of matrix multiplication on o1 and o2, or NULL on failure. The operation is done in-place when o1 supports it. This is the equivalent of the Python statement o1 @= o2.

Nouveau dans la version 3.5.

## PyObject \*PyNumber\_InPlaceFloorDivide (PyObject \*o1, PyObject \*o2)

Return value: New reference. Part of the Stable ABI. Returns the mathematical floor of dividing o1 by o2, or NULL on failure. The operation is done *in-place* when o1 supports it. This is the equivalent of the Python statement o1 //= o2.

### PyObject \*PyNumber\_InPlaceTrueDivide (PyObject \*o1, PyObject \*o2)

Return value: New reference. Part of the Stable ABI. Return a reasonable approximation for the mathematical value of o1 divided by o2, or NULL on failure. The return value is "approximate" because binary floating point numbers are approximate; it is not possible to represent all real numbers in base two. This function can return a floating point value when passed two integers. The operation is done *in-place* when o1 supports it. This is the equivalent of the Python statement o1 /= o2.

#### PyObject \*PyNumber\_InPlaceRemainder (PyObject \*o1, PyObject \*o2)

Return value: New reference. Part of the Stable ABI. Returns the remainder of dividing o1 by o2, or NULL on failure. The operation is done in-place when o1 supports it. This is the equivalent of the Python statement o1 %= o2.

### PyObject \*PyNumber\_InPlacePower (PyObject \*o1, PyObject \*o2, PyObject \*o3)

Return value: New reference. Part of the Stable ABI. See the built-in function pow(). Returns NULL on failure. The operation is done *in-place* when o1 supports it. This is the equivalent of the Python statement o1 \*\*= o2 when o3 is  $Py\_None$ , or an in-place variant of pow(o1, o2, o3) otherwise. If o3 is to be ignored, pass  $Py\_None$  in its place (passing NULL for o3 would cause an illegal memory access).

### PyObject \*PyNumber\_InPlaceLshift (PyObject \*o1, PyObject \*o2)

Return value: New reference. Part of the Stable ABI. Returns the result of left shifting o1 by o2 on success, or NULL on failure. The operation is done *in-place* when o1 supports it. This is the equivalent of the Python statement o1 <<= o2.

#### PyObject \*PyNumber\_InPlaceRshift (PyObject \*o1, PyObject \*o2)

Return value: New reference. Part of the Stable ABI. Returns the result of right shifting o1 by o2 on success, or NULL on failure. The operation is done *in-place* when o1 supports it. This is the equivalent of the Python statement o1 >>= o2.

### PyObject \*PyNumber\_InPlaceAnd (PyObject \*o1, PyObject \*o2)

Return value: New reference. Part of the Stable ABI. Returns the "bitwise and" of o1 and o2 on success and NULL on failure. The operation is done *in-place* when o1 supports it. This is the equivalent of the Python statement o1 &= o2.

### PyObject \*PyNumber\_InPlaceXor (PyObject \*o1, PyObject \*o2)

Return value: New reference. Part of the Stable ABI. Returns the "bitwise exclusive or" of o1 by o2 on success, or NULL on failure. The operation is done *in-place* when o1 supports it. This is the equivalent of the Python statement  $o1 ^= o2$ .

#### PyObject \*PyNumber\_InPlaceOr (PyObject \*o1, PyObject \*o2)

Return value: New reference. Part of the Stable ABI. Returns the "bitwise or" of o1 and o2 on success, or NULL

on failure. The operation is done *in-place* when o1 supports it. This is the equivalent of the Python statement o1 = o2.

### PyObject \*PyNumber\_Long (PyObject \*o)

*Return value : New reference. Part of the* Stable ABI. Returns the *o* converted to an integer object on success, or NULL on failure. This is the equivalent of the Python expression int (0).

### PyObject \*PyNumber\_Float (PyObject \*o)

*Return value : New reference. Part of the* Stable ABI. Returns the *o* converted to a float object on success, or NULL on failure. This is the equivalent of the Python expression float (o).

### PyObject \*PyNumber\_Index (PyObject \*o)

*Return value : New reference. Part of the* Stable ABI. Returns the *o* converted to a Python int on success or NULL with a TypeError exception raised on failure.

Modifié dans la version 3.10: The result always has exact type int. Previously, the result could have been an instance of a subclass of int.

### PyObject \*PyNumber\_ToBase (PyObject \*n, int base)

Return value: New reference. Part of the Stable ABI. Returns the integer n converted to base base as a string. The base argument must be one of 2, 8, 10, or 16. For base 2, 8, or 16, the returned string is prefixed with a base marker of '0b', '0o', or '0x', respectively. If n is not a Python int, it is converted with PyNumber\_Index() first.

```
Py_ssize_t PyNumber_AsSsize_t (PyObject *o, PyObject *exc)
```

Part of the Stable ABI. Returns o converted to a  $Py\_ssize\_t$  value if o can be interpreted as an integer. If the call fails, an exception is raised and -1 is returned.

If o can be converted to a Python int but the attempt to convert to a  $Py\_ssize\_t$  value would raise an OverflowError, then the exc argument is the type of exception that will be raised (usually IndexError or OverflowError). If exc is NULL, then the exception is cleared and the value is clipped to PY\_SSIZE\_T\_MIN for a negative integer or PY\_SSIZE\_T\_MAX for a positive integer.

#### int PyIndex\_Check (PyObject \*o)

Part of the Stable ABI since version 3.8. Returns 1 if o is an index integer (has the nb\_index slot of the tp\_as\_number structure filled in), and 0 otherwise. This function always succeeds.

# 7.4 Sequence Protocol

#### int PySequence\_Check (PyObject \*o)

Part of the Stable ABI. Return 1 if the object provides the sequence protocol, and 0 otherwise. Note that it returns 1 for Python classes with a \_\_getitem\_\_() method, unless they are dict subclasses, since in general it is impossible to determine what type of keys the class supports. This function always succeeds.

### Py\_ssize\_t PySequence\_Size (PyObject \*o)

## Py\_ssize\_t PySequence\_Length (PyObject \*o)

Part of the Stable ABI. Returns the number of objects in sequence o on success, and -1 on failure. This is equivalent to the Python expression len (0).

### PyObject \*PySequence\_Concat (PyObject \*o1, PyObject \*o2)

Return value: New reference. Part of the Stable ABI. Return the concatenation of o1 and o2 on success, and NULL on failure. This is the equivalent of the Python expression o1 + o2.

### PyObject \*PySequence\_Repeat (PyObject \*o, Py\_ssize\_t count)

Return value: New reference. Part of the Stable ABI. Return the result of repeating sequence object o count times, or NULL on failure. This is the equivalent of the Python expression o \* count.

#### PyObject \*PySequence\_InPlaceConcat (PyObject \*o1, PyObject \*o2)

Return value: New reference. Part of the Stable ABI. Return the concatenation of o1 and o2 on success, and NULL on failure. The operation is done *in-place* when o1 supports it. This is the equivalent of the Python expression o1 += o2.

#### PyObject \*PySequence InPlaceRepeat (PyObject \*o, Py ssize t count)

Return value: New reference. Part of the Stable ABI. Return the result of repeating sequence object o count times, or NULL on failure. The operation is done *in-place* when o supports it. This is the equivalent of the Python expression o \*= count.

### PyObject \*PySequence\_GetItem (PyObject \*o, Py\_ssize\_t i)

*Return value : New reference. Part of the* Stable ABI. Return the *i*th element of o, or NULL on failure. This is the equivalent of the Python expression o[i].

### PyObject \*PySequence\_GetSlice (PyObject \*o, Py\_ssize\_t i1, Py\_ssize\_t i2)

Return value: New reference. Part of the Stable ABI. Return the slice of sequence object o between il and i2, or NULL on failure. This is the equivalent of the Python expression o[i1:i2].

### int PySequence\_SetItem (PyObject \*o, Py\_ssize\_t i, PyObject \*v)

Part of the Stable ABI. Assign object v to the *i*th element of o. Raise an exception and return -1 on failure; return 0 on success. This is the equivalent of the Python statement o[i] = v. This function *does not* steal a reference to v

If v is NULL, the element is deleted, but this feature is deprecated in favour of using  $PySequence\_DelItem()$ .

### int PySequence\_DelItem (PyObject \*o, Py\_ssize\_t i)

*Part of the* Stable ABI. Delete the *i*th element of object o. Returns -1 on failure. This is the equivalent of the Python statement del o[i].

#### int PySequence\_SetSlice (PyObject \*o, Py\_ssize\_t i1, Py\_ssize\_t i2, PyObject \*v)

Part of the Stable ABI. Assign the sequence object v to the slice in sequence object o from i1 to i2. This is the equivalent of the Python statement o[i1:i2] = v.

## int PySequence\_DelSlice (PyObject \*o, Py\_ssize\_t i1, Py\_ssize\_t i2)

Part of the Stable ABI. Delete the slice in sequence object o from il to i2. Returns -1 on failure. This is the equivalent of the Python statement del o[i1:i2].

### Py\_ssize\_t PySequence\_Count (PyObject \*o, PyObject \*value)

Part of the Stable ABI. Return the number of occurrences of value in o, that is, return the number of keys for which o [key] == value. On failure, return -1. This is equivalent to the Python expression o.count (value).

### int PySequence\_Contains (*PyObject* \*o, *PyObject* \*value)

*Part of the* Stable ABI. Determine if o contains *value*. If an item in o is equal to *value*, return 1, otherwise return 0. On error, return -1. This is equivalent to the Python expression value in o.

### Py\_ssize\_t PySequence\_Index (PyObject \*o, PyObject \*value)

*Part of the* Stable ABI. Return the first index *i* for which o[i] = value. On error, return -1. This is equivalent to the Python expression o.index(value).

### PyObject \*PySequence\_List (PyObject \*o)

Return value: New reference. Part of the Stable ABI. Return a list object with the same contents as the sequence or iterable o, or NULL on failure. The returned list is guaranteed to be new. This is equivalent to the Python expression list (o).

### PyObject \*PySequence\_Tuple (PyObject \*o)

Return value: New reference. Part of the Stable ABI. Return a tuple object with the same contents as the sequence or iterable o, or NULL on failure. If o is a tuple, a new reference will be returned, otherwise a tuple will be constructed with the appropriate contents. This is equivalent to the Python expression tuple ( $\circ$ ).

#### PyObject \*PySequence\_Fast (PyObject \*o, const char \*m)

Return value: New reference. Part of the Stable ABI. Return the sequence or iterable o as an object usable by the other PySequence\_Fast\* family of functions. If the object is not a sequence or iterable, raises TypeError with m as the message text. Returns NULL on failure.

The PySequence\_Fast\* functions are thus named because they assume o is a PyTupleObject or a PyListObject and access the data fields of o directly.

As a CPython implementation detail, if o is already a sequence or list, it will be returned.

### Py\_ssize\_t PySequence\_Fast\_GET\_SIZE (PyObject \*o)

Returns the length of o, assuming that o was returned by  $PySequence\_Fast$  () and that o is not NULL. The size can also be retrieved by calling  $PySequence\_Size$  () on o, but  $PySequence\_Fast\_GET\_SIZE$  () is faster because it can assume o is a list or tuple.

## PyObject \*PySequence\_Fast\_GET\_ITEM (PyObject \*o, Py\_ssize\_t i)

*Return value : Borrowed reference.* Return the *i*th element of o, assuming that o was returned by  $PySequence\ Fast()$ , o is not NULL, and that i is within bounds.

## PyObject \*\*PySequence\_Fast\_ITEMS (PyObject \*o)

Return the underlying array of PyObject pointers. Assumes that o was returned by  $PySequence\_Fast()$  and o is not NULL.

Note, if a list gets resized, the reallocation may relocate the items array. So, only use the underlying array pointer in contexts where the sequence cannot change.

### PyObject \*PySequence\_ITEM (PyObject \*o, Py\_ssize\_t i)

Return value: New reference. Return the ith element of o or NULL on failure. Faster form of PySequence\_GetItem() but without checking that PySequence\_Check() on o is true and without adjustment for negative indices.

# 7.5 Protocole de correspondance

Voir aussi PyObject\_GetItem(), PyObject\_SetItem() et PyObject\_DelItem().

### int PyMapping\_Check (PyObject \*o)

Part of the Stable ABI. Return 1 if the object provides the mapping protocol or supports slicing, and 0 otherwise. Note that it returns 1 for Python classes with a \_\_getitem\_\_() method, since in general it is impossible to determine what type of keys the class supports. This function always succeeds.

#### Py\_ssize\_t PyMapping\_Size (PyObject \*o)

### Py\_ssize\_t PyMapping\_Length (PyObject \*o)

Part of the Stable ABI. Renvoie le nombre de clefs dans l'objet o et -1 en cas d'échec. C'est l'équivalent de l'expression Python len (o).

### PyObject \*PyMapping\_GetItemString (PyObject \*o, const char \*key)

Return value : New reference. Part of the Stable ABI. Renvoie les éléments de o qui correspondent à la chaîne key ou NULL en cas d'échec. C'est l'équivalent de l'expression Python o [key]. Voir aussi PyObject\_GetItem().

## int PyMapping\_SetItemString (PyObject \*o, const char \*key, PyObject \*v)

Part of the Stable ABI. Fait correspondre la chaîne key à la valeur v dans l'objet o. Renvoie -1 en cas d'échec. C'est l'équivalent de la commande Python o[key] = v. Voir aussi  $PyObject\_SetItem()$ . Cette fonction ne vole pas de référence à v.

## int PyMapping\_DelItem (PyObject \*o, PyObject \*key)

Supprime la correspondance associée à l'objet *key* dans l'objet *o*. Renvoie –1 en cas d'échec. C'est l'équivalent de la commande Python del o [key]. C'est un alias pour *PyObject\_DelItem()*.

### int PyMapping\_DelItemString (PyObject \*o, const char \*key)

Supprime la correspondance associée à la chaîne key dans l'objet o. Renvoie -1 en cas d'échec. C'est l'équivalent de la commande Python del o[key].

#### int PyMapping\_HasKey (PyObject \*o, PyObject \*key)

Part of the Stable ABI. Renvoie 1 si l'objet de correspondance possède une clef key et 0 sinon. C'est l'équivalent de l'expression Python key in o. Cette fonction ne provoque jamais d'erreur.

Notez que les exceptions qui surviennent pendant l'appel de la méthode \_\_getitem\_\_() seront supprimées. Pour obtenir le rapport d'erreur, utilisez plutôt PyObject\_GetItem().

### int PyMapping\_HasKeyString (PyObject \*o, const char \*key)

Part of the Stable ABI. Renvoie 1 si l'objet de correspondance possède une clef key et 0 sinon. C'est l'équivalent de l'expression Python key in o. Cette fonction ne provoque jamais d'erreur.

Notez que les exceptions qui surviennent en créant une chaîne de caractères temporaire pendant l'appel de la méthode \_\_getitem\_\_() seront supprimées. Pour obtenir le rapport d'erreur, utilisez plutôt  $PyMapping\_GetItemString()$ .

#### PyObject \*PyMapping\_Keys (PyObject \*o)

Return value : New reference. Part of the Stable ABI. Renvoie la liste des clefs dans l'objet o. En cas d'échec, renvoie NULL.

Modifié dans la version 3.7 : Auparavant, la fonction renvoyait une liste ou un *n*-uplet.

## PyObject \*PyMapping\_Values (PyObject \*o)

Return value : New reference. Part of the Stable ABI. Renvoie la liste des valeurs dans l'objet o. En cas d'échec, renvoie NULL.

Modifié dans la version 3.7 : Auparavant, la fonction renvoyait une liste ou un *n*-uplet.

### PyObject \*PyMapping\_Items (PyObject \*o)

Return value : New reference. Part of the Stable ABI. Renvoie la liste des éléments dans l'objet o, où chaque élément est un n-uplet contenant une paire clef-valeur. En cas d'échec, renvoie NULL.

Modifié dans la version 3.7: Auparavant, la fonction renvoyait une liste ou un n-uplet.

## 7.6 Protocole d'itération

Il existe deux fonctions dédiées à l'interaction avec les itérateurs.

## int PyIter\_Check (PyObject \*o)

Part of the Stable ABI since version 3.8. Return non-zero if the object o can be safely passed to  $PyIter_Next()$ , and 0 otherwise. This function always succeeds.

### int PyAIter\_Check (PyObject \*o)

*Part of the* Stable ABI *since version 3.10.* Return non-zero if the object *o* provides the AsyncIterator protocol, and 0 otherwise. This function always succeeds.

Nouveau dans la version 3.10.

#### PyObject \*PyIter\_Next (PyObject \*o)

Return value: New reference. Part of the Stable ABI. Return the next value from the iterator o. The object must be an iterator according to  $PyIter\_Check$  () (it is up to the caller to check this). If there are no remaining values, returns NULL with no exception set. If an error occurs while retrieving the item, returns NULL and passes along the exception.

Pour écrire une boucle itérant un itérateur, le code C devrait ressembler à :

```
PyObject *iterator = PyObject_GetIter(obj);
PyObject *item;

if (iterator == NULL) {
    /* propagate error */
}

while ((item = PyIter_Next(iterator))) {
    /* do something with item */
    ...
    /* release reference when done */
    Py_DECREF(item);
}

Py_DECREF(iterator);

if (PyErr_Occurred()) {
    /* propagate error */
}
else {
    /* continue doing useful work */
}
```

### type PySendResult

The enum value used to represent different results of  $PyIter\_Send()$ .

Nouveau dans la version 3.10.

PySendResult PyIter\_Send (PyObject \*iter, PyObject \*arg, PyObject \*\*presult)

Part of the Stable ABI since version 3.10. Sends the arg value into the iterator iter. Returns:

- PYGEN\_RETURN if iterator returns. Return value is returned via presult.
- PYGEN\_NEXT if iterator yields. Yielded value is returned via *presult*.
- PYGEN\_ERROR if iterator has raised and exception. *presult* is set to NULL.

Nouveau dans la version 3.10.

# 7.7 Protocole tampon

Certains objets Python enveloppent l'accès à un tableau de mémoire sous-jacente (nommée zone tampon ou simplement tampon, *buffer* en anglais). Les objets natifs bytes et bytearray en sont des exemples, ainsi que quelques types d'extension comme array. Les bibliothèques tierces peuvent définir leurs propres types à des fins spéciales, telles que le traitement d'image ou l'analyse numérique.

Alors que chacun de ces types a sa propre sémantique, ils partagent la caractéristique commune d'être soutenus par un tampon de mémoire important. Il est donc souhaitable, dans certains cas, d'accéder à cette mémoire directement sans l'étape intermédiaire de copie.

Python fournit une telle facilité au niveau du C sous la forme de protocole tampon. Ce protocole comporte deux aspects :

- du côté producteur, un type peut exporter une "interface tampon" qui permet aux objets de ce type d'exposer des informations concernant leur tampon sous-jacent. Cette interface est décrite dans la section Buffer Object Structures;
- du côté consommateur, plusieurs moyens sont disponibles pour obtenir un pointeur vers les données sous-jacentes brutes d'un objet (par exemple un paramètre de méthode).

Des objets simples tels que bytes et bytearray exposent leur tampon sous-jacent dans un format orienté octet. D'autres formes sont possibles; par exemple, les éléments exposés par un array array peuvent être des valeurs multi-octets.

Un exemple de consommateur de l'interface tampon est la méthode write() des objets fichiers : tout objet qui peut exporter une série d'octets à travers l'interface tampon peut être écrit dans un fichier. Alors que write() n'a besoin que d'un accès lecture au contenu interne de l'objet qui lui est passé, d'autres méthodes telles que readinto() nécessitent un accès écriture au contenu de leur argument. L'interface *buffer* permet aux objets d'autoriser ou de rejeter sélectivement l'exportation de tampons en mode lecture-écriture et en mode lecture seule.

Un consommateur de l'interface tampon peut acquérir un tampon sur un objet cible de deux manières :

- appelez PyObject\_GetBuffer() avec les paramètres appropriés;
- appelez <code>PyArg\_ParseTuple()</code> (ou l'un de ses fonctions sœurs) avec l'un des y\*, w\* ou s\* format codes.

  Dans les deux cas, <code>PyBuffer\_Release()</code> doit être appelée quand le tampon n'est plus nécessaire. Ne pas le faire peut conduire à divers problèmes tels que des fuites de ressources.

### 7.7.1 La structure buffer

Les structures tampons (ou simplement les "tampons", *buffers* en anglais) sont utiles pour exposer les données binaires d'un autre objet au programmeur Python. Elles peuvent également être utilisées comme un mécanisme de découpage sans copie. En utilisant leur capacité à référencer un bloc de mémoire, il est possible d'exposer toutes les données au programmeur Python assez facilement. La mémoire peut être un grand tableau constant dans une extension C, il peut s'agir d'un bloc brut de mémoire à manipuler avant de passer à une bibliothèque de système d'exploitation ou être utilisé pour transmettre des données structurées dans son format natif en mémoire.

Contrairement à la plupart des types de données exposés par l'interpréteur Python, les tampons ne sont pas de simples pointeurs vers PyObject mais plutôt des structures C simples. Cela leur permet d'être créés et copiés très simplement. lorsque vous avez besoin d'une enveloppe générique (wrapper en anglais) pour un tampon, un objet memoryview peut être créé.

For short instructions how to write an exporting object, see *Buffer Object Structures*. For obtaining a buffer, see *PyObject\_GetBuffer()*.

## $type \ \textbf{Py\_buffer}$

Part of the Stable ABI (including all members) since version 3.11.

### void \*buf

A pointer to the start of the logical structure described by the buffer fields. This can be any location within the underlying physical memory block of the exporter. For example, with negative strides the value may point to the end of the memory block.

For *contiguous* arrays, the value points to the beginning of the memory block.

### PyObject \*obj

A new reference to the exporting object. The reference is owned by the consumer and automatically decremented and set to NULL by  $PyBuffer\_Release()$ . The field is the equivalent of the return value of any standard C-API function.

As a special case, for *temporary* buffers that are wrapped by *PyMemoryView\_FromBuffer()* or *PyBuffer\_FillInfo()* this field is NULL. In general, exporting objects MUST NOT use this scheme.

### Py ssize t len

product (shape) \* itemsize. For contiguous arrays, this is the length of the underlying memory block. For non-contiguous arrays, it is the length that the logical structure would have if it were copied to a contiguous representation.

Accessing ((char \*)buf)[0] up to ((char \*)buf)[len-1] is only valid if the buffer has been obtained by a request that guarantees contiguity. In most cases such a request will be PyBUF\_SIMPLE or PyBUF WRITABLE.

### int readonly

An indicator of whether the buffer is read-only. This field is controlled by the PyBUF WRITABLE flag.

#### Py ssize titemsize

Item size in bytes of a single element. Same as the value of struct.calcsize() called on non-NULL format values.

Important exception: If a consumer requests a buffer without the PyBUF\_FORMAT flag, format will be set to NULL, but itemsize still has the value for the original format.

If shape is present, the equality product (shape) \* itemsize == len still holds and the consumer can use itemsize to navigate the buffer.

If shape is NULL as a result of a  $PyBUF\_SIMPLE$  or a  $PyBUF\_WRITABLE$  request, the consumer must disregard itemsize and assume itemsize == 1.

### const char \*format

A *NUL* terminated string in struct module style syntax describing the contents of a single item. If this is NULL, "B" (unsigned bytes) is assumed.

This field is controlled by the PyBUF\_FORMAT flag.

#### int ndim

The number of dimensions the memory represents as an n-dimensional array. If it is 0, buf points to a single item representing a scalar. In this case, shape, strides and suboffsets MUST be NULL.

The macro PyBUF\_MAX\_NDIM limits the maximum number of dimensions to 64. Exporters MUST respect this limit, consumers of multi-dimensional buffers SHOULD be able to handle up to PyBUF\_MAX\_NDIM dimensions.

## Py\_ssize\_t \*shape

An array of  $Py\_ssize\_t$  of length ndim indicating the shape of the memory as an n-dimensional array. Note that shape [0] \* ... \* shape [ndim-1] \* itemsize MUST be equal to <math>len.

Shape values are restricted to shape[n] >= 0. The case shape[n] == 0 requires special attention. See *complex arrays* for further information.

The shape array is read-only for the consumer.

#### Py ssize t\*strides

An array of Py\_ssize\_t of length ndim giving the number of bytes to skip to get to a new element in each dimension.

Stride values can be any integer. For regular arrays, strides are usually positive, but a consumer MUST be able to handle the case  $strides[n] \le 0$ . See *complex arrays* for further information.

The strides array is read-only for the consumer.

### Py\_ssize\_t \*suboffsets

An array of  $Py\_ssize\_t$  of length ndim. If suboffsets[n] >= 0, the values stored along the nth dimension are pointers and the suboffset value dictates how many bytes to add to each pointer after dereferencing. A suboffset value that is negative indicates that no de-referencing should occur (striding in a contiguous memory block).

If all suboffsets are negative (i.e. no de-referencing is needed), then this field must be NULL (the default value).

This type of array representation is used by the Python Imaging Library (PIL). See *complex arrays* for further information how to access elements of such an array.

The suboffsets array is read-only for the consumer.

#### void \*internal

This is for use internally by the exporting object. For example, this might be re-cast as an integer by the exporter and used to store flags about whether or not the shape, strides, and suboffsets arrays must be freed when the buffer is released. The consumer MUST NOT alter this value.

## 7.7.2 Buffer request types

Buffers are usually obtained by sending a buffer request to an exporting object via <code>PyObject\_GetBuffer()</code>. Since the complexity of the logical structure of the memory can vary drastically, the consumer uses the <code>flags</code> argument to specify the exact buffer type it can handle.

All Py\_buffer fields are unambiguously defined by the request type.

## request-independent fields

The following fields are not influenced by *flags* and must always be filled in with the correct values : obj, buf, len, itemsize, ndim.

## readonly, format

#### PyBUF\_WRITABLE

Controls the readonly field. If set, the exporter MUST provide a writable buffer or else report failure. Otherwise, the exporter MAY provide either a read-only or writable buffer, but the choice MUST be consistent for all consumers.

## PyBUF\_FORMAT

Controls the format field. If set, this field MUST be filled in correctly. Otherwise, this field MUST be NULL.

PyBUF\_WRITABLE can be I'd to any of the flags in the next section. Since PyBUF\_SIMPLE is defined as 0, PyBUF\_WRITABLE can be used as a stand-alone flag to request a simple writable buffer.

 $PYBUF\_FORMAT$  can be I'd to any of the flags except  $PYBUF\_SIMPLE$ . The latter already implies format B (unsigned bytes).

#### shape, strides, suboffsets

The flags that control the logical structure of the memory are listed in decreasing order of complexity. Note that each flag contains all bits of the flags below it.

Request	shape	strides	suboffsets
PyBUF_INDIRECT	oui	oui	si nécessaire
PyBUF_STRIDES	oui	oui	NULL
PyBUF_ND	oui	NULL	NULL
PyBUF_SIMPLE	NULL	NULL	NULL

## contiguity requests

C or Fortran *contiguity* can be explicitly requested, with and without stride information. Without stride information, the buffer must be C-contiguous.

Request	shape	strides	suboffsets	contig
PyBUF_C_CONTIGUOUS	oui	oui	NULL	С
PyBUF_F_CONTIGUOUS	oui	oui	NULL	F
PyBUF_ANY_CONTIGUOUS	oui	oui	NULL	C or F
PyBUF_ND	oui	NULL	NULL	С

## compound requests

All possible requests are fully defined by some combination of the flags in the previous section. For convenience, the buffer protocol provides frequently used combinations as single flags.

In the following table U stands for undefined contiguity. The consumer would have to call  $PyBuffer\_IsContiguous$  () to determine contiguity.

Request	shape	strides	suboffsets	contig	lecture seule	format
PyBUF_FULL	oui	oui	si nécessaire	U	0	oui
PyBUF_FULL_RO	oui	oui	si nécessaire	U	0 ou 1	oui
PyBUF_RECORDS	oui	oui	NULL	U	0	oui
PyBUF_RECORDS_RO	oui	oui	NULL	U	0 ou 1	oui
PyBUF_STRIDED	oui	oui	NULL	U	0	NULL
PyBUF_STRIDED_RO	oui	oui	NULL	U	0 ou 1	NULL
PyBUF_CONTIG	oui	NULL	NULL	С	0	NULL
PyBUF_CONTIG_RO	oui	NULL	NULL	С	0 ou 1	NULL

## 7.7.3 Complex arrays

### NumPy-style: shape and strides

The logical structure of NumPy-style arrays is defined by itemsize, ndim, shape and strides.

If ndim == 0, the memory location pointed to by buf is interpreted as a scalar of size itemsize. In that case, both shape and strides are NULL.

If strides is NULL, the array is interpreted as a standard n-dimensional C-array. Otherwise, the consumer must access an n-dimensional array as follows:

```
ptr = (char *)buf + indices[0] * strides[0] + ... + indices[n-1] * strides[n-1];
item = *((typeof(item) *)ptr);
```

As noted above, buf can point to any location within the actual memory block. An exporter can check the validity of a buffer with this function:

```
def verify_structure(memlen, itemsize, ndim, shape, strides, offset):
    """Verify that the parameters represent a valid array within
       the bounds of the allocated memory:
           char *mem: start of the physical memory block
           memlen: length of the physical memory block
           offset: (char *)buf - mem
    11 11 11
   if offset % itemsize:
       return False
    if offset < 0 or offset+itemsize > memlen:
       return False
    if any(v % itemsize for v in strides):
       return False
   if ndim <= 0:
       return ndim == 0 and not shape and not strides
   if 0 in shape:
       return True
   imin = sum(strides[j]*(shape[j]-1) for j in range(ndim)
               if strides[j] <= 0)</pre>
   imax = sum(strides[j]*(shape[j]-1) for j in range(ndim)
               if strides[j] > 0)
    return 0 <= offset+imin and offset+imax+itemsize <= memlen</pre>
```

### PIL-style: shape, strides and suboffsets

In addition to the regular items, PIL-style arrays can contain pointers that must be followed in order to get to the next element in a dimension. For example, the regular three-dimensional C-array char v[2][2][3] can also be viewed as an array of 2 pointers to 2 two-dimensional arrays: char (\*v[2])[2][3]. In suboffsets representation, those two pointers can be embedded at the start of buf, pointing to two char x[2][3] arrays that can be located anywhere in memory.

Here is a function that returns a pointer to the element in an N-D array pointed to by an N-dimensional index when there are both non-NULL strides and suboffsets:

### 7.7.4 Fonctions relatives aux tampons

#### int PyObject\_CheckBuffer (PyObject \*obj)

Part of the Stable ABI since version 3.11. Return 1 if obj supports the buffer interface otherwise 0. When 1 is returned, it doesn't guarantee that PyObject\_GetBuffer() will succeed. This function always succeeds.

```
int PyObject_GetBuffer (PyObject *exporter, Py_buffer *view, int flags)
```

Part of the Stable ABI since version 3.11. Send a request to exporter to fill in view as specified by flags. If the exporter cannot provide a buffer of the exact type, it MUST raise PyExc\_BufferError, set view->obj to NULL and return -1.

On success, fill in *view*, set view->obj to a new reference to *exporter* and return 0. In the case of chained buffer providers that redirect requests to a single object, view->obj MAY refer to this object instead of *exporter* (See *Buffer Object Structures*).

Successful calls to  $PyObject\_GetBuffer()$  must be paired with calls to  $PyBuffer\_Release()$ , similar to malloc() and free(). Thus, after the consumer is done with the buffer,  $PyBuffer\_Release()$  must be called exactly once.

```
void PyBuffer_Release (Py_buffer *view)
```

Part of the Stable ABI since version 3.11. Release the buffer view and decrement the reference count for view->obj. This function MUST be called when the buffer is no longer being used, otherwise reference leaks may occur.

It is an error to call this function on a buffer that was not obtained via PyObject\_GetBuffer().

#### Py\_ssize\_t PyBuffer\_SizeFromFormat (const char \*format)

Part of the Stable ABI since version 3.11. Retourne l'itemsize du format. En cas d'erreur, lève une exception et retourne -1.

Nouveau dans la version 3.9.

#### int PyBuffer\_IsContiguous (const *Py\_buffer* \*view, char order)

Part of the Stable ABI since version 3.11. Return 1 if the memory defined by the view is C-style (order is 'C') or Fortran-style (order is 'F') contiguous or either one (order is 'A'). Return 0 otherwise. This function always succeeds.

```
void *PyBuffer_GetPointer (const Py_buffer *view, const Py_ssize_t *indices)
```

Part of the Stable ABI since version 3.11. Get the memory area pointed to by the indices inside the given view. indices must point to an array of view->ndim indices.

```
int PyBuffer_FromContiguous (const Py_buffer *view, const void *buf, Py_ssize_t len, char fort)
```

Part of the Stable ABI since version 3.11. Copy contiguous len bytes from buf to view. fort can be 'C' or 'F' (for C-style or Fortran-style ordering). 0 is returned on success, -1 on error.

int PyBuffer\_ToContiquous (void \*buf, const Py\_buffer \*src, Py\_ssize\_t len, char order)

Part of the Stable ABI since version 3.11. Copy len bytes from src to its contiguous representation in buf. order can be 'C' or 'F' or 'A' (for C-style or Fortran-style ordering or either one). 0 is returned on success, -1 on error. This function fails if len!= src->len.

int PyObject\_CopyData (PyObject \*dest, PyObject \*src)

Part of the Stable ABI since version 3.11. Copy data from src to dest buffer. Can convert between C-style and or Fortran-style buffers.

0 is returned on success, -1 on error.

void **PyBuffer\_FillContiguousStrides** (int ndims,  $Py\_ssize\_t$  \*shape,  $Py\_ssize\_t$  \*strides, int itemsize, char order)

Part of the Stable ABI since version 3.11. Fill the strides array with byte-strides of a contiguous (C-style if order is 'C' or Fortran-style if order is 'F') array of the given shape with the given number of bytes per element.

int PyBuffer\_FillInfo (Py\_buffer \*view, PyObject \*exporter, void \*buf, Py\_ssize\_t len, int readonly, int flags)

Part of the Stable ABI since version 3.11. Handle buffer requests for an exporter that wants to expose buf of size len with writability set according to readonly. buf is interpreted as a sequence of unsigned bytes.

The *flags* argument indicates the request type. This function always fills in *view* as specified by flags, unless *buf* has been designated as read-only and *PyBUF\_WRITABLE* is set in *flags*.

On success, set view->obj to a new reference to *exporter* and return 0. Otherwise, raise PyExc\_BufferError, set view->obj to NULL and return -1;

If this function is used as part of a *getbufferproc*, *exporter* MUST be set to the exporting object and *flags* must be passed unmodified. Otherwise, *exporter* MUST be NULL.

# 7.8 Ancien Protocole Tampon

Obsolète depuis la version 3.0.

Ces fonctions faisaient partie de l'API de l'ancien protocole de tampons dans Python 2. Dans Python 3, ce protocole n'existe plus, mais les fonctions sont toujours exposées pour simplifier le portage de code Python 2.x. Elles se comportent comme une abstraction de compatibilité du *nouveau protocole de tampons*, mais sans vous donner de contrôle sur la durée de vie des ressources acquises lorsqu'un tampon est exporté.

Il est donc recommandé d'appeler  $PyObject\_GetBuffer()$  (ou les codes y\* ou w\* à la famille de fonctions  $PyArg\_ParseTuple()$ ) pour obtenir une vue d'un tampon sur un objet, et  $PyBuffer\_Release()$  lorsque la vue peut être libérée.

```
int PyObject_AsCharBuffer (PyObject *obj, const char **buffer, Py_ssize_t *buffer_len)
```

Part of the Stable ABI. Retourne un pointeur vers un emplacement de mémoire en lecture seule utilisable en tant qu'entrée basée sur des caractères. L'argument *obj* doit prendre en charge l'interface de tampon de caractère à segment unique. En cas de succès, retourne 0, définit *buffer* à l'emplacement de la mémoire et *buffer\_len* à la longueur de la mémoire tampon. Retourne -1 et affecte une exception TypeError en cas d'erreur.

int PyObject\_AsReadBuffer (PyObject \*obj, const void \*\*buffer, Py\_ssize\_t \*buffer\_len)

Part of the Stable ABI. Retourne un pointeur vers un emplacement de mémoire en lecture seule contenant des données arbitraires. L'argument *obj* doit prendre en charge l'interface de tampon lisible à segment unique. En cas de succès, retourne 0, définit *buffer* à l'emplacement de la mémoire et *buffer\_len* à la longueur de la mémoire tampon. Renvoie -1 et affecte l'exception TypeError en cas d'erreur.

int PyObject CheckReadBuffer (PyObject \*o)

*Part of the* Stable ABI. Retourne 1 si *o* prend en charge l'interface de mémoire tampon lisible à segment unique. Sinon, renvoie 0. Cette fonction réussit toujours.

Notez que cette fonction tente d'obtenir et de libérer une mémoire tampon, et les exceptions qui se produisent lors de l'appel des fonctions correspondantes seront supprimées. Pour que les erreurs vous soient signalées, utilisez <code>PyObject\_GetBuffer()</code> à la place.

int PyObject\_AsWriteBuffer (PyObject \*obj, void \*\*buffer, Py\_ssize\_t \*buffer\_len)

Part of the Stable ABI. Retourne un pointeur vers un emplacement de mémoire accessible en écriture. L'argument obj doit prendre en charge l'interface de mémoire tampon de caractère à segment unique. En cas de succès, retourne 0, définit buffer à l'emplacement de la mémoire et buffer\_len à la longueur de la mémoire tampon. Renvoie -1 et affecte l'exception TypeError en cas d'erreur.

# Couche des objets concrets

Les fonctions de ce chapitre sont spécifiques à certains types d'objets Python. Leur donner un objet du mauvais type n'est pas une bonne idée, si vous recevez un objet d'un programme Python, et que vous n'êtes pas sûr qu'il soit du bon type, vous devez vérifier son type en premier. Par exemple, pour vérifier qu'un objet est un dictionnaire, utilisez PyDict\_Check(). Ce chapitre est organisé comme un arbre généalogique de types d'objets Python.

**Avertissement :** Tandis que les fonctions décrites dans ce chapitre vérifient avec soin le type des objets qui leur sont passés, beaucoup d'entre elles ne vérifient pas que NULL est passé au lieu d'un objet valide. Autoriser NULL à être passé peut provoquer des violations d'accès à la mémoire et ainsi terminer immédiatement l'interpréteur.

# 8.1 Objets fondamentaux

Cette section décrit les objets de type Python et l'objet singleton None.

## 8.1.1 Objets type

#### type PyTypeObject

Part of the Limited API (as an opaque struct). The C structure of the objects used to describe built-in types.

#### PyTypeObject PyType\_Type

Part of the Stable ABI. This is the type object for type objects; it is the same object as type in the Python layer.

#### int PyType\_Check (PyObject \*o)

Return non-zero if the object *o* is a type object, including instances of types derived from the standard type object. Return 0 in all other cases. This function always succeeds.

#### int PyType\_CheckExact (PyObject \*o)

Return non-zero if the object o is a type object, but not a subtype of the standard type object. Return 0 in all other cases. This function always succeeds.

#### unsigned int PyType\_ClearCache()

Part of the Stable ABI. Clear the internal lookup cache. Return the current version tag.

### unsigned long PyType\_GetFlags (PyTypeObject \*type)

Part of the Stable ABI. Return the  $tp\_flags$  member of type. This function is primarily meant for use with Py\_LIMITED\_API; the individual flag bits are guaranteed to be stable across Python releases, but access to  $tp\_flags$  itself is not part of the limited API.

Nouveau dans la version 3.2.

Modifié dans la version 3.4: The return type is now unsigned long rather than long.

#### void PyType\_Modified (PyTypeObject \*type)

Part of the Stable ABI. Invalidate the internal lookup cache for the type and all of its subtypes. This function must be called after any manual modification of the attributes or base classes of the type.

### int PyType\_HasFeature (PyTypeObject \*o, int feature)

Return non-zero if the type object o sets the feature feature. Type features are denoted by single bit flags.

### int **PyType\_IS\_GC** (*PyTypeObject* \*o)

Return true if the type object includes support for the cycle detector; this tests the type flag Py TPFLAGS HAVE GC.

### int PyType\_IsSubtype (PyTypeObject \*a, PyTypeObject \*b)

Part of the Stable ABI. Return true if a is a subtype of b.

This function only checks for actual subtypes, which means that  $\_\_subclasscheck\_\_$  () is not called on b. Call  $PyObject\_IsSubclass$  () to do the same check that issubclass () would do.

#### *PyObject* \*PyType\_GenericAlloc (*PyTypeObject* \*type, *Py\_ssize\_t* nitems)

Return value: New reference. Part of the Stable ABI. Generic handler for the  $tp_alloc$  slot of a type object. Use Python's default memory allocation mechanism to allocate a new instance and initialize all its contents to NULL.

### PyObject \*PyType\_GenericNew (PyTypeObject \*type, PyObject \*args, PyObject \*kwds)

Return value: New reference. Part of the Stable ABI. Generic handler for the  $tp\_new$  slot of a type object. Create a new instance using the type's  $tp\_alloc$  slot.

#### int **PyType\_Ready** (*PyTypeObject* \*type)

Part of the Stable ABI. Finalize a type object. This should be called on all type objects to finish their initialization. This function is responsible for adding inherited slots from a type's base class. Return 0 on success, or return -1 and sets an exception on error.

**Note:** If some of the base classes implements the GC protocol and the provided type does not include the  $Py\_TPFLAGS\_HAVE\_GC$  in its flags, then the GC protocol will be automatically implemented from its parents. On the contrary, if the type being created does include  $Py\_TPFLAGS\_HAVE\_GC$  in its flags then it **must** implement the GC protocol itself by at least implementing the  $tp\_traverse$  handle.

#### PyObject \*PyType\_GetName (PyTypeObject \*type)

*Return value : New reference. Part of the* Stable ABI *since version 3.11.* Return the type's name. Equivalent to getting the type's \_\_name\_\_ attribute.

Nouveau dans la version 3.11.

#### PyObject \*PyType\_GetQualName (PyTypeObject \*type)

*Return value : New reference. Part of the* Stable ABI *since version 3.11.* Return the type's qualified name. Equivalent to getting the type's \_\_qualname\_\_ attribute.

Nouveau dans la version 3.11.

#### void \*PyType\_GetSlot (PyTypeObject \*type, int slot)

Part of the Stable ABI since version 3.4. Return the function pointer stored in the given slot. If the result is NULL, this indicates that either the slot is NULL, or that the function was called with invalid parameters. Callers will typically cast the result pointer into the appropriate function type.

See PyType\_Slot.slot for possible values of the *slot* argument.

Nouveau dans la version 3.4.

Modifié dans la version 3.10 : PyType\_GetSlot () can now accept all types. Previously, it was limited to *heap types*.

### PyObject \*PyType\_GetModule (PyTypeObject \*type)

Part of the Stable ABI since version 3.10. Return the module object associated with the given type when the type was created using PyType\_FromModuleAndSpec().

If no module is associated with the given type, sets TypeError and returns NULL.

This function is usually used to get the module in which a method is defined. Note that in such a method, PyType\_GetModule(Py\_TYPE(self)) may not return the intended result. Py\_TYPE(self) may be a *subclass* of the intended class, and subclasses are not necessarily defined in the same module as their superclass. See PyCMethod to get the class that defines the method. See PyType\_GetModuleByDef() for cases when PyCMethod cannot be used.

Nouveau dans la version 3.9.

#### void \*PyType\_GetModuleState (PyTypeObject \*type)

Part of the Stable ABI since version 3.10. Return the state of the module object associated with the given type. This is a shortcut for calling <code>PyModule\_GetState()</code> on the result of <code>PyType\_GetModule()</code>.

If no module is associated with the given type, sets TypeError and returns NULL.

If the *type* has an associated module but its state is NULL, returns NULL without setting an exception.

Nouveau dans la version 3.9.

### PyObject \*PyType\_GetModuleByDef (PyTypeObject \*type, struct PyModuleDef \*def)

Find the first superclass whose module was created from the given <code>PyModuleDef def</code>, and return that module. If no module is found, raises a <code>TypeError</code> and returns <code>NULL</code>.

This function is intended to be used together with  $PyModule\_GetState()$  to get module state from slot methods (such as  $tp\_init$  or  $nb\_add$ ) and other places where a method's defining class cannot be passed using the PyCMethod calling convention.

Nouveau dans la version 3.11.

### **Creating Heap-Allocated Types**

The following functions and structs are used to create *heap types*.

#### PyObject \*PyType\_FromModuleAndSpec (PyObject \*module, PyType\_Spec \*spec, PyObject \*bases)

Return value: New reference. Part of the Stable ABI since version 3.10. Creates and returns a heap type from the spec (Py TPFLAGS HEAPTYPE).

The *bases* argument can be used to specify base classes; it can either be only one class or a tuple of classes. If *bases* is NULL, the  $Py\_tp\_bases$  slot is used instead. If that also is NULL, the  $Py\_tp\_base$  slot is used instead. If that also is NULL, the new type derives from object.

The *module* argument can be used to record the module in which the new class is defined. It must be a module object or NULL. If not NULL, the module is associated with the new type and can later be retrieved with  $PyType\_GetModule()$ . The associated module is not inherited by subclasses; it must be specified for each class individually.

This function calls PyType Ready () on the new type.

Nouveau dans la version 3.9.

Modifié dans la version 3.10: The function now accepts a single class as the *bases* argument and NULL as the tp doc slot.

```
PyObject *PyType_FromSpecWithBases (PyType_Spec *spec, PyObject *bases)
     Return value: New reference. Part of the Stable ABI since version 3.3. Equivalent to
     PyType_FromModuleAndSpec(NULL, spec, bases).
     Nouveau dans la version 3.3.
PyObject *PyType_FromSpec (PyType_Spec *spec)
     Return value: New reference. Part of the Stable ABI. Equivalent to PyType_FromSpecWithBases (spec,
     NULL).
type PyType_Spec
     Part of the Stable ABI (including all members). Structure defining a type's behavior.
     const char *PyType_Spec.name
          Name of the type, used to set PyTypeObject.tp_name.
     int PyType_Spec.basicsize
     int PyType_Spec.itemsize
          Size of the instance in bytes, used to set PyTypeObject.tp_basicsize and PyTypeObject.
          tp_itemsize.
     int PyType Spec.flags
          Type flags, used to set PyTypeObject.tp_flags.
          If the Py_TPFLAGS_HEAPTYPE flag is not set, PyType_FromSpecWithBases () sets it automati-
          cally.
     PyType_Slot *PyType_Spec.slots
          Array of PyType_Slot structures. Terminated by the special slot value {0, NULL}.
type PyType_Slot
     Part of the Stable ABI (including all members). Structure defining optional functionality of a type, containing a slot
     ID and a value pointer.
     int PyType_Slot.slot
             A slot ID.
             Slot IDs are named like the field names of the structures PyTypeObject, PyNumberMethods,
              PySequenceMethods, PyMappingMethods and PyAsyncMethods with an added Py
             prefix. For example, use:
             — Py_tp_dealloc to set PyTypeObject.tp_dealloc
             — Py_nb_add to set PyNumberMethods.nb_add
               - Py sq length to set PySequenceMethods.sq length
             The following fields cannot be set at all using PyType_Spec and PyType_Slot:
             - tp_dict
             - tp_mro
              — tp_cache
              — tp subclasses
             - tp_weaklist
             - tp vectorcall
              — tp weaklistoffset (see PyMemberDef)
             — tp dictoffset (see PyMemberDef)
              — tp_vectorcall_offset (see PyMemberDef)
             Setting Py_tp_bases or Py_tp_base may be problematic on some platforms. To avoid issues,
              use the bases argument of PyType_FromSpecWithBases() instead.
          Modifié dans la version 3.9 : Slots in PyBufferProcs may be set in the unlimited API.
          Modifié dans la version 3.11: bf_getbuffer and bf_releasebuffer are now available under the
          limited API.
     void *PyType_Slot.pfunc
          The desired value of the slot. In most cases, this is a pointer to a function.
          Slots other than Py_tp_doc may not be NULL.
```

### 8.1.2 L'objet None

Notez que le PyTypeObject de None n'est pas directement exposé via l'API Python/C. Puisque None est un singleton, tester son identité (en utilisant == en C) est suffisant. Il n'existe pas de fonction PyNone\_Check () pour la même raison.

#### PyObject \*Py\_None

L'objet Python None, exprimant l'absence de valeur. Cet objet n'a aucune méthode. Il doit être traité exactement comme les autres objets en terme de comptage de références.

#### Py\_RETURN\_NONE

Renvoie, de la bonne manière, Py\_None depuis une fonction C (c'est à dire en incrémentant les références à None avant de le donner).

# 8.2 Objets numériques

### 8.2.1 Objets Integer

All integers are implemented as "long" integer objects of arbitrary size.

On error, most PyLong\_As\* APIs return (return type) -1 which cannot be distinguished from a number. Use PyErr\_Occurred() to disambiguate.

### type PyLongObject

Part of the Limited API (as an opaque struct). This subtype of PyObject represents a Python integer object.

#### PyTypeObject PyLong\_Type

Part of the Stable ABI. This instance of PyTypeObject represents the Python integer type. This is the same object as int in the Python layer.

#### int PyLong\_Check (PyObject \*p)

Return true if its argument is a PyLongObject or a subtype of PyLongObject. This function always succeeds.

### int PyLong\_CheckExact (PyObject \*p)

Return true if its argument is a PyLongObject, but not a subtype of PyLongObject. This function always succeeds.

#### PyObject \*PyLong\_FromLong (long v)

Return value: New reference. Part of the Stable ABI. Return a new PyLongObject object from v, or NULL on failure

The current implementation keeps an array of integer objects for all integers between -5 and 256. When you create an int in that range you actually just get back a reference to the existing object.

### PyObject \*PyLong\_FromUnsignedLong (unsigned long v)

Return value: New reference. Part of the Stable ABI. Return a new PyLongObject object from a C unsigned long, or NULL on failure.

### PyObject \*PyLong\_FromSsize\_t (Py\_ssize\_t v)

Return value: New reference. Part of the Stable ABI. Return a new PyLongObject object from a C Py\_ssize\_t, or NULL on failure.

#### PyObject \*PyLong\_FromSize\_t (size\_t v)

Return value: New reference. Part of the Stable ABI. Return a new PyLongObject object from a C size\_t, or NULL on failure.

#### PyObject \*PyLong\_FromLongLong (long long v)

Return value: New reference. Part of the Stable ABI. Return a new PyLongObject object from a C long long, or NULL on failure.

#### PyObject \*PyLong\_FromUnsignedLongLong (unsigned long long v)

Return value: New reference. Part of the Stable ABI. Return a new PyLongObject object from a C unsigned long, or NULL on failure.

#### PyObject \*PyLong\_FromDouble (double v)

Return value: New reference. Part of the Stable ABI. Return a new PyLongObject object from the integer part of v, or NULL on failure.

### PyObject \*PyLong\_FromString (const char \*str, char \*\*pend, int base)

Return value: New reference. Part of the Stable ABI. Return a new PyLongObject based on the string value in str, which is interpreted according to the radix in base. If pend is non-NULL, \*pend will point to the first character in str which follows the representation of the number. If base is 0, str is interpreted using the integers definition; in this case, leading zeros in a non-zero decimal number raises a ValueError. If base is not 0, it must be between 2 and 36, inclusive. Leading spaces and single underscores after a base specifier and between digits are ignored. If there are no digits, ValueError will be raised.

#### Voir aussi:

Python methods int.to\_bytes() and int.from\_bytes() to convert a PyLongObject to/from an array of bytes in base 256. You can call those from C using PyObject\_CallMethod().

#### PyObject \*PyLong\_FromUnicodeObject (PyObject \*u, int base)

*Return value : New reference.* Convert a sequence of Unicode digits in the string *u* to a Python integer value. Nouveau dans la version 3.3.

#### PyObject \*PyLong\_FromVoidPtr (void \*p)

*Return value : New reference. Part of the* Stable ABI. Create a Python integer from the pointer p. The pointer value can be retrieved from the resulting value using  $PyLong\_AsVoidPtr()$ .

### long PyLong\_AsLong (PyObject \*obj)

*Part of the* Stable ABI. Return a Clong representation of *obj*. If *obj* is not an instance of *PyLongObject*, first call its \_\_index\_\_() method (if present) to convert it to a *PyLongObject*.

Raise OverflowError if the value of *obj* is out of range for a long.

Returns -1 on error. Use PyErr\_Occurred () to disambiguate.

Modifié dans la version 3.8 : Use \_\_index\_\_ () if available.

Modifié dans la version 3.10 : This function will no longer use \_\_int\_\_().

### long PyLong\_AsLongAndOverflow (PyObject \*obj, int \*overflow)

Part of the Stable ABI. Return a C long representation of obj. If obj is not an instance of PyLongObject, first call its  $\_index\_$  () method (if present) to convert it to a PyLongObject.

If the value of *obj* is greater than LONG\_MAX or less than LONG\_MIN, set \**overflow* to 1 or -1, respectively, and return -1; otherwise, set \**overflow* to 0. If any other exception occurs set \**overflow* to 0 and return -1 as usual.

Returns -1 on error. Use PyErr\_Occurred () to disambiguate.

Modifié dans la version 3.8 : Use index () if available.

Modifié dans la version 3.10 : This function will no longer use \_\_\_int\_\_\_().

#### long long PyLong\_AsLongLong (*PyObject* \*obj)

Part of the Stable ABI. Return a Clong long representation of obj. If obj is not an instance of PyLongObject, first call its \_\_index\_\_() method (if present) to convert it to a PyLongObject.

Raise OverflowError if the value of *obj* is out of range for a long long.

Returns -1 on error. Use PyErr\_Occurred() to disambiguate.

Modifié dans la version 3.8 : Use \_\_index\_\_() if available.

Modifié dans la version 3.10 : This function will no longer use \_\_int\_\_().

#### long long PyLong\_AsLongLongAndOverflow (PyObject \*obj, int \*overflow)

Part of the Stable ABI. Return a Clong long representation of obj. If obj is not an instance of PyLongObject, first call its \_\_index\_\_() method (if present) to convert it to a PyLongObject.

If the value of *obj* is greater than LLONG\_MAX or less than LLONG\_MIN, set \**overflow* to 1 or -1, respectively, and return -1; otherwise, set \**overflow* to 0. If any other exception occurs set \**overflow* to 0 and return -1 as usual.

Returns -1 on error. Use PyErr Occurred () to disambiguate.

Nouveau dans la version 3.2.

Modifié dans la version 3.8 : Use \_\_index\_\_() if available.

Modifié dans la version 3.10 : This function will no longer use \_\_int\_\_().

### Py\_ssize\_t PyLong\_AsSsize\_t (PyObject \*pylong)

Part of the Stable ABI. Return a C Py\_ssize\_t representation of pylong. pylong must be an instance of PyLongObject.

Raise OverflowError if the value of *pylong* is out of range for a *Py\_ssize\_t*.

Returns -1 on error. Use PyErr\_Occurred () to disambiguate.

### unsigned long PyLong\_AsUnsignedLong (PyObject \*pylong)

Part of the Stable ABI. Return a C unsigned long representation of pylong. pylong must be an instance of PyLongObject.

Raise OverflowError if the value of *pylong* is out of range for a unsigned long.

Returns (unsigned long) -1 on error. Use PyErr\_Occurred() to disambiguate.

### size\_t PyLong\_AsSize\_t (PyObject \*pylong)

Part of the Stable ABI. Return a C size\_t representation of pylong. pylong must be an instance of PyLongObject.

Raise OverflowError if the value of pylong is out of range for a size t.

Returns (size\_t) -1 on error. Use PyErr\_Occurred() to disambiguate.

#### unsigned long long PyLong\_AsUnsignedLongLong (PyObject \*pylong)

Part of the Stable ABI. Return a C unsigned long long representation of pylong. pylong must be an instance of PyLongObject.

Raise OverflowError if the value of pylong is out of range for an unsigned long long.

Returns (unsigned long long) -1 on error. Use PyErr Occurred() to disambiguate.

Modifié dans la version 3.1 : A negative *pylong* now raises OverflowError, not TypeError.

#### unsigned long PyLong\_AsUnsignedLongMask (PyObject \*obj)

Part of the Stable ABI. Return a C unsigned long representation of obj. If obj is not an instance of PyLongObject, first call its \_\_index\_\_() method (if present) to convert it to a PyLongObject.

If the value of *obj* is out of range for an unsigned long, return the reduction of that value modulo ULONG\_MAX + 1.

Returns (unsigned long) -1 on error. Use PyErr\_Occurred() to disambiguate.

Modifié dans la version 3.8 : Use index () if available.

Modifié dans la version 3.10 : This function will no longer use \_\_int\_\_().

### unsigned long long PyLong\_AsUnsignedLongLongMask (PyObject \*obj)

Part of the Stable ABI. Return a C unsigned long long representation of obj. If obj is not an instance of PyLongObject, first call its \_\_index\_\_() method (if present) to convert it to a PyLongObject.

If the value of obj is out of range for an unsigned long long, return the reduction of that value modulo ULLONG\_MAX + 1.

Returns (unsigned long long) -1 on error. Use PyErr\_Occurred() to disambiguate.

Modifié dans la version 3.8 : Use \_\_index\_\_ () if available.

Modifié dans la version 3.10 : This function will no longer use \_\_int\_\_().

#### double PyLong\_AsDouble (*PyObject* \*pylong)

Part of the Stable ABI. Return a C double representation of pylong. pylong must be an instance of PyLongObject.

Raise OverflowError if the value of *pylong* is out of range for a double.

Returns -1.0 on error. Use PyErr\_Occurred() to disambiguate.

#### void \*PyLong\_AsVoidPtr (PyObject \*pylong)

Part of the Stable ABI. Convert a Python integer pylong to a C void pointer. If pylong cannot be converted, an OverflowError will be raised. This is only assured to produce a usable void pointer for values created with PyLong\_FromVoidPtr().

Returns NULL on error. Use PyErr\_Occurred() to disambiguate.

### 8.2.2 Les objets booléens

Les booléens en Python sont implémentés comme une classe dérivée des entiers. Il y a seulement deux booléens, Py\_False et Py\_True. Comme tel, les fonctions de création de suppression ne s'appliquent pas aux booléens. Toutefois, les macros suivantes sont disponibles.

#### int PyBool\_Check (PyObject \*o)

Renvoie vrai si *o* est de type PyBook\_Type. Cette fonction réussit systématiquement.

### PyObject \*Py\_False

L'objet Python False. Cet objet n'a pas de méthodes. En ce qui concerne le comptage de référence, il doit être traité comme n'importe quel autre objet.

#### PyObject \*Py\_True

L'objet Python True. Cet objet n'a pas de méthodes. En ce qui concerne le comptage de références, il doit être traité comme n'importe quel autre objet.

#### Py RETURN FALSE

Renvoie Py\_False depuis une fonction tout en incrémentant son nombre de références.

### Py\_RETURN\_TRUE

Renvoie Py\_True depuis une fonction, en incrémentant son nombre de références.

#### PyObject \*PyBool\_FromLong (long v)

Return value : New reference. Part of the Stable ABI. Renvoie une nouvelle référence de  $Py\_True$  ou  $Py\_False$  en fonction de la valeur de v.

### 8.2.3 Objets représentant les nombres à virgule flottante

#### type PyFloatObject

Ce sous-type de l'objet PyObject représente un nombre à virgule flottante en Python.

### PyTypeObject PyFloat\_Type

Part of the Stable ABI. Cette instance de l'objet PyTypeObject représente le type nombre à virgule flottante en Python. C'est le même objet que la classe float de la couche Python.

#### int PyFloat\_Check (PyObject \*p)

Return true if its argument is a PyFloatObject or a subtype of PyFloatObject. This function always succeeds.

#### int PyFloat\_CheckExact (PyObject \*p)

Return true if its argument is a <code>PyFloatObject</code>, but not a subtype of <code>PyFloatObject</code>. This function always succeeds.

#### PyObject \*PyFloat\_FromString (PyObject \*str)

*Return value : New reference. Part of the* Stable ABI. Create a *PyFloatObject* object based on the string value in *str*, or NULL on failure.

#### PyObject \*PyFloat\_FromDouble (double v)

Return value: New reference. Part of the Stable ABI. Create a PyFloatObject object from v, or NULL on failure.

#### double PyFloat\_AsDouble (*PyObject* \*pyfloat)

Part of the Stable ABI. Return a C double representation of the contents of pyfloat. If pyfloat is not a Python floating point object but has a \_\_float\_\_() method, this method will first be called to convert pyfloat into a float. If \_\_float\_\_() is not defined then it falls back to \_\_index\_\_(). This method returns -1.0 upon failure, so one should call PyErr\_Occurred() to check for errors.

Modifié dans la version 3.8 : Use \_\_index\_\_() if available.

#### double PyFloat\_AS\_DOUBLE (PyObject \*pyfloat)

Return a C double representation of the contents of *pyfloat*, but without error checking.

#### PyObject \*PyFloat\_GetInfo (void)

Return value: New reference. Part of the Stable ABI. Renvoie une instance structseq qui contient les informations sur la précision et les valeurs minimales et maximales pour un nombre à virgule flottante. C'est une enveloppe autour du fichier d'entête float.h.

#### double PyFloat\_GetMax()

Part of the Stable ABI. Return the maximum representable finite float DBL\_MAX as C double.

#### double PyFloat\_GetMin()

Part of the Stable ABI. Return the minimum normalized positive float DBL MIN as C double.

#### **Pack and Unpack functions**

The pack and unpack functions provide an efficient platform-independent way to store floating-point values as byte strings. The Pack routines produce a bytes string from a C double, and the Unpack routines produce a C double from such a bytes string. The suffix (2, 4 or 8) specifies the number of bytes in the bytes string.

On platforms that appear to use IEEE 754 formats these functions work by copying bits. On other platforms, the 2-byte format is identical to the IEEE 754 binary16 half-precision format, the 4-byte format (32-bit) is identical to the IEEE 754 binary32 single precision format, and the 8-byte format to the IEEE 754 binary64 double precision format, although the packing of INFs and NaNs (if such things exist on the platform) isn't handled correctly, and attempting to unpack a bytes string containing an IEEE INF or NaN will raise an exception.

On non-IEEE platforms with more precision, or larger dynamic range, than IEEE 754 supports, not all values can be packed; on non-IEEE platforms with less precision, or smaller dynamic range, not all values can be unpacked. What happens in such cases is partly accidental (alas).

Nouveau dans la version 3.11.

### 8.2.4 Pack functions

The pack routines write 2, 4 or 8 bytes, starting at p. le is an int argument, non-zero if you want the bytes string in little-endian format (exponent last, at p+1, p+3, or p+6 p+7), zero if you want big-endian format (exponent first, at p). The PY\_BIG\_ENDIAN constant can be used to use the native endian: it is equal to 1 on big endian processor, or 0 on little endian processor.

Return value: 0 if all is OK, -1 if error (and an exception is set, most likely OverflowError).

There are two problems on non-IEEE platforms:

- What this does is undefined if x is a NaN or infinity.
- -0.0 and +0.0 produce the same bytes string.

int PyFloat\_Pack2 (double x, unsigned char \*p, int le)

Pack a C double as the IEEE 754 binary16 half-precision format.

int PyFloat\_Pack4 (double x, unsigned char \*p, int le)

Pack a C double as the IEEE 754 binary32 single precision format.

int **PyFloat\_Pack8** (double x, unsigned char \*p, int le)

Pack a C double as the IEEE 754 binary64 double precision format.

### 8.2.5 Unpack functions

The unpack routines read 2, 4 or 8 bytes, starting at p. le is an int argument, non-zero if the bytes string is in little-endian format (exponent last, at p+1, p+3 or p+6 and p+7), zero if big-endian (exponent first, at p). The PY\_BIG\_ENDIAN constant can be used to use the native endian: it is equal to 1 on big endian processor, or 0 on little endian processor.

Return value: The unpacked double. On error, this is -1.0 and  $PyErr\_Occurred()$  is true (and an exception is set, most likely OverflowError).

Note that on a non-IEEE platform this will refuse to unpack a bytes string that represents a NaN or infinity.

double PyFloat\_Unpack2 (const unsigned char \*p, int le)

Unpack the IEEE 754 binary16 half-precision format as a C double.

double PyFloat\_Unpack4 (const unsigned char \*p, int le)

Unpack the IEEE 754 binary32 single precision format as a C double.

double PyFloat\_Unpack8 (const unsigned char \*p, int le)

Unpack the IEEE 754 binary64 double precision format as a C double.

### 8.2.6 Objets représentant des nombres complexes

Les nombres complexes Python sont implémentés comme deux types distincts, lorsqu'ils sont vus de l'API C : l'un est l'objet Python tel qu'il est vu par les programmes Python, et l'autre est une structure C qui représente la valeur exacte du nombre complexe. L'API fournit des fonctions pour travailler avec ces deux représentations.

### Nombres complexes en tant que structures C

Les fonctions qui acceptent ces structures comme paramètres et les renvoient comme résultats le font en fonction de leur *valeur* au lieu de les dé-référencer en utilisant des pointeurs. C'est constant dans toute l'API.

#### type Py\_complex

Structure C représentant la valeur d'un nombre complexe Python. La majorité des fonctions qui traitent des nombres complexes utilisent cette structure en entrée ou en sortie, selon le cas. Elle est définie par :

```
typedef struct {
   double real;
   double imag;
} Py_complex;
```

```
Py_complex _Py_c_sum (Py_complex left, Py_complex right)
```

Renvoie la somme de deux nombres complexes, sous la forme d'un Py\_complex en C.

```
Py_complex _Py_c_diff(Py_complex left, Py_complex right)
```

Renvoie la différence de deux nombres complexes, sous la forme d'un Py\_complex en C.

```
Py_complex _Py_c_neg (Py_complex num)
```

Return the negation of the complex number *num*, using the C Py\_complex representation.

```
Py_complex _Py_c_prod (Py_complex left, Py_complex right)
```

Renvoie le produit de deux nombres complexes, sous la forme d'un Py\_complex en C.

```
Py_complex _Py_c_quot (Py_complex dividend, Py_complex divisor)
```

Renvoie le quotient de deux nombres complexes, sous la forme d'un Py\_complex en C.

Si divisor est nul, cette méthode renvoie zéro et assigne EDOM à errno.

```
Py_complex _Py_c_pow (Py_complex num, Py_complex exp)
```

Renvoie *num* à la puissance *exp*, sous la forme d'un *Py\_complex* en C.

Si *num* est nul et *exp* n'est pas un nombre réel positif, cette méthode renvoie zéro et assigne EDOM à errno.

#### Nombres complexes en tant qu'objets Python

#### type PyComplexObject

Ce sous-type de l'objet PyObject représente un nombre complexe en Python.

```
PyTypeObject PyComplex_Type
```

Part of the Stable ABI. Cette instance de PyTypeObject représente le type nombre complexe Python. C'est le même objet que la classe complex de la couche Python.

```
int PyComplex_Check (PyObject *p)
```

Return true if its argument is a PyComplexObject or a subtype of PyComplexObject. This function always succeeds.

```
int PyComplex_CheckExact (PyObject *p)
```

Return true if its argument is a PyComplexObject, but not a subtype of PyComplexObject. This function always succeeds.

```
PyObject *PyComplex_FromCComplex (Py_complex v)
```

Return value : New reference. Crée un nouveau nombre complexe à partir de la valeur d'un Py\_complex en C.

#### PyObject \*PyComplex\_FromDoubles (double real, double imag)

Return value : New reference. Part of the Stable ABI. Renvoie un nouveau PyComplexObject à partir de real et de imag.

#### double PyComplex\_RealAsDouble (PyObject \*op)

Part of the Stable ABI. Return the real part of op as a C double.

### double PyComplex\_ImagAsDouble (PyObject \*op)

Part of the Stable ABI. Return the imaginary part of op as a C double.

#### Py\_complex PyComplex\_AsCComplex (PyObject \*op)

Renvoie la valeur du nombre complexe op sous la forme d'un Py\_complex en C.

If op is not a Python complex number object but has a \_\_complex\_\_() method, this method will first be called to convert op to a Python complex number object. If \_\_complex\_\_() is not defined then it falls back to \_\_float\_\_(). If \_\_float\_\_() is not defined then it falls back to \_\_index\_\_(). Upon failure, this method returns -1.0 as a real value.

Modifié dans la version 3.8 : Use \_\_index\_\_ () if available.

# 8.3 Objets séquences

Les opérations génériques sur les objets séquences ont été discutées dans le chapitre précédent. Cette section traite des genres spécifiques d'objets séquences qui sont intrinsèques au langage Python.

### 8.3.1 Objets bytes

These functions raise TypeError when expecting a bytes parameter and called with a non-bytes parameter.

### type PyBytesObject

This subtype of PyObject represents a Python bytes object.

#### PyTypeObject PyBytes Type

Part of the Stable ABI. This instance of PyTypeObject represents the Python bytes type; it is the same object as bytes in the Python layer.

#### int PyBytes\_Check (PyObject \*o)

Return true if the object o is a bytes object or an instance of a subtype of the bytes type. This function always succeeds.

#### int PyBytes\_CheckExact (PyObject \*o)

Return true if the object o is a bytes object, but not an instance of a subtype of the bytes type. This function always succeeds.

### PyObject \*PyBytes\_FromString (const char \*v)

Return value: New reference. Part of the Stable ABI. Return a new bytes object with a copy of the string v as value on success, and NULL on failure. The parameter v must not be NULL; it will not be checked.

#### PyObject \*PyBytes\_FromStringAndSize (const char \*v, Py\_ssize\_t len)

Return value: New reference. Part of the Stable ABI. Return a new bytes object with a copy of the string v as value and length len on success, and NULL on failure. If v is NULL, the contents of the bytes object are uninitialized.

#### PyObject \*PyBytes\_FromFormat (const char \*format, ...)

Return value: New reference. Part of the Stable ABI. Take a C printf()-style format string and a variable number of arguments, calculate the size of the resulting Python bytes object and return a bytes object with the values formatted into it. The variable arguments must be C types and must correspond exactly to the format characters in the format string. The following format characters are allowed:

Caractères de format	Туре	Comment	
응응	n/a	The literal % character.	
%C	int	A single byte, represented as a C int.	
%d	int	Equivalent to printf("%d").	
%u	unsigned int	Equivalent to printf("%u").	
%ld	long	Equivalent to printf("%ld").	
%lu	unsigned long	Equivalent to printf("%lu").	
%zd	Py_ssize_t	Equivalent to printf("%zd").	
%zu	size_t	Equivalent to printf("%zu").1	
%i	int	Equivalent to printf("%i").1	
%X	int	Equivalent to printf("%x").	
%S	const char*	A null-terminated C character array.	
%p	const void*	The hex representation of a C pointer. Mostly equivalent to	
		printf("%p") except that it is guaranteed to start with	
		the literal 0x regardless of what the platform's printf	
		yields.	

An unrecognized format character causes all the rest of the format string to be copied as-is to the result object, and any extra arguments discarded.

### PyObject \*PyBytes\_FromFormatV (const char \*format, va\_list vargs)

*Return value : New reference. Part of the* Stable ABI. Identical to *PyBytes\_FromFormat()* except that it takes exactly two arguments.

#### PyObject \*PyBytes\_FromObject (PyObject \*o)

*Return value : New reference. Part of the* Stable ABI. Return the bytes representation of object *o* that implements the buffer protocol.

#### Py\_ssize\_t PyBytes\_Size (PyObject \*o)

Part of the Stable ABI. Return the length of the bytes in bytes object o.

### Py\_ssize\_t PyBytes\_GET\_SIZE (PyObject \*o)

Similar to PyBytes\_Size(), but without error checking.

### char \*PyBytes\_AsString (PyObject \*o)

Part of the Stable ABI. Return a pointer to the contents of o. The pointer refers to the internal buffer of o, which consists of len(o) + 1 bytes. The last byte in the buffer is always null, regardless of whether there are any other null bytes. The data must not be modified in any way, unless the object was just created using PyBytes\_FromStringAndSize(NULL, size). It must not be deallocated. If o is not a bytes object at all,  $PyBytes\_AsString()$  returns NULL and raises TypeError.

#### char \*PyBytes\_AS\_STRING (PyObject \*string)

Similar to PyBytes\_AsString(), but without error checking.

#### int PyBytes\_AsStringAndSize (PyObject \*obj, char \*\*buffer, Py\_ssize\_t \*length)

Part of the Stable ABI. Return the null-terminated contents of the object obj through the output variables buffer and length.

 $<sup>1. \ \ \</sup>text{For integer specifiers } (d,u,ld,lu,zd,zu,i,x): the \ 0-conversion \ flag \ has \ effect \ even \ when \ a \ precision \ is \ given.$ 

If *length* is NULL, the bytes object may not contain embedded null bytes; if it does, the function returns -1 and a ValueError is raised.

The buffer refers to an internal buffer of *obj*, which includes an additional null byte at the end (not counted in *length*). The data must not be modified in any way, unless the object was just created using PyBytes\_FromStringAndSize(NULL, size). It must not be deallocated. If *obj* is not a bytes object at all, *PyBytes\_AsStringAndSize()* returns -1 and raises TypeError.

Modifié dans la version 3.5 : Previously, TypeError was raised when embedded null bytes were encountered in the bytes object.

### void PyBytes\_Concat (PyObject \*\*bytes, PyObject \*newpart)

Part of the Stable ABI. Create a new bytes object in \*bytes containing the contents of newpart appended to bytes; the caller will own the new reference. The reference to the old value of bytes will be stolen. If the new object cannot be created, the old reference to bytes will still be discarded and the value of \*bytes will be set to NULL; the appropriate exception will be set.

#### void PyBytes\_ConcatAndDel (PyObject \*\*bytes, PyObject \*newpart)

Part of the Stable ABI. Create a new bytes object in \*bytes containing the contents of newpart appended to bytes. This version decrements the reference count of newpart.

#### int \_PyBytes\_Resize (PyObject \*\*bytes, Py\_ssize\_t newsize)

A way to resize a bytes object even though it is "immutable". Only use this to build up a brand new bytes object; don't use this if the bytes may already be known in other parts of the code. It is an error to call this function if the refcount on the input bytes object is not one. Pass the address of an existing bytes object as an Ivalue (it may be written into), and the new size desired. On success, \*bytes holds the resized bytes object and 0 is returned; the address in \*bytes may differ from its input value. If the reallocation fails, the original bytes object at \*bytes is deallocated, \*bytes is set to NULL, MemoryError is set, and -1 is returned.

### 8.3.2 Objets tableau d'octets

#### type PyByteArrayObject

Ce sous-type de *PyObject* représente un objet bytearray Python.

### PyTypeObject PyByteArray\_Type

Part of the Stable ABI. Cette instance de PyTypeObject représente le type Python bytearray, c'est le même que bytearray côté Python.

### Macros de vérification de type

### int PyByteArray\_Check (PyObject \*o)

Renvoie vrai si l'objet o est un bytearray ou une instance d'un sous-type du type bytearray. Cette méthode réussit toujours.

#### int PyByteArray\_CheckExact (PyObject \*o)

Renvoie vrai si l'objet *o* est un bytearray, mais pas une instance d'un sous-type du type bytearray. Cette méthode réussit toujours.

#### Fonctions directes sur l'API

#### PyObject \*PyByteArray\_FromObject (PyObject \*o)

Return value : New reference. Part of the Stable ABI. Renvoie un nouvel objet bytearray depuis n'importe quel objet, o, qui implémente le protocole buffer.

### PyObject \*PyByteArray\_FromStringAndSize (const char \*string, Py\_ssize\_t len)

Return value : New reference. Part of the Stable ABI. Crée un nouvel objet bytearray à partir d'un objet string et de sa longueur, len. En cas d'échec, NULL est renvoyé.

```
PyObject *PyByteArray_Concat (PyObject *a, PyObject *b)
```

Return value : New reference. Part of the Stable ABI. Concatène les bytearrays a et b et renvoie un nouveau bytearray avec le résultat.

```
Py_ssize_t PyByteArray_Size (PyObject *bytearray)
```

Part of the Stable ABI. Renvoie la taille de bytearray après vérification de la présence d'un pointeur NULL.

```
char *PyByteArray_AsString (PyObject *bytearray)
```

Part of the Stable ABI. Renvoie le contenu de bytearray sous forme d'un tableau de caractères, en vérifiant que ce n'est pas un pointeur NULL. Le tableau renvoyé a toujours un caractère null rajouté.

```
int PyByteArray_Resize (PyObject *bytearray, Py_ssize_t len)
```

Part of the Stable ABI. Redimensionne le tampon interne de bytearray à la taille len.

#### **Macros**

Ces macros sont taillées pour la vitesse d'exécution et ne vérifient pas les pointeurs.

```
char *PyByteArray_AS_STRING (PyObject *bytearray)
```

Similar to PyByteArray\_AsString(), but without error checking.

```
Py_ssize_t PyByteArray_GET_SIZE (PyObject *bytearray)
```

Similar to PyByteArray\_Size(), but without error checking.

### 8.3.3 Objets Unicode et Codecs

#### **Objets Unicode**

Depuis l'implémentation de **PEP 393** dans Python 3.3, les objets Unicode utilisent une variété de représentations internes, pour permettre de gérer l'intervalle complet des caractères Unicode en restant efficace en termes de mémoire. Il y a des cas spéciaux pour les chaînes où tous les points de code sont inférieurs à 128, 256, ou 65536; sinon, les points de code doivent être inférieurs à 1114112 (qui est l'intervalle Unicode complet).

Des représentations  $Py\_UNICODE^*$  et UTF-8 sont créées à la demande et mises en cache dans l'objet Unicode. La représentation  $Py\_UNICODE^*$  est dépréciée et inefficace.

En raison de la transition des anciennes APIs vers les nouvelles APIs, les objets Unicode peuvent être dans deux états internes selon comment ils ont été créés :

- Les objets Unicode « canoniques » sont tous les objets créés par une API Unicode non-dépréciée. Ils utilisent la représentation la plus efficace permise par l'implémentation.
- Les objets Unicode « historiques » ont été créés via une des APIs dépréciées (typiquement PyUnicode\_FromUnicode()) et supportent uniquement la représentation Py\_UNICODE\*; vous devrez appeler PyUnicode READY() sur eux avant d'appeler n'importe quelle autre API.

**Note :** Les objets Unicode « historiques » vont être supprimés de Python 3.12 avec les APIs dépréciées. Tous les objets Unicode vont être « canoniques » à partir de là. Voir **PEP 623** pour plus d'information.

### **Type Unicode**

Voici les types d'objets Unicode utilisés pour l'implémentation Unicode en Python :

type Py\_UCS4

type Py\_UCS2

type Py\_UCS1

Part of the Stable ABI. Voici les *typedefs* pour les types entiers non signés suffisamment large pour contenir des caractères de 32 bits, 16 bits et 8 bits, respectivement. Pour traiter des caractères uniques, utilisez *Py\_UCS4*. Nouveau dans la version 3.3.

#### type Py\_UNICODE

Ceci est un typedef de wchar\_t, qui est un type 16-bit ou un type 32-bit selon la plateforme.

Modifié dans la version 3.3 : Dans les versions précédentes, ceci était un type 16-bit ou un type 32-bit selon que vous choisissiez une version Unicode *narrow* ou *wide* de Python à la compilation.

#### type PyASCIIObject

type PyCompactUnicodeObject

#### type PyUnicodeObject

These subtypes of PyObject represent a Python Unicode object. In almost all cases, they shouldn't be used directly, since all API functions that deal with Unicode objects take and return PyObject pointers.

Nouveau dans la version 3.3.

#### PyTypeObject PyUnicode\_Type

Part of the Stable ABI. This instance of PyTypeObject represents the Python Unicode type. It is exposed to Python code as str.

The following APIs are C macros and static inlined functions for fast checks and access to internal read-only data of Unicode objects:

#### int PyUnicode Check (PyObject \*o)

Return true if the object o is a Unicode object or an instance of a Unicode subtype. This function always succeeds.

### int PyUnicode\_CheckExact (PyObject \*o)

Return true if the object o is a Unicode object, but not an instance of a subtype. This function always succeeds.

#### int PyUnicode\_READY (PyObject \*o)

Ensure the string object o is in the "canonical" representation. This is required before using any of the access macros described below.

Returns 0 on success and -1 with an exception set on failure, which in particular happens if memory allocation fails.

Nouveau dans la version 3.3.

Obsolète depuis la version 3.10, sera supprimé dans la version 3.12 : This API will be removed with <code>PyUnicode\_FromUnicode()</code>.

### Py\_ssize\_t PyUnicode\_GET\_LENGTH (PyObject \*o)

Return the length of the Unicode string, in code points. *o* has to be a Unicode object in the "canonical" representation (not checked).

Nouveau dans la version 3.3.

```
Py_UCS1 *PyUnicode_1BYTE_DATA (PyObject *o)
```

Py\_UCS2 \*PyUnicode\_2BYTE\_DATA (PyObject \*o)

Py\_UCS4 \*PyUnicode\_4BYTE\_DATA (PyObject \*o)

Return a pointer to the canonical representation cast to UCS1, UCS2 or UCS4 integer types for direct character access. No checks are performed if the canonical representation has the correct character size; use <code>PyUnicode\_KIND()</code> to select the right macro. Make sure <code>PyUnicode\_READY()</code> has been called before accessing this.

Nouveau dans la version 3.3.

#### PyUnicode\_WCHAR\_KIND

PyUnicode\_1BYTE\_KIND

PyUnicode\_2BYTE\_KIND

PyUnicode\_4BYTE\_KIND

Return values of the PyUnicode\_KIND() macro.

Nouveau dans la version 3.3.

Obsolète depuis la version 3.10, sera supprimé dans la version 3.12 : PyUnicode\_WCHAR\_KIND is deprecated.

#### int PyUnicode\_KIND (PyObject \*o)

Return one of the PyUnicode kind constants (see above) that indicate how many bytes per character this Unicode object uses to store its data. *o* has to be a Unicode object in the "canonical" representation (not checked).

Nouveau dans la version 3.3.

### void \*PyUnicode\_DATA (PyObject \*o)

Return a void pointer to the raw Unicode buffer. *o* has to be a Unicode object in the "canonical" representation (not checked).

Nouveau dans la version 3.3.

### void **PyUnicode\_WRITE** (int kind, void \*data, *Py\_ssize\_t* index, *Py\_UCS4* value)

Write into a canonical representation *data* (as obtained with *PyUnicode\_DATA()*). This function performs no sanity checks, and is intended for usage in loops. The caller should cache the *kind* value and *data* pointer as obtained from other calls. *index* is the index in the string (starts at 0) and *value* is the new code point value which should be written to that location.

Nouveau dans la version 3.3.

### Py\_UCS4 PyUnicode\_READ (int kind, void \*data, Py\_ssize\_t index)

Read a code point from a canonical representation *data* (as obtained with *PyUnicode\_DATA()*). No checks or ready calls are performed.

Nouveau dans la version 3.3.

### Py\_UCS4 PyUnicode\_READ\_CHAR (PyObject \*o, Py\_ssize\_t index)

Read a character from a Unicode object o, which must be in the "canonical" representation. This is less efficient than PyUnicode\_READ() if you do multiple consecutive reads.

Nouveau dans la version 3.3.

#### Py\_UCS4 PyUnicode\_MAX\_CHAR\_VALUE (PyObject \*o)

Return the maximum code point that is suitable for creating another string based on o, which must be in the "canonical" representation. This is always an approximation but more efficient than iterating over the string.

Nouveau dans la version 3.3.

#### Py\_ssize\_t PyUnicode\_GET\_SIZE (PyObject \*o)

Return the size of the deprecated  $PY\_UNICODE$  representation, in code units (this includes surrogate pairs as 2 units). o has to be a Unicode object (not checked).

Obsolète depuis la version 3.3, sera supprimé dans la version 3.12 : Part of the old-style Unicode API, please migrate to using <code>PyUnicode\_GET\_LENGTH()</code>.

#### Py\_ssize\_t PyUnicode\_GET\_DATA\_SIZE (PyObject \*o)

Return the size of the deprecated  $Py\_UNICODE$  representation in bytes. o has to be a Unicode object (not checked). Obsolète depuis la version 3.3, sera supprimé dans la version 3.12 : Part of the old-style Unicode API, please migrate to using  $PyUnicode\_GET\_LENGTH()$ .

```
Py_UNICODE *PyUnicode_AS_UNICODE (PyObject *o)
```

```
const char *PyUnicode_AS_DATA (PyObject *o)
```

Return a pointer to a *Py\_UNICODE* representation of the object. The returned buffer is always terminated with an extra null code point. It may also contain embedded null code points, which would cause the string to be truncated when used in most C functions. The AS\_DATA form casts the pointer to const char\*. The *o* argument has to be a Unicode object (not checked).

Modifié dans la version 3.3 : This function is now inefficient -- because in many cases the  $Py\_UNICODE$  representation does not exist and needs to be created -- and can fail (return NULL with an exception set). Try to port the code to use the new PyUnicode\_nBYTE\_DATA() macros or use  $PyUnicode\_WRITE()$  or  $PyUnicode\_READ()$ .

Obsolète depuis la version 3.3, sera supprimé dans la version 3.12 : Part of the old-style Unicode API, please migrate to using the PyUnicode\_nBYTE\_DATA() family of macros.

```
int PyUnicode_IsIdentifier (PyObject *o)
```

Part of the Stable ABI. Return 1 if the string is a valid identifier according to the language definition, section identifiers. Return 0 otherwise.

Modifié dans la version 3.9: The function does not call Py\_FatalError() anymore if the string is not ready.

### **Unicode Character Properties**

Unicode provides many different character properties. The most often needed ones are available through these macros which are mapped to C functions depending on the Python configuration.

```
int Py UNICODE ISSPACE (Py UCS4 ch)
```

Return 1 or 0 depending on whether *ch* is a whitespace character.

```
int Py_UNICODE_ISLOWER (Py_UCS4 ch)
```

Return 1 or 0 depending on whether ch is a lowercase character.

```
int Py_UNICODE_ISUPPER (Py_UCS4 ch)
```

Return 1 or 0 depending on whether ch is an uppercase character.

```
int Py UNICODE ISTITLE (Py UCS4 ch)
```

Return 1 or 0 depending on whether ch is a titlecase character.

```
int Py_UNICODE_ISLINEBREAK (Py_UCS4 ch)
```

Return 1 or 0 depending on whether ch is a linebreak character.

```
int Py UNICODE ISDECIMAL (Py UCS4 ch)
```

Return 1 or 0 depending on whether ch is a decimal character.

```
int Py_UNICODE_ISDIGIT (Py_UCS4 ch)
```

Return 1 or 0 depending on whether *ch* is a digit character.

```
int Py UNICODE ISNUMERIC (Py UCS4 ch)
```

Return 1 or 0 depending on whether ch is a numeric character.

```
int Py_UNICODE_ISALPHA (Py_UCS4 ch)
```

Return 1 or 0 depending on whether *ch* is an alphabetic character.

#### int Py\_UNICODE\_ISALNUM (Py\_UCS4 ch)

Return 1 or 0 depending on whether *ch* is an alphanumeric character.

### int Py\_UNICODE\_ISPRINTABLE (Py\_UCS4 ch)

Return 1 or 0 depending on whether ch is a printable character. Nonprintable characters are those characters defined in the Unicode character database as "Other" or "Separator", excepting the ASCII space (0x20) which is considered printable. (Note that printable characters in this context are those which should not be escaped when repr() is invoked on a string. It has no bearing on the handling of strings written to sys.stdout or sys.stderr.)

These APIs can be used for fast direct character conversions:

### Py\_UCS4 Py\_UNICODE\_TOLOWER (Py\_UCS4 ch)

Return the character ch converted to lower case.

Obsolète depuis la version 3.3 : This function uses simple case mappings.

#### Py\_UCS4 Py\_UNICODE\_TOUPPER (Py\_UCS4 ch)

Return the character ch converted to upper case.

Obsolète depuis la version 3.3 : This function uses simple case mappings.

### Py\_UCS4 Py\_UNICODE\_TOTITLE (Py\_UCS4 ch)

Return the character *ch* converted to title case.

Obsolète depuis la version 3.3 : This function uses simple case mappings.

### int Py\_UNICODE\_TODECIMAL (Py\_UCS4 ch)

Return the character ch converted to a decimal positive integer. Return -1 if this is not possible. This macro does not raise exceptions.

### int Py\_UNICODE\_TODIGIT (Py\_UCS4 ch)

Return the character ch converted to a single digit integer. Return -1 if this is not possible. This macro does not raise exceptions.

#### double Py\_UNICODE\_TONUMERIC (Py\_UCS4 ch)

Return the character ch converted to a double. Return -1.0 if this is not possible. This macro does not raise exceptions.

These APIs can be used to work with surrogates:

### Py\_UNICODE\_IS\_SURROGATE (ch)

Check if ch is a surrogate (0xD800 <= ch <= 0xDFFF).

#### Py\_UNICODE\_IS\_HIGH\_SURROGATE (ch)

Check if ch is a high surrogate (0xD800 <= ch <= 0xDBFF).

#### Py\_UNICODE\_IS\_LOW\_SURROGATE (ch)

Check if ch is a low surrogate (0xDC00 <= ch <= 0xDFFF).

### Py\_UNICODE\_JOIN\_SURROGATES (high, low)

Join two surrogate characters and return a single Py\_UCS4 value. *high* and *low* are respectively the leading and trailing surrogates in a surrogate pair.

### **Creating and accessing Unicode strings**

To create Unicode objects and access their basic sequence properties, use these APIs:

#### PyObject \*PyUnicode\_New (Py\_ssize\_t size, Py\_UCS4 maxchar)

*Return value : New reference.* Create a new Unicode object. *maxchar* should be the true maximum code point to be placed in the string. As an approximation, it can be rounded up to the nearest value in the sequence 127, 255, 65535, 1114111.

This is the recommended way to allocate a new Unicode object. Objects created using this function are not resizable. Nouveau dans la version 3.3.

### PyObject \*PyUnicode\_FromKindAndData (int kind, const void \*buffer, Py\_ssize\_t size)

Return value: New reference. Create a new Unicode object with the given kind (possible values are PyUnicode\_1BYTE\_KIND etc., as returned by PyUnicode\_KIND()). The buffer must point to an array of size units of 1, 2 or 4 bytes per character, as given by the kind.

If necessary, the input *buffer* is copied and transformed into the canonical representation. For example, if the *buffer* is a UCS4 string (*PyUnicode\_4BYTE\_KIND*) and it consists only of codepoints in the UCS1 range, it will be transformed into UCS1 (*PyUnicode\_1BYTE\_KIND*).

Nouveau dans la version 3.3.

#### PyObject \*PyUnicode\_FromStringAndSize (const char \*u, Py\_ssize\_t size)

Return value: New reference. Part of the Stable ABI. Create a Unicode object from the char buffer u. The bytes will be interpreted as being UTF-8 encoded. The buffer is copied into the new object. If the buffer is not NULL, the return value might be a shared object, i.e. modification of the data is not allowed.

If u is NULL, this function behaves like  $PyUnicode\_FromUnicode$  () with the buffer set to NULL. This usage is deprecated in favor of  $PyUnicode\_New$  (), and will be removed in Python 3.12.

#### PyObject \*PyUnicode\_FromString (const char \*u)

Return value: New reference. Part of the Stable ABI. Create a Unicode object from a UTF-8 encoded null-terminated char buffer u.

### PyObject \*PyUnicode\_FromFormat (const char \*format, ...)

Return value: New reference. Part of the Stable ABI. Take a C printf()-style format string and a variable number of arguments, calculate the size of the resulting Python Unicode string and return a string with the values formatted into it. The variable arguments must be C types and must correspond exactly to the format characters in the format ASCII-encoded string. The following format characters are allowed:

Caractères de format	Туре	Comment
9 9	n/a	The literal % character.
%C	int	A single character, represented as a C int.
%d	int	Equivalent to printf("%d"). 1
%u	unsigned int	Equivalent to printf ("%u"). page 125, 1
%ld	long	Equivalent to printf ("%ld"). page 125, 1
%li	long	Equivalent to printf ("%li").page 125, 1
%lu	unsigned long	Equivalent to printf ("%lu").page 125, 1
%lld	long long	Equivalent to printf("%lld").page 125, 1
%11i	long long	Equivalent to printf("%lli").page 125, 1
%llu	unsigned long long	Equivalent to printf ("%llu").page 125, 1
%zd	Py_ssize_t	Equivalent to printf ("%zd").page 125, 1
%zi	Py_ssize_t	Equivalent to printf ("%zi").page 125, 1
%zu	size_t	Equivalent to printf ("%zu").page 125, 1
%i	int	Equivalent to printf ("%i"). page 125, 1
%X	int	Equivalent to printf ("%x"). page 125, 1
%S	const char*	A null-terminated C character array.
%p	const void*	The hex representation of a C pointer. Mostly
		equivalent to printf("%p") except that it is
		guaranteed to start with the literal 0x regardless of
		what the platform's printf yields.
%A	PyObject*	The result of calling ascii().
%U	PyObject*	A Unicode object.
%V	PyObject*, const char*	A Unicode object (which may be NULL) and a
		null-terminated C character array as a second
		parameter (which will be used, if the first parameter
		is NULL).
%S	PyObject*	The result of calling PyObject_Str().
%R	PyObject*	The result of calling PyObject_Repr().

An unrecognized format character causes all the rest of the format string to be copied as-is to the result string, and any extra arguments discarded.

Note: The width formatter unit is number of characters rather than bytes. The precision formatter unit is number of bytes for "%s" and "%V" (if the PyObject\* argument is NULL), and a number of characters for "%A", "%U", "%S", "%R" and "%V" (if the PyObject\* argument is not NULL).

Modifié dans la version 3.2 : Support for "%lld" and "%llu" added.

Modifié dans la version 3.3 : Support for "%li", "%lli" and "%zi" added.

Modifié dans la version 3.4 : Support width and precision formatter for "%s", "%A", "%U", "%V", "%S", "%R" added.

### PyObject \*PyUnicode\_FromFormatV (const char \*format, va\_list vargs)

*Return value : New reference. Part of the* Stable ABI. Identical to *PyUnicode\_FromFormat()* except that it takes exactly two arguments.

### PyObject \*PyUnicode\_FromObject (PyObject \*obj)

Return value: New reference. Part of the Stable ABI. Copy an instance of a Unicode subtype to a new true Unicode object if necessary. If obj is already a true Unicode object (not a subtype), return the reference with incremented refcount.

Objects other than Unicode or its subtypes will cause a TypeError.

<sup>1.</sup> For integer specifiers (d, u, ld, li, lu, lld, lli, llu, zd, zi, zu, i, x): the 0-conversion flag has effect even when a precision is given.

#### PyObject \*PyUnicode\_FromEncodedObject (PyObject \*obj, const char \*encoding, const char \*errors)

Return value: New reference. Part of the Stable ABI. Decode an encoded object obj to a Unicode object.

bytes, bytearray and other *bytes-like objects* are decoded according to the given *encoding* and using the error handling defined by *errors*. Both can be NULL to have the interface use the default values (see *Built-in Codecs* for details).

All other objects, including Unicode objects, cause a TypeError to be set.

The API returns NULL if there was an error. The caller is responsible for decref'ing the returned objects.

### Py\_ssize\_t PyUnicode\_GetLength (PyObject \*unicode)

Part of the Stable ABI since version 3.7. Return the length of the Unicode object, in code points.

Nouveau dans la version 3.3.

# Py\_ssize\_t PyUnicode\_CopyCharacters (PyObject \*to, Py\_ssize\_t to\_start, PyObject \*from, Py\_ssize\_t from\_start, Py\_ssize\_t how\_many)

Copy characters from one Unicode object into another. This function performs character conversion when necessary and falls back to memcpy () if possible. Returns -1 and sets an exception on error, otherwise returns the number of copied characters.

Nouveau dans la version 3.3.

### Py\_ssize\_t PyUnicode\_Fill (PyObject \*unicode, Py\_ssize\_t start, Py\_ssize\_t length, Py\_UCS4 fill\_char)

Fill a string with a character: write fill\_char into unicode[start:start+length].

Fail if fill\_char is bigger than the string maximum character, or if the string has more than 1 reference.

Return the number of written character, or return -1 and raise an exception on error.

Nouveau dans la version 3.3.

### int PyUnicode\_WriteChar (*PyObject* \*unicode, *Py\_ssize\_t* index, *Py\_UCS4* character)

Part of the Stable ABI since version 3.7. Write a character to a string. The string must have been created through PyUnicode\_New(). Since Unicode strings are supposed to be immutable, the string must not be shared, or have been hashed yet.

This function checks that *unicode* is a Unicode object, that the index is not out of bounds, and that the object can be modified safely (i.e. that it its reference count is one).

Nouveau dans la version 3.3.

### Py\_UCS4 PyUnicode\_ReadChar (PyObject \*unicode, Py\_ssize\_t index)

Part of the Stable ABI since version 3.7. Read a character from a string. This function checks that unicode is a Unicode object and the index is not out of bounds, in contrast to PyUnicode\_READ\_CHAR(), which performs no error checking.

Nouveau dans la version 3.3.

#### PyObject \*PyUnicode\_Substring (PyObject \*str, Py\_ssize\_t start, Py\_ssize\_t end)

Return value: New reference. Part of the Stable ABI since version 3.7. Return a substring of str, from character index start (included) to character index end (excluded). Negative indices are not supported.

Nouveau dans la version 3.3.

### Py\_UCS4 \*PyUnicode\_AsuCS4 (PyObject \*u, Py\_UCS4 \*buffer, Py\_ssize\_t buflen, int copy\_null)

*Part of the* Stable ABI *since version 3.7.* Copy the string *u* into a UCS4 buffer, including a null character, if *copy\_null* is set. Returns NULL and sets an exception on error (in particular, a SystemError if *buflen* is smaller than the length of *u*). *buffer* is returned on success.

Nouveau dans la version 3.3.

### Py\_UCS4 \*PyUnicode\_AsUCS4Copy (PyObject \*u)

Part of the Stable ABI since version 3.7. Copy the string u into a new UCS4 buffer that is allocated using  $PyMem\_Malloc()$ . If this fails, NULL is returned with a MemoryError set. The returned buffer always has an extra null code point appended.

Nouveau dans la version 3.3.

### Deprecated Py\_UNICODE APIs

Obsolète depuis la version 3.3, sera supprimé dans la version 3.12.

These API functions are deprecated with the implementation of **PEP 393**. Extension modules can continue using them, as they will not be removed in Python 3.x, but need to be aware that their use can now cause performance and memory hits

#### PyObject \*PyUnicode FromUnicode (const Py UNICODE \*u, Py ssize t size)

*Return value : New reference.* Create a Unicode object from the Py\_UNICODE buffer *u* of the given size. *u* may be NULL which causes the contents to be undefined. It is the user's responsibility to fill in the needed data. The buffer is copied into the new object.

If the buffer is not NULL, the return value might be a shared object. Therefore, modification of the resulting Unicode object is only allowed when u is NULL.

If the buffer is NULL, <code>PyUnicode\_READY()</code> must be called once the string content has been filled before using any of the access macros such as <code>PyUnicode\_KIND()</code>.

Obsolète depuis la version 3.3, sera supprimé dans la version 3.12 : Part of the old-style Unicode API, please migrate to using <code>PyUnicode\_FromKindAndData()</code>, <code>PyUnicode\_FromWideChar()</code>, or <code>PyUnicode\_New()</code>.

### Py\_UNICODE \*PyUnicode\_AsUnicode (PyObject \*unicode)

Return a read-only pointer to the Unicode object's internal  $Py\_UNICODE$  buffer, or NULL on error. This will create the  $Py\_UNICODE^*$  representation of the object if it is not yet available. The buffer is always terminated with an extra null code point. Note that the resulting  $Py\_UNICODE$  string may also contain embedded null code points, which would cause the string to be truncated when used in most C functions.

Obsolète depuis la version 3.3, sera supprimé dans la version 3.12 : Part of the old-style Unicode API, please migrate to using <code>PyUnicode\_Asucs4()</code>, <code>PyUnicode\_AswideChar()</code>, <code>PyUnicode\_ReadChar()</code> or similar new APIs.

#### Py\_UNICODE \*PyUnicode\_AsUnicodeAndSize (PyObject \*unicode, Py\_ssize\_t \*size)

Like  $PyUnicode\_AsUnicode()$ , but also saves the  $Py\_UNICODE()$  array length (excluding the extra null terminator) in *size*. Note that the resulting  $Py\_UNICODE*$  string may contain embedded null code points, which would cause the string to be truncated when used in most C functions.

Nouveau dans la version 3.3.

Obsolète depuis la version 3.3, sera supprimé dans la version 3.12 : Part of the old-style Unicode API, please migrate to using <code>PyUnicode\_Asucs4()</code>, <code>PyUnicode\_AswideChar()</code>, <code>PyUnicode\_ReadChar()</code> or similar new APIs.

### Py\_ssize\_t PyUnicode\_GetSize (PyObject \*unicode)

*Part of the* Stable ABI. Return the size of the deprecated *Py\_UNICODE* representation, in code units (this includes surrogate pairs as 2 units).

Obsolète depuis la version 3.3, sera supprimé dans la version 3.12 : Part of the old-style Unicode API, please migrate to using PyUnicode GET LENGTH().

### **Locale Encoding**

The current locale encoding can be used to decode text from the operating system.

#### PyObject \*PyUnicode\_DecodeLocaleAndSize (const char \*str, Py\_ssize\_t len, const char \*errors)

Return value: New reference. Part of the Stable ABI since version 3.7. Decode a string from UTF-8 on Android and VxWorks, or from the current locale encoding on other platforms. The supported error handlers are "strict" and "surrogateescape" (PEP 383). The decoder uses "strict" error handler if errors is NULL. str must end with a null character but cannot contain embedded null characters.

Use <code>PyUnicode\_DecodeFSDefaultAndSize()</code> to decode a string from <code>Py\_FileSystemDefaultEncoding()</code> the locale encoding read at Python startup).

This function ignores the Python UTF-8 Mode.

#### Voir aussi:

The Py\_DecodeLocale() function.

Nouveau dans la version 3.3.

Modifié dans la version 3.7: The function now also uses the current locale encoding for the surrogateescape error handler, except on Android. Previously,  $Py\_DecodeLocale()$  was used for the surrogateescape, and the current locale encoding was used for strict.

#### PyObject \*PyUnicode\_DecodeLocale (const char \*str, const char \*errors)

Return value: New reference. Part of the Stable ABI since version 3.7. Similar to  $PyUnicode\_DecodeLocaleAndSize()$ , but compute the string length using strlen().

Nouveau dans la version 3.3.

### PyObject \*PyUnicode\_EncodeLocale (PyObject \*unicode, const char \*errors)

Return value: New reference. Part of the Stable ABI since version 3.7. Encode a Unicode object to UTF-8 on Android and VxWorks, or to the current locale encoding on other platforms. The supported error handlers are "strict" and "surrogateescape" (PEP 383). The encoder uses "strict" error handler if errors is NULL. Return a bytes object. unicode cannot contain embedded null characters.

Use PyUnicode\_EncodeFSDefault () to encode a string to Py\_FileSystemDefaultEncoding (the locale encoding read at Python startup).

This function ignores the Python UTF-8 Mode.

#### Voir aussi:

The Py\_EncodeLocale() function.

Nouveau dans la version 3.3.

Modifié dans la version 3.7: The function now also uses the current locale encoding for the surrogateescape error handler, except on Android. Previously,  $Py\_EncodeLocale()$  was used for the surrogateescape, and the current locale encoding was used for strict.

### **File System Encoding**

To encode and decode file names and other environment strings, Py\_FileSystemDefaultEncoding should be used as the encoding, and Py\_FileSystemDefaultEncodeErrors should be used as the error handler (PEP 383 and PEP 529). To encode file names to bytes during argument parsing, the "O&" converter should be used, passing PyUnicode\_FSConverter() as the conversion function:

#### int PyUnicode\_FSConverter (*PyObject* \*obj, void \*result)

Part of the Stable ABI. ParseTuple converter: encode str objects -- obtained directly or through the os. PathLike interface -- to bytes using <code>PyUnicode\_EncodeFSDefault()</code>; bytes objects are output as-is. result must be a <code>PyBytesObject\*</code> which must be released when it is no longer used.

Nouveau dans la version 3.1.

Modifié dans la version 3.6 : Accepte un path-like object.

To decode file names to str during argument parsing, the "O&" converter should be used, passing  $PyUnicode\_FSDecoder()$  as the conversion function:

### int PyUnicode\_FSDecoder (*PyObject* \*obj, void \*result)

Part of the Stable ABI. ParseTuple converter: decode bytes objects -- obtained either directly or indirectly through the os.PathLike interface -- to str using <code>PyUnicode\_DecodeFSDefaultAndSize()</code>; str objects are output as-is. <code>result</code> must be a <code>PyUnicodeObject\*</code> which must be released when it is no longer used. Nouveau dans la version 3.2.

Modifié dans la version 3.6 : Accepte un path-like object.

#### PyObject \*PyUnicode\_DecodeFSDefaultAndSize (const char \*s, Py\_ssize\_t size)

Return value: New reference. Part of the Stable ABI. Decode a string from the filesystem encoding and error handler. If Py\_FileSystemDefaultEncoding is not set, fall back to the locale encoding.

Py\_FileSystemDefaultEncoding is initialized at startup from the locale encoding and cannot be modified later. If you need to decode a string from the current locale encoding, use PyUnicode\_DecodeLocaleAndSize().

#### Voir aussi:

The Py\_DecodeLocale() function.

 $\label{local_modified_model} \textbf{Modifi\'ed} \ \ \textbf{dans} \ \ \textbf{la} \ \ \textbf{version} \ \ \textbf{3.6} : \textbf{Use} \ \texttt{Py\_FileSystemDefaultEncodeErrors} \ \ \textbf{error} \ \ \textbf{handler}.$ 

### PyObject \*PyUnicode\_DecodeFSDefault (const char \*s)

Return value: New reference. Part of the Stable ABI. Decode a null-terminated string from the filesystem encoding and error handler.

If Py FileSystemDefaultEncoding is not set, fall back to the locale encoding.

Use PyUnicode\_DecodeFSDefaultAndSize() if you know the string length.

Modifié dans la version 3.6: Use Py\_FileSystemDefaultEncodeErrors error handler.

### PyObject \*PyUnicode\_EncodeFSDefault (PyObject \*unicode)

Return value: New reference. Part of the Stable ABI. Encode a Unicode object to Py\_FileSystemDefaultEncoding with the Py\_FileSystemDefaultEncodeErrors error handler, and return bytes. Note that the resulting bytes object may contain null bytes.

If Py\_FileSystemDefaultEncoding is not set, fall back to the locale encoding.

 $\label{eq:py_file_system} \begin{picture}{l} Py\_FileSystemDefaultEncoding is initialized at startup from the locale encoding and cannot be modified later. If you need to encode a string to the current locale encoding, use $PyUnicode\_EncodeLocale()$. \end{picture}$ 

#### Voir aussi:

The Py\_EncodeLocale() function.

Nouveau dans la version 3.2.

Modifié dans la version 3.6 : Use Py\_FileSystemDefaultEncodeErrors error handler.

#### wchar t Support

wchar\_t support for platforms which support it:

#### PyObject \*PyUnicode\_FromWideChar (const wchar\_t \*w, Py\_ssize\_t size)

Return value: New reference. Part of the Stable ABI. Create a Unicode object from the wchar\_t buffer w of the given size. Passing -1 as the size indicates that the function must itself compute the length, using wcslen. Return NULL on failure.

### Py\_ssize\_t PyUnicode\_AsWideChar (PyObject \*unicode, wchar\_t \*w, Py\_ssize\_t size)

Part of the Stable ABI. Copy the Unicode object contents into the wchar\_t buffer w. At most size wchar\_t characters are copied (excluding a possibly trailing null termination character). Return the number of wchar\_t characters copied or -1 in case of an error. Note that the resulting wchar\_t\* string may or may not be null-terminated. It is the responsibility of the caller to make sure that the wchar\_t\* string is null-terminated in case this is required by the application. Also, note that the wchar\_t\* string might contain null characters, which would cause the string to be truncated when used with most C functions.

### wchar t \*PyUnicode AsWideCharString (PyObject \*unicode, Py ssize t \*size)

Part of the Stable ABI since version 3.7. Convert the Unicode object to a wide character string. The output string always ends with a null character. If size is not NULL, write the number of wide characters (excluding the trailing null termination character) into \*size. Note that the resulting wchar\_t string might contain null characters, which would cause the string to be truncated when used with most C functions. If size is NULL and the wchar\_t \* string contains null characters a ValueError is raised.

Returns a buffer allocated by PyMem\_Alloc() (use PyMem\_Free() to free it) on success. On error, returns NULL and \*size is undefined. Raises a MemoryError if memory allocation is failed.

Nouveau dans la version 3.2.

Modifié dans la version 3.7 : Raises a ValueError if *size* is NULL and the wchar\_t\* string contains null characters.

#### **Built-in Codecs**

Python provides a set of built-in codecs which are written in C for speed. All of these codecs are directly usable via the following functions.

Many of the following APIs take two arguments encoding and errors, and they have the same semantics as the ones of the built-in str () string object constructor.

Setting encoding to NULL causes the default encoding to be used which is UTF-8. The file system calls should use <code>PyUnicode\_FSConverter()</code> for encoding file names. This uses the variable <code>Py\_FileSystemDefaultEncoding</code> internally. This variable should be treated as read-only: on some systems, it will be a pointer to a static string, on others, it will change at run-time (such as when the application invokes setlocale).

Error handling is set by errors which may also be set to NULL meaning to use the default handling defined for the codec. Default error handling for all built-in codecs is "strict" (ValueError is raised).

The codecs all use a similar interface. Only deviations from the following generic ones are documented for simplicity.

#### **Generic Codecs**

These are the generic codec APIs:

PyObject \*PyUnicode Decode (const char \*s, Py\_ssize\_t size, const char \*encoding, const char \*errors)

Return value: New reference. Part of the Stable ABI. Create a Unicode object by decoding size bytes of the encoded string s. encoding and errors have the same meaning as the parameters of the same name in the str() built-in function. The codec to be used is looked up using the Python codec registry. Return NULL if an exception was raised by the codec.

PyObject \*PyUnicode\_AsEncodedString (PyObject \*unicode, const char \*encoding, const char \*errors)

Return value: New reference. Part of the Stable ABI. Encode a Unicode object and return the result as Python bytes object. encoding and errors have the same meaning as the parameters of the same name in the Unicode encode () method. The codec to be used is looked up using the Python codec registry. Return NULL if an exception was raised by the codec.

#### **UTF-8 Codecs**

These are the UTF-8 codec APIs:

PyObject \*PyUnicode DecodeUTF8 (const char \*s, Py\_ssize\_t size, const char \*errors)

*Return value : New reference. Part of the* Stable ABI. Create a Unicode object by decoding *size* bytes of the UTF-8 encoded string *s*. Return NULL if an exception was raised by the codec.

PyObject \*PyUnicode\_DecodeUTF8Stateful (const char \*s, Py\_ssize\_t size, const char \*errors, Py\_ssize\_t \*consumed)

Return value: New reference. Part of the Stable ABI. If consumed is NULL, behave like PyUnicode\_DecodeUTF8(). If consumed is not NULL, trailing incomplete UTF-8 byte sequences will

not be treated as an error. Those bytes will not be decoded and the number of bytes that have been decoded will be stored in *consumed*.

```
PyObject *PyUnicode_AsUTF8String (PyObject *unicode)
```

Return value: New reference. Part of the Stable ABI. Encode a Unicode object using UTF-8 and return the result as Python bytes object. Error handling is "strict". Return NULL if an exception was raised by the codec.

```
const char *PyUnicode_AsUTF8AndSize (PyObject *unicode, Py_ssize_t *size)
```

Part of the Stable ABI since version 3.10. Return a pointer to the UTF-8 encoding of the Unicode object, and store the size of the encoded representation (in bytes) in size. The size argument can be NULL; in this case no size will be stored. The returned buffer always has an extra null byte appended (not included in size), regardless of whether there are any other null code points.

In the case of an error, NULL is returned with an exception set and no *size* is stored.

This caches the UTF-8 representation of the string in the Unicode object, and subsequent calls will return a pointer to the same buffer. The caller is not responsible for deallocating the buffer. The buffer is deallocated and pointers to it become invalid when the Unicode object is garbage collected.

Nouveau dans la version 3.3.

Modifié dans la version 3.7 : The return type is now const char \* rather of char \*.

Modifié dans la version 3.10: This function is a part of the *limited API*.

```
const char *PyUnicode_AsUTF8 (PyObject *unicode)
```

As PyUnicode\_AsUTF8AndSize(), but does not store the size.

Nouveau dans la version 3.3.

Modifié dans la version 3.7: The return type is now const char \* rather of char \*.

#### **UTF-32 Codecs**

These are the UTF-32 codec APIs:

```
PyObject *PyUnicode_DecodeUTF32 (const char *s, Py_ssize_t size, const char *errors, int *byteorder)
```

*Return value : New reference. Part of the* Stable ABI. Decode *size* bytes from a UTF-32 encoded buffer string and return the corresponding Unicode object. *errors* (if non-NULL) defines the error handling. It defaults to "strict".

If byteorder is non-NULL, the decoder starts decoding using the given byte order:

```
*byteorder == -1: little endian

*byteorder == 0: native order

*byteorder == 1: big endian
```

If \*byteorder is zero, and the first four bytes of the input data are a byte order mark (BOM), the decoder switches to this byte order and the BOM is not copied into the resulting Unicode string. If \*byteorder is -1 or 1, any byte order mark is copied to the output.

After completion, \*byteorder is set to the current byte order at the end of input data.

If *byteorder* is NULL, the codec starts in native order mode.

Return NULL if an exception was raised by the codec.

```
PyObject *PyUnicode_DecodeUTF32Stateful (const char *s, Py_ssize_t size, const char *errors, int *byteorder, Py_ssize_t *consumed)
```

Return value: New reference. Part of the Stable ABI. If consumed is NULL, behave like PyUnicode\_DecodeUTF32(). If consumed is not NULL, PyUnicode\_DecodeUTF32Stateful() will not treat trailing incomplete UTF-32 byte sequences (such as a number of bytes not divisible by four) as an error. Those bytes will not be decoded and the number of bytes that have been decoded will be stored in consumed.

#### PyObject \*PyUnicode\_AsUTF32String (PyObject \*unicode)

*Return value : New reference. Part of the* Stable ABI. Return a Python byte string using the UTF-32 encoding in native byte order. The string always starts with a BOM mark. Error handling is "strict". Return NULL if an exception was raised by the codec.

#### **UTF-16 Codecs**

These are the UTF-16 codec APIs:

```
PyObject *PyUnicode_DecodeUTF16 (const char *s, Py_ssize_t size, const char *errors, int *byteorder)
```

Return value: New reference. Part of the Stable ABI. Decode size bytes from a UTF-16 encoded buffer string and return the corresponding Unicode object. errors (if non-NULL) defines the error handling. It defaults to "strict".

If byteorder is non-NULL, the decoder starts decoding using the given byte order:

```
*byteorder == -1: little endian

*byteorder == 0: native order

*byteorder == 1: big endian
```

If \*byteorder is zero, and the first two bytes of the input data are a byte order mark (BOM), the decoder switches to this byte order and the BOM is not copied into the resulting Unicode string. If \*byteorder is -1 or 1, any byte order mark is copied to the output (where it will result in either a \ufeff or a \ufeff character).

After completion, \*byteorder is set to the current byte order at the end of input data.

If *byteorder* is NULL, the codec starts in native order mode.

Return NULL if an exception was raised by the codec.

```
PyObject *PyUnicode_DecodeUTF16Stateful (const char *s, Py_ssize_t size, const char *errors, int *byteorder, Py_ssize_t *consumed)
```

Return value: New reference. Part of the Stable ABI. If consumed is NULL, behave like PyUnicode\_DecodeUTF16(). If consumed is not NULL, PyUnicode\_DecodeUTF16Stateful() will not treat trailing incomplete UTF-16 byte sequences (such as an odd number of bytes or a split surrogate pair) as an error. Those bytes will not be decoded and the number of bytes that have been decoded will be stored in consumed.

### PyObject \*PyUnicode\_AsUTF16String (PyObject \*unicode)

*Return value : New reference. Part of the* Stable ABI. Return a Python byte string using the UTF-16 encoding in native byte order. The string always starts with a BOM mark. Error handling is "strict". Return NULL if an exception was raised by the codec.

#### **UTF-7 Codecs**

These are the UTF-7 codec APIs:

```
PyObject *PyUnicode_DecodeUTF7 (const char *s, Py_ssize_t size, const char *errors)
```

*Return value : New reference. Part of the* Stable ABI. Create a Unicode object by decoding *size* bytes of the UTF-7 encoded string *s*. Return NULL if an exception was raised by the codec.

```
PyObject *PyUnicode_DecodeUTF7Stateful (const char *s, Py_ssize_t size, const char *errors, Py_ssize_t *consumed)
```

Return value: New reference. Part of the Stable ABI. If consumed is NULL, behave like PyUnicode\_DecodeUTF7(). If consumed is not NULL, trailing incomplete UTF-7 base-64 sections will not be treated as an error. Those bytes will not be decoded and the number of bytes that have been decoded will be stored in consumed.

### **Unicode-Escape Codecs**

These are the "Unicode Escape" codec APIs:

PyObject \*PyUnicode\_DecodeUnicodeEscape (const char \*s, Py\_ssize\_t size, const char \*errors)

*Return value : New reference. Part of the* Stable ABI. Create a Unicode object by decoding *size* bytes of the Unicode-Escape encoded string *s*. Return NULL if an exception was raised by the codec.

PyObject \*PyUnicode\_AsUnicodeEscapeString (PyObject \*unicode)

Return value: New reference. Part of the Stable ABI. Encode a Unicode object using Unicode-Escape and return the result as a bytes object. Error handling is "strict". Return NULL if an exception was raised by the codec.

#### Raw-Unicode-Escape Codecs

These are the "Raw Unicode Escape" codec APIs:

PyObject \*PyUnicode\_DecodeRawUnicodeEscape (const char \*s, Py\_ssize\_t size, const char \*errors)

*Return value : New reference. Part of the* Stable ABI. Create a Unicode object by decoding *size* bytes of the Raw-Unicode-Escape encoded string *s.* Return NULL if an exception was raised by the codec.

PyObject \*PyUnicode\_AsRawUnicodeEscapeString (PyObject \*unicode)

Return value: New reference. Part of the Stable ABI. Encode a Unicode object using Raw-Unicode-Escape and return the result as a bytes object. Error handling is "strict". Return NULL if an exception was raised by the codec.

#### **Latin-1 Codecs**

These are the Latin-1 codec APIs: Latin-1 corresponds to the first 256 Unicode ordinals and only these are accepted by the codecs during encoding.

PyObject \*PyUnicode\_DecodeLatin1 (const char \*s, Py\_ssize\_t size, const char \*errors)

*Return value : New reference. Part of the* Stable ABI. Create a Unicode object by decoding *size* bytes of the Latin-1 encoded string *s*. Return NULL if an exception was raised by the codec.

PyObject \*PyUnicode\_AsLatin1String (PyObject \*unicode)

Return value: New reference. Part of the Stable ABI. Encode a Unicode object using Latin-1 and return the result as Python bytes object. Error handling is "strict". Return NULL if an exception was raised by the codec.

### **ASCII Codecs**

These are the ASCII codec APIs. Only 7-bit ASCII data is accepted. All other codes generate errors.

PyObject \*PyUnicode\_DecodeASCII (const char \*s, Py\_ssize\_t size, const char \*errors)

*Return value : New reference. Part of the* Stable ABI. Create a Unicode object by decoding *size* bytes of the ASCII encoded string *s*. Return NULL if an exception was raised by the codec.

PyObject \*PyUnicode\_AsASCIIString (PyObject \*unicode)

Return value: New reference. Part of the Stable ABI. Encode a Unicode object using ASCII and return the result as Python bytes object. Error handling is "strict". Return NULL if an exception was raised by the codec.

### **Character Map Codecs**

This codec is special in that it can be used to implement many different codecs (and this is in fact what was done to obtain most of the standard codecs included in the <code>encodings</code> package). The codec uses mappings to encode and decode characters. The mapping objects provided must support the <code>\_\_getitem\_\_()</code> mapping interface; dictionaries and sequences work well.

These are the mapping codec APIs:

```
PyObject *PyUnicode_DecodeCharmap (const char *data, Py_ssize_t size, PyObject *mapping, const char *errors)
```

*Return value : New reference. Part of the* Stable ABI. Create a Unicode object by decoding *size* bytes of the encoded string *s* using the given *mapping* object. Return NULL if an exception was raised by the codec.

If mapping is NULL, Latin-1 decoding will be applied. Else mapping must map bytes ordinals (integers in the range from 0 to 255) to Unicode strings, integers (which are then interpreted as Unicode ordinals) or None. Unmapped data bytes -- ones which cause a LookupError, as well as ones which get mapped to None, 0xFFFE or '\ufffe', are treated as undefined mappings and cause an error.

```
PyObject *PyUnicode_AsCharmapString (PyObject *unicode, PyObject *mapping)
```

Return value: New reference. Part of the Stable ABI. Encode a Unicode object using the given mapping object and return the result as a bytes object. Error handling is "strict". Return NULL if an exception was raised by the codec. The mapping object must map Unicode ordinal integers to bytes objects, integers in the range from 0 to 255 or None. Unmapped character ordinals (ones which cause a LookupError) as well as mapped to None are treated as "undefined mapping" and cause an error.

The following codec API is special in that maps Unicode to Unicode.

```
PyObject *PyUnicode_Translate (PyObject *str, PyObject *table, const char *errors)
```

Return value: New reference. Part of the Stable ABI. Translate a string by applying a character mapping table to it and return the resulting Unicode object. Return NULL if an exception was raised by the codec.

The mapping table must map Unicode ordinal integers to Unicode ordinal integers or None (causing deletion of the character).

Mapping tables need only provide the \_\_getitem\_\_() interface; dictionaries and sequences work well. Unmapped character ordinals (ones which cause a LookupError) are left untouched and are copied as-is. *errors* has the usual meaning for codecs. It may be NULL which indicates to use the default error handling.

#### **MBCS** codecs for Windows

These are the MBCS codec APIs. They are currently only available on Windows and use the Win32 MBCS converters to implement the conversions. Note that MBCS (or DBCS) is a class of encodings, not just one. The target encoding is defined by the user settings on the machine running the codec.

```
PyObject *PyUnicode_DecodeMBCS (const char *s, Py_ssize_t size, const char *errors)
```

Return value: New reference. Part of the Stable ABI on Windows since version 3.7. Create a Unicode object by decoding size bytes of the MBCS encoded string s. Return NULL if an exception was raised by the codec.

```
PyObject *PyUnicode_DecodeMBCSStateful (const char *s, Py_ssize_t size, const char *errors, Py_ssize_t *consumed)
```

Return value: New reference. Part of the Stable ABI on Windows since version 3.7. If consumed is NULL, behave like PyUnicode\_DecodeMBCS(). If consumed is not NULL, PyUnicode\_DecodeMBCSStateful() will not decode trailing lead byte and the number of bytes that have been decoded will be stored in consumed.

#### PyObject \*PyUnicode\_AsMBCSString (PyObject \*unicode)

Return value: New reference. Part of the Stable ABI on Windows since version 3.7. Encode a Unicode object using MBCS and return the result as Python bytes object. Error handling is "strict". Return NULL if an exception was raised by the codec.

PyObject \*PyUnicode\_EncodeCodePage (int code\_page, PyObject \*unicode, const char \*errors)

Return value: New reference. Part of the Stable ABI on Windows since version 3.7. Encode the Unicode object using the specified code page and return a Python bytes object. Return NULL if an exception was raised by the codec. Use CP\_ACP code page to get the MBCS encoder.

Nouveau dans la version 3.3.

#### **Methods & Slots**

#### **Methods and Slot Functions**

The following APIs are capable of handling Unicode objects and strings on input (we refer to them as strings in the descriptions) and return Unicode objects or integers as appropriate.

They all return NULL or −1 if an exception occurs.

PyObject \*PyUnicode\_Concat (PyObject \*left, PyObject \*right)

Return value: New reference. Part of the Stable ABI. Concat two strings giving a new Unicode string.

PyObject \*PyUnicode\_Split (PyObject \*s, PyObject \*sep, Py\_ssize\_t maxsplit)

Return value: New reference. Part of the Stable ABI. Split a string giving a list of Unicode strings. If sep is NULL, splitting will be done at all whitespace substrings. Otherwise, splits occur at the given separator. At most maxsplit splits will be done. If negative, no limit is set. Separators are not included in the resulting list.

PyObject \*PyUnicode\_Splitlines (PyObject \*s, int keepend)

Return value: New reference. Part of the Stable ABI. Split a Unicode string at line breaks, returning a list of Unicode strings. CRLF is considered to be one line break. If keepend is 0, the line break characters are not included in the resulting strings.

PyObject \*PyUnicode\_Join (PyObject \*separator, PyObject \*seq)

*Return value : New reference. Part of the* Stable ABI. Join a sequence of strings using the given *separator* and return the resulting Unicode string.

- Py\_ssize\_t PyUnicode\_Tailmatch (PyObject \*str, PyObject \*substr, Py\_ssize\_t start, Py\_ssize\_t end, int direction)

  Part of the Stable ABI. Return 1 if substr matches str[start:end] at the given tail end (direction == -1 means to do a prefix match, direction == 1 a suffix match), 0 otherwise. Return -1 if an error occurred.
- Py\_ssize\_t PyUnicode\_Find (PyObject \*str, PyObject \*substr, Py\_ssize\_t start, Py\_ssize\_t end, int direction)

Part of the Stable ABI. Return the first position of substr in str[start:end] using the given direction (direction == 1 means to do a forward search, direction == -1 a backward search). The return value is the index of the first match; a value of -1 indicates that no match was found, and -2 indicates that an error occurred and an exception has been set.

Py\_ssize\_t PyUnicode\_FindChar (PyObject \*str, Py\_UCS4 ch, Py\_ssize\_t start, Py\_ssize\_t end, int direction)

Part of the Stable ABI since version 3.7. Return the first position of the character ch in str[start:end] using the given direction (direction == 1 means to do a forward search, direction == -1 a backward search). The return value is the index of the first match; a value of -1 indicates that no match was found, and -2 indicates that an error occurred and an exception has been set.

Nouveau dans la version 3.3.

Modifié dans la version 3.7: start and end are now adjusted to behave like str[start:end].

#### Py\_ssize\_t PyUnicode\_Count (PyObject \*str, PyObject \*substr, Py\_ssize\_t start, Py\_ssize\_t end)

*Part of the* Stable ABI. Return the number of non-overlapping occurrences of *substr* in str[start:end]. Return -1 if an error occurred.

#### PyObject \*PyUnicode\_Replace (PyObject \*str, PyObject \*substr, PyObject \*replstr, Py\_ssize\_t maxcount)

Return value: New reference. Part of the Stable ABI. Replace at most maxcount occurrences of substr in str with replstr and return the resulting Unicode object. maxcount == -1 means replace all occurrences.

#### int PyUnicode Compare (PyObject \*left, PyObject \*right)

Part of the Stable ABI. Compare two strings and return -1, 0, 1 for less than, equal, and greater than, respectively. This function returns -1 upon failure, so one should call PyErr\_Occurred () to check for errors.

#### int PyUnicode\_CompareWithASCIIString (PyObject \*uni, const char \*string)

Part of the Stable ABI. Compare a Unicode object, uni, with string and return -1, 0, 1 for less than, equal, and greater than, respectively. It is best to pass only ASCII-encoded strings, but the function interprets the input string as ISO-8859-1 if it contains non-ASCII characters.

This function does not raise exceptions.

### PyObject \*PyUnicode\_RichCompare (PyObject \*left, PyObject \*right, int op)

Return value: New reference. Part of the Stable ABI. Rich compare two Unicode strings and return one of the following:

- NULL in case an exception was raised
- Py\_True or Py\_False for successful comparisons
- Py\_NotImplemented in case the type combination is unknown

Possible values for op are Py\_GT, Py\_GE, Py\_EQ, Py\_NE, Py\_LT, and Py\_LE.

### PyObject \*PyUnicode\_Format (PyObject \*format, PyObject \*args)

Return value: New reference. Part of the Stable ABI. Return a new string object from format and args; this is analogous to format % args.

### int PyUnicode\_Contains (PyObject \*container, PyObject \*element)

Part of the Stable ABI. Check whether *element* is contained in *container* and return true or false accordingly. *element* has to coerce to a one element Unicode string. –1 is returned if there was an error.

#### void PyUnicode\_InternInPlace (PyObject \*\*string)

Part of the Stable ABI. Intern the argument \*string in place. The argument must be the address of a pointer variable pointing to a Python Unicode string object. If there is an existing interned string that is the same as \*string, it sets \*string to it (decrementing the reference count of the old string object and incrementing the reference count of the interned string object), otherwise it leaves \*string alone and interns it (incrementing its reference count). (Clarification: even though there is a lot of talk about reference counts, think of this function as reference-count-neutral; you own the object after the call if and only if you owned it before the call.)

### PyObject \*PyUnicode\_InternFromString (const char \*v)

Return value: New reference. Part of the Stable ABI. A combination of PyUnicode\_FromString() and PyUnicode\_InternInPlace(), returning either a new Unicode string object that has been interned, or a new ("owned") reference to an earlier interned string object with the same value.

# 8.3.4 Tuple Objects

## type PyTupleObject

This subtype of PyObject represents a Python tuple object.

# PyTypeObject PyTuple\_Type

Part of the Stable ABI. This instance of PyTypeObject represents the Python tuple type; it is the same object as tuple in the Python layer.

#### int PyTuple Check (PyObject \*p)

Return true if p is a tuple object or an instance of a subtype of the tuple type. This function always succeeds.

# int PyTuple\_CheckExact (PyObject \*p)

Return true if p is a tuple object, but not an instance of a subtype of the tuple type. This function always succeeds.

```
PyObject *PyTuple_New (Py_ssize_t len)
```

Return value: New reference. Part of the Stable ABI. Return a new tuple object of size len, or NULL on failure.

```
PyObject *PyTuple_Pack (Py_ssize_t n, ...)
```

Return value: New reference. Part of the Stable ABI. Return a new tuple object of size n, or NULL on failure. The tuple values are initialized to the subsequent n C arguments pointing to Python objects. PyTuple\_Pack (2, a, b) is equivalent to Py\_BuildValue("(00)", a, b).

```
Py_ssize_t PyTuple_Size (PyObject *p)
```

Part of the Stable ABI. Take a pointer to a tuple object, and return the size of that tuple.

```
Py_ssize_t PyTuple_GET_SIZE (PyObject *p)
```

Return the size of the tuple p, which must be non-NULL and point to a tuple; no error checking is performed.

```
PyObject *PyTuple_GetItem (PyObject *p, Py_ssize_t pos)
```

*Return value : Borrowed reference. Part of the* Stable ABI. Return the object at position *pos* in the tuple pointed to by *p.* If *pos* is negative or out of bounds, return NULL and set an IndexError exception.

```
PyObject *PyTuple_GET_ITEM (PyObject *p, Py_ssize_t pos)
```

Return value: Borrowed reference. Like PyTuple\_GetItem(), but does no checking of its arguments.

```
PyObject *PyTuple_GetSlice (PyObject *p, Py_ssize_t low, Py_ssize_t high)
```

Return value: New reference. Part of the Stable ABI. Return the slice of the tuple pointed to by p between low and high, or NULL on failure. This is the equivalent of the Python expression p[low:high]. Indexing from the end of the list is not supported.

```
int PyTuple_SetItem (PyObject *p, Py_ssize_t pos, PyObject *o)
```

*Part of the* Stable ABI. Insert a reference to object *o* at position *pos* of the tuple pointed to by *p*. Return 0 on success. If *pos* is out of bounds, return -1 and set an IndexError exception.

**Note:** This function "steals" a reference to *o* and discards a reference to an item already in the tuple at the affected position.

```
void PyTuple_SET_ITEM (PyObject *p, Py_ssize_t pos, PyObject *o)
```

Like PyTuple\_SetItem(), but does no error checking, and should only be used to fill in brand new tuples.

**Note:** This function "steals" a reference to o, and, unlike PyTuple\_SetItem(), does not discard a reference to any item that is being replaced; any reference in the tuple at position pos will be leaked.

#### int \_PyTuple\_Resize (PyObject \*\*p, Py\_ssize\_t newsize)

Can be used to resize a tuple. *newsize* will be the new length of the tuple. Because tuples are *supposed* to be immutable, this should only be used if there is only one reference to the object. Do *not* use this if the tuple may already be known to some other part of the code. The tuple will always grow or shrink at the end. Think of this as destroying the old tuple and creating a new one, only more efficiently. Returns 0 on success. Client code should never assume that the resulting value of \*p will be the same as before calling this function. If the object referenced by \*p is replaced, the original \*p is destroyed. On failure, returns -1 and sets \*p to NULL, and raises MemoryError or SystemError.

# 8.3.5 Struct Sequence Objects

Struct sequence objects are the C equivalent of namedtuple() objects, i.e. a sequence whose items can also be accessed through attributes. To create a struct sequence, you first have to create a specific struct sequence type.

## PyTypeObject \*PyStructSequence\_NewType (PyStructSequence\_Desc \*desc)

Return value: New reference. Part of the Stable ABI. Create a new struct sequence type from the data in desc, described below. Instances of the resulting type can be created with PyStructSequence\_New().

# void PyStructSequence\_InitType (PyTypeObject \*type, PyStructSequence\_Desc \*desc)

Initializes a struct sequence type type from desc in place.

#### int PyStructSequence\_InitType2 (PyTypeObject \*type, PyStructSequence\_Desc \*desc)

The same as PyStructSequence\_InitType, but returns 0 on success and -1 on failure. Nouveau dans la version 3.4.

#### type PyStructSequence Desc

Part of the Stable ABI (including all members). Contains the meta information of a struct sequence type to create.

Champ	Type C	Signification
name	const char *	name of the struct sequence type
doc	const char *	pointer to docstring for the type or NULL to omit
fields	PyStructSequence_Fiel	d pointer to NULL-terminated array with field names of the
	*	new type
n_in_sequenceint		number of fields visible to the Python side (if used as
		tuple)

#### type PyStructSequence\_Field

Part of the Stable ABI (including all members). Describes a field of a struct sequence. As a struct sequence is modeled as a tuple, all fields are typed as PyObject\*. The index in the fields array of the PyStructSequence\_Desc determines which field of the struct sequence is described.

Cham	р Туре С	Signification		
name	const	name for the field or NULL to end the list of named fields, set to		
	char *	PyStructSequence_UnnamedField to leave unnamed		
doc	const	field docstring or NULL to omit		
	char *			

#### const char \*const PyStructSequence\_UnnamedField

Part of the Stable ABI since version 3.11. Special value for a field name to leave it unnamed.

Modifié dans la version 3.9: The type was changed from char \*.

### PyObject \*PyStructSequence\_New (PyTypeObject \*type)

Return value: New reference. Part of the Stable ABI. Creates an instance of type, which must have been created with  $PyStructSequence\_NewType()$ .

#### PyObject \*PyStructSequence\_GetItem (PyObject \*p, Py\_ssize\_t pos)

*Return value : Borrowed reference. Part of the* Stable ABI. Return the object at position *pos* in the struct sequence pointed to by *p*. No bounds checking is performed.

#### PyObject \*PyStructSequence\_GET\_ITEM (PyObject \*p, Py\_ssize\_t pos)

Return value: Borrowed reference. Macro equivalent of PyStructSequence\_GetItem().

#### void PyStructSequence\_SetItem (PyObject \*p, Py\_ssize\_t pos, PyObject \*o)

Part of the Stable ABI. Sets the field at index pos of the struct sequence p to value o. Like  $PyTuple\ SET\ ITEM()$ , this should only be used to fill in brand new instances.

**Note:** This function "steals" a reference to o.

# void PyStructSequence\_SET\_ITEM (PyObject \*p, Py\_ssize\_t \*pos, PyObject \*o)

Similar to PyStructSequence SetItem(), but implemented as a static inlined function.

**Note:** This function "steals" a reference to o.

# 8.3.6 List Objects

#### type PyListObject

This subtype of PyObject represents a Python list object.

#### PyTypeObject PyList\_Type

Part of the Stable ABI. This instance of PyTypeObject represents the Python list type. This is the same object as list in the Python layer.

#### int PyList\_Check (*PyObject* \*p)

Return true if p is a list object or an instance of a subtype of the list type. This function always succeeds.

# int PyList\_CheckExact (PyObject \*p)

Return true if p is a list object, but not an instance of a subtype of the list type. This function always succeeds.

#### PyObject \*PyList\_New (Py\_ssize\_t len)

Return value: New reference. Part of the Stable ABI. Return a new list of length len on success, or NULL on failure.

**Note:** If *len* is greater than zero, the returned list object's items are set to NULL. Thus you cannot use abstract API functions such as  $PySequence\_SetItem()$  or expose the object to Python code before setting all items to a real object with  $PyList\_SetItem()$ .

## Py\_ssize\_t PyList\_Size (PyObject \*list)

Part of the Stable ABI. Return the length of the list object in list; this is equivalent to len (list) on a list object.

# Py\_ssize\_t PyList\_GET\_SIZE (PyObject \*list)

Similar to PyList\_Size (), but without error checking.

#### PyObject \*PyList GetItem (PyObject \*list, Py ssize t index)

Return value: Borrowed reference. Part of the Stable ABI. Return the object at position index in the list pointed to by list. The position must be non-negative; indexing from the end of the list is not supported. If index is out of bounds (<0 or >=len(list)), return NULL and set an IndexError exception.

#### PyObject \*PyList\_GET\_ITEM (PyObject \*list, Py\_ssize\_t i)

Return value: Borrowed reference. Similar to PyList\_GetItem(), but without error checking.

#### int PyList\_SetItem (PyObject \*list, Py\_ssize\_t index, PyObject \*item)

Part of the Stable ABI. Set the item at index index in list to item. Return 0 on success. If index is out of bounds, return -1 and set an IndexError exception.

**Note:** This function "steals" a reference to *item* and discards a reference to an item already in the list at the affected position.

#### void PyList\_SET\_ITEM (PyObject \*list, Py\_ssize\_t i, PyObject \*o)

Macro form of  $PyList\_SetItem()$  without error checking. This is normally only used to fill in new lists where there is no previous content.

**Note:** This macro "steals" a reference to *item*, and, unlike *PyList\_SetItem()*, does *not* discard a reference to any item that is being replaced; any reference in *list* at position *i* will be leaked.

#### int **PyList Insert** (*PyObject* \*list, *Py ssize t* index, *PyObject* \*item)

Part of the Stable ABI. Insert the item into list list in front of index index. Return 0 if successful; return -1 and set an exception if unsuccessful. Analogous to list.insert (index, item).

#### int PyList\_Append (PyObject \*list, PyObject \*item)

Part of the Stable ABI. Append the object item at the end of list list. Return 0 if successful; return -1 and set an exception if unsuccessful. Analogous to list.append(item).

#### PyObject \*PyList\_GetSlice (PyObject \*list, Py\_ssize\_t low, Py\_ssize\_t high)

Return value: New reference. Part of the Stable ABI. Return a list of the objects in list containing the objects between low and high. Return NULL and set an exception if unsuccessful. Analogous to list[low:high]. Indexing from the end of the list is not supported.

## int PyList\_SetSlice (PyObject \*list, Py\_ssize\_t low, Py\_ssize\_t high, PyObject \*itemlist)

Part of the Stable ABI. Set the slice of *list* between *low* and *high* to the contents of *itemlist*. Analogous to list [low:high] = itemlist. The *itemlist* may be NULL, indicating the assignment of an empty list (slice deletion). Return 0 on success, -1 on failure. Indexing from the end of the list is not supported.

#### int PyList\_Sort (PyObject \*list)

Part of the Stable ABI. Sort the items of *list* in place. Return 0 on success, -1 on failure. This is equivalent to list.sort().

#### int PyList\_Reverse (PyObject \*list)

Part of the Stable ABI. Reverse the items of *list* in place. Return 0 on success, -1 on failure. This is the equivalent of list.reverse().

#### PyObject \*PyList\_AsTuple (PyObject \*list)

Return value: New reference. Part of the Stable ABI. Return a new tuple object containing the contents of list; equivalent to tuple (list).

# 8.4 Objets conteneurs

# 8.4.1 Objets dictionnaires

#### type PyDictObject

This subtype of PyObject represents a Python dictionary object.

#### PyTypeObject PyDict\_Type

*Part of the* Stable ABI. This instance of *PyTypeObject* represents the Python dictionary type. This is the same object as dict in the Python layer.

#### int PyDict\_Check (PyObject \*p)

Return true if *p* is a dict object or an instance of a subtype of the dict type. This function always succeeds.

#### int PyDict\_CheckExact (PyObject \*p)

Return true if p is a dict object, but not an instance of a subtype of the dict type. This function always succeeds.

```
PyObject *PyDict_New()
```

Return value: New reference. Part of the Stable ABI. Return a new empty dictionary, or NULL on failure.

```
PyObject *PyDictProxy_New (PyObject *mapping)
```

Return value: New reference. Part of the Stable ABI. Return a types. MappingProxyType object for a mapping which enforces read-only behavior. This is normally used to create a view to prevent modification of the dictionary for non-dynamic class types.

```
void PyDict_Clear (PyObject *p)
```

Part of the Stable ABI. Empty an existing dictionary of all key-value pairs.

```
int PyDict_Contains (PyObject *p, PyObject *key)
```

Part of the Stable ABI. Determine if dictionary p contains key. If an item in p is matches key, return 1, otherwise return 0. On error, return -1. This is equivalent to the Python expression key in p.

```
PyObject *PyDict_Copy (PyObject *p)
```

Return value: New reference. Part of the Stable ABI. Return a new dictionary that contains the same key-value pairs as p.

```
int PyDict_SetItem (PyObject *p, PyObject *key, PyObject *val)
```

Part of the Stable ABI. Insert val into the dictionary p with a key of key. key must be hashable; if it isn't, TypeError will be raised. Return 0 on success or -1 on failure. This function  $does \ not$  steal a reference to val.

```
int PyDict_SetItemString (PyObject *p, const char *key, PyObject *val)
```

Part of the Stable ABI. Insert val into the dictionary p using key as a key. key should be a const char\*. The key object is created using PyUnicode\_FromString (key). Return 0 on success or -1 on failure. This function does not steal a reference to val.

```
int PyDict_DelItem (PyObject *p, PyObject *key)
```

Part of the Stable ABI. Remove the entry in dictionary p with key key. key must be hashable; if it isn't, TypeError is raised. If key is not in the dictionary, KeyError is raised. Return 0 on success or -1 on failure.

```
int PyDict_DelItemString (PyObject *p, const char *key)
```

Part of the Stable ABI. Remove the entry in dictionary p which has a key specified by the string key. If key is not in the dictionary, KeyError is raised. Return 0 on success or -1 on failure.

#### PyObject \*PyDict\_GetItem (PyObject \*p, PyObject \*key)

*Return value : Borrowed reference. Part of the* Stable ABI. Return the object from dictionary *p* which has a key *key*. Return NULL if the key *key* is not present, but *without* setting an exception.

Note that exceptions which occur while calling  $\_$ hash $\_$ () and  $\_$ eq $\_$ () methods will get suppressed. To get error reporting use  $PyDict\_GetItemWithError$ () instead.

Modifié dans la version 3.10 : Calling this API without *GIL* held had been allowed for historical reason. It is no longer allowed.

## PyObject \*PyDict\_GetItemWithError (PyObject \*p, PyObject \*key)

Return value: Borrowed reference. Part of the Stable ABI. Variant of PyDict\_GetItem() that does not suppress exceptions. Return NULL with an exception set if an exception occurred. Return NULL without an exception set if the key wasn't present.

## PyObject \*PyDict\_GetItemString (PyObject \*p, const char \*key)

Return value: Borrowed reference. Part of the Stable ABI. This is the same as PyDict\_GetItem(), but key is specified as a const\_char\*, rather than a PyObject\*.

Note that exceptions which occur while calling \_\_hash\_\_() and \_\_eq\_\_() methods and creating a temporary string object will get suppressed. To get error reporting use PyDict\_GetItemWithError() instead.

```
PyObject *PyDict_SetDefault (PyObject *p, PyObject *key, PyObject *defaultobj)
```

Return value: Borrowed reference. This is the same as the Python-level dict.setdefault(). If present, it returns the value corresponding to key from the dictionary p. If the key is not in the dict, it is inserted with value defaultobj and defaultobj is returned. This function evaluates the hash function of key only once, instead of evaluating it independently for the lookup and the insertion.

Nouveau dans la version 3.4.

```
PyObject *PyDict_Items (PyObject *p)
```

*Return value : New reference. Part of the* Stable ABI. Return a *PyListObject* containing all the items from the dictionary.

```
PyObject *PyDict_Keys (PyObject *p)
```

*Return value : New reference. Part of the* Stable ABI. Return a *PyListObject* containing all the keys from the dictionary.

```
PyObject *PyDict_Values (PyObject *p)
```

*Return value : New reference. Part of the* Stable ABI. Return a PyListObject containing all the values from the dictionary p.

```
Py ssize t PyDict Size (PyObject *p)
```

Part of the Stable ABI. Return the number of items in the dictionary. This is equivalent to len (p) on a dictionary.

```
int PyDict Next (PyObject *p, Py ssize t *ppos, PyObject **pkey, PyObject **pvalue)
```

Part of the Stable ABI. Iterate over all key-value pairs in the dictionary p. The  $Py\_ssize\_t$  referred to by ppos must be initialized to 0 prior to the first call to this function to start the iteration; the function returns true for each pair in the dictionary, and false once all pairs have been reported. The parameters pkey and pvalue should either point to PyObject\* variables that will be filled in with each key and value, respectively, or may be NULL. Any references returned through them are borrowed. ppos should not be altered during iteration. Its value represents offsets within the internal dictionary structure, and since the structure is sparse, the offsets are not consecutive.

Par exemple:

```
PyObject *key, *value;
Py_ssize_t pos = 0;

while (PyDict_Next(self->dict, &pos, &key, &value)) {
    /* do something interesting with the values... */
```

(suite sur la page suivante)

(suite de la page précédente)

```
}
```

The dictionary *p* should not be mutated during iteration. It is safe to modify the values of the keys as you iterate over the dictionary, but only so long as the set of keys does not change. For example :

```
PyObject *key, *value;
Py_ssize_t pos = 0;

while (PyDict_Next(self->dict, &pos, &key, &value)) {
    long i = PyLong_AsLong(value);
    if (i == -1 && PyErr_Occurred()) {
        return -1;
    }
    PyObject *o = PyLong_FromLong(i + 1);
    if (o == NULL)
        return -1;
    if (PyDict_SetItem(self->dict, key, o) < 0) {
        Py_DECREF(o);
        return -1;
    }
    Py_DECREF(o);
}</pre>
```

# int PyDict\_Merge (PyObject \*a, PyObject \*b, int override)

Part of the Stable ABI. Iterate over mapping object b adding key-value pairs to dictionary a. b may be a dictionary, or any object supporting  $PyMapping\_Keys$  () and  $PyObject\_GetItem$  (). If override is true, existing pairs in a will be replaced if a matching key is found in b, otherwise pairs will only be added if there is not a matching key in a. Return 0 on success or -1 if an exception was raised.

# int PyDict\_Update (PyObject \*a, PyObject \*b)

Part of the Stable ABI. This is the same as PyDict\_Merge (a, b, 1) in C, and is similar to a .update (b) in Python except that PyDict\_Update() doesn't fall back to the iterating over a sequence of key value pairs if the second argument has no "keys" attribute. Return 0 on success or -1 if an exception was raised.

### int PyDict\_MergeFromSeq2 (PyObject \*a, PyObject \*seq2, int override)

Part of the Stable ABI. Update or merge into dictionary a, from the key-value pairs in seq2. seq2 must be an iterable object producing iterable objects of length 2, viewed as key-value pairs. In case of duplicate keys, the last wins if *override* is true, else the first wins. Return 0 on success or -1 if an exception was raised. Equivalent Python (except for the return value):

```
def PyDict_MergeFromSeq2(a, seq2, override):
    for key, value in seq2:
        if override or key not in a:
            a[key] = value
```

# 8.4.2 Set Objects

This section details the public API for set and frozenset objects. Any functionality not listed below is best accessed using either the abstract object protocol (including PyObject\_CallMethod(), PyObject\_RichCompareBool(), PyObject\_Hash(), PyObject\_Repr(), PyObject\_IsTrue(), PyObject\_Print(), and PyObject\_GetIter()) or the abstract number protocol (including PyNumber\_And(), PyNumber\_Subtract(), PyNumber\_Or(), PyNumber\_Xor(), PyNumber\_InPlaceAnd(), PyNumber\_InPlaceSubtract(), PyNumber\_InPlaceOr(), and PyNumber\_InPlaceXor()).

# type PySetObject

This subtype of *PyObject* is used to hold the internal data for both set and frozenset objects. It is like a *PyDictObject* in that it is a fixed size for small sets (much like tuple storage) and will point to a separate, variable sized block of memory for medium and large sized sets (much like list storage). None of the fields of this structure should be considered public and all are subject to change. All access should be done through the documented API rather than by manipulating the values in the structure.

#### PyTypeObject PySet\_Type

Part of the Stable ABI. This is an instance of PyTypeObject representing the Python set type.

#### PyTypeObject PyFrozenSet\_Type

Part of the Stable ABI. This is an instance of PyTypeObject representing the Python frozenset type.

The following type check macros work on pointers to any Python object. Likewise, the constructor functions work with any iterable Python object.

```
int PySet_Check (PyObject *p)
```

Return true if *p* is a set object or an instance of a subtype. This function always succeeds.

#### int PyFrozenSet\_Check (PyObject \*p)

Return true if p is a frozenset object or an instance of a subtype. This function always succeeds.

### int PyAnySet\_Check (PyObject \*p)

Return true if p is a set object, a frozenset object, or an instance of a subtype. This function always succeeds.

#### int PySet\_CheckExact (PyObject \*p)

Return true if p is a set object but not an instance of a subtype. This function always succeeds.

Nouveau dans la version 3.10.

# int PyAnySet\_CheckExact (PyObject \*p)

Return true if p is a set object or a frozenset object but not an instance of a subtype. This function always succeeds.

### int PyFrozenSet\_CheckExact (PyObject \*p)

Return true if *p* is a frozenset object but not an instance of a subtype. This function always succeeds.

```
PyObject *PySet_New (PyObject *iterable)
```

Return value: New reference. Part of the Stable ABI. Return a new set containing objects returned by the iterable. The iterable may be NULL to create a new empty set. Return the new set on success or NULL on failure. Raise TypeError if iterable is not actually iterable. The constructor is also useful for copying a set (c=set (s)).

## PyObject \*PyFrozenSet\_New (PyObject \*iterable)

Return value: New reference. Part of the Stable ABI. Return a new frozenset containing objects returned by the iterable. The iterable may be NULL to create a new empty frozenset. Return the new set on success or NULL on failure. Raise TypeError if iterable is not actually iterable.

The following functions and macros are available for instances of set or frozenset or instances of their subtypes.

#### Py\_ssize\_t PySet\_Size (PyObject \*anyset)

Part of the Stable ABI. Return the length of a set or frozenset object. Equivalent to len(anyset). Raises a PyExc\_SystemError if anyset is not a set, frozenset, or an instance of a subtype.

#### Py\_ssize\_t PySet\_GET\_SIZE (PyObject \*anyset)

Macro form of PySet\_Size () without error checking.

```
int PySet_Contains (PyObject *anyset, PyObject *key)
```

Part of the Stable ABI. Return 1 if found, 0 if not found, and -1 if an error is encountered. Unlike the Python \_\_contains\_\_ () method, this function does not automatically convert unhashable sets into temporary frozensets. Raise a TypeError if the key is unhashable. Raise PyExc\_SystemError if anyset is not a set, frozenset, or an instance of a subtype.

```
int PySet_Add (PyObject *set, PyObject *key)
```

Part of the Stable ABI. Add key to a set instance. Also works with frozenset instances (like PyTuple\_SetItem() it can be used to fill in the values of brand new frozensets before they are exposed to other code). Return 0 on success or -1 on failure. Raise a TypeError if the key is unhashable. Raise a MemoryError if there is no room to grow. Raise a SystemError if set is not an instance of set or its subtype.

The following functions are available for instances of set or its subtypes but not for instances of frozenset or its subtypes.

```
int PySet_Discard (PyObject *set, PyObject *key)
```

Part of the Stable ABI. Return 1 if found and removed, 0 if not found (no action taken), and -1 if an error is encountered. Does not raise KeyError for missing keys. Raise a TypeError if the key is unhashable. Unlike the Python discard() method, this function does not automatically convert unhashable sets into temporary frozensets. Raise PyExc\_SystemError if set is not an instance of set or its subtype.

```
PyObject *PySet_Pop (PyObject *set)
```

Return value: New reference. Part of the Stable ABI. Return a new reference to an arbitrary object in the set, and removes the object from the set. Return NULL on failure. Raise KeyError if the set is empty. Raise a SystemError if set is not an instance of set or its subtype.

```
int PySet_Clear (PyObject *set)
```

Part of the Stable ABI. Empty an existing set of all elements.

# 8.5 Objets fonctions

# 8.5.1 Objets fonction

Certaines fonctions sont spécifiques aux fonctions Python.

#### type PyFunctionObject

La structure C utilisée pour les fonctions.

#### PyTypeObject PyFunction\_Type

C'est une instance de PyTypeObject et représente le type fonction en Python. Il est exposé aux développeurs comme types. FunctionType.

#### int PyFunction Check (PyObject \*o)

Renvoie vrai si o est un objet de type fonction (a comme type  $PyFunction\_Type$ ). Le paramètre ne doit pas être NULL. Cette fonction réussit toujours.

#### PyObject \*PyFunction\_New (PyObject \*code, PyObject \*globals)

Return value : New reference. Renvoie une nouvelle fonction associée avec l'objet code. globals doit être un dictionnaire avec les variables globales accessibles à la fonction.

La docstring et le nom de la fonction sont récupérés à partir de l'objet code. \_\_module\_\_ est récupéré à partir de globals. Les arguments par défaut, les annotations et la fermeture sont mis à NULL. \_\_qualname\_\_ est mis à la même valeur que celle du champ co\_qualname de l'objet code.

#### PyObject \*PyFunction NewWithQualName (PyObject \*code, PyObject \*globals, PyObject \*qualname)

Return value: New reference. Comme <code>PyFunction\_New()</code>, mais accepte aussi une valeur à utiliser pour l'attribut \_\_qualname\_\_ de l'objet fonction. qualname doit être un objet Unicode ou <code>NULL</code>; s'il est <code>NULL</code>, l'attribut \_\_qualname\_\_ de l'objet fonction prend la valeur de l'attribut <code>co\_qualname</code> de l'objet code.

Nouveau dans la version 3.3.

## PyObject \*PyFunction\_GetCode (PyObject \*op)

Return value : Borrowed reference. Renvoie l'objet code associé avec l'objet de la fonction op.

#### PyObject \*PyFunction\_GetGlobals (PyObject \*op)

Return value : Borrowed reference. Renvoie le dictionnaire global associé avec l'objet de la fonction op.

#### PyObject \*PyFunction\_GetModule (PyObject \*op)

Return value : Borrowed reference. Renvoie un borrowed reference à l'attribut \_\_module\_\_ de l'objet fonction op. Il peut être NULL.

C'est typiquement une chaîne de caractère contenant le nom du module, mais il peut être changé par du code Python pour n'importe quel autre objet.

#### PyObject \*PyFunction\_GetDefaults (PyObject \*op)

Return value : Borrowed reference. Renvoie les valeurs par défaut de l'argument de l'objet de la fonction op. Cela peut être un tuple d'arguments ou NULL.

# int PyFunction\_SetDefaults (PyObject \*op, PyObject \*defaults)

Définir les valeurs par défaut de l'argument pour l'objet de la fonction *op. defaults* doit être Py\_None ou un tuple. Lève SystemError et renvoie -1 en cas de d'échec.

# PyObject \*PyFunction\_GetClosure (PyObject \*op)

*Return value : Borrowed reference.* Renvoie la fermeture associée avec l'objet de la fonction *op.* Cela peut être NULL ou un tuple d'objets cellule.

#### int PyFunction\_SetClosure (PyObject \*op, PyObject \*closure)

Définir la fermeture associée avec l'objet de la fonction *op. closure* doit être Py\_None ou un tuple d'objets cellule. Lève SystemError et renvoie -1 en cas de d'échec.

#### PyObject \*PyFunction GetAnnotations (PyObject \*op)

*Return value : Borrowed reference.* Renvoie les annotations de l'objet de la fonction *op.* Cela peut être un dictionnaire mutable ou NULL.

# int PyFunction\_SetAnnotations (PyObject \*op, PyObject \*annotations)

Définir les annotations pour l'objet de la fonction op. annotations doit être un dictionnaire ou Py\_None.

Lève SystemError et renvoie -1 en cas de d'échec.

# 8.5.2 Instance Method Objects

An instance method is a wrapper for a PyCFunction and the new way to bind a PyCFunction to a class object. It replaces the former call PyMethod\_New(func, NULL, class).

## PyTypeObject PyInstanceMethod\_Type

This instance of PyTypeObject represents the Python instance method type. It is not exposed to Python programs.

# int PyInstanceMethod\_Check (PyObject \*o)

Return true if o is an instance method object (has type  $PyInstanceMethod\_Type$ ). The parameter must not be NULL. This function always succeeds.

#### PyObject \*PyInstanceMethod\_New (PyObject \*func)

Return value: New reference. Return a new instance method object, with func being any callable object. func is the function that will be called when the instance method is called.

#### PyObject \*PyInstanceMethod\_Function (PyObject \*im)

Return value: Borrowed reference. Return the function object associated with the instance method im.

#### PyObject \*PyInstanceMethod GET FUNCTION (PyObject \*im)

*Return value : Borrowed reference.* Macro version of *PyInstanceMethod\_Function()* which avoids error checking.

# 8.5.3 Objets méthode

Methods are bound function objects. Methods are always bound to an instance of a user-defined class. Unbound methods (methods bound to a class object) are no longer available.

## PyTypeObject PyMethod\_Type

This instance of PyTypeObject represents the Python method type. This is exposed to Python programs as types. MethodType.

#### int PyMethod\_Check (PyObject \*o)

Return true if o is a method object (has type  $PyMethod\_Type$ ). The parameter must not be NULL. This function always succeeds.

```
PyObject *PyMethod_New (PyObject *func, PyObject *self)
```

*Return value : New reference.* Return a new method object, with *func* being any callable object and *self* the instance the method should be bound. *func* is the function that will be called when the method is called. *self* must not be NULL.

#### PyObject \*PyMethod Function (PyObject \*meth)

Return value: Borrowed reference. Return the function object associated with the method meth.

# PyObject \*PyMethod\_GET\_FUNCTION (PyObject \*meth)

Return value: Borrowed reference. Macro version of PyMethod\_Function() which avoids error checking.

#### PyObject \*PyMethod\_Self (PyObject \*meth)

Return value: Borrowed reference. Return the instance associated with the method meth.

#### PyObject \*PyMethod\_GET\_SELF (PyObject \*meth)

Return value: Borrowed reference. Macro version of PyMethod\_Self() which avoids error checking.

# 8.5.4 Objets Cellules

Les objets "Cellules" (*cell* en anglais) sont utilisés pour implémenter des variables référencées dans de multiples environnements. Pour chacune de ces variables, un objet cellule est créé pour stocker sa valeur; les variables locales de chaque pile d'exécution qui référence cette valeur contiennent une référence sur les cellules des autres environnements qui utilisent aussi cette variable. Quand la valeur est accédée, la valeur de la cellule est utilisée, au lei de celle de l'objet cellule proprement dit. Ce dé-référencement de l'objet cellule requiert l'intervention du *bytecode* généré; il n'est pas automatiquement dé-référencé quand il est accédé. Il est plausible que les objets cellules ne soit utilisés ailleurs.

## type PyCellObject

Structure C utilisée pour les objets cellules.

#### PyTypeObject PyCell\_Type

Type objet correspondant aux objets cellules.

#### int PyCell\_Check (ob)

Return true if *ob* is a cell object; *ob* must not be NULL. This function always succeeds.

```
PyObject *PyCell_New (PyObject *ob)
```

Return value: New reference. Create and return a new cell object containing the value ob. The parameter may be NULL.

```
PyObject *PyCell_Get (PyObject *cell)
```

Return value : New reference. Renvoie le contenu de la cellule cell.

```
PyObject *PyCell_GET (PyObject *cell)
```

*Return value : Borrowed reference.* Return the contents of the cell *cell*, but without checking that *cell* is non-NULL and a cell object.

```
int PyCell_Set (PyObject *cell, PyObject *value)
```

Set the contents of the cell object *cell* to *value*. This releases the reference to any current content of the cell. *value* may be NULL. *cell* must be non-NULL; if it is not a cell object, -1 will be returned. On success, 0 will be returned.

```
void PyCell_SET (PyObject *cell, PyObject *value)
```

Sets the value of the cell object *cell* to *value*. No reference counts are adjusted, and no checks are made for safety; *cell* must be non-NULL and must be a cell object.

# 8.5.5 Objets code

Les objets *Code* sont spécifiques à l'implémentation bas niveau de CPython. Chacun d'eux représente une partie de code exécutable, qui n'a pas encore été lié dans une fonction.

#### type PyCodeObject

La structure C utilisée pour décrire les objets *Code*. Les attributs de cette structure sont sujets à changer à tout moment.

### PyTypeObject PyCode\_Type

C'est une instance de PyTypeObject représentant le type Python code.

```
int PyCode_Check (PyObject *co)
```

Return true if co is a code object. This function always succeeds.

```
int PyCode_GetNumFree (PyCodeObject *co)
```

Renvoie le nombre de variables libres dans co.

PyCodeObject \*PyCode\_New (int argcount, int kwonlyargcount, int nlocals, int stacksize, int flags, PyObject \*code,
PyObject \*consts, PyObject \*names, PyObject \*varnames, PyObject \*freevars, PyObject
\*cellvars, PyObject \*filename, PyObject \*name, int firstlineno, PyObject \*linetable,
PyObject \*exceptiontable)

Return value: New reference. Return a new code object. If you need a dummy code object to create a frame, use  $PyCode_NewEmpty()$  instead. Calling  $PyCode_New()$  directly will bind you to a precise Python version since the definition of the bytecode changes often. The many arguments of this function are inter-dependent in complex ways, meaning that subtle changes to values are likely to result in incorrect execution or VM crashes. Use this function only with extreme care.

Modifié dans la version 3.11 : Added exceptiontable parameter.

PyCodeObject \*PyCode\_NewWithPosOnlyArgs (int argcount, int posonlyargcount, int kwonlyargcount, int nlocals, int stacksize, int flags, PyObject \*code, PyObject \*consts, PyObject \*names, PyObject \*varnames, PyObject \*freevars, PyObject \*felename, PyObject \*name, int firstlineno, PyObject \*linetable, PyObject \*exceptiontable)

Return value: New reference. Similar to  $PyCode_New()$ , but with an extra "posonlyargcount" for positional-only arguments. The same caveats that apply to  $PyCode_New$  also apply to this function.

Nouveau dans la version 3.8.

Modifié dans la version 3.11 : Added exceptiontable parameter.

#### PyCodeObject \*PyCode\_NewEmpty (const char \*filename, const char \*funcname, int firstlineno)

*Return value : New reference.* Return a new empty code object with the specified filename, function name, and first line number. The resulting code object will raise an Exception if executed.

#### int **PyCode\_Addr2Line** (*PyCodeObject* \*co, int byte\_offset)

Return the line number of the instruction that occurs on or before byte\_offset and ends after it. If you just need the line number of a frame, use PyFrame\_GetLineNumber() instead.

For efficiently iterating over the line numbers in a code object, use the API described in PEP 626.

int PyCode\_Addr2Location (*PyObject* \*co, int byte\_offset, int \*start\_line, int \*start\_column, int \*end\_line, int \*end\_column)

Sets the passed int pointers to the source code line and column numbers for the instruction at byte\_offset. Sets the value to 0 when information is not available for any particular element.

Returns 1 if the function succeeds and 0 otherwise.

Nouveau dans la version 3.11.

#### PyObject \*PyCode\_GetCode (PyCodeObject \*co)

Equivalent to the Python code  $getattr(co, 'co\_code')$ . Returns a strong reference to a PyBytesObject representing the bytecode in a code object. On error, NULL is returned and an exception is raised.

This PyBytesObject may be created on-demand by the interpreter and does not necessarily represent the bytecode actually executed by CPython. The primary use case for this function is debuggers and profilers.

Nouveau dans la version 3.11.

#### PyObject \*PyCode\_GetVarnames (PyCodeObject \*co)

Equivalent to the Python code  $getattr(co, 'co_varnames')$ . Returns a new reference to a PyTupleObject containing the names of the local variables. On error, NULL is returned and an exception is raised.

Nouveau dans la version 3.11.

#### PyObject \*PyCode\_GetCellvars (PyCodeObject \*co)

Equivalent to the Python code getattr(co, 'co\_cellvars'). Returns a new reference to a

PyTupleObject containing the names of the local variables that are referenced by nested functions. On error, NULL is returned and an exception is raised.

Nouveau dans la version 3.11.

# PyObject \*PyCode\_GetFreevars (PyCodeObject \*co)

Equivalent to the Python code <code>getattr(co, 'co\_freevars')</code>. Returns a new reference to a <code>PyTupleObject</code> containing the names of the free variables. On error, <code>NULL</code> is returned and an exception is raised.

Nouveau dans la version 3.11.

# 8.6 Autres objets

# 8.6.1 Objets fichiers

These APIs are a minimal emulation of the Python 2 C API for built-in file objects, which used to rely on the buffered I/O (FILE\*) support from the C standard library. In Python 3, files and streams use the new  $i \circ$  module, which defines several layers over the low-level unbuffered I/O of the operating system. The functions described below are convenience C wrappers over these new APIs, and meant mostly for internal error reporting in the interpreter; third-party code is advised to access the  $i \circ$  APIs instead.

PyObject \*PyFile\_FromFd (int fd, const char \*name, const char \*mode, int buffering, const char \*encoding, const char \*errors, const char \*newline, int closefd)

Return value: New reference. Part of the Stable ABI. Create a Python file object from the file descriptor of an already opened file fd. The arguments name, encoding, errors and newline can be NULL to use the defaults; buffering can be -1 to use the default. name is ignored and kept for backward compatibility. Return NULL on failure. For a more comprehensive description of the arguments, please refer to the io.open() function documentation.

**Avertissement :** Étant donné que les flux de données Python possèdent leur propre couche de tampon, les mélanger avec des descripteurs de fichiers du niveau du système d'exploitation peut produire des erreurs (comme par exemple un ordre des données inattendu).

Modifié dans la version 3.2 : ignore l'attribut name

#### int PyObject\_AsFileDescriptor(PyObject \*p)

Part of the Stable ABI. Return the file descriptor associated with p as an int. If the object is an integer, its value is returned. If not, the object's fileno() method is called if it exists; the method must return an integer, which is returned as the file descriptor value. Sets an exception and returns -1 on failure.

#### PyObject \*PyFile\_GetLine (PyObject \*p, int n)

Return value: New reference. Part of the Stable ABI. Cette fonction, équivalente à p.readline([n]), lit une ligne de l'objet p. p peut être un objet fichier ou n'importe quel objet qui possède une méthode readline(). Si n vaut 0, une seule ligne est lue, indépendamment de la taille de la ligne. Si n est plus grand que 0, un maximum de n octets seront lus en provenance du fichier; une ligne partielle peut être renvoyée. Dans les deux cas, une chaîne de caractères vide est renvoyée si la fin du fichier est atteinte immédiatement. Cependant, si n est plus petit que 0, une ligne est lue indépendamment de sa taille, mais EOFError est levée si la fin du fichier est atteinte immédiatement.

#### int PyFile SetOpenCodeHook (Py OpenCodeHookFunction handler)

Overrides the normal behavior of io.open\_code () to pass its parameter through the provided handler.

The handler is a function of type PyObject \*(\*) (PyObject \*path, void \*userData), where path is guaranteed to be PyUnicodeObject.

The *userData* pointer is passed into the hook function. Since hook functions may be called from different runtimes, this pointer should not refer directly to Python state.

As this hook is intentionally used during import, avoid importing new modules during its execution unless they are known to be frozen or available in sys.modules.

Once a hook has been set, it cannot be removed or replaced, and later calls to PyFile\_SetOpenCodeHook () will fail. On failure, the function returns -1 and sets an exception if the interpreter has been initialized.

This function is safe to call before Py\_Initialize().

Raises an auditing event setopencodehook with no arguments.

Nouveau dans la version 3.8.

```
int PyFile_WriteObject (PyObject *obj, PyObject *p, int flags)
```

Part of the Stable ABI. Écrit l'objet obj dans l'objet fichier p. La seule option gérée pour flags est Py\_PRINT\_RAW; si défini, l'attribut str() de l'objet est écrit à la place de l'attribut repr(). Retourne 0 en cas de succès ou -1 en cas échec; l'exception appropriée sera levée.

```
int PyFile_WriteString (const char *s, PyObject *p)
```

Part of the Stable ABI. Écrit la chaîne de caractères s dans l'objet fichier p. Retourne 0 en cas de succès ou -1 en cas d'échec; l'exception appropriée sera mise en place.

# 8.6.2 Module Objects

#### PyTypeObject PyModule\_Type

Part of the Stable ABI. This instance of PyTypeObject represents the Python module type. This is exposed to Python programs as types. ModuleType.

```
int PyModule_Check (PyObject *p)
```

Return true if p is a module object, or a subtype of a module object. This function always succeeds.

```
int PyModule_CheckExact (PyObject *p)
```

Return true if p is a module object, but not a subtype of PyModule\_Type. This function always succeeds.

```
PyObject *PyModule_NewObject (PyObject *name)
```

Return value: New reference. Part of the Stable ABI since version 3.7. Return a new module object with the \_\_name\_\_ attribute set to name. The module's \_\_name\_\_, \_\_doc\_\_, \_\_package\_\_, and \_\_loader\_\_ attributes are filled in (all but \_\_name\_\_ are set to None); the caller is responsible for providing a \_\_file\_\_ attribute.

Nouveau dans la version 3.3.

Modifié dans la version 3.4 : \_\_package\_\_ and \_\_loader\_\_ are set to None.

#### PyObject \*PyModule\_New (const char \*name)

Return value: New reference. Part of the Stable ABI. Similar to PyModule\_NewObject(), but the name is a UTF-8 encoded string instead of a Unicode object.

```
PyObject *PyModule_GetDict (PyObject *module)
```

Return value: Borrowed reference. Part of the Stable ABI. Return the dictionary object that implements module's namespace; this object is the same as the \_\_dict\_\_ attribute of the module object. If module is not a module object (or a subtype of a module object), SystemError is raised and NULL is returned.

It is recommended extensions use other PyModule\_\* and PyObject\_\* functions rather than directly manipulate a module's \_\_dict\_.

#### PyObject \*PyModule\_GetNameObject (PyObject \*module)

Return value: New reference. Part of the Stable ABI since version 3.7. Return module's \_\_name\_\_ value. If the module does not provide one, or if it is not a string, SystemError is raised and NULL is returned. Nouveau dans la version 3.3.

```
const char *PyModule_GetName (PyObject *module)
```

Part of the Stable ABI. Similar to PyModule\_GetNameObject () but return the name encoded to 'utf-8'.

#### void \*PyModule\_GetState (PyObject \*module)

Part of the Stable ABI. Return the "state" of the module, that is, a pointer to the block of memory allocated at module creation time, or NULL. See <code>PyModuleDef.m\_size</code>.

#### PyModuleDef \*PyModule\_GetDef (PyObject \*module)

*Part of the* Stable ABI. Return a pointer to the *PyModuleDef* struct from which the module was created, or NULL if the module wasn't created from a definition.

#### PyObject \*PyModule\_GetFilenameObject (PyObject \*module)

Return value: New reference. Part of the Stable ABI. Return the name of the file from which module was loaded using module's \_\_\_file\_\_ attribute. If this is not defined, or if it is not a unicode string, raise SystemError and return NULL; otherwise return a reference to a Unicode object.

Nouveau dans la version 3.2.

#### const char \*PyModule\_GetFilename (PyObject \*module)

Part of the Stable ABI. Similar to PyModule\_GetFilenameObject() but return the filename encoded to 'utf-8'.

Obsolète depuis la version 3.2 : PyModule\_GetFilename() raises UnicodeEncodeError on unencodable filenames, use PyModule\_GetFilenameObject() instead.

# **Initializing C modules**

Modules objects are usually created from extension modules (shared libraries which export an initialization function), or compiled-in modules (where the initialization function is added using <code>PyImport\_AppendInittab()</code>). See building or extending-with-embedding for details.

The initialization function can either pass a module definition instance to <code>PyModule\_Create()</code>, and return the resulting module object, or request "multi-phase initialization" by returning the definition struct itself.

## type PyModuleDef

Part of the Stable ABI (including all members). The module definition struct, which holds all information needed to create a module object. There is usually only one statically initialized variable of this type for each module.

## PyModuleDef\_Base m\_base

Always initialize this member to PyModuleDef HEAD INIT.

```
const char *m_name
```

Name for the new module.

```
const char *m doc
```

Docstring for the module; usually a docstring variable created with PyDoc\_STRVAR is used.

### Py\_ssize\_t m\_size

Module state may be kept in a per-module memory area that can be retrieved with  $PyModule\_GetState()$ , rather than in static globals. This makes modules safe for use in multiple sub-interpreters.

This memory area is allocated based on  $m\_size$  on module creation, and freed when the module object is deallocated, after the  $m\_free$  function has been called, if present.

Setting  $m_size$  to -1 means that the module does not support sub-interpreters, because it has global state. Setting it to a non-negative value means that the module can be re-initialized and specifies the additional amount of memory it requires for its state. Non-negative  $m_size$  is required for multi-phase initialization. See **PEP 3121** for more details.

## PyMethodDef \*m\_methods

A pointer to a table of module-level functions, described by *PyMethodDef* values. Can be NULL if no functions are present.

#### PyModuleDef\_Slot \*m\_slots

An array of slot definitions for multi-phase initialization, terminated by a  $\{0, \text{NULL}\}\$  entry. When using single-phase initialization,  $m\_slots$  must be NULL.

Modifié dans la version 3.5 : Prior to version 3.5, this member was always set to NULL, and was defined as :

inquiry m\_reload

#### traverseproc m\_traverse

A traversal function to call during GC traversal of the module object, or NULL if not needed.

This function is not called if the module state was requested but is not allocated yet. This is the case immediately after the module is created and before the module is executed ( $Py\_mod\_exec$  function). More precisely, this function is not called if  $m\_size$  is greater than 0 and the module state (as returned by  $PyModule\_GetState()$ ) is NULL.

Modifié dans la version 3.9 : No longer called before the module state is allocated.

#### inquiry m\_clear

A clear function to call during GC clearing of the module object, or NULL if not needed.

This function is not called if the module state was requested but is not allocated yet. This is the case immediately after the module is created and before the module is executed ( $Py\_mod\_exec$  function). More precisely, this function is not called if  $m\_size$  is greater than 0 and the module state (as returned by  $PyModule\_GetState()$ ) is NULL.

Like  $PyTypeObject.tp\_clear$ , this function is not *always* called before a module is deallocated. For example, when reference counting is enough to determine that an object is no longer used, the cyclic garbage collector is not involved and  $m\_free$  is called directly.

Modifié dans la version 3.9 : No longer called before the module state is allocated.

#### freefunc m free

A function to call during deallocation of the module object, or NULL if not needed.

This function is not called if the module state was requested but is not allocated yet. This is the case immediately after the module is created and before the module is executed ( $Py\_mod\_exec$  function). More precisely, this function is not called if  $m\_size$  is greater than 0 and the module state (as returned by  $PyModule\ GetState()$ ) is NULL.

Modifié dans la version 3.9: No longer called before the module state is allocated.

#### Single-phase initialization

The module initialization function may create and return the module object directly. This is referred to as "single-phase initialization", and uses one of the following two module creation functions:

```
PyObject *PyModule_Create (PyModuleDef *def)
```

*Return value : New reference.* Create a new module object, given the definition in *def*. This behaves like <code>PyModule\_Create2()</code> with <code>module\_api\_version</code> set to <code>PYTHON\_API\_VERSION</code>.

```
PyObject *PyModule_Create2 (PyModuleDef *def, int module_api_version)
```

Return value: New reference. Part of the Stable ABI. Create a new module object, given the definition in def, assuming the API version module\_api\_version. If that version does not match the version of the running interpreter, a RuntimeWarning is emitted.

**Note:** Most uses of this function should be using <code>PyModule\_Create()</code> instead; only use this if you are sure you need it.

Before it is returned from in the initialization function, the resulting module object is typically populated using functions like <code>PyModule\_AddObjectRef()</code>.

# Multi-phase initialization

An alternate way to specify extensions is to request "multi-phase initialization". Extension modules created this way behave more like Python modules: the initialization is split between the *creation phase*, when the module object is created, and the *execution phase*, when it is populated. The distinction is similar to the \_\_new\_\_() and \_\_init\_\_() methods of classes.

Unlike modules created using single-phase initialization, these modules are not singletons: if the *sys.modules* entry is removed and the module is re-imported, a new module object is created, and the old module is subject to normal garbage collection -- as with Python modules. By default, multiple modules created from the same definition should be independent: changes to one should not affect the others. This means that all state should be specific to the module object (using e.g. using *PyModule\_GetState()*), or its contents (such as the module's \_\_dict\_\_ or individual classes created with *PyType\_FromSpec()*).

All modules created using multi-phase initialization are expected to support *sub-interpreters*. Making sure multiple modules are independent is typically enough to achieve this.

To request multi-phase initialization, the initialization function (PyInit\_modulename) returns a PyModuleDef instance with non-empty  $m\_slots$ . Before it is returned, the PyModuleDef instance must be initialized with the following function:

## PyObject \*PyModuleDef\_Init (PyModuleDef \*def)

*Return value : Borrowed reference. Part of the* Stable ABI *since version 3.5.* Ensures a module definition is a properly initialized Python object that correctly reports its type and reference count.

Returns def cast to PyObject\*, or NULL if an error occurred.

Nouveau dans la version 3.5.

The *m\_slots* member of the module definition must point to an array of PyModuleDef\_Slot structures:

## type PyModuleDef\_Slot

int slot

A slot ID, chosen from the available values explained below.

void \*value

Value of the slot, whose meaning depends on the slot ID.

Nouveau dans la version 3.5.

The m slots array must be terminated by a slot with id 0.

The available slot types are:

#### Py\_mod\_create

Specifies a function that is called to create the module object itself. The *value* pointer of this slot must point to a function of the signature :

```
PyObject *create_module (PyObject *spec, PyModuleDef *def)
```

The function receives a ModuleSpec instance, as defined in PEP 451, and the module definition. It should return a new module object, or set an error and return NULL.

This function should be kept minimal. In particular, it should not call arbitrary Python code, as trying to import the same module again may result in an infinite loop.

Multiple Py\_mod\_create slots may not be specified in one module definition.

If  $Py_{mod_create}$  is not specified, the import machinery will create a normal module object using  $Py_{module_New()}$ . The name is taken from spec, not the definition, to allow extension modules to dynamically adjust to their place in the module hierarchy and be imported under different names through symlinks, all while sharing a single module definition.

There is no requirement for the returned object to be an instance of <code>PyModule\_Type</code>. Any type can be used, as long as it supports setting and getting import-related attributes. However, only <code>PyModule\_Type</code> instances may be returned if the <code>PyModuleDef</code> has non-NULL <code>m\_traverse</code>, <code>m\_clear</code>, <code>m\_free</code>; non-zero <code>m\_size</code>; or slots other than <code>Py\_mod\_create</code>.

## Py\_mod\_exec

Specifies a function that is called to *execute* the module. This is equivalent to executing the code of a Python module: typically, this function adds classes and constants to the module. The signature of the function is:

int exec\_module (PyObject \*module)

If multiple Py\_mod\_exec slots are specified, they are processed in the order they appear in the *m\_slots* array.

See PEP 489 for more details on multi-phase initialization.

#### Low-level module creation functions

The following functions are called under the hood when using multi-phase initialization. They can be used directly, for example when creating module objects dynamically. Note that both PyModule\_FromDefAndSpec and PyModule\_ExecDef must be called to fully initialize a module.

# PyObject \*PyModule\_FromDefAndSpec (PyModuleDef \*def, PyObject \*spec)

Return value: New reference. Create a new module object, given the definition in def and the ModuleSpec spec. This behaves like PyModule\_FromDefAndSpec2() with module\_api\_version set to PYTHON\_API\_VERSION. Nouveau dans la version 3.5.

### PyObject \*PyModule\_FromDefAndSpec2 (PyModuleDef \*def, PyObject \*spec, int module\_api\_version)

Return value: New reference. Part of the Stable ABI since version 3.7. Create a new module object, given the definition in def and the ModuleSpec spec, assuming the API version module\_api\_version. If that version does not match the version of the running interpreter, a RuntimeWarning is emitted.

**Note:** Most uses of this function should be using <code>PyModule\_FromDefAndSpec()</code> instead; only use this if you are sure you need it.

Nouveau dans la version 3.5.

# int PyModule\_ExecDef (PyObject \*module, PyModuleDef \*def)

Part of the Stable ABI since version 3.7. Process any execution slots (Py\_mod\_exec) given in def. Nouveau dans la version 3.5.

#### int PyModule\_SetDocString (PyObject \*module, const char \*docstring)

Part of the Stable ABI since version 3.7. Set the docstring for module to docstring. This function is called automatically when creating a module from PyModuleDef, using either PyModule\_Create or PyModule\_FromDefAndSpec.

Nouveau dans la version 3.5.

# int PyModule\_AddFunctions (PyObject \*module, PyMethodDef \*functions)

Part of the Stable ABI since version 3.7. Add the functions from the NULL terminated functions array to module. Refer to the <code>PyMethodDef</code> documentation for details on individual entries (due to the lack of a shared module namespace, module level "functions" implemented in C typically receive the module as their first parameter, making them similar to instance methods on Python classes). This function is called automatically when creating a module from <code>PyModuleDef</code>, using either <code>PyModule\_Create</code> or <code>PyModule\_FromDefAndSpec</code>.

Nouveau dans la version 3.5.

# **Support functions**

The module initialization function (if using single phase initialization) or a function called from a module execution slot (if using multi-phase initialization), can use the following functions to help initialize the module state:

```
int PyModule_AddObjectRef (PyObject *module, const char *name, PyObject *value)
```

Part of the Stable ABI since version 3.10. Add an object to module as name. This is a convenience function which can be used from the module's initialization function.

On success, return 0. On error, raise an exception and return -1.

Return NULL if value is NULL. It must be called with an exception raised in this case.

Example usage:

```
static int
add_spam(PyObject *module, int value)
{
    PyObject *obj = PyLong_FromLong(value);
    if (obj == NULL) {
        return -1;
    }
    int res = PyModule_AddObjectRef(module, "spam", obj);
    Py_DECREF(obj);
    return res;
}
```

The example can also be written without checking explicitly if *obj* is NULL:

```
static int
add_spam(PyObject *module, int value)
{
    PyObject *obj = PyLong_FromLong(value);
    int res = PyModule_AddObjectRef(module, "spam", obj);
    Py_XDECREF(obj);
    return res;
}
```

Note that Py\_XDECREF () should be used instead of Py\_DECREF () in this case, since *obj* can be NULL. Nouveau dans la version 3.10.

```
int PyModule_AddObject (PyObject *module, const char *name, PyObject *value)
```

Part of the Stable ABI. Similar to PyModule\_AddObjectRef(), but steals a reference to value on success (if it returns 0).

The new  $PyModule\_AddObjectRef()$  function is recommended, since it is easy to introduce reference leaks by misusing the  $PyModule\_AddObject()$  function.

**Note:** Unlike other functions that steal references, PyModule\_AddObject() only decrements the reference count of *value* on success.

This means that its return value must be checked, and calling code must Py\_DECREF () value manually on error.

# Example usage:

```
static int
add_spam(PyObject *module, int value)
{
    PyObject *obj = PyLong_FromLong(value);
    if (obj == NULL) {
        return -1;
```

(suite sur la page suivante)

(suite de la page précédente)

```
if (PyModule_AddObject(module, "spam", obj) < 0) {
    Py_DECREF(obj);
    return -1;
}

// PyModule_AddObject() stole a reference to obj:
    // Py_DECREF(obj) is not needed here
    return 0;
}</pre>
```

The example can also be written without checking explicitly if *obj* is NULL:

```
static int
add_spam(PyObject *module, int value)
{
    PyObject *obj = PyLong_FromLong(value);
    if (PyModule_AddObject(module, "spam", obj) < 0) {
        Py_XDECREF(obj);
        return -1;
    }
    // PyModule_AddObject() stole a reference to obj:
    // Py_DECREF(obj) is not needed here
    return 0;
}</pre>
```

Note that Py\_XDECREF () should be used instead of Py\_DECREF () in this case, since obj can be NULL.

# int PyModule\_AddIntConstant (PyObject \*module, const char \*name, long value)

Part of the Stable ABI. Add an integer constant to module as name. This convenience function can be used from the module's initialization function. Return -1 on error, 0 on success.

```
int PyModule_AddStringConstant (PyObject *module, const char *name, const char *value)
```

*Part of the* Stable ABI. Add a string constant to *module* as *name*. This convenience function can be used from the module's initialization function. The string *value* must be NULL-terminated. Return -1 on error, 0 on success.

```
int PyModule AddIntMacro (PyObject *module, macro)
```

Add an int constant to *module*. The name and the value are taken from *macro*. For example PyModule\_AddIntMacro(module, AF\_INET) adds the int constant  $AF\_INET$  with the value of  $AF\_INET$  to *module*. Return -1 on error, 0 on success.

#### int **PyModule\_AddStringMacro** (*PyObject* \*module, macro)

Add a string constant to module.

# int PyModule\_AddType (PyObject \*module, PyTypeObject \*type)

Part of the Stable ABI since version 3.10. Add a type object to module. The type object is finalized by calling internally  $PyType\_Ready()$ . The name of the type object is taken from the last component of  $tp\_name$  after dot. Return -1 on error, 0 on success.

Nouveau dans la version 3.9.

## Module lookup

Single-phase initialization creates singleton modules that can be looked up in the context of the current interpreter. This allows the module object to be retrieved later with only a reference to the module definition.

These functions will not work on modules created using multi-phase initialization, since multiple such modules can be created from a single definition.

```
PyObject *PyState_FindModule (PyModuleDef *def)
```

Return value: Borrowed reference. Part of the Stable ABI. Returns the module object that was created from def for the current interpreter. This method requires that the module object has been attached to the interpreter state with PyState\_AddModule() beforehand. In case the corresponding module object is not found or has not been attached to the interpreter state yet, it returns NULL.

#### int PyState\_AddModule (PyObject \*module, PyModuleDef \*def)

*Part of the* Stable ABI *since version 3.3.* Attaches the module object passed to the function to the interpreter state. This allows the module object to be accessible via *PyState\_FindModule()*.

Only effective on modules created using single-phase initialization.

Python calls PyState\_AddModule automatically after importing a module, so it is unnecessary (but harmless) to call it from module initialization code. An explicit call is needed only if the module's own init code subsequently calls PyState\_FindModule. The function is mainly intended for implementing alternative import mechanisms (either by calling it directly, or by referring to its implementation for details of the required state updates).

The caller must hold the GIL.

Return 0 on success or -1 on failure.

Nouveau dans la version 3.3.

#### int PyState\_RemoveModule (PyModuleDef \*def)

Part of the Stable ABI since version 3.3. Removes the module object created from def from the interpreter state. Return 0 on success or -1 on failure.

The caller must hold the GIL.

Nouveau dans la version 3.3.

# 8.6.3 Itérateurs

Python fournit deux itérateurs d'usage générique. Le premier est un itérateur de séquence, il fonctionne avec n'importe quelle séquence implémentant la méthode \_\_getitem\_\_ () . Le second fonctionne avec un objet appelable et une valeur sentinelle, l'appelable permet d'obtenir chaque élément de la séquence, et l'itération se termine lorsque la sentinelle est atteinte.

## PyTypeObject PySeqIter\_Type

Part of the Stable ABI. Type des itérateurs renvoyés par les fonctions  $PySeqIter_New()$  et la forme à un argument de la fonction native iter() pour les séquences natives.

#### int PySeqIter\_Check (op)

Return true if the type of *op* is *PySeqIter\_Type*. This function always succeeds.

## PyObject \*PySeqIter\_New (PyObject \*seq)

Return value : New reference. Part of the Stable ABI. Renvoie un itérateur sur la séquence seq. L'itération prend fin lorsque la séquence lève IndexError lors d'une tentative d'accès.

#### PyTypeObject PyCallIter\_Type

Part of the Stable ABI. Type de l'itérateur renvoyé par les fonctions  $PyCallIter\_New()$  et iter() à deux arguments.

#### int PyCallIter\_Check (op)

Return true if the type of *op* is *PyCallIter\_Type*. This function always succeeds.

PyObject \*PyCallIter\_New (PyObject \*callable, PyObject \*sentinel)

Return value: New reference. Part of the Stable ABI. Renvoie un nouvel itérateur. Le premier paramètre, callable, peut être n'importe quel objet Python appelable sans aucun paramètre; chaque appel doit renvoyer l'élément suivant de l'itération. Lorsque callable renvoie une valeur égale à sentinel, l'itération prend fin.

# 8.6.4 Les descripteurs

Les "Descripteurs" sont des objets décrivant des attributs pour un objet. Ils se trouvent dans le dictionnaire du type de l'objet.

PyTypeObject PyProperty\_Type

Part of the Stable ABI. L'objet type des descripteurs natifs.

PyObject \*PyDescr\_NewGetSet (PyTypeObject \*type, struct PyGetSetDef \*getset)

Return value: New reference. Part of the Stable ABI.

PyObject \*PyDescr\_NewMember (PyTypeObject \*type, struct PyMemberDef \*meth)

Return value: New reference. Part of the Stable ABI.

PyObject \*PyDescr\_NewMethod (PyTypeObject \*type, struct PyMethodDef \*meth)

Return value: New reference. Part of the Stable ABI.

PyObject \*PyDescr\_NewWrapper (PyTypeObject \*type, struct wrapperbase \*wrapper, void \*wrapped)

Return value: New reference.

PyObject \*PyDescr\_NewClassMethod (PyTypeObject \*type, PyMethodDef \*method)

Return value: New reference. Part of the Stable ABI.

int PyDescr\_IsData (PyObject \*descr)

Return non-zero if the descriptor objects *descr* describes a data attribute, or 0 if it describes a method. *descr* must be a descriptor object; there is no error checking.

PyObject \*PyWrapper\_New (PyObject\*, PyObject\*)

Return value: New reference. Part of the Stable ABI.

# 8.6.5 Slice Objects

#### PyTypeObject PySlice\_Type

Part of the Stable ABI. The type object for slice objects. This is the same as slice in the Python layer.

int PySlice\_Check (PyObject \*ob)

Return true if ob is a slice object; ob must not be NULL. This function always succeeds.

PyObject \*PySlice\_New (PyObject \*start, PyObject \*stop, PyObject \*step)

Return value: New reference. Part of the Stable ABI. Return a new slice object with the given values. The start, stop, and step parameters are used as the values of the slice object attributes of the same names. Any of the values may be <code>NULL</code>, in which case the <code>None</code> will be used for the corresponding attribute. Return <code>NULL</code> if the new object could not be allocated.

```
int PySlice_GetIndices (PyObject *slice, Py_ssize_t length, Py_ssize_t *start, Py_ssize_t *stop, Py_ssize_t *step)
```

Part of the Stable ABI. Retrieve the start, stop and step indices from the slice object slice, assuming a sequence of length length. Treats indices greater than length as errors.

Returns 0 on success and -1 on error with no exception set (unless one of the indices was not None and failed to be converted to an integer, in which case -1 is returned with an exception set).

You probably do not want to use this function.

Modifié dans la version 3.2: The parameter type for the *slice* parameter was PySliceObject\* before.

```
int PySlice_GetIndicesEx (PyObject *slice, Py_ssize_t length, Py_ssize_t *start, Py_ssize_t *stop, Py_ssize_t *stop, Py_ssize_t *slicelength)
```

Part of the Stable ABI. Usable replacement for PySlice\_GetIndices(). Retrieve the start, stop, and step indices from the slice object *slice* assuming a sequence of length *length*, and store the length of the slice in *slicelength*. Out of bounds indices are clipped in a manner consistent with the handling of normal slices.

Returns 0 on success and -1 on error with exception set.

**Note:** This function is considered not safe for resizable sequences. Its invocation should be replaced by a combination of *PySlice\_Unpack()* and *PySlice\_AdjustIndices()* where

```
if (PySlice_GetIndicesEx(slice, length, &start, &stop, &step, &slicelength) < 0) {
    // return error
}</pre>
```

#### is replaced by

```
if (PySlice_Unpack(slice, &start, &stop, &step) < 0) {
    // return error
}
slicelength = PySlice_AdjustIndices(length, &start, &stop, step);</pre>
```

Modifié dans la version 3.2: The parameter type for the *slice* parameter was PySliceObject\* before.

Modifié dans la version 3.6.1: If Py\_LIMITED\_API is not set or set to the value between  $0 \times 03050400$  and  $0 \times 03060000$  (not including) or  $0 \times 03060100$  or higher PySlice\_GetIndicesEx() is implemented as a macro using PySlice\_Unpack() and PySlice\_AdjustIndices(). Arguments *start*, *stop* and *step* are evaluated more than once.

Obsolète depuis la version 3.6.1: If Py\_LIMITED\_API is set to the value less than 0x03050400 or between 0x03060000 and 0x03060100 (not including) PySlice\_GetIndicesEx() is a deprecated function.

```
int PySlice_Unpack (PyObject *slice, Py_ssize_t *start, Py_ssize_t *stop, Py_ssize_t *step)
```

Part of the Stable ABI since version 3.7. Extract the start, stop and step data members from a slice object as C integers. Silently reduce values larger than PY\_SSIZE\_T\_MAX to PY\_SSIZE\_T\_MAX, silently boost the start and stop values less than PY\_SSIZE\_T\_MIN to PY\_SSIZE\_T\_MIN, and silently boost the step values less than -PY\_SSIZE\_T\_MAX to -PY\_SSIZE\_T\_MAX.

Return -1 on error, 0 on success.

Nouveau dans la version 3.6.1.

```
Py_ssize_t PySlice_AdjustIndices (Py_ssize_t length, Py_ssize_t *start, Py_ssize_t *stop, Py_ssize_t step)
```

Part of the Stable ABI since version 3.7. Adjust start/end slice indices assuming a sequence of the specified length. Out of bounds indices are clipped in a manner consistent with the handling of normal slices.

Return the length of the slice. Always successful. Doesn't call Python code.

Nouveau dans la version 3.6.1.

# 8.6.6 Ellipsis Object

## PyObject \*Py\_Ellipsis

The Python Ellipsis object. This object has no methods. It needs to be treated just like any other object with respect to reference counts. Like Py\_None it is a singleton object.

# 8.6.7 Objets de type MemoryView

Un objet Python memoryview expose le *protocole tampon* du C. Cet objet peut ensuite être passé comme n'importe quel objet.

## PyObject \*PyMemoryView\_FromObject (PyObject \*obj)

Return value : New reference. Part of the Stable ABI. Crée un objet memoryview à partir d'un objet implémentant le protocole tampon. Si obj permet d'exporter des tampons modifiables, l'objet memoryview crée acceptera la lecture et écriture, sinon l'objet crée est soit en lecture seule ou lecture/écriture, à la discrétion de l'exporteur.

## PyObject \*PyMemoryView\_FromMemory (char \*mem, Py\_ssize\_t size, int flags)

Return value: New reference. Part of the Stable ABI since version 3.7. Crée un objet memoryview utilisant mem comme un tampon sous-jacent. flags peut être PyBUF\_READ ou PyBUF\_WRITE.

Nouveau dans la version 3.3.

## PyObject \*PyMemoryView\_FromBuffer (const Py\_buffer \*view)

Return value : New reference. Part of the Stable ABI since version 3.11. Crée un objet memoryview à partir de la structure tampon view. Pour de simples tampons d'octets, PyMemoryView\_FromMemory() est préférée.

# PyObject \*PyMemoryView\_GetContiguous (PyObject \*obj, int buffertype, char order)

Return value: New reference. Part of the Stable ABI. Crée un objet memoryview vers un segment de mémoire contiguous (organisé comme en 'C' ou comme en 'F' pour Fortran) à partir d'un objet qui expose le protocole tampon. Si la mémoire est contiguë, l'objet memoryview pointe vers la mémoire d'origine. Sinon une copie est faite et la memoryview pointe vers un nouvel objet bytes.

## int PyMemoryView\_Check (PyObject \*obj)

Return true if the object *obj* is a memoryview object. It is not currently allowed to create subclasses of memoryview. This function always succeeds.

# Py\_buffer \*PyMemoryView\_GET\_BUFFER (PyObject \*mview)

Retourne un pointeur vers la copie privée du tampon de l'exporteur de memoryview. mview doit être une instance de memoryview; cette macro ne vérifie pas le type, vous devez le faire vous-même sinon vous pourriez subir un crash.

#### PyObject \*PyMemoryView GET BASE (PyObject \*mview)

Renvoie soit un pointeur vers l'objet exporté sur lequel est basé la *memoryview* ou NULL si la *memoryview* a été crée par *PyMemoryView\_FromMemory()* ou *PyMemoryView\_FromBuffer()*. *mview* doit être une instance de *memoryview*.

# 8.6.8 Objets à références faibles

Python gère les *références faibles* comme des objets de première classe. Il existe deux types d'objets spécifiques qui implémentent directement les références faibles. Le premier est un objet de référence simple, et le second agit autant que possible comme un mandataire vers l'objet original.

#### int PyWeakref\_Check (ob)

Return true if *ob* is either a reference or proxy object. This function always succeeds.

#### int PyWeakref\_CheckRef (ob)

Return true if *ob* is a reference object. This function always succeeds.

#### int PyWeakref CheckProxy (ob)

Return true if *ob* is a proxy object. This function always succeeds.

# PyObject \*PyWeakref\_NewRef (PyObject \*ob, PyObject \*callback)

Return value: New reference. Part of the Stable ABI. Return a weak reference object for the object ob. This will always return a new reference, but is not guaranteed to create a new object; an existing reference object may be returned. The second parameter, callback, can be a callable object that receives notification when ob is garbage collected; it should accept a single parameter, which will be the weak reference object itself. callback may also be None or NULL. If ob is not a weakly referencable object, or if callback is not callable, None, or NULL, this will return NULL and raise TypeError.

# PyObject \*PyWeakref\_NewProxy (PyObject \*ob, PyObject \*callback)

Return value: New reference. Part of the Stable ABI. Return a weak reference proxy object for the object ob. This will always return a new reference, but is not guaranteed to create a new object; an existing proxy object may be returned. The second parameter, callback, can be a callable object that receives notification when ob is garbage collected; it should accept a single parameter, which will be the weak reference object itself. callback may also be None or NULL. If ob is not a weakly referencable object, or if callback is not callable, None, or NULL, this will return NULL and raise TypeError.

#### PyObject \*PyWeakref\_GetObject (PyObject \*ref)

Return value : Borrowed reference. Part of the Stable ABI. Retourne l'objet référencé à partir d'une référence faible, ref. Si le référence n'existe plus, alors l'objet renvoie Py\_None.

**Note:** This function returns a *borrowed reference* to the referenced object. This means that you should always call  $Py\_INCREF()$  on the object except when it cannot be destroyed before the last usage of the borrowed reference.

#### PyObject \*PyWeakref\_GET\_OBJECT (PyObject \*ref)

Return value: Borrowed reference. Similar to PyWeakref\_GetObject(), but does no error checking.

#### void PyObject\_ClearWeakRefs (PyObject \*object)

Part of the Stable ABI. This function is called by the tp\_dealloc handler to clear weak references.

This iterates through the weak references for *object* and calls callbacks for those references which have one. It returns when all callbacks have been attempted.

# 8.6.9 Capsules

Reportez-vous à using-capsules pour plus d'informations sur l'utilisation de ces objets.

Nouveau dans la version 3.1.

#### type PyCapsule

This subtype of <code>PyObject</code> represents an opaque value, useful for C extension modules who need to pass an opaque value (as a <code>void\*</code> pointer) through Python code to other C code. It is often used to make a C function pointer defined in one module available to other modules, so the regular import mechanism can be used to access C APIs defined in dynamically loaded modules.

## type PyCapsule\_Destructor

Part of the Stable ABI. The type of a destructor callback for a capsule. Defined as:

```
typedef void (*PyCapsule_Destructor) (PyObject *);
```

See PyCapsule\_New() for the semantics of PyCapsule\_Destructor callbacks.

## int PyCapsule\_CheckExact (PyObject \*p)

Return true if its argument is a PyCapsule. This function always succeeds.

# PyObject \*PyCapsule\_New (void \*pointer, const char \*name, PyCapsule\_Destructor destructor)

*Return value : New reference. Part of the* Stable ABI. Create a *PyCapsule* encapsulating the *pointer*. The *pointer* argument may not be NULL.

On failure, set an exception and return NULL.

The *name* string may either be NULL or a pointer to a valid C string. If non-NULL, this string must outlive the capsule. (Though it is permitted to free it inside the *destructor*.)

If the destructor argument is not NULL, it will be called with the capsule as its argument when it is destroyed.

If this capsule will be stored as an attribute of a module, the *name* should be specified as modulename. attributename. This will enable other modules to import the capsule using <code>PyCapsule\_Import()</code>.

## void \*PyCapsule\_GetPointer (*PyObject* \*capsule, const char \*name)

Part of the Stable ABI. Retrieve the pointer stored in the capsule. On failure, set an exception and return NULL.

The *name* parameter must compare exactly to the name stored in the capsule. If the name stored in the capsule is NULL, the *name* passed in must also be NULL. Python uses the C function strcmp() to compare capsule names.

# PyCapsule\_Destructor PyCapsule\_GetDestructor (PyObject \*capsule)

Part of the Stable ABI. Return the current destructor stored in the capsule. On failure, set an exception and return NULL.

It is legal for a capsule to have a NULL destructor. This makes a NULL return code somewhat ambiguous; use <code>PyCapsule\_IsValid()</code> or <code>PyErr\_Occurred()</code> to disambiguate.

#### void \*PyCapsule\_GetContext (PyObject \*capsule)

Part of the Stable ABI. Return the current context stored in the capsule. On failure, set an exception and return NULL.

It is legal for a capsule to have a NULL context. This makes a NULL return code somewhat ambiguous; use <code>PyCapsule\_IsValid()</code> or <code>PyErr\_Occurred()</code> to disambiguate.

# $const\ char\ \textbf{*PyCapsule\_GetName}\ (\textit{PyObject}\ \textbf{*} capsule)$

Part of the Stable ABI. Return the current name stored in the capsule. On failure, set an exception and return NULL. It is legal for a capsule to have a NULL name. This makes a NULL return code somewhat ambiguous; use PyCapsule\_IsValid() or PyErr\_Occurred() to disambiguate.

#### void \*PyCapsule\_Import (const char \*name, int no\_block)

Part of the Stable ABI. Import a pointer to a C object from a capsule attribute in a module. The *name* parameter should specify the full name to the attribute, as in module.attribute. The *name* stored in the capsule must match this string exactly.

Return the capsule's internal *pointer* on success. On failure, set an exception and return NULL.

Modifié dans la version 3.3 : *no\_block* has no effect anymore.

## int PyCapsule\_IsValid (*PyObject* \*capsule, const char \*name)

Part of the Stable ABI. Determines whether or not capsule is a valid capsule. A valid capsule is non-NULL, passes PyCapsule\_CheckExact(), has a non-NULL pointer stored in it, and its internal name matches the name parameter. (See PyCapsule\_GetPointer() for information on how capsule names are compared.)

In other words, if <code>PyCapsule\_IsValid()</code> returns a true value, calls to any of the accessors (any function starting with <code>PyCapsule\_Get()</code>) are guaranteed to succeed.

Return a nonzero value if the object is valid and matches the name passed in. Return 0 otherwise. This function will not fail.

## int PyCapsule\_SetContext (PyObject \*capsule, void \*context)

Part of the Stable ABI. Set the context pointer inside capsule to context.

Return 0 on success. Return nonzero and set an exception on failure.

## int PyCapsule\_SetDestructor (PyObject \*capsule, PyCapsule\_Destructor destructor)

Part of the Stable ABI. Set the destructor inside capsule to destructor.

Return 0 on success. Return nonzero and set an exception on failure.

# int PyCapsule\_SetName (PyObject \*capsule, const char \*name)

*Part of the* Stable ABI. Set the name inside *capsule* to *name*. If non-NULL, the name must outlive the capsule. If the previous *name* stored in the capsule was not NULL, no attempt is made to free it.

Return 0 on success. Return nonzero and set an exception on failure.

# int PyCapsule\_SetPointer (PyObject \*capsule, void \*pointer)

Part of the Stable ABI. Set the void pointer inside capsule to pointer. The pointer may not be NULL.

Return 0 on success. Return nonzero and set an exception on failure.

# 8.6.10 Objets décrivant les frames

## type PyFrameObject

Part of the Limited API (as an opaque struct). Structure des objets C utilisée pour décrire les objets frame.

Il n'y a pas de membres publics dans cette structure.

Modifié dans la version 3.11 : Les membres de la structure API publique ont été retirés de l'API publique de C. Visiter l'entrée dans la page des nouveautés de Python pour plus détails.

Les fonctions PyEval\_GetFrame () et PyThreadState\_GetFrame () peuvent être utilisées pour avoir un objet de frame.

Voir aussi Réflexion

# PyTypeObject PyFrame\_Type

Le type des objets de frame. C'est le même objet que types.FrameType dans la couche de Python.

Modifié dans la version 3.11 : Précédemment, ce type était disponible uniquement après l'inclusion de <frameobject.h>.

#### int PyFrame\_Check (PyObject \*obj)

Renvoie un entier non nul si obj est un objet frame.

Modifié dans la version 3.11 : Précédemment, ce type était disponible uniquement après l'inclusion de <frameobject.h>.

# PyFrameObject \*PyFrame\_GetBack (PyFrameObject \*frame)

Renvoie la frame encadrant immédiatement à frame.

Renvoie un strong reference, ou NULL si frame n'a pas de frame encadrante.

Nouveau dans la version 3.9.

#### PyObject \*PyFrame\_GetBuiltins (PyFrameObject \*frame)

Obtenir l'attribut f buitins de frame.

Renvoie un strong reference. Le résultat ne peut être NULL.

Nouveau dans la version 3.11.

## PyCodeObject \*PyFrame\_GetCode (PyFrameObject \*frame)

Part of the Stable ABI since version 3.10. Obtenir le code frame.

Renvoie un strong reference.

Le résultat (code *frame*) ne peut être NULL.

Nouveau dans la version 3.9.

## PyObject \*PyFrame\_GetGenerator (PyFrameObject \*frame)

Obtenir le générateur, coroutine, ou un générateur asynchrone qui maintient cette *frame*, ou NULL si cette *frame* n'est pas maintenu par un générateur. Il ne lève pas d'exception, même si la valeur renvoyée est NULL.

Renvoie un strong reference, ou NULL.

Nouveau dans la version 3.11.

# PyObject \*PyFrame\_GetGlobals (PyFrameObject \*frame)

Obtenir l'attribut f\_globals de frame.

Renvoie un *strong reference*. Le résultat ne peut être NULL.

Nouveau dans la version 3.11.

#### int PyFrame\_GetLasti (PyFrameObject \*frame)

Obtenir l'attribut f lasti de frame.

Renvoie -1 si frame .f\_lasti est None.

Nouveau dans la version 3.11.

# PyObject \*PyFrame\_GetLocals (PyFrameObject \*frame)

Obtenir l'attribut (dict) f\_locals de frame.

Renvoie un strong reference.

Nouveau dans la version 3.11.

#### int PyFrame GetLineNumber (PyFrameObject \*frame)

Part of the Stable ABI since version 3.10. Renvoie le numéro de ligne que cette frame est en train d'exécuter.

# 8.6.11 Objets générateur

Python utilise des objets générateurs pour implémenter les itérations de générateurs. Ils sont normalement crées en itérant sur une fonction donnant des valeurs via yield, au lieu d'appeler explicitement  $PyGen_New()$  ou  $PyGen_NewWithQualName()$ .

#### type PyGenObject

La structure C utilisée pour les objets générateurs.

## PyTypeObject PyGen\_Type

Le type objet correspondant aux objets générateurs.

```
int PyGen_Check (PyObject *ob)
```

Return true if ob is a generator object; ob must not be NULL. This function always succeeds.

```
int PyGen_CheckExact (PyObject *ob)
```

Return true if ob's type is PyGen\_Type; ob must not be NULL. This function always succeeds.

```
PyObject *PyGen_New (PyFrameObject *frame)
```

*Return value : New reference.* Create and return a new generator object based on the *frame* object. A reference to *frame* is stolen by this function. The argument must not be NULL.

```
PyObject *PyGen_NewWithQualName (PyFrameObject *frame, PyObject *name, PyObject *qualname)
```

Return value: New reference. Create and return a new generator object based on the frame object, with \_\_name\_\_ and \_\_qualname\_\_ set to name and qualname. A reference to frame is stolen by this function. The frame argument must not be NULL.

# 8.6.12 Objets coroutines

Nouveau dans la version 3.5.

Les objets coroutines sont les objets renvoyés par les fonctions déclarées avec le mot clef async.

#### type PyCoroObject

La structure C utilisée pour les objets coroutine.

#### PyTypeObject PyCoro\_Type

L'objet type correspondant aux objets coroutines.

```
int PyCoro_CheckExact (PyObject *ob)
```

Return true if *ob*'s type is *PyCoro\_Type*; *ob* must not be NULL. This function always succeeds.

```
PyObject *PyCoro_New (PyFrameObject *frame, PyObject *name, PyObject *qualname)
```

Return value: New reference. Create and return a new coroutine object based on the frame object, with \_\_name\_\_ and \_\_qualname\_\_ set to name and qualname. A reference to frame is stolen by this function. The frame argument must not be NULL.

# 8.6.13 Context Variables Objects

Modifié dans la version 3.7.1:

**Note:** In Python 3.7.1 the signatures of all context variables C APIs were **changed** to use *PyObject* pointers instead of *PyContext, PyContextVar*, and *PyContextToken*, e.g.:

```
// in 3.7.0:
PyContext *PyContext_New(void);

// in 3.7.1+:
PyObject *PyContext_New(void);
```

See bpo-34762 for more details.

Nouveau dans la version 3.7.

This section details the public C API for the contextvars module.

#### type PyContext

The C structure used to represent a contextvars.Context object.

#### type PyContextVar

The C structure used to represent a contextvars. ContextVar object.

# $type \ {\bf PyContextToken}$

The C structure used to represent a contextvars. Token object.

#### PyTypeObject PyContext\_Type

The type object representing the *context* type.

# PyTypeObject PyContextVar\_Type

The type object representing the *context variable* type.

#### PyTypeObject PyContextToken Type

The type object representing the *context variable token* type.

Macros pour vérifier les types :

```
int PyContext_CheckExact (PyObject *o)
```

Return true if o is of type PyContext\_Type. o must not be NULL. This function always succeeds.

```
int PyContextVar_CheckExact (PyObject *o)
```

Return true if o is of type PyContextVar\_Type. o must not be NULL. This function always succeeds.

```
int PyContextToken_CheckExact (PyObject *o)
```

Return true if o is of type  $PyContextToken\_Type$ . o must not be NULL. This function always succeeds.

Context object management functions:

```
PyObject *PyContext_New (void)
```

Return value: New reference. Create a new empty context object. Returns NULL if an error has occurred.

```
PyObject *PyContext_Copy (PyObject *ctx)
```

*Return value : New reference.* Create a shallow copy of the passed *ctx* context object. Returns NULL if an error has occurred.

#### PyObject \*PyContext\_CopyCurrent (void)

*Return value : New reference.* Create a shallow copy of the current thread context. Returns NULL if an error has occurred.

#### int PyContext Enter (PyObject \*ctx)

Set ctx as the current context for the current thread. Returns 0 on success, and -1 on error.

#### int PyContext Exit (PyObject \*ctx)

Deactivate the *ctx* context and restore the previous context as the current context for the current thread. Returns 0 on success, and -1 on error.

Context variable functions:

```
PyObject *PyContextVar_New (const char *name, PyObject *def)
```

Return value: New reference. Create a new ContextVar object. The name parameter is used for introspection and debug purposes. The def parameter specifies a default value for the context variable, or NULL for no default. If an error has occurred, this function returns NULL.

```
int PyContextVar_Get (PyObject *var, PyObject *default_value, PyObject **value)
```

Get the value of a context variable. Returns -1 if an error has occurred during lookup, and 0 if no error occurred, whether or not a value was found.

If the context variable was found, *value* will be a pointer to it. If the context variable was *not* found, *value* will point to:

- *default\_value*, if not NULL;
- the default value of *var*, if not NULL;
- NULL

Except for NULL, the function returns a new reference.

#### PyObject \*PyContextVar\_Set (PyObject \*var, PyObject \*value)

*Return value : New reference.* Set the value of *var* to *value* in the current context. Returns a new token object for this change, or NULL if an error has occurred.

```
int PyContextVar_Reset (PyObject *var, PyObject *token)
```

Reset the state of the var context variable to that it was in before  $PyContextVar\_Set$  () that returned the token was called. This function returns 0 on success and -1 on error.

# 8.6.14 Objets DateTime

De nombreux objets *date* et *time* sont exposés par le module <code>DateTime</code>. Avant d'utiliser une de ces fonctions, le fichier d'en-tête datetime. h doit être inclus dans vos sources (veuillez noter qu'il n'est pas inclus par le fichier <code>Python</code>. h) et la macro <code>PyDateTime\_IMPORT</code> doit être invoquée, généralement lors de la fonction d'initialisation du module. La macro crée un pointeur vers une structure C et place celui-ci dans une variable statique, <code>PyDateTimeAPI</code>, qui est utilisée par les macros suivantes.

Macro pour accéder au singleton UTC:

### PyObject \*PyDateTime\_TimeZone\_UTC

Renvoie le singleton du fuseau horaire UTC, qui est le même objet que datetime.timezone.utc.

Nouveau dans la version 3.7.

Macros pour vérifier les types :

```
int PyDate_Check (PyObject *ob)
```

Return true if ob is of type PyDateTime\_DateType or a subtype of PyDateTime\_DateType. ob must not be NULL. This function always succeeds.

#### int PyDate\_CheckExact (PyObject \*ob)

Return true if ob is of type PyDateTime\_DateType. ob must not be NULL. This function always succeeds.

#### int PyDateTime\_Check (PyObject \*ob)

Return true if ob is of type PyDateTime\_DateTimeType or a subtype of PyDateTime\_DateTimeType. ob must not be NULL. This function always succeeds.

## int PyDateTime\_CheckExact (PyObject \*ob)

Return true if ob is of type PyDateTime\_DateTimeType. ob must not be NULL. This function always succeeds.

#### int PyTime\_Check (PyObject \*ob)

Return true if ob is of type PyDateTime\_TimeType or a subtype of PyDateTime\_TimeType. ob must not be NULL. This function always succeeds.

#### int PyTime\_CheckExact (PyObject \*ob)

Return true if ob is of type PyDateTime\_TimeType. ob must not be NULL. This function always succeeds.

# int PyDelta\_Check (PyObject \*ob)

Return true if ob is of type PyDateTime\_DeltaType or a subtype of PyDateTime\_DeltaType. ob must not be NULL. This function always succeeds.

# int PyDelta\_CheckExact (PyObject \*ob)

Return true if ob is of type PyDateTime\_DeltaType. ob must not be NULL. This function always succeeds.

## int PyTZInfo\_Check (PyObject \*ob)

Return true if ob is of type PyDateTime\_TZInfoType or a subtype of PyDateTime\_TZInfoType. ob must not be NULL. This function always succeeds.

# int PyTZInfo\_CheckExact (PyObject \*ob)

Return true if ob is of type PyDateTime\_TZInfoType. ob must not be NULL. This function always succeeds.

Macros pour créer des objets :

#### PyObject \*PyDate\_FromDate (int year, int month, int day)

Return value : New reference. Renvoie un objet datetime. date avec l'année, le mois et le jour spécifiés.

# PyObject \*PyDateTime\_FromDateAndTime (int year, int month, int day, int hour, int minute, int second, int usecond)

Return value : New reference. Renvoie un objet datetime . datetime avec l'année, le mois, le jour, l'heure, la minute, la seconde et la microseconde spécifiés.

# PyObject \*PyDateTime\_FromDateAndTimeAndFold (int year, int month, int day, int hour, int minute, int second, int usecond, int fold)

Return value : New reference. Renvoie un objet datetime . datetime avec l'année, le mois, le jour, l'heure, la minute, la seconde, la microseconde et le pli (fold en anglais) spécifiés.

Nouveau dans la version 3.6.

## PyObject \*PyTime\_FromTime (int hour, int minute, int second, int usecond)

Return value : New reference. Renvoie un objet datetime.time avec l'heure, la minute, la seconde et la microseconde spécifiées.

#### PyObject \*PyTime\_FromTimeAndFold (int hour, int minute, int second, int usecond, int fold)

Return value: New reference. Renvoie un objet datetime.time avec l'heure, la minute, la seconde, la microseconde et le pli (fold en anglais) spécifiés.

Nouveau dans la version 3.6.

## PyObject \*PyDelta\_FromDSU (int days, int seconds, int useconds)

Return value : New reference. Renvoie un objet datetime.timedelta représentant le nombre passé en paramètre de jours, de secondes et de microsecondes. Le résultat est normalisé pour que le nombre de microsecondes et de secondes tombe dans la plage documentée pour les objets datetime.timedelta.

# PyObject \*PyTimeZone\_FromOffset (PyDateTime\_DeltaType \*offset)

Return value: New reference. Renvoie un objet datetime.timezone avec un décalage anonyme fixe représenté par l'argument offset.

Nouveau dans la version 3.7.

## PyObject \*PyTimeZone\_FromOffsetAndName (PyDateTime\_DeltaType \*offset, PyUnicode \*name)

Return value : New reference. Renvoie un objet datetime.timezone avec un décalage fixe représenté par l'argument offset et avec le nom de fuseau horaire name.

Nouveau dans la version 3.7.

Macros to extract fields from date objects. The argument must be an instance of PyDateTime\_Date, including subclasses (such as PyDateTime\_DateTime). The argument must not be NULL, and the type is not checked:

#### int **PyDateTime\_GET\_YEAR** (PyDateTime\_Date \*o)

Renvoie l'année, sous forme d'entier positif.

# int PyDateTime\_GET\_MONTH (PyDateTime\_Date \*o)

Renvoie le mois, sous forme d'entier allant de 1 à 12.

# int PyDateTime\_GET\_DAY (PyDateTime\_Date \*o)

Renvoie le jour, sous forme d'entier allant de 1 à 31.

Macros to extract fields from datetime objects. The argument must be an instance of PyDateTime\_DateTime, including subclasses. The argument must not be NULL, and the type is not checked:

```
int PyDateTime_DATE_GET_HOUR (PyDateTime_DateTime *o)
```

Renvoie l'heure, sous forme d'entier allant de 0 à 23.

## int PyDateTime\_DATE\_GET\_MINUTE (PyDateTime\_DateTime \*o)

Renvoie la minute, sous forme d'entier allant de 0 à 59.

#### int PyDateTime DATE GET SECOND (PyDateTime DateTime \*o)

Renvoie la seconde, sous forme d'entier allant de 0 à 59.

#### int PyDateTime\_DATE\_GET\_MICROSECOND (PyDateTime\_DateTime \*o)

Renvoie la microseconde, sous forme d'entier allant de 0 à 999999.

# int PyDateTime\_DATE\_GET\_FOLD (PyDateTime\_DateTime \*o)

Return the fold, as an int from 0 through 1.

Nouveau dans la version 3.6.

#### PyObject \*PyDateTime\_DATE\_GET\_TZINFO (PyDateTime\_DateTime \*o)

Return the tzinfo (which may be None).

Nouveau dans la version 3.10.

Macros to extract fields from time objects. The argument must be an instance of PyDateTime\_Time, including subclasses. The argument must not be NULL, and the type is not checked:

```
int PyDateTime TIME GET HOUR (PyDateTime *o)
```

Renvoie l'heure, sous forme d'entier allant de 0 à 23.

# int PyDateTime\_TIME\_GET\_MINUTE (PyDateTime\_Time \*o)

Renvoie la minute, sous forme d'entier allant de 0 à 59.

## int PyDateTime\_TIME\_GET\_SECOND (PyDateTime\_Time \*o)

Renvoie la seconde, sous forme d'entier allant de 0 à 59.

#### int PyDateTime\_TIME\_GET\_MICROSECOND (PyDateTime\_Time \*o)

Renvoie la microseconde, sous forme d'entier allant de 0 à 999999.

## int PyDateTime\_TIME\_GET\_FOLD (PyDateTime\_Time \*o)

Return the fold, as an int from 0 through 1.

Nouveau dans la version 3.6.

# PyObject \*PyDateTime\_TIME\_GET\_TZINFO (PyDateTime\_Time \*o)

Return the tzinfo (which may be None).

Nouveau dans la version 3.10.

Macros to extract fields from time delta objects. The argument must be an instance of PyDateTime\_Delta, including subclasses. The argument must not be NULL, and the type is not checked:

#### int PyDateTime\_DELTA\_GET\_DAYS (PyDateTime\_Delta \*o)

Renvoie le nombre de jours, sous forme d'entier allant de -999999999 à 999999999.

Nouveau dans la version 3.3.

#### int PyDateTime\_DELTA\_GET\_SECONDS (PyDateTime\_Delta \*o)

Renvoie le nombre de secondes sous forme d'entier allant de 0 à 86399.

Nouveau dans la version 3.3.

#### int PyDateTime\_DELTA\_GET\_MICROSECONDS (PyDateTime\_Delta \*o)

Renvoie le nombre de microsecondes, sous forme d'entier allant de 0 à 999999.

Nouveau dans la version 3.3.

Macros de confort pour les modules implémentant l'API DB:

# PyObject \*PyDateTime\_FromTimestamp (PyObject \*args)

Return value : New reference. Crée et renvoie un nouvel objet datetime à partir d'un n-uplet qui peut être passé à datetime . datetime . fromtimes tamp () .

#### PyObject \*PyDate\_FromTimestamp (PyObject \*args)

Return value : New reference. Crée et renvoie un nouvel objet datetime . date à partir d'un n-uplet qui peut être passé à datetime . date . fromtime stamp ().

# 8.6.15 Objects for Type Hinting

Various built-in types for type hinting are provided. Currently, two types exist -- GenericAlias and Union. Only GenericAlias is exposed to C.

# PyObject \*Py\_GenericAlias (PyObject \*origin, PyObject \*args)

Part of the Stable ABI since version 3.9. Create a GenericAlias object. Equivalent to calling the Python class types. GenericAlias. The origin and args arguments set the GenericAlias's \_\_origin\_\_ and \_\_args\_\_ attributes respectively. origin should be a PyTypeObject\*, and args can be a PyTupleObject\* or any PyObject\*. If args passed is not a tuple, a 1-tuple is automatically constructed and \_\_args\_\_ is set to (args,). Minimal checking is done for the arguments, so the function will succeed even if origin is not a type. The GenericAlias's \_\_parameters\_\_ attribute is constructed lazily from \_\_args\_\_. On failure, an exception is raised and NULL is returned.

Here's an example of how to make an extension type generic:

```
static PyMethodDef my_obj_methods[] = {
    // Other methods.
    ...
    {"__class_getitem__", Py_GenericAlias, METH_O|METH_CLASS, "See PEP 585"}
    ...
}
```

# Voir aussi:

The data model method \_\_class\_getitem\_\_().

Nouveau dans la version 3.9.

# PyTypeObject Py\_GenericAliasType

Part of the Stable ABI since version 3.9. The C type of the object returned by  $Py\_GenericAlias()$ . Equivalent to types. GenericAlias in Python.

Nouveau dans la version 3.9.

# CHAPITRE 9

# Initialization, Finalization, and Threads

See also Python Initialization Configuration.

# 9.1 Before Python Initialization

In an application embedding Python, the  $Py\_Initialize()$  function must be called before using any other Python/C API functions; with the exception of a few functions and the *global configuration variables*.

The following functions can be safely called before Python is initialized:

```
— Configuration functions:
  — PyImport_AppendInittab()
  — PyImport_ExtendInittab()
  — PyInitFrozenExtensions()
  — PyMem_SetAllocator()
  — PyMem_SetupDebugHooks()
  — PyObject_SetArenaAllocator()
  — Py_SetPath()
  — Py_SetProgramName()
  — Py_SetPythonHome()
  — Py_SetStandardStreamEncoding()
  — PySys_AddWarnOption()
  — PySys_AddXOption()
  — PySys_ResetWarnOptions()
— Informative functions:
  — Py_IsInitialized()
  - PyMem GetAllocator()
  — PyObject_GetArenaAllocator()
  — Py_GetBuildInfo()
  — Py_GetCompiler()
  — Py_GetCopyright()
  — Py_GetPlatform()
  — Py_GetVersion()
```

Note: The following functions should not be called before  $Py_Initialize(): Py_EncodeLocale()$ ,  $Py_GetPath()$ ,  $Py_GetPrefix()$ ,  $Py_GetExecPrefix()$ ,  $Py_GetProgramFullPath()$ ,  $Py_GetPythonHome()$ ,  $Py_GetProgramName()$  and  $PyEval_InitThreads()$ .

# 9.2 Global configuration variables

Python has variables for the global configuration to control different features and options. By default, these flags are controlled by command line options.

When a flag is set by an option, the value of the flag is the number of times that the option was set. For example,  $\neg b$  sets  $Py\_BytesWarningFlag$  to 1 and  $\neg bb$  sets  $Py\_BytesWarningFlag$  to 2.

#### int Py\_BytesWarningFlag

Issue a warning when comparing bytes or bytearray with str or bytes with int. Issue an error if greater or equal to 2.

Set by the -b option.

### int Py\_DebugFlag

Turn on parser debugging output (for expert only, depending on compilation options).

Set by the -d option and the PYTHONDEBUG environment variable.

### int Py\_DontWriteBytecodeFlag

If set to non-zero, Python won't try to write .pyc files on the import of source modules.

Set by the -B option and the PYTHONDONTWRITEBYTECODE environment variable.

### int Py\_FrozenFlag

Suppress error messages when calculating the module search path in Py\_GetPath().

Private flag used by \_freeze\_module and frozenmain programs.

### int Py\_HashRandomizationFlag

Set to 1 if the PYTHONHASHSEED environment variable is set to a non-empty string.

If the flag is non-zero, read the PYTHONHASHSEED environment variable to initialize the secret hash seed.

#### int Py IgnoreEnvironmentFlag

Ignore toutes les variables d'environnement PYTHON\* qui pourraient être définies. Par exemple, PYTHONPATH et PYTHONHOME.

Set by the  $-\mathbb{E}$  and  $-\mathbb{I}$  options.

### int Py\_InspectFlag

When a script is passed as first argument or the -c option is used, enter interactive mode after executing the script or the command, even when sys.stdin does not appear to be a terminal.

Set by the -i option and the PYTHONINSPECT environment variable.

### int Py\_InteractiveFlag

Set by the -i option.

### int Py\_IsolatedFlag

Run Python in isolated mode. In isolated mode sys.path contains neither the script's directory nor the user's site-packages directory.

Set by the -I option.

Nouveau dans la version 3.4.

#### int Py\_LegacyWindowsFSEncodingFlag

If the flag is non-zero, use the mbcs encoding with replace error handler, instead of the UTF-8 encoding with surrogatepass error handler, for the *filesystem encoding and error handler*.

Set to 1 if the PYTHONLEGACYWINDOWSFSENCODING environment variable is set to a non-empty string.

Voir la PEP 529 pour plus d'informations.

Disponibilité: Windows.

### int Py\_LegacyWindowsStdioFlag

If the flag is non-zero, use io.FileIO instead of WindowsConsoleIO for sys standard streams.

Set to 1 if the PYTHONLEGACYWINDOWSSTDIO environment variable is set to a non-empty string.

See PEP 528 for more details.

Disponibilité: Windows.

#### int Py\_NoSiteFlag

Désactive l'importation du module site et les modifications locales de sys.path qu'il implique. Désactive aussi ces manipulations si site est importé explicitement plus tard (appelez site.main() si vous voulez les déclencher).

Set by the -S option.

#### int Py\_NoUserSiteDirectory

N'ajoute pas le répertoire utilisateur site-packages à sys.path.

Set by the -s and -I options, and the PYTHONNOUSERSITE environment variable.

### int Py\_OptimizeFlag

Set by the -O option and the PYTHONOPTIMIZE environment variable.

#### int Py\_QuietFlag

N'affiche pas le copyright et la version, même en mode interactif.

Set by the -q option.

Nouveau dans la version 3.2.

### int Py\_UnbufferedStdioFlag

Force the stdout and stderr streams to be unbuffered.

Set by the -u option and the PYTHONUNBUFFERED environment variable.

### int Py\_VerboseFlag

Print a message each time a module is initialized, showing the place (filename or built-in module) from which it is loaded. If greater or equal to 2, print a message for each file that is checked for when searching for a module. Also provides information on module cleanup at exit.

Set by the -v option and the PYTHONVERBOSE environment variable.

# 9.3 Initializing and finalizing the interpreter

#### void Py\_Initialize()

*Part of the* Stable ABI. Initialize the Python interpreter. In an application embedding Python, this should be called before using any other Python/C API functions; see *Before Python Initialization* for the few exceptions.

This initializes the table of loaded modules (sys.modules), and creates the fundamental modules builtins, \_\_main\_\_ and sys. It also initializes the module search path (sys.path). It does not set sys.argv; use  $PySys\_SetArgvEx()$  for that. This is a no-op when called for a second time (without calling  $Py\_FinalizeEx()$  first). There is no return value; it is a fatal error if the initialization fails.

**Note:** On Windows, changes the console mode from O\_TEXT to O\_BINARY, which will also affect non-Python uses of the console using the C Runtime.

#### void Py\_InitializeEx (int initsigs)

Part of the Stable ABI. This function works like Py\_Initialize() if initsigs is 1. If initsigs is 0, it skips initialization registration of signal handlers, which might be useful when Python is embedded.

### int Py\_IsInitialized()

Part of the Stable ABI. Return true (nonzero) when the Python interpreter has been initialized, false (zero) if not. After Py\_FinalizeEx() is called, this returns false until Py\_Initialize() is called again.

### int Py\_FinalizeEx()

Part of the Stable ABI since version 3.6. Undo all initializations made by  $Py\_Initialize()$  and subsequent use of Python/C API functions, and destroy all sub-interpreters (see  $Py\_NewInterpreter()$  below) that were created and not yet destroyed since the last call to  $Py\_Initialize()$ . Ideally, this frees all memory allocated by the Python interpreter. This is a no-op when called for a second time (without calling  $Py\_Initialize()$  again first). Normally the return value is 0. If there were errors during finalization (flushing buffered data), -1 is returned.

This function is provided for a number of reasons. An embedding application might want to restart Python without having to restart the application itself. An application that has loaded the Python interpreter from a dynamically loadable library (or DLL) might want to free all memory allocated by Python before unloading the DLL. During a hunt for memory leaks in an application a developer might want to free all memory allocated by Python before exiting from the application.

**Bugs and caveats:** The destruction of modules and objects in modules is done in random order; this may cause destructors (\_\_del\_\_() methods) to fail when they depend on other objects (even functions) or modules. Dynamically loaded extension modules loaded by Python are not unloaded. Small amounts of memory allocated by the Python interpreter may not be freed (if you find a leak, please report it). Memory tied up in circular references between objects is not freed. Some memory allocated by extension modules may not be freed. Some extensions may not work properly if their initialization routine is called more than once; this can happen if an application calls Py\_Initialize() and Py\_FinalizeEx() more than once.

Raises an auditing event cpython.\_PySys\_ClearAuditHooks with no arguments.

Nouveau dans la version 3.6.

### void Py\_Finalize()

Part of the Stable ABI. This is a backwards-compatible version of  $Py\_FinalizeEx()$  that disregards the return value.

# 9.4 Process-wide parameters

### int Py\_SetStandardStreamEncoding (const char \*encoding, const char \*errors)

This API is kept for backward compatibility: setting PyConfig.stdio\_encoding and PyCon

This function should be called before  $Py\_Initialize()$ , if it is called at all. It specifies which encoding and error handling to use with standard IO, with the same meanings as in str.encode().

It overrides PYTHONIOENCODING values, and allows embedding code to control IO encoding when the environment variable does not work.

encoding and/or errors may be NULL to use PYTHONIOENCODING and/or default values (depending on other settings).

Note that sys.stderr always uses the "backslashreplace" error handler, regardless of this (or any other) setting. If  $Py\_FinalizeEx()$  is called, this function will need to be called again in order to affect subsequent calls to  $Py\_Initialize()$ .

Returns 0 if successful, a nonzero value on error (e.g. calling after the interpreter has already been initialized).

Nouveau dans la version 3.4.

Obsolète depuis la version 3.11.

### void Py\_SetProgramName (const wchar\_t \*name)

*Part of the* Stable ABI. This API is kept for backward compatibility: setting <code>PyConfig.program\_name</code> should be used instead, see *Python Initialization Configuration*.

This function should be called before  $Py\_Initialize()$  is called for the first time, if it is called at all. It tells the interpreter the value of the argv[0] argument to the main() function of the program (converted to wide characters). This is used by  $Py\_GetPath()$  and some other functions below to find the Python run-time libraries relative to the interpreter executable. The default value is 'python'. The argument should point to a zero-terminated wide character string in static storage whose contents will not change for the duration of the program's execution. No code in the Python interpreter will change the contents of this storage.

Use Py\_DecodeLocale() to decode a bytes string to get a wchar\_\* string.

Obsolète depuis la version 3.11.

### wchar \*Py\_GetProgramName()

*Part of the* Stable ABI. Return the program name set with *Py\_SetProgramName()*, or the default. The returned string points into static storage; the caller should not modify its value.

This function should not be called before Py Initialize(), otherwise it returns NULL.

Modifié dans la version 3.10 : It now returns NULL if called before Py\_Initialize().

### $wchar_t *Py_GetPrefix()$

Part of the Stable ABI. Return the prefix for installed platform-independent files. This is derived through a number of complicated rules from the program name set with  $Py\_SetProgramName()$  and some environment variables; for example, if the program name is '/usr/local/bin/python', the prefix is '/usr/local'. The returned string points into static storage; the caller should not modify its value. This corresponds to the **prefix** variable in the top-level Makefile and the --prefix argument to the **configure** script at build time. The value is available to Python code as sys.prefix. It is only useful on Unix. See also the next function.

This function should not be called before Py\_Initialize(), otherwise it returns NULL.

Modifié dans la version 3.10 : It now returns NULL if called before Py\_Initialize().

### wchar\_t \*Py\_GetExecPrefix()

Part of the Stable ABI. Return the exec-prefix for installed platform-dependent files. This is derived through a number of complicated rules from the program name set with Py\_SetProgramName() and some environment variables; for example, if the program name is '/usr/local/bin/python', the exec-prefix is '/usr/local'. The returned string points into static storage; the caller should not modify its value. This corresponds to the exec\_prefix variable in the top-level Makefile and the --exec-prefix argument to the

**configure** script at build time. The value is available to Python code as sys.exec\_prefix. It is only useful on Unix.

Background: The exec-prefix differs from the prefix when platform dependent files (such as executables and shared libraries) are installed in a different directory tree. In a typical installation, platform dependent files may be installed in the /usr/local/plat subtree while platform independent may be installed in /usr/local.

Generally speaking, a platform is a combination of hardware and software families, e.g. Sparc machines running the Solaris 2.x operating system are considered the same platform, but Intel machines running Solaris 2.x are another platform, and Intel machines running Linux are yet another platform. Different major revisions of the same operating system generally also form different platforms. Non-Unix operating systems are a different story; the installation strategies on those systems are so different that the prefix and exec-prefix are meaningless, and set to the empty string. Note that compiled Python bytecode files are platform independent (but not independent from the Python version by which they were compiled!).

System administrators will know how to configure the **mount** or **automount** programs to share /usr/local between platforms while having /usr/local/plat be a different filesystem for each platform.

This function should not be called before Py\_Initialize(), otherwise it returns NULL.

Modifié dans la version 3.10 : It now returns NULL if called before Py\_Initialize().

### wchar\_t \*Py\_GetProgramFullPath()

Part of the Stable ABI. Return the full program name of the Python executable; this is computed as a side-effect of deriving the default module search path from the program name (set by <code>Py\_SetProgramName()</code> above). The returned string points into static storage; the caller should not modify its value. The value is available to Python code as <code>sys.executable</code>.

This function should not be called before  $Py\_Initialize()$ , otherwise it returns NULL.

Modifié dans la version 3.10 : It now returns NULL if called before Py\_Initialize().

### wchar\_t \*Py\_GetPath()

Part of the Stable ABI. Return the default module search path; this is computed from the program name (set by  $Py\_SetProgramName()$  above) and some environment variables. The returned string consists of a series of directory names separated by a platform dependent delimiter character. The delimiter character is ':' on Unix and macOS, ';' on Windows. The returned string points into static storage; the caller should not modify its value. The list sys.path is initialized with this value on interpreter startup; it can be (and usually is) modified later to change the search path for loading modules.

This function should not be called before Py\_Initialize(), otherwise it returns NULL.

Modifié dans la version 3.10 : It now returns NULL if called before Py\_Initialize().

#### void Py SetPath (const wchar t\*)

Part of the Stable ABI since version 3.7. This API is kept for backward compatibility: setting PyConfig. module\_search\_paths and PyConfig.module\_search\_paths\_set should be used instead, see Python Initialization Configuration.

Set the default module search path. If this function is called before <code>Py\_Initialize()</code>, then <code>Py\_GetPath()</code> won't attempt to compute a default search path but uses the one provided instead. This is useful if Python is embedded by an application that has full knowledge of the location of all modules. The path components should be separated by the platform dependent delimiter character, which is ':' on Unix and macOS, ';' on Windows.

This also causes sys.executable to be set to the program full path (see Py\_GetProgramFullPath()) and for sys.prefix and sys.exec\_prefix to be empty. It is up to the caller to modify these if required after calling Py\_Initialize().

Use Py\_DecodeLocale() to decode a bytes string to get a wchar\_\* string.

The path argument is copied internally, so the caller may free it after the call completes.

Modifié dans la version 3.8: The program full path is now used for sys.executable, instead of the program name.

Obsolète depuis la version 3.11.

#### const char \*Py\_GetVersion()

Part of the Stable ABI. Return the version of this Python interpreter. This is a string that looks something like

```
"3.0a5+ (py3k:63103M, May 12 2008, 00:53:55) \n[GCC 4.2.3]"
```

The first word (up to the first space character) is the current Python version; the first characters are the major and minor version separated by a period. The returned string points into static storage; the caller should not modify its value. The value is available to Python code as sys.version.

See also the Py Version constant.

### const char \*Py\_GetPlatform()

Part of the Stable ABI. Return the platform identifier for the current platform. On Unix, this is formed from the "official" name of the operating system, converted to lower case, followed by the major revision number; e.g., for Solaris 2.x, which is also known as SunOS 5.x, the value is 'sunos5'. On macOS, it is 'darwin'. On Windows, it is 'win'. The returned string points into static storage; the caller should not modify its value. The value is available to Python code as sys.platform.

### const char \*Py\_GetCopyright()

Part of the Stable ABI. Return the official copyright string for the current Python version, for example

```
'Copyright 1991-1995 Stichting Mathematisch Centrum, Amsterdam'
```

The returned string points into static storage; the caller should not modify its value. The value is available to Python code as sys.copyright.

### const char \*Py\_GetCompiler()

Part of the Stable ABI. Return an indication of the compiler used to build the current Python version, in square brackets, for example :

```
"[GCC 2.7.2.2]"
```

The returned string points into static storage; the caller should not modify its value. The value is available to Python code as part of the variable sys.version.

### const char \*Py\_GetBuildInfo()

Part of the Stable ABI. Return information about the sequence number and build date and time of the current Python interpreter instance, for example

```
"#67, Aug 1 1997, 22:34:28"
```

The returned string points into static storage; the caller should not modify its value. The value is available to Python code as part of the variable sys.version.

### void PySys\_SetArgvEx (int argc, wchar\_t \*\*argv, int updatepath)

Part of the Stable ABI. This API is kept for backward compatibility: setting PyConfig.argv, PyConfig. parse\_argv and PyConfig.safe\_path should be used instead, see Python Initialization Configuration.

Set sys.argv based on argc and argv. These parameters are similar to those passed to the program's main () function with the difference that the first entry should refer to the script file to be executed rather than the executable hosting the Python interpreter. If there isn't a script that will be run, the first entry in argv can be an empty string. If this function fails to initialize sys.argv, a fatal condition is signalled using  $Py\_FatalError()$ .

If *updatepath* is zero, this is all the function does. If *updatepath* is non-zero, the function also modifies sys.path according to the following algorithm:

- If the name of an existing script is passed in argv[0], the absolute path of the directory where the script is located is prepended to sys.path.
- Otherwise (that is, if *argc* is 0 or argv [0] doesn't point to an existing file name), an empty string is prepended to sys.path, which is the same as prepending the current working directory (".").

Use Py\_DecodeLocale() to decode a bytes string to get a wchar\_\* string.

 $See \ also \ \textit{PyConfig.argv} \ and \ \textit{PyConfig.argv} \ members \ of \ the \ \textit{Python Initialization Configuration}.$ 

**Note:** It is recommended that applications embedding the Python interpreter for purposes other than executing a single script pass 0 as *updatepath*, and update sys.path themselves if desired. See CVE-2008-5983.

On versions before 3.1.3, you can achieve the same effect by manually popping the first sys.path element after having called  $PySys\_SetArgv()$ , for example using:

```
PyRun_SimpleString("import sys; sys.path.pop(0)\n");
```

Nouveau dans la version 3.1.3.

Obsolète depuis la version 3.11.

### void PySys\_SetArgv (int argc, wchar\_t \*\*argv)

Part of the Stable ABI. This API is kept for backward compatibility: setting PyConfig.argv and PyConfig. parse\_argv should be used instead, see Python Initialization Configuration.

This function works like  $PySys\_SetArgvEx()$  with *updatepath* set to 1 unless the **python** interpreter was started with the -I.

Use Py\_DecodeLocale() to decode a bytes string to get a wchar\_\* string.

See also PyConfig.orig\_argv and PyConfig.argv members of the Python Initialization Configuration.

Modifié dans la version 3.4 : The *updatepath* value depends on -I.

Obsolète depuis la version 3.11.

### void Py\_SetPythonHome (const wchar\_t \*home)

Part of the Stable ABI. This API is kept for backward compatibility: setting PyConfig. home should be used instead, see Python Initialization Configuration.

Set the default "home" directory, that is, the location of the standard Python libraries. See PYTHONHOME for the meaning of the argument string.

The argument should point to a zero-terminated character string in static storage whose contents will not change for the duration of the program's execution. No code in the Python interpreter will change the contents of this storage.

Use Py\_DecodeLocale() to decode a bytes string to get a wchar\_\* string.

Obsolète depuis la version 3.11.

#### wchar\_t \*Py\_GetPythonHome()

Part of the Stable ABI. Return the default "home", that is, the value set by a previous call to Py\_SetPythonHome(), or the value of the PYTHONHOME environment variable if it is set.

This function should not be called before Py\_Initialize(), otherwise it returns NULL.

Modifié dans la version 3.10 : It now returns NULL if called before Py\_Initialize().

# 9.5 Thread State and the Global Interpreter Lock

The Python interpreter is not fully thread-safe. In order to support multi-threaded Python programs, there's a global lock, called the *global interpreter lock* or *GIL*, that must be held by the current thread before it can safely access Python objects. Without the lock, even the simplest operations could cause problems in a multi-threaded program: for example, when two threads simultaneously increment the reference count of the same object, the reference count could end up being incremented only once instead of twice.

Therefore, the rule exists that only the thread that has acquired the *GIL* may operate on Python objects or call Python/C API functions. In order to emulate concurrency of execution, the interpreter regularly tries to switch threads (see sys.setswitchinterval()). The lock is also released around potentially blocking I/O operations like reading or writing a file, so that other Python threads can run in the meantime.

The Python interpreter keeps some thread-specific bookkeeping information inside a data structure called <code>PyThreadState</code>. There's also one global variable pointing to the current <code>PyThreadState</code>: it can be retrieved using <code>PyThreadState\_Get()</code>.

## 9.5.1 Releasing the GIL from extension code

Most extension code manipulating the GIL has the following simple structure :

```
Save the thread state in a local variable.
Release the global interpreter lock.
... Do some blocking I/O operation ...
Reacquire the global interpreter lock.
Restore the thread state from the local variable.
```

This is so common that a pair of macros exists to simplify it:

```
Py_BEGIN_ALLOW_THREADS
... Do some blocking I/O operation ...
Py_END_ALLOW_THREADS
```

The Py\_BEGIN\_ALLOW\_THREADS macro opens a new block and declares a hidden local variable; the Py\_END\_ALLOW\_THREADS macro closes the block.

The block above expands to the following code:

```
PyThreadState *_save;

_save = PyEval_SaveThread();
... Do some blocking I/O operation ...
PyEval_RestoreThread(_save);
```

Here is how these functions work: the global interpreter lock is used to protect the pointer to the current thread state. When releasing the lock and saving the thread state, the current thread state pointer must be retrieved before the lock is released (since another thread could immediately acquire the lock and store its own thread state in the global variable). Conversely, when acquiring the lock and restoring the thread state, the lock must be acquired before storing the thread state pointer.

**Note:** Calling system I/O functions is the most common use case for releasing the GIL, but it can also be useful before calling long-running computations which don't need access to Python objects, such as compression or cryptographic functions operating over memory buffers. For example, the standard zlib and hashlib modules release the GIL when compressing or hashing data.

### 9.5.2 Non-Python created threads

When threads are created using the dedicated Python APIs (such as the threading module), a thread state is automatically associated to them and the code showed above is therefore correct. However, when threads are created from C (for example by a third-party library with its own thread management), they don't hold the GIL, nor is there a thread state structure for them.

If you need to call Python code from these threads (often this will be part of a callback API provided by the aforementioned third-party library), you must first register these threads with the interpreter by creating a thread state data structure, then acquiring the GIL, and finally storing their thread state pointer, before you can start using the Python/C API. When you are done, you should reset the thread state pointer, release the GIL, and finally free the thread state data structure.

The  $PyGILState\_Ensure()$  and  $PyGILState\_Release()$  functions do all of the above automatically. The typical idiom for calling into Python from a C thread is:

```
PyGILState_STATE gstate;
gstate = PyGILState_Ensure();

/* Perform Python actions here. */
result = CallSomeFunction();
/* evaluate result or handle exception */

/* Release the thread. No Python API allowed beyond this point. */
PyGILState_Release(gstate);
```

Note that the PyGILState\_\* functions assume there is only one global interpreter (created automatically by Py\_Initialize()). Python supports the creation of additional interpreters (using Py\_NewInterpreter()), but mixing multiple interpreters and the PyGILState\_\* API is unsupported.

### 9.5.3 Cautions about fork()

Another important thing to note about threads is their behaviour in the face of the  $C \, fork$  () call. On most systems with fork (), after a process forks only the thread that issued the fork will exist. This has a concrete impact both on how locks must be handled and on all stored state in CPython's runtime.

The fact that only the "current" thread remains means any locks held by other threads will never be released. Python solves this for os.fork() by acquiring the locks it uses internally before the fork, and releasing them afterwards. In addition, it resets any lock-objects in the child. When extending or embedding Python, there is no way to inform Python of additional (non-Python) locks that need to be acquired before or reset after a fork. OS facilities such as pthread\_atfork() would need to be used to accomplish the same thing. Additionally, when extending or embedding Python, calling fork() directly rather than through os.fork() (and returning to or calling into Python) may result in a deadlock by one of Python's internal locks being held by a thread that is defunct after the fork.  $PyOS_AfterFork_Child()$  tries to reset the necessary locks, but is not always able to.

The fact that all other threads go away also means that CPython's runtime state there must be cleaned up properly, which os.fork() does. This means finalizing all other <code>PyThreadState</code> objects belonging to the current interpreter and all other <code>PyInterpreterState</code> objects. Due to this and the special nature of the "main" interpreter, fork() should only be called in that interpreter's "main" thread, where the CPython global runtime was originally initialized. The only exception is if <code>exec()</code> will be called immediately after.

## 9.5.4 High-level API

These are the most commonly used types and functions when writing C extension code, or when embedding the Python interpreter:

### type PyInterpreterState

Part of the Limited API (as an opaque struct). This data structure represents the state shared by a number of cooperating threads. Threads belonging to the same interpreter share their module administration and a few other internal items. There are no public members in this structure.

Threads belonging to different interpreters initially share nothing, except process state like available memory, open file descriptors and such. The global interpreter lock is also shared by all threads, regardless of to which interpreter they belong.

### type PyThreadState

Part of the Limited API (as an opaque struct). This data structure represents the state of a single thread. The only public data member is interp (PyInterpreterState\*), which points to this thread's interpreter state.

### void PyEval\_InitThreads()

Part of the Stable ABI. Deprecated function which does nothing.

In Python 3.6 and older, this function created the GIL if it didn't exist.

Modifié dans la version 3.9: The function now does nothing.

Modifié dans la version 3.7 : This function is now called by <code>Py\_Initialize()</code>, so you don't have to call it yourself anymore.

Modifié dans la version 3.2 : This function cannot be called before Py\_Initialize() anymore.

Obsolète depuis la version 3.9.

### int PyEval\_ThreadsInitialized()

Part of the Stable ABI. Returns a non-zero value if <code>PyEval\_InitThreads()</code> has been called. This function can be called without holding the GIL, and therefore can be used to avoid calls to the locking API when running single-threaded.

Modifié dans la version 3.7 : The GIL is now initialized by Py Initialize ().

Obsolète depuis la version 3.9.

#### PyThreadState \*PyEval\_SaveThread()

Part of the Stable ABI. Release the global interpreter lock (if it has been created) and reset the thread state to NULL, returning the previous thread state (which is not NULL). If the lock has been created, the current thread must have acquired it.

### void PyEval\_RestoreThread (PyThreadState \*tstate)

Part of the Stable ABI. Acquire the global interpreter lock (if it has been created) and set the thread state to tstate, which must not be NULL. If the lock has been created, the current thread must not have acquired it, otherwise deadlock ensues.

**Note:** Calling this function from a thread when the runtime is finalizing will terminate the thread, even if the thread was not created by Python. You can use \_Py\_IsFinalizing() or sys.is\_finalizing() to check if the interpreter is in process of being finalized before calling this function to avoid unwanted termination.

#### PyThreadState \*PyThreadState\_Get()

*Part of the* Stable ABI. Return the current thread state. The global interpreter lock must be held. When the current thread state is NULL, this issues a fatal error (so that the caller needn't check for NULL).

### PyThreadState \*PyThreadState\_Swap (PyThreadState \*tstate)

*Part of the* Stable ABI. Swap the current thread state with the thread state given by the argument *tstate*, which may be NULL. The global interpreter lock must be held and is not released.

The following functions use thread-local storage, and are not compatible with sub-interpreters:

### PyGILState\_STATE PyGILState\_Ensure()

Part of the Stable ABI. Ensure that the current thread is ready to call the Python C API regardless of the current state of Python, or of the global interpreter lock. This may be called as many times as desired by a thread as long as each call is matched with a call to <code>PyGILState\_Release()</code>. In general, other thread-related APIs may be used between <code>PyGILState\_Ensure()</code> and <code>PyGILState\_Release()</code> calls as long as the thread state is restored to its previous state before the Release(). For example, normal usage of the <code>Py\_BEGIN\_ALLOW\_THREADS</code> and <code>Py\_END\_ALLOW\_THREADS</code> macros is acceptable.

The return value is an opaque "handle" to the thread state when <code>PyGILState\_Ensure()</code> was called, and must be passed to <code>PyGILState\_Release()</code> to ensure Python is left in the same state. Even though recursive calls are allowed, these handles <code>cannot</code> be shared - each unique call to <code>PyGILState\_Ensure()</code> must save the handle for its call to <code>PyGILState\_Release()</code>.

When the function returns, the current thread will hold the GIL and be able to call arbitrary Python code. Failure is a fatal error.

**Note:** Calling this function from a thread when the runtime is finalizing will terminate the thread, even if the thread was not created by Python. You can use <code>\_Py\_IsFinalizing()</code> or <code>sys.is\_finalizing()</code> to check if the interpreter is in process of being finalized before calling this function to avoid unwanted termination.

### void PyGILState\_Release (PyGILState\_STATE)

Part of the Stable ABI. Release any resources previously acquired. After this call, Python's state will be the same as it was prior to the corresponding PyGILState\_Ensure() call (but generally this state will be unknown to the caller, hence the use of the GILState API).

Every call to  $PyGILState\_Ensure()$  must be matched by a call to  $PyGILState\_Release()$  on the same thread.

### PyThreadState \*PyGILState\_GetThisThreadState()

*Part of the* Stable ABI. Get the current thread state for this thread. May return NULL if no GILState API has been used on the current thread. Note that the main thread always has such a thread-state, even if no auto-thread-state call has been made on the main thread. This is mainly a helper/diagnostic function.

### int PyGILState\_Check()

Return 1 if the current thread is holding the GIL and 0 otherwise. This function can be called from any thread at any time. Only if it has had its Python thread state initialized and currently is holding the GIL will it return 1. This is mainly a helper/diagnostic function. It can be useful for example in callback contexts or memory allocation functions when knowing that the GIL is locked can allow the caller to perform sensitive actions or otherwise behave differently.

Nouveau dans la version 3.4.

The following macros are normally used without a trailing semicolon; look for example usage in the Python source distribution.

#### Py\_BEGIN\_ALLOW\_THREADS

Part of the Stable ABI. This macro expands to { PyThreadState \*\_save; \_save = PyEval\_SaveThread();. Note that it contains an opening brace; it must be matched with a following Py\_END\_ALLOW\_THREADS macro. See above for further discussion of this macro.

### Py\_END\_ALLOW\_THREADS

Part of the Stable ABI. This macro expands to PyEval\_RestoreThread(\_save); }. Note that it contains a closing brace; it must be matched with an earlier  $Py\_BEGIN\_ALLOW\_THREADS$  macro. See above for further discussion of this macro.

### Py\_BLOCK\_THREADS

Part of the Stable ABI. This macro expands to PyEval\_RestoreThread(\_save); : it is equivalent to Py\_END\_ALLOW\_THREADS without the closing brace.

#### Py\_UNBLOCK\_THREADS

Part of the Stable ABI. This macro expands to \_save = PyEval\_SaveThread(); : it is equivalent to Py\_BEGIN\_ALLOW\_THREADS without the opening brace and variable declaration.

### 9.5.5 Low-level API

All of the following functions must be called after Py\_Initialize().

Modifié dans la version 3.7 : Py\_Initialize () now initializes the GIL.

#### PyInterpreterState \*PyInterpreterState\_New()

*Part of the* Stable ABI. Create a new interpreter state object. The global interpreter lock need not be held, but may be held if it is necessary to serialize calls to this function.

Raises an auditing event cpython.PyInterpreterState\_New with no arguments.

### void PyInterpreterState\_Clear (PyInterpreterState \*interp)

Part of the Stable ABI. Reset all information in an interpreter state object. The global interpreter lock must be held. Raises an auditing event cpython.PyInterpreterState\_Clear with no arguments.

#### void PyInterpreterState\_Delete (PyInterpreterState \*interp)

Part of the Stable ABI. Destroy an interpreter state object. The global interpreter lock need not be held. The interpreter state must have been reset with a previous call to PyInterpreterState Clear().

### PyThreadState \*PyThreadState\_New (PyInterpreterState \*interp)

Part of the Stable ABI. Create a new thread state object belonging to the given interpreter object. The global interpreter lock need not be held, but may be held if it is necessary to serialize calls to this function.

### void PyThreadState\_Clear (PyThreadState \*tstate)

Part of the Stable ABI. Reset all information in a thread state object. The global interpreter lock must be held.

Modifié dans la version 3.9: This function now calls the PyThreadState.on\_delete callback. Previously, that happened in  $PyThreadState_Delete()$ .

#### void PyThreadState\_Delete (PyThreadState \*tstate)

Part of the Stable ABI. Destroy a thread state object. The global interpreter lock need not be held. The thread state must have been reset with a previous call to <code>PyThreadState\_Clear()</code>.

### void PyThreadState\_DeleteCurrent (void)

Destroy the current thread state and release the global interpreter lock. Like <code>PyThreadState\_Delete()</code>, the global interpreter lock need not be held. The thread state must have been reset with a previous call to <code>PyThreadState\_Clear()</code>.

### PyFrameObject \*PyThreadState\_GetFrame (PyThreadState \*tstate)

Part of the Stable ABI since version 3.10. Get the current frame of the Python thread state tstate.

Return a strong reference. Return NULL if no frame is currently executing.

See also PyEval GetFrame().

*tstate* must not be NULL.

Nouveau dans la version 3.9.

### uint64\_t PyThreadState\_GetID (PyThreadState \*tstate)

Part of the Stable ABI since version 3.10. Get the unique thread state identifier of the Python thread state tstate. tstate must not be NULL.

Nouveau dans la version 3.9.

### PyInterpreterState \*PyThreadState\_GetInterpreter (PyThreadState \*tstate)

Part of the Stable ABI since version 3.10. Get the interpreter of the Python thread state tstate.

*tstate* must not be NULL.

Nouveau dans la version 3.9.

#### void PyThreadState\_EnterTracing (PyThreadState \*tstate)

Suspend tracing and profiling in the Python thread state tstate.

Resume them using the <code>PyThreadState\_LeaveTracing()</code> function.

Nouveau dans la version 3.11.

### void PyThreadState\_LeaveTracing (PyThreadState \*tstate)

Resume tracing and profiling in the Python thread state *tstate* suspended by the *PyThreadState\_EnterTracing()* function.

See also PyEval\_SetTrace() and PyEval\_SetProfile() functions.

Nouveau dans la version 3.11.

### PyInterpreterState \*PyInterpreterState\_Get (void)

Part of the Stable ABI since version 3.9. Get the current interpreter.

Issue a fatal error if there no current Python thread state or no current interpreter. It cannot return NULL.

The caller must hold the GIL.

Nouveau dans la version 3.9.

### int64\_t PyInterpreterState\_GetID (PyInterpreterState \*interp)

Part of the Stable ABI since version 3.7. Return the interpreter's unique ID. If there was any error in doing so then −1 is returned and an error is set.

The caller must hold the GIL.

Nouveau dans la version 3.7.

### PyObject \*PyInterpreterState\_GetDict (PyInterpreterState \*interp)

Part of the Stable ABI since version 3.8. Return a dictionary in which interpreter-specific data may be stored. If this function returns NULL then no exception has been raised and the caller should assume no interpreter-specific dict is available.

This is not a replacement for  $PyModule\_GetState()$ , which extensions should use to store interpreter-specific state information.

Nouveau dans la version 3.8.

### $typedef \textit{PyObject} *(*\_\textbf{PyFrameEvalFunction}) (\textit{PyThreadState} *tstate, \_PyInterpreterFrame *frame, int throwflag)) \\$

Type of a frame evaluation function.

The *throwflag* parameter is used by the throw () method of generators: if non-zero, handle the current exception. Modifié dans la version 3.9: The function now takes a *tstate* parameter.

Modifié dans la version 3.11 : The *frame* parameter changed from PyFrameObject\* to \_PyInterpreterFrame\*.

#### \_PyFrameEvalFunction \_PyInterpreterState \_GetEvalFrameFunc (PyInterpreterState \*interp)

Get the frame evaluation function.

See the PEP 523 "Adding a frame evaluation API to CPython".

Nouveau dans la version 3.9.

# void \_PyInterpreterState\_SetEvalFrameFunc (PyInterpreterState \*interp, \_PyFrameEvalFunction eval frame)

Set the frame evaluation function.

See the PEP 523 "Adding a frame evaluation API to CPython".

Nouveau dans la version 3.9.

### PyObject \*PyThreadState\_GetDict()

Return value: Borrowed reference. Part of the Stable ABI. Return a dictionary in which extensions can store thread-specific state information. Each extension should use a unique key to use to store state in the dictionary. It is okay to call this function when no current thread state is available. If this function returns NULL, no exception has been raised and the caller should assume no current thread state is available.

### int PyThreadState\_SetAsyncExc (unsigned long id, PyObject \*exc)

Part of the Stable ABI. Asynchronously raise an exception in a thread. The *id* argument is the thread id of the target thread; *exc* is the exception object to be raised. This function does not steal any references to *exc*. To prevent naive misuse, you must write your own C extension to call this. Must be called with the GIL held. Returns the number of thread states modified; this is normally one, but will be zero if the thread id isn't found. If *exc* is NULL, the pending exception (if any) for the thread is cleared. This raises no exceptions.

Modifié dans la version 3.7: The type of the *id* parameter changed from long to unsigned long.

#### void PyEval\_AcquireThread (PyThreadState \*tstate)

*Part of the* Stable ABI. Acquire the global interpreter lock and set the current thread state to *tstate*, which must not be NULL. The lock must have been created earlier. If this thread already has the lock, deadlock ensues.

**Note:** Calling this function from a thread when the runtime is finalizing will terminate the thread, even if the thread was not created by Python. You can use <code>\_Py\_IsFinalizing()</code> or <code>sys.is\_finalizing()</code> to check if the interpreter is in process of being finalized before calling this function to avoid unwanted termination.

Modifié dans la version 3.8 : Updated to be consistent with <code>PyEval\_RestoreThread()</code>, <code>Py\_END\_ALLOW\_THREADS()</code>, and <code>PyGILState\_Ensure()</code>, and terminate the current thread if called while the interpreter is finalizing.

PyEval\_RestoreThread() is a higher-level function which is always available (even when threads have not been initialized).

### void PyEval\_ReleaseThread (PyThreadState \*tstate)

Part of the Stable ABI. Reset the current thread state to NULL and release the global interpreter lock. The lock must have been created earlier and must be held by the current thread. The *tstate* argument, which must not be NULL, is only used to check that it represents the current thread state --- if it isn't, a fatal error is reported.

*PyEval\_SaveThread()* is a higher-level function which is always available (even when threads have not been initialized).

### void PyEval\_AcquireLock()

Part of the Stable ABI. Acquire the global interpreter lock. The lock must have been created earlier. If this thread already has the lock, a deadlock ensues.

Obsolète depuis la version 3.2 : This function does not update the current thread state. Please use PyEval\_RestoreThread() or PyEval\_AcquireThread() instead.

**Note:** Calling this function from a thread when the runtime is finalizing will terminate the thread, even if the thread was not created by Python. You can use <code>\_Py\_IsFinalizing()</code> or <code>sys.is\_finalizing()</code> to check if the interpreter is in process of being finalized before calling this function to avoid unwanted termination.

Modifié dans la version 3.8 : Updated to be consistent with  $PyEval\_RestoreThread()$ ,  $Py\_END\_ALLOW\_THREADS()$ , and  $PyGILState\_Ensure()$ , and terminate the current thread if called while the interpreter is finalizing.

### void PyEval\_ReleaseLock()

Part of the Stable ABI. Release the global interpreter lock. The lock must have been created earlier.

Obsolète depuis la version 3.2: This function does not update the current thread state. Please use  $PyEval\_SaveThread()$  or  $PyEval\_ReleaseThread()$  instead.

# 9.6 Sub-interpreter support

While in most uses, you will only embed a single Python interpreter, there are cases where you need to create several independent interpreters in the same process and perhaps even in the same thread. Sub-interpreters allow you to do that.

The "main" interpreter is the first one created when the runtime initializes. It is usually the only Python interpreter in a process. Unlike sub-interpreters, the main interpreter has unique process-global responsibilities like signal handling. It is also responsible for execution during runtime initialization and is usually the active interpreter during runtime finalization. The <code>PyInterpreterState\_Main()</code> function returns a pointer to its state.

You can switch between sub-interpreters using the  $PyThreadState\_Swap()$  function. You can create and destroy them using the following functions:

### PyThreadState \*Py\_NewInterpreter()

Part of the Stable ABI. Create a new sub-interpreter. This is an (almost) totally separate environment for the execution of Python code. In particular, the new interpreter has separate, independent versions of all imported modules, including the fundamental modules builtins, \_\_main\_\_ and sys. The table of loaded modules (sys.modules) and the module search path (sys.path) are also separate. The new environment has no sys.argv variable. It has new standard I/O stream file objects sys.stdin, sys.stdout and sys.stderr (however these refer to the same underlying file descriptors).

The return value points to the first thread state created in the new sub-interpreter. This thread state is made in the current thread state. Note that no actual thread is created; see the discussion of thread states below. If creation of the new interpreter is unsuccessful, NULL is returned; no exception is set since the exception state is stored in the current thread state and there may not be a current thread state. (Like all other Python/C API functions, the global interpreter lock must be held before calling this function and is still held when it returns; however, unlike most other Python/C API functions, there needn't be a current thread state on entry.)

Extension modules are shared between (sub-)interpreters as follows:

- For modules using multi-phase initialization, e.g. PyModule\_FromDefAndSpec(), a separate module object is created and initialized for each interpreter. Only C-level static and global variables are shared between these module objects.
- For modules using single-phase initialization, e.g.  $PyModule\_Create()$ , the first time a particular extension is imported, it is initialized normally, and a (shallow) copy of its module's dictionary is squirreled away. When the same extension is imported by another (sub-)interpreter, a new module is initialized and filled with the contents of this copy; the extension's init function is not called. Objects in the module's dictionary thus end up shared across (sub-)interpreters, which might cause unwanted behavior (see <code>Bugs and caveats</code> below). Note that this is different from what happens when an extension is imported after the interpreter has been completely re-initialized by calling  $Py\_FinalizeEx()$  and  $Py\_Initialize()$ ; in that case, the extension's initmodule function <code>is</code> called again. As with multi-phase initialization, this means that only C-level static and global variables are shared between these modules.

### void Py\_EndInterpreter (PyThreadState \*tstate)

Part of the Stable ABI. Destroy the (sub-)interpreter represented by the given thread state. The given thread state must be the current thread state. See the discussion of thread states below. When the call returns, the current thread state is NULL. All thread states associated with this interpreter are destroyed. (The global interpreter lock must be held before calling this function and is still held when it returns.)  $Py_FinalizeEx()$  will destroy all sub-interpreters that haven't been explicitly destroyed at that point.

### 9.6.1 Bugs and caveats

Because sub-interpreters (and the main interpreter) are part of the same process, the insulation between them isn't perfect --- for example, using low-level file operations like os.close() they can (accidentally or maliciously) affect each other's open files. Because of the way extensions are shared between (sub-)interpreters, some extensions may not work properly; this is especially likely when using single-phase initialization or (static) global variables. It is possible to insert objects created in one sub-interpreter into a namespace of another (sub-)interpreter; this should be avoided if possible.

Special care should be taken to avoid sharing user-defined functions, methods, instances or classes between sub-interpreters, since import operations executed by such objects may affect the wrong (sub-)interpreter's dictionary of loaded modules. It is equally important to avoid sharing objects from which the above are reachable.

Also note that combining this functionality with PyGILState\_\* APIs is delicate, because these APIs assume a bijection between Python thread states and OS-level threads, an assumption broken by the presence of sub-interpreters. It is highly recommended that you don't switch sub-interpreters between a pair of matching PyGILState\_Ensure() and PyGILState\_Release() calls. Furthermore, extensions (such as ctypes) using these APIs to allow calling of Python code from non-Python created threads will probably be broken when using sub-interpreters.

# 9.7 Asynchronous Notifications

A mechanism is provided to make asynchronous notifications to the main interpreter thread. These notifications take the form of a function pointer and a void pointer argument.

int Py\_AddPendingCall (int (\*func)(void\*), void \*arg)

Part of the Stable ABI. Schedule a function to be called from the main interpreter thread. On success, 0 is returned and func is queued for being called in the main thread. On failure, -1 is returned without setting any exception.

When successfully queued, *func* will be *eventually* called from the main interpreter thread with the argument *arg*. It will be called asynchronously with respect to normally running Python code, but with both these conditions met:

- on a *bytecode* boundary;
- with the main thread holding the *global interpreter lock* (func can therefore use the full C API).

func must return 0 on success, or -1 on failure with an exception set. func won't be interrupted to perform another asynchronous notification recursively, but it can still be interrupted to switch threads if the global interpreter lock is released.

This function doesn't need a current thread state to run, and it doesn't need the global interpreter lock.

To call this function in a subinterpreter, the caller must hold the GIL. Otherwise, the function *func* can be scheduled to be called from the wrong interpreter.

**Avertissement:** This is a low-level function, only useful for very special cases. There is no guarantee that *func* will be called as quick as possible. If the main thread is busy executing a system call, *func* won't be called before the system call returns. This function is generally **not** suitable for calling Python code from arbitrary C threads. Instead, use the *PyGILState API*.

Modifié dans la version 3.9: If this function is called in a subinterpreter, the function *func* is now scheduled to be called from the subinterpreter, rather than being called from the main interpreter. Each subinterpreter now has its own list of scheduled calls.

Nouveau dans la version 3.1.

# 9.8 Profiling and Tracing

The Python interpreter provides some low-level support for attaching profiling and execution tracing facilities. These are used for profiling, debugging, and coverage analysis tools.

This C interface allows the profiling or tracing code to avoid the overhead of calling through Python-level callable objects, making a direct C function call instead. The essential attributes of the facility have not changed; the interface allows trace functions to be installed per-thread, and the basic events reported to the trace function are the same as had been reported to the Python-level trace functions in previous versions.

typedef int (\*Py\_tracefunc)(PyObject \*obj, PyFrameObject \*frame, int what, PyObject \*arg)

The type of the trace function registered using <code>PyEval\_SetProfile()</code> and <code>PyEval\_SetTrace()</code>. The first parameter is the object passed to the registration function as <code>obj</code>, <code>frame</code> is the frame object to which the event pertains, <code>what</code> is one of the constants <code>PyTrace\_CALL</code>, <code>PyTrace\_EXCEPTION</code>, <code>PyTrace\_LINE</code>, <code>PyTrace\_RETURN</code>, <code>PyTrace\_C\_EXCEPTION</code>, <code>PyTrace\_C\_RETURN</code>, or <code>PyTrace\_OPCODE</code>, and <code>arg</code> depends on the value of <code>what</code>:

Value of what	Meaning of arg
PyTrace_CALL	Always Py_None.
PyTrace_EXCEPTION	Exception information as returned by sys.exc_info().
PyTrace_LINE	Always Py_None.
PyTrace_RETURN	Value being returned to the caller, or NULL if caused by an exception.
PyTrace_C_CALL	Function object being called.
PyTrace_C_EXCEPTION	Function object being called.
PyTrace_C_RETURN	Function object being called.
PyTrace_OPCODE	Always Py_None.

### int PyTrace\_CALL

The value of the *what* parameter to a *Py\_tracefunc* function when a new call to a function or method is being reported, or a new entry into a generator. Note that the creation of the iterator for a generator function is not reported as there is no control transfer to the Python bytecode in the corresponding frame.

#### int PyTrace EXCEPTION

The value of the *what* parameter to a *Py\_tracefunc* function when an exception has been raised. The callback function is called with this value for *what* when after any bytecode is processed after which the exception becomes set within the frame being executed. The effect of this is that as exception propagation causes the Python stack to unwind, the callback is called upon return to each frame as the exception propagates. Only trace functions receives these events; they are not needed by the profiler.

### int PyTrace\_LINE

The value passed as the *what* parameter to a  $Py\_tracefunc$  function (but not a profiling function) when a line-number event is being reported. It may be disabled for a frame by setting f\_trace\_lines to  $\theta$  on that frame.

### int PyTrace RETURN

The value for the *what* parameter to Py\_tracefunc functions when a call is about to return.

#### int PyTrace C CALL

The value for the *what* parameter to *Py\_tracefunc* functions when a C function is about to be called.

### int PyTrace\_C\_EXCEPTION

The value for the *what* parameter to Py\_tracefunc functions when a C function has raised an exception.

### int PyTrace\_C\_RETURN

The value for the *what* parameter to Py\_tracefunc functions when a C function has returned.

#### int PyTrace\_OPCODE

The value for the *what* parameter to *Py\_tracefunc* functions (but not profiling functions) when a new opcode is about to be executed. This event is not emitted by default: it must be explicitly requested by setting f trace opcodes to *I* on the frame.

```
void PyEval_SetProfile (Py_tracefunc func, PyObject *obj)
```

Set the profiler function to *func*. The *obj* parameter is passed to the function as its first parameter, and may be any Python object, or NULL. If the profile function needs to maintain state, using a different value for *obj* for each thread provides a convenient and thread-safe place to store it. The profile function is called for all monitored events except PyTrace\_LINE PyTrace\_OPCODE and PyTrace\_EXCEPTION.

See also the sys.setprofile() function.

The caller must hold the GIL.

```
void PyEval_SetTrace (Py_tracefunc func, PyObject *obj)
```

Set the tracing function to *func*. This is similar to *PyEval\_SetProfile()*, except the tracing function does receive line-number events and per-opcode events, but does not receive any event related to C function objects being called. Any trace function registered using *PyEval\_SetTrace()* will not receive *PyTrace\_C\_CALL*, *PyTrace\_C\_EXCEPTION* or *PyTrace\_C\_RETURN* as a value for the *what* parameter.

See also the sys.settrace() function.

The caller must hold the GIL.

# 9.9 Support avancé du débogueur

These functions are only intended to be used by advanced debugging tools.

```
PyInterpreterState *PyInterpreterState_Head()
```

Return the interpreter state object at the head of the list of all such objects.

```
PyInterpreterState *PyInterpreterState_Main()
```

Return the main interpreter state object.

```
PyInterpreterState *PyInterpreterState_Next (PyInterpreterState *interp)
```

Return the next interpreter state object after *interp* from the list of all such objects.

```
PyThreadState *PyInterpreterState_ThreadHead (PyInterpreterState *interp)
```

Return the pointer to the first PyThreadState object in the list of threads associated with the interpreter interp.

```
PyThreadState *PyThreadState_Next (PyThreadState *tstate)
```

Return the next thread state object after *tstate* from the list of all such objects belonging to the same <code>PyInterpreterState</code> object.

# 9.10 Thread Local Storage Support

The Python interpreter provides low-level support for thread-local storage (TLS) which wraps the underlying native TLS implementation to support the Python-level thread local storage API (threading.local). The CPython C level APIs are similar to those offered by pthreads and Windows: use a thread key and functions to associate a void\* value per thread.

The GIL does *not* need to be held when calling these functions; they supply their own locking.

Note that Python.h does not include the declaration of the TLS APIs, you need to include pythread.h to use thread-local storage.

**Note:** None of these API functions handle memory management on behalf of the void\* values. You need to allocate and deallocate them yourself. If the void\* values happen to be *PyObject*\*, these functions don't do refcount operations on them either.

### 9.10.1 Thread Specific Storage (TSS) API

TSS API is introduced to supersede the use of the existing TLS API within the CPython interpreter. This API uses a new type  $Py\_tss\_t$  instead of int to represent thread keys.

Nouveau dans la version 3.7.

#### Voir aussi:

"A New C-API for Thread-Local Storage in CPython" (PEP 539)

### type Py\_tss\_t

This data structure represents the state of a thread key, the definition of which may depend on the underlying TLS implementation, and it has an internal field representing the key's initialization state. There are no public members in this structure

When Py\_LIMITED\_API is not defined, static allocation of this type by Py\_tss\_NEEDS\_INIT is allowed.

#### Py\_tss\_NEEDS\_INIT

This macro expands to the initializer for  $Py\_tss\_t$  variables. Note that this macro won't be defined with  $Py\_LIMITED\_API$ .

### **Dynamic Allocation**

Dynamic allocation of the  $Py\_tss\_t$ , required in extension modules built with  $Py\_LIMITED\_API$ , where static allocation of this type is not possible due to its implementation being opaque at build time.

### Py\_tss\_t \*PyThread\_tss\_alloc()

Part of the Stable ABI since version 3.7. Return a value which is the same state as a value initialized with  $Py\_tss\_NEEDS\_INIT$ , or NULL in the case of dynamic allocation failure.

### void PyThread\_tss\_free (Py\_tss\_t \*key)

Part of the Stable ABI since version 3.7. Free the given key allocated by PyThread\_tss\_alloc(), after first calling PyThread\_tss\_delete() to ensure any associated thread locals have been unassigned. This is a no-op if the key argument is NULL.

**Note:** A freed key becomes a dangling pointer. You should reset the key to NULL.

#### Méthodes

The parameter *key* of these functions must not be NULL. Moreover, the behaviors of *PyThread\_tss\_set()* and *PyThread\_tss\_get()* are undefined if the given *Py\_tss\_t* has not been initialized by *PyThread\_tss\_create()*.

```
int PyThread_tss_is_created (Py_tss_t *key)
```

Part of the Stable ABI since version 3.7. Return a non-zero value if the given  $Py\_tss\_t$  has been initialized by  $PyThread\_tss\_create()$ .

#### int PyThread\_tss\_create (Py\_tss\_t \*key)

Part of the Stable ABI since version 3.7. Return a zero value on successful initialization of a TSS key. The behavior is undefined if the value pointed to by the key argument is not initialized by Py\_tss\_NEEDS\_INIT. This function can be called repeatedly on the same key -- calling it on an already initialized key is a no-op and immediately returns success.

```
void PyThread_tss_delete (Py_tss_t *key)
```

Part of the Stable ABI since version 3.7. Destroy a TSS key to forget the values associated with the key across all threads, and change the key's initialization state to uninitialized. A destroyed key is able to be initialized again by <code>PyThread\_tss\_create()</code>. This function can be called repeatedly on the same key -- calling it on an already destroyed key is a no-op.

```
int PyThread_tss_set (Py_tss_t *key, void *value)
```

Part of the Stable ABI since version 3.7. Return a zero value to indicate successfully associating a void\* value with a TSS key in the current thread. Each thread has a distinct mapping of the key to a void\* value.

```
void *PyThread_tss_get (Py_tss_t *key)
```

Part of the Stable ABI since version 3.7. Return the void\* value associated with a TSS key in the current thread. This returns NULL if no value is associated with the key in the current thread.

### 9.10.2 Thread Local Storage (TLS) API

Obsolète depuis la version 3.7 : This API is superseded by *Thread Specific Storage (TSS) API*.

**Note:** This version of the API does not support platforms where the native TLS key is defined in a way that cannot be safely cast to int. On such platforms, <code>PyThread\_create\_key()</code> will return immediately with a failure status, and the other TLS functions will all be no-ops on such platforms.

Due to the compatibility problem noted above, this version of the API should not be used in new code.

```
int PyThread_create_key()
          Part of the Stable ABI.
void PyThread_delete_key(int key)
          Part of the Stable ABI.
int PyThread_set_key_value(int key, void *value)
          Part of the Stable ABI.
void *PyThread_get_key_value(int key)
          Part of the Stable ABI.
void PyThread_delete_key_value(int key)
          Part of the Stable ABI.
void PyThread_ReInitTLS()
          Part of the Stable ABI.
```

# CHAPITRE 10

# Python Initialization Configuration

Nouveau dans la version 3.8.

Python can be initialized with  $Py\_InitializeFromConfig$  () and the PyConfig structure. It can be preinitialized with  $Py\_PreInitialize$  () and the PyPreConfig structure.

There are two kinds of configuration:

- The *Python Configuration* can be used to build a customized Python which behaves as the regular Python. For example, environment variables and command line arguments are used to configure Python.
- The *Isolated Configuration* can be used to embed Python into an application. It isolates Python from the system. For example, environment variables are ignored, the LC\_CTYPE locale is left unchanged and no signal handler is registered.

The Py\_RunMain () function can be used to write a customized Python program.

See also Initialization, Finalization, and Threads.

### Voir aussi:

PEP 587 "Python Initialization Configuration".

# 10.1 Example

Example of customized Python always running in isolated mode:

(suite sur la page suivante)

(suite de la page précédente)

```
status = PyConfig_SetBytesArgv(&config, argc, argv);
if (PyStatus_Exception(status)) {
    goto exception;
}

status = Py_InitializeFromConfig(&config);
if (PyStatus_Exception(status)) {
    goto exception;
}
PyConfig_Clear(&config);

return Py_RunMain();

exception:
    PyConfig_Clear(&config);
    if (PyStatus_IsExit(status)) {
        return status.exitcode;
}
/* Display the error message and exit the process with non-zero exit code */
Py_ExitStatusException(status);
}
```

# 10.2 PyWideStringList

```
type PyWideStringList
      List of wchar t* strings.
      If length is non-zero, items must be non-NULL and all strings must be non-NULL.
      Methods:
      PyStatus PyWideStringList_Append (PyWideStringList *list, const wchar_t *item)
           Append item to list.
           Python must be preinitialized to call this function.
      PyStatus PyWideStringList_Insert (PyWideStringList *list, Py_ssize_t index, const wchar_t *item)
           Insert item into list at index.
           If index is greater than or equal to list length, append item to list.
           index must be greater than or equal to 0.
           Python must be preinitialized to call this function.
      Structure fields:
      Py_ssize_t length
           List length.
      wchar_t **items
           List items.
```

# 10.3 PyStatus

```
type PyStatus
     Structure to store an initialization function status: success, error or exit.
     For an error, it can store the C function name which created the error.
     Structure fields:
     int exitcode
          Exit code. Argument passed to exit ().
     const char *err_msg
          Error message.
     const char *func
          Name of the function which created an error, can be NULL.
     Functions to create a status:
     PyStatus PyStatus_Ok (void)
          Success.
     PyStatus_Error (const char *err_msg)
          Initialization error with a message.
          err_msg must not be NULL.
     PyStatus PyStatus_NoMemory (void)
          Memory allocation failure (out of memory).
     PyStatus_Exit (int exitcode)
          Exit Python with the specified exit code.
     Functions to handle a status:
     int PyStatus_Exception (PyStatus status)
          Is the status an error or an exit? If true, the exception must be handled; by calling
          Py_ExitStatusException() for example.
     int PyStatus_IsError (PyStatus status)
          Is the result an error?
     int PyStatus_IsExit (PyStatus status)
          Is the result an exit?
     void Py_ExitStatusException (PyStatus status)
          Call exit (exitcode) if status is an exit. Print the error message and exit with a non-zero exit code if
          status is an error. Must only be called if PyStatus_Exception (status) is non-zero.
```

**Note:** Internally, Python uses macros which set PyStatus.func, whereas functions to create a status set func to NULL.

#### Exemple:

```
PyStatus alloc(void **ptr, size_t size)
{
    *ptr = PyMem_RawMalloc(size);
    if (*ptr == NULL) {
        return PyStatus_NoMemory();
    }
    return PyStatus_Ok();
}
```

(suite sur la page suivante)

10.3. PyStatus 197

(suite de la page précédente)

```
int main(int argc, char **argv)
    void *ptr;
    PyStatus status = alloc(&ptr, 16);
    if (PyStatus_Exception(status)) {
        Py_ExitStatusException(status);
   PyMem_Free(ptr);
    return 0;
```

# 10.4 PyPreConfig

```
type PyPreConfig
     Structure used to preinitialize Python.
     Function to initialize a preconfiguration:
     void PyPreConfig_InitPythonConfig (PyPreConfig *preconfig)
          Initialize the preconfiguration with Python Configuration.
     void PyPreConfig_InitIsolatedConfig (PyPreConfig *preconfig)
          Initialize the preconfiguration with Isolated Configuration.
     Structure fields:
     int allocator
          Name of the Python memory allocators:
          — PYMEM ALLOCATOR NOT SET (0): don't change memory allocators (use defaults).

    — PYMEM_ALLOCATOR_DEFAULT (1): default memory allocators.

          — PYMEM_ALLOCATOR_DEBUG (2): default memory allocators with debug hooks.
          — PYMEM_ALLOCATOR_MALLOC(3): use malloc() of the C library.
          — PYMEM_ALLOCATOR_MALLOC_DEBUG (4): force usage of malloc() with debug hooks.
          — PYMEM ALLOCATOR PYMALLOC (5): Python pymalloc memory allocator.

    — PYMEM_ALLOCATOR_PYMALLOC_DEBUG (6): Python pymalloc memory allocator with debug hooks.

          PYMEM_ALLOCATOR_PYMALLOC and PYMEM_ALLOCATOR_PYMALLOC_DEBUG are not supported if
          Python is configured using --without-pymalloc.
          See Memory Management.
          Default: PYMEM_ALLOCATOR_NOT_SET.
     int configure_locale
          Set the LC_CTYPE locale to the user preferred locale.
          If equals to 0, set coerce_c_locale and coerce_c_locale_warn members to 0.
          See the locale encoding.
          Default: 1 in Python config, 0 in isolated config.
     int coerce_c_locale
          If equals to 2, coerce the C locale.
          If equals to 1, read the LC_CTYPE locale to decide if it should be coerced.
          See the locale encoding.
          Default: -1 in Python config, 0 in isolated config.
     int coerce_c_locale_warn
          If non-zero, emit a warning if the C locale is coerced.
```

Default: -1 in Python config, 0 in isolated config.

#### int dev mode

Python Development Mode: see PyConfig.dev\_mode.

Default: -1 in Python mode, 0 in isolated mode.

#### int isolated

Isolated mode: see *PyConfig.isolated*. Default: 0 in Python mode, 1 in isolated mode.

### int legacy\_windows\_fs\_encoding

#### If non-zero:

- Set PyPreConfig.utf8\_mode to 0,
- Set PyConfig.filesystem\_encoding to "mbcs",
- Set PyConfig.filesystem\_errors to "replace".

Initialized the from PYTHONLEGACYWINDOWSFSENCODING environment variable value.

Only available on Windows. #ifdef MS\_WINDOWS macro can be used for Windows specific code.

Default: 0.

### int parse\_argv

If non-zero,  $Py\_PreInitializeFromArgs()$  and  $Py\_PreInitializeFromBytesArgs()$  parse their argv argument the same way the regular Python parses command line arguments: see Command Line Arguments.

Default: 1 in Python config, 0 in isolated config.

#### int use\_environment

Use environment variables? See PyConfig.use\_environment.

Default: 1 in Python config and 0 in isolated config.

#### int utf8 mode

If non-zero, enable the Python UTF-8 Mode.

Set to 0 or 1 by the -X utf8 command line option and the PYTHONUTF8 environment variable.

Also set to 1 if the LC CTYPE locale is C or POSIX.

Default: -1 in Python config and 0 in isolated config.

# 10.5 Preinitialize Python with PyPreConfig

The preinitialization of Python:

- Set the Python memory allocators (PyPreConfig.allocator)
- Configure the LC\_CTYPE locale (*locale encoding*)
- Set the Python UTF-8 Mode (PyPreConfig.utf8\_mode)

The current preconfiguration (PyPreConfig type) is stored in \_PyRuntime.preconfig.

Functions to preinitialize Python:

#### PyStatus Py PreInitialize (const PyPreConfig \*preconfig)

Preinitialize Python from *preconfig* preconfiguration.

preconfig must not be NULL.

### PyStatus Py\_PreInitializeFromBytesArgs (const PyPreConfig \*preconfig, int argc, char \*const \*argv)

Preinitialize Python from *preconfig* preconfiguration.

Parse *argv* command line arguments (bytes strings) if *parse\_argv* of *preconfig* is non-zero. *preconfig* must not be NULL.

```
PyStatus Py_PreInitializeFromArgs (const PyPreConfig *preconfig, int argc, wchar_t *const *argv)
```

Preinitialize Python from *preconfig* preconfiguration.

Parse *argv* command line arguments (wide strings) if *parse\_argv* of *preconfig* is non-zero. *preconfig* must not be NULL.

The caller is responsible to handle exceptions (error or exit) using PyStatus\_Exception() and Py\_ExitStatusException().

For *Python Configuration* (PyPreConfig\_InitPythonConfig()), if Python is initialized with command line arguments, the command line arguments must also be passed to preinitialize Python, since they have an effect on the pre-configuration like encodings. For example, the -X utf8 command line option enables the Python UTF-8 Mode.

PyMem\_SetAllocator() can be called after Py\_PreInitialize() and before Py\_InitializeFromConfig() to install a custom memory allocator. It can be called before Py\_PreInitialize() if PyPreConfig.allocator is set to PYMEM\_ALLOCATOR\_NOT\_SET.

Python memory allocation functions like  $PyMem\_RawMalloc()$  must not be used before the Python preinitialization, whereas calling directly malloc() and free() is always safe.  $Py\_DecodeLocale()$  must not be called before the Python preinitialization.

Example using the preinitialization to enable the Python UTF-8 Mode:

```
PyStatus status;
PyPreConfig preconfig;
PyPreConfig_InitPythonConfig(&preconfig);

preconfig.utf8_mode = 1;

status = Py_PreInitialize(&preconfig);
if (PyStatus_Exception(status)) {
    Py_ExitStatusException(status);
}

/* at this point, Python speaks UTF-8 */

Py_Initialize();
/* ... use Python API here ... */
Py_Finalize();
```

# 10.6 PyConfig

#### type PyConfig

Structure containing most parameters to configure Python.

When done, the PyConfig Clear () function must be used to release the configuration memory.

Structure methods:

```
void PyConfig_InitPythonConfig (PyConfig *config)
```

Initialize configuration with the *Python Configuration*.

void PyConfig\_InitIsolatedConfig (PyConfig \*config)

Initialize configuration with the Isolated Configuration.

PyStatus PyConfig\_SetString (PyConfig \*config, wchar\_t \*const \*config\_str, const wchar\_t \*str)

Copy the wide character string str into \*config\_str.

Preinitialize Python if needed.

```
PyStatus PyConfig_SetBytesString (PyConfig *config, wchar_t *config_str, const char *str)
```

Decode str using Py\_DecodeLocale() and set the result into \*config\_str.

Preinitialize Python if needed.

PyStatus PyConfig\_SetArgv (PyConfig \*config, int argc, wchar\_t \*const \*argv)

Set command line arguments (argv member of config) from the argv list of wide character strings. *Preinitialize Python* if needed.

```
PyStatus PyConfig_SetBytesArgv (PyConfig *config, int argc, char *const *argv)
```

Set command line arguments (argv member of config) from the argv list of bytes strings. Decode bytes using  $Py\_DecodeLocale()$ .

Preinitialize Python if needed.

```
PyStatus PyConfig_SetWideStringList (PyConfig *config, PyWideStringList *list, Py_ssize_t length, wchar_t **items)
```

Set the list of wide strings list to length and items.

Preinitialize Python if needed.

```
PyStatus PyConfig_Read (PyConfig *config)
```

Read all Python configuration.

Fields which are already initialized are left unchanged.

Fields for *path configuration* are no longer calculated or modified when calling this function, as of Python 3.11.

The <code>PyConfig\_Read()</code> function only parses <code>PyConfig.argv</code> arguments once: <code>PyConfig.parse\_argv</code> is set to 2 after arguments are parsed. Since Python arguments are strippped from <code>PyConfig.argv</code>, parsing arguments twice would parse the application options as Python options. <code>Preinitialize Python</code> if needed.

Modifié dans la version 3.10: The <code>PyConfig.argv</code> arguments are now only parsed once, <code>PyConfig.parse\_argv</code> is set to 2 after arguments are parsed, and arguments are only parsed if <code>PyConfig.parse\_argv</code> equals 1.

Modifié dans la version  $3.11: PyConfig_Read()$  no longer calculates all paths, and so fields listed under *Python Path Configuration* may no longer be updated until  $Py_InitializeFromConfig()$  is called.

### void PyConfig\_Clear (PyConfig \*config)

Release configuration memory.

Most PyConfig methods *preinitialize Python* if needed. In that case, the Python preinitialization configuration (*PyPreConfig*) in based on the *PyConfig*. If configuration fields which are in common with *PyPreConfig* are tuned, they must be set before calling a *PyConfig* method:

```
- PyConfig.dev_mode
```

- PyConfig.isolated
- PyConfig.parse\_argv
- PyConfig.use\_environment

Moreover, if PyConfig\_SetArgv() or PyConfig\_SetBytesArgv() is used, this method must be called before other methods, since the preinitialization configuration depends on command line arguments (if parse\_argv is non-zero).

The caller of these methods is responsible to handle exceptions (error or exit) using PyStatus\_Exception() and Py ExitStatusException().

Structure fields:

#### PyWideStringList argv

Command line arguments: sys.argv.

Set parse\_argv to 1 to parse argv the same way the regular Python parses Python command line arguments and then to strip Python arguments from argv.

If argv is empty, an empty string is added to ensure that sys.argv always exists and is never empty.

Default: NULL.

See also the orig\_argv member.

10.6. PyConfig 201

#### int safe path

If equals to zero, Py\_RunMain() prepends a potentially unsafe path to sys.path at startup:

- If argv[0] is equal to L"-m" (python -m module), prepend the current working directory.
- If running a script (python script.py), prepend the script's directory. If it's a symbolic link, resolve symbolic links.
- Otherwise (python -c code and python), prepend an empty string, which means the current working directory.

Set to 1 by the -P command line option and the PYTHONSAFEPATH environment variable.

Default: 0 in Python config, 1 in isolated config.

Nouveau dans la version 3.11.

### wchar\_t \*base\_exec\_prefix

```
sys.base_exec_prefix.
```

Default: NULL.

Part of the Python Path Configuration output.

### wchar\_t \*base\_executable

Python base executable: sys.\_base\_executable.

Set by the \_\_\_PYVENV\_LAUNCHER\_\_ environment variable.

Set from PyConfig.executable if NULL.

Default: NULL.

Part of the *Python Path Configuration* output.

### wchar\_t \*base\_prefix

```
sys.base_prefix.
```

Default: NULL.

Part of the Python Path Configuration output.

#### int buffered\_stdio

If equals to 0 and configure\_c\_stdio is non-zero, disable buffering on the C streams stdout and stderr.

Set to 0 by the -u command line option and the PYTHONUNBUFFERED environment variable.

stdin is always opened in buffered mode.

Default: 1.

### int bytes\_warning

If equals to 1, issue a warning when comparing bytes or bytearray with str, or comparing bytes with int

If equal or greater to 2, raise a BytesWarning exception in these cases.

Incremented by the -b command line option.

Default: 0.

### int warn\_default\_encoding

If non-zero, emit a EncodingWarning warning when io. TextIOWrapper uses its default encoding. See io-encoding-warning for details.

Default: 0.

Nouveau dans la version 3.10.

### int code\_debug\_ranges

If equals to 0, disables the inclusion of the end line and column mappings in code objects. Also disables traceback printing carets to specific error locations.

Set to 0 by the PYTHONNODEBUGRANGES environment variable and by the -X no\_debug\_ranges command line option.

Default: 1.

Nouveau dans la version 3.11.

#### wchar\_t \*check\_hash\_pycs\_mode

Control the validation behavior of hash-based .pyc files : value of the --check-hash-based-pycs command line option.

#### Valid values:

- L"always": Hash the source file for invalidation regardless of value of the 'check\_source' flag.
- L"never" : Assume that hash-based pycs always are valid.
- L"default": The 'check source' flag in hash-based pycs determines invalidation.

Default: L"default".

See also PEP 552 "Deterministic pycs".

### int configure\_c\_stdio

If non-zero, configure C standard streams:

- On Windows, set the binary mode (O\_BINARY) on stdin, stdout and stderr.
- If buffered\_stdio equals zero, disable buffering of stdin, stdout and stderr streams.
- If interactive is non-zero, enable stream buffering on stdin and stdout (only stdout on Windows).

Default: 1 in Python config, 0 in isolated config.

### int dev\_mode

If non-zero, enable the Python Development Mode.

Set to 1 by the -X dev option and the PYTHONDEVMODE environment variable.

Default: -1 in Python mode, 0 in isolated mode.

### int dump\_refs

Dump Python references?

If non-zero, dump all objects which are still alive at exit.

Set to 1 by the PYTHONDUMPREFS environment variable.

Need a special build of Python with the Py\_TRACE\_REFS macro defined : see the configure --with-trace-refs option.

Default: 0.

### wchar\_t \*exec\_prefix

The site-specific directory prefix where the platform-dependent Python files are installed : sys.exec\_prefix.

Default: NULL.

Part of the Python Path Configuration output.

#### wchar\_t \*executable

The absolute path of the executable binary for the Python interpreter: sys.executable.

Default: NULL.

Part of the Python Path Configuration output.

### int faulthandler

Enable faulthandler?

If non-zero, call faulthandler.enable() at startup.

Set to 1 by -X faulthandler and the PYTHONFAULTHANDLER environment variable.

Default: -1 in Python mode, 0 in isolated mode.

### wchar\_t \*filesystem\_encoding

Filesystem encoding: sys.getfilesystemencoding().

On macOS, Android and VxWorks: use "utf-8" by default.

On Windows: use "utf-8" by default, or "mbcs" if legacy\_windows\_fs\_encoding of PyPreConfig is non-zero.

Default encoding on other platforms:

- "utf-8" if PyPreConfig.utf8\_mode is non-zero.
- "ascii" if Python detects that nl\_langinfo (CODESET) announces the ASCII encoding, whereas the mbstowcs () function decodes from a different encoding (usually Latin1).

10.6. PyConfig 203

```
— "utf-8" if nl_langinfo (CODESET) returns an empty string.
```

Otherwise, use the locale encoding: nl\_langinfo (CODESET) result.

At Python startup, the encoding name is normalized to the Python codec name. For example, "ANSI\_X3.4-1968" is replaced with "ascii".

See also the filesystem\_errors member.

### wchar\_t \*filesystem\_errors

Filesystem error handler: sys.getfilesystemencodeerrors().

On Windows: use "surrogatepass" by default, or "replace" if legacy\_windows\_fs\_encoding of PyPreConfig is non-zero.

On other platforms: use "surrogateescape" by default.

Supported error handlers:

- "strict"
- "surrogateescape"
- "surrogatepass" (only supported with the UTF-8 encoding)

See also the filesystem\_encoding member.

### unsigned long hash\_seed

### int use\_hash\_seed

Randomized hash function seed.

If use\_hash\_seed is zero, a seed is chosen randomly at Python startup, and hash\_seed is ignored.

Set by the PYTHONHASHSEED environment variable.

Default *use\_hash\_seed* value : -1 in Python mode, 0 in isolated mode.

#### wchar t\*home

Python home directory.

If Py\_SetPythonHome () has been called, use its argument if it is not NULL.

Set by the PYTHONHOME environment variable.

Default: NULL.

Part of the Python Path Configuration input.

### int import\_time

If non-zero, profile import time.

Set the 1 by the -X importtime option and the PYTHONPROFILEIMPORTTIME environment variable.

Default: 0.

#### int inspect

Enter interactive mode after executing a script or a command.

If greater than 0, enable inspect: when a script is passed as first argument or the -c option is used, enter interactive mode after executing the script or the command, even when sys.stdin does not appear to be a terminal.

Incremented by the -i command line option. Set to 1 if the PYTHONINSPECT environment variable is non-empty.

Default: 0.

### int install\_signal\_handlers

Install Python signal handlers?

Default: 1 in Python mode, 0 in isolated mode.

#### int interactive

If greater than 0, enable the interactive mode (REPL).

Incremented by the -i command line option.

Default: 0.

#### int isolated

If greater than 0, enable isolated mode:

- Set safe\_path to 1: don't prepend a potentially unsafe path to sys.path at Python startup.
- Set use\_environment to 0.
- Set user\_site\_directory to 0 : don't add the user site directory to sys.path.
- Python REPL doesn't import readline nor enable default readline configuration on interactive prompts.

Set to 1 by the -I command line option.

Default : 0 in Python mode, 1 in isolated mode.

See also PyPreConfig.isolated.

### int legacy\_windows\_stdio

If non-zero, use io.FileIO instead of io.WindowsConsoleIO for sys.stdin, sys.stdout and sys.stderr.

Set to 1 if the PYTHONLEGACYWINDOWSSTDIO environment variable is set to a non-empty string.

Only available on Windows. #ifdef MS\_WINDOWS macro can be used for Windows specific code.

Default: 0.

See also the PEP 528 (Change Windows console encoding to UTF-8).

### int malloc\_stats

If non-zero, dump statistics on Python pymalloc memory allocator at exit.

Set to 1 by the PYTHONMALLOCSTATS environment variable.

The option is ignored if Python is configured using the --without-pymalloc option.

Default: 0.

### wchar\_t \*platlibdir

Platform library directory name: sys.platlibdir.

Set by the PYTHONPLATLIBDIR environment variable.

Default: value of the PLATLIBDIR macro which is set by the configure --with-platlibdir option (default: "lib", or "DLLs" on Windows).

Part of the Python Path Configuration input.

Nouveau dans la version 3.9.

Modifié dans la version 3.11: This macro is now used on Windows to locate the standard library extension modules, typically under DLLs. However, for compatibility, note that this value is ignored for any non-standard layouts, including in-tree builds and virtual environments.

#### wchar t\*pythonpath env

Module search paths (sys.path) as a string separated by DELIM (os.path.pathsep).

Set by the PYTHONPATH environment variable.

Default: NULL.

Part of the Python Path Configuration input.

### PyWideStringList module\_search\_paths

### int module\_search\_paths\_set

Module search paths: sys.path.

If module\_search\_paths\_set is equal to 0, Py\_InitializeFromConfig() will replace module\_search\_paths and sets module\_search\_paths\_set to 1.

Default: empty list (module\_search\_paths) and 0 (module\_search\_paths\_set).

Part of the Python Path Configuration output.

### int optimization\_level

Compilation optimization level:

- 0: Peephole optimizer, set \_\_debug\_\_ to True.
- 1: Level 0, remove assertions, set \_\_debug\_\_ to False.
- 2 : Level 1, strip docstrings.

Incremented by the -O command line option. Set to the PYTHONOPTIMIZE environment variable value.

Default: 0.

10.6. PyConfig 205

#### PyWideStringList orig\_argv

The list of the original command line arguments passed to the Python executable: sys.orig\_argv.

If orig\_argv list is empty and argv is not a list only containing an empty string, PyConfig\_Read() copies argv into orig\_argv before modifying argv (if parse\_argv is non-zero).

See also the argv member and the Py\_GetArgcArgv() function.

Default: empty list.

Nouveau dans la version 3.10.

### int parse\_argv

Parse command line arguments?

If equals to 1, parse argv the same way the regular Python parses command line arguments, and strip Python arguments from argv.

The <code>PyConfig\_Read()</code> function only parses <code>PyConfig.argv</code> arguments once: <code>PyConfig.parse\_argv</code> is set to 2 after arguments are parsed. Since Python arguments are strippped from <code>PyConfig.argv</code>, parsing arguments twice would parse the application options as Python options.

Default: 1 in Python mode, 0 in isolated mode.

Modifié dans la version 3.10: The <code>PyConfig.argv</code> arguments are now only parsed if <code>PyConfig.parse\_argv</code> equals to 1.

#### int parser\_debug

Parser debug mode. If greater than 0, turn on parser debugging output (for expert only, depending on compilation options).

Incremented by the -d command line option. Set to the PYTHONDEBUG environment variable value.

Default: 0.

### int pathconfig\_warnings

If non-zero, calculation of path configuration is allowed to log warnings into stderr. If equals to 0, suppress these warnings.

Default: 1 in Python mode, 0 in isolated mode.

Part of the Python Path Configuration input.

Modifié dans la version 3.11 : Now also applies on Windows.

### wchar\_t \*prefix

The site-specific directory prefix where the platform independent Python files are installed: sys.prefix.

Default: NULL.

Part of the Python Path Configuration output.

### wchar\_t \*program\_name

Program name used to initialize executable and in early error messages during Python initialization.

- If Py\_SetProgramName() has been called, use its argument.
- On macOS, use PYTHONEXECUTABLE environment variable if set.
- If the WITH\_NEXT\_FRAMEWORK macro is defined, use \_\_\_PYVENV\_LAUNCHER\_\_ environment variable if set.
- Use argy [0] of argy if available and non-empty.
- Otherwise, use L"python" on Windows, or L"python3" on other platforms.

Default: NULL.

Part of the Python Path Configuration input.

### wchar\_t \*pycache\_prefix

Directory where cached .pyc files are written: sys.pycache\_prefix.

Set by the -X pycache\_prefix=PATH command line option and the PYTHONPYCACHEPREFIX environment variable.

If NULL, sys.pycache\_prefix is set to None.

Default: NULL.

#### int quiet

Quiet mode. If greater than 0, don't display the copyright and version at Python startup in interactive mode. Incremented by the -g command line option.

Default: 0.

#### wchar\_t \*run\_command

Value of the -c command line option.

Used by Py\_RunMain().

Default: NULL.

#### wchar\_t \*run\_filename

Filename passed on the command line: trailing command line argument without -c or -m. It is used by the Py RunMain() function.

For example, it is set to script.py by the python3 script.py arg command line.

See also the PyConfig.skip\_source\_first\_line option.

Default: NULL.

### wchar\_t \*run\_module

Value of the -m command line option.

Used by Py\_RunMain().

Default: NULL.

#### int show ref count

Show total reference count at exit?

Set to 1 by -X showrefcount command line option.

Need a debug build of Python (the Py\_REF\_DEBUG macro must be defined).

Default: 0.

### int site\_import

Import the site module at startup?

If equal to zero, disable the import of the module site and the site-dependent manipulations of sys.path that it entails.

Also disable these manipulations if the site module is explicitly imported later (call site.main() if you want them to be triggered).

Set to 0 by the -S command line option.

sys.flags.no\_site is set to the inverted value of site\_import.

Default: 1.

### int skip\_source\_first\_line

If non-zero, skip the first line of the <code>PyConfig.run\_filename</code> source.

It allows the usage of non-Unix forms of #! cmd. This is intended for a DOS specific hack only.

Set to 1 by the -x command line option.

Default: 0.

#### wchar\_t \*stdio\_encoding

#### wchar t\*stdio errors

Encoding and encoding errors of sys.stdin, sys.stdout and sys.stderr (but sys.stderr always uses "backslashreplace" error handler).

If Py\_SetStandardStreamEncoding() has been called, use its *error* and *errors* arguments if they are not NULL.

Use the PYTHONIOENCODING environment variable if it is non-empty.

#### Default encoding:

- "UTF-8" if PyPreConfig.utf8\_mode is non-zero.
- Otherwise, use the locale encoding.

Default error handler:

10.6. PyConfig 207

- On Windows: use "surrogateescape".
- "surrogateescape" if PyPreConfig.utf8\_mode is non-zero, or if the LC\_CTYPE locale is "C" or "POSIX".
- "strict" otherwise.

#### int tracemalloc

Enable tracemalloc?

If non-zero, call tracemalloc.start() at startup.

Set by -X tracemalloc=N command line option and by the PYTHONTRACEMALLOC environment variable.

Default: -1 in Python mode, 0 in isolated mode.

#### int use\_environment

Use environment variables?

If equals to zero, ignore the environment variables.

Set to 0 by the -E environment variable.

Default: 1 in Python config and 0 in isolated config.

### int user\_site\_directory

If non-zero, add the user site directory to sys.path.

Set to 0 by the -s and -I command line options.

Set to 0 by the PYTHONNOUSERSITE environment variable.

Default: 1 in Python mode, 0 in isolated mode.

#### int verbose

Verbose mode. If greater than 0, print a message each time a module is imported, showing the place (filename or built-in module) from which it is loaded.

If greater or equal to 2, print a message for each file that is checked for when searching for a module. Also provides information on module cleanup at exit.

Incremented by the -v command line option.

Set to the PYTHONVERBOSE environment variable value.

Default: 0.

### PyWideStringList warnoptions

Options of the warnings module to build warnings filters, lowest to highest priority : sys. warnoptions.

The warnings module adds sys.warnoptions in the reverse order: the last *PyConfig.warnoptions* item becomes the first item of warnings.filters which is checked first (highest priority)

The -W command line options adds its value to warnoptions, it can be used multiple times.

The PYTHONWARNINGS environment variable can also be used to add warning options. Multiple options can be specified, separated by commas (, ).

Default: empty list.

### int write\_bytecode

If equal to 0, Python won't try to write .pyc files on the import of source modules.

Set to 0 by the -B command line option and the PYTHONDONTWRITEBYTECODE environment variable.

sys.dont\_write\_bytecode is initialized to the inverted value of write\_bytecode.

Default: 1.

### PyWideStringList xoptions

Values of the -X command line options: sys.\_xoptions.

Default: empty list.

If parse\_argv is non-zero, argv arguments are parsed the same way the regular Python parses command line arguments, and Python arguments are stripped from argv.

The xoptions options are parsed to set other options : see the -X command line option.

Modifié dans la version 3.9 : The show\_alloc\_count field has been removed.

# 10.7 Initialization with PyConfig

Function to initialize Python:

```
PyStatus Py_InitializeFromConfig (const PyConfig *config)
```

Initialize Python from config configuration.

The caller is responsible to handle exceptions (error or exit) using PyStatus\_Exception() and Py\_ExitStatusException().

If PyImport\_FrozenModules(), PyImport\_AppendInittab() or PyImport\_ExtendInittab() are used, they must be set or called after Python preinitialization and before the Python initialization. If Python is initialized multiple times, PyImport\_AppendInittab() or PyImport\_ExtendInittab() must be called before each Python initialization.

The current configuration (PyConfig type) is stored in PyInterpreterState.config.

Example setting the program name:

```
void init_python(void)
   PyStatus status;
   PyConfig config;
   PyConfig_InitPythonConfig(&config);
    /* Set the program name. Implicitly preinitialize Python. */
   status = PyConfig_SetString(&config, &config.program_name,
                                L"/path/to/my_program");
    if (PyStatus_Exception(status)) {
        goto exception;
    status = Py_InitializeFromConfig(&config);
    if (PyStatus_Exception(status)) {
        goto exception;
   PyConfig_Clear(&config);
   return;
exception:
   PyConfig_Clear(&config);
    Py_ExitStatusException(status);
```

More complete example modifying the default configuration, read the configuration, and then override some parameters. Note that since 3.11, many parameters are not calculated until initialization, and so values cannot be read from the configuration structure. Any values set before initialize is called will be left unchanged by initialization:

```
PyStatus init_python(const char *program_name)
{
    PyStatus status;
```

(suite sur la page suivante)

(suite de la page précédente)

```
PyConfig config;
   PyConfig_InitPythonConfig(&config);
    /* Set the program name before reading the configuration
       (decode byte string from the locale encoding).
       Implicitly preinitialize Python. */
   status = PyConfig_SetBytesString(&config, &config.program_name,
                                     program_name);
   if (PyStatus_Exception(status)) {
       goto done;
   /* Read all configuration at once */
   status = PyConfig_Read(&config);
   if (PyStatus_Exception(status)) {
       goto done;
    /* Specify sys.path explicitly */
    /* If you want to modify the default set of paths, finish
       initialization first and then use PySys_GetObject("path") */
   config.module_search_paths_set = 1;
   status = PyWideStringList_Append(&config.module_search_paths,
                                     L"/path/to/stdlib");
   if (PyStatus_Exception(status)) {
       goto done;
    }
   status = PyWideStringList_Append(&config.module_search_paths,
                                     L"/path/to/more/modules");
   if (PyStatus_Exception(status)) {
       goto done;
    /* Override executable computed by PyConfig_Read() */
   status = PyConfig_SetString(&config, &config.executable,
                                L"/path/to/my_executable");
   if (PyStatus_Exception(status)) {
       goto done;
   status = Py_InitializeFromConfig(&config);
done:
   PyConfig_Clear(&config);
    return status;
```

# 10.8 Isolated Configuration

PyPreConfig\_InitIsolatedConfig() and PyConfig\_InitIsolatedConfig() functions create a configuration to isolate Python from the system. For example, to embed Python into an application.

This configuration ignores global configuration variables, environment variables, command line arguments (PyConfig. argv is not parsed) and user site directory. The C standard streams (ex:stdout) and the LC\_CTYPE locale are left unchanged. Signal handlers are not installed.

Configuration files are still used with this configuration to determine paths that are unspecified. Ensure PyConfig. home is specified to avoid computing the default path configuration.

# 10.9 Python Configuration

PyPreConfig\_InitPythonConfig() and PyConfig\_InitPythonConfig() functions create a configuration to build a customized Python which behaves as the regular Python.

Environments variables and command line arguments are used to configure Python, whereas global configuration variables are ignored.

This function enables C locale coercion (PEP 538) and Python UTF-8 Mode (PEP 540) depending on the LC\_CTYPE locale, PYTHONUTF8 and PYTHONCOERCECLOCALE environment variables.

# 10.10 Python Path Configuration

PyConfig contains multiple fields for the path configuration :

- Path configuration inputs :
  - PyConfig.home
  - PyConfig.platlibdir
  - PyConfig.pathconfig warnings
  - PyConfig.program name
  - PyConfig.pythonpath\_env
  - current working directory: to get absolute paths
  - PATH environment variable to get the program full path (from PyConfig.program\_name)
  - PYVENV LAUNCHER environment variable
  - (Windows only) Application paths in the registry under "SoftwarePythonPythonCoreX.YPythonPath" of HKEY CURRENT USER and HKEY LOCAL MACHINE (where X.Y is the Python version).
- Path configuration output fields:
  - PyConfig.base\_exec\_prefix
  - PyConfig.base\_executable
  - PyConfig.base\_prefix
  - PyConfig.exec\_prefix
  - PyConfig.executable
  - PyConfig.module\_search\_paths\_set, PyConfig.module\_search\_paths
  - PyConfig.prefix

If at least one "output field" is not set, Python calculates the path configuration to fill unset fields. If <code>module\_search\_paths\_set</code> is equal to 0, <code>module\_search\_paths</code> is overridden and <code>module\_search\_paths\_set</code> is set to 1.

It is possible to completely ignore the function calculating the default path configuration by setting explicitly all path configuration output fields listed above. A string is considered as set even if it is non-empty. module\_search\_paths

is considered as set if module\_search\_paths\_set is set to 1. In this case, module\_search\_paths will be used without modification.

Set pathconfig\_warnings to 0 to suppress warnings when calculating the path configuration (Unix only, Windows does not log any warning).

If base\_prefix or base\_exec\_prefix fields are not set, they inherit their value from prefix and exec prefix respectively.

Py RunMain() and Py Main() modify sys.path:

- If run\_filename is set and is a directory which contains a \_\_main\_\_.py script, prepend run\_filename to sys.path.
- If isolated is zero:
  - If run\_module is set, prepend the current directory to sys.path. Do nothing if the current directory cannot be read.
  - If run\_filename is set, prepend the directory of the filename to sys.path.
  - Otherwise, prepend an empty string to sys.path.

If <code>site\_import</code> is non-zero, <code>sys.path</code> can be modified by the <code>site</code> module. If <code>user\_site\_directory</code> is non-zero and the user's site-package directory exists, the <code>site</code> module appends the user's site-package directory to <code>sys.path</code>.

The following configuration files are used by the path configuration:

```
— pyvenv.cfg
```

- \_\_\_\_pth file (ex:python.\_pth)
- pybuilddir.txt (Unix only)

If a .\_pth file is present:

- Set isolated to 1.
- Set use environment to 0.
- Set site\_import to 0.
- Set safe\_path to 1.

The \_\_PYVENV\_LAUNCHER\_\_ environment variable is used to set PyConfig.base\_executable

# 10.11 Py\_RunMain()

int Py\_RunMain (void)

Execute the command (PyConfig.run\_command), the script (PyConfig.run\_filename) or the module (PyConfig.run\_module) specified on the command line or in the configuration.

By default and when if -i option is used, run the REPL.

Finally, finalizes Python and returns an exit status that can be passed to the exit () function.

See Python Configuration for an example of customized Python always running in isolated mode using Py\_RunMain().

# 10.12 Py\_GetArgcArgv()

```
void Py_GetArgcArgv (int *argc, wchar_t ***argv)
```

Get the original command line arguments, before Python modified them.

See also PyConfig.orig\_argv member.

# 10.13 Multi-Phase Initialization Private Provisional API

This section is a private provisional API introducing multi-phase initialization, the core feature of PEP 432:

- "Core" initialization phase, "bare minimum Python" :
  - Builtin types;
  - Builtin exceptions;
  - Builtin and frozen modules;
  - The sys module is only partially initialized (ex: sys.path doesn't exist yet).
- "Main" initialization phase, Python is fully initialized:
  - Install and configure importlib;
  - Apply the *Path Configuration*;
  - Install signal handlers;
  - Finish sys module initialization (ex: create sys.stdout and sys.path);
  - Enable optional features like faulthandler and tracemalloc;
  - Import the site module;
  - etc.

Private provisional API:

- PyConfig.\_init\_main: if set to 0, Py\_InitializeFromConfig() stops at the "Core" initialization phase.
- PyConfig.\_isolated\_interpreter: if non-zero, disallow threads, subprocesses and fork.

## PyStatus \_Py\_InitializeMain(void)

Move to the "Main" initialization phase, finish the Python initialization.

No module is imported during the "Core" phase and the importlib module is not configured: the *Path Configuration* is only applied during the "Main" phase. It may allow to customize Python in Python to override or tune the *Path Configuration*, maybe install a custom sys.meta\_path importer or an import hook, etc.

It may become possible to calculatin the *Path Configuration* in Python, after the Core phase and before the Main phase, which is one of the **PEP 432** motivation.

The "Core" phase is not properly defined: what should be and what should not be available at this phase is not specified yet. The API is marked as private and provisional: the API can be modified or even be removed anytime until a proper public API is designed.

Example running Python code between "Core" and "Main" initialization phases:

```
void init_python(void)
{
    PyStatus status;

    PyConfig config;
    PyConfig_InitPythonConfig(&config);
    config._init_main = 0;

    /* ... customize 'config' configuration ... */

    status = Py_InitializeFromConfig(&config);
    PyConfig_Clear(&config);
    if (PyStatus_Exception(status)) {
        Py_ExitStatusException(status);
    }

    /* Use sys.stderr because sys.stdout is only created
        by _Py_InitializeMain() */
    int res = PyRun_SimpleString(
        "import sys; "
```

(suite sur la page suivante)

(suite de la page précédente)

```
"print('Run Python code before _Py_InitializeMain', "
    "file=sys.stderr)");
if (res < 0) {
    exit(1);
}

/* ... put more configuration code here ... */

status = _Py_InitializeMain();
if (PyStatus_Exception(status)) {
    Py_ExitStatusException(status);
}</pre>
```

# CHAPITRE 11

Memory Management

# 11.1 Aperçu

Memory management in Python involves a private heap containing all Python objects and data structures. The management of this private heap is ensured internally by the *Python memory manager*. The Python memory manager has different components which deal with various dynamic storage management aspects, like sharing, segmentation, preallocation or caching.

At the lowest level, a raw memory allocator ensures that there is enough room in the private heap for storing all Python-related data by interacting with the memory manager of the operating system. On top of the raw memory allocator, several object-specific allocators operate on the same heap and implement distinct memory management policies adapted to the peculiarities of every object type. For example, integer objects are managed differently within the heap than strings, tuples or dictionaries because integers imply different storage requirements and speed/space tradeoffs. The Python memory manager thus delegates some of the work to the object-specific allocators, but ensures that the latter operate within the bounds of the private heap.

It is important to understand that the management of the Python heap is performed by the interpreter itself and that the user has no control over it, even if they regularly manipulate object pointers to memory blocks inside that heap. The allocation of heap space for Python objects and other internal buffers is performed on demand by the Python memory manager through the Python/C API functions listed in this document.

To avoid memory corruption, extension writers should never try to operate on Python objects with the functions exported by the C library:  $\mathtt{malloc}()$ ,  $\mathtt{calloc}()$ ,  $\mathtt{realloc}()$  and  $\mathtt{free}()$ . This will result in mixed calls between the C allocator and the Python memory manager with fatal consequences, because they implement different algorithms and operate on different heaps. However, one may safely allocate and release memory blocks with the C library allocator for individual purposes, as shown in the following example:

```
PyObject *res;
char *buf = (char *) malloc(BUFSIZ); /* for I/O */

if (buf == NULL)
    return PyErr_NoMemory();
...Do some I/O operation involving buf...
res = PyBytes_FromString(buf);
```

(suite sur la page suivante)

(suite de la page précédente)

```
free(buf); /* malloc'ed */
return res;
```

In this example, the memory request for the I/O buffer is handled by the C library allocator. The Python memory manager is involved only in the allocation of the bytes object returned as a result.

In most situations, however, it is recommended to allocate memory from the Python heap specifically because the latter is under control of the Python memory manager. For example, this is required when the interpreter is extended with new object types written in C. Another reason for using the Python heap is the desire to *inform* the Python memory manager about the memory needs of the extension module. Even when the requested memory is used exclusively for internal, highly specific purposes, delegating all memory requests to the Python memory manager causes the interpreter to have a more accurate image of its memory footprint as a whole. Consequently, under certain circumstances, the Python memory manager may or may not trigger appropriate actions, like garbage collection, memory compaction or other preventive procedures. Note that by using the C library allocator as shown in the previous example, the allocated memory for the I/O buffer escapes completely the Python memory manager.

#### Voir aussi:

The PYTHONMALLOC environment variable can be used to configure the memory allocators used by Python.

The PYTHONMALLOCSTATS environment variable can be used to print statistics of the *pymalloc memory allocator* every time a new pymalloc object arena is created, and on shutdown.

# 11.2 Allocator Domains

All allocating functions belong to one of three different "domains" (see also <code>PyMemAllocatorDomain</code>). These domains represent different allocation strategies and are optimized for different purposes. The specific details on how every domain allocates memory or what internal functions each domain calls is considered an implementation detail, but for debugging purposes a simplified table can be found at <code>here</code>. There is no hard requirement to use the memory returned by the allocation functions belonging to a given domain for only the purposes hinted by that domain (although this is the recommended practice). For example, one could use the memory returned by <code>PyMem\_RawMalloc()</code> for allocating Python objects or the memory returned by <code>PyObject\_Malloc()</code> for allocating memory for buffers.

The three allocation domains are:

- Raw domain: intended for allocating memory for general-purpose memory buffers where the allocation *must* go to the system allocator or where the allocator can operate without the *GIL*. The memory is requested directly to the system.
- "Mem" domain: intended for allocating memory for Python buffers and general-purpose memory buffers where the allocation must be performed with the *GIL* held. The memory is taken from the Python private heap.
- Object domain: intended for allocating memory belonging to Python objects. The memory is taken from the Python private heap.

When freeing memory previously allocated by the allocating functions belonging to a given domain, the matching specific deallocating functions must be used. For example,  $PyMem\_Free()$  must be used to free memory allocated using  $PyMem\_Malloc()$ .

# 11.3 Raw Memory Interface

The following function sets are wrappers to the system allocator. These functions are thread-safe, the GIL does not need to be held.

The *default raw memory allocator* uses the following functions: malloc(), calloc(), realloc() and free(); call malloc(1) (or calloc(1, 1)) when requesting zero bytes.

Nouveau dans la version 3.4.

## void \*PyMem\_RawMalloc (size\_t n)

Allocates n bytes and returns a pointer of type void\* to the allocated memory, or NULL if the request fails.

Requesting zero bytes returns a distinct non-NULL pointer if possible, as if PyMem\_RawMalloc(1) had been called instead. The memory will not have been initialized in any way.

## void \*PyMem\_RawCalloc (size\_t nelem, size\_t elsize)

Allocates *nelem* elements each whose size in bytes is *elsize* and returns a pointer of type void\* to the allocated memory, or NULL if the request fails. The memory is initialized to zeros.

Requesting zero elements or elements of size zero bytes returns a distinct non-NULL pointer if possible, as if PyMem\_RawCalloc(1, 1) had been called instead.

Nouveau dans la version 3.5.

## void \*PyMem\_RawRealloc (void \*p, size\_t n)

Resizes the memory block pointed to by p to n bytes. The contents will be unchanged to the minimum of the old and the new sizes.

If p is NULL, the call is equivalent to PyMem\_RawMalloc(n); else if n is equal to zero, the memory block is resized but is not freed, and the returned pointer is non-NULL.

Unless p is NULL, it must have been returned by a previous call to  $PyMem_RawMalloc()$ ,  $PyMem_RawRealloc()$  or  $PyMem_RawCalloc()$ .

If the request fails,  $PyMem_RawRealloc()$  returns NULL and p remains a valid pointer to the previous memory area.

## void PyMem\_RawFree (void \*p)

Frees the memory block pointed to by p, which must have been returned by a previous call to  $PyMem_RawMalloc()$ ,  $PyMem_RawRealloc()$  or  $PyMem_RawCalloc()$ . Otherwise, or if  $PyMem_RawFree(p)$  has been called before, undefined behavior occurs.

If p is NULL, no operation is performed.

# 11.4 Memory Interface

The following function sets, modeled after the ANSI C standard, but specifying behavior when requesting zero bytes, are available for allocating and releasing memory from the Python heap.

The default memory allocator uses the pymalloc memory allocator.

**Avertissement :** The *GIL* must be held when using these functions.

Modifié dans la version 3.6: The default allocator is now pymalloc instead of system malloc().

#### void \*PyMem Malloc (size t n)

*Part of the* Stable ABI. Allocates n bytes and returns a pointer of type void\* to the allocated memory, or NULL if the request fails.

Requesting zero bytes returns a distinct non-NULL pointer if possible, as if PyMem\_Malloc(1) had been called instead. The memory will not have been initialized in any way.

```
void *PyMem_Calloc (size_t nelem, size_t elsize)
```

Part of the Stable ABI since version 3.7. Allocates nelem elements each whose size in bytes is elsize and returns a pointer of type void\* to the allocated memory, or NULL if the request fails. The memory is initialized to zeros.

Requesting zero elements or elements of size zero bytes returns a distinct non-NULL pointer if possible, as if  $PyMem\_Calloc(1, 1)$  had been called instead.

Nouveau dans la version 3.5.

## void \*PyMem\_Realloc (void \*p, size\_t n)

Part of the Stable ABI. Resizes the memory block pointed to by p to n bytes. The contents will be unchanged to the minimum of the old and the new sizes.

If p is NULL, the call is equivalent to PyMem\_Malloc(n); else if n is equal to zero, the memory block is resized but is not freed, and the returned pointer is non-NULL.

Unless p is NULL, it must have been returned by a previous call to  $PyMem\_Malloc()$ ,  $PyMem\_Realloc()$  or  $PyMem\_Calloc()$ .

If the request fails,  $PyMem_Realloc()$  returns NULL and p remains a valid pointer to the previous memory area.

## void PyMem\_Free (void \*p)

Part of the Stable ABI. Frees the memory block pointed to by p, which must have been returned by a previous call to  $PyMem\_Malloc()$ ,  $PyMem\_Realloc()$  or  $PyMem\_Calloc()$ . Otherwise, or if  $PyMem\_Free(p)$  has been called before, undefined behavior occurs.

If p is NULL, no operation is performed.

The following type-oriented macros are provided for convenience. Note that TYPE refers to any C type.

# TYPE \*PyMem\_New (TYPE, size\_t n)

Same as <code>PyMem\_Malloc()</code>, but allocates (n \* sizeof(TYPE)) bytes of memory. Returns a pointer cast to <code>TYPE\*</code>. The memory will not have been initialized in any way.

# TYPE \*PyMem\_Resize (void \*p, TYPE, size\_t n)

Same as  $PyMem_Realloc()$ , but the memory block is resized to (n \* sizeof(TYPE)) bytes. Returns a pointer cast to TYPE\*. On return, p will be a pointer to the new memory area, or NULL in the event of failure.

This is a C preprocessor macro; p is always reassigned. Save the original value of p to avoid losing memory when handling errors.

## void PyMem\_Del (void \*p)

Same as PyMem\_Free().

In addition, the following macro sets are provided for calling the Python memory allocator directly, without involving the C API functions listed above. However, note that their use does not preserve binary compatibility across Python versions and is therefore deprecated in extension modules.

- PyMem\_MALLOC(size)
- PyMem\_NEW(type, size)
- PyMem\_REALLOC(ptr, size)
- PyMem\_RESIZE(ptr, type, size)
- PyMem\_FREE(ptr)
- PyMem\_DEL(ptr)

# 11.5 Object allocators

The following function sets, modeled after the ANSI C standard, but specifying behavior when requesting zero bytes, are available for allocating and releasing memory from the Python heap.

**Note:** There is no guarantee that the memory returned by these allocators can be successfully cast to a Python object when intercepting the allocating functions in this domain by the methods described in the *Customize Memory Allocators* section.

The default object allocator uses the pymalloc memory allocator.

**Avertissement:** The *GIL* must be held when using these functions.

#### void \*PyObject\_Malloc (size\_t n)

*Part of the* Stable ABI. Allocates n bytes and returns a pointer of type void\* to the allocated memory, or NULL if the request fails.

Requesting zero bytes returns a distinct non-NULL pointer if possible, as if PyObject\_Malloc(1) had been called instead. The memory will not have been initialized in any way.

# void \*PyObject\_Calloc (size\_t nelem, size\_t elsize)

Part of the Stable ABI since version 3.7. Allocates nelem elements each whose size in bytes is elsize and returns a pointer of type void\* to the allocated memory, or NULL if the request fails. The memory is initialized to zeros.

Requesting zero elements or elements of size zero bytes returns a distinct non-NULL pointer if possible, as if  $PyObject\_Calloc(1, 1)$  had been called instead.

Nouveau dans la version 3.5.

# void \*PyObject\_Realloc (void \*p, size\_t n)

Part of the Stable ABI. Resizes the memory block pointed to by p to n bytes. The contents will be unchanged to the minimum of the old and the new sizes.

If p is NULL, the call is equivalent to PyObject\_Malloc(n); else if n is equal to zero, the memory block is resized but is not freed, and the returned pointer is non-NULL.

Unless p is NULL, it must have been returned by a previous call to  $PyObject\_Malloc()$ ,  $PyObject\_Realloc()$  or  $PyObject\_Calloc()$ .

If the request fails,  $PyObject\_Realloc()$  returns NULL and p remains a valid pointer to the previous memory area.

### void PyObject\_Free (void \*p)

Part of the Stable ABI. Frees the memory block pointed to by p, which must have been returned by a previous call to  $PyObject\_Malloc()$ ,  $PyObject\_Realloc()$  or  $PyObject\_Calloc()$ . Otherwise, or if  $PyObject\_Free(p)$  has been called before, undefined behavior occurs.

If p is NULL, no operation is performed.

# 11.6 Default Memory Allocators

Default memory allocators:

Configuration	Nom	Py-	PyMem_Malloc	PyOb-
		Mem_RawMalloc		ject_Malloc
Release build	"pymalloc"	malloc	pymalloc	pymalloc
Debug build	"pymalloc_debug	"malloc + debug	pymalloc+de-	pymalloc+de-
			bug	bug
Release build, without py-	"malloc"	malloc	malloc	malloc
malloc				
Debug build, without py-	"malloc_debug"	malloc + debug	malloc + debug	malloc + debug
malloc				

## Legend:

- Name : value for PYTHONMALLOC environment variable.
- malloc: system allocators from the standard C library, C functions: malloc(), calloc(), realloc() and free().
- pymalloc: pymalloc memory allocator.
- "+ debug": with debug hooks on the Python memory allocators.
- "Debug build": Python build in debug mode.

# 11.7 Customize Memory Allocators

Nouveau dans la version 3.4.

## type PyMemAllocatorEx

Structure used to describe a memory block allocator. The structure has the following fields:

Champ	Signification
void *ctx	user context passed as first argument
<pre>void* malloc(void *ctx, size_t size)</pre>	allocate a memory block
<pre>void* calloc(void *ctx, size_t nelem, size_t</pre>	allocate a memory block initialized with
elsize)	zeros
<pre>void* realloc(void *ctx, void *ptr, size_t</pre>	allocate or resize a memory block
new_size)	
<pre>void free(void *ctx, void *ptr)</pre>	free a memory block

Modifié dans la version 3.5 : The PyMemAllocator structure was renamed to PyMemAllocatorEx and a new calloc field was added.

## type PyMemAllocatorDomain

Enum used to identify an allocator domain. Domains:

# PYMEM\_DOMAIN\_RAW

### Functions:

- PyMem\_RawMalloc()
- PyMem\_RawRealloc()
- PyMem\_RawCalloc()
- PyMem\_RawFree()

#### PYMEM DOMAIN MEM

#### Functions:

- PyMem\_Malloc(),
- PyMem\_Realloc()
- PyMem\_Calloc()
- PyMem\_Free()

#### PYMEM DOMAIN OBJ

### Functions:

— PyObject\_Malloc()— PyObject\_Realloc()— PyObject\_Calloc()— PyObject\_Free()

void PyMem\_GetAllocator (PyMemAllocatorDomain domain, PyMemAllocatorEx \*allocator)

Get the memory block allocator of the specified domain.

void PyMem\_SetAllocator (PyMemAllocatorDomain domain, PyMemAllocatorEx \*allocator)

Set the memory block allocator of the specified domain.

The new allocator must return a distinct non-NULL pointer when requesting zero bytes.

For the PYMEM\_DOMAIN\_RAW domain, the allocator must be thread-safe: the *GIL* is not held when the allocator is called.

If the new allocator is not a hook (does not call the previous allocator), the <code>PyMem\_SetupDebugHooks()</code> function must be called to reinstall the debug hooks on top on the new allocator.

See also PyPreConfig. allocator and Preinitialize Python with PyPreConfig.

## **Avertissement:** PyMem SetAllocator() does have the following contract:

- It can be called after  $Py\_PreInitialize()$  and before  $Py\_InitializeFromConfig()$  to install a custom memory allocator. There are no restrictions over the installed allocator other than the ones imposed by the domain (for instance, the Raw Domain allows the allocator to be called without the GIL held). See *the section on allocator domains* for more information.
- If called after Python has finish initializing (after Py\_InitializeFromConfig() has been called) the allocator **must** wrap the existing allocator. Substituting the current allocator for some other arbitrary one is **not supported**.

#### void PyMem SetupDebugHooks (void)

Setup debug hooks in the Python memory allocators to detect memory errors.

# 11.8 Debug hooks on the Python memory allocators

When Python is built in debug mode, the <code>PyMem\_SetupDebugHooks()</code> function is called at the <code>Python preinitialization</code> to setup debug hooks on Python memory allocators to detect memory errors.

The PYTHONMALLOC environment variable can be used to install debug hooks on a Python compiled in release mode (ex:PYTHONMALLOC=debug).

The <code>PyMem\_SetupDebugHooks()</code> function can be used to set debug hooks after calling <code>PyMem\_SetAllocator()</code>.

These debug hooks fill dynamically allocated memory blocks with special, recognizable bit patterns. Newly allocated memory is filled with the byte 0xCD (PYMEM\_CLEANBYTE), freed memory is filled with the byte 0xDD (PYMEM\_DEADBYTE). Memory blocks are surrounded by "forbidden bytes" filled with the byte 0xFD (PYMEM FORBIDDENBYTE). Strings of these bytes are unlikely to be valid addresses, floats, or ASCII strings.

### Runtime checks:

- Detect API violations. For example, detect if PyObject\_Free() is called on a memory block allocated by PyMem Malloc().
- Detect write before the start of the buffer (buffer underflow).
- Detect write after the end of the buffer (buffer overflow).
- Check that the *GIL* is held when allocator functions of PYMEM\_DOMAIN\_OBJ (ex: *PyObject\_Malloc()*) and PYMEM DOMAIN MEM (ex: *PyMem Malloc()*) domains are called.

On error, the debug hooks use the tracemalloc module to get the traceback where a memory block was allocated. The traceback is only displayed if tracemalloc is tracing Python memory allocations and the memory block was traced.

Let  $S = \mathtt{sizeof}(\mathtt{size\_t})$ . 2\*S bytes are added at each end of each block of N bytes requested. The memory layout is like so, where p represents the address returned by a malloc-like or realloc-like function (p[i:j] means the slice of bytes from \* (p+i) inclusive up to \* (p+j) exclusive; note that the treatment of negative indices differs from a Python slice):

p[-2\*S:-S] Number of bytes originally asked for. This is a size\_t, big-endian (easier to read in a memory dump).

```
p[-S] API identifier (ASCII character):
```

- 'r' for PYMEM\_DOMAIN\_RAW.
- 'm' for PYMEM\_DOMAIN\_MEM.
- 'o' for PYMEM\_DOMAIN\_OBJ.

p[-S+1:0] Copies of PYMEM\_FORBIDDENBYTE. Used to catch under- writes and reads.

p[0:N] The requested memory, filled with copies of PYMEM\_CLEANBYTE, used to catch reference to uninitialized memory. When a realloc-like function is called requesting a larger memory block, the new excess bytes are also filled with PYMEM\_CLEANBYTE. When a free-like function is called, these are overwritten with PYMEM\_DEADBYTE, to catch reference to freed memory. When a realloc-like function is called requesting a smaller memory block, the excess old bytes are also filled with PYMEM\_DEADBYTE.

p[N:N+S] Copies of PYMEM\_FORBIDDENBYTE. Used to catch over- writes and reads.

p[N+S:N+2\*S] Only used if the PYMEM\_DEBUG\_SERIALNO macro is defined (not defined by default).

A serial number, incremented by 1 on each call to a malloc-like or realloc-like function. Big-endian size\_t. If "bad memory" is detected later, the serial number gives an excellent way to set a breakpoint on the next run, to capture the instant at which this block was passed out. The static function bumpserialno() in obmalloc.c is the only place the serial number is incremented, and exists so you can set such a breakpoint easily.

A realloc-like or free-like function first checks that the PYMEM\_FORBIDDENBYTE bytes at each end are intact. If they've been altered, diagnostic output is written to stderr, and the program is aborted via Py\_FatalError(). The other main failure mode is provoking a memory error when a program reads up one of the special bit patterns and tries to use it as an address. If you get in a debugger then and look at the object, you're likely to see that it's entirely filled with PYMEM\_DEADBYTE (meaning freed memory is getting used) or PYMEM\_CLEANBYTE (meaning uninitialized memory is getting used).

Modifié dans la version 3.6 : The <code>PyMem\_SetupDebugHooks()</code> function now also works on Python compiled in release mode. On error, the debug hooks now use <code>tracemalloc</code> to get the traceback where a memory block was allocated. The debug hooks now also check if the GIL is held when functions of <code>PYMEM\_DOMAIN\_OBJ</code> and <code>PYMEM\_DOMAIN\_MEM</code> domains are called.

Modifié dans la version 3.8 : Byte patterns 0xCB (PYMEM\_CLEANBYTE), 0xDB (PYMEM\_DEADBYTE) and 0xFB (PYMEM\_FORBIDDENBYTE) have been replaced with 0xCD, 0xDD and 0xFD to use the same values than Windows CRT debug malloc() and free().

# 11.9 The pymalloc allocator

Python has a *pymalloc* allocator optimized for small objects (smaller or equal to 512 bytes) with a short lifetime. It uses memory mappings called "arenas" with a fixed size of 256 KiB. It falls back to  $PyMem_RawMalloc()$  and  $PyMem_RawRealloc()$  for allocations larger than 512 bytes.

pymalloc is the default allocator of the PYMEM\_DOMAIN\_MEM (ex: PyMem\_Malloc()) and PYMEM\_DOMAIN\_OBJ (ex: PyObject\_Malloc()) domains.

The arena allocator uses the following functions:

- VirtualAlloc() and VirtualFree() on Windows,
- mmap () and munmap () if available,
- malloc() and free() otherwise.

This allocator is disabled if Python is configured with the --without-pymalloc option. It can also be disabled at runtime using the PYTHONMALLOC environment variable (ex: PYTHONMALLOC=malloc).

# 11.9.1 Customize pymalloc Arena Allocator

Nouveau dans la version 3.4.

## type PyObjectArenaAllocator

Structure used to describe an arena allocator. The structure has three fields:

Champ	Signification
void *ctx	user context passed as first argument
<pre>void* alloc(void *ctx, size_t size)</pre>	allocate an arena of size bytes
<pre>void free(void *ctx, void *ptr, size_t size)</pre>	free an arena

# void PyObject\_GetArenaAllocator (PyObjectArenaAllocator \*allocator)

Get the arena allocator.

# void PyObject\_SetArenaAllocator (PyObjectArenaAllocator \*allocator)

Set the arena allocator.

# 11.10 tracemalloc C API

Nouveau dans la version 3.7.

int PyTraceMalloc\_Track (unsigned int domain, uintptr\_t ptr, size\_t size)

Track an allocated memory block in the tracemalloc module.

Return 0 on success, return -1 on error (failed to allocate memory to store the trace). Return -2 if tracemalloc is disabled.

If memory block is already tracked, update the existing trace.

### int PyTraceMalloc\_Untrack (unsigned int domain, uintptr\_t ptr)

Untrack an allocated memory block in the tracemalloc module. Do nothing if the block was not tracked.

Return -2 if tracemalloc is disabled, otherwise return 0.

# 11.11 Exemples

Here is the example from section *Aperçu*, rewritten so that the I/O buffer is allocated from the Python heap by using the first function set:

```
PyObject *res;
char *buf = (char *) PyMem_Malloc(BUFSIZ); /* for I/O */

if (buf == NULL)
    return PyErr_NoMemory();
/* ...Do some I/O operation involving buf... */
res = PyBytes_FromString(buf);
PyMem_Free(buf); /* allocated with PyMem_Malloc */
return res;
```

The same code using the type-oriented function set:

```
PyObject *res;
char *buf = PyMem_New(char, BUFSIZ); /* for I/O */

if (buf == NULL)
    return PyErr_NoMemory();
/* ...Do some I/O operation involving buf... */
res = PyBytes_FromString(buf);
PyMem_Del(buf); /* allocated with PyMem_New */
return res;
```

Note that in the two examples above, the buffer is always manipulated via functions belonging to the same set. Indeed, it is required to use the same memory API family for a given memory block, so that the risk of mixing different allocators is reduced to a minimum. The following code sequence contains two errors, one of which is labeled as *fatal* because it mixes two different allocators operating on different heaps.

```
char *buf1 = PyMem_New(char, BUFSIZ);
char *buf2 = (char *) malloc(BUFSIZ);
char *buf3 = (char *) PyMem_Malloc(BUFSIZ);
...
PyMem_Del(buf3); /* Wrong -- should be PyMem_Free() */
free(buf2); /* Right -- allocated via malloc() */
free(buf1); /* Fatal -- should be PyMem_Del() */
```

In addition to the functions aimed at handling raw memory blocks from the Python heap, objects in Python are allocated and released with <code>PyObject\_New()</code>, <code>PyObject\_NewVar()</code> and <code>PyObject\_Del()</code>.

These will be explained in the next chapter on defining and implementing new object types in C.

# Implémentation d'objets

Ce chapitre décrit les fonctions, types, et macros utilisées pour définir de nouveaux types d'objets.

# 12.1 Allouer des objets dans le tas

```
PyObject *_PyObject_New (PyTypeObject *type)
```

Return value: New reference.

PyVarObject \*\_PyObject\_NewVar (PyTypeObject \*type, Py\_ssize\_t size)

Return value: New reference.

PyObject \*PyObject\_Init (PyObject \*op, PyTypeObject \*type)

Return value: Borrowed reference. Part of the Stable ABI. Initialize a newly allocated object op with its type and initial reference. Returns the initialized object. If type indicates that the object participates in the cyclic garbage detector, it is added to the detector's set of observed objects. Other fields of the object are not affected.

PyVarObject \*PyObject\_InitVar (PyVarObject \*op, PyTypeObject \*type, Py\_ssize\_t size)

Return value : Borrowed reference. Part of the Stable ABI. Effectue les mêmes opérations que PyObject\_Init() fait, et initialise également l'information de la longueur pour un objet de taille variable.

TYPE \*PyObject\_New (TYPE, PyTypeObject \*type)

Return value : New reference. Alloue un nouvel objet Python en utilisant le type de structure C TYPE et l'objet Python type. Les champs non définis par l'en-tête de l'objet Python ne sont pas initialisés ; le compteur de la référence objet sera égal à un. La taille de l'allocation mémoire est déterminée par le champ tp\_basicsize de l'objet type.

TYPE \*PyObject\_NewVar (TYPE, PyTypeObject \*type, Py\_ssize\_t size)

Return value : New reference. Alloue un nouvel objet Python en utilisant le type de structure C TYPE et l'objet Python de type type. Les champs non définis par l'en-tête de l'objet Python ne sont pas initialisés. La mémoire allouée est suffisante pour la structure TYPE plus size champs de la taille donnée par le champ de type tp\_itemsize. Ceci est utile pour l'implémentation d'objets comme les n-uplets, qui sont capables de déterminer leur taille à la construction. Allouer les champs en même temps que l'objet diminue le nombre d'allocations, améliorant ainsi les performances.

## void PyObject\_Del (void \*op)

Libère la mémoire allouée à un objet utilisant  $PyObject_New()$  ou  $PyObject_NewVar()$ . Ceci est normalement appelé par le gestionnaire  $tp_dealloc$  spécifié dans le type d'objet. Les champs de l'objet ne doivent plus être accédés après cet appel puisque cet emplacement mémoire ne correspond plus à un objet Python valide.

## PyObject \_Py\_NoneStruct

Objet qui est visible en tant que None dans Python. Ne devrait être accessible uniquement en utilisant la macro  $Py\_None$ , qui évalue cet objet à un pointeur.

### Voir aussi:

PyModule\_Create () Allouer et créer des modules d'extension.

# 12.2 Common Object Structures

There are a large number of structures which are used in the definition of object types for Python. This section describes these structures and how they are used.

# 12.2.1 Base object types and macros

All Python objects ultimately share a small number of fields at the beginning of the object's representation in memory. These are represented by the PyObject and PyVarObject types, which are defined, in turn, by the expansions of some macros also used, whether directly or indirectly, in the definition of all other Python objects.

## type PyObject

Part of the Limited API. (Only some members are part of the stable ABI.) All object types are extensions of this type. This is a type which contains the information Python needs to treat a pointer to an object as an object. In a normal "release" build, it contains only the object's reference count and a pointer to the corresponding type object. Nothing is actually declared to be a PyObject, but every pointer to a Python object can be cast to a PyObject\*. Access to the members must be done by using the macros Py\_REFCNT and Py\_TYPE.

## type PyVarObject

Part of the Limited API. (Only some members are part of the stable ABI.) This is an extension of PyObject that adds the ob\_size field. This is only used for objects that have some notion of length. This type does not often appear in the Python/C API. Access to the members must be done by using the macros  $Py\_REFCNT$ ,  $Py\_TYPE$ , and  $Py\_SIZE$ .

#### PyObject HEAD

This is a macro used when declaring new types which represent objects without a varying length. The PyObject\_HEAD macro expands to :

```
PyObject ob_base;
```

See documentation of PyObject above.

# PyObject\_VAR\_HEAD

This is a macro used when declaring new types which represent objects with a length that varies from instance to instance. The PyObject\_VAR\_HEAD macro expands to :

```
PyVarObject ob_base;
```

See documentation of PyVarObject above.

## int **Py\_Is** (*PyObject* \*x, *PyObject* \*y)

Part of the Stable ABI since version 3.10. Test if the x object is the y object, the same as  $\times$  is y in Python.

Nouveau dans la version 3.10.

## int Py\_IsNone (PyObject \*x)

Part of the Stable ABI since version 3.10. Test if an object is the None singleton, the same as x is None in Python.

Nouveau dans la version 3.10.

## int Py\_IsTrue (PyObject \*x)

Part of the Stable ABI since version 3.10. Test if an object is the True singleton, the same as x is True in Python.

Nouveau dans la version 3.10.

## int Py\_IsFalse (PyObject \*x)

Part of the Stable ABI since version 3.10. Test if an object is the False singleton, the same as x is False in Python.

Nouveau dans la version 3.10.

## PyTypeObject \*Py\_TYPE (PyObject \*o)

Get the type of the Python object o.

Return a borrowed reference.

Use the  $Py\_SET\_TYPE$  () function to set an object type.

Modifié dans la version  $3.11: Py\_TYPE()$  is changed to an inline static function. The parameter type is no longer const PyObject\*.

# int **Py\_IS\_TYPE** (*PyObject* \*o, *PyTypeObject* \*type)

Return non-zero if the object o type is type. Return zero otherwise. Equivalent to: Py\_TYPE(o) == type.

Nouveau dans la version 3.9.

# void Py\_SET\_TYPE (PyObject \*o, PyTypeObject \*type)

Set the object o type to type.

Nouveau dans la version 3.9.

## Py\_ssize\_t Py\_REFCNT (PyObject \*o)

Get the reference count of the Python object o.

Use the Py\_SET\_REFCNT() function to set an object reference count.

Modifié dans la version 3.11 : The parameter type is no longer const PyObject\*.

Modifié dans la version 3.10 : Py\_REFCNT () is changed to the inline static function.

## void **Py\_SET\_REFCNT** (*PyObject* \*o, *Py\_ssize\_t* refcnt)

Set the object o reference counter to refent.

Nouveau dans la version 3.9.

# Py\_ssize\_t Py\_SIZE (PyVarObject \*o)

Get the size of the Python object o.

Use the Py\_SET\_SIZE() function to set an object size.

Modifié dans la version 3.11 : Py\_SIZE () is changed to an inline static function. The parameter type is no longer const PyVarObject\*.

# void Py\_SET\_SIZE (PyVarObject \*o, Py\_ssize\_t size)

Set the object o size to size.

Nouveau dans la version 3.9.

## PyObject\_HEAD\_INIT (type)

This is a macro which expands to initialization values for a new PyObject type. This macro expands to:

```
_PyObject_EXTRA_INIT
1, type,
```

## PyVarObject\_HEAD\_INIT (type, size)

This is a macro which expands to initialization values for a new <code>PyVarObject</code> type, including the <code>ob\_size</code> field. This macro expands to:

```
_PyObject_EXTRA_INIT
1, type, size,
```

# 12.2.2 Implementing functions and methods

# type PyCFunction

Part of the Stable ABI. Type of the functions used to implement most Python callables in C. Functions of this type take two PyObject\* parameters and return one such value. If the return value is NULL, an exception shall have been set. If not NULL, the return value is interpreted as the return value of the function as exposed in Python. The function must return a new reference.

The function signature is:

# type PyCFunctionWithKeywords

Part of the Stable ABI. Type of the functions used to implement Python callables in C with signature METH\_VARARGS | METH\_KEYWORDS. The function signature is:

# type \_PyCFunctionFast

Type of the functions used to implement Python callables in C with signature <code>METH\_FASTCALL</code>. The function signature is :

## type \_PyCFunctionFastWithKeywords

Type of the functions used to implement Python callables in C with signature <code>METH\_FASTCALL</code> | <code>METH\_KEYWORDS</code>. The function signature is :

## type PyCMethod

Type of the functions used to implement Python callables in C with signature METH\_METHOD | METH FASTCALL | METH KEYWORDS. The function signature is:

Nouveau dans la version 3.9.

## type PyMethodDef

Part of the Stable ABI (including all members). Structure used to describe a method of an extension type. This structure has four fields:

```
const char *ml_name
name of the method

PyCFunction ml_meth
pointer to the C implementation
int ml_flags
flags bits indicating how the call should be constructed
const char *ml_doc
```

points to the contents of the docstring

The ml\_meth is a C function pointer. The functions may be of different types, but they always return PyObject\*. If the function is not of the PyCFunction, the compiler will require a cast in the method table. Even though PyCFunction defines the first parameter as PyObject\*, it is common that the method implementation uses the specific C type of the self object.

The ml\_flags field is a bitfield which can include the following flags. The individual flags indicate either a calling convention or a binding convention.

There are these calling conventions:

## METH\_VARARGS

This is the typical calling convention, where the methods have the type PyCFunction. The function expects two PyObject\* values. The first one is the *self* object for methods; for module functions, it is the module object. The second parameter (often called *args*) is a tuple object representing all arguments. This parameter is typically processed using  $PyArg\_ParseTuple()$  or  $PyArg\_UnpackTuple()$ .

# METH\_VARARGS | METH\_KEYWORDS

Methods with these flags must be of type PyCFunctionWithKeywords. The function expects three parameters: self, args, kwargs where kwargs is a dictionary of all the keyword arguments or possibly NULL if there are no keyword arguments. The parameters are typically processed using  $PyArg\_ParseTupleAndKeywords$ ().

## METH\_FASTCALL

Fast calling convention supporting only positional arguments. The methods have the type  $\_PyCFunctionFast$ . The first parameter is self, the second parameter is a C array of PyObject\* values indicating the arguments and the third parameter is the number of arguments (the length of the array).

Nouveau dans la version 3.7.

Modifié dans la version 3.10 : METH\_FASTCALL is now part of the stable ABI.

### METH\_FASTCALL | METH\_KEYWORDS

Extension of <code>METH\_FASTCALL</code> supporting also keyword arguments, with methods of type <code>\_PyCFunctionFastWithKeywords</code>. Keyword arguments are passed the same way as in the <code>vector-call protocol</code>: there is an additional fourth <code>PyObject\*</code> parameter which is a tuple representing the names of the keyword arguments (which are guaranteed to be strings) or possibly <code>NULL</code> if there are no keywords. The values of the keyword arguments are stored in the <code>args</code> array, after the positional arguments.

Nouveau dans la version 3.7.

#### METH METHOD | METH FASTCALL | METH KEYWORDS

Extension of METH\_FASTCALL | METH\_KEYWORDS supporting the *defining class*, that is, the class that contains the method in question. The defining class might be a superclass of Py\_TYPE(self).

The method needs to be of type *PyCMethod*, the same as for METH\_FASTCALL | METH\_KEYWORDS with defining\_class argument added after self.

Nouveau dans la version 3.9.

## METH\_NOARGS

Methods without parameters don't need to check whether arguments are given if they are listed with the METH\_NOARGS flag. They need to be of type PyCFunction. The first parameter is typically named self and will hold a reference to the module or object instance. In all cases the second parameter will be NULL.

The function must have 2 parameters. Since the second parameter is unused, Py\_UNUSED can be used to prevent a compiler warning.

# METH\_O

Methods with a single object argument can be listed with the METH\_O flag, instead of invoking PyArg\_ParseTuple() with a "O" argument. They have the type PyCFunction, with the self parameter, and a PyObject\* parameter representing the single argument.

These two constants are not used to indicate the calling convention but the binding when use with methods of classes. These may not be used for functions defined for modules. At most one of these flags may be set for any given method.

## METH\_CLASS

The method will be passed the type object as the first parameter rather than an instance of the type. This is used to create *class methods*, similar to what is created when using the classmethod() built-in function.

### METH STATIC

The method will be passed NULL as the first parameter rather than an instance of the type. This is used to create *static methods*, similar to what is created when using the staticmethod() built-in function.

One other constant controls whether a method is loaded in place of another definition with the same method name.

### METH COEXIST

The method will be loaded in place of existing definitions. Without *METH\_COEXIST*, the default is to skip repeated definitions. Since slot wrappers are loaded before the method table, the existence of a *sq\_contains* slot, for example, would generate a wrapped method named \_\_contains\_\_ () and preclude the loading of a corresponding PyCFunction with the same name. With the flag defined, the PyCFunction will be loaded in place of the wrapper object and will co-exist with the slot. This is helpful because calls to PyCFunctions are optimized more than wrapper object calls.

# 12.2.3 Accessing attributes of extension types

### type PyMemberDef

Part of the Stable ABI (including all members). Structure which describes an attribute of a type which corresponds to a C struct member. Its fields are :

Champ	Type C	Signification	
name	const char *	name of the member	
type	int	the type of the member in the C struct	
offset	Py_ssize_t	the offset in bytes that the member is located on the type's object struct	
flags	int	flag bits indicating if the field should be read-only or writable	
doc	const char *	points to the contents of the docstring	

type can be one of many T macros corresponding to various C types. When the member is accessed in Python, it will be converted to the equivalent Python type.

Macro name	Type C
T_SHORT	short
T_INT	int
T_LONG	long
T_FLOAT	float
T_DOUBLE	double
T_STRING	const char *
T_OBJECT	PyObject *
T_OBJECT_EX	PyObject *
T_CHAR	char
T_BYTE	char
T_UBYTE	unsigned char
T_UINT	unsigned int
T_USHORT	unsigned short
T_ULONG	unsigned long
T_BOOL	char
T_LONGLONG	long long
T_ULONGLONG	unsigned long long
T_PYSSIZET	Py_ssize_t

 $T_OBJECT$  and  $T_OBJECT_EX$  differ in that  $T_OBJECT$  returns None if the member is NULL and  $T_OBJECT_EX$  raises an AttributeError. Try to use  $T_OBJECT_EX$  over  $T_OBJECT$  because  $T_OBJECT_EX$  handles use of the del statement on that attribute more correctly than  $T_OBJECT$ .

flags can be 0 for write and read access or READONLY for read-only access. Using T\_STRING for type implies READONLY. T\_STRING data is interpreted as UTF-8. Only T\_OBJECT and T\_OBJECT\_EX members can be deleted. (They are set to NULL).

Heap allocated types (created using PyType\_FromSpec() or similar), PyMemberDef may contain definitions for the special members \_\_dictoffset\_\_, \_\_weaklistoffset\_\_ and \_\_vectorcalloffset\_\_, corresponding to tp\_dictoffset, tp\_weaklistoffset and tp\_vectorcall\_offset in type objects. These must be defined with T PYSSIZET and READONLY, for example:

## PyObject \*PyMember\_GetOne (const char \*obj\_addr, struct PyMemberDef \*m)

Get an attribute belonging to the object at address  $obj\_addr$ . The attribute is described by PyMemberDef m. Returns NULL on error.

## int **PyMember\_SetOne** (char \*obj\_addr, struct *PyMemberDef* \*m, *PyObject* \*o)

Set an attribute belonging to the object at address *obj\_addr* to object o. The attribute to set is described by PyMemberDef m. Returns 0 if successful and a negative value on failure.

## type PyGetSetDef

Part of the Stable ABI (including all members). Structure to define property-like access for a type. See also description of the PyTypeObject.tp\_getset slot.

Champ	Type C	Signification
name	const char *	attribute name
get	getter	C function to get the attribute
set	setter	optional C function to set or delete the attribute, if omitted the attribute is readonly
doc	const char *	optional docstring
closure	void *	optional function pointer, providing additional data for getter and setter

The get function takes one PyObject\* parameter (the instance) and a function pointer (the associated closure):

```
typedef PyObject *(*getter)(PyObject *, void *);
```

It should return a new reference on success or NULL with a set exception on failure.

set functions take two PyObject\* parameters (the instance and the value to be set) and a function pointer (the associated closure):

```
typedef int (*setter)(PyObject *, PyObject *, void *);
```

In case the attribute should be deleted the second parameter is NULL. Should return 0 on success or -1 with a set exception on failure.

# 12.3 Objets type

Perhaps one of the most important structures of the Python object system is the structure that defines a new type: the PyTypeObject structure. Type objects can be handled using any of the  $PyObject_*$  or  $PyType_*$  functions, but do not offer much that's interesting to most Python applications. These objects are fundamental to how objects behave, so they are very important to the interpreter itself and to any extension module that implements new types.

Type objects are fairly large compared to most of the standard types. The reason for the size is that each type object stores a large number of values, mostly C function pointers, each of which implements a small part of the type's functionality. The fields of the type object are examined in detail in this section. The fields will be described in the order in which they occur in the structure.

In addition to the following quick reference, the *Exemples* section provides at-a-glance insight into the meaning and use of *PyTypeObject*.

## 12.3.1 Quick Reference

"tp slots"

PyTypeObject Slot <sup>page 233, 1</sup>	Туре	special methods/attrs	Info <sup>page</sup> 233, 2
			OTDI
<r> tp_name</r>	const char *	name	XX
tp_basicsize	Py_ssize_t		XXX
tp_itemsize	Py_ssize_t		XX
tp_dealloc	destructor		XXX
tp_vectorcall_offset	Py_ssize_t		XX
(tp_getattr)	getattrfunc	getattribute,getattr	G
(tp_setattr)	setattrfunc	setattr,delattr	G
tp_as_async	PyAsyncMethods*	sub-slots	%
tp_repr	reprfunc	repr	XXX
tp_as_number	PyNumberMethods*	sub-slots	%
tp_as_sequence	PySequenceMethods*	sub-slots	%
tp_as_mapping	PyMappingMethods*	sub-slots	%
tp_hash	hashfunc	hash	X G
tp_call	ternaryfunc	call	XX
tp_str	reprfunc	str	XX
tp_getattro	getattrofunc	getattribute,getattr	X X G

suite sur la page suivante

Tableau 1 - suite de la page précédente

PyTypeObject Slot <sup>page 233, 1</sup>	Type	special methods/attrs		Info <sup>page 233</sup> ,		
			Q	Т	DΙ	
tp_setattro	setattrofunc	setattr,delattr	X	X	G	
tp_as_buffer	PyBufferProcs*				%	
tp_flags	unsigned long		X	X	?	
tp_doc	const char *	doc	X	X		
tp_traverse	traverseproc			X	G	
tp_clear	inquiry			X	G	
tp_richcompare	richcmpfunc	lt,le,eq,ne, gt,ge	X		G	
tp_weaklistoffset	Py_ssize_t			X	?	
tp_iter	getiterfunc	iter			X	
tp_iternext	iternextfunc	next			X	
tp_methods	PyMethodDef[]		X	X		
tp_members	PyMemberDef[]			X		
tp_getset	PyGetSetDef[]		X	X		
tp_base	PyTypeObject*	base			X	
tp_dict	PyObject*	dict			?	
tp_descr_get	descrgetfunc	get			X	
tp_descr_set	descrsetfunc	set,delete			X	
tp_dictoffset	Py_ssize_t			X	?	
tp_init	initproc	init	X	X	X	
tp_alloc	allocfunc		X		? ?	
tp_new	newfunc	new	X	X	? ?	
tp_free	freefunc		X	X	? ?	
tp_is_gc	inquiry			X	X	
<tp_bases></tp_bases>	PyObject*	bases			~	
<tp_mro></tp_mro>	PyObject*	mro			~	
[tp_cache]	PyObject*					
[tp_subclasses]	PyObject*	subclasses				
[tp_weaklist]	PyObject*					
(tp_del)	destructor					
[tp_version_tag]	unsigned int					
tp_finalize	destructor	del			$\overline{X}$	
tp_vectorcall	vectorcallfunc				$\top$	

<sup>1. ():</sup> A slot name in parentheses indicates it is (effectively) deprecated.

Also see the inheritance column ("I").

"I": inheritance

12.3. Objets type 233

<sup>&</sup>lt;> : Names in angle brackets should be initially set to NULL and treated as read-only.

<sup>[]:</sup> Names in square brackets are for internal use only.

<sup>&</sup>lt;R> (as a prefix) means the field is required (must be non-NULL).

<sup>2.</sup> Columns:

<sup>&</sup>quot;O": set on PyBaseObject\_Type

<sup>&</sup>quot;T": set on PyType\_Type
"D": default (if slot is set to NULL)

X - PyType\_Ready sets this value if it is NULL

<sup>~ -</sup> PyType\_Ready always sets this value (it should be NULL)

<sup>? -</sup> PyType\_Ready may set this value depending on other slots

## sub-slots

Slot	Type	special methods
am_await	unaryfunc	await
am_aiter	unaryfunc	aiter
am_anext	unaryfunc	anext
am_send	sendfunc	
nb_add	binaryfunc	addradd
nb_inplace_add	binaryfunc	iadd
nb_subtract	binaryfunc	subrsub
nb_inplace_subtract	binaryfunc	isub
nb_multiply	binaryfunc	mulrmul
nb_inplace_multiply	binaryfunc	imul
nb_remainder	binaryfunc	modrmod
nb_inplace_remainder	binaryfunc	imod
nb_divmod	binaryfunc	divmodrdiv-
		mod
nb_power	ternaryfunc	powrpow
nb_inplace_power	ternaryfunc	ipow
nb_negative	unaryfunc	neg
nb_positive	unaryfunc	pos
nb_absolute	unaryfunc	abs
nb_bool	inquiry	bool
nb_invert	unaryfunc	invert
nb_lshift	binaryfunc	lshiftrlshift
nb_inplace_lshift	binaryfunc	ilshift
nb_rshift	binaryfunc	rshiftrrshift
nb_inplace_rshift	binaryfunc	irshift
nb_and	binaryfunc	andrand
nb_inplace_and	binaryfunc	iand
nb_xor	binaryfunc	xorrxor
nb_inplace_xor	binaryfunc	ixor
nb_or	binaryfunc	orror
nb_inplace_or	binaryfunc	ior
nb_int	unaryfunc	int
nb_reserved	void *	
nb_float	unaryfunc	float

suite sur la page suivante

Note that some slots are effectively inherited through the normal attribute lookup chain.

X - type slot is inherited via \*PyType\_Ready\* if defined with a \*NULL\* value

 $<sup>\</sup>mbox{\ensuremath{\$}}$  - the slots of the sub-struct are inherited individually

G - inherited, but only in combination with other slots; see the slot's description

<sup>? -</sup> it's complicated; see the slot's description

# Tableau 2 - suite de la page précédente

Slot	Type	special methods
nb_floor_divide	binaryfunc	floordiv
nb_inplace_floor_divide	binaryfunc	ifloordiv
nb_true_divide	binaryfunc	truediv
nb_inplace_true_divide	binaryfunc	itruediv
nb_index	unaryfunc	index
nb_matrix_multiply	binaryfunc	matmulrmat-
		mul
nb_inplace_matrix_multiply	binaryfunc	imatmul
	•	
mp_length	lenfunc	len
mp_subscript	binaryfunc	getitem
mp_ass_subscript	objobjargproc	setitem,deli-
		tem
	·	
sq_length	lenfunc	len
sq_concat	binaryfunc	add
sq_repeat	ssizeargfunc	mul
sq_item	ssizeargfunc	getitem
sq_ass_item	ssizeobjargproc	setitemdeli-
		tem
sq_contains	objobjproc	contains
sq_inplace_concat	binaryfunc	iadd
sq_inplace_repeat	ssizeargfunc	imul
bf_getbuffer	getbufferproc()	
bf_releasebuffer	releasebufferproc()	

12.3. Objets type 235

# slot typedefs

typedef	Parameter Types	Return Type
allocfunc		PyObject*
	PyTypeObject*	
	Py_ssize_t	
destructor	void *	void
freefunc	void *	void
traverseproc		int
	void *	
	visitproc	
	void *	
	void	
newfunc		PyObject*
iic w i aiic		1 400 3000
	PyObject*	
	PyObject*	
	PyObject *	
initproc		int
	D-07 '	
	PyObject*	
	PyObject*	
	PyObject*	
reprfunc	PyObject*	PyObject*
getattrfunc		PyObject*
	PyObject*	
	const char *	
	Colist Chai	
setattrfunc		int
occure France		
	PyObject *	
	const char *	
	PyObject*	
getattrofunc		PyObject*
	Dr. Ob +	
	PyObject*	
	PyObject*	
		:4
setattrofunc		int
	PyObject *	
	PyObject*	
	PyObject*	
	1,00,000	
descrgetfunc		PyObject*
		1 400 1000
	PyObject *	
	PyObject*	
	PyObject*	
36		Chanitre 12 Implémentation d'obje
descrsetfunc		Chapitre 12. Implémentation d'obje
	D	
	PyObject*	
	1 Dr.Ob - a - + *	1

PyObject \*

See *Slot Type typedefs* below for more detail.

# 12.3.2 PyTypeObject Definition

The structure definition for PyTypeObject can be found in Include/object.h. For convenience of reference, this repeats the definition found there:

```
typedef struct _typeobject {
   PyObject_VAR_HEAD
   const char *tp_name; /* For printing, in format "<module>.<name>" */
   Py_ssize_t tp_basicsize, tp_itemsize; /* For allocation */
   /* Methods to implement standard operations */
   destructor tp_dealloc;
   Py_ssize_t tp_vectorcall_offset;
   getattrfunc tp_getattr;
   setattrfunc tp_setattr;
   PyAsyncMethods *tp_as_async; /* formerly known as tp_compare (Python 2)
                                    or tp_reserved (Python 3) */
   reprfunc tp_repr;
   /* Method suites for standard classes */
   PyNumberMethods *tp_as_number;
   PySequenceMethods *tp_as_sequence;
   PyMappingMethods *tp_as_mapping;
   /* More standard operations (here for binary compatibility) */
   hashfunc tp_hash;
   ternaryfunc tp_call;
   reprfunc tp_str;
   getattrofunc tp_getattro;
   setattrofunc tp_setattro;
   /* Functions to access object as input/output buffer */
   PyBufferProcs *tp_as_buffer;
   /* Flags to define presence of optional/expanded features */
   unsigned long tp_flags;
   const char *tp_doc; /* Documentation string */
   /* Assigned meaning in release 2.0 */
   /* call function for all accessible objects */
   traverseproc tp_traverse;
   /* delete references to contained objects */
   inquiry tp_clear;
   /* Assigned meaning in release 2.1 */
   /* rich comparisons */
   richcmpfunc tp_richcompare;
   /* weak reference enabler */
   Py_ssize_t tp_weaklistoffset;
```

(suite sur la page suivante)

12.3. Objets type 237

(suite de la page précédente)

```
/* Iterators */
   getiterfunc tp_iter;
   iternextfunc tp_iternext;
   /* Attribute descriptor and subclassing stuff */
   struct PyMethodDef *tp_methods;
   struct PyMemberDef *tp_members;
   struct PyGetSetDef *tp_getset;
   // Strong reference on a heap type, borrowed reference on a static type
   struct _typeobject *tp_base;
   PyObject *tp_dict;
   descrgetfunc tp_descr_get;
   descrsetfunc tp_descr_set;
   Py_ssize_t tp_dictoffset;
   initproc tp_init;
   allocfunc tp_alloc;
   newfunc tp_new;
   freefunc tp_free; /* Low-level free-memory routine */
   inquiry tp_is_qc; /* For PyObject_IS_GC */
   PyObject *tp_bases;
   PyObject *tp_mro; /* method resolution order */
   PyObject *tp_cache;
   PyObject *tp_subclasses;
   PyObject *tp_weaklist;
   destructor tp_del;
   /* Type attribute cache version tag. Added in version 2.6 */
   unsigned int tp_version_tag;
   destructor tp_finalize;
   vectorcallfunc tp_vectorcall;
} PyTypeObject;
```

# 12.3.3 PyObject Slots

The type object structure extends the PyVarObject structure. The ob\_size field is used for dynamic types (created by type\_new(), usually called from a class statement). Note that  $PyType_Type$  (the metatype) initializes  $tp\_itemsize$ , which means that its instances (i.e. type objects) *must* have the ob\_size field.

```
Py_ssize_t PyObject.ob_refcnt
```

Part of the Stable ABI. This is the type object's reference count, initialized to 1 by the PyObject\_HEAD\_INIT macro. Note that for *statically allocated type objects*, the type's instances (objects whose ob\_type points back to the type) do *not* count as references. But for *dynamically allocated type objects*, the instances *do* count as references.

## **Inheritance:**

This field is not inherited by subtypes.

# PyTypeObject \*PyObject.ob\_type

Part of the Stable ABI. This is the type's type, in other words its metatype. It is initialized by the argument to the PyObject\_HEAD\_INIT macro, and its value should normally be &PyType\_Type. However, for dynamically loadable extension modules that must be usable on Windows (at least), the compiler complains that this is not a valid initializer. Therefore, the convention is to pass NULL to the PyObject\_HEAD\_INIT macro and to initialize this field explicitly at the start of the module's initialization function, before doing anything else. This is typically done like this:

```
Foo_Type.ob_type = &PyType_Type;
```

This should be done before any instances of the type are created.  $PyType\_Ready()$  checks if ob\_type is NULL, and if so, initializes it to the ob\_type field of the base class.  $PyType\_Ready()$  will not change this field if it is non-zero.

#### Inheritance:

This field is inherited by subtypes.

```
PyObject *PyObject._ob_next
PyObject *PyObject._ob_prev
```

These fields are only present when the macro Py\_TRACE\_REFS is defined (see the configure --with-trace-refs option).

Their initialization to NULL is taken care of by the PyObject\_HEAD\_INIT macro. For *statically allocated objects*, these fields always remain NULL. For *dynamically allocated objects*, these two fields are used to link the object into a doubly linked list of *all* live objects on the heap.

This could be used for various debugging purposes; currently the only uses are the sys.getobjects() function and to print the objects that are still alive at the end of a run when the environment variable PYTHONDUMPREFS is set.

#### Inheritance:

These fields are not inherited by subtypes.

# 12.3.4 PyVarObject Slots

```
Py_ssize_t PyVarObject.ob_size
```

Part of the Stable ABI. For statically allocated type objects, this should be initialized to zero. For dynamically allocated type objects, this field has a special internal meaning.

#### Inheritance:

This field is not inherited by subtypes.

# 12.3.5 PyTypeObject Slots

Each slot has a section describing inheritance. If  $PyType\_Ready()$  may set a value when the field is set to NULL then there will also be a "Default" section. (Note that many fields set on  $PyBaseObject\_Type$  and  $PyType\_Type$  effectively act as defaults.)

```
const char *PyTypeObject.tp_name
```

Pointer to a NUL-terminated string containing the name of the type. For types that are accessible as module globals, the string should be the full module name, followed by a dot, followed by the type name; for built-in types, it should be just the type name. If the module is a submodule of a package, the full package name is part of the full module name. For example, a type named T defined in module M in subpackage Q in package P should have the  $tp\_name$  initializer "P.Q.M.T".

For *dynamically allocated type objects*, this should just be the type name, and the module name explicitly stored in the type dict as the value for key '\_\_module\_\_'.

For *statically allocated type objects*, the *tp\_name* field should contain a dot. Everything before the last dot is made accessible as the \_\_module\_\_ attribute, and everything after the last dot is made accessible as the \_\_name\_\_ attribute.

If no dot is present, the entire <code>tp\_name</code> field is made accessible as the <code>\_\_name\_\_</code> attribute, and the <code>\_\_module\_\_</code> attribute is undefined (unless explicitly set in the dictionary, as explained above). This means your type will be impossible to pickle. Additionally, it will not be listed in module documentations created with pydoc. This field must not be <code>NULL</code>. It is the only required field in <code>PyTypeObject()</code> (other than potentially <code>tp\_itemsize()</code>.

12.3. Objets type 239

### **Inheritance:**

This field is not inherited by subtypes.

```
Py_ssize_t PyTypeObject.tp_basicsize
Py_ssize_t PyTypeObject.tp_itemsize
```

These fields allow calculating the size in bytes of instances of the type.

There are two kinds of types: types with fixed-length instances have a zero  $tp\_itemsize$  field, types with variable-length instances have a non-zero  $tp\_itemsize$  field. For a type with fixed-length instances, all instances have the same size, given in  $tp\_basicsize$ .

For a type with variable-length instances, the instances must have an ob\_size field, and the instance size is  $tp\_basicsize$  plus N times  $tp\_itemsize$ , where N is the "length" of the object. The value of N is typically stored in the instance's ob\_size field. There are exceptions: for example, into use a negative ob\_size to indicate a negative number, and N is abs (ob\_size) there. Also, the presence of an ob\_size field in the instance layout doesn't mean that the instance structure is variable-length (for example, the structure for the list type has fixed-length instances, yet those instances have a meaningful ob\_size field).

The basic size includes the fields in the instance declared by the macro <code>PyObject\_HEAD</code> or <code>PyObject\_VAR\_HEAD</code> (whichever is used to declare the instance struct) and this in turn includes the <code>\_ob\_prev</code> and <code>\_ob\_next</code> fields if they are present. This means that the only correct way to get an initializer for the <code>tp\_basicsize</code> is to use the <code>sizeof</code> operator on the struct used to declare the instance layout. The basic size does not include the GC header size.

A note about alignment: if the variable items require a particular alignment, this should be taken care of by the value of  $tp\_basicsize$ . Example: suppose a type implements an array of double.  $tp\_itemsize$  is sizeof(double). It is the programmer's responsibility that  $tp\_basicsize$  is a multiple of sizeof(double) (assuming this is the alignment requirement for double).

For any type with variable-length instances, this field must not be NULL.

## **Inheritance:**

These fields are inherited separately by subtypes. If the base type has a non-zero  $tp\_itemsize$ , it is generally not safe to set  $tp\_itemsize$  to a different non-zero value in a subtype (though this depends on the implementation of the base type).

```
destructor PyTypeObject.tp_dealloc
```

A pointer to the instance destructor function. This function must be defined unless the type guarantees that its instances will never be deallocated (as is the case for the singletons <code>None</code> and <code>Ellipsis</code>). The function signature is:

```
void tp_dealloc(PyObject *self);
```

The destructor function is called by the  $Py\_DECREF()$  and  $Py\_XDECREF()$  macros when the new reference count is zero. At this point, the instance is still in existence, but there are no references to it. The destructor function should free all references which the instance owns, free all memory buffers owned by the instance (using the freeing function corresponding to the allocation function used to allocate the buffer), and call the type's  $tp\_free$  function. If the type is not subtypable (doesn't have the  $Py\_TPFLAGS\_BASETYPE$  flag bit set), it is permissible to call the object deallocator directly instead of via  $tp\_free$ . The object deallocator should be the one used to allocate the instance; this is normally  $PyObject\_Del()$  if the instance was allocated using  $PyObject\_New()$  or  $PyObject\_VarNew()$ , or  $PyObject\_GC\_Del()$  if the instance was allocated using  $PyObject\_GC\_New()$  or  $PyObject\_GC\_NewVar()$ .

If the type supports garbage collection (has the  $Py\_TPFLAGS\_HAVE\_GC$  flag bit set), the destructor should call  $PyObject\_GC\_UnTrack$  () before clearing any member fields.

```
static void foo_dealloc(foo_object *self) {
    PyObject_GC_UnTrack(self);
    Py_CLEAR(self->ref);
    Py_TYPE(self)->tp_free((PyObject *)self);
}
```

Finally, if the type is heap allocated ( $Py\_TPFLAGS\_HEAPTYPE$ ), the deallocator should decrement the reference count for its type object after calling the type deallocator. In order to avoid dangling pointers, the recommended way to achieve this is:

```
static void foo_dealloc(foo_object *self) {
    PyTypeObject *tp = Py_TYPE(self);
    // free references and buffers here
    tp->tp_free(self);
    Py_DECREF(tp);
}
```

#### Inheritance:

This field is inherited by subtypes.

## Py\_ssize\_t PyTypeObject.tp\_vectorcall\_offset

An optional offset to a per-instance function that implements calling the object using the *vectorcall protocol*, a more efficient alternative of the simpler  $tp\_call$ .

This field is only used if the flag Py\_TPFLAGS\_HAVE\_VECTORCALL is set. If so, this must be a positive integer containing the offset in the instance of a vectorcallfunc pointer.

The *vectorcallfunc* pointer may be NULL, in which case the instance behaves as if  $Py\_TPFLAGS\_HAVE\_VECTORCALL$  was not set: calling the instance falls back to  $tp\_call$ .

Any class that sets Py\_TPFLAGS\_HAVE\_VECTORCALL must also set  $tp\_call$  and make sure its behaviour is consistent with the *vectorcallfunc* function. This can be done by setting  $tp\_call$  to  $PyVectorcall\_Call$  ().

**Avertissement:** It is not recommended for *mutable heap types* to implement the vectorcall protocol. When a user sets \_\_call\_\_ in Python code, only *tp\_call* is updated, likely making it inconsistent with the vectorcall function.

Modifié dans la version 3.8 : Before version 3.8, this slot was named tp\_print. In Python 2.x, it was used for printing to a file. In Python 3.0 to 3.7, it was unused.

## **Inheritance:**

This field is always inherited. However, the  $Py\_TPFLAGS\_HAVE\_VECTORCALL$  flag is not always inherited. If it's not, then the subclass won't use vectorcall, except when  $PyVectorcall\_Call$  () is explicitly called. This is in particular the case for types without the  $Py\_TPFLAGS\_IMMUTABLETYPE$  flag set (including subclasses defined in Python).

### getattrfunc PyTypeObject.tp\_getattr

An optional pointer to the get-attribute-string function.

This field is deprecated. When it is defined, it should point to a function that acts the same as the  $tp\_getattro$  function, but taking a C string instead of a Python string object to give the attribute name.

### **Inheritance:**

```
Group:tp_getattr,tp_getattro
```

This field is inherited by subtypes together with  $tp\_getattro$ : a subtype inherits both  $tp\_getattr$  and  $tp\_getattro$  from its base type when the subtype's  $tp\_getattr$  and  $tp\_getattro$  are both NULL.

```
setattrfunc PyTypeObject.tp_setattr
```

An optional pointer to the function for setting and deleting attributes.

This field is deprecated. When it is defined, it should point to a function that acts the same as the  $tp\_setattro$  function, but taking a C string instead of a Python string object to give the attribute name.

## **Inheritance:**

```
Group:tp_setattr,tp_setattro
```

This field is inherited by subtypes together with  $tp\_setattro$ : a subtype inherits both  $tp\_setattr$  and  $tp\_setattro$  from its base type when the subtype's  $tp\_setattr$  and  $tp\_setattro$  are both NULL.

12.3. Objets type 241

## PyAsyncMethods \*PyTypeObject.tp\_as\_async

Pointer to an additional structure that contains fields relevant only to objects which implement *awaitable* and *asynchronous iterator* protocols at the C-level. See *Async Object Structures* for details.

Nouveau dans la version 3.5 : Formerly known as tp\_compare and tp\_reserved.

#### **Inheritance:**

The tp\_as\_async field is not inherited, but the contained fields are inherited individually.

## reprfunc PyTypeObject.tp\_repr

An optional pointer to a function that implements the built-in function repr ().

The signature is the same as for PyObject\_Repr():

```
PyObject *tp_repr(PyObject *self);
```

The function must return a string or a Unicode object. Ideally, this function should return a string that, when passed to eval(), given a suitable environment, returns an object with the same value. If this is not feasible, it should return a string starting with '<' and ending with '>' from which both the type and the value of the object can be deduced.

#### Inheritance:

This field is inherited by subtypes.

#### Default:

When this field is not set, a string of the form <%s object at %p> is returned, where %s is replaced by the type name, and %p by the object's memory address.

## PyNumberMethods \*PyTypeObject.tp\_as\_number

Pointer to an additional structure that contains fields relevant only to objects which implement the number protocol. These fields are documented in *Number Object Structures*.

#### **Inheritance:**

The tp as number field is not inherited, but the contained fields are inherited individually.

### *PySequenceMethods* \**PyTypeObject*.**tp\_as\_sequence**

Pointer to an additional structure that contains fields relevant only to objects which implement the sequence protocol. These fields are documented in *Sequence Object Structures*.

#### **Inheritance:**

The  $tp\_as\_sequence$  field is not inherited, but the contained fields are inherited individually.

# PyMappingMethods \*PyTypeObject.tp\_as\_mapping

Pointer to an additional structure that contains fields relevant only to objects which implement the mapping protocol. These fields are documented in *Mapping Object Structures*.

# Inheritance:

The tp\_as\_mapping field is not inherited, but the contained fields are inherited individually.

## hashfunc PyTypeObject.tp\_hash

An optional pointer to a function that implements the built-in function hash ().

The signature is the same as for PyObject Hash():

```
Py_hash_t tp_hash(PyObject *);
```

The value -1 should not be returned as a normal return value; when an error occurs during the computation of the hash value, the function should set an exception and return -1.

When this field is not set (and tp\_richcompare is not set), an attempt to take the hash of the object raises TypeError. This is the same as setting it to  $PyObject\_HashNotImplemented()$ .

This field can be set explicitly to  $PyObject\_HashNotImplemented()$  to block inheritance of the hash method from a parent type. This is interpreted as the equivalent of  $\_$ hash $\_$  = None at the Python level, causing isinstance(o, collections.Hashable) to correctly return False. Note that the converse

is also true - setting \_\_hash\_\_ = None on a class at the Python level will result in the  $tp_hash$  slot being set to  $PyObject_HashNotImplemented()$ .

### **Inheritance:**

Group:tp\_hash,tp\_richcompare

This field is inherited by subtypes together with  $tp\_richcompare$ : a subtype inherits both of  $tp\_richcompare$  and  $tp\_hash$ , when the subtype's  $tp\_richcompare$  and  $tp\_hash$  are both NULL.

```
ternaryfunc PyTypeObject.tp_call
```

An optional pointer to a function that implements calling the object. This should be NULL if the object is not callable. The signature is the same as for PyObject Call():

```
PyObject *tp_call(PyObject *self, PyObject *args, PyObject *kwargs);
```

#### Inheritance:

This field is inherited by subtypes.

```
reprfunc PyTypeObject.tp_str
```

An optional pointer to a function that implements the built-in operation str(). (Note that str is a type now, and str() calls the constructor for that type. This constructor calls  $PyObject\_Str()$  to do the actual work, and  $PyObject\_Str()$  will call this handler.)

The signature is the same as for PyObject\_Str():

```
PyObject *tp_str(PyObject *self);
```

The function must return a string or a Unicode object. It should be a "friendly" string representation of the object, as this is the representation that will be used, among other things, by the print () function.

### **Inheritance:**

This field is inherited by subtypes.

## **Default:**

When this field is not set, PyObject\_Repr() is called to return a string representation.

```
getattrofunc PyTypeObject.tp_getattro
```

An optional pointer to the get-attribute function.

The signature is the same as for PyObject\_GetAttr():

```
PyObject *tp_getattro(PyObject *self, PyObject *attr);
```

It is usually convenient to set this field to  $PyObject\_GenericGetAttr()$ , which implements the normal way of looking for object attributes.

### **Inheritance:**

Group:tp\_getattr,tp\_getattro

This field is inherited by subtypes together with  $tp\_getattr$ : a subtype inherits both  $tp\_getattr$  and  $tp\_getattr$  from its base type when the subtype's  $tp\_getattr$  and  $tp\_getattr$  are both NULL.

### Default:

 ${\tt PyBaseObject\_Type} \ {\tt uses} \ {\tt PyObject\_GenericGetAttr()}.$ 

```
setattrofunc PyTypeObject.tp_setattro
```

An optional pointer to the function for setting and deleting attributes.

The signature is the same as for PyObject SetAttr():

```
int tp_setattro(PyObject *self, PyObject *attr, PyObject *value);
```

In addition, setting *value* to NULL to delete an attribute must be supported. It is usually convenient to set this field to PyObject\_GenericSetAttr(), which implements the normal way of setting object attributes.

Inheritance:

12.3. Objets type 243

```
Group:tp_setattr,tp_setattro
```

This field is inherited by subtypes together with  $tp\_setattr$ : a subtype inherits both  $tp\_setattr$  and  $tp\_setattro$  from its base type when the subtype's  $tp\_setattr$  and  $tp\_setattro$  are both NULL.

### **Default:**

PyBaseObject\_Type uses PyObject\_GenericSetAttr().

# PyBufferProcs \*PyTypeObject.tp\_as\_buffer

Pointer to an additional structure that contains fields relevant only to objects which implement the buffer interface. These fields are documented in *Buffer Object Structures*.

#### **Inheritance:**

The tp as buffer field is not inherited, but the contained fields are inherited individually.

## unsigned long PyTypeObject.tp\_flags

This field is a bit mask of various flags. Some flags indicate variant semantics for certain situations; others are used to indicate that certain fields in the type object (or in the extension structures referenced via  $tp\_as\_number$ ,  $tp\_as\_sequence$ ,  $tp\_as\_mapping$ , and  $tp\_as\_buffer$ ) that were historically not always present are valid; if such a flag bit is clear, the type fields it guards must not be accessed and must be considered to have a zero or NULL value instead.

#### Inheritance:

Inheritance of this field is complicated. Most flag bits are inherited individually, i.e. if the base type has a flag bit set, the subtype inherits this flag bit. The flag bits that pertain to extension structures are strictly inherited if the extension structure is inherited, i.e. the base type's value of the flag bit is copied into the subtype together with a pointer to the extension structure. The  $Py\_TPFLAGS\_HAVE\_GC$  flag bit is inherited together with the  $tp\_traverse$  and  $tp\_clear$  fields, i.e. if the  $Py\_TPFLAGS\_HAVE\_GC$  flag bit is clear in the subtype and the  $tp\_traverse$  and  $tp\_clear$  fields in the subtype exist and have NULL values.

### **Default:**

PyBaseObject Type uses Py TPFLAGS DEFAULT | Py TPFLAGS BASETYPE.

### Bit Masks:

The following bit masks are currently defined; these can be ORed together using the | operator to form the value of the  $tp\_flags$  field. The macro  $PyType\_HasFeature()$  takes a type and a flags value, tp and f, and checks whether  $tp->tp\_flags$  & f is non-zero.

## Py\_TPFLAGS\_HEAPTYPE

This bit is set when the type object itself is allocated on the heap, for example, types created dynamically using  $PyType\_FromSpec()$ . In this case, the ob\_type field of its instances is considered a reference to the type, and the type object is INCREF'ed when a new instance is created, and DECREF'ed when an instance is destroyed (this does not apply to instances of subtypes; only the type referenced by the instance's ob\_type gets INCREF'ed or DECREF'ed).

## **Inheritance:**

???

# Py\_TPFLAGS\_BASETYPE

This bit is set when the type can be used as the base type of another type. If this bit is clear, the type cannot be subtyped (similar to a "final" class in Java).

# Inheritance:

???

# Py\_TPFLAGS\_READY

This bit is set when the type object has been fully initialized by PyType\_Ready ().

## **Inheritance:**

???

## Py\_TPFLAGS\_READYING

This bit is set while PyType\_Ready () is in the process of initializing the type object.

### **Inheritance:**

???

#### Py\_TPFLAGS\_HAVE\_GC

This bit is set when the object supports garbage collection. If this bit is set, instances must be created using  $PyObject\_GC\_New()$  and destroyed using  $PyObject\_GC\_Del()$ . More information in section Supporting Cyclic Garbage Collection. This bit also implies that the GC-related fields  $tp\_traverse$  and  $tp\_clear$  are present in the type object.

#### **Inheritance:**

```
Group:Py_TPFLAGS_HAVE_GC, tp_traverse, tp_clear
```

The Py\_TPFLAGS\_HAVE\_GC flag bit is inherited together with the tp\_traverse and tp\_clear fields, i.e. if the Py\_TPFLAGS\_HAVE\_GC flag bit is clear in the subtype and the tp\_traverse and tp\_clear fields in the subtype exist and have NULL values.

#### Py\_TPFLAGS\_DEFAULT

This is a bitmask of all the bits that pertain to the existence of certain fields in the type object and its extension structures. Currently, it includes the following bits: Py\_TPFLAGS\_HAVE\_STACKLESS\_EXTENSION.

#### **Inheritance:**

222

#### Py\_TPFLAGS\_METHOD\_DESCRIPTOR

This bit indicates that objects behave like unbound methods.

If this flag is set for type (meth), then:

```
— meth.__get__(obj, cls) (*args, **kwds) (with obj not None) must be equivalent to
  meth(obj, *args, **kwds).
```

This flag enables an optimization for typical method calls like obj.meth(): it avoids creating a temporary "bound method" object for obj.meth.

Nouveau dans la version 3.8.

#### **Inheritance:**

This flag is never inherited by types without the  $Py\_TPFLAGS\_IMMUTABLETYPE$  flag set. For extension types, it is inherited whenever  $tp\_descr\_get$  is inherited.

```
Py_TPFLAGS_LONG_SUBCLASS
```

Py\_TPFLAGS\_LIST\_SUBCLASS

Py TPFLAGS TUPLE SUBCLASS

Py\_TPFLAGS\_BYTES\_SUBCLASS

Py\_TPFLAGS\_UNICODE\_SUBCLASS

Py\_TPFLAGS\_DICT\_SUBCLASS

Py\_TPFLAGS\_BASE\_EXC\_SUBCLASS

#### Py\_TPFLAGS\_TYPE\_SUBCLASS

These flags are used by functions such as  $PyLong\_Check$  () to quickly determine if a type is a subclass of a built-in type; such specific checks are faster than a generic check, like  $PyObject\_IsInstance$  (). Custom types that inherit from built-ins should have their  $tp\_flags$  set appropriately, or the code that interacts with such types will behave differently depending on what kind of check is used.

#### Py\_TPFLAGS\_HAVE\_FINALIZE

This bit is set when the  $tp\_finalize$  slot is present in the type structure.

Nouveau dans la version 3.4.

Obsolète depuis la version 3.8 : This flag isn't necessary anymore, as the interpreter assumes the  $tp\_finalize$  slot is always present in the type structure.

12.3. Objets type 245

#### Py\_TPFLAGS\_HAVE\_VECTORCALL

This bit is set when the class implements the *vectorcall protocol*. See tp\_vectorcall\_offset for details.

#### **Inheritance:**

This bit is inherited for types with the  $Py\_TPFLAGS\_IMMUTABLETYPE$  flag set, if  $tp\_call$  is also inherited.

Nouveau dans la version 3.9.

#### Py\_TPFLAGS\_IMMUTABLETYPE

This bit is set for type objects that are immutable: type attributes cannot be set nor deleted.

PyType\_Ready () automatically applies this flag to static types.

#### **Inheritance:**

This flag is not inherited.

Nouveau dans la version 3.10.

#### Py\_TPFLAGS\_DISALLOW\_INSTANTIATION

Disallow creating instances of the type : set  $tp_new$  to NULL and don't create the \_\_new\_\_ key in the type dictionary.

The flag must be set before creating the type, not after. For example, it must be set before  $PyType\_Ready()$  is called on the type.

The flag is set automatically on *static types* if  $tp\_base$  is NULL or &PyBaseObject\_Type and  $tp\_new$  is NULL.

#### Inheritance:

This flag is not inherited. However, subclasses will not be instantiable unless they provide a non-NULL  $tp\_new$  (which is only possible via the C API).

**Note:** To disallow instantiating a class directly but allow instantiating its subclasses (e.g. for an *abstract base class*), do not use this flag. Instead, make  $tp\_new$  only succeed for subclasses.

Nouveau dans la version 3.10.

# Py\_TPFLAGS\_MAPPING

This bit indicates that instances of the class may match mapping patterns when used as the subject of a match block. It is automatically set when registering or subclassing collections.abc.Mapping, and unset when registering collections.abc.Sequence.

**Note:** Py\_TPFLAGS\_MAPPING and Py\_TPFLAGS\_SEQUENCE are mutually exclusive; it is an error to enable both flags simultaneously.

#### **Inheritance:**

This flag is inherited by types that do not already set Py\_TPFLAGS\_SEQUENCE.

#### Voir aussi:

PEP 634 -- Structural Pattern Matching: Specification

Nouveau dans la version 3.10.

#### Py\_TPFLAGS\_SEQUENCE

This bit indicates that instances of the class may match sequence patterns when used as the subject of a match block. It is automatically set when registering or subclassing collections.abc.Sequence, and unset when registering collections.abc.Mapping.

**Note:** Py\_TPFLAGS\_MAPPING and Py\_TPFLAGS\_SEQUENCE are mutually exclusive; it is an error to enable both flags simultaneously.

#### Inheritance:

This flag is inherited by types that do not already set Py\_TPFLAGS\_MAPPING.

#### Voir aussi:

PEP 634 -- Structural Pattern Matching: Specification

Nouveau dans la version 3.10.

```
const char *PyTypeObject.tp_doc
```

An optional pointer to a NUL-terminated C string giving the docstring for this type object. This is exposed as the \_\_doc\_\_ attribute on the type and instances of the type.

#### **Inheritance:**

This field is *not* inherited by subtypes.

```
traverseproc PyTypeObject.tp_traverse
```

An optional pointer to a traversal function for the garbage collector. This is only used if the Py\_TPFLAGS\_HAVE\_GC flag bit is set. The signature is:

```
int tp_traverse(PyObject *self, visitproc visit, void *arg);
```

More information about Python's garbage collection scheme can be found in section Supporting Cyclic Garbage Collection.

The  $tp\_traverse$  pointer is used by the garbage collector to detect reference cycles. A typical implementation of a  $tp\_traverse$  function simply calls  $Py\_VISIT()$  on each of the instance's members that are Python objects that the instance owns. For example, this is function local\_traverse() from the \_thread extension module:

```
static int
local_traverse(localobject *self, visitproc visit, void *arg)
{
    Py_VISIT(self->args);
    Py_VISIT(self->kw);
    Py_VISIT(self->dict);
    return 0;
}
```

Note that  $Py\_VISIT()$  is called only on those members that can participate in reference cycles. Although there is also a self->key member, it can only be NULL or a Python string and therefore cannot be part of a reference cycle.

On the other hand, even if you know a member can never be part of a cycle, as a debugging aid you may want to visit it anyway just so the gc module's get\_referents() function will include it.

**Avertissement:** When implementing  $tp\_traverse$ , only the members that the instance *owns* (by having *strong references* to them) must be visited. For instance, if an object supports weak references via the  $tp\_weaklist$  slot, the pointer supporting the linked list (what  $tp\_weaklist$  points to) must **not** be visited as the instance does not directly own the weak references to itself (the weakreference list is there to support the weak reference machinery, but the instance has no strong reference to the elements inside it, as they are allowed to be removed even if the instance is still alive).

Note that  $Py\_VISIT()$  requires the *visit* and *arg* parameters to local\_traverse() to have these specific names; don't name them just anything.

Instances of *heap-allocated types* hold a reference to their type. Their traversal function must therefore either visit  $Py\_TYPE\ (self)$ , or delegate this responsibility by calling tp\_traverse of another heap-allocated type (such as a heap-allocated superclass). If they do not, the type object may not be garbage-collected.

Modifié dans la version 3.9: Heap-allocated types are expected to visit Py\_TYPE (self) in tp\_traverse. In earlier versions of Python, due to bug 40217, doing this may lead to crashes in subclasses.

**Inheritance:** 

12.3. Objets type 247

```
Group: Py_TPFLAGS_HAVE_GC, tp_traverse, tp_clear
```

This field is inherited by subtypes together with  $tp\_clear$  and the  $Py\_TPFLAGS\_HAVE\_GC$  flag bit: the flag bit,  $tp\_traverse$ , and  $tp\_clear$  are all inherited from the base type if they are all zero in the subtype.

```
inquiry PyTypeObject.tp_clear
```

An optional pointer to a clear function for the garbage collector. This is only used if the *Py\_TPFLAGS\_HAVE\_GC* flag bit is set. The signature is :

```
int tp_clear(PyObject *);
```

The  $tp\_clear$  member function is used to break reference cycles in cyclic garbage detected by the garbage collector. Taken together, all  $tp\_clear$  functions in the system must combine to break all reference cycles. This is subtle, and if in any doubt supply a  $tp\_clear$  function. For example, the tuple type does not implement a  $tp\_clear$  function, because it's possible to prove that no reference cycle can be composed entirely of tuples. Therefore the  $tp\_clear$  functions of other types must be sufficient to break any cycle containing a tuple. This isn't immediately obvious, and there's rarely a good reason to avoid implementing  $tp\_clear$ .

Implementations of  $tp\_clear$  should drop the instance's references to those of its members that may be Python objects, and set its pointers to those members to NULL, as in the following example:

```
static int
local_clear(localobject *self)
{
    Py_CLEAR(self->key);
    Py_CLEAR(self->args);
    Py_CLEAR(self->kw);
    Py_CLEAR(self->kw);
    Py_CLEAR(self->dict);
    return 0;
}
```

The Py\_CLEAR () macro should be used, because clearing references is delicate: the reference to the contained object must not be decremented until after the pointer to the contained object is set to NULL. This is because decrementing the reference count may cause the contained object to become trash, triggering a chain of reclamation activity that may include invoking arbitrary Python code (due to finalizers, or weakref callbacks, associated with the contained object). If it's possible for such code to reference self again, it's important that the pointer to the contained object be NULL at that time, so that self knows the contained object can no longer be used. The Py\_CLEAR () macro performs the operations in a safe order.

Note that  $tp\_clear$  is not always called before an instance is deallocated. For example, when reference counting is enough to determine that an object is no longer used, the cyclic garbage collector is not involved and  $tp\_dealloc$  is called directly.

Because the goal of  $tp\_clear$  functions is to break reference cycles, it's not necessary to clear contained objects like Python strings or Python integers, which can't participate in reference cycles. On the other hand, it may be convenient to clear all contained Python objects, and write the type's  $tp\_dealloc$  function to invoke  $tp\_clear$ .

More information about Python's garbage collection scheme can be found in section Supporting Cyclic Garbage Collection.

#### **Inheritance:**

```
Group:Py_TPFLAGS_HAVE_GC, tp_traverse, tp_clear
```

This field is inherited by subtypes together with  $tp\_traverse$  and the  $Py\_TPFLAGS\_HAVE\_GC$  flag bit: the flag bit,  $tp\_traverse$ , and  $tp\_clear$  are all inherited from the base type if they are all zero in the subtype.

```
richcmpfunc PyTypeObject.tp_richcompare
```

An optional pointer to the rich comparison function, whose signature is:

```
PyObject *tp_richcompare(PyObject *self, PyObject *other, int op);
```

The first parameter is guaranteed to be an instance of the type that is defined by PyTypeObject.

The function should return the result of the comparison (usually Py\_True or Py\_False). If the comparison is undefined, it must return Py\_NotImplemented, if another error occurred it must return NULL and set an exception condition.

The following constants are defined to be used as the third argument for  $tp\_richcompare$  and for  $PyObject\_RichCompare()$ :

Constante	Comparaison	
Py_LT	<	
Py_LE	<=	
Py_EQ	==	
Py_NE	!=	
Py_GT	>	
Py_GE	>=	

The following macro is defined to ease writing rich comparison functions:

# Py\_RETURN\_RICHCOMPARE (VAL\_A, VAL\_B, op)

Return Py\_True or Py\_False from the function, depending on the result of a comparison. VAL\_A and VAL\_B must be orderable by C comparison operators (for example, they may be C ints or floats). The third argument specifies the requested operation, as for  $PyObject_RichCompare()$ .

The return value's reference count is properly incremented.

On error, sets an exception and returns NULL from the function.

Nouveau dans la version 3.7.

#### **Inheritance:**

Group:tp\_hash,tp\_richcompare

This field is inherited by subtypes together with  $tp\_hash$ : a subtype inherits  $tp\_richcompare$  and  $tp\_hash$  when the subtype's  $tp\_richcompare$  and  $tp\_hash$  are both NULL.

#### **Default:**

PyBaseObject\_Type provides a tp\_richcompare implementation, which may be inherited. However, if only tp\_hash is defined, not even the inherited function is used and instances of the type will not be able to participate in any comparisons.

#### Py\_ssize\_t PyTypeObject.tp\_weaklistoffset

If the instances of this type are weakly referenceable, this field is greater than zero and contains the offset in the instance structure of the weak reference list head (ignoring the GC header, if present); this offset is used by  $PyObject\_ClearWeakRefs$  () and the  $PyWeakref\_*$  functions. The instance structure needs to include a field of type PyObject\* which is initialized to NULL.

Do not confuse this field with  $tp\_weaklist$ ; that is the list head for weak references to the type object itself.

# **Inheritance:**

This field is inherited by subtypes, but see the rules listed below. A subtype may override this offset; this means that the subtype uses a different weak reference list head than the base type. Since the list head is always found via  $tp\_weaklistoffset$ , this should not be a problem.

When a type defined by a class statement has no \_\_slots\_\_ declaration, and none of its base types are weakly referenceable, the type is made weakly referenceable by adding a weak reference list head slot to the instance layout and setting the tp\_weaklistoffset of that slot's offset.

When a type's \_\_slots\_\_ declaration contains a slot named \_\_weakref\_\_, that slot becomes the weak reference list head for instances of the type, and the slot's offset is stored in the type's tp\_weaklistoffset.

When a type's \_\_slots\_\_ declaration does not contain a slot named \_\_weakref\_\_, the type inherits its tp\_weaklistoffset from its base type.

#### getiterfunc PyTypeObject.tp\_iter

An optional pointer to a function that returns an *iterator* for the object. Its presence normally signals that the instances of this type are *iterable* (although sequences may be iterable without this function).

This function has the same signature as PyObject\_GetIter():

12.3. Objets type 249

```
PyObject *tp_iter(PyObject *self);
```

#### Inheritance:

This field is inherited by subtypes.

## iternextfunc PyTypeObject.tp\_iternext

An optional pointer to a function that returns the next item in an *iterator*. The signature is:

```
PyObject *tp_iternext(PyObject *self);
```

When the iterator is exhausted, it must return NULL; a StopIteration exception may or may not be set. When another error occurs, it must return NULL too. Its presence signals that the instances of this type are iterators.

Iterator types should also define the  $tp\_iter$  function, and that function should return the iterator instance itself (not a new iterator instance).

This function has the same signature as PyIter\_Next().

#### Inheritance:

This field is inherited by subtypes.

#### struct PyMethodDef \*PyTypeObject.tp\_methods

An optional pointer to a static NULL-terminated array of PyMethodDef structures, declaring regular methods of this type.

For each entry in the array, an entry is added to the type's dictionary (see  $tp\_dict$  below) containing a method descriptor.

#### **Inheritance:**

This field is not inherited by subtypes (methods are inherited through a different mechanism).

#### struct PyMemberDef \*PyTypeObject.tp\_members

An optional pointer to a static NULL-terminated array of PyMemberDef structures, declaring regular data members (fields or slots) of instances of this type.

For each entry in the array, an entry is added to the type's dictionary (see  $tp\_dict$  below) containing a member descriptor.

#### **Inheritance:**

This field is not inherited by subtypes (members are inherited through a different mechanism).

```
struct PyGetSetDef *PyTypeObject.tp getset
```

An optional pointer to a static NULL-terminated array of PyGetSetDef structures, declaring computed attributes of instances of this type.

For each entry in the array, an entry is added to the type's dictionary (see  $tp\_dict$  below) containing a getset descriptor.

#### **Inheritance:**

This field is not inherited by subtypes (computed attributes are inherited through a different mechanism).

#### PyTypeObject \*PyTypeObject.tp\_base

An optional pointer to a base type from which type properties are inherited. At this level, only single inheritance is supported; multiple inheritance require dynamically creating a type object by calling the metatype.

**Note:** Slot initialization is subject to the rules of initializing globals. C99 requires the initializers to be "address constants". Function designators like <code>PyType\_GenericNew()</code>, with implicit conversion to a pointer, are valid C99 address constants.

However, the unary '&' operator applied to a non-static variable like PyBaseObject\_Type() is not required to produce an address constant. Compilers may support this (gcc does), MSVC does not. Both compilers are strictly standard conforming in this particular behavior.

Consequently, *tp\_base* should be set in the extension module's init function.

#### **Inheritance:**

This field is not inherited by subtypes (obviously).

#### **Default:**

This field defaults to &PyBaseObject\_Type (which to Python programmers is known as the type object).

# PyObject \*PyTypeObject.tp\_dict

The type's dictionary is stored here by PyType\_Ready().

This field should normally be initialized to NULL before PyType\_Ready is called; it may also be initialized to a dictionary containing initial attributes for the type. Once PyType\_Ready() has initialized the type, extra attributes for the type may be added to this dictionary only if they don't correspond to overloaded operations (like \_\_add\_\_()).

#### **Inheritance:**

This field is not inherited by subtypes (though the attributes defined in here are inherited through a different mechanism).

#### Default:

If this field is NULL, PyType\_Ready () will assign a new dictionary to it.

**Avertissement:** It is not safe to use  $PyDict\_SetItem()$  on or otherwise modify  $tp\_dict$  with the dictionary C-API.

#### descrgetfunc PyTypeObject.tp\_descr\_get

An optional pointer to a "descriptor get" function.

The function signature is:

```
PyObject * tp_descr_get(PyObject *self, PyObject *obj, PyObject *type);
```

#### Inheritance:

This field is inherited by subtypes.

```
descrsetfunc PyTypeObject.tp_descr_set
```

An optional pointer to a function for setting and deleting a descriptor's value.

The function signature is:

```
int tp_descr_set(PyObject *self, PyObject *obj, PyObject *value);
```

The *value* argument is set to NULL to delete the value.

#### **Inheritance:**

This field is inherited by subtypes.

# Py\_ssize\_t PyTypeObject.tp\_dictoffset

If the instances of this type have a dictionary containing instance variables, this field is non-zero and contains the offset in the instances of the type of the instance variable dictionary; this offset is used by <code>PyObject GenericGetAttr()</code>.

Do not confuse this field with  $tp\_dict$ ; that is the dictionary for attributes of the type object itself.

If the value of this field is greater than zero, it specifies the offset from the start of the instance structure. If the value is less than zero, it specifies the offset from the *end* of the instance structure. A negative offset is more expensive to use, and should only be used when the instance structure contains a variable-length part. This is used for example to add an instance variable dictionary to subtypes of str or tuple. Note that the  $tp\_basicsize$  field should account for the dictionary added to the end in that case, even though the dictionary is not included in the basic object layout. On a system with a pointer size of 4 bytes,  $tp\_dictoffset$  should be set to -4 to indicate that the dictionary is at the very end of the structure.

12.3. Objets type 251

The  $tp\_dictoffset$  should be regarded as write-only. To get the pointer to the dictionary call  $PyObject\_GenericGetDict()$ . Calling  $PyObject\_GenericGetDict()$  may need to allocate memory for the dictionary, so it is may be more efficient to call  $PyObject\_GetAttr()$  when accessing an attribute on the object.

#### **Inheritance:**

This field is inherited by subtypes, but see the rules listed below. A subtype may override this offset; this means that the subtype instances store the dictionary at a difference offset than the base type. Since the dictionary is always found via tp\_dictoffset, this should not be a problem.

When a type defined by a class statement has no \_\_slots\_\_ declaration, and none of its base types has an instance variable dictionary, a dictionary slot is added to the instance layout and the tp\_dictoffset is set to that slot's offset.

When a type defined by a class statement has a \_\_slots\_\_ declaration, the type inherits its tp\_dictoffset from its base type.

(Adding a slot named \_\_dict\_\_ to the \_\_slots\_\_ declaration does not have the expected effect, it just causes confusion. Maybe this should be added as a feature just like \_\_weakref\_\_ though.)

#### Default

This slot has no default. For *static types*, if the field is NULL then no \_\_dict\_\_ gets created for instances.

#### initproc PyTypeObject.tp init

An optional pointer to an instance initialization function.

This function corresponds to the \_\_init\_\_() method of classes. Like \_\_init\_\_(), it is possible to create an instance without calling \_\_init\_\_(), and it is possible to reinitialize an instance by calling its \_\_init\_\_() method again.

The function signature is:

```
int tp_init(PyObject *self, PyObject *args, PyObject *kwds);
```

The self argument is the instance to be initialized; the *args* and *kwds* arguments represent positional and keyword arguments of the call to \_\_init\_\_().

The  $tp\_init$  function, if not NULL, is called when an instance is created normally by calling its type, after the type's  $tp\_new$  function has returned an instance of the type. If the  $tp\_new$  function returns an instance of some other type that is not a subtype of the original type, no  $tp\_init$  function is called; if  $tp\_new$  returns an instance of a subtype of the original type, the subtype's  $tp\_init$  is called.

Returns 0 on success, -1 and sets an exception on error.

#### **Inheritance:**

This field is inherited by subtypes.

#### **Default:**

For static types this field does not have a default.

```
allocfunc PyTypeObject.tp_alloc
```

An optional pointer to an instance allocation function.

The function signature is:

```
PyObject *tp_alloc(PyTypeObject *self, Py_ssize_t nitems);
```

#### **Inheritance:**

This field is inherited by static subtypes, but not by dynamic subtypes (subtypes created by a class statement).

#### Default •

For dynamic subtypes, this field is always set to PyType\_GenericAlloc(), to force a standard heap allocation strategy.

For static subtypes,  $PyBaseObject_Type$  uses  $PyType_GenericAlloc()$ . That is the recommended value for all statically defined types.

#### newfunc PyTypeObject.tp\_new

An optional pointer to an instance creation function.

The function signature is:

```
PyObject *tp_new(PyTypeObject *subtype, PyObject *args, PyObject *kwds);
```

The *subtype* argument is the type of the object being created; the *args* and *kwds* arguments represent positional and keyword arguments of the call to the type. Note that *subtype* doesn't have to equal the type whose  $tp\_new$  function is called; it may be a subtype of that type (but not an unrelated type).

The  $tp\_new$  function should call subtype->tp\_alloc(subtype, nitems) to allocate space for the object, and then do only as much further initialization as is absolutely necessary. Initialization that can safely be ignored or repeated should be placed in the  $tp\_init$  handler. A good rule of thumb is that for immutable types, all initialization should take place in  $tp\_new$ , while for mutable types, most initialization should be deferred to  $tp\_init$ .

Set the Py\_TPFLAGS\_DISALLOW\_INSTANTIATION flag to disallow creating instances of the type in Python.

#### **Inheritance:**

This field is inherited by subtypes, except it is not inherited by *static types* whose  $tp\_base$  is NULL or &PyBaseObject\_Type.

#### **Default:**

For *static types* this field has no default. This means if the slot is defined as NULL, the type cannot be called to create new instances; presumably there is some other way to create instances, like a factory function.

```
freefunc PyTypeObject.tp_free
```

An optional pointer to an instance deallocation function. Its signature is:

```
void tp_free(void *self);
```

An initializer that is compatible with this signature is PyObject\_Free().

#### **Inheritance:**

This field is inherited by static subtypes, but not by dynamic subtypes (subtypes created by a class statement)

#### **Default:**

In dynamic subtypes, this field is set to a deallocator suitable to match  $PyType\_GenericAlloc()$  and the value of the  $Py\_TPFLAGS\_HAVE\_GC$  flag bit.

For static subtypes, PyBaseObject\_Type uses PyObject\_Del.

```
inquiry PyTypeObject.tp_is_gc
```

An optional pointer to a function called by the garbage collector.

The garbage collector needs to know whether a particular object is collectible or not. Normally, it is sufficient to look at the object's type's  $tp\_flags$  field, and check the  $Py\_TPFLAGS\_HAVE\_GC$  flag bit. But some types have a mixture of statically and dynamically allocated instances, and the statically allocated instances are not collectible. Such types should define this function; it should return 1 for a collectible instance, and 0 for a non-collectible instance. The signature is:

```
int tp_is_gc(PyObject *self);
```

(The only example of this are types themselves. The metatype,  $P_YType\_Type$ , defines this function to distinguish between statically and *dynamically allocated types*.)

#### **Inheritance:**

This field is inherited by subtypes.

#### **Default**

This slot has no default. If this field is NULL, Py\_TPFLAGS\_HAVE\_GC is used as the functional equivalent.

12.3. Objets type 253

#### PyObject \*PyTypeObject.tp\_bases

Tuple of base types.

This field should be set to NULL and treated as read-only. Python will fill it in when the type is <code>initialized</code>. For dynamically created classes, the <code>Py\_tp\_bases</code> <code>slot</code> can be used instead of the <code>bases</code> argument of

PyType\_FromSpecWithBases(). The argument form is preferred.

**Avertissement:** Multiple inheritance does not work well for statically defined types. If you set tp\_bases to a tuple, Python will not raise an error, but some slots will only be inherited from the first base.

#### Inheritance:

This field is not inherited.

# PyObject \*PyTypeObject.tp\_mro

Tuple containing the expanded set of base types, starting with the type itself and ending with object, in Method Resolution Order.

This field should be set to NULL and treated as read-only. Python will fill it in when the type is <code>initialized</code>.

#### **Inheritance:**

This field is not inherited; it is calculated fresh by PyType Ready ().

#### PyObject \*PyTypeObject.tp\_cache

Unused. Internal use only.

#### **Inheritance:**

This field is not inherited.

# PyObject \*PyTypeObject.tp\_subclasses

List of weak references to subclasses. Internal use only.

#### Inheritance:

This field is not inherited.

#### PyObject \*PyTypeObject.tp\_weaklist

Weak reference list head, for weak references to this type object. Not inherited. Internal use only.

#### **Inheritance:**

This field is not inherited.

# destructor PyTypeObject.tp\_del

This field is deprecated. Use  $tp\_finalize$  instead.

```
unsigned int PyTypeObject.tp_version_tag
```

Used to index into the method cache. Internal use only.

#### **Inheritance:**

This field is not inherited.

```
destructor PyTypeObject.tp_finalize
```

An optional pointer to an instance finalization function. Its signature is :

```
void tp_finalize(PyObject *self);
```

If tp\_finalize is set, the interpreter calls it once when finalizing an instance. It is called either from the garbage collector (if the instance is part of an isolated reference cycle) or just before the object is deallocated. Either way, it is guaranteed to be called before attempting to break reference cycles, ensuring that it finds the object in a sane state.

 $tp\_finalize$  should not mutate the current exception status; therefore, a recommended way to write a non-trivial finalizer is:

```
static void
local_finalize(PyObject *self)
{
    PyObject *error_type, *error_value, *error_traceback;

    /* Save the current exception, if any. */
    PyErr_Fetch(&error_type, &error_value, &error_traceback);

    /* ... */

    /* Restore the saved exception. */
    PyErr_Restore(error_type, error_value, error_traceback);
}
```

Also, note that, in a garbage collected Python,  $tp\_dealloc$  may be called from any Python thread, not just the thread which created the object (if the object becomes part of a refcount cycle, that cycle might be collected by a garbage collection on any thread). This is not a problem for Python API calls, since the thread on which  $tp\_dealloc$  is called will own the Global Interpreter Lock (GIL). However, if the object being destroyed in turn destroys objects from some other C or C++ library, care should be taken to ensure that destroying those objects on the thread which called  $tp\_dealloc$  will not violate any assumptions of the library.

#### **Inheritance:**

This field is inherited by subtypes.

Nouveau dans la version 3.4.

Modifié dans la version 3.8 : Before version 3.8 it was necessary to set the Py\_TPFLAGS\_HAVE\_FINALIZE flags bit in order for this field to be used. This is no longer required.

#### Voir aussi:

"Safe object finalization" (PEP 442)

```
vectorcallfunc PyTypeObject.tp_vectorcall
```

Vectorcall function to use for calls of this type object. In other words, it is used to implement *vectorcall* for type. \_\_call\_\_. If tp\_vectorcall is NULL, the default call implementation using \_\_new\_\_ and \_\_init\_\_ is used.

# **Inheritance:**

This field is never inherited.

Nouveau dans la version 3.9: (the field exists since 3.8 but it's only used since 3.9)

# 12.3.6 Static Types

Traditionally, types defined in C code are *static*, that is, a static PyTypeObject structure is defined directly in code and initialized using  $PyType\_Ready()$ .

This results in types that are limited relative to types defined in Python :

- Static types are limited to one base, i.e. they cannot use multiple inheritance.
- Static type objects (but not necessarily their instances) are immutable. It is not possible to add or modify the type object's attributes from Python.
- Static type objects are shared across *sub-interpreters*, so they should not include any subinterpreter-specific state. Also, since *PyTypeObject* is only part of the *Limited API* as an opaque struct, any extension modules using static types must be compiled for a specific Python minor version.

12.3. Objets type 255

# 12.3.7 Heap Types

An alternative to *static types* is *heap-allocated types*, or *heap types* for short, which correspond closely to classes created by Python's class statement. Heap types have the *Py\_TPFLAGS\_HEAPTYPE* flag set.

```
This is done by filling a PyType_Spec structure and calling PyType_FromSpec(), PyType_FromSpecWithBases(), or PyType_FromModuleAndSpec().
```

# 12.4 Number Object Structures

#### type PyNumberMethods

This structure holds pointers to the functions which an object uses to implement the number protocol. Each function is used by the function of similar name documented in the *Number Protocol* section.

Here is the structure definition:

```
typedef struct {
    binaryfunc nb_add;
    binaryfunc nb_subtract;
    binaryfunc nb_multiply;
    binaryfunc nb_remainder;
    binaryfunc nb_divmod;
    ternaryfunc nb_power;
    unaryfunc nb_negative;
    unaryfunc nb_positive;
    unaryfunc nb_absolute;
    inquiry nb_bool;
    unaryfunc nb_invert;
    binaryfunc nb_lshift;
    binaryfunc nb_rshift;
    binaryfunc nb_and;
    binaryfunc nb_xor;
    binaryfunc nb_or;
    unaryfunc nb_int;
    void *nb_reserved;
    unaryfunc nb_float;
    binaryfunc nb_inplace_add;
    binaryfunc nb_inplace_subtract;
    binaryfunc nb_inplace_multiply;
    binaryfunc nb_inplace_remainder;
    ternaryfunc nb_inplace_power;
    binaryfunc nb_inplace_lshift;
    binaryfunc nb_inplace_rshift;
    binaryfunc nb_inplace_and;
    binaryfunc nb_inplace_xor;
    binaryfunc nb_inplace_or;
    binaryfunc nb_floor_divide;
    binaryfunc nb_true_divide;
    binaryfunc nb_inplace_floor_divide;
    binaryfunc nb_inplace_true_divide;
    unaryfunc nb_index;
    binaryfunc nb_matrix_multiply;
```

(suite sur la page suivante)

(suite de la page précédente)

```
binaryfunc nb_inplace_matrix_multiply;
} PyNumberMethods;
```

**Note:** Binary and ternary functions must check the type of all their operands, and implement the necessary conversions (at least one of the operands is an instance of the defined type). If the operation is not defined for the given operands, binary and ternary functions must return Py\_NotImplemented, if another error occurred they must return NULL and set an exception.

**Note:** The *nb\_reserved* field should always be NULL. It was previously called nb\_long, and was renamed in Python 3.0.1.

```
binaryfunc PyNumberMethods.nb_add
binaryfunc PyNumberMethods.nb_subtract
binaryfunc PyNumberMethods.nb_multiply
binaryfunc PyNumberMethods.nb_remainder
binaryfunc PyNumberMethods.nb_divmod
ternaryfunc PyNumberMethods.nb_power
unaryfunc PyNumberMethods.nb_negative
unaryfunc PyNumberMethods.nb_positive
unaryfunc PyNumberMethods.nb_absolute
inquiry PyNumberMethods.nb_bool
unaryfunc PyNumberMethods.nb_invert
binaryfunc PyNumberMethods.nb_lshift
binaryfunc PyNumberMethods.nb_rshift
binaryfunc PyNumberMethods.nb_and
binaryfunc PyNumberMethods.nb_xor
binaryfunc PyNumberMethods.nb or
unaryfunc PyNumberMethods.nb int
void *PyNumberMethods.nb reserved
unaryfunc PyNumberMethods.nb_float
binaryfunc PyNumberMethods.nb_inplace_add
binaryfunc PyNumberMethods.nb_inplace_subtract
binaryfunc PyNumberMethods.nb_inplace_multiply
```

```
binaryfunc PyNumberMethods.nb_inplace_remainder

ternaryfunc PyNumberMethods.nb_inplace_power

binaryfunc PyNumberMethods.nb_inplace_lshift

binaryfunc PyNumberMethods.nb_inplace_rshift

binaryfunc PyNumberMethods.nb_inplace_and

binaryfunc PyNumberMethods.nb_inplace_xor

binaryfunc PyNumberMethods.nb_inplace_or

binaryfunc PyNumberMethods.nb_floor_divide

binaryfunc PyNumberMethods.nb_true_divide

binaryfunc PyNumberMethods.nb_inplace_floor_divide

binaryfunc PyNumberMethods.nb_inplace_true_divide

unaryfunc PyNumberMethods.nb_inplace_true_divide

unaryfunc PyNumberMethods.nb_index

binaryfunc PyNumberMethods.nb_index

binaryfunc PyNumberMethods.nb_inplace_matrix_multiply

binaryfunc PyNumberMethods.nb_inplace_matrix_multiply
```

# 12.5 Mapping Object Structures

#### type PyMappingMethods

This structure holds pointers to the functions which an object uses to implement the mapping protocol. It has three members :

## lenfunc PyMappingMethods.mp\_length

This function is used by <code>PyMapping\_Size()</code> and <code>PyObject\_Size()</code>, and has the same signature. This slot may be set to <code>NULL</code> if the object has no defined length.

#### binaryfunc PyMappingMethods.mp\_subscript

This function is used by  $PyObject\_GetItem()$  and  $PySequence\_GetSlice()$ , and has the same signature as  $PyObject\_GetItem()$ . This slot must be filled for the  $PyMapping\_Check()$  function to return 1, it can be NULL otherwise.

# objobjargproc PyMappingMethods.mp\_ass\_subscript

This function is used by <code>PyObject\_SetItem()</code>, <code>PyObject\_DelItem()</code>, <code>PyObject\_SetSlice()</code> and <code>PyObject\_DelSlice()</code>. It has the same signature as <code>PyObject\_SetItem()</code>, but <code>v</code> can also be set to <code>NULL</code> to delete an item. If this slot is <code>NULL</code>, the object does not support item assignment and deletion.

# 12.6 Sequence Object Structures

#### type PySequenceMethods

This structure holds pointers to the functions which an object uses to implement the sequence protocol.

#### lenfunc PySequenceMethods.sq length

This function is used by PySequence\_Size() and PyObject\_Size(), and has the same signature. It is also used for handling negative indices via the sq\_item and the sq\_ass\_item slots.

#### binaryfunc PySequenceMethods.sq\_concat

This function is used by  $PySequence\_Concat$  () and has the same signature. It is also used by the + operator, after trying the numeric addition via the  $nb\_add$  slot.

#### ssizeargfunc PySequenceMethods.sq\_repeat

This function is used by PySequence\_Repeat () and has the same signature. It is also used by the \* operator, after trying numeric multiplication via the nb\_multiply slot.

#### ssizeargfunc PySequenceMethods.sq\_item

This function is used by  $PySequence\_GetItem()$  and has the same signature. It is also used by  $PyObject\_GetItem()$ , after trying the subscription via the  $mp\_subscript$  slot. This slot must be filled for the  $PySequence\_Check()$  function to return 1, it can be NULL otherwise.

Negative indexes are handled as follows: if the sq\_length slot is filled, it is called and the sequence length is used to compute a positive index which is passed to sq\_item. If sq\_length is NULL, the index is passed as is to the function.

#### ssizeobjargproc PySequenceMethods.sq\_ass\_item

This function is used by <code>PySequence\_SetItem()</code> and has the same signature. It is also used by <code>PyObject\_SetItem()</code> and <code>PyObject\_DelItem()</code>, after trying the item assignment and deletion via the <code>mp\_ass\_subscript</code> slot. This slot may be left to <code>NULL</code> if the object does not support item assignment and deletion.

#### objobjproc PySequenceMethods.sq contains

This function may be used by <code>PySequence\_Contains()</code> and has the same signature. This slot may be left to <code>NULL</code>, in this case <code>PySequence\_Contains()</code> simply traverses the sequence until it finds a match.

# binaryfunc PySequenceMethods.sq\_inplace\_concat

This function is used by  $PySequence\_InPlaceConcat()$  and has the same signature. It should modify its first operand, and return it. This slot may be left to NULL, in this case  $PySequence\_InPlaceConcat()$  will fall back to  $PySequence\_Concat()$ . It is also used by the augmented assignment +=, after trying numeric in-place addition via the  $nb\_inplace\_add$  slot.

#### ssizeargfunc PySequenceMethods.sq\_inplace\_repeat

This function is used by <code>PySequence\_InPlaceRepeat()</code> and has the same signature. It should modify its first operand, and return it. This slot may be left to <code>NULL</code>, in this case <code>PySequence\_InPlaceRepeat()</code> will fall back to <code>PySequence\_Repeat()</code>. It is also used by the augmented assignment <code>\*=</code>, after trying numeric in-place multiplication via the <code>nb\_inplace\_multiply</code> slot.

# 12.7 Buffer Object Structures

## type PyBufferProcs

This structure holds pointers to the functions required by the *Buffer protocol*. The protocol defines how an exporter object can expose its internal data to consumer objects.

getbufferproc PyBufferProcs.bf\_getbuffer

The signature of this function is:

```
int (PyObject *exporter, Py_buffer *view, int flags);
```

Handle a request to *exporter* to fill in *view* as specified by *flags*. Except for point (3), an implementation of this function MUST take these steps :

- (1) Check if the request can be met. If not, raise PyExc\_BufferError, set view->obj to NULL and return -1.
- (2) Fill in the requested fields.
- (3) Increment an internal counter for the number of exports.
- (4) Set view->obj to exporter and increment view->obj.
- (5) Return 0.

If exporter is part of a chain or tree of buffer providers, two main schemes can be used:

- Re-export: Each member of the tree acts as the exporting object and sets view->obj to a new reference to itself.
- Redirect: The buffer request is redirected to the root object of the tree. Here, view->obj will be a new reference to the root object.

The individual fields of *view* are described in section *Buffer structure*, the rules how an exporter must react to specific requests are in section *Buffer request types*.

All memory pointed to in the *Py\_buffer* structure belongs to the exporter and must remain valid until there are no consumers left. *format*, *shape*, *strides*, *suboffsets* and *internal* are read-only for the consumer. *PyBuffer\_FillInfo()* provides an easy way of exposing a simple bytes buffer while dealing correctly with all request types.

PyObject\_GetBuffer() is the interface for the consumer that wraps this function.

#### releasebufferproc PyBufferProcs.bf\_releasebuffer

The signature of this function is:

```
void (PyObject *exporter, Py_buffer *view);
```

Handle a request to release the resources of the buffer. If no resources need to be released, PyBufferProcs.  $bf\_releasebuffer$  may be NULL. Otherwise, a standard implementation of this function will take these optional steps:

- (1) Decrement an internal counter for the number of exports.
- (2) If the counter is 0, free all memory associated with view.

The exporter MUST use the *internal* field to keep track of buffer-specific resources. This field is guaranteed to remain constant, while a consumer MAY pass a copy of the original buffer as the *view* argument.

This function MUST NOT decrement view->obj, since that is done automatically in PyBuffer\_Release() (this scheme is useful for breaking reference cycles).

PyBuffer Release () is the interface for the consumer that wraps this function.

# 12.8 Async Object Structures

Nouveau dans la version 3.5.

#### type PyAsyncMethods

This structure holds pointers to the functions required to implement *awaitable* and *asynchronous iterator* objects. Here is the structure definition:

```
typedef struct {
    unaryfunc am_await;
    unaryfunc am_aiter;
    unaryfunc am_anext;
    sendfunc am_send;
} PyAsyncMethods;
```

# unaryfunc PyAsyncMethods.am\_await

The signature of this function is:

```
PyObject *am_await(PyObject *self);
```

The returned object must be an *iterator*, i.e. PyIter\_Check() must return 1 for it.

This slot may be set to NULL if an object is not an awaitable.

```
unaryfunc PyAsyncMethods.am_aiter
```

The signature of this function is:

```
PyObject *am_aiter(PyObject *self);
```

Must return an asynchronous iterator object. See \_\_anext\_\_ () for details.

This slot may be set to NULL if an object does not implement asynchronous iteration protocol.

```
unaryfunc PyAsyncMethods.am_anext
```

The signature of this function is:

```
PyObject *am_anext(PyObject *self);
```

Must return an awaitable object. See \_\_anext\_\_ () for details. This slot may be set to NULL.

```
sendfunc PyAsyncMethods.am send
```

The signature of this function is:

```
PySendResult am_send(PyObject *self, PyObject *arg, PyObject **result);
```

See PyIter\_Send() for details. This slot may be set to NULL.

Nouveau dans la version 3.10.

# 12.9 Slot Type typedefs

```
typedef PyObject *(*allocfunc)(PyTypeObject *cls, Py_ssize_t nitems)
```

Part of the Stable ABI. The purpose of this function is to separate memory allocation from memory initialization. It should return a pointer to a block of memory of adequate length for the instance, suitably aligned, and initialized to zeros, but with ob\_refcnt set to 1 and ob\_type set to the type argument. If the type's tp\_itemsize is non-zero, the object's ob\_size field should be initialized to nitems and the length of the allocated memory block should be tp\_basicsize + nitems\*tp\_itemsize, rounded up to a multiple of sizeof(void\*); otherwise, nitems is not used and the length of the block should be tp\_basicsize.

```
be done by tp_new.
typedef void (*destructor)(PyObject*)
     Part of the Stable ABI.
typedef void (*freefunc)(void*)
     See tp_free.
typedef PyObject *(*newfunc)(PyObject*, PyObject*, PyObject*)
     Part of the Stable ABI. See tp_new.
typedef int (*initproc)(PyObject*, PyObject*, PyObject*)
     Part of the Stable ABI. See tp init.
typedef PyObject *(*reprfunc)(PyObject*)
     Part of the Stable ABI. See tp_repr.
typedef PyObject *(*getattrfunc)(PyObject *self, char *attr)
     Part of the Stable ABI. Return the value of the named attribute for the object.
typedef int (*setattrfunc)(PyObject *self, char *attr, PyObject *value)
     Part of the Stable ABI. Set the value of the named attribute for the object. The value argument is set to NULL to
     delete the attribute.
typedef PyObject *(*getattrofunc)(PyObject *self, PyObject *attr)
     Part of the Stable ABI. Return the value of the named attribute for the object.
     See tp_getattro.
typedef int (*setattrofunc)(PyObject *self, PyObject *attr, PyObject *value)
     Part of the Stable ABI. Set the value of the named attribute for the object. The value argument is set to NULL to
     delete the attribute.
     See tp_setattro.
typedef PyObject *(*descrgetfunc)(PyObject*, PyObject*, PyObject*)
     Part of the Stable ABI. See tp descr get.
typedef int (*descrsetfunc)(PyObject*, PyObject*, PyObject*)
     Part of the Stable ABI. See tp_descr_set.
typedef Py_hash_t (*hashfunc)(PyObject*)
     Part of the Stable ABI. See tp hash.
typedef PyObject *(*richcmpfunc)(PyObject*, PyObject*, int)
     Part of the Stable ABI. See tp richcompare.
typedef PyObject *(*qetiterfunc)(PyObject*)
     Part of the Stable ABI. See tp_iter.
typedef PyObject *(*iternextfunc)(PyObject*)
     Part of the Stable ABI. See tp_iternext.
typedef Py ssize t (*lenfunc)(PyObject*)
     Part of the Stable ABI.
typedef int (*getbufferproc)(PyObject*, Py_buffer*, int)
typedef void (*releasebufferproc)(PyObject*, Py_buffer*)
```

This function should not do any other instance initialization, not even to allocate additional memory; that should

```
typedef PyObject *(*unaryfunc)(PyObject*)
     Part of the Stable ABI.
typedef PyObject *(*binaryfunc)(PyObject*, PyObject*)
     Part of the Stable ABI.
typedef PySendResult (*sendfunc)(PyObject*, PyObject*, PyObject**)
     See am send.
typedef PyObject *(*ternaryfunc)(PyObject*, PyObject*, PyObject*)
     Part of the Stable ABI.
typedef PyObject *(*ssizeargfunc)(PyObject*, Py_ssize_t)
     Part of the Stable ABI.
typedef int (*ssizeobjargproc)(PyObject*, Py_ssize_t, PyObject*)
     Part of the Stable ABI.
typedef int (*objobjproc)(PyObject*, PyObject*)
     Part of the Stable ABI.
typedef int (*objobjargproc)(PyObject*, PyObject*, PyObject*)
     Part of the Stable ABI.
```

# 12.10 Exemples

The following are simple examples of Python type definitions. They include common usage you may encounter. Some demonstrate tricky corner cases. For more examples, practical info, and a tutorial, see defining-new-types and new-types-topics.

A basic static type:

```
typedef struct {
    PyObject_HEAD
    const char *data;
} MyObject;

static PyTypeObject MyObject_Type = {
    PyVarObject_HEAD_INIT(NULL, 0)
    .tp_name = "mymod.MyObject",
    .tp_basicsize = sizeof(MyObject),
    .tp_doc = PyDoc_STR("My objects"),
    .tp_new = myobj_new,
    .tp_dealloc = (destructor)myobj_dealloc,
    .tp_repr = (reprfunc)myobj_repr,
};
```

You may also find older code (especially in the CPython code base) with a more verbose initializer:

(suite sur la page suivante)

12.10. Exemples 263

(suite de la page précédente)

```
0,
                                     /* tp_getattr */
                                      /* tp_setattr */
    0,
                                      /* tp_as_async */
    0,
                                      /* tp_repr */
    (reprfunc) myobj_repr,
                                      /* tp_as_number */
    0,
                                      /* tp_as_sequence */
    0,
                                      /* tp_as_mapping */
    0,
                                      /* tp_hash */
                                      /* tp_call */
    0,
    0,
                                      /* tp_str */
    0,
                                      /* tp_getattro */
    0,
                                      /* tp_setattro */
    0,
                                      /* tp_as_buffer */
                                     /* tp_flags */
                                     /* tp_doc */
   PyDoc_STR("My objects"),
                                      /* tp_traverse */
   Ο,
                                      /* tp_clear */
    0,
                                      /* tp_richcompare */
    0,
                                      /* tp_weaklistoffset */
    0,
    0,
                                      /* tp_iter */
    0,
                                      /* tp_iternext */
    0.
                                      /* tp_methods */
                                      /* tp_members */
    0,
    0,
                                      /* tp_getset */
    0,
                                     /* tp_base */
    0,
                                     /* tp_dict */
    0,
                                     /* tp_descr_get */
                                     /* tp_descr_set */
    0,
                                     /* tp_dictoffset */
    0,
                                      /* tp_init */
    0,
                                      /* tp_alloc */
    0,
                                      /* tp_new */
   myobj_new,
};
```

A type that supports weakrefs, instance dicts, and hashing:

```
typedef struct {
   PyObject_HEAD
   const char *data;
   PyObject *inst_dict;
   PyObject *weakreflist;
} MyObject;
static PyTypeObject MyObject_Type = {
   PyVarObject_HEAD_INIT(NULL, 0)
    .tp_name = "mymod.MyObject",
    .tp_basicsize = sizeof(MyObject),
    .tp_doc = PyDoc_STR("My objects"),
    .tp_weaklistoffset = offsetof(MyObject, weakreflist),
    .tp_dictoffset = offsetof(MyObject, inst_dict),
    .tp_flags = Py_TPFLAGS_DEFAULT | Py_TPFLAGS_BASETYPE | Py_TPFLAGS_HAVE_GC,
    .tp_new = myobj_new,
    .tp_traverse = (traverseproc)myobj_traverse,
    .tp_clear = (inquiry)myobj_clear,
    .tp_alloc = PyType_GenericNew,
    .tp_dealloc = (destructor)myobj_dealloc,
    .tp_repr = (reprfunc)myobj_repr,
```

(suite sur la page suivante)

(suite de la page précédente)

```
.tp_hash = (hashfunc)myobj_hash,
.tp_richcompare = PyBaseObject_Type.tp_richcompare,
};
```

A str subclass that cannot be subclassed and cannot be called to create instances (e.g. uses a separate factory func) using Py\_TPFLAGS\_DISALLOW\_INSTANTIATION flag:

```
typedef struct {
    PyUnicodeObject raw;
    char *extra;
} MyStr;

static PyTypeObject MyStr_Type = {
    PyVarObject_HEAD_INIT(NULL, 0)
    .tp_name = "mymod.MyStr",
    .tp_basicsize = sizeof(MyStr),
    .tp_base = NULL, // set to &PyUnicode_Type in module init
    .tp_doc = PyDoc_STR("my custom str"),
    .tp_flags = Py_TPFLAGS_DEFAULT | Py_TPFLAGS_DISALLOW_INSTANTIATION,
    .tp_repr = (reprfunc)myobj_repr,
};
```

The simplest *static type* with fixed-length instances:

```
typedef struct {
    PyObject_HEAD
} MyObject;

static PyTypeObject MyObject_Type = {
    PyVarObject_HEAD_INIT(NULL, 0)
    .tp_name = "mymod.MyObject",
};
```

The simplest *static type* with variable-length instances:

```
typedef struct {
    PyObject_VAR_HEAD
    const char *data[1];
} MyObject;

static PyTypeObject MyObject_Type = {
    PyVarObject_HEAD_INIT(NULL, 0)
    .tp_name = "mymod.MyObject",
    .tp_basicsize = sizeof(MyObject) - sizeof(char *),
    .tp_itemsize = sizeof(char *),
};
```

12.10. Exemples 265

# 12.11 Supporting Cyclic Garbage Collection

Python's support for detecting and collecting garbage which involves circular references requires support from object types which are "containers" for other objects which may also be containers. Types which do not store references to other objects, or which only store references to atomic types (such as numbers or strings), do not need to provide any explicit support for garbage collection.

To create a container type, the  $tp\_flags$  field of the type object must include the  $Py\_TPFLAGS\_HAVE\_GC$  and provide an implementation of the  $tp\_traverse$  handler. If instances of the type are mutable, a  $tp\_clear$  implementation must also be provided.

#### Py\_TPFLAGS\_HAVE\_GC

Objects with a type with this flag set must conform with the rules documented here. For convenience these objects will be referred to as container objects.

Constructors for container types must conform to two rules:

- 1. The memory for the object must be allocated using PyObject\_GC\_New() or PyObject\_GC\_NewVar().
- 2. Once all the fields which may contain references to other containers are initialized, it must call <code>PyObject\_GC\_Track()</code>.

Similarly, the deallocator for the object must conform to a similar pair of rules :

- 1. Before fields which refer to other containers are invalidated, PyObject\_GC\_UnTrack() must be called.
- 2. The object's memory must be deallocated using  $PyObject\_GC\_Del()$ .

**Avertissement :** If a type adds the Py\_TPFLAGS\_HAVE\_GC, then it *must* implement at least a *tp\_traverse* handler or explicitly use one from its subclasses.

When calling  $PyType\_Ready()$  or some of the APIs that indirectly call it like  $PyType\_FromSpecWithBases()$  or  $PyType\_FromSpec()$  the interpreter will automatically populate the  $tp\_flags$ ,  $tp\_traverse$  and  $tp\_clear$  fields if the type inherits from a class that implements the garbage collector protocol and the child class does not include the  $Py\_TPFLAGS\_HAVE\_GC$  flag.

# TYPE \*PyObject\_GC\_New (TYPE, PyTypeObject \*type)

Analogous to PyObject\_New() but for container objects with the Py\_TPFLAGS\_HAVE\_GC flag set.

#### TYPE \*PyObject\_GC\_NewVar (TYPE, PyTypeObject \*type, Py\_ssize\_t size)

Analogous to PyObject\_NewVar() but for container objects with the Py\_TPFLAGS\_HAVE\_GC flag set.

# TYPE \*PyObject\_GC\_Resize (TYPE, PyVarObject \*op, Py\_ssize\_t newsize)

Resize an object allocated by  $PyObject_NewVar()$ . Returns the resized object or NULL on failure. op must not be tracked by the collector yet.

#### void PyObject\_GC\_Track (PyObject \*op)

Part of the Stable ABI. Adds the object op to the set of container objects tracked by the collector. The collector can run at unexpected times so objects must be valid while being tracked. This should be called once all the fields followed by the  $tp\_traverse$  handler become valid, usually near the end of the constructor.

#### int PyObject\_IS\_GC (PyObject \*obj)

Returns non-zero if the object implements the garbage collector protocol, otherwise returns 0.

The object cannot be tracked by the garbage collector if this function returns 0.

# int PyObject\_GC\_IsTracked (PyObject \*op)

Part of the Stable ABI since version 3.9. Returns 1 if the object type of op implements the GC protocol and op is being currently tracked by the garbage collector and 0 otherwise.

This is analogous to the Python function gc.is\_tracked().

Nouveau dans la version 3.9.

```
int PyObject_GC_IsFinalized (PyObject *op)
```

Part of the Stable ABI since version 3.9. Returns 1 if the object type of op implements the GC protocol and op has been already finalized by the garbage collector and 0 otherwise.

This is analogous to the Python function gc.is finalized().

Nouveau dans la version 3.9.

```
void PyObject GC Del (void *op)
```

Part of the Stable ABI. Releases memory allocated to an object using PyObject\_GC\_New() or PyObject\_GC\_NewVar().

```
void PyObject_GC_UnTrack (void *op)
```

Part of the Stable ABI. Remove the object op from the set of container objects tracked by the collector. Note that  $PyObject\_GC\_Track()$  can be called again on this object to add it back to the set of tracked objects. The deal-locator ( $tp\_dealloc$  handler) should call this for the object before any of the fields used by the  $tp\_traverse$  handler become invalid.

Modifié dans la version 3.8: The \_PyObject\_GC\_TRACK() and \_PyObject\_GC\_UNTRACK() macros have been removed from the public C API.

The tp\_traverse handler accepts a function parameter of this type:

```
typedef int (*visitproc)(PyObject *object, void *arg)
```

Part of the Stable ABI. Type of the visitor function passed to the tp\_traverse handler. The function should be called with an object to traverse as *object* and the third parameter to the tp\_traverse handler as arg. The Python core uses several visitor functions to implement cyclic garbage detection; it's not expected that users will need to write their own visitor functions.

The tp\_traverse handler must have the following type:

```
typedef int (*traverseproc)(PyObject *self, visitproc visit, void *arg)
```

Part of the Stable ABI. Traversal function for a container object. Implementations must call the *visit* function for each object directly contained by *self*, with the parameters to *visit* being the contained object and the *arg* value passed to the handler. The *visit* function must not be called with a NULL object argument. If *visit* returns a non-zero value that value should be returned immediately.

To simplify writing  $tp\_traverse$  handlers, a  $Py\_VISIT()$  macro is provided. In order to use this macro, the  $tp\_traverse$  implementation must name its arguments exactly visit and arg:

```
void Py VISIT (PyObject *o)
```

If o is not NULL, call the *visit* callback, with arguments o and arg. If *visit* returns a non-zero value, then return it. Using this macro,  $tp\_traverse$  handlers look like:

```
static int
my_traverse(Noddy *self, visitproc visit, void *arg)
{
    Py_VISIT(self->foo);
    Py_VISIT(self->bar);
    return 0;
}
```

The tp\_clear handler must be of the inquiry type, or NULL if the object is immutable.

```
typedef int (*inquiry)(PyObject *self)
```

Part of the Stable ABI. Drop references that may have created reference cycles. Immutable objects do not have to define this method since they can never directly create reference cycles. Note that the object must still be valid after

calling this method (don't just call  $Py\_DECREF$  () on a reference). The collector will call this method if it detects that this object is involved in a reference cycle.

# 12.11.1 Controlling the Garbage Collector State

The C-API provides the following functions for controlling garbage collection runs.

#### Py\_ssize\_t PyGC\_Collect (void)

Part of the Stable ABI. Perform a full garbage collection, if the garbage collector is enabled. (Note that gc.collect() runs it unconditionally.)

Returns the number of collected + unreachable objects which cannot be collected. If the garbage collector is disabled or already collecting, returns 0 immediately. Errors during garbage collection are passed to sys.unraisablehook. This function does not raise exceptions.

#### int PyGC\_Enable (void)

Part of the Stable ABI since version 3.10. Enable the garbage collector: similar to gc.enable(). Returns the previous state, 0 for disabled and 1 for enabled.

Nouveau dans la version 3.10.

#### int PyGC\_Disable (void)

Part of the Stable ABI since version 3.10. Disable the garbage collector: similar to gc.disable(). Returns the previous state, 0 for disabled and 1 for enabled.

Nouveau dans la version 3.10.

### int PyGC\_IsEnabled (void)

Part of the Stable ABI since version 3.10. Query the state of the garbage collector: similar to gc.isenabled(). Returns the current state, 0 for disabled and 1 for enabled.

Nouveau dans la version 3.10.

# CHAPITRE 13

# Version des API et ABI

CPython révèle son numéro de version dans les macros suivantes. À noter qu'ils correspondent au code de la version **compilée** avec, pas nécessairement la version utilisée à l'**exécution**.

Voir Stabilité de l'API C pour une discussion sur la stabilité des API et ABI entre (ou en fonction) de la version.

# PY\_MAJOR\_VERSION

Le 3 dans 3.4.1a2.)

# PY\_MINOR\_VERSION

Le 4 dans 3.4.1a2.

# PY\_MICRO\_VERSION

Le 1 dans 3.4.1a2.)

#### PY\_RELEASE\_LEVEL

The a in 3.4.1a2. This can be 0xA for alpha, 0xB for beta, 0xC for release candidate or 0xF for final.

#### PY RELEASE SERIAL

Le 2 dans 3.4.1a2. Nul pour des versions finales.

#### PY\_VERSION\_HEX

Le numéro de version de Python encodé en un seul entier.

L'information sur la version sous-jacente peut être trouvée en la traitant comme un nombre sous 32 bits de la manière suivante :

Octets	Bits (ordre gros-boutiste)	Signification	Valeur pour 3.4.1a2
1	1-8	PY_MAJOR_VERSION	0x03
2	9-16	PY_MINOR_VERSION	0x04
3	17-24	PY_MICRO_VERSION	0x01
4	25-28	PY_RELEASE_LEVEL	0xA
	29-32	PY_RELEASE_SERIAL	0x2

Ainsi, 0x030401a2 est la version en notation hexadécimale sur un entier de 3.4.1a2 et 0x030a00f0 est la version en notation hexadécimale sur un entier de 3.10.0

Vous pouvez l'utiliser pour les comparaisons numériques, par exemple, #if PY\_VERSION\_HEX >= .... Cette version est aussi disponible via le symbole Py\_Version.

# const unsigned long Py\_Version

Part of the Stable ABI since version 3.11. La version à l'exécution de Python est encodée en une constante, avec le même format que la macro PY\_VERSION\_HEX. Cela contient la version de Python utilisée lors de l'exécution. Nouveau dans la version 3.11.

Toutes les macros données sont définies dans Include/patchlevel.h.

# ANNEXE A

# Glossaire

- >>> L'invite de commande utilisée par défaut dans l'interpréteur interactif. On la voit souvent dans des exemples de code qui peuvent être exécutés interactivement dans l'interpréteur.
- ... Peut faire référence à :
  - L'invite de commande utilisée par défaut dans l'interpréteur interactif lorsqu'on entre un bloc de code indenté, dans des délimiteurs fonctionnant par paires (parenthèses, crochets, accolades, triple guillemets), ou après un avoir spécifié un décorateur.
  - La constante Ellipsis.
- **2to3** Outil qui essaie de convertir du code pour Python 2.x en code pour Python 3.x en gérant la plupart des incompatibilités qui peuvent être détectées en analysant la source et parcourant son arbre syntaxique.
  - 2to3 est disponible dans la bibliothèque standard sous le nom de lib2to3; un point d'entrée indépendant est fourni via Tools/scripts/2to3. Cf. 2to3-reference.
- classe mère abstraite Les classes mères abstraites (ABC, suivant l'abréviation anglaise Abstract Base Class) complètent le duck-typing en fournissant un moyen de définir des interfaces pour les cas où d'autres techniques comme hasattr() seraient inélégantes ou subtilement fausses (par exemple avec les méthodes magiques). Les ABC introduisent des sous-classes virtuelles qui n'héritent pas d'une classe mais qui sont quand même reconnues par isinstance() ou issubclass() (voir la documentation du module abc). Python contient de nombreuses ABC pour les structures de données (dans le module collections.abc), les nombres (dans le module numbers), les flux (dans le module io) et les chercheurs-chargeurs du système d'importation (dans le module importlib.abc). Vous pouvez créer vos propres ABC avec le module abc.
- **annotation** Étiquette associée à une variable, un attribut de classe, un paramètre de fonction ou une valeur de retour. Elle est utilisée par convention comme *type hint*.
  - Les annotations de variables locales ne sont pas accessibles au moment de l'exécution, mais les annotations de variables globales, d'attributs de classe et de fonctions sont stockées dans l'attribut spécial \_\_annotations\_\_ des modules, classes et fonctions, respectivement.
  - Voir *annotation de variable*, *annotation de fonction*, les **PEP 484** et **PEP 526**, qui décrivent cette fonctionnalité. Voir aussi annotations-howto sur les bonnes pratiques concernant les annotations.
- argument Valeur, donnée à une fonction ou à une méthode lors de son appel. Il existe deux types d'arguments :
  - argument nommé: un argument précédé d'un identifiant (comme name=) ou un dictionnaire précédé de \*\*, lors d'un appel de fonction. Par exemple, 3 et 5 sont tous les deux des arguments nommés dans l'appel à complex () ici:

```
complex(real=3, imag=5)
complex(**{'real': 3, 'imag': 5})
```

— *argument positionnel*: un argument qui n'est pas nommé. Les arguments positionnels apparaissent au début de la liste des arguments, ou donnés sous forme d'un *itérable* précédé par \*. Par exemple, 3 et 5 sont tous les deux des arguments positionnels dans les appels suivants:

```
complex(3, 5)
complex(*(3, 5))
```

Les arguments se retrouvent dans le corps de la fonction appelée parmi les variables locales. Voir la section calls à propos des règles dictant cette affectation. Syntaxiquement, toute expression est acceptée comme argument, et c'est la valeur résultante de l'expression qui sera affectée à la variable locale.

Voir aussi *paramètre* dans le glossaire, la question Différence entre argument et paramètre de la FAQ et la PEP 362.

- gestionnaire de contexte asynchrone (asynchronous context manager en anglais) Objet contrôlant l'environnement à l'intérieur d'une instruction with en définissant les méthodes \_\_aenter\_\_() et \_\_aexit\_\_(). A été Introduit par la PEP 492.
- **générateur asynchrone** Fonction qui renvoie un *itérateur de générateur asynchrone*. Cela ressemble à une coroutine définie par async def, sauf qu'elle contient une ou des expressions yield produisant ainsi uns série de valeurs utilisables dans une boucle async for.

Générateur asynchrone fait généralement référence à une fonction, mais peut faire référence à un *itérateur de générateur asynchrone* dans certains contextes. Dans les cas où le sens voulu n'est pas clair, utiliser l'ensemble des termes lève l'ambiguïté.

Un générateur asynchrone peut contenir des expressions await ainsi que des instructions async for, et async with.

itérateur de générateur asynchrone Objet créé par un générateur asynchrone.

C'est un *asynchronous iterator* qui, lorsqu'il est appelé via la méthode \_\_anext\_\_\_() renvoie un objet *awaitable* qui exécute le corps de la fonction du générateur asynchrone jusqu'au prochain yield.

Chaque yield suspend temporairement l'exécution, en gardant en mémoire l'endroit et l'état de l'exécution (ce qui inclut les variables locales et les *try* en cours). Lorsque l'exécution de l'itérateur de générateur asynchrone reprend avec un nouvel *awaitable* renvoyé par \_\_anext\_\_ (), elle repart de là où elle s'était arrêtée. Voir les PEP 492 et PEP 525.

- **itérable asynchrone** Objet qui peut être utilisé dans une instruction async for. Sa méthode \_\_aiter\_\_() doit renvoyer un *asynchronous iterator*. A été introduit par la PEP 492.
- itérateur asynchrone Objet qui implémente les méthodes \_\_aiter\_\_() et \_\_anext\_\_(). \_\_anext\_\_ doit renvoyer un objet awaitable. Tant que la méthode \_\_anext\_\_() produit des objets awaitable, le async for appelant les consomme. L'itérateur asynchrone lève une exception StopAsyncIteration pour signifier la fin de l'itération. A été introduit par la PEP 492.
- **attribut** Valeur associée à un objet et habituellement désignée par son nom *via* une notation utilisant des points. Par exemple, si un objet *o* possède un attribut *a*, cet attribut est référencé par *o.a*.
  - Il est possible de donner à un objet un attribut dont le nom n'est pas un identifiant tel que défini pour les identifiers, par exemple en utilisant setatr(), si l'objet le permet. Un tel attribut ne sera pas accessible à l'aide d'une expression pointée et on devra y accéder avec getatr().
- attendable (awaitable) Objet pouvant être utilisé dans une expression await. Ce peut être une coroutine ou un objet avec une méthode \_\_await\_\_(). Voir aussi la PEP 492.
- **BDFL** Dictateur bienveillant à vie (*Benevolent Dictator For Life* en anglais). Pseudonyme de Guido van Rossum, le créateur de Python.
- **fichier binaire** Un *file object* capable de lire et d'écrire des *bytes-like objects*. Des fichiers binaires sont, par exemple, les fichiers ouverts en mode binaire ('rb', 'wb', ou 'rb+'), sys.stdin.buffer, sys.stdout.buffer, les instances de io.BytesIO ou de gzip.GzipFile.

Consultez fichier texte, un objet fichier capable de lire et d'écrire des objets str.

272 Annexe A. Glossaire

**référence empruntée** Dans l'API C de Python, une référence empruntée est une référence vers un objet qui n'affecte pas son compteur de référence. Elle devient invalide si l'objet est supprimé, par exemple au cours d'un passage du ramasse-miettes qui conduit à la disparition de la dernière *référence forte* vers l'objet.

Il est recommandé d'appeler  $Py\_INCREF()$  sur la référence empruntée, ce qui la transforme in situ en une référence forte. Vous pouvez faire une exception si vous êtes certain que l'objet ne peut pas être supprimé avant la dernière utilisation de la référence empruntée. Voir aussi la fonction  $Py\_NewRef()$ , qui crée une nouvelle référence forte.

**objet octet-compatible** Un objet gérant le *protocole tampon* et pouvant exporter un tampon (*buffer* en anglais) C-*contigu*. Cela inclut les objets bytes, bytearray et array ainsi que beaucoup d'objets memoryview. Les objets octets-compatibles peuvent être utilisés pour diverses opérations sur des données binaires, comme la compression, la sauvegarde dans un fichier binaire ou l'envoi sur le réseau.

Certaines opérations nécessitent de travailler sur des données binaires variables. La documentation parle de ceuxci comme des *read-write bytes-like objects*. Par exemple, bytearray ou une memoryview d'un bytearray en font partie. D'autres opérations nécessitent de travailler sur des données binaires stockées dans des objets immuables (« *objets octets-compatibles en lecture seule* »), par exemple des bytes ou des memoryview d'un objet bytes.

code intermédiaire (*bytecode*) Le code source, en Python, est compilé en un code intermédiaire (*bytecode* en anglais), la représentation interne à CPython d'un programme Python. Le code intermédiaire est mis en cache dans un fichier .pyc de manière à ce qu'une seconde exécution soit plus rapide (la compilation en code intermédiaire a déjà été faite). On dit que ce *langage intermédiaire* est exécuté sur une *virtual machine* qui exécute des instructions machine pour chaque instruction du code intermédiaire. Notez que le code intermédiaire n'a pas vocation à fonctionner sur différentes machines virtuelles Python ou à être stable entre différentes versions de Python.

La documentation du module dis fournit une liste des instructions du code intermédiaire.

**appelable** (*callable*) Un appelable est un objet qui peut être appelé, éventuellement avec un ensemble d'arguments (voir *argument*), avec la syntaxe suivante :

```
callable(argument1, argument2, argumentN)
```

Une *fonction*, et par extension une *méthode*, est un appelable. Une instance d'une classe qui implémente la méthode \_\_call\_\_() est également un appelable.

**fonction de rappel** (*callback*) Une fonction (classique, par opposition à une coroutine) passée en argument pour être exécutée plus tard.

**classe** Modèle pour créer des objets définis par l'utilisateur. Une définition de classe (*class*) contient normalement des définitions de méthodes qui agissent sur les instances de la classe.

variable de classe Une variable définie dans une classe et destinée à être modifiée uniquement au niveau de la classe (c'est-à-dire, pas dans une instance de la classe).

nombre complexe Extension des nombres réels familiers, dans laquelle tous les nombres sont exprimés sous la forme d'une somme d'une partie réelle et d'une partie imaginaire. Les nombres imaginaires sont les nombres réels multipliés par l'unité imaginaire (la racine carrée de -1, souvent écrite i en mathématiques ou j par les ingénieurs). Python comprend nativement les nombres complexes, écrits avec cette dernière notation : la partie imaginaire est écrite avec un suffixe j, exemple, 3+1j. Pour utiliser les équivalents complexes de math, utilisez cmath. Les nombres complexes sont un concept assez avancé en mathématiques. Si vous ne connaissez pas ce concept, vous pouvez tranquillement les ignorer.

**gestionnaire de contexte** Objet contrôlant l'environnement à l'intérieur d'un bloc with en définissant les méthodes \_\_enter\_\_() et \_\_exit\_\_(). Consultez la PEP 343.

variable de contexte Une variable qui peut avoir des valeurs différentes en fonction de son contexte. Cela est similaire au stockage par fil d'exécution (*Thread Local Storage* en anglais) dans lequel chaque fil d'exécution peut avoir une valeur différente pour une variable. Toutefois, avec les variables de contexte, il peut y avoir plusieurs contextes dans un fil d'exécution et l'utilisation principale pour les variables de contexte est de garder une trace des variables dans les tâches asynchrones concourantes. Voir contextvars.

**contigu** Un tampon (*buffer* en anglais) est considéré comme contigu s'il est soit *C-contigu* soit *Fortran-contigu*. Les tampons de dimension zéro sont C-contigus et Fortran-contigus. Pour un tableau à une dimension, ses éléments

doivent être placés en mémoire l'un à côté de l'autre, dans l'ordre croissant de leur indice, en commençant à zéro. Pour qu'un tableau multidimensionnel soit C-contigu, le dernier indice doit être celui qui varie le plus rapidement lors du parcours de ses éléments dans l'ordre de leur adresse mémoire. À l'inverse, dans les tableaux Fortrancontigu, c'est le premier indice qui doit varier le plus rapidement.

- **coroutine** Les coroutines sont une forme généralisée des fonctions. On entre dans une fonction en un point et on en sort en un autre point. On peut entrer, sortir et reprendre l'exécution d'une coroutine en plusieurs points. Elles peuvent être implémentées en utilisant l'instruction async def. Voir aussi la **PEP 492**.
- fonction coroutine Fonction qui renvoie un objet *coroutine*. Une fonction coroutine peut être définie par l'instruction async def et peut contenir les mots clés await, async for ainsi que async with. A été introduit par la PEP 492.
- **CPython** L'implémentation canonique du langage de programmation Python, tel que distribué sur python.org. Le terme "CPython" est utilisé dans certains contextes lorsqu'il est nécessaire de distinguer cette implémentation des autres comme *Jython* ou *IronPython*.
- **décorateur** Fonction dont la valeur de retour est une autre fonction. Un décorateur est habituellement utilisé pour transformer une fonction via la syntaxe @wrapper, dont les exemples typiques sont : classmethod() et staticmethod().

La syntaxe des décorateurs est simplement du sucre syntaxique, les définitions des deux fonctions suivantes sont sémantiquement équivalentes :

```
def f(arg):
    ...
f = staticmethod(f)

@staticmethod
def f(arg):
    ...
```

Quoique moins fréquemment utilisé, le même concept existe pour les classes. Consultez la documentation définitions de fonctions et définitions de classes pour en savoir plus sur les décorateurs.

- **descripteur** N'importe quel objet définissant les méthodes \_\_get\_\_(), \_\_set\_\_(), ou \_\_delete\_\_(). Lorsque l'attribut d'une classe est un descripteur, son comportement spécial est déclenché lors de la recherche des attributs. Normalement, lorsque vous écrivez a.b pour obtenir, affecter ou effacer un attribut, Python recherche l'objet nommé b dans le dictionnaire de la classe de a. Mais si b est un descripteur, c'est la méthode de ce descripteur qui est alors appelée. Comprendre les descripteurs est requis pour avoir une compréhension approfondie de Python, ils sont la base de nombre de ses caractéristiques notamment les fonctions, méthodes, propriétés, méthodes de classes, méthodes statiques et les références aux classes parentes.
  - Pour plus d'informations sur les méthodes des descripteurs, consultez descriptors ou le guide pour l'utilisation des descripteurs.
- **dictionnaire** Structure de donnée associant des clés à des valeurs. Les clés peuvent être n'importe quel objet possédant les méthodes \_\_hash\_\_ () et \_\_eq\_\_ (). En Perl, les dictionnaires sont appelés "hash".
- dictionnaire en compréhension (ou dictionnaire en intension) Écriture concise pour traiter tout ou partie des éléments d'un itérable et renvoyer un dictionnaire contenant les résultats. results = {n: n \*\* 2 for n in range (10)} génère un dictionnaire contenant des clés n liées à leurs valeurs n \*\* 2. Voir compréhensions.
- vue de dictionnaire Objets retournés par les méthodes dict.keys(), dict.values() et dict.items().
  Ils fournissent des vues dynamiques des entrées du dictionnaire, ce qui signifie que lorsque le dictionnaire change, la vue change. Pour transformer une vue en vraie liste, utilisez list (dictview). Voir dict-views.
- chaîne de documentation (docstring) Première chaîne littérale qui apparaît dans l'expression d'une classe, fonction, ou module. Bien qu'ignorée à l'exécution, elle est reconnue par le compilateur et placée dans l'attribut \_\_\_doc\_\_ de la classe, de la fonction ou du module. Comme cette chaîne est disponible par introspection, c'est l'endroit idéal pour documenter l'objet.
- **typage canard** (*duck-typing*) Style de programmation qui ne prend pas en compte le type d'un objet pour déterminer s'il respecte une interface, mais qui appelle simplement la méthode ou l'attribut (*Si ça a un bec et que ça cancane*,

274 Annexe A. Glossaire

ça doit être un canard, duck signifie canard en anglais). En se concentrant sur les interfaces plutôt que les types, du code bien construit améliore sa flexibilité en autorisant des substitutions polymorphiques. Le duck-typing évite de vérifier les types via type () ou isinstance (), Notez cependant que le duck-typing peut travailler de pair avec les classes mère abstraites. À la place, le duck-typing utilise plutôt hasattr () ou la programmation EAFP.

- **EAFP** Il est plus simple de demander pardon que demander la permission (*Easier to Ask for Forgiveness than Permission* en anglais). Ce style de développement Python fait l'hypothèse que le code est valide et traite les exceptions si cette hypothèse s'avère fausse. Ce style, propre et efficace, est caractérisé par la présence de beaucoup de mots clés try et except. Cette technique de programmation contraste avec le style *LBYL* utilisé couramment dans les langages tels que C.
- expression Suite logique de termes et chiffres conformes à la syntaxe Python dont l'évaluation fournit une valeur. En d'autres termes, une expression est une suite d'éléments tels que des noms, opérateurs, littéraux, accès d'attributs, méthodes ou fonctions qui aboutissent à une valeur. Contrairement à beaucoup d'autres langages, les différentes constructions du langage ne sont pas toutes des expressions. On trouve également des *instructions* qui ne peuvent pas être utilisées comme expressions, tel que while. Les affectations sont également des instructions et non des expressions.
- **module d'extension** Module écrit en C ou C++, utilisant l'API C de Python pour interagir avec Python et le code de l'utilisateur.
- **f-string** Chaîne littérale préfixée de 'f' ou 'F'. Les "f-strings" sont un raccourci pour formatted string literals. Voir la **PEP 498**.
- **objet fichier** Objet exposant une ressource via une API orientée fichier (avec les méthodes read () ou write ()). En fonction de la manière dont il a été créé, un objet fichier peut interfacer l'accès à un fichier sur le disque ou à un autre type de stockage ou de communication (typiquement l'entrée standard, la sortie standard, un tampon en mémoire, un connecteur réseau...). Les objets fichiers sont aussi appelés *file-like-objects* ou *streams*.
  - Il existe en réalité trois catégories de fichiers objets : les *fichiers binaires* bruts, les *fichiers binaires* avec tampon (*buffer*) et les *fichiers textes*. Leurs interfaces sont définies dans le module io. Le moyen le plus simple et direct de créer un objet fichier est d'utiliser la fonction open ().
- objet fichier-compatible Synonyme de objet fichier.
- **encodage du système de fichiers et gestionnaire d'erreurs associé** Encodage et gestionnaire d'erreurs utilisés par Python pour décoder les octets fournis par le système d'exploitation et encoder les chaînes de caractères Unicode afin de les passer au système.

L'encodage du système de fichiers doit impérativement pouvoir décoder tous les octets jusqu'à 128. Si ce n'est pas le cas, certaines fonctions de l'API lèvent UnicodeError.

Cet encodage et son gestionnaire d'erreur peuvent être obtenus à l'aide des fonctions sys. getfilesystemencoding() et sys.getfilesystemencodeerrors().

L'encodage du système de fichiers et gestionnaire d'erreurs associé sont configurés au démarrage de Python par la fonction PyConfig\_Read(): regardez filesystem\_encoding et filesystem\_errors dans les membres de PyConfig.

Voir aussi encodage régional.

**chercheur** Objet qui essaie de trouver un *chargeur* pour le module en cours d'importation.

Depuis Python 3.3, il existe deux types de chercheurs : les *chercheurs dans les méta-chemins* à utiliser avec sys.meta\_path; les *chercheurs d'entrée dans path* à utiliser avec sys.path\_hooks.

Voir les PEP 302, PEP 420 et PEP 451 pour plus de détails.

- **division entière** Division mathématique arrondissant à l'entier inférieur. L'opérateur de la division entière est //. Par exemple l'expression 11 // 4 vaut 2, contrairement à 11 / 4 qui vaut 2.75. Notez que (-11) // 4 vaut -3 car l'arrondi se fait à l'entier inférieur. Voir la **PEP 328**.
- **fonction** Suite d'instructions qui renvoie une valeur à son appelant. On peut lui passer des *arguments* qui pourront être utilisés dans le corps de la fonction. Voir aussi *paramètre*, *méthode* et function.
- **annotation de fonction** *annotation* d'un paramètre de fonction ou valeur de retour.

Les annotations de fonctions sont généralement utilisées pour des *indications de types* : par exemple, cette fonction devrait prendre deux arguments int et devrait également avoir une valeur de retour de type int :

```
def sum_two_numbers(a: int, b: int) -> int:
    return a + b
```

L'annotation syntaxique de la fonction est expliquée dans la section function.

Voir *annotation de variable* et la **PEP 484**, qui décrivent cette fonctionnalité. Voir aussi annotations-howto sur les bonnes pratiques concernant les annotations.

\_\_future\_\_ Une importation depuis le futur s'écrit from \_\_future\_\_ import <fonctionnalité>.

Lorsqu'une importation du futur est active dans un module, Python compile ce module avec une certaine modification de la syntaxe ou du comportement qui est vouée à devenir standard dans une version ultérieure. Le module \_\_future\_\_ documente les possibilités pour *fonctionnalité*. L'importation a aussi l'effet normal d'importer une variable du module. Cette variable contient des informations utiles sur la fonctionnalité en question, notamment la version de Python dans laquelle elle a été ajoutée, et celle dans laquelle elle deviendra standard :

```
>>> import __future__
>>> __future__.division
_Feature((2, 2, 0, 'alpha', 2), (3, 0, 0, 'alpha', 0), 8192)
```

**ramasse-miettes** (*garbage collection* en anglais) Mécanisme permettant de libérer de la mémoire lorsqu'elle n'est plus utilisée. Python utilise un ramasse-miettes par comptage de référence et un ramasse-miettes cyclique capable de détecter et casser les références circulaires. Le ramasse-miettes peut être contrôlé en utilisant le module gc.

**générateur** Fonction qui renvoie un *itérateur de générateur*. Cela ressemble à une fonction normale, en dehors du fait qu'elle contient une ou des expressions yield produisant une série de valeurs utilisable dans une boucle *for* ou récupérées une à une via la fonction next ().

Fait généralement référence à une fonction génératrice mais peut faire référence à un *itérateur de générateur* dans certains contextes. Dans les cas où le sens voulu n'est pas clair, utiliser les termes complets lève l'ambiguïté.

itérateur de générateur Objet créé par une fonction générateur.

Chaque yield suspend temporairement l'exécution, en se rappelant l'endroit et l'état de l'exécution (y compris les variables locales et les *try* en cours). Lorsque l'itérateur de générateur reprend, il repart là où il en était (contrairement à une fonction qui prendrait un nouveau départ à chaque invocation).

**expression génératrice** Expression qui donne un itérateur. Elle ressemble à une expression normale, suivie d'une clause for définissant une variable de boucle, un intervalle et une clause if optionnelle. Toute cette expression génère des valeurs pour la fonction qui l'entoure :

```
>>> sum(i*i for i in range(10))  # sum of squares 0, 1, 4, ... 81
285
```

**fonction générique** Fonction composée de plusieurs fonctions implémentant les mêmes opérations pour différents types. L'implémentation à utiliser est déterminée lors de l'appel par l'algorithme de répartition.

Voir aussi single dispatch, le décorateur functools.singledispatch() et la PEP 443.

**type générique** Un *type* qui peut être paramétré; généralement un conteneur comme list ou dict. Utilisé pour les *indications de type* et les *annotations*.

Pour plus de détails, voir types alias génériques et le module typing. On trouvera l'historique de cette fonctionnalité dans les PEP 483, PEP 484 et PEP 585.

**GIL** Voir global interpreter lock.

verrou global de l'interpréteur (global interpreter lock en anglais) Mécanisme utilisé par l'interpréteur CPython pour s'assurer qu'un seul fil d'exécution (thread en anglais) n'exécute le bytecode à la fois. Cela simplifie l'implémentation de CPython en rendant le modèle objet (incluant des parties critiques comme la classe native dict) implicitement protégé contre les accès concourants. Verrouiller l'interpréteur entier rend plus facile l'implémentation de multiples fils d'exécution (multi-thread en anglais), au détriment malheureusement de beaucoup du parallélisme possible sur les machines ayant plusieurs processeurs.

Cependant, certains modules d'extension, standards ou non, sont conçus de manière à libérer le GIL lorsqu'ils effectuent des tâches lourdes tel que la compression ou le hachage. De la même manière, le GIL est toujours libéré lors des entrées-sorties.

276 Annexe A. Glossaire

Les tentatives précédentes d'implémenter un interpréteur Python avec une granularité de verrouillage plus fine ont toutes échouées, à cause de leurs mauvaises performances dans le cas d'un processeur unique. Il est admis que corriger ce problème de performance induit mènerait à une implémentation beaucoup plus compliquée et donc plus coûteuse à maintenir.

- *pyc* utilisant le hachage Un fichier de cache de code intermédiaire (*bytecode* en anglais) qui utilise le hachage plutôt que l'heure de dernière modification du fichier source correspondant pour déterminer sa validité. Voir pycinvalidation.
- hachable Un objet est *hachable* s'il a une empreinte (*hash*) qui ne change jamais (il doit donc implémenter une méthode \_\_hash\_\_()) et s'il peut être comparé à d'autres objets (avec la méthode \_\_eq\_\_()). Les objets hachables dont la comparaison par \_\_eq\_\_ est vraie doivent avoir la même empreinte.
  - La hachabilité permet à un objet d'être utilisé comme clé de dictionnaire ou en tant que membre d'un ensemble (type *set*), car ces structures de données utilisent ce *hash*.
  - La plupart des types immuables natifs de Python sont hachables, mais les conteneurs muables (comme les listes ou les dictionnaires) ne le sont pas; les conteneurs immuables (comme les n-uplets ou les ensembles figés) ne sont hachables que si leurs éléments sont hachables. Les instances de classes définies par les utilisateurs sont hachables par défaut. Elles sont toutes considérées différentes (sauf avec elles-mêmes) et leur valeur de hachage est calculée à partir de leur id().
- **IDLE** Environnement d'apprentissage et de développement intégré pour Python. IDLE est un éditeur basique et un interpréteur livré avec la distribution standard de Python.
- **immuable** Objet dont la valeur ne change pas. Les nombres, les chaînes et les *n*-uplets sont immuables. Ils ne peuvent être modifiés. Un nouvel objet doit être créé si une valeur différente doit être stockée. Ils jouent un rôle important quand une valeur de *hash* constante est requise, typiquement en clé de dictionnaire.
- **chemin des importations** Liste de *entrées* dans lesquelles le *chercheur basé sur les chemins* cherche les modules à importer. Typiquement, lors d'une importation, cette liste vient de sys.path; pour les sous-paquets, elle peut aussi venir de l'attribut \_\_path\_\_ du paquet parent.
- importation Processus rendant le code Python d'un module disponible dans un autre.
- importateur Objet qui trouve et charge un module, en même temps un chercheur et un chargeur.
- interactif Python a un interpréteur interactif, ce qui signifie que vous pouvez écrire des expressions et des instructions à l'invite de l'interpréteur. L'interpréteur Python va les exécuter immédiatement et vous en présenter le résultat. Démarrez juste python (probablement depuis le menu principal de votre ordinateur). C'est un moyen puissant pour tester de nouvelles idées ou étudier de nouveaux modules (souvenez-vous de help(x)).
- **interprété** Python est un langage interprété, en opposition aux langages compilés, bien que la frontière soit floue en raison de la présence d'un compilateur en code intermédiaire. Cela signifie que les fichiers sources peuvent être exécutés directement, sans avoir à compiler un fichier exécutable intermédiaire. Les langages interprétés ont généralement un cycle de développement / débogage plus court que les langages compilés. Cependant, ils s'exécutent généralement plus lentement. Voir aussi *interactif*.
- arrêt de l'interpréteur Lorsqu'on lui demande de s'arrêter, l'interpréteur Python entre dans une phase spéciale où il libère graduellement les ressources allouées, comme les modules ou quelques structures de données internes. Il fait aussi quelques appels au *ramasse-miettes*. Cela peut déclencher l'exécution de code dans des destructeurs ou des fonctions de rappels de *weakrefs*. Le code exécuté lors de l'arrêt peut rencontrer des exceptions puisque les ressources auxquelles il fait appel sont susceptibles de ne plus fonctionner, (typiquement les modules des bibliothèques ou le mécanisme de *warning*).
  - La principale raison d'arrêt de l'interpréteur est que le module \_\_main\_\_ ou le script en cours d'exécution a terminé de s'exécuter.
- **itérable** Objet capable de renvoyer ses éléments un à un. Par exemple, tous les types de séquences (comme list, str, et tuple), quelques autres types comme dict, les *objets fichiers* ou tout objet d'une classe ayant une méthode \_\_iter\_\_() ou \_\_getitem\_\_() qui implémente la sémantique d'une *séquence*.
  - Les itérables peuvent être utilisés dans des boucles for et à beaucoup d'autres endroits où une séquence est requise (zip(), map()...). Lorsqu'un itérable est passé comme argument à la fonction native iter(), celle-ci fournit en retour un itérateur sur cet itérable. Cet itérateur n'est valable que pour une seule passe sur le jeu de valeurs. Lors

de l'utilisation d'itérables, il n'est habituellement pas nécessaire d'appeler iter () ou de s'occuper soi-même des objets itérateurs. L'instruction for le fait automatiquement pour vous, créant une variable temporaire anonyme pour garder l'itérateur durant la boucle. Voir aussi *itérateur*, *séquence* et *générateur*.

itérateur Objet représentant un flux de donnée. Des appels successifs à la méthode \_\_next\_\_\_() de l'itérateur (ou le passer à la fonction native next()) donne successivement les objets du flux. Lorsque plus aucune donnée n'est disponible, une exception StopIteration est levée. À ce point, l'itérateur est épuisé et tous les appels suivants à sa méthode \_\_next\_\_\_() lèveront encore une exception StopIteration. Les itérateurs doivent avoir une méthode \_\_iter\_\_\_() qui renvoie l'objet itérateur lui-même, de façon à ce que chaque itérateur soit aussi itérable et puisse être utilisé dans la plupart des endroits où d'autres itérables sont attendus. Une exception notable est un code qui tente plusieurs itérations complètes. Un objet conteneur, (tel que list) produit un nouvel itérateur neuf à chaque fois qu'il est passé à la fonction iter() ou s'il est utilisé dans une boucle for. Faire ceci sur un itérateur donnerait simplement le même objet itérateur épuisé utilisé dans son itération précédente, le faisant ressembler à un conteneur vide.

Vous trouverez davantage d'informations dans typeiter.

Particularité de l'implémentation CPython : CPython n'est pas toujours cohérent sur le fait de demander ou non à un itérateur de définir \_\_iter\_\_().

**fonction clé** Une fonction clé est un objet appelable qui renvoie une valeur à fins de tri ou de classement. Par exemple, la fonction locale.strxfrm() est utilisée pour générer une clé de classement prenant en compte les conventions de classement spécifiques aux paramètres régionaux courants.

Plusieurs outils dans Python acceptent des fonctions clés pour déterminer comment les éléments sont classés ou groupés. On peut citer les fonctions min(), max(), sorted(), list.sort(), heapq.merge(), heapq.nsmallest(), heapq.nlargest() et itertools.groupby().

Il existe plusieurs moyens de créer une fonction clé. Par exemple, la méthode str.lower() peut servir de fonction clé pour effectuer des recherches insensibles à la casse. Aussi, il est possible de créer des fonctions clés avec des expressions lambda, comme lambda r: (r[0], r[2]). Par ailleurs attrgetter(), itemgetter() et methodcaller() permettent de créer des fonctions clés. Voir le guide pour le tri pour des exemples de création et d'utilisation de fonctions clefs.

# argument nommé Voir argument.

**lambda** Fonction anonyme sous la forme d'une *expression* et ne contenant qu'une seule expression, exécutée lorsque la fonction est appelée. La syntaxe pour créer des fonctions lambda est : lambda [parameters]: expression

**LBYL** Regarde avant de sauter, (*Look before you leap* en anglais). Ce style de programmation consiste à vérifier des conditions avant d'effectuer des appels ou des accès. Ce style contraste avec le style *EAFP* et se caractérise par la présence de beaucoup d'instructions if.

Dans un environnement avec plusieurs fils d'exécution (*multi-threaded* en anglais), le style *LBYL* peut engendrer un séquencement critique (*race condition* en anglais) entre le "regarde" et le "sauter". Par exemple, le code if key in mapping: return mapping [key] peut échouer si un autre fil d'exécution supprime la clé *key* du *mapping* après le test mais avant l'accès. Ce problème peut être résolu avec des verrous (*locks*) ou avec l'approche EAFP.

**encodage régional** Sous Unix, il est défini par la variable régionale LC\_CTYPE. Il peut être modifié par locale. setlocale (locale.LC\_CTYPE, new\_locale).

Sous Windows, c'est un encodage ANSI (par ex.: "cp1252").

Sous Android et VxWorks, Python utilise "utf-8" comme encodage régional.

locale.getencoding() permet de récupérer l'encodage régional.

Voir aussi l'encodage du systèmes de fichiers et gestionnaire d'erreurs associé.

**liste** Un type natif de *sequence* dans Python. En dépit de son nom, une list ressemble plus à un tableau (*array* dans la plupart des langages) qu'à une liste chaînée puisque les accès se font en O(1).

liste en compréhension (ou liste en intension) Écriture concise pour manipuler tout ou partie des éléments d'une séquence et renvoyer une liste contenant les résultats. result = ['{:#04x}'.format(x) for x in range(256) if x % 2 == 0] génère la liste composée des nombres pairs de 0 à 255 écrits sous formes de chaînes de caractères et en hexadécimal(0x...). La clause if est optionnelle. Si elle est omise, tous les éléments du range(256) seront utilisés.

278 Annexe A. Glossaire

**chargeur** Objet qui charge un module. Il doit définir une méthode nommée load\_module(). Un chargeur est typiquement donné par un *chercheur*. Voir la PEP 302 pour plus de détails et importlib.ABC.Loader pour sa *classe mère abstraite*.

**méthode magique** Un synonyme informel de *special method*.

tableau de correspondances (*mapping* en anglais) Conteneur permettant de rechercher des éléments à partir de clés et implémentant les méthodes spécifiées dans les classes mères abstraites des tableaux de correspondances (immuables) ou tableaux de correspondances muables (voir les classes mères abstraites). Les classes suivantes sont des exemples de tableaux de correspondances : dict, collections.defaultdict, collections.OrderedDict et collections.Counter.

**chercheur dans les méta-chemins** Un *chercheur* renvoyé par une recherche dans sys.meta\_path. Les chercheurs dans les méta-chemins ressemblent, mais sont différents des *chercheurs d'entrée dans path*.

Voir importlib.abc.MetaPathFinder pour les méthodes que les chercheurs dans les méta-chemins doivent implémenter.

**métaclasse** Classe d'une classe. Les définitions de classe créent un nom pour la classe, un dictionnaire de classe et une liste de classes parentes. La métaclasse a pour rôle de réunir ces trois paramètres pour construire la classe. La plupart des langages orientés objet fournissent une implémentation par défaut. La particularité de Python est la possibilité de créer des métaclasses personnalisées. La plupart des utilisateurs n'auront jamais besoin de cet outil, mais lorsque le besoin survient, les métaclasses offrent des solutions élégantes et puissantes. Elles sont utilisées pour journaliser les accès à des propriétés, rendre sûrs les environnements *multi-threads*, suivre la création d'objets, implémenter des singletons et bien d'autres tâches.

Plus d'informations sont disponibles dans : metaclasses.

**méthode** Fonction définie à l'intérieur d'une classe. Lorsqu'elle est appelée comme un attribut d'une instance de cette classe, la méthode reçoit l'instance en premier *argument* (qui, par convention, est habituellement nommé self). Voir *function* et *nested scope*.

**ordre de résolution des méthodes** L'ordre de résolution des méthodes (*MRO* pour *Method Resolution Order* en anglais) est, lors de la recherche d'un attribut dans les classes parentes, la façon dont l'interpréteur Python classe ces classes parentes. Voir The Python 2.3 Method Resolution Order pour plus de détails sur l'algorithme utilisé par l'interpréteur Python depuis la version 2.3.

**module** Objet utilisé pour organiser une portion unitaire de code en Python. Les modules ont un espace de nommage et peuvent contenir n'importe quels objets Python. Charger des modules est appelé *importer*.

Voir aussi paquet

spécificateur de module Espace de nommage contenant les informations, relatives à l'importation, utilisées pour charger un module. C'est une instance de la classe importlib.machinery.ModuleSpec.

MRO Voir ordre de résolution des méthodes.

muable Un objet muable peut changer de valeur tout en gardant le même id(). Voir aussi immuable.

**n-uplet nommé** Le terme "n-uplet nommé" s'applique à tous les types ou classes qui héritent de la classe tuple et dont les éléments indexables sont aussi accessibles en utilisant des attributs nommés. Les types et classes peuvent avoir aussi d'autres caractéristiques.

Plusieurs types natifs sont appelés n-uplets, y compris les valeurs retournées par time.localtime() et os. stat(). Un autre exemple est sys.float\_info:

```
>>> sys.float_info[1]  # indexed access
1024
>>> sys.float_info.max_exp  # named field access
1024
>>> isinstance(sys.float_info, tuple)  # kind of tuple
True
```

Certains *n-uplets nommés* sont des types natifs (comme les exemples ci-dessus). Sinon, un *n-uplet nommé* peut être créé à partir d'une définition de classe habituelle qui hérite de tuple et qui définit les champs nommés. Une telle classe peut être écrite à la main ou être créée avec la fonction collections.namedtuple (). Cette dernière méthode ajoute des méthodes supplémentaires qui ne seront pas trouvées dans celles écrites à la main ni dans les n-uplets nommés natifs.

- espace de nommage L'endroit où une variable est stockée. Les espaces de nommage sont implémentés avec des dictionnaires. Il existe des espaces de nommage globaux, natifs ou imbriqués dans les objets (dans les méthodes). Les espaces de nommage favorisent la modularité car ils permettent d'éviter les conflits de noms. Par exemple, les fonctions builtins.open et os.open() sont différenciées par leurs espaces de nom. Les espaces de nommage aident aussi à la lisibilité et la maintenabilité en rendant clair quel module implémente une fonction. Par exemple, écrire random.seed() ou itertools.islice() affiche clairement que ces fonctions sont implémentées respectivement dans les modules random et itertools.
- **paquet-espace de nommage** Un *paquet* tel que défini dans la **PEP 421** qui ne sert qu'à contenir des sous-paquets. Les paquets-espace de nommage peuvent n'avoir aucune représentation physique et, plus spécifiquement, ne sont pas comme un *paquet classique* puisqu'ils n'ont pas de fichier \_\_init\_\_.py.

  Voir aussi *module*.
- portée imbriquée Possibilité de faire référence à une variable déclarée dans une définition englobante. Typiquement, une fonction définie à l'intérieur d'une autre fonction a accès aux variables de cette dernière. Souvenez-vous cependant que cela ne fonctionne que pour accéder à des variables, pas pour les assigner. Les variables locales sont lues et assignées dans l'espace de nommage le plus proche. Tout comme les variables globales qui sont stockés dans l'espace de nommage global, le mot clef nonlocal permet d'écrire dans l'espace de nommage dans lequel est déclarée la variable.
- **nouvelle classe** Ancien nom pour l'implémentation actuelle des classes, pour tous les objets. Dans les anciennes versions de Python, seules les nouvelles classes pouvaient utiliser les nouvelles fonctionnalités telles que \_\_slots\_\_, les descripteurs, les propriétés, \_\_getattribute\_\_(), les méthodes de classe et les méthodes statiques.
- **objet** N'importe quelle donnée comportant des états (sous forme d'attributs ou d'une valeur) et un comportement (des méthodes). C'est aussi (object) l'ancêtre commun à absolument toutes les *nouvelles classes*.
- **paquet** *module* Python qui peut contenir des sous-modules ou des sous-paquets. Techniquement, un paquet est un module qui possède un attribut \_\_path\_\_.

Voir aussi paquet classique et namespace package.

- **paramètre** Entité nommée dans la définition d'une *fonction* (ou méthode), décrivant un *argument* (ou dans certains cas des arguments) que la fonction accepte. Il existe cinq sortes de paramètres :
  - *positional-or-keyword*: l'argument peut être passé soit par sa *position*, soit en tant que *argument nommé*. C'est le type de paramètre par défaut. Par exemple, *foo* et *bar* dans l'exemple suivant :

```
def func(foo, bar=None): ...
```

— positional-only: définit un argument qui ne peut être fourni que par position. Les paramètres positional-only peuvent être définis en insérant un caractère "/" dans la liste de paramètres de la définition de fonction après eux. Par exemple: posonly1 et posonly2 dans le code suivant:

```
def func(posonly1, posonly2, /, positional_or_keyword): ...
```

— keyword-only: l'argument ne peut être fourni que nommé. Les paramètres keyword-only peuvent être définis en utilisant un seul paramètre var-positional, ou en ajoutant une étoile (\*) seule dans la liste des paramètres avant eux. Par exemple, kw\_only1 et kw\_only2 dans le code suivant:

```
def func(arg, *, kw_only1, kw_only2): ...
```

var-positional: une séquence d'arguments positionnels peut être fournie (en plus de tous les arguments positionnels déjà acceptés par d'autres paramètres). Un tel paramètre peut être défini en préfixant son nom par une \*. Par exemple args ci-après:

```
def func(*args, **kwargs): ...
```

— var-keyword : une quantité arbitraire d'arguments peut être passée, chacun étant nommé (en plus de tous les arguments nommés déjà acceptés par d'autres paramètres). Un tel paramètre est défini en préfixant le nom du paramètre par \*\*. Par exemple, kwargs ci-dessus.

Les paramètres peuvent spécifier des arguments obligatoires ou optionnels, ainsi que des valeurs par défaut pour les arguments optionnels.

280 Annexe A. Glossaire

Voir aussi *argument* dans le glossaire, la question sur la différence entre les arguments et les paramètres dans la FAQ, la classe inspect. Parameter, la section function et la PEP 362.

**entrée de chemin** Emplacement dans le *chemin des importations (import path* en anglais, d'où le *path*) que le *chercheur basé sur les chemins* consulte pour trouver des modules à importer.

**chercheur de chemins** *chercheur* renvoyé par un appelable sur un sys.path\_hooks (c'est-à-dire un *point d'entrée pour la recherche dans path*) qui sait où trouver des modules lorsqu'on lui donne une *entrée de path*.

Voir importlib.abc.PathEntryFinder pour les méthodes qu'un chercheur d'entrée dans path doit implémenter.

**point d'entrée pour la recherche dans** *path* Appelable dans la liste sys.path\_hook qui donne un *chercheur d'entrée dans path* s'il sait où trouver des modules pour une *entrée dans path* donnée.

**chercheur basé sur les chemins** L'un des *chercheurs dans les méta-chemins* par défaut qui cherche des modules dans un *chemin des importations*.

objet simili-chemin Objet représentant un chemin du système de fichiers. Un objet simili-chemin est un objet str ou un objet bytes représentant un chemin ou un objet implémentant le protocole os.PathLike. Un objet qui accepte le protocole os.PathLike peut être converti en un chemin str ou bytes du système de fichiers en appelant la fonction os.fspath().os.fsdecode() et os.fsencode() peuvent être utilisées, respectivement, pour garantir un résultat de type str ou bytes à la place. A été Introduit par la PEP 519.

**PEP** *Python Enhancement Proposal* (Proposition d'amélioration de Python). Une PEP est un document de conception fournissant des informations à la communauté Python ou décrivant une nouvelle fonctionnalité pour Python, ses processus ou son environnement. Les PEP doivent fournir une spécification technique concise et une justification des fonctionnalités proposées.

Les PEP sont censées être les principaux mécanismes pour proposer de nouvelles fonctionnalités majeures, pour recueillir les commentaires de la communauté sur une question et pour documenter les décisions de conception qui sont intégrées en Python. L'auteur du PEP est responsable de l'établissement d'un consensus au sein de la communauté et de documenter les opinions contradictoires.

Voir la PEP 1.

**portion** Jeu de fichiers dans un seul dossier (pouvant être stocké sous forme de fichier zip) qui contribue à l'espace de nommage d'un paquet, tel que défini dans la **PEP 420**.

argument positionnel Voir argument.

**API provisoire** Une API provisoire est une API qui n'offre aucune garantie de rétrocompatibilité (la bibliothèque standard exige la rétrocompatibilité). Bien que des changements majeurs d'une telle interface ne soient pas attendus, tant qu'elle est étiquetée provisoire, des changements cassant la rétrocompatibilité (y compris sa suppression complète) peuvent survenir si les développeurs principaux le jugent nécessaire. Ces modifications ne surviendront que si de sérieux problèmes sont découverts et qu'ils n'avaient pas été identifiés avant l'ajout de l'API.

Même pour les API provisoires, les changements cassant la rétrocompatibilité sont considérés comme des "solutions de dernier recours". Tout ce qui est possible sera fait pour tenter de résoudre les problèmes en conservant la rétrocompatibilité.

Ce processus permet à la bibliothèque standard de continuer à évoluer avec le temps, sans se bloquer longtemps sur des erreurs d'architecture. Voir la PEP 411 pour plus de détails.

paquet provisoire Voir provisional API.

**Python 3000** Surnom donné à la série des Python 3.x (très vieux surnom donné à l'époque où Python 3 représentait un futur lointain). Aussi abrégé *Py3k*.

**Pythonique** Idée, ou bout de code, qui colle aux idiomes de Python plutôt qu'aux concepts communs rencontrés dans d'autres langages. Par exemple, il est idiomatique en Python de parcourir les éléments d'un itérable en utilisant for. Beaucoup d'autres langages n'ont pas cette possibilité, donc les gens qui ne sont pas habitués à Python utilisent parfois un compteur numérique à la place :

```
for i in range(len(food)):
    print(food[i])
```

Plutôt qu'utiliser la méthode, plus propre et élégante, donc Pythonique :

```
for piece in food:
   print(piece)
```

**nom qualifié** Nom, comprenant des points, montrant le "chemin" de l'espace de nommage global d'un module vers une classe, fonction ou méthode définie dans ce module, tel que défini dans la **PEP 3155**. Pour les fonctions et classes de premier niveau, le nom qualifié est le même que le nom de l'objet :

```
>>> class C:
...     class D:
...     def meth(self):
...     pass
...
>>> C.__qualname__
'C'
>>> C.D.__qualname__
'C.D'
>>> C.D.meth.__qualname__
'C.D.meth'
```

Lorsqu'il est utilisé pour nommer des modules, le *nom qualifié complet (fully qualified name - FQN* en anglais) signifie le chemin complet (séparé par des points) vers le module, incluant tous les paquets parents. Par exemple : email.mime.text:

```
>>> import email.mime.text
>>> email.mime.text.__name__
'email.mime.text'
```

nombre de références Nombre de références à un objet. Lorsque le nombre de références à un objet descend à zéro, l'objet est désalloué. Le comptage de référence n'est généralement pas visible dans le code Python, mais c'est un élément clé de l'implémentation *CPython*. Les développeurs peuvent utiliser la fonction sys.getrefcount () pour obtenir le nombre de références à un objet donné.

**paquet classique** *paquet* traditionnel, tel qu'un dossier contenant un fichier \_\_init\_\_.py. Voir aussi *paquet-espace de nommage*.

**\_\_slots**\_\_ Déclaration dans une classe qui économise de la mémoire en pré-allouant de l'espace pour les attributs des instances et qui élimine le dictionnaire (des attributs) des instances. Bien que populaire, cette technique est difficile à maîtriser et devrait être réservée à de rares cas où un grand nombre d'instances dans une application devient un sujet critique pour la mémoire.

**séquence** *itérable* qui offre un accès efficace à ses éléments par un indice sous forme de nombre entier via la méthode spéciale \_\_getitem\_\_() et qui définit une méthode \_\_len\_\_() donnant sa taille. Voici quelques séquences natives : list, str, tuple, et bytes. Notez que dict possède aussi une méthode \_\_getitem\_\_() et une méthode \_\_len\_\_(), mais il est considéré comme un *mapping* plutôt qu'une séquence, car ses accès se font par une clé arbitraire *immuable* plutôt qu'un nombre entier.

La classe abstraite de base collections.abc.Sequence définit une interface plus riche qui va au-delà des simples \_\_getitem\_\_() et \_\_len\_\_(), en ajoutant count(), index(), \_\_contains\_\_() et \_\_reversed\_\_(). Les types qui implémentent cette interface étendue peuvent s'enregistrer explicitement en utilisant register().

ensemble en compréhension (ou ensemble en intension) Une façon compacte de traiter tout ou partie des éléments d'un itérable et de renvoyer un set avec les résultats. results = {c for c in 'abracadabra' if c not in 'abc'} génère l'ensemble contenant les lettres « r » et « d » { 'r', 'd'}. Voir comprehensions.

**distribution simple** Forme de distribution, comme les *fonction génériques*, où l'implémentation est choisie en fonction du type d'un seul argument.

**tranche** (*slice* en anglais), un objet contenant habituellement une portion de *séquence*. Une tranche est créée en utilisant la notation [] avec des : entre les nombres lorsque plusieurs sont fournis, comme dans variable\_name[1:3:5]. Cette notation utilise des objets slice en interne.

282 Annexe A. Glossaire

**méthode spéciale** (*special method* en anglais) Méthode appelée implicitement par Python pour exécuter une opération sur un type, comme une addition. De telles méthodes ont des noms commençant et terminant par des doubles tirets bas. Les méthodes spéciales sont documentées dans specialnames.

**instruction** Une instruction (*statement* en anglais) est un composant d'un "bloc" de code. Une instruction est soit une *expression*, soit une ou plusieurs constructions basées sur un mot-clé, comme if, while ou for.

**référence forte** Dans l'API C de Python, une référence forte est une référence vers un objet qui incrémente son compteur de références lorsqu'elle est créée et le décrémente lorsqu'elle est effacée.

Une référence forte est créée à l'aide de la fonction  $Py\_NewRef()$ . Il faut normalement appeler  $Py\_DECREF()$  dessus avant de sortir de sa portée lexicale, sans quoi il y a une fuite de référence.

Voir aussi référence empruntée.

encodages de texte Une chaîne de caractères en Python est une suite de points de code Unicode (dans l'intervalle U+0000--U+10FFFF). Pour stocker ou transmettre une chaîne, il est nécessaire de la sérialiser en suite d'octets. Sérialiser une chaîne de caractères en une suite d'octets s'appelle « encoder » et recréer la chaîne à partir de la suite d'octets s'appelle « décoder ».

Il existe de multiples codecs pour la sérialisation de texte, que l'on regroupe sous l'expression « encodages de texte ».

**fichier texte** *Objet fichier* capable de lire et d'écrire des objets str. Souvent, un fichier texte (*text file* en anglais) accède en fait à un flux de donnée en octets et gère l'*encodage de texte* automatiquement. Des exemples de fichiers textes sont les fichiers ouverts en mode texte ('r' ou 'w'), sys.stdin, sys.stdout et les instances de io.StringIO.

Voir aussi fichier binaire pour un objet fichier capable de lire et d'écrire des objets octets-compatibles.

**chaîne entre triple guillemets** Chaîne qui est délimitée par trois guillemets simples (') ou trois guillemets doubles ("). Bien qu'elle ne fournisse aucune fonctionnalité qui ne soit pas disponible avec une chaîne entre guillemets, elle est utile pour de nombreuses raisons. Elle vous autorise à insérer des guillemets simples et doubles dans une chaîne sans avoir à les protéger et elle peut s'étendre sur plusieurs lignes sans avoir à terminer chaque ligne par un \. Elle est ainsi particulièrement utile pour les chaînes de documentation (*docstrings*).

type Le type d'un objet Python détermine quel genre d'objet c'est. Tous les objets ont un type. Le type d'un objet peut être obtenu via son attribut \_\_class\_\_ ou via type (obj).

alias de type Synonyme d'un type, créé en affectant le type à un identifiant.

Les alias de types sont utiles pour simplifier les *indications de types*. Par exemple :

pourrait être rendu plus lisible comme ceci :

```
Color = tuple[int, int, int]

def remove_gray_shades(colors: list[Color]) -> list[Color]:
    pass
```

Voir typing et la PEP 484, qui décrivent cette fonctionnalité.

**indication de type** L'*annotation* qui spécifie le type attendu pour une variable, un attribut de classe, un paramètre de fonction ou une valeur de retour.

Les indications de type sont facultatives et ne sont pas indispensables à l'interpréteur Python, mais elles sont utiles aux outils d'analyse de type statique et aident les IDE à compléter et à réusiner (*code refactoring* en anglais) le code.

Les indications de type de variables globales, d'attributs de classe et de fonctions, mais pas de variables locales, peuvent être consultées en utilisant typing.get\_type\_hints().

Voir typing et la PEP 484, qui décrivent cette fonctionnalité.

retours à la ligne universels Une manière d'interpréter des flux de texte dans lesquels sont reconnues toutes les fins de ligne suivantes : la convention Unix '\n', la convention Windows '\r\n' et l'ancienne convention Macintosh '\r'. Voir la PEP 278 et la PEP 3116, ainsi que la fonction bytes.splitlines() pour d'autres usages.

**annotation de variable** annotation d'une variable ou d'un attribut de classe.

Lorsque vous annotez une variable ou un attribut de classe, l'affectation est facultative :

```
class C:
    field: 'annotation'
```

Les annotations de variables sont généralement utilisées pour des *indications de types* : par exemple, cette variable devrait prendre des valeurs de type int :

```
count: int = 0
```

La syntaxe d'annotation de variable est expliquée dans la section annassign.

Reportez-vous à *annotation de fonction*, à la **PEP 484** et à la **PEP 526** qui décrivent cette fonctionnalité. Voir aussi annotations-howto sur les bonnes pratiques concernant les annotations.

**environnement virtuel** Environnement d'exécution isolé (en mode coopératif) qui permet aux utilisateurs de Python et aux applications d'installer et de mettre à jour des paquets sans interférer avec d'autres applications Python fonctionnant sur le même système.

Voir aussi venv.

**machine virtuelle** Ordinateur défini entièrement par du logiciel. La machine virtuelle (*virtual machine*) de Python exécute le *code intermédiaire* produit par le compilateur de *bytecode*.

Le zen de Python Liste de principes et de préceptes utiles pour comprendre et utiliser le langage. Cette liste peut être obtenue en tapant "import this" dans une invite Python interactive.

284 Annexe A. Glossaire

## À propos de ces documents

Ces documents sont générés à partir de sources en reStructuredText par Sphinx, un analyseur de documents spécialement conçu pour la documentation Python.

Le développement de la documentation et de ses outils est entièrement basé sur le volontariat, tout comme Python. Si vous voulez contribuer, allez voir la page reporting-bugs qui contient des informations pour vous y aider. Les nouveaux volontaires sont toujours les bienvenus!

#### Merci beaucoup à :

- Fred L. Drake, Jr., créateur des outils originaux de la documentation Python et rédacteur de la plupart de son contenu:
- le projet Docutils pour avoir créé reStructuredText et la suite d'outils Docutils;
- Fredrik Lundh pour son projet *Alternative Python Reference*, dont Sphinx a pris beaucoup de bonnes idées.

# **B.1 Contributeurs de la documentation Python**

De nombreuses personnes ont contribué au langage Python, à sa bibliothèque standard et à sa documentation. Consultez Misc/ACKS dans les sources de la distribution Python pour avoir une liste partielle des contributeurs.

Ce n'est que grâce aux suggestions et contributions de la communauté Python que Python a une documentation si merveilleuse — Merci!

# ANNEXE C

Histoire et licence

## C.1 Histoire du logiciel

Python a été créé au début des années 1990 par Guido van Rossum, au Stichting Mathematisch Centrum (CWI, voir https://www.cwi.nl/) aux Pays-Bas en tant que successeur d'un langage appelé ABC. Guido est l'auteur principal de Python, bien qu'il inclut de nombreuses contributions de la part d'autres personnes.

En 1995, Guido continua son travail sur Python au Corporation for National Research Initiatives (CNRI, voir https://www.cnri.reston.va.us/) de Reston, en Viriginie, d'où il diffusa plusieurs versions du logiciel.

En mai 2000, Guido et l'équipe de développement centrale de Python sont partis vers BeOpen.com pour former l'équipe BeOpen PythonLabs. En octobre de la même année, l'équipe de PythonLabs est partie vers Digital Creations (désormais Zope Corporation; voir https://www.zope.com/). En 2001, la Python Software Foundation (PSF, voir https://www.python.org/psf/) voit le jour. Il s'agit d'une organisation à but non lucratif détenant les droits de propriété intellectuelle de Python. Zope Corporation en est un sponsor.

Toutes les versions de Python sont Open Source (voir https://www.opensource.org/ pour la définition d'Open Source). Historiquement, la plupart, mais pas toutes, des versions de Python ont également été compatible avec la GPL, le tableau ci-dessous résume les différentes versions.

Version	Dérivé de	Année	Propriétaire	Compatible avec la GPL?
0.9.0 à 1.2	n/a	1991-1995	CWI	oui
1.3 à 1.5.2	1.2	1995-1999	CNRI	oui
1.6	1.5.2	2000	CNRI	non
2.0	1.6	2000	BeOpen.com	non
1.6.1	1.6	2001	CNRI	non
2.1	2.0+1.6.1	2001	PSF	non
2.0.1	2.0+1.6.1	2001	PSF	oui
2.1.1	2.1+2.0.1	2001	PSF	oui
2.1.2	2.1.1	2002	PSF	oui
2.1.3	2.1.2	2002	PSF	oui
2.2 et ultérieure	2.1.1	2001-maintenant	PSF	oui

**Note:** Compatible GPL ne signifie pas que nous distribuons Python sous licence GPL. Toutes les licences Python, excepté la licence GPL, vous permettent la distribution d'une version modifiée sans rendre open source ces changements. La licence « compatible GPL » rend possible la diffusion de Python avec un autre logiciel qui est lui, diffusé sous la licence GPL; les licences « non-compatibles GPL » ne le peuvent pas.

Merci aux nombreux bénévoles qui ont travaillé sous la direction de Guido pour rendre ces versions possibles.

## C.2 Conditions générales pour accéder à, ou utiliser, Python

Le logiciel Python et sa documentation sont distribués sous la licence d'utilisation PSF.

Depuis Python 3.8.6, les exemples, recettes et autres codes présents dans la documentation sont sous la double licence d'utilisation PSF et *la licence Zero-Clause BSD*.

Certains logiciels faisant partie de Python sont soumis à d'autres licences. Ces licences sont incluses avec le code lié à celles-ci. Voir *Licences et remerciements pour les logiciels tiers* pour une liste non exhaustive de ces licences.

#### C.2.1 PSF LICENSE AGREEMENT FOR PYTHON 3.11.3

- 1. This LICENSE AGREEMENT is between the Python Software Foundation ("PSF"),  $\Box$  and
- the Individual or Organization ("Licensee") accessing and otherwise using  $\rightarrow$  Python
  - 3.11.3 software in source or binary form and its associated documentation.
- $\rightarrow$ reproduce,
  - analyze, test, perform and/or display publicly, prepare derivative works, distribute, and otherwise use Python 3.11.3 alone or in any derivative version, provided, however, that PSF's License Agreement and PSF's notice.
- copyright, i.e., "Copyright © 2001-2023 Python Software Foundation; All- $\rightarrow$ Rights
  - Reserved" are retained in Python 3.11.3 alone or in any derivative version prepared by Licensee.
- 3. In the event Licensee prepares a derivative work that is based on or incorporates Python 3.11.3 or any part thereof, and wants to make the derivative work available to others as provided herein, then Licensee.
- agrees to include in any such work a brief summary of the changes made to→ Python 3.11.3.
- 4. PSF is making Python 3.11.3 available to Licensee on an "AS IS" basis.
  PSF MAKES NO REPRESENTATIONS OR WARRANTIES, EXPRESS OR IMPLIED. BY WAY OF
  EXAMPLE, BUT NOT LIMITATION, PSF MAKES NO AND DISCLAIMS ANY REPRESENTATION.
- WARRANTY OF MERCHANTABILITY OR FITNESS FOR ANY PARTICULAR PURPOSE OR THAT— THE

USE OF PYTHON 3.11.3 WILL NOT INFRINGE ANY THIRD PARTY RIGHTS.

5. PSF SHALL NOT BE LIABLE TO LICENSEE OR ANY OTHER USERS OF PYTHON 3.11.3 FOR ANY INCIDENTAL, SPECIAL, OR CONSEQUENTIAL DAMAGES OR LOSS AS A RESULT.

MODIFYING, DISTRIBUTING, OR OTHERWISE USING PYTHON 3.11.3, OR ANY-DERIVATIVE THEREOF, EVEN IF ADVISED OF THE POSSIBILITY THEREOF.

6. This License Agreement will automatically terminate upon a material breach  ${ \leadsto } \text{of}$ 

its terms and conditions.

- 7. Nothing in this License Agreement shall be deemed to create any—relationship
- of agency, partnership, or joint venture between PSF and Licensee. This—License

Agreement does not grant permission to use PSF trademarks or trade name in...

trademark sense to endorse or promote products or services of Licensee, or →any
third party.

8. By copying, installing or otherwise using Python 3.11.3, Licensee agrees to be bound by the terms and conditions of this License Agreement.

#### C.2.2 LICENCE D'UTILISATION BEOPEN.COM POUR PYTHON 2.0

#### LICENCE D'UTILISATION LIBRE BEOPEN PYTHON VERSION 1

- 1. This LICENSE AGREEMENT is between BeOpen.com ("BeOpen"), having an office at 160 Saratoga Avenue, Santa Clara, CA 95051, and the Individual or Organization ("Licensee") accessing and otherwise using this software in source or binary form and its associated documentation ("the Software").
- 2. Subject to the terms and conditions of this BeOpen Python License Agreement, BeOpen hereby grants Licensee a non-exclusive, royalty-free, world-wide license to reproduce, analyze, test, perform and/or display publicly, prepare derivative works, distribute, and otherwise use the Software alone or in any derivative version, provided, however, that the BeOpen Python License is retained in the Software, alone or in any derivative version prepared by Licensee.
- 3. BeOpen is making the Software available to Licensee on an "AS IS" basis.
  BEOPEN MAKES NO REPRESENTATIONS OR WARRANTIES, EXPRESS OR IMPLIED. BY WAY OF
  EXAMPLE, BUT NOT LIMITATION, BEOPEN MAKES NO AND DISCLAIMS ANY REPRESENTATION OR
  WARRANTY OF MERCHANTABILITY OR FITNESS FOR ANY PARTICULAR PURPOSE OR THAT THE
  USE OF THE SOFTWARE WILL NOT INFRINGE ANY THIRD PARTY RIGHTS.
- 4. BEOPEN SHALL NOT BE LIABLE TO LICENSEE OR ANY OTHER USERS OF THE SOFTWARE FOR ANY INCIDENTAL, SPECIAL, OR CONSEQUENTIAL DAMAGES OR LOSS AS A RESULT OF USING, MODIFYING OR DISTRIBUTING THE SOFTWARE, OR ANY DERIVATIVE THEREOF, EVEN IF ADVISED OF THE POSSIBILITY THEREOF.
- 5. This License Agreement will automatically terminate upon a material breach of

its terms and conditions.

- 6. This License Agreement shall be governed by and interpreted in all respects by the law of the State of California, excluding conflict of law provisions. Nothing in this License Agreement shall be deemed to create any relationship of agency, partnership, or joint venture between BeOpen and Licensee. This License Agreement does not grant permission to use BeOpen trademarks or trade names in a trademark sense to endorse or promote products or services of Licensee, or any third party. As an exception, the "BeOpen Python" logos available at http://www.pythonlabs.com/logos.html may be used according to the permissions granted on that web page.
- 7. By copying, installing or otherwise using the software, Licensee agrees to be bound by the terms and conditions of this License Agreement.

#### C.2.3 LICENCE D'UTILISATION CNRI POUR PYTHON 1.6.1

- 1. This LICENSE AGREEMENT is between the Corporation for National Research Initiatives, having an office at 1895 Preston White Drive, Reston, VA 20191 ("CNRI"), and the Individual or Organization ("Licensee") accessing and otherwise using Python 1.6.1 software in source or binary form and its associated documentation.
- 2. Subject to the terms and conditions of this License Agreement, CNRI hereby grants Licensee a nonexclusive, royalty-free, world-wide license to reproduce, analyze, test, perform and/or display publicly, prepare derivative works, distribute, and otherwise use Python 1.6.1 alone or in any derivative version, provided, however, that CNRI's License Agreement and CNRI's notice of copyright, i.e., "Copyright © 1995-2001 Corporation for National Research Initiatives; All Rights Reserved" are retained in Python 1.6.1 alone or in any derivative version prepared by Licensee. Alternately, in lieu of CNRI's License Agreement, Licensee may substitute the following text (omitting the quotes): "Python 1.6.1 is made available subject to the terms and conditions in CNRI's License Agreement. This Agreement together with Python 1.6.1 may be located on the internet using the following unique, persistent identifier (known as a handle): 1895.22/1013. This Agreement may also be obtained from a proxy server on the internet using the following URL: http://hdd.handle.net/1895.22/1013."
- 3. In the event Licensee prepares a derivative work that is based on or incorporates Python 1.6.1 or any part thereof, and wants to make the derivative work available to others as provided herein, then Licensee hereby agrees to include in any such work a brief summary of the changes made to Python 1.6.1.
- 4. CNRI is making Python 1.6.1 available to Licensee on an "AS IS" basis. CNRI MAKES NO REPRESENTATIONS OR WARRANTIES, EXPRESS OR IMPLIED. BY WAY OF EXAMPLE, BUT NOT LIMITATION, CNRI MAKES NO AND DISCLAIMS ANY REPRESENTATION OR WARRANTY OF MERCHANTABILITY OR FITNESS FOR ANY PARTICULAR PURPOSE OR THAT THE USE OF PYTHON 1.6.1 WILL NOT INFRINGE ANY THIRD PARTY RIGHTS.
- 5. CNRI SHALL NOT BE LIABLE TO LICENSEE OR ANY OTHER USERS OF PYTHON 1.6.1 FOR ANY INCIDENTAL, SPECIAL, OR CONSEQUENTIAL DAMAGES OR LOSS AS A RESULT OF MODIFYING, DISTRIBUTING, OR OTHERWISE USING PYTHON 1.6.1, OR ANY DERIVATIVE THEREOF, EVEN IF ADVISED OF THE POSSIBILITY THEREOF.

- 6. This License Agreement will automatically terminate upon a material breach of its terms and conditions.
- 7. This License Agreement shall be governed by the federal intellectual property law of the United States, including without limitation the federal copyright law, and, to the extent such U.S. federal law does not apply, by the law of the Commonwealth of Virginia, excluding Virginia's conflict of law provisions. Notwithstanding the foregoing, with regard to derivative works based on Python 1.6.1 that incorporate non-separable material that was previously distributed under the GNU General Public License (GPL), the law of the Commonwealth of Virginia shall govern this License Agreement only as to issues arising under or with respect to Paragraphs 4, 5, and 7 of this License Agreement. Nothing in this License Agreement shall be deemed to create any relationship of agency, partnership, or joint venture between CNRI and Licensee. This License Agreement does not grant permission to use CNRI trademarks or trade name in a trademark sense to endorse or promote products or services of Licensee, or any third party.
- 8. By clicking on the "ACCEPT" button where indicated, or by copying, installing or otherwise using Python 1.6.1, Licensee agrees to be bound by the terms and conditions of this License Agreement.

#### C.2.4 LICENCE D'UTILISATION CWI POUR PYTHON 0.9.0 à 1.2

Copyright © 1991 - 1995, Stichting Mathematisch Centrum Amsterdam, The Netherlands. All rights reserved.

Permission to use, copy, modify, and distribute this software and its documentation for any purpose and without fee is hereby granted, provided that the above copyright notice appear in all copies and that both that copyright notice and this permission notice appear in supporting documentation, and that the name of Stichting Mathematisch Centrum or CWI not be used in advertising or publicity pertaining to distribution of the software without specific, written prior permission.

STICHTING MATHEMATISCH CENTRUM DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS, IN NO EVENT SHALL STICHTING MATHEMATISCH CENTRUM BE LIABLE FOR ANY SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

# C.2.5 LICENCE BSD ZERO-CLAUSE POUR LE CODE DANS LA DOCUMENTATION DE PYTHON 3.11.3

Permission to use, copy, modify, and/or distribute this software for any purpose with or without fee is hereby granted.

THE SOFTWARE IS PROVIDED "AS IS" AND THE AUTHOR DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS. IN NO EVENT SHALL THE AUTHOR BE LIABLE FOR ANY SPECIAL, DIRECT,

INDIRECT, OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

## C.3 Licences et remerciements pour les logiciels tiers

Cette section est une liste incomplète mais grandissante de licences et remerciements pour les logiciels tiers incorporés dans la distribution de Python.

#### C.3.1 Mersenne twister

Le module \_random inclut du code construit à partir d'un téléchargement depuis http://www.math.sci.hiroshima-u.ac. jp/~m-mat/MT/MT2002/emt19937ar.html. Voici mot pour mot les commentaires du code original :

A C-program for MT19937, with initialization improved 2002/1/26. Coded by Takuji Nishimura and Makoto Matsumoto.

Before using, initialize the state by using init\_genrand(seed) or init\_by\_array(init\_key, key\_length).

Copyright (C) 1997 - 2002, Makoto Matsumoto and Takuji Nishimura, All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- The names of its contributors may not be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS
"AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT
LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR
A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR
CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL,
EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO,
PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR
PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF
LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING
NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS
SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

Any feedback is very welcome. http://www.math.sci.hiroshima-u.ac.jp/~m-mat/MT/emt.html email: m-mat @ math.sci.hiroshima-u.ac.jp (remove space)

## C.3.2 Interfaces de connexion (sockets)

The socket module uses the functions, getaddrinfo(), and getnameinfo(), which are coded in separate source files from the WIDE Project, https://www.wide.ad.jp/.

Copyright (C) 1995, 1996, 1997, and 1998 WIDE Project. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- Neither the name of the project nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE PROJECT AND CONTRIBUTORS ``AS IS'' AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE PROJECT OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

## C.3.3 Interfaces de connexion asynchrones

Les modules asynchat et asyncore contiennent la note suivante :

Copyright 1996 by Sam Rushing

All Rights Reserved

Permission to use, copy, modify, and distribute this software and its documentation for any purpose and without fee is hereby granted, provided that the above copyright notice appear in all copies and that both that copyright notice and this permission notice appear in supporting documentation, and that the name of Sam Rushing not be used in advertising or publicity pertaining to distribution of the software without specific, written prior permission.

SAM RUSHING DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS, IN NO EVENT SHALL SAM RUSHING BE LIABLE FOR ANY SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

## C.3.4 Gestion de témoin (cookie)

Le module http.cookies contient la note suivante :

```
Copyright 2000 by Timothy O'Malley <timo@alum.mit.edu>
```

All Rights Reserved

Permission to use, copy, modify, and distribute this software and its documentation for any purpose and without fee is hereby granted, provided that the above copyright notice appear in all copies and that both that copyright notice and this permission notice appear in supporting documentation, and that the name of Timothy O'Malley not be used in advertising or publicity pertaining to distribution of the software without specific, written prior permission.

Timothy O'Malley DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS, IN NO EVENT SHALL Timothy O'Malley BE LIABLE FOR ANY SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

## C.3.5 Traçage d'exécution

Le module trace contient la note suivante :

```
portions copyright 2001, Autonomous Zones Industries, Inc., all rights...
err... reserved and offered to the public under the terms of the
Python 2.2 license.
Author: Zooko O'Whielacronx
http://zooko.com/
mailto:zooko@zooko.com

Copyright 2000, Mojam Media, Inc., all rights reserved.
Author: Skip Montanaro

Copyright 1999, Bioreason, Inc., all rights reserved.
Author: Andrew Dalke

Copyright 1995-1997, Automatrix, Inc., all rights reserved.
Author: Skip Montanaro
```

Copyright 1991-1995, Stichting Mathematisch Centrum, all rights reserved.

Permission to use, copy, modify, and distribute this Python software and its associated documentation for any purpose without fee is hereby granted, provided that the above copyright notice appears in all copies, and that both that copyright notice and this permission notice appear in supporting documentation, and that the name of neither Automatrix, Bioreason or Mojam Media be used in advertising or publicity pertaining to distribution of the software without specific, written prior permission.

#### C.3.6 Les fonctions UUencode et UUdecode

Le module 1111 contient la note suivante :

Copyright 1994 by Lance Ellinghouse Cathedral City, California Republic, United States of America. All Rights Reserved

Permission to use, copy, modify, and distribute this software and its documentation for any purpose and without fee is hereby granted, provided that the above copyright notice appear in all copies and that both that copyright notice and this permission notice appear in supporting documentation, and that the name of Lance Ellinghouse not be used in advertising or publicity pertaining to distribution of the software without specific, written prior permission.

LANCE ELLINGHOUSE DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS, IN NO EVENT SHALL LANCE ELLINGHOUSE CENTRUM BE LIABLE FOR ANY SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

Modified by Jack Jansen, CWI, July 1995:

- Use binascii module to do the actual line-by-line conversion between ascii and binary. This results in a 1000-fold speedup. The C version is still 5 times faster, though.
- Arguments more compliant with Python standard

## C.3.7 Appel de procédures distantes en XML (RPC, pour Remote Procedure Call)

Le module xmlrpc.client contient la note suivante :

```
The XML-RPC client interface is

Copyright (c) 1999-2002 by Secret Labs AB
Copyright (c) 1999-2002 by Fredrik Lundh
```

By obtaining, using, and/or copying this software and/or its associated documentation, you agree that you have read, understood, and will comply with the following terms and conditions:

Permission to use, copy, modify, and distribute this software and its associated documentation for any purpose and without fee is hereby granted, provided that the above copyright notice appears in all copies, and that both that copyright notice and this permission notice appear in supporting documentation, and that the name of Secret Labs AB or the author not be used in advertising or publicity pertaining to distribution of the software without specific, written prior permission.

SECRET LABS AB AND THE AUTHOR DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANT-ABILITY AND FITNESS. IN NO EVENT SHALL SECRET LABS AB OR THE AUTHOR BE LIABLE FOR ANY SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

## C.3.8 test\_epoll

#### Le module test\_epoll contient la note suivante :

Copyright (c) 2001-2006 Twisted Matrix Laboratories.

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

## C.3.9 Select kqueue

#### Le module select contient la note suivante pour l'interface kqueue :

Copyright (c) 2000 Doug White, 2006 James Knight, 2007 Christian Heimes All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

THIS SOFTWARE IS PROVIDED BY THE AUTHOR AND CONTRIBUTORS ``AS IS'' AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

## C.3.10 SipHash24

Le fichier Python/pyhash.c contient une implémentation par Marek Majkowski de l'algorithme SipHash24 de Dan Bernstein. Il contient la note suivante :

```
<MIT License>
Copyright (c) 2013 Marek Majkowski <marek@popcount.org>
Permission is hereby granted, free of charge, to any person obtaining a copy
of this software and associated documentation files (the "Software"), to deal
in the Software without restriction, including without limitation the rights
to use, copy, modify, merge, publish, distribute, sublicense, and/or sell
copies of the Software, and to permit persons to whom the Software is
furnished to do so, subject to the following conditions:
The above copyright notice and this permission notice shall be included in
all copies or substantial portions of the Software.
</MIT License>
Original location:
  https://github.com/majek/csiphash/
Solution inspired by code from:
   Samuel Neves (supercop/crypto_auth/siphash24/little)
  djb (supercop/crypto_auth/siphash24/little2)
   Jean-Philippe Aumasson (https://131002.net/siphash/siphash24.c)
```

#### C.3.11 strtod et dtoa

The file Python/dtoa.c, which supplies C functions dtoa and strtod for conversion of C doubles to and from strings, is derived from the file of the same name by David M. Gay, currently available from https://web.archive.org/web/ 20220517033456/http://www.netlib.org/fp/dtoa.c. The original file, as retrieved on March 16, 2009, contains the following copyright and licensing notice:

```
/*********************
* The author of this software is David M. Gay.
* Copyright (c) 1991, 2000, 2001 by Lucent Technologies.
* Permission to use, copy, modify, and distribute this software for any
* purpose without fee is hereby granted, provided that this entire notice
* is included in all copies of any software which is or includes a copy
^{\star} or modification of this software and in all copies of the supporting
* documentation for such software.
* THIS SOFTWARE IS BEING PROVIDED "AS IS", WITHOUT ANY EXPRESS OR IMPLIED
* WARRANTY. IN PARTICULAR, NEITHER THE AUTHOR NOR LUCENT MAKES ANY
* REPRESENTATION OR WARRANTY OF ANY KIND CONCERNING THE MERCHANTABILITY
* OF THIS SOFTWARE OR ITS FITNESS FOR ANY PARTICULAR PURPOSE.
******************
```

## C.3.12 OpenSSL

Les modules hashlib, posix, ssl, et crypt utilisent la bibliothèque OpenSSL pour améliorer les performances, si elle est disponible via le système d'exploitation. Aussi les outils d'installation sur Windows et macOS peuvent inclure une copie des bibliothèques d'OpenSSL, donc on colle une copie de la licence d'OpenSSL ici :

```
LICENSE ISSUES
_____
The OpenSSL toolkit stays under a dual license, i.e. both the conditions of
the OpenSSL License and the original SSLeay license apply to the toolkit.
See below for the actual license texts. Actually both licenses are BSD-style
Open Source licenses. In case of any license issues related to OpenSSL
please contact openssl-core@openssl.org.
OpenSSL License
  /* _______
   * Copyright (c) 1998-2008 The OpenSSL Project. All rights reserved.
   * Redistribution and use in source and binary forms, with or without
   * modification, are permitted provided that the following conditions
   * are met:
   * 1. Redistributions of source code must retain the above copyright
       notice, this list of conditions and the following disclaimer.
   * 2. Redistributions in binary form must reproduce the above copyright
       notice, this list of conditions and the following disclaimer in
```

```
the documentation and/or other materials provided with the
         distribution.
    ^{\star} 3. All advertising materials mentioning features or use of this
         software must display the following acknowledgment:
         "This product includes software developed by the OpenSSL Project
         for use in the OpenSSL Toolkit. (http://www.openssl.org/)"
    * 4. The names "OpenSSL Toolkit" and "OpenSSL Project" must not be used to
        endorse or promote products derived from this software without
        prior written permission. For written permission, please contact
        openssl-core@openssl.org.
    * 5. Products derived from this software may not be called "OpenSSL"
        nor may "OpenSSL" appear in their names without prior written
        permission of the OpenSSL Project.
    ^{\star} 6. Redistributions of any form whatsoever must retain the following
         acknowledgment:
         "This product includes software developed by the OpenSSL Project
        for use in the OpenSSL Toolkit (http://www.openssl.org/)"
    * THIS SOFTWARE IS PROVIDED BY THE OpenSSL PROJECT ``AS IS'' AND ANY
    * EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE
    * IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR
    * PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE OpenSSL PROJECT OR
    * ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL,
    * SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT
    * NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES;
    * LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION)
    * HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT,
    * STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE)
    * ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED
    * OF THE POSSIBILITY OF SUCH DAMAGE.
    * This product includes cryptographic software written by Eric Young
    ^{\star} (eay@cryptsoft.com). This product includes software written by Tim
    * Hudson (tjh@cryptsoft.com).
    * /
Original SSLeay License
   /* Copyright (C) 1995-1998 Eric Young (eay@cryptsoft.com)
    * All rights reserved.
    ^{\star} This package is an SSL implementation written
    * by Eric Young (eay@cryptsoft.com).
    * The implementation was written so as to conform with Netscapes SSL.
    * This library is free for commercial and non-commercial use as long as
    * the following conditions are aheared to. The following conditions
    * apply to all code found in this distribution, be it the RC4, RSA,
    * lhash, DES, etc., code; not just the SSL code. The SSL documentation
    * included with this distribution is covered by the same copyright terms
```

```
* except that the holder is Tim Hudson (tjh@cryptsoft.com).
* Copyright remains Eric Young's, and as such any Copyright notices in
* the code are not to be removed.
* If this package is used in a product, Eric Young should be given attribution
* as the author of the parts of the library used.
* This can be in the form of a textual message at program startup or
* in documentation (online or textual) provided with the package.
* Redistribution and use in source and binary forms, with or without
* modification, are permitted provided that the following conditions
* are met:
* 1. Redistributions of source code must retain the copyright
    notice, this list of conditions and the following disclaimer.
* 2. Redistributions in binary form must reproduce the above copyright
    notice, this list of conditions and the following disclaimer in the
     documentation and/or other materials provided with the distribution.
 3. All advertising materials mentioning features or use of this software
     must display the following acknowledgement:
     "This product includes cryptographic software written by
     Eric Young (eay@cryptsoft.com) "
    The word 'cryptographic' can be left out if the rouines from the library
    being used are not cryptographic related :-).
* 4. If you include any Windows specific code (or a derivative thereof) from
     the apps directory (application code) you must include an acknowledgement:
     "This product includes software written by Tim Hudson (tjh@cryptsoft.com)"
* THIS SOFTWARE IS PROVIDED BY ERIC YOUNG ``AS IS'' AND
* ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE
* IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE
* ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR OR CONTRIBUTORS BE LIABLE
* FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL
* DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS
* OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION)
* HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT
* LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY
* OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF
* SUCH DAMAGE.
* The licence and distribution terms for any publically available version or
* derivative of this code cannot be changed. i.e. this code cannot simply be
* copied and put under another distribution licence
* [including the GNU Public Licence.]
```

## **C.3.13** expat

Le module pyexpat est compilé avec une copie des sources d'*expat*, sauf si la compilation est configurée avec --with-system-expat:

```
Copyright (c) 1998, 1999, 2000 Thai Open Source Software Center Ltd
and Clark Cooper

Permission is hereby granted, free of charge, to any person obtaining
a copy of this software and associated documentation files (the
```

"Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

#### C.3.14 libffi

Le module \_ctypes est compilé en utilisant une copie des sources de la *libffi*, sauf si la compilation est configurée avec --with-system-libffi:

Copyright (c) 1996-2008 Red Hat, Inc and others.

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the ``Software''), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED ``AS IS'', WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

#### C.3.15 zlib

Le module zlib est compilé en utilisant une copie du code source de *zlib* si la version de *zlib* trouvée sur le système est trop vieille pour être utilisée :

Copyright (C) 1995-2011 Jean-loup Gailly and Mark Adler

This software is provided 'as-is', without any express or implied warranty. In no event will the authors be held liable for any damages arising from the use of this software.

Permission is granted to anyone to use this software for any purpose, including commercial applications, and to alter it and redistribute it freely, subject to the following restrictions:

- The origin of this software must not be misrepresented; you must not claim that you wrote the original software. If you use this software in a product, an acknowledgment in the product documentation would be appreciated but is not required.
- 2. Altered source versions must be plainly marked as such, and must not be misrepresented as being the original software.
- 3. This notice may not be removed or altered from any source distribution.

Jean-loup Gailly Mark Adler

jloup@gzip.org madler@alumni.caltech.edu

#### C.3.16 cfuhash

L'implémentation des dictionnaires, utilisée par le module tracemalloc est basée sur le projet cfuhash :

Copyright (c) 2005 Don Owens All rights reserved.

This code is released under the BSD license:

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- \* Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- \* Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- \* Neither the name of the author nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS

FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

## C.3.17 libmpdec

Le module \_decimal est construit en incluant une copie de la bibliothèque *libmpdec*, sauf si elle est compilée avec --with-system-libmpdec:

Copyright (c) 2008-2020 Stefan Krah. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

THIS SOFTWARE IS PROVIDED BY THE AUTHOR AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

## C.3.18 Ensemble de tests C14N du W3C

Les tests de C14N version 2.0 du module test (Lib/test/xmltestdata/c14n-20/) proviennent du site du W3C à l'adresse https://www.w3.org/TR/xml-c14n2-testcases/ et sont distribués sous licence BSD modifiée :

Copyright (c) 2013 W3C(R) (MIT, ERCIM, Keio, Beihang), All Rights Reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

 $^{\star}$  Redistributions of works must retain the original copyright notice,

this list of conditions and the following disclaimer.

- \* Redistributions in binary form must reproduce the original copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- \* Neither the name of the W3C nor the names of its contributors may be used to endorse or promote products derived from this work without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

## C.3.19 Audioop

The audioop module uses the code base in g771.c file of the SoX project:

Programming the AdLib/Sound Blaster FM Music Chips Version 2.0 (24 Feb 1992) Copyright (c) 1991, 1992 by Jeffrey S. Lee jlee@smylex.uucp Warranty and Copyright Policy This document is provided on an "as-is" basis, and its author makes no warranty or representation, express or implied, with respect to its quality performance or fitness for a particular purpose. In no event will the author of this document be liable for direct, indirect, special, incidental, or consequential damages arising out of the use or inability to use the information contained within. Use of this document is at your own risk. This file may be used and copied freely so long as the applicable copyright notices are retained, and no modifications are made to the text of the document. No money shall be charged for its distribution beyond reasonable shipping, handling and duplication costs, nor shall proprietary changes be made to this document so that it cannot be distributed freely. This document may not be included in published

material or commercial packages without the written consent of its

author.

ANNEXE	U

# Copyright

Python et cette documentation sont :

Copyright  $\ensuremath{@}$  2001-2023 Python Software Foundation. All rights reserved.

Copyright © 2000 BeOpen.com. Tous droits réservés.

 $Copyright © 1995-2000 \ \textit{Corporation for National Research Initiatives}. \ Tous \ droits \ r\'eserv\'es.$ 

Copyright © 1991-1995 Stichting Mathematisch Centrum. Tous droits réservés.

Voir *Histoire et licence* pour des informations complètes concernant la licence et les permissions.

Non alphabétique	_PyTuple_Resize ( <i>C function</i> ), 137
, 271	_thread
2to3, <b>271</b>	module, 183
>>>, 271	Α
all(package variable), 62	A
dict (module attribute), 151	abort(),62
doc (module attribute), 151	abs
file ( <i>module attribute</i> ), 151, 152	built-in function, 89
future, <b>276</b>	alias de type, <b>283</b>
import	allocfunc ( $C$ type), $261$
built-in function, 62	annotation, 271
loader (module attribute), 151	annotation de fonction, 275
main	annotation de variable, 284
module, 12, 176, 188	API provisoire, 281
name (module attribute), 151	appelable (callable), 273
package (module attribute), 151	argument, 271
PYVENV_LAUNCHER, 202, 206	argument nommé, 278
slots, <b>282</b>	argument positionnel, 281
_frozen (C struct), 65	argv (in module sys), 179
_inittab( <i>C struct</i> ), 65	arrêt de l'interpréteur, 277
$_{\text{Py\_c\_diff}}(C function), 115$	ascii
$_{\rm Py\_c\_neg}$ ( <i>C function</i> ), 115	built-in function, 81
$_{\text{Py\_c\_pow}}$ ( <i>C function</i> ), 115	attendable (awaitable), 272
$_{\rm Py\_c\_prod}$ ( <i>C function</i> ), 115	attribut, 272
_Py_c_quot ( <i>C function</i> ), 115	В
_Py_c_sum (C function), 115	_
_Py_InitializeMain( <i>C function</i> ), 213	BDFL, 272
_Py_NoneStruct ( <i>C var</i> ), 226	binaryfunc ( <i>C type</i> ), 263
_PyBytes_Resize( <i>C function</i> ), 118	buffer interface
_PyCFunctionFast ( <i>Ctype</i> ), 228	(see buffer protocol), 95
_PyCFunctionFastWithKeywords( <i>Ctype</i> ), 228	buffer object
_PyFrameEvalFunction( <i>Ctype</i> ), 186	(see buffer protocol), 95 buffer protocol, 95
_PyInterpreterState_GetEvalFrameFunc ( $C$	built-in function
function), 186	
_PyInterpreterState_SetEvalFrameFunc ( $C$	import,62 abs,89
function), 186	ascii, 81
_PyObject_GetDictPtr(C function), 81	bytes, 82
_PyObject_New (C function), 225	classmethod, 230
_PyObject_NewVar( <i>C function</i> ), 225	compile, 63
	compare, os

divmod, 89 float, 91 hash, 82, 242	descrsetfunc ( <i>C type</i> ), 262 destructor ( <i>C type</i> ), 262 dictionary
int,91	object, 141
len, 83, 91, 93, 139, 142, 145 pow, 89, 90	dictionnaire, 274 dictionnaire en compréhension (ou diction-
repr, 81, 242	naire en intension), 274
staticmethod, 230	distribution simple, 282
tuple, 92, 140	division entière, 275
type, 82	divmod
builtins	built-in function, 89
module, 12, 176, 188	E
bytearray	
object,118	EAFP, <b>275</b>
bytes	encodage du système de fichiers et
built-in function, 82 object, 116	gestionnaire d'erreurs associé, 275
С	encodage régional, 278
	encodages de texte, 283
calloc(),215	ensemble en compréhension (ou ensemble en intension), 282
Capsule	entrée de chemin, 281
object, 163	environnement virtuel, 284
C-contiguous, 98, 273 chaîne de documentation ( <i>docstring</i> ), <b>274</b>	EOFError (built-in exception), 150
chaîne de documentation (docsimg), 274 chaîne entre triple guillemets, 283	espace de nommage, 280
chargeur, 279	exc_info() (in module sys), 10
chemin des importations, 277	executable (in module sys), 178
chercheur, 275	exit(),62
chercheur basé sur les chemins, 281	expression, 275
chercheur dans les méta-chemins, 279	expression génératrice, 276
chercheur de chemins, 281	onproduction generalized, 2.0
classe, 273	F
classe mère abstraite, <b>271</b>	f-string, 275
classmethod	fichier binaire, 272
built-in function, 230	fichier texte, 283
cleanup functions, 62	file
close() (in module os), 188	object, 150
CO_FUTURE_DIVISION (C var), 39	float
code intermédiaire ( <i>bytecode</i> ), 273	built-in function, 91
code object, 148	floating point
compile	object, 112
built-in function, 63	fonction, 275
complex number	fonction clé, 278
object, 114	fonction coroutine, 274
contigu, 273	fonction de rappel (callback), 273
contiguous, 98	fonction générique, 276
copyright (in module sys), 179	Fortran contiguous, 98, 273
coroutine, 274	free(),215
CPython, 274	freefunc ( $C type$ ), 262
	freeze utility,65
D	frozenset
décorateur, 274	object, 144
descrgetfunc ( <i>C type</i> ), 262	function
descripteur, 274	object, 145

G	built-in function, 83, 91, 93, 139, 142, 145
générateur, 276	lenfunc ( $Ctype$ ), 262
générateur asynchrone, 272	list
gestionnaire de contexte, 273	object, 139
gestionnaire de contexte asynchrone, 272	liste, <b>278</b>
getattrfunc( <i>Ctype</i> ), 262	liste en compréhension (ou liste en intension),
getattrofunc( <i>Ctype</i> ), 262	278
getbufferproc( <i>Ctype</i> ), 262	lock, interpreter, 180
getiterfunc ( $C type$ ), $262$	long integer
GIL, <b>276</b>	object, 109
global interpreter lock, 180	LONG_MAX, 110
Н	M
hachable, 277	machine virtuelle, 284
hash	magic
built-in function, 82, 242	méthode, 279
hashfunc ( $C$ type), 262	main(),177,179
V1 //	malloc(), 215
	mapping
IDLE, <b>277</b>	object, 141
immuable, 277	memoryview
importateur, 277	object, 161
importation, 277	métaclasse, 279
incr_item(), 11, 12	METH_CLASS (variable de base), 230
indication de type, 283	METH_COEXIST (variable de base), 230
initproc( <i>Ctype</i> ), 262	METH_FASTCALL (variable de base), 229
inquiry ( <i>Ctype</i> ), 267	METH_NOARGS (variable de base), 230
instancemethod	METH_O (variable de base), 230
object, 147	METH_STATIC (variable de base), 230
instruction, 283	METH_VARARGS (variable de base), 229 method
int	object, 147
built-in function, 91	méthode, 279
integer	magic, 279
object, 109	special, 283
interactif, 277	méthode magique, 279
interprété, <b>277</b>	méthode spéciale, 283
interpreter lock, 180	MethodType (in module types), 145, 147
itérable, 277	module, <b>279</b>
itérable asynchrone, 272	main, 12, 176, 188
itérateur, 278	thread, 183
itérateur asynchrone, 272	builtins, 12, 176, 188
itérateur de générateur, 276	object, 151
itérateur de générateur asynchrone, 272	search path, 12, 176, 178
iternextfunc( <i>Ctype</i> ), 262	signal, 50
K	sys, 12, 176, 188
	module d'extension, 275
KeyboardInterrupt (built-in exception), 50	modules (in module sys), 62, 176
1	ModuleType (in module types), 151
L	MRO, 279
lambda, <b>278</b>	muable, <b>279</b>
LBYL, <b>278</b>	N1
Le zen de Python, 284	N
len	n-uplet nommé, 279

newfunc ( <i>C type</i> ), 262	PATH, 12
nom qualifié, 282	path
nombre complexe, 273	module search, 12, 176, 178
nombre de références, 282	path (in module sys), 12, 176, 178
None	PEP, <b>281</b>
object, 109	platform (in module sys), 179
nouvelle classe, 280	point d'entrée pour la recherche dans
numeric	path, <b>281</b>
object, 109	portée imbriquée, 280
_	portion, 281
0	pow
object	built-in function, 89, 90
bytearray, 118	Py_ABS ( <i>C macro</i> ), 4
bytes, 116	Py_AddPendingCall ( <i>C function</i> ), 189
Capsule, 163	Py_AddPendingCall(),189
code, 148	Py_ALWAYS_INLINE (C macro), 4
complex number, 114	Py_AtExit ( <i>C function</i> ), 62
dictionary, 141	Py_BEGIN_ALLOW_THREADS, 181
file, 150	Py_BEGIN_ALLOW_THREADS (C macro), 184
floating point, 112	Py_BLOCK_THREADS (C macro), 184
frozenset, 144	Py_buffer (C type), 96
function, 145	Py_buffer.buf( <i>C member</i> ), 96
instancemethod, 147	Py_buffer.format (C member), 97
integer, 109	Py_buffer.internal( <i>C member</i> ), 97
list, 139	Py_buffer.itemsize( <i>C member</i> ), 96
long integer, 109	Py_buffer.len( <i>C member</i> ), 96
mapping, 141	Py_buffer.ndim( <i>C member</i> ), 97
	Py_buffer.obj( <i>C member</i> ),96
memoryview, 161	Py_buffer.readonly (C member), 96
method, 147	Py_buffer.shape (C member), 97
module, 151	Py_buffer.strides ( <i>C member</i> ), 97
None, 109	Py_buffer.suboffsets(C member), 97
numeric, 109	Py_BuildValue ( <i>C function</i> ), 73
sequence, 116	Py_BytesMain (C function), 35
set, 144	Py_BytesWarningFlag (C var), 174
tuple, 137	Py_CHARMASK ( <i>C macro</i> ), 5
type, 6, 105	Py_CLEAR ( <i>C function</i> ), 42
objet, 280	Py_CompileString (C function), 37
objet fichier, 275	Py_CompileString(),38
objet fichier-compatible, 275	Py_CompileStringExFlags ( <i>C function</i> ), 38
objet octet-compatible, 273	Py_CompileStringFlags (C function), 37
objet simili-chemin, 281	Py_CompileStringObject ( <i>C function</i> ), 37
objobjargproc (Ctype), 263	Py_complex (C type), 115
objobjproc ( <i>C type</i> ), 263	Py_DebugFlag (C var), 174
ordre de résolution des méthodes, 279	Py_DecodeLocale ( <i>C function</i> ), 58
OverflowError (built-in exception), 110, 111	Py_DECREF (C function), 41
P	Py_DecRef (C function), 42
	Py_DECREF(),7
package variable	Py_DEPRECATED (C macro), 5
all,62	Py_Defrecated (C macro), 3 Py_DontWriteBytecodeFlag (C var), 174
paquet, 280	Py_Ellipsis (C var), 161
paquet classique, 282	Py_EncodeLocale ( <i>C function</i> ), 59
paquet provisoire, 281	Py_END_ALLOW_THREADS, 181
paquet-espace de nommage, 280	Py_END_ALLOW_THREADS, 181 Py_END_ALLOW_THREADS (C macro), 184
paramètre, 280	T Y_END_ALLOW_THREADS (C Macro), 104

Py_EndInterpreter (C function), 188	Py_LIMITED_API (C macro), 15
Py_EnterRecursiveCall (C function), 53	Py_Main ( <i>C function</i> ), 35
Py_eval_input ( $C var$ ), 38	PY_MAJOR_VERSION (C macro), 269
Py_Exit (C function), 62	Ру_МАХ ( <i>C macro</i> ), 5
Py_False ( <i>C var</i> ), 112	Py_MEMBER_SIZE (C macro), 5
Py_FatalError ( <i>C function</i> ), 62	PY_MICRO_VERSION (C macro), 269
Py_FatalError(), 179	Py_MIN (C macro), 5
Py_FdIsInteractive (C function), 57	PY_MINOR_VERSION (C macro), 269
Py_file_input (C var), 38	Py_mod_create(C macro), 154
Py_Finalize ( <i>C function</i> ), 176	Py_mod_create.create_module(Cfunction), 154
Py_FinalizeEx ( <i>C function</i> ), 176	Py_mod_exec (C macro), 155
Py_FinalizeEx(),62,176,188	Py_mod_exec.exec_module(C function), 155
Py_FrozenFlag (C var), 174	Py_NewInterpreter (C function), 188
Py_GenericAlias ( <i>C function</i> ), 171	Py_NewRef (C function), 41
Py_GenericAliasType ( <i>C var</i> ), 172	Py_NO_INLINE (C macro), 5
Py_GetArgcArgv ( <i>C function</i> ), 212	Py_None ( <i>C var</i> ), 109
Py_GetBuildInfo ( <i>C function</i> ), 179	Py_NoSiteFlag (C var), 175
Py_GetCompiler ( <i>C function</i> ), 179	Py_NotImplemented(C var), 79
Py_GetCopyright ( <i>C function</i> ), 179	Py_NoUserSiteDirectory (C var), 175
Py_GETENV (C macro), 5	Py_OptimizeFlag (C var), 175
Py_GetExecPrefix (C function), 177	Py_PreInitialize ( <i>C function</i> ), 199
Py_GetExecPrefix(),12	Py_PreInitializeFromArgs ( <i>C function</i> ), 199
Py_GetPath ( <i>C function</i> ), 178	Py_PreInitializeFromBytesArgs (C function),
Py_GetPath(), 12, 177, 178	199
Py_GetPlatform ( <i>C function</i> ), 179	Py_PRINT_RAW, 151
Py_GetPrefix (C function), 177	Py_QuietFlag (C var), 175
Py_GetPrefix(),12	Py_REFCNT (C function), 227
Py_GetProgramFullPath ( <i>C function</i> ), 178	PY_RELEASE_LEVEL (C macro), 269
Py_GetProgramFullPath(), 12	PY_RELEASE_SERIAL (C macro), 269
Py_GetProgramName ( <i>C function</i> ), 177	Py_ReprEnter (C function), 53
Py_GetPythonHome (C function), 180	Py_ReprLeave (C function), 53
Py_GetVersion (C function), 178	Py_RETURN_FALSE (C macro), 112
Py_HashRandomizationFlag(Cvar), 174	Py_RETURN_NONE ( <i>C macro</i> ), 109
Py_IgnoreEnvironmentFlag (C var), 174	Py_RETURN_NOTIMPLEMENTED (C macro), 79
Py_INCREF (C function), 41	Py_RETURN_TRUE (C macro), 112
Py_IncRef (C function), 42	Py_RunMain ( <i>C function</i> ), 212
Py_INCREF(),7	Py_SET_REFCNT (C function), 227
Py_Initialize ( <i>C function</i> ), 176	Py_SET_SIZE (C function), 227
Py_Initialize(), 12, 177, 188	Py_SET_TYPE (C function), 227
Py_InitializeEx (C function), 176	Py_SetPath (C function), 178
Py_InitializeFromConfig(C function), 209	Py_SetPath(), 178
Py_InspectFlag (C var), 174	Py_SetProgramName ( <i>C function</i> ), 177
Py_InteractiveFlag (C var), 174	Py_SetProgramName(), 12, 176178
Py_Is (C function), 226	Py_SetPythonHome (C function), 180
Py_IS_TYPE (C function), 227	Py_SetStandardStreamEncoding ( $C$ function),
Py_IsFalse (C function), 227	177
Py_IsInitialized ( <i>C function</i> ), 176	Py_single_input (C var), 38
Py_IsInitialized(),12	Py_SIZE ( $C$ function), 227
Py_IsNone (C function), 227	Py_ssize_t (C type), 10
Py_IsolatedFlag (C var), 174	PY_SSIZE_T_MAX, 111
Py_IsTrue (C function), 227	Py_STRINGIFY (C macro), 5
Py_LeaveRecursiveCall (C function), 53	Py_TPFLAGS_BASE_EXC_SUBCLASS (variable de
Py_LegacyWindowsFSEncodingFlag(Cvar), 175	base), 245
Py_LegacyWindowsStdioFlag(Cvar), 175	Py_TPFLAGS_BASETYPE (variable de base), 244

Py_TPFLAGS_BYTES_SUBCLASS (variable de base), 245	Py_UNICODE_ISTITLE ( <i>C function</i> ), 122 Py_UNICODE_ISUPPER ( <i>C function</i> ), 122
Py_TPFLAGS_DEFAULT (variable de base), 245	Py_UNICODE_JOIN_SURROGATES (C macro), 123
Py_TPFLAGS_DICT_SUBCLASS (variable de base),	Py_UNICODE_TODECIMAL (C function), 123
245	Py_UNICODE_TODIGIT ( <i>C function</i> ), 123
	Py_UNICODE_TOLOWER (C function), 123
riable de base), 246	Py_UNICODE_TONUMERIC (C function), 123
Py_TPFLAGS_HAVE_FINALIZE (variable de base),	Py_UNICODE_TOTITLE (C function), 123
245	Py_UNICODE_TOUPPER (C function), 123
Py_TPFLAGS_HAVE_GC (variable de base), 244	Py_UNREACHABLE (C macro), 5
Py_TPFLAGS_HAVE_VECTORCALL (variable de base),	Py_UNUSED (C macro), 6
245	Py_VaBuildValue ( <i>C function</i> ), 74
Py_TPFLAGS_HEAPTYPE (variable de base), 244	PY_VECTORCALL_ARGUMENTS_OFFSET (C macro),
Py_TPFLAGS_IMMUTABLETYPE (variable de base),	84
246	Py_VerboseFlag ( <i>C var</i> ), 175
Py_TPFLAGS_LIST_SUBCLASS (variable de base),	Py_Version ( <i>C var</i> ), 270
245	PY_VERSION_HEX (C macro), 269
Py_TPFLAGS_LONG_SUBCLASS (variable de base),	Py_VISIT (C function), 267
245	Py_XDECREF (C function), 42
Py_TPFLAGS_MAPPING (variable de base), 246	Py_XDECREF(), 12
	Py_XINCREF (C function), 41
base), 245	Py_XNewRef (C function), 41
Py_TPFLAGS_READY (variable de base), 244	PyAIter_Check (C function), 94
Py_TPFLAGS_READYING (variable de base), 244	PyAnySet_Check ( <i>C function</i> ), 144
Py_TPFLAGS_SEQUENCE (variable de base), 246	PyAnySet_CheckExact ( $C$ function), 144
Py_TPFLAGS_TUPLE_SUBCLASS (variable de base),	PyArg_Parse ( $C$ function), 72
245	PyArg_ParseTuple ( $C$ function), 71
Py_TPFLAGS_TYPE_SUBCLASS (variable de base),	PyArg_ParseTupleAndKeywords ( $C$ function), 71
245	PyArg_UnpackTuple ( $C$ function), 72
Py_TPFLAGS_UNICODE_SUBCLASS (variable de	PyArg_ValidateKeywordArguments ( $C$ func-
base), 245	tion), 72
Py_tracefunc( <i>Ctype</i> ), 190	PyArg_VaParse ( <i>C function</i> ), 71
Py_True ( <i>C var</i> ), 112	PyArg_VaParseTupleAndKeywords ( $C$ function),
Py_tss_NEEDS_INIT (C macro), 192	72
Py_tss_t ( <i>Ctype</i> ), 192	PyASCIIObject ( <i>Ctype</i> ), 120
Py_TYPE (C function), 227	PyAsyncMethods ( <i>C type</i> ), 261
Py_UCS1 ( <i>C type</i> ), 120	PyAsyncMethods.am_aiter( <i>C member</i> ), 261
Py_UCS2 ( <i>C type</i> ), 120	PyAsyncMethods.am_anext( <i>C member</i> ), 261
Py_UCS4 ( <i>C type</i> ), 120	PyAsyncMethods.am_await( <i>C member</i> ), 261
Py_UNBLOCK_THREADS (C macro), 184	PyAsyncMethods.am_send( <i>C member</i> ), 261
Py_UnbufferedStdioFlag ( <i>C var</i> ), 175	PyBool_Check (C function), 112
Py_UNICODE ( $C type$ ), 120	PyBool_FromLong (C function), 112
Py_UNICODE_IS_HIGH_SURROGATE (C macro), 123	PyBUF_ANY_CONTIGUOUS (C macro), 99
Py_UNICODE_IS_LOW_SURROGATE (C macro), 123	PyBUF_C_CONTIGUOUS (C macro), 99
Py_UNICODE_IS_SURROGATE (C macro), 123	PyBUF_CONTIG (C macro), 99
Py_UNICODE_ISALNUM (C function), 122	PyBUF_CONTIG_RO (C macro), 99
Py_UNICODE_ISALPHA (C function), 122	PyBUF_F_CONTIGUOUS (C macro), 99
Py_UNICODE_ISDECIMAL (C function), 122	PyBUF_FORMAT (C macro), 98
Py_UNICODE_ISDIGIT (C function), 122	PyBUF_FULL (C macro), 99
Py_UNICODE_ISLINEBREAK (C function), 122	PyBUF_FULL_RO (C macro), 99
Py_UNICODE_ISLOWER (C function), 122	PyBUF_INDIRECT (C macro), 98
Py_UNICODE_ISNUMERIC (C function), 122	PyBUF_ND (C macro), 98
Py_UNICODE_ISPRINTABLE (C function), 123	PyBUF_RECORDS (C macro), 99
Py_UNICODE_ISSPACE (C function), 122	PyBUF_RECORDS_RO (C macro), 99

PyBUF_SIMPLE (C macro), 98	PyCapsule_CheckExact (C function), 163
PyBUF_STRIDED (C macro), 99	PyCapsule_Destructor (C type), 163
PyBUF_STRIDED_RO (C macro), 99	PyCapsule_GetContext (C function), 163
Pybuf_strides (C macro), 98	PyCapsule_GetDestructor (C function), 163
Pybuf_writable ( <i>C macro</i> ), 98	PyCapsule_GetName (C function), 163
PyBuffer_FillContiguousStrides ( $C\ func-$	PyCapsule_GetPointer (C function), 163
tion), 102	PyCapsule_Import ( <i>C function</i> ), 163
PyBuffer_FillInfo (C function), 102	PyCapsule_IsValid (C function), 164
PyBuffer_FromContiguous (C function), 101	PyCapsule_New (C function), 163
PyBuffer_GetPointer ( $C$ function), $101$	PyCapsule_SetContext ( $C$ function), 164
PyBuffer_IsContiguous (C function), 101	PyCapsule_SetDestructor (C function), 164
PyBuffer_Release (C function), 101	PyCapsule_SetName ( $C$ function), 164
PyBuffer_SizeFromFormat (Cfunction), 101	PyCapsule_SetPointer ( $C$ function), 164
PyBuffer_ToContiguous (C function), 101	PyCell_Check (C function), 148
PyBufferProcs, 95	PyCell_GET (C function), 148
PyBufferProcs (C type), 260	PyCell_Get (C function), 148
PyBufferProcs.bf_getbuffer(C member), 260	PyCell_New (C function), 148
<pre>PyBufferProcs.bf_releasebuffer(Cmember),</pre>	PyCell_SET (C function), 148
260	PyCell_Set (C function), 148
PyByteArray_AS_STRING (C function), 119	PyCell_Type (C var), 148
PyByteArray_AsString (C function), 119	PyCellObject (C type), 148
PyByteArray_Check (C function), 118	PyCFunction ( $C$ type), 228
PyByteArray_CheckExact (C function), 118	PyCFunctionWithKeywords ( $Ctype$ ), 228
PyByteArray_Concat (C function), 119	PyCMethod (C type), 228
PyByteArray_FromObject(C function), 119	PyCode_Addr2Line (C function), 149
PyByteArray_FromStringAndSize ( $C\ function$ ),	PyCode_Addr2Location (C function), 149
119	PyCode_Check ( $C$ function), 148
PyByteArray_GET_SIZE (C function), 119	PyCode_GetCellvars ( $C$ function), 149
PyByteArray_Resize (C function), 119	PyCode_GetCode (C function), 149
PyByteArray_Size (C function), 119	PyCode_GetFreevars ( $C$ function), 150
PyByteArray_Type (C var), 118	PyCode_GetNumFree ( $C$ function), 148
PyByteArrayObject( <i>Ctype</i> ), 118	PyCode_GetVarnames ( <i>C function</i> ), 149
PyBytes_AS_STRING (C function), 117	PyCode_New ( $C$ function), 148
PyBytes_AsString (C function), 117	PyCode_NewEmpty ( $C$ function), 149
PyBytes_AsStringAndSize(Cfunction), 117	PyCode_NewWithPosOnlyArgs (C function), 149
PyBytes_Check (C function), 116	PyCode_Type ( <i>C var</i> ), 148
PyBytes_CheckExact (C function), 116	PyCodec_BackslashReplaceErrors ( $C\ func$
PyBytes_Concat ( <i>C function</i> ), 118	<i>tion</i> ), 78
PyBytes_ConcatAndDel(C function), 118	PyCodec_Decode (C function), 76
PyBytes_FromFormat (C function), 116	PyCodec_Decoder (C function), 77
PyBytes_FromFormatV( $C$ function), 117	PyCodec_Encode ( $C$ function), 76
PyBytes_FromObject (C function), 117	PyCodec_Encoder ( $C$ function), 77
PyBytes_FromString (C function), 116	PyCodec_IgnoreErrors (C function), 77
PyBytes_FromStringAndSize(C function), 116	PyCodec_IncrementalDecoder (C function), 77
PyBytes_GET_SIZE (C function), 117	PyCodec_IncrementalEncoder (C function), 77
PyBytes_Size (C function), 117	PyCodec_KnownEncoding ( $C$ function), 76
PyBytes_Type (C var), 116	PyCodec_LookupError (C function), 77
PyBytesObject (Ctype), 116	PyCodec_NameReplaceErrors ( $C$ function), 78
pyc utilisant le hachage, 277	PyCodec_Register (C function), 76
PyCallable_Check (C function), 88	PyCodec_RegisterError ( $C$ function), 77
PyCallIter_Check (C function), 158	PyCodec_ReplaceErrors ( $C$ function), 78
PyCallIter_New (C function), 159	PyCodec_StreamReader(C function),77
PyCallIter_Type (C var), 158	PyCodec_StreamWriter ( $C$ function), 77
PyCapsule ( <i>C type</i> ), 163	PyCodec_StrictErrors (C function), 77

PyCodec_Unregister (C function), 76	PyConfig.parse_argv(C member), 206
${\tt PyCodec\_XMLCharRefReplaceErrors}~(C~func-$	PyConfig.parser_debug(C member), 206
tion), 78	PyConfig.pathconfig_warnings ( $C$ member),
PyCodeObject (Ctype), 148	206
PyCompactUnicodeObject ( $Ctype$ ), 120	PyConfig.platlibdir ( $C$ member), 205
PyCompilerFlags (C struct), 38	PyConfig.prefix( <i>C member</i> ), 206
	PyConfig.program_name( <i>C member</i> ), 206
member), 39	PyConfig.pycache_prefix(C member), 206
<pre>PyCompilerFlags.cf_flags(C member), 39</pre>	PyConfig_Clear ( $C$ function), 201
PyComplex_AsCComplex( <i>C function</i> ), 116	PyConfig_InitIsolatedConfig ( ${\it C}$
PyComplex_Check ( <i>C function</i> ), 115	function), 200
PyComplex_CheckExact (C function), 115	PyConfig_InitPythonConfig $(C$
PyComplex_FromCComplex( <i>C function</i> ), 115	function), 200
PyComplex_FromDoubles (C function), 115	PyConfig_Read ( $C$ function), 201
$PyComplex_ImagAsDouble$ ( $C$ function), 116	PyConfig.PyConfig_SetArgv ( $C$ function), 201
$PyComplex_RealAsDouble$ ( $C$ function), 116	PyConfig_SetBytesArgv ( $C\ func$ -
PyComplex_Type (C var), 115	tion), 201
PyComplexObject (C type), 115	PyConfig_PyConfig_SetBytesString (C func-
PyConfig ( <i>C type</i> ), 200	tion), 200
PyConfig.argv (C member), 201	PyConfig.PyConfig_SetString(Cfunction), 200
PyConfig.base_exec_prefix(C member), 202	PyConfig.PyConfig_SetWideStringList ( $C$
PyConfig.base_executable (C member), 202	function), 201
PyConfig.base_prefix(C member), 202	PyConfig.pythonpath_env(C member), 205
PyConfig.buffered_stdio(C member), 202	PyConfig.quiet (C member), 206
PyConfig.bytes_warning(C member), 202	PyConfig.run_command( <i>C member</i> ), 207
PyConfig.check_hash_pycs_mode ( <i>C member</i> ),	PyConfig.run_filename ( <i>C member</i> ), 207
202	PyConfig.run_module( <i>C member</i> ), 207
PyConfig.code_debug_ranges ( <i>C member</i> ), 202	PyConfig.safe_path(Cmember), 201
PyConfig.configure_c_stdio(C member), 203	PyConfig.show_ref_count (C member), 207
PyConfig.dev_mode(C member), 203	PyConfig.site_import ( <i>C member</i> ), 207
PyConfig.dump_refs ( <i>C member</i> ), 203 PyConfig.exec_prefix ( <i>C member</i> ), 203	PyConfig.skip_source_first_line ( <i>C member</i> ), 207
PyConfig.exec_prefix (C member), 203	PyConfig.stdio_encoding( <i>C member</i> ), 207
PyConfig.faulthandler ( <i>C member</i> ), 203	PyConfig.stdio_encoding(C member), 207  PyConfig.stdio_errors(C member), 207
PyConfig.filesystem_encoding (C member),	PyConfig.tracemalloc( <i>C member</i> ), 208
203	PyConfig.use_environment ( <i>C member</i> ), 208
PyConfig.filesystem_errors( <i>C member</i> ), 204	PyConfig.use_hash_seed( <i>C member</i> ), 204
PyConfig.hash_seed (C member), 204	PyConfig.user_site_directory (C member),
PyConfig.home ( <i>C member</i> ), 204	208
PyConfig.import_time (C member), 204	PyConfig.verbose ( <i>C member</i> ), 208
PyConfig.inspect (C member), 204	PyConfig.warn_default_encoding(Cmember),
PyConfig.install_signal_handlers (C mem-	202
ber), 204	PyConfig.warnoptions (C member), 208
PyConfig.interactive (C member), 204	PyConfig.write_bytecode (C member), 208
PyConfig.isolated(C member), 204	PyConfig.xoptions (C member), 208
PyConfig.legacy_windows_stdio (C member),	PyContext (C type), 167
205	PyContext_CheckExact (C function), 167
PyConfig.malloc_stats(C member), 205	PyContext_Copy (C function), 167
<pre>PyConfig.module_search_paths (C member),</pre>	PyContext_CopyCurrent (C function), 167
205	PyContext_Enter (C function), 168
PyConfig.module_search_paths_set (C mem-	PyContext_Exit ( <i>C function</i> ), 168
ber), 205	PyContext_New (C function), 167
PyConfig.optimization_level( <i>C member</i> ), 205	PyContext_Type (C var), 167
PyConfig.orig argv (C member), 205	PyContextToken (C type), 167

PyContextToken_CheckExact (C function), 167	PyDescr_NewWrapper ( <i>C function</i> ), 159
PyContextToken_Type (C var), 167	PyDict_Check (C function), 141
PyContextVar (C type), 167	PyDict_CheckExact (C function), 141
PyContextVar_CheckExact (C function), 167	PyDict_Clear (C function), 141
PyContextVar_Get (C function), 168	PyDict_Contains ( $C$ function), 141
PyContextVar_New (C function), 168	PyDict_Copy (C function), 141
PyContextVar_Reset (C function), 168	PyDict_DelItem (C function), 141
PyContextVar_Set (C function), 168	PyDict_DelItemString ( $C$ function), 141
PyContextVar_Type (C var), 167	PyDict_GetItem (C function), 141
PyCoro_CheckExact (C function), 166	PyDict_GetItemString ( $C$ function), 142
PyCoro_New (C function), 166	PyDict_GetItemWithError(C function), 142
PyCoro_Type ( <i>C var</i> ), 166	PyDict_Items (C function), 142
PyCoroObject (Ctype), 166	PyDict_Keys (C function), 142
PyDate_Check (C function), 168	PyDict_Merge (C function), 143
PyDate_CheckExact (C function), 168	PyDict_MergeFromSeq2 (C function), 143
PyDate_FromDate (C function), 169	PyDict_New ( $C$ function), 141
PyDate_FromTimestamp ( $C function$ ), 171	PyDict_Next (C function), 142
PyDateTime_Check ( $C$ function), 169	PyDict_SetDefault (C function), 142
PyDateTime_CheckExact ( $C$ function), 169	PyDict_SetItem ( $C$ function), 141
PyDateTime_DATE_GET_FOLD ( $C$ function), 170	PyDict_SetItemString ( $C$ function), 141
PyDateTime_DATE_GET_HOUR ( $C$ function), 170	PyDict_Size (C function), 142
${\tt PyDateTime\_DATE\_GET\_MICROSECOND} \ \ (C \ \textit{func-}$	PyDict_Type ( $C var$ ), 141
tion), 170	PyDict_Update ( $C$ function), 143
PyDateTime_DATE_GET_MINUTE (C function), 170	PyDict_Values (C function), 142
PyDateTime_DATE_GET_SECOND ( <i>C function</i> ), 170	PyDictObject ( $Ctype$ ), 141
PyDateTime_DATE_GET_TZINFO ( $C\ function$ ), 170	PyDictProxy_New ( $C$ function), 141
PyDateTime_DELTA_GET_DAYS ( <i>C function</i> ), 171	PyDoc_STR ( <i>C macro</i> ), 6
	PyDoc_STRVAR ( <i>C macro</i> ), 6
function), 171	PyErr_BadArgument ( <i>C function</i> ), 44
${\tt PyDateTime\_DELTA\_GET\_SECONDS} \ \ (C \ \textit{function}),$	PyErr_BadInternalCall ( $C$ function), 46
171	PyErr_CheckSignals ( $C$ function), $50$
PyDateTime_FromDateAndTime ( $C$ function), 169	PyErr_Clear (C function), 44
${\tt PyDateTime\_FromDateAndTimeAndFold} \qquad (C$	PyErr_Clear(), 10, 12
function), 169	PyErr_ExceptionMatches ( $C$ function), 48
PyDateTime_FromTimestamp(Cfunction), 171	PyErr_ExceptionMatches(), 12
PyDateTime_GET_DAY (C function), 170	PyErr_Fetch (C function), 48
PyDateTime_GET_MONTH (C function), 170	PyErr_Format ( <i>C function</i> ), 44
PyDateTime_GET_YEAR (C function), 170	PyErr_FormatV(C function), 44
PyDateTime_TIME_GET_FOLD (C function), 171	PyErr_GetExcInfo (C function), 49
PyDateTime_TIME_GET_HOUR (C function), 170	PyErr_GetHandledException ( $C$ function), 49
PyDateTime_TIME_GET_MICROSECOND ( $C\ func-$	PyErr_GivenExceptionMatches ( $C$ function), 48
tion), 171	PyErr_NewException ( $C$ function), 51
PyDateTime_TIME_GET_MINUTE (C function), 170	PyErr_NewExceptionWithDoc(C function), 51
PyDateTime_TIME_GET_SECOND (C function), 170	PyErr_NoMemory (C function), 45
PyDateTime_TIME_GET_TZINFO ( $C$ function), 171	PyErr_NormalizeException ( $C$ function), 48
PyDateTime_TimeZone_UTC(C var), 168	PyErr_Occurred ( <i>C function</i> ), 47
PyDelta_Check ( $C$ function), 169	PyErr_Occurred(),10
PyDelta_CheckExact (C function), 169	PyErr_Print (C function), 44
PyDelta_FromDSU (C function), 169	PyErr_PrintEx (C function), 44
PyDescr_IsData (C function), 159	PyErr_ResourceWarning (C function), 47
PyDescr_NewClassMethod ( <i>C function</i> ), 159	PyErr_Restore ( <i>C function</i> ), 48
PyDescr_NewGetSet (C function), 159	PyErr_SetExcFromWindowsErr(C function), 45
PyDescr_NewMember (C function), 159	PyErr_SetExcFromWindowsErrWithFilename
PyDescr_NewMethod (C function), 159	(C function), 46

```
PyErr_SetExcFromWindowsErrWithFilenameObpeEtal_SaveThread (C function), 183
       (C function), 45
                                              PyEval SaveThread(), 181, 183
PyErr SetExcFromWindowsErrWithFilenameObpeEtal SetProfile (C function), 191
                                             PyEval_SetTrace (C function), 191
       (C function), 46
PyErr_SetExcInfo (C function), 49
                                              PyEval ThreadsInitialized (C function), 183
PyErr SetFromErrno (C function), 45
                                             PyExc ArithmeticError, 53
PyErr SetFromErrnoWithFilename (C func-
                                             PyExc AssertionError, 53
                                              PyExc_AttributeError, 53
       tion), 45
                                             PyExc_BaseException, 53
PyErr_SetFromErrnoWithFilenameObject (C
       function), 45
                                              PyExc_BlockingIOError, 53
PyErr_SetFromErrnoWithFilenameObjects
                                              PyExc_BrokenPipeError, 53
       (C function), 45
                                             PyExc_BufferError, 53
PyErr_SetFromWindowsErr (C function), 45
                                             PyExc_BytesWarning, 55
PyErr_SetFromWindowsErrWithFilename
                                             PyExc_ChildProcessError, 53
                                             PyExc_ConnectionAbortedError, 53
       function), 45
PyErr_SetHandledException (C function), 49
                                              PyExc_ConnectionError, 53
PyErr_SetImportError (C function), 46
                                             PyExc_ConnectionRefusedError, 53
PyErr_SetImportErrorSubclass (C function),
                                             PyExc ConnectionResetError, 53
                                             PyExc_DeprecationWarning, 55
PyErr SetInterrupt (C function), 50
                                              PyExc EnvironmentError, 55
PyErr_SetInterruptEx (C function), 50
                                             PyExc_EOFError, 53
PyErr_SetNone (C function), 44
                                              PyExc Exception, 53
PyErr_SetObject (C function), 44
                                              PyExc_FileExistsError, 53
PyErr_SetString (C function), 44
                                              PyExc FileNotFoundError, 53
PyErr_SetString(), 10
                                             PyExc FloatingPointError, 53
PyErr_SyntaxLocation (C function), 46
                                              PyExc_FutureWarning, 55
PyErr_SyntaxLocationEx (C function), 46
                                             PyExc_GeneratorExit, 53
PyErr_SyntaxLocationObject (C function), 46
                                             PyExc_ImportError, 53
PyErr_WarnEx (C function), 47
                                             PyExc_ImportWarning, 55
PyErr_WarnExplicit (C function), 47
                                             PyExc_IndentationError, 53
PyErr_WarnExplicitObject (C function), 47
                                             PyExc_IndexError, 53
PyErr_WarnFormat (C function), 47
                                             PyExc_InterruptedError, 53
PyErr_WriteUnraisable (C function), 44
                                              PyExc_IOError, 55
PyEval_AcquireLock (C function), 187
                                             PyExc_IsADirectoryError, 53
PvEval AcquireThread (C function), 187
                                             PyExc KeyboardInterrupt, 53
PyEval_AcquireThread(), 183
                                             PyExc_KeyError, 53
PyEval EvalCode (C function), 38
                                              PyExc LookupError, 53
PyEval_EvalCodeEx (C function), 38
                                              PyExc_MemoryError, 53
PyEval_EvalFrame (C function), 38
                                              PyExc ModuleNotFoundError, 53
PyEval_EvalFrameEx (C function), 38
                                             PyExc_NameError, 53
PyEval GetBuiltins (C function), 76
                                              PyExc NotADirectoryError, 53
PyEval GetFrame (C function), 76
                                             PyExc NotImplementedError, 53
PyEval GetFuncDesc (C function), 76
                                             PyExc_OSError, 53
PyEval_GetFuncName (C function), 76
                                             PyExc_OverflowError, 53
PyEval_GetGlobals (C function), 76
                                              PyExc_PendingDeprecationWarning, 55
PyEval_GetLocals (C function), 76
                                              PyExc_PermissionError, 53
PyEval_InitThreads (C function), 182
                                             PyExc_ProcessLookupError, 53
PyEval_InitThreads(), 176
                                             PyExc_RecursionError, 53
PyEval_MergeCompilerFlags (C function), 38
                                             PyExc_ReferenceError, 53
PyEval_ReleaseLock (C function), 187
                                             PyExc_ResourceWarning, 55
PyEval_ReleaseThread (C function), 187
                                             PyExc_RuntimeError, 53
PyEval_ReleaseThread(), 183
                                             PyExc_RuntimeWarning, 55
PyEval_RestoreThread (C function), 183
                                              PyExc_StopAsyncIteration, 53
PyEval_RestoreThread(), 181, 183
                                              PyExc_StopIteration, 53
```

PyExc_SyntaxError, 53	PyFrame_GetLocals (C function), 165
PyExc_SyntaxWarning, 55	PyFrame_Type (C var), 164
PyExc_SystemError, 53	PyFrameObject ( <i>Ctype</i> ), 164
PyExc_SystemExit, 53	PyFrozenSet_Check (C function), 144
PyExc_TabError, 53	PyFrozenSet_CheckExact (C function), 144
PyExc_TimeoutError, 53	PyFrozenSet_New (C function), 144
PyExc_TypeError, 53	PyFrozenSet_Type (C var), 144
PyExc_UnboundLocalError, 53	PyFunction_Check (C function), 145
PyExc_UnicodeDecodeError, 53	PyFunction_GetAnnotations (C function), 146
PyExc_UnicodeEncodeError, 53	PyFunction_GetClosure (C function), 146
PyExc_UnicodeError, 53	PyFunction_GetCode ( $C$ function), 146
PyExc_UnicodeTranslateError, 53	PyFunction_GetDefaults (C function), 146
PyExc_UnicodeWarning,55	PyFunction_GetGlobals ( $C$ function), 146
PyExc_UserWarning, 55	PyFunction_GetModule ( $C$ function), 146
PyExc_ValueError, 53	PyFunction_New ( $C$ function), 145
PyExc_Warning, 55	PyFunction_NewWithQualName (C function), 146
PyExc_WindowsError, 55	PyFunction_SetAnnotations (C function), 146
PyExc_ZeroDivisionError, 53	PyFunction_SetClosure ( $C$ function), 146
PyException_GetCause (C function), 51	PyFunction_SetDefaults(C function), 146
PyException_GetContext (C function), 51	PyFunction_Type ( $C \ var$ ), 145
PyException_GetTraceback(Cfunction), 51	PyFunctionObject (Ctype), 145
PyException_SetCause (C function), 51	PyGC_Collect ( $C$ function), 268
PyException_SetContext (C function), 51	PyGC_Disable ( $C$ function), 268
PyException_SetTraceback(Cfunction), 51	PyGC_Enable ( $C$ function), 268
PyFile_FromFd (C function), 150	PyGC_IsEnabled ( $C$ function), 268
PyFile_GetLine (C function), 150	PyGen_Check ( $C$ function), 166
PyFile_SetOpenCodeHook ( $C$ function), 150	PyGen_CheckExact (C function), 166
PyFile_WriteObject(C function), 151	PyGen_New ( $C$ function), 166
PyFile_WriteString ( <i>C function</i> ), 151	PyGen_NewWithQualName ( $C$ function), 166
PyFloat_AS_DOUBLE ( <i>C function</i> ), 113	PyGen_Type ( $C var$ ), 166
PyFloat_AsDouble ( <i>C function</i> ), 113	PyGenObject ( <i>Ctype</i> ), 166
PyFloat_Check ( <i>C function</i> ), 112	PyGetSetDef (C type), 231
PyFloat_CheckExact (C function), 112	PyGILState_Check (C function), 184
PyFloat_FromDouble ( <i>C function</i> ), 113	PyGILState_Ensure ( $C$ function), 183
PyFloat_FromString ( <i>C function</i> ), 113	PyGILState_GetThisThreadState ( $\emph{C}$ function),
PyFloat_GetInfo( <i>C function</i> ), 113	184
PyFloat_GetMax ( <i>C function</i> ), 113	PyGILState_Release ( $C$ function), 184
PyFloat_GetMin (C function), 113	PyImport_AddModule ( $C$ function), 63
PyFloat_Pack2 (C function), 114	PyImport_AddModuleObject ( $C$ function), $63$
PyFloat_Pack4 ( <i>C function</i> ), 114	PyImport_AppendInittab ( $C$ function), 65
PyFloat_Pack8 (C function), 114	PyImport_ExecCodeModule ( $C$ function), 63
PyFloat_Type (C var), 112	PyImport_ExecCodeModuleEx(C function), 64
PyFloat_Unpack2 (C function), 114	PyImport_ExecCodeModuleObject ( $C\ function$ ),
PyFloat_Unpack4 (C function), 114	64
PyFloat_Unpack8 (C function), 114	<code>PyImport_ExecCodeModuleWithPathnames</code> ( $\it C$
PyFloatObject ( $Ctype$ ), 112	function), 64
PyFrame_Check (C function), 164	PyImport_ExtendInittab ( $C$ function), $65$
PyFrame_GetBack ( <i>C function</i> ), 165	PyImport_FrozenModules ( $C$ $var$ ), $65$
PyFrame_GetBuiltins ( <i>C function</i> ), 165	PyImport_GetImporter ( $C$ function), 64
PyFrame_GetCode ( <i>C function</i> ), 165	PyImport_GetMagicNumber ( $C\ function$ ), 64
PyFrame_GetGenerator(C function), 165	PyImport_GetMagicTag( $C$ function), 64
PyFrame_GetGlobals( <i>C function</i> ), 165	PyImport_GetModule ( $C$ function), 64
PyFrame_GetLasti( <i>C function</i> ), 165	PyImport_GetModuleDict( $C\ function$ ), 64
PyFrame_GetLineNumber (C function), 165	PyImport_Import (C function), 63

PyImport_ImportFrozenModule (C function), 65	PyLong_AsLong ( $C$ function), 110
${\tt PyImport\_ImportFrozenModuleObject} \qquad (C$	PyLong_AsLongAndOverflow ( $C$ function), 110
function), 64	PyLong_AsLongLong ( $C$ function), 110
PyImport_ImportModule (C function), 62	PyLong_AsLongLongAndOverflow ( $C\ function$ ),
PyImport_ImportModuleEx(C function), 62	111
PyImport_ImportModuleLevel (C function), 63	PyLong_AsSize_t (C function), 111
PyImport_ImportModuleLevelObject (C func-	PyLong_AsSsize_t (C function), 111
tion), 62	PyLong_AsUnsignedLong (C function), 111
PyImport_ImportModuleNoBlock (C function),	PyLong_AsUnsignedLongLong (C function), 111
62	PyLong_AsUnsignedLongLongMask (C function),
PyImport_ReloadModule (C function), 63	111
PyIndex_Check (C function), 91	PyLong_AsUnsignedLongMask (C function), 111
PyInstanceMethod_Check (C function), 147	PyLong_AsVoidPtr( <i>C function</i> ), 112
PyInstanceMethod_Function (C function), 147	PyLong_Check (C function), 109
PyInstanceMethod_GET_FUNCTION ( <i>C function</i> ),	PyLong_CheckExact (C function), 109
147	PyLong_FromDouble ( <i>C function</i> ), 110
PyInstanceMethod_New (C function), 147	PyLong_FromLong (C function), 109
PyInstanceMethod_Type (C var), 147	PyLong_FromLongLong (C function), 109
PyInterpreterState (C type), 182	PyLong_FromSize_t (C function), 109
PyInterpreterState_Clear (C function), 185	PyLong_FromSsize_t (C function), 109
PyInterpreterState_Delete (C function), 185	PyLong_FromString (C function), 110
PyInterpreterState_Get (C function), 186	PyLong_FromUnicodeObject (C function), 110
PyInterpreterState_GetDict (C function), 186	PyLong_FromUnsignedLong (C function), 109
PyInterpreterState_GetID (C function), 186	PyLong_FromUnsignedLongLong(Cfunction), 110
PyInterpreterState_Head(C function), 191	PyLong_FromVoidPtr(C function), 110
PyInterpreterState_Main (C function), 191	PyLong_Type (C var), 109
PyInterpreterState_New (C function), 185	PyLongObject (C type), 109
PyInterpreterState_Next (C function), 191	PyMapping_Check (C function), 93
${\tt PyInterpreterState\_ThreadHead}~(C~\textit{function}),$	PyMapping_DelItem ( $C$ function), 93
191	PyMapping_DelItemString ( $C$ function), 93
PyIter_Check (C function), 94	PyMapping_GetItemString ( $C$ function), 93
PyIter_Next (C function), 94	PyMapping_HasKey ( $C$ function), 94
PyIter_Send(C function), 95	PyMapping_HasKeyString ( $C$ function), 94
PyList_Append ( $C$ function), 140	PyMapping_Items (C function), 94
PyList_AsTuple (C function), 140	PyMapping_Keys (C function), 94
PyList_Check ( <i>C function</i> ), 139	PyMapping_Length ( $C$ function), 93
PyList_CheckExact (C function), 139	PyMapping_SetItemString ( $C$ function), 93
PyList_GET_ITEM (C function), 139	PyMapping_Size ( $C$ function), 93
PyList_GET_SIZE (C function), 139	PyMapping_Values ( $C$ function), 94
PyList_GetItem (C function), 139	PyMappingMethods ( $Ctype$ ), 258
$PyList\_GetItem(), 9$	PyMappingMethods.mp_ass_subscript $(C$
PyList_GetSlice (C function), 140	member), 258
PyList_Insert (C function), 140	PyMappingMethods.mp_length(C member), 258
PyList_New (C function), 139	${\tt PyMappingMethods.mp\_subscript}~(C~\textit{member}),$
PyList_Reverse (C function), 140	258
PyList_SET_ITEM (C function), 140	${\tt PyMarshal\_ReadLastObjectFromFile}~(C~func-$
PyList_SetItem (C function), 140	tion), 66
<pre>PyList_SetItem(),7</pre>	PyMarshal_ReadLongFromFile ( $C\ function$ ), 66
PyList_SetSlice (C function), 140	${\tt PyMarshal\_ReadObjectFromFile} \enskip (C\enskip function),$
PyList_Size (C function), 139	66
PyList_Sort (C function), 140	${\tt PyMarshal\_ReadObjectFromString} \ \ (C \ \textit{func-}$
PyList_Type (C var), 139	tion), 66
PyListObject (C type), 139	PyMarshal_ReadShortFromFile ( <i>C function</i> ), 66
PyLong_AsDouble (C function), 111	PyMarshal_WriteLongToFile ( <i>C function</i> ), 66

PyMarshal_WriteObjectToFile(C function), 66	PyModule_AddType ( <i>C function</i> ), 157
${\tt PyMarshal\_WriteObjectToString}~(C~\textit{function}),$	PyModule_Check ( <i>C function</i> ), 151
66	PyModule_CheckExact (C function), 151
PyMem_Calloc (C function), 218	PyModule_Create (C function), 153
PyMem_Del (C function), 218	PyModule_Create2 (C function), 153
PyMem_Free (C function), 218	PyModule_ExecDef (C function), 155
PyMem_GetAllocator (C function), 221	PyModule_FromDefAndSpec (C function), 155
PyMem_Malloc (C function), 217	PyModule_FromDefAndSpec2 (C function), 155
PyMem_New (C function), 218	PyModule_GetDef(C function), 152
PyMem_RawCalloc (C function), 217	PyModule_GetDict(C function), 151
PyMem_RawFree (C function), 217	PyModule_GetFilename (C function), 152
PyMem_RawMalloc (C function), 217	PyModule_GetFilenameObject (C function), 152
PyMem_RawRealloc (C function), 217	PyModule_GetName (C function), 151
PyMem_Realloc (C function), 218	PyModule_GetNameObject (C function), 151
PyMem_Resize (C function), 218	PyModule_GetState (C function), 152
PyMem_SetAllocator (C function), 221	PyModule_New (C function), 151
PyMem_SetupDebugHooks (C function), 221	PyModule_NewObject (C function), 151
PyMemAllocatorDomain (C type), 220	PyModule_SetDocString (C function), 155
PyMemAllocatorDomain.PYMEM_DOMAIN_MEM	PyModule_Type (C var), 151
(C macro), 220	PyModuleDef (C type), 152
PyMemAllocatorDomain.PYMEM_DOMAIN_OBJ	PyModuleDef_Init (C function), 154
(C macro), 221	PyModuleDef_Slot (C type), 154
PyMemAllocatorDomain.PYMEM_DOMAIN_RAW	PyModuleDef_Slot.slot (C member), 154
(C macro), 220	PyModuleDef_Slot.value( <i>C member</i> ), 154
PyMemAllocatorEx (C type), 220	PyModuleDef.m_base(C member), 152
PyMember_GetOne (C function), 231	PyModuleDef.m_clear(C member), 153
PyMember_SetOne (C function), 231	PyModuleDef.m_doc(C member), 152
PyMemberDef (C type), 230	PyModuleDef.m_free (C member), 153
PyMemoryView_Check (C function), 161	PyModuleDef.m_methods (C member), 152
PyMemoryView_FromBuffer(C function), 161	PyModuleDef.m_name ( <i>C member</i> ), 152
PyMemoryView_FromMemory (C function), 161	PyModuleDef.m_size(C member), 152
PyMemoryView_FromObject (C function), 161	PyModuleDef.m_slots(C member), 153
PyMemoryView_GET_BASE (C function), 161	PyModuleDef.m_slots.m_reload (C member),
PyMemoryView_GET_BUFFER(C function), 161	153
PyMemoryView_GetContiguous ( <i>C function</i> ), 161	PyModuleDef.m_traverse(C member), 153
PyMethod_Check ( <i>C function</i> ), 147	PyNumber_Absolute (C function), 89
PyMethod_Function ( <i>C function</i> ), 147	PyNumber_Add (C function), 88
PyMethod_GET_FUNCTION (C function), 147	PyNumber_And (C function), 89
PyMethod_GET_SELF (C function), 147	PyNumber_AsSsize_t (C function), 91
PyMethod_New (C function), 147	PyNumber_Check (C function), 88
PyMethod_Self (C function), 147	PyNumber_Divmod (C function), 89
PyMethod_Type (C var), 147	PyNumber_Float ( <i>C function</i> ), 91
PyMethodDef(Ctype), 229	PyNumber_FloorDivide (C function), 88
PyMethodDef.ml_doc(C member), 229	PyNumber_Index (C function), 91
PyMethodDef.ml_flags(C member), 229	PyNumber_InPlaceAdd (C function), 89
PyMethodDef.ml_meth(C member), 229	PyNumber_InPlaceAnd (C function), 90
PyMethodDef.ml_name(C member), 229	PyNumber_InPlaceFloorDivide (C function), 90
PyModule_AddFunctions ( <i>C function</i> ), 155	PyNumber_InPlaceLshift (C function), 90
PyModule_AddIntConstant ( <i>C function</i> ), 157	PyNumber_InPlaceMatrixMultiply (C func-
PyModule_AddIntMacro ( <i>C function</i> ), 157	tion), 90
PyModule_AddObject (C function), 156	PyNumber_InPlaceMultiply ( <i>C function</i> ), 89
PyModule_AddObjectRef ( <i>C function</i> ), 156	PyNumber_InPlaceOr(C function), 90
PyModule_AddStringConstant ( <i>C function</i> ), 157	PyNumber_InPlacePower (C function), 90
PyModule AddStringMacro (C function) 157	PyNumber InPlaceRemainder (C function), 90

PyNumber_InPlaceRshift ( <i>C function</i> ), 90 PyNumber_InPlaceSubtract ( <i>C function</i> ), 89	PyNumberMethods.nb_inplace_xor( <i>C member</i> ), 258
PyNumber_InPlaceTrueDivide (C function), 90	PyNumberMethods.nb_int(C member), 257
PyNumber_InPlaceXor (C function), 90	PyNumberMethods.nb_invert( <i>C member</i> ), 257
PyNumber_Invert (C function), 89	PyNumberMethods.nb_lshift(C member), 257
PyNumber_Long (C function), 91	PyNumberMethods.nb_matrix_multiply (C
PyNumber_Lshift ( <i>C function</i> ), 89	member), 258
PyNumber_MatrixMultiply (C function), 88	PyNumberMethods.nb_multiply(C member), 257
PyNumber_Multiply (C function), 88	PyNumberMethods.nb_negative(Cmember), 257
PyNumber_Negative (C function), 89	PyNumberMethods.nb_or( <i>C member</i> ), 257
PyNumber_Or (C function), 89	PyNumberMethods.nb_positive( <i>C member</i> ), 257
PyNumber_Positive ( <i>C function</i> ), 89	PyNumberMethods.nb_power( <i>C member</i> ), 257
PyNumber_Power (C function), 89	PyNumberMethods.nb_remainder (C member),
PyNumber_Remainder (C function), 88	257
PyNumber_Rshift ( <i>C function</i> ), 89	PyNumberMethods.nb_reserved(C member), 257
PyNumber_Subtract (C function), 88	PyNumberMethods.nb_rshift ( <i>C member</i> ), 257
PyNumber_ToBase (C function), 91	PyNumberMethods.nb_subtract (C member), 257
PyNumber_TrueDivide (C function), 88	PyNumberMethods.nb_true_divide(Cmember),
PyNumber_Xor (C function), 89	258
PyNumberMethods ( <i>Ctype</i> ), 256	PyNumberMethods.nb_xor(C member), 257
PyNumberMethods.nb_absolute( <i>C member</i> ), 257	PyObject (C type), 226
PyNumberMethods.nb_add(C member), 257	PyObject_AsCharBuffer ( <i>C function</i> ), 102
PyNumberMethods.nb_and(C member), 257	PyObject_ASCII ( <i>C function</i> ), 81
PyNumberMethods.nb_bool (C member), 257	PyObject_AsFileDescriptor ( <i>C function</i> ), 150
PyNumberMethods.nb_divmod(C member), 257	PyObject_AsReadBuffer ( <i>C function</i> ), 102
PyNumberMethods.nb_float (C member), 257	PyObject_AsWriteBuffer ( <i>C function</i> ), 103
PyNumberMethods.nb_floor_divide ( <i>C memoer</i> ), 257	PyObject_Bytes ( <i>C function</i> ), 81
ber), 258	PyObject_Call ( <i>C function</i> ), 86
PyNumberMethods.nb_index(C member), 258	PyObject_CallFunction ( <i>C function</i> ), 86
PyNumberMethods.nb_inplace_add(Cmember),	PyObject_CallFunctionObjArgs ( <i>C function</i> ),
257	87
PyNumberMethods.nb_inplace_and(Cmember),	PyObject_CallMethod( <i>C function</i> ), 87
258	PyObject_CallMethodNoArgs (C function), 87
PyNumberMethods.nb_inplace_floor_divide	
(C member), 258	PyObject_CallMethodOneArg(Cfunction), 87
	PyObject_CallNoArgs (C function), 86
member), 258	PyObject_CallObject (C function), 86
PyNumberMethods.nb_inplace_matrix_multi	
(C member), 258	PyObject_CallOneArg(Cfunction), 86
PyNumberMethods.nb_inplace_multiply ( $C$	
member), 257	PyObject_CheckReadBuffer ( <i>C function</i> ), 102
PyNumberMethods.nb_inplace_or ( <i>C member</i> ), 258	PyObject_ClearWeakRefs ( <i>C function</i> ), 162 PyObject_CopyData ( <i>C function</i> ), 102
PyNumberMethods.nb_inplace_power (C mem-	PyObject_Del(C function), 225
ber), 258	PyObject_DelAttr (C function), 80
PyNumberMethods.nb_inplace_remainder (C	PyObject_DelAttrString (C function), 80
member), 257	PyObject_DelItem(C function), 83
PyNumberMethods.nb_inplace_rshift (C	PyObject_Dir(C function), 83
member), 258	PyObject_Format (C function), 81
	PyObject_Free (C function), 219
member), 257	PyObject_GC_Del(C function), 267
PyNumberMethods.nb_inplace_true_divide	PyObject_GC_IsFinalized ( <i>C function</i> ), 267
(C member), 258	PyObject_GC_IsTracked ( <i>C function</i> ), 266
	PyObject_GC_New (C function), 266

```
PyObject_GC_NewVar (C function), 266
                                                PvObject.ob type (C member), 238
PyObject_GC_Resize (C function), 266
                                               PyOS_AfterFork (C function), 58
PyObject GC Track (C function), 266
                                               PyOS AfterFork Child (C function), 58
PyObject_GC_UnTrack (C function), 267
                                               PyOS_AfterFork_Parent (C function), 57
PyObject GenericGetAttr (C function), 80
                                               PyOS BeforeFork (C function), 57
PyObject GenericGetDict (C function), 80
                                               PyOS CheckStack (C function), 58
PyObject GenericSetAttr (C function), 80
                                                PyOS double to string (C function), 75
                                               PyOS FSPath (C function), 57
PyObject GenericSetDict (C function), 80
PyObject GetAIter (C function), 83
                                               PyOS getsig (C function), 58
PyObject_GetArenaAllocator (C function), 223
                                               PyOS_InputHook (C var), 36
PyObject_GetAttr(C function), 80
                                               PyOS_ReadlineFunctionPointer(C var), 37
PyObject_GetAttrString (C function), 80
                                               PyOS_setsig(C function), 58
PyObject_GetBuffer (C function), 101
                                               PyOS_snprintf(C function), 74
PyObject_GetItem (C function), 83
                                               PyOS_stricmp (C function), 75
PyObject_GetIter (C function), 83
                                               PyOS_string_to_double (C function), 75
PyObject_HasAttr (C function), 79
                                               PyOS_strnicmp (C function), 75
PyObject_HasAttrString (C function), 79
                                               PyOS_vsnprintf (C function), 74
PyObject Hash (C function), 82
                                                PyPreConfig (Ctype), 198
PyObject_HashNotImplemented (C function), 82
                                               PyPreConfig.allocator (C member), 198
PyObject_HEAD (C macro), 226
                                               PyPreConfig.coerce_c_locale(Cmember), 198
PyObject_HEAD_INIT (C macro), 227
                                               PyPreConfig.coerce_c_locale_warn (C mem-
PyObject Init (C function), 225
                                                       ber), 198
PyObject_InitVar(C function), 225
                                               PyPreConfig.configure_locale (C member),
PyObject IS GC (C function), 266
PyObject_IsInstance (C function), 82
                                               PyPreConfig.dev mode (C member), 198
PyObject IsSubclass (C function), 82
                                                PyPreConfig.isolated (C member), 199
PyObject_IsTrue (C function), 82
                                               PyPreConfig.legacy_windows_fs_encoding
PyObject_Length (C function), 83
                                                        (C member), 199
PyObject_LengthHint (C function), 83
                                               PyPreConfig.parse_argv(C member), 199
PyObject_Malloc (C function), 219
                                               PyPreConfig_InitIsolatedConfig
PyObject_New (C function), 225
                                                        (C function), 198
PyObject_NewVar (C function), 225
                                               PyPreConfig_InitPythonConfig
PyObject_Not (C function), 82
                                                        (C function), 198
PyObject._ob_next(C member), 239
                                               PyPreConfig.use_environment (C member), 199
PyObject. ob prev (C member), 239
                                               PvPreConfig.utf8 mode (C member), 199
PyObject_Print (C function), 79
                                               PyProperty_Type (C var), 159
PyObject Realloc (C function), 219
                                                PyRun AnyFile (C function), 35
PyObject_Repr (C function), 81
                                               PyRun_AnyFileEx (C function), 35
PyObject_RichCompare (C function), 81
                                                PyRun AnyFileExFlags (C function), 36
PyObject_RichCompareBool (C function), 81
                                               PyRun_AnyFileFlags (C function), 35
PyObject SetArenaAllocator (C function), 223
                                                PyRun File (C function), 37
PyObject SetAttr (C function), 80
                                               PyRun FileEx (C function), 37
PyObject SetAttrString (C function), 80
                                               PyRun FileExFlags (C function), 37
PyObject_SetItem (C function), 83
                                               PyRun_FileFlags (C function), 37
PyObject_Size (C function), 83
                                                PyRun_InteractiveLoop (C function), 36
PyObject_Str (C function), 81
                                               PyRun_InteractiveLoopFlags (C function), 36
PyObject_Type (C function), 82
                                               PyRun_InteractiveOne (C function), 36
PyObject_TypeCheck (C function), 82
                                               PyRun_InteractiveOneFlags (C function), 36
PyObject_VAR_HEAD (C macro), 226
                                               PyRun_SimpleFile (C function), 36
PyObject_Vectorcall (C function), 87
                                               PyRun_SimpleFileEx (C function), 36
PyObject_VectorcallDict (C function), 87
                                               PyRun_SimpleFileExFlags (C function), 36
PyObject_VectorcallMethod (C function), 87
                                               PyRun SimpleString (C function), 36
PyObjectArenaAllocator (Ctype), 223
                                               PyRun_SimpleStringFlags (C function), 36
PyObject.ob_refcnt(C member), 238
                                                PyRun String (C function), 37
```

PyRun_StringFlags ( <i>C function</i> ), 37	PySignal_SetWakeupFd(C function), 50
PySendResult (C type), 95	PySlice_AdjustIndices (C function), 160
PySeqIter_Check (C function), 158	PySlice_Check (C function), 159
PySeqIter_New (C function), 158	PySlice_GetIndices ( $C$ function), 159
PySeqIter_Type (C var), 158	PySlice_GetIndicesEx(C function), 160
PySequence_Check (C function), 91	PySlice_New ( $C$ function), 159
PySequence_Concat (C function), 91	PySlice_Type (C var), 159
PySequence_Contains (C function), 92	PySlice_Unpack (C function), 160
PySequence_Count (C function), 92	PyState_AddModule ( <i>C function</i> ), 158
PySequence_DelItem ( $C$ function), 92	PyState_FindModule ( $C$ function), 158
PySequence_DelSlice (C function), 92	PyState_RemoveModule (C function), 158
PySequence_Fast ( <i>C function</i> ), 92	PyStatus ( <i>C type</i> ), 197
PySequence_Fast_GET_ITEM ( $C$ function), 93	PyStatus.err_msg( <i>C member</i> ), 197
PySequence_Fast_GET_SIZE ( <i>C function</i> ), 93	PyStatus.exitcode ( <i>C member</i> ), 197
PySequence_Fast_ITEMS ( <i>C function</i> ), 93	PyStatus.func( <i>C member</i> ), 197
PySequence_GetItem ( $C$ function), 92	PyStatus.Py_ExitStatusException ( $C\ func-$
PySequence_GetItem(), $9$	tion), 197
PySequence_GetSlice(C function), 92	PyStatus.PyStatus_Error ( $C$ function), 197
PySequence_Index ( <i>C function</i> ), 92	PyStatus_Exception ( $C$ function), 197
PySequence_InPlaceConcat (C function), 91	PyStatus.PyStatus_Exit ( <i>C function</i> ), 197
PySequence_InPlaceRepeat (C function), 92	PyStatus.PyStatus_IsError( <i>C function</i> ), 197
PySequence_ITEM (C function), 93	PyStatus.PyStatus_IsExit ( $C$ function), 197
PySequence_Length (C function), 91	PyStatus_PyStatus_NoMemory ( <i>C function</i> ), 197
PySequence_List (C function), 92	PyStatus.PyStatus_Ok (C function), 197
PySequence_Repeat (C function), 91	PyStructSequence_Desc( <i>Ctype</i> ), 138
PySequence_SetItem (C function), 92	PyStructSequence_Field( <i>Ctype</i> ), 138
PySequence_SetSlice (C function), 92	PyStructSequence_GET_ITEM(C function), 139
PySequence_Size (C function), 91	PyStructSequence_GetItem (C function), 138
PySequence_Tuple ( <i>C function</i> ), 92	PyStructSequence_InitType (C function), 138
PySequenceMethods ( <i>Ctype</i> ), 259	PyStructSequence_InitType2 (C function), 138
PySequenceMethods.sq_ass_item ( <i>C member</i> ), 259	PyStructSequence_New(C function), 138 PyStructSequence_NewType(C function), 138
PySequenceMethods.sq_concat( <i>C member</i> ), 259	PyStructSequence_SET_ITEM(C function), 139
PySequenceMethods.sq_contains ( $C$ member), 259	PyStructSequence_SetItem ( <i>C function</i> ), 139
	PyStructSequence_UnnamedField ( <i>C var</i> ), 138 PySys_AddAuditHook ( <i>C function</i> ), 61
PySequenceMethods.sq_inplace_concat (C member), 259	PySys_AddWarnOption ( <i>C function</i> ), 60
PySequenceMethods.sq_inplace_repeat ( $C$ member), 259	PySys_AddXOption ( $C$ function), $61$
PySequenceMethods.sq_item(C member), 259	PySys_Audit (C function), 61
PySequenceMethods.sq_length(C member), 259	PySys_FormatStderr ( $C$ function), 61
PySequenceMethods.sq_repeat(C member), 259	PySys_FormatStdout ( $C$ function), $60$
PySet_Add (C function), 145	PySys_GetObject ( $C$ function), $60$
PySet_Check ( <i>C function</i> ), 144	PySys_GetXOptions ( <i>C function</i> ), 61
$PySet\_CheckExact$ ( $C$ function), 144	PySys_ResetWarnOptions ( $C$ function), $60$
PySet_Clear ( <i>C function</i> ), 145	PySys_SetArgv ( <i>C function</i> ), 180
PySet_Contains ( <i>C function</i> ), 145	PySys_SetArgv(),176
PySet_Discard ( <i>C function</i> ), 145	PySys_SetArgvEx (C function), 179
PySet_GET_SIZE (C function), 145	PySys_SetArgvEx(),176
PySet_New (C function), 144	PySys_SetObject ( $C$ function), $60$
PySet_Pop (C function), 145	PySys_SetPath (C function), 60
PySet_Size (C function), 144	PySys_WriteStderr(C function), 60
PySet_Type ( <i>C var</i> ), 144	PySys_WriteStdout ( <i>C function</i> ), 60
PySetObject (C type), 144	Python 3000, <b>281</b>

	DUTUONED IN THE 202
Python Enhancement Proposals	PYTHONFAULTHANDLER, 203
PEP 1, 281	PYTHONHASHSEED, 174, 204
PEP 7, 3, 6	PYTHONHOME, 12, 174, 180, 204
PEP 238, 39	PYTHONINSPECT, 174, 204
PEP 278, 284	PYTHONIOENCODING, 177, 207
PEP 302, 275, 279	Pythonique, 281
PEP 328, 275	PYTHONLEGACYWINDOWSFSENCODING, 175, 199
PEP 343, 273	PYTHONLEGACYWINDOWSSTDIO, 175, 205
PEP 353, 10	PYTHONMALLOC, 216, 220, 221, 223
PEP 362, 272, 281	PYTHONMALLOCSTATS, 205, 216
PEP 383, 127, 128	PYTHONNODEBUGRANGES, 202
PEP 387, 15	PYTHONNOUSERSITE, 175, 208
PEP 393, 119, 127	PYTHONOPTIMIZE, 175, 205
PEP 411,281	PYTHONPATH, 12, 174, 205
PEP 420, 275, 281	PYTHONPLATLIBDIR, 205
PEP 421,280	PYTHONPROFILEIMPORTTIME, 204
PEP 432,213	PYTHONPYCACHEPREFIX, 206
PEP 442,255	PYTHONSAFEPATH, 202
PEP 443,276	PYTHONTRACEMALLOC, 208
PEP 451, 154, 275	PYTHONUNBUFFERED, 175, 202
PEP 483,276	PYTHONUTF8, 199, 211
PEP 484, 271, 276, 283, 284	PYTHONVERBOSE, 175, 208
PEP 489,155	PYTHONWARNINGS, 208
PEP 492, 272, 274	PyThread_create_key (C function), 193
PEP 498, 275	PyThread_delete_key (C function), 193
PEP 519,281	PyThread_delete_key_value (C function), 193
PEP 523, 186	PyThread_get_key_value (C function), 193
PEP 525, 272	PyThread_ReInitTLS ( <i>C function</i> ), 193
PEP 526, 271, 284	PyThread_set_key_value (C function), 193
PEP 528, 175, 205	PyThread_tss_alloc(C function), 192
PEP 529, 128, 175	PyThread_tss_create (C function), 192
PEP 538,211	PyThread_tss_delete(C function), 193
PEP 539, 192	PyThread_tss_free ( <i>C function</i> ), 192
PEP 540,211	PyThread_tss_get (C function), 193
PEP 552, 203	PyThread_tss_is_created (C function), 192
PEP 578,61	PyThread_tss_set ( <i>C function</i> ), 193
PEP 585, 276	PyThreadState, 180
PEP 587, 195	PyThreadState ( <i>C type</i> ), 182
PEP 590,84	PyThreadState_Clear ( <i>C function</i> ), 185
PEP 623, 120	PyThreadState_Delete ( <i>C function</i> ), 185
PEP 634, 246, 247	PyThreadState_DeleteCurrent ( <i>C function</i> ), 185
PEP 3116, 284	PyThreadState_EnterTracing ( <i>C function</i> ), 185
PEP 3119, 82	PyThreadState_Get ( <i>C function</i> ), 183
PEP 3121, 152	PyThreadState_GetDict (C function), 186
PEP 3147,64	PyThreadState_GetFrame ( <i>C function</i> ), 185
PEP 3151,55	PyThreadState_GetID (C function), 185
PEP 3155, 35 PEP 3155, 282	PyThreadState_GetInterpreter ( <i>C function</i> ),
PYTHON*, 174	185
PYTHON^, 174 PYTHONCOERCECLOCALE, 211	
	PyThreadState_LeaveTracing ( <i>C function</i> ), 186 PyThreadState_New ( <i>C function</i> ), 185
PYTHONDESUMODE 203	= · · · · · · · · · · · · · · · · · · ·
PYTHONDEVMODE, 203	PyThreadState_Next ( <i>C function</i> ), 191
PYTHONDONTWRITEBYTECODE, 174, 208	PyThreadState_SetAsyncExc(C function), 186
PYTHONDUMPREFS, 203, 239	PyThreadState_Swap (C function), 183
PYTHONEXECUTABLE, 206	PyTime_Check ( <i>C function</i> ), 169

PyTime_CheckExact ( <i>C function</i> ), 169	<pre>PyType_Slot.PyType_Slot.slot (C member),</pre>
PyTime_FromTime (C function), 169	108
PyTime_FromTimeAndFold ( $C$ function), 169	PyType_Spec ( $C$ type), $108$
PyTimeZone_FromOffset (C function), 170	PyType_Spec.PyType_Spec.basicsize (C
PyTimeZone_FromOffsetAndName ( $C$ function),	member), 108
170	<pre>PyType_Spec.PyType_Spec.flags (C member),</pre>
PyTrace_C_CALL (C var), 190	108
PyTrace_C_EXCEPTION (C var), 190	PyType_Spec.PyType_Spec.itemsize (C mem-
PyTrace_C_RETURN (C var), 190	ber), 108
PyTrace_CALL (C var), 190	PyType_Spec.PyType_Spec.name ( <i>C member</i> ),
PyTrace_EXCEPTION (C var), 190	108
PyTrace_LINE (C var), 190	PyType_Spec.PyType_Spec.slots ( <i>C member</i> ),
PyTrace_OPCODE (C var), 190	108
PyTrace_RETURN (C var), 190	PyType_Type ( <i>C var</i> ), 105
PyTraceMalloc_Track (C function), 223	PyTypeObject (C type), 105
PyTraceMalloc_Untrack (C function), 223	PyTypeObject.tp_alloc(C member), 252
PyTuple_Check (C function), 137	PyTypeObject.tp_as_async( <i>C member</i> ), 241
PyTuple_CheckExact ( <i>C function</i> ), 137	PyTypeObject.tp_as_buffer(Cmember), 244
PyTuple_GET_ITEM (C function), 137	PyTypeObject.tp_as_mapping(Cmember), 242
PyTuple_GET_SIZE (C function), 137	PyTypeObject.tp_as_number( <i>C member</i> ), 242
PyTuple_GetItem (C function), 137	PyTypeObject.tp_as_sequence(Cmember), 242
PyTuple_GetSlice ( <i>C function</i> ), 137	PyTypeObject.tp_base(C member), 250
PyTuple_New (C function), 137	PyTypeObject.tp_bases(C member), 253
PyTuple_Pack (C function), 137	PyTypeObject.tp_basicsize( <i>C member</i> ), 240
PyTuple_SET_ITEM ( <i>C function</i> ), 137	PyTypeObject.tp_cache(Cmember), 254
PyTuple_SetItem ( <i>C function</i> ), 137	PyTypeObject.tp_call(C member), 243
PyTuple_SetItem(),7	PyTypeObject.tp_clear(C member), 248
PyTuple_Size (C function), 137	PyTypeObject.tp_dealloc(C member), 240
PyTuple_Type (C var), 137	PyTypeObject.tp_del(C member), 254
PyTupleObject (C type), 137  PyTuple Check (C type), 105	PyTypeObject.tp_descr_get (C member), 251
PyType_Check (C function), 105	PyTypeObject.tp_descr_set (C member), 251
PyType_CheckExact ( <i>C function</i> ), 105 PyType_ClearCache ( <i>C function</i> ), 105	PyTypeObject.tp_dict(C member), 251
	PyTypeObject.tp_dictoffset ( <i>C member</i> ), 251 PyTypeObject.tp_doc( <i>C member</i> ), 247
PyType_FromModuleAndSpec (C function), 107	
PyType_FromSpec ( <i>C function</i> ), 108 PyType_FromSpecWithBases ( <i>C function</i> ), 108	PyTypeObject.tp_finalize( <i>C member</i> ), 254 PyTypeObject.tp_flags( <i>C member</i> ), 244
PyType_GenericAlloc (C function), 106	PyTypeObject.tp_free(C member), 253
PyType_GenericNew ( <i>C function</i> ), 106	PyTypeObject.tp_getattr(C member), 241
PyType_GetFlags ( <i>C function</i> ), 106	PyTypeObject.tp_getattro( <i>C member</i> ), 243
PyType_GetModule ( <i>C function</i> ), 107	PyTypeObject.tp_getset(C member), 250
PyType_GetModuleByDef ( <i>C function</i> ), 107	PyTypeObject.tp_hash(C member), 242
PyType_GetModuleState ( <i>C function</i> ), 107	PyTypeObject.tp_init(C member), 252
PyType_GetName (C function), 106	PyTypeObject.tp_is_gc(C member), 253
PyType_GetQualName (C function), 106	PyTypeObject.tp_itemsize( <i>C member</i> ), 240
PyType_GetSlot ( <i>C function</i> ), 106	PyTypeObject.tp_iter(C member), 249
PyType_HasFeature ( <i>C function</i> ), 106	PyTypeObject.tp_iternext( <i>C member</i> ), 250
PyType_IS_GC (C function), 106	PyTypeObject.tp_members(C member), 250
PyType_IsSubtype ( <i>C function</i> ), 106	PyTypeObject.tp_methods ( <i>C member</i> ), 250
PyType_Modified ( <i>C function</i> ), 106	PyTypeObject.tp_mro( <i>C member</i> ), 254
PyType_Ready (C tunction), 106	PyTypeObject.tp_name(C member), 239
PyType_Slot (C type), 108  PyType_Slot PyType_Slot pfunc (C member)	PyTypeObject.tp_new(C member), 252
PyType_Slot.PyType_Slot.pfunc ( <i>C member</i> ),	PyTypeObject.tp_repr(C member), 242
108	PyTypeObject.tp_richcompare(C member), 248

PyTypeObject.tp_richcompare.Py_RETURN_R	
(C macro), 249	PyUnicode_DecodeASCII (C function), 133
PyTypeObject.tp_setattr( <i>C member</i> ), 241	PyUnicode_DecodeCharmap ( $C$ function), 134
PyTypeObject.tp_setattro( <i>C member</i> ), 243	PyUnicode_DecodeFSDefault (C function), 129
PyTypeObject.tp_str( <i>C member</i> ), 243	${\tt PyUnicode\_DecodeFSDefaultAndSize}~(C~func-$
PyTypeObject.tp_subclasses( <i>C member</i> ), 254	tion), 128
PyTypeObject.tp_traverse( <i>C member</i> ), 247	PyUnicode_DecodeLatin1 (C function), 133
PyTypeObject.tp_vectorcall(C member), 255	PyUnicode_DecodeLocale ( $C$ function), 128
PyTypeObject.tp_vectorcall_offset ( <i>C member</i> ), 241	PyUnicode_DecodeLocaleAndSize ( $C$ function), 127
PyTypeObject.tp_version_tag( <i>C member</i> ), 254	PyUnicode_DecodeMBCS (C function), 134
PyTypeObject.tp_weaklist(C member), 254	PyUnicode_DecodeMBCSStateful (C function),
<pre>PyTypeObject.tp_weaklistoffset(Cmember),</pre>	134
249	PyUnicode_DecodeRawUnicodeEscape ( $C\ func$ -
PyTZInfo_Check (C function), 169	tion), 133
PyTZInfo_CheckExact (C function), 169	PyUnicode_DecodeUnicodeEscape ( $C\ function$ ),
PyUnicode_1BYTE_DATA (C function), 120	133
PyUnicode_1BYTE_KIND (C macro), 121	PyUnicode_DecodeUTF7 (C function), 132
PyUnicode_2BYTE_DATA (C function), 120	PyUnicode_DecodeUTF7Stateful ( $C\ function$ ),
PyUnicode_2BYTE_KIND (C macro), 121	132
PyUnicode_4BYTE_DATA (C function), 120	PyUnicode_DecodeUTF8 ( $C$ function), 130
PyUnicode_4BYTE_KIND (C macro), 121	PyUnicode_DecodeUTF8Stateful ( $C\ function$ ),
PyUnicode_AS_DATA (C function), 122	130
PyUnicode_AS_UNICODE (C function), 122	PyUnicode_DecodeUTF16 (C function), 132
PyUnicode_AsASCIIString (C function), 133	${\tt PyUnicode\_DecodeUTF16Stateful}~(C~\textit{function}),$
PyUnicode_AsCharmapString(C function), 134	132
PyUnicode_AsEncodedString (C function), 130	PyUnicode_DecodeUTF32 (C function), 131
PyUnicode_AsLatin1String(Cfunction), 133	${\tt PyUnicode\_DecodeUTF32Stateful}~(C~\textit{function}),$
PyUnicode_AsMBCSString ( $C$ function), 134	131
PyUnicode_AsRawUnicodeEscapeString $(C$	PyUnicode_EncodeCodePage (C function), 135
function), 133	PyUnicode_EncodeFSDefault ( $C$ function), 129
PyUnicode_AsUCS4 (C function), 126	PyUnicode_EncodeLocale ( $C$ function), 128
PyUnicode_AsUCS4Copy (C function), 126	PyUnicode_Fill ( <i>C function</i> ), 126
PyUnicode_AsUnicode ( $C$ function), 127	PyUnicode_Find ( $C$ function), 135
PyUnicode_AsUnicodeAndSize (C function), 127	PyUnicode_FindChar ( <i>C function</i> ), 135
PyUnicode_AsUnicodeEscapeString ( $C\ func-$	PyUnicode_Format (C function), 136
tion), 133	PyUnicode_FromEncodedObject(Cfunction), 125
PyUnicode_AsUTF8 (C function), 131	PyUnicode_FromFormat ( $C$ function), 124
PyUnicode_AsUTF8AndSize (C function), 131	PyUnicode_FromFormatV( $C\ function$ ), 125
PyUnicode_AsUTF8String (C function), 131	PyUnicode_FromKindAndData ( $C$ function), 124
PyUnicode_AsUTF16String (C function), 132	PyUnicode_FromObject ( $C$ function), 125
PyUnicode_AsUTF32String (C function), 131	PyUnicode_FromString ( $C$ function), 124
PyUnicode_AsWideChar (C function), 129	PyUnicode_FromString(),141
PyUnicode_AsWideCharString(C function), 129	PyUnicode_FromStringAndSize(Cfunction), 124
PyUnicode_Check (C function), 120	PyUnicode_FromUnicode ( $C$ function), 127
PyUnicode_CheckExact (C function), 120	PyUnicode_FromWideChar ( $C$ function), 129
PyUnicode_Compare (C function), 136	PyUnicode_FSConverter ( <i>C function</i> ), 128
PyUnicode_CompareWithASCIIString ( $C\ func$ -	PyUnicode_FSDecoder ( <i>C function</i> ), 128
tion), 136	PyUnicode_GET_DATA_SIZE ( $C$ function), 121
PyUnicode_Concat (C function), 135	PyUnicode_GET_LENGTH ( $C$ function), 120
PyUnicode_Contains (C function), 136	PyUnicode_GET_SIZE ( <i>C function</i> ), 121
PyUnicode_CopyCharacters ( <i>C function</i> ), 126	PyUnicode_GetLength (C function), 126
Drilly i godo Count (C function) 125	. <u> </u>
PyUnicode_Count ( <i>C function</i> ), 135 PyUnicode_DATA ( <i>C function</i> ), 121	PyUnicode_GetSize ( <i>C function</i> ), 127 PyUnicode_InternFromString ( <i>C function</i> ), 136

PyUnicode_InternInPlace ( <i>C function</i> ), 136 PyUnicode_IsIdentifier ( <i>C function</i> ), 122	PyUnicodeTranslateError_GetObject ( $C$ function), 52
PyUnicode_Join ( <i>C function</i> ), 135 PyUnicode_KIND ( <i>C function</i> ), 121	PyUnicodeTranslateError_GetReason ( $C$ function), 52
PyUnicode_MAX_CHAR_VALUE (C function), 121	PyUnicodeTranslateError_GetStart ( $C\ func$ -
PyUnicode_New (C function), 124	tion), 52
PyUnicode_READ (C function), 121	PyUnicodeTranslateError_SetEnd ( $C$ func-
PyUnicode_READ_CHAR ( $C$ function), 121	tion), 52
PyUnicode_ReadChar (C function), 126	PyUnicodeTranslateError_SetReason ( $C$
PyUnicode_READY (C function), 120	function), 52
PyUnicode_Replace ( <i>C function</i> ), 136	PyUnicodeTranslateError_SetStart ( $C\ func$ -
PyUnicode_RichCompare (C function), 136	tion), 52
PyUnicode_Split ( <i>C function</i> ), 135	PyVarObject ( <i>Ctype</i> ), 226
PyUnicode_Splitlines ( <i>C function</i> ), 135	PyVarObject_HEAD_INIT (C macro), 228
PyUnicode_Substring (C function), 126	PyVarObject.ob_size(C member), 239
PyUnicode_Tailmatch (C function), 135	PyVectorcall_Call ( <i>C function</i> ), 85
PyUnicode_Translate ( <i>C function</i> ), 134	PyVectorcall_Function ( <i>C function</i> ), 85
PyUnicode_Type (C var), 120	PyVectorcall_NARGS (C function), 85
PyUnicode_WCHAR_KIND (C macro), 121	PyWeakref_Check ( <i>C function</i> ), 162
PyUnicode_WRITE ( <i>C function</i> ), 121	PyWeakref_CheckProxy (C function), 162
PyUnicode_WriteChar (C function), 126	PyWeakref_CheckRef ( <i>C function</i> ), 162
PyUnicodeDecodeError_Create (C function), 52	PyWeakref_GET_OBJECT (C function), 162
PyUnicodeDecodeError_GetEncoding ( <i>C func-tion</i> ), 52	PyWeakref_GetObject ( <i>C function</i> ), 162 PyWeakref_NewProxy ( <i>C function</i> ), 162
PyUnicodeDecodeError_GetEnd ( <i>C function</i> ), 52	PyWeakref_NewRef ( <i>C function</i> ), 162
PyUnicodeDecodeError_GetObject (C func-	PyWideStringList ( <i>Ctype</i> ), 196
tion), 52	PyWideStringList.items (C member), 196
PyUnicodeDecodeError_GetReason (C func-	PyWideStringList.length (C member), 196
tion), 52	PyWideStringList.PyWideStringList_Append
PyUnicodeDecodeError_GetStart (C function),	( <i>C function</i> ), 196
52	PyWideStringList.PyWideStringList_Insert
PyUnicodeDecodeError_SetEnd(C function), 52	(C function), 196
PyUnicodeDecodeError_SetReason (C func- tion), 52	PyWrapper_New (C function), 159
PyUnicodeDecodeError_SetStart ( <i>C function</i> ),	R
52	ramasse-miettes, 276
PyUnicodeEncodeError_GetEncoding (C func-	realloc(), 215
tion), 52	référence empruntée, 273
PyUnicodeEncodeError_GetEnd(C function), 52	référence forte, 283
PyUnicodeEncodeError_GetObject ( $C\ func$ -	releasebufferproc( <i>Ctype</i> ), 262
tion), 52	repr
PyUnicodeEncodeError_GetReason ( $C\ func$ -	built-in function, 81, 242
tion), 52	reprfunc ( <i>C type</i> ), 262
${\tt PyUnicodeEncodeError\_GetStart}~(C~\textit{function}),$	retours à la ligne universels, 284
52	richempfunc ( <i>C type</i> ), 262
PyUnicodeEncodeError_SetEnd(C function), 52	
PyUnicodeEncodeError_SetReason ( $C\ func$ -	S
tion), 52	sdterr
${\tt PyUnicodeEncodeError\_SetStart}~(C~\textit{function}),$	stdin stdout, 177
52	search
PyUnicodeObject (C type), 120	path, module, 12, 176, 178
PyUnicodeTranslateError_GetEnd (C func-	sendfunc ( <i>C type</i> ), 263
tion), 52	sequence
	object, 116

séquence, 282	V	
set	variable de classe, 273	
object, 144	variable de contexte, 273	
set_all(),8	variable d'environnement	
setattrfunc( <i>Ctype</i> ), 262	PYVENV_LAUNCHER, 202, 206	
setattrofunc ( <i>Ctype</i> ), 262	PATH, 12	
setswitchinterval() (in module sys), 180	PYTHON*, 174	
SIGINT, 50	PYTHONCOERCECLOCALE, 211	
signal	PYTHONDEBUG, 174, 206	
module, 50	PYTHONDEVMODE, 203	
SIZE_MAX, 111	PYTHONDONTWRITEBYTECODE, 174, 208	
special	PYTHONDUMPREFS, 203, 239	
méthode, 283	PYTHONEXECUTABLE, 206	
spécificateur de module, 279	PYTHONFAULTHANDLER, 203	
ssizeargfunc ( <i>Ctype</i> ), 263	PYTHONHASHSEED, 174, 204	
ssizeobjargproc ( <i>C type</i> ), 263	PYTHONHOME, 12, 174, 180, 204	
staticmethod	PYTHONINSPECT, 174, 204	
built-in function, 230	PYTHONIOENCODING, 177, 207	
stderr (in module sys), 188		175,
stdin	199	175,
stdout sdterr, 177	PYTHONLEGACYWINDOWSSTDIO, 175, 205	
stdin (in module sys), 188	PYTHONMALLOC, 216, 220, 221, 223	
stdout	PYTHONMALLOCSTATS, 205, 216	
sdterr, stdin, 177	PYTHONNODEBUGRANGES, 202	
stdout (in module sys), 188	PYTHONNOUSERSITE, 175, 208	
strerror(),45	PYTHONOPTIMIZE, 175, 205	
string	PYTHONPATH, 12, 174, 205	
PyObject_Str ( <i>C function</i> ), 81	PYTHONPLATLIBDIR, 205	
$sum_list(), 9$	PYTHONPROFILEIMPORTTIME, 204	
sum_sequence(), 10, 11	PYTHONPYCACHEPREFIX, 206	
sys	PYTHONSAFEPATH, 202	
module, 12, 176, 188	PYTHONTRACEMALLOC, 208	
SystemError (built-in exception), 151, 152	PYTHONUNBUFFERED, 175, 202	
<b>-</b>	PYTHONUTF8, 199, 211	
Т	PYTHONVERBOSE, 175, 208	
tableau de correspondances (mapping en an-	PYTHONWARNINGS, 208	
glais), <b>279</b>	vectorcallfunc (C type), 84	
ternaryfunc (C type), 263	verrou global de l'interpréteur, 276	
tranche, 282	version (in module sys), 179	
traverseproc( <i>Ctype</i> ), 267	visitproc( <i>Ctype</i> ), 267	
tuple	vue de dictionnaire, 274	
built-in function, 92, 140		
object, 137		
typage canard (duck-typing), 274		
type, <b>283</b>		
built-in function, 82		
object, 6, 105		
type générique, 276		
U		
ULONG_MAX, 111		
unaryfunc ( <i>C type</i> ), 262		
→ · · · · · · · · · · · · · · · · · · ·		