AUFIT & BatchAufit
User's manual

By Jean Louis-Guérin (DrCoolZic)
Revision 1.1.5671 – July 12, 2015

Table of Content

AUFIT User's manual 1
Table of Content 2
Presentation 3
Program Download / Installation 3
Running the AUFIT Program ..... **Erreur ! Signet non défini.**
Using Aufit ..... **Erreur ! Signet non défini.**
Loading Image Files 5
Selecting a specific track 7
Selecting a specific revolution 7
The Histogram Graph 8
The Information tab 8
The Track View 9
Flux Transitions Chart 9
Bit Width Chart 9
Data Graph 10
Zooming and Panning in the Track view 10
The Disk View 11
The Data View 12
Track Layout 12
Track Buffer 13
Sectors Buffer 14
Saving Data View content 16
The Analysis View 17
Save Image View 20
Checking Quality of generated images 21
Cleaning 23
Analyzing Images 23
Document History 26
Program History ..... **Erreur ! Signet non défini.**

Presentation

AUFIT is the acronym for ***Atari Universal Floppy-Disk Image Tool***. This document describes the usage of the AUFIT and BatchAufit Programs.

The Aufit program reads an Atari Floppy Disk image, analyzes it and displays the content using different Graphical and Text windows. The floppy disk image can be saved to different formats used by emulators. Therefore Aufit program is often used to convert Stream files to a format suitable for Atari emulators.

Currently the supported input formats are **.scp** SuperCard Pro and KryoFlux **.raw** and supported output formats are **.stx** format for protected diskette and **.st**, **.msa** for non-protected diskettes.

It is for example possible to convert KryoFlux RAW stream files to the Pasti STX format used by many Atari emulators. Beside the multi-format conversion capability Aufit performs several deep analysis of a disk image content and displays the corresponding information. For example it is possible to detect most of the key disk protections used or to analyze the quality of the input stream.

The program has been designed to be as simple as possible for casual users only interested in converting files. Actually convertion can even be done in batch mode without user intervention. However the program also provides powerful features to deeply analyze floppy content for advanced users.

Program Download / Installation

The program can be downloaded from http://info-coach.fr/atari/software/pc-projects/Aufit.php .

To install the program just execute the downloaded setup.exe file.

The program run under Windows Vista SP2, Windows 7 SP1, and Windows 8 or above. The program requires that the Microsoft.NET Framework 4.5 or above is installed. If this is not the case you will be proposed to install it from Microsoft site.

The program can check for newer version. When a new version is available you will be ask if you want to install it. It is usually recommended to accept to install the latest version.

The program uses the ClickOnce technology from Microsoft and therefore it is not installed in the standard location. ClickOnce deployment of Aufit creates an "Aufit" shortcut in "DrCoolZic" Program Group under Start menu.

Normally the start menu can be found at

```
C:\Users\Your_Login\AppData\Roaming\Microsoft\Windows\Start Menu.
```


The actual program is actually installed inside the following directory.

```
C:\Users\Your_Login\AppData\Local\Apps\2.0\
```

Running Aufit

The program can be started by using the Aufit shortcut provided in the start menu, or by double clicking on an image file associated with the Program. It is therefore recommended to associate the .**scp** and .**raw** files with the Aufit program (please refer to Microsoft documentation).


When the program starts you will see the following window:



The Aufit windows contains three main regions:


- The first top row contains:
  - On the left the ***Load Image*** button allows to specify an image to load, and the ***Reload*** button allows to reload an already specified image. Once loaded the name of the image file is displayed next to this button.
  - On the right you have the ***Rev*** field that indicates the revolution currently used (as well as the number of revolutions) followed by a **–** and **+** sign that allow to select a different revolution number see Selecting a specific revolution.
  - Followed by the ***Limit Flux*** check box -- see Flux Transitions Chart for more information on how to use it. Followed by a ***Save Pict*** button: allows to save a picture of the currently displayed Aufit window. Followed by the Update button: checks on the Web if a new version of the program is available. Followed by the help button: allos to display this document.
- The second row contains the track grid region on the left and the Histogram / Information region on the right.
- The third row region contains different tabs corresponding to specific functions: Track view, Disk view, Data view, Master view, Analysis, and Save image.

Checking for Update



When you click the Check Update button, the program check on Internet if a new version is available. If a new version is available you are proposed to install it and restart the program.

Getting Help



When you click the Help button, the program displays this user's manual.

Loading Image Files

The first thing to do once Aufit is started is to specify the Floppy disk image to work on. This image can be composed of a single file SuperCopy Pro "**.scp**" file or of a set of KryoFlux "**.raw**" files.

In the latter case all the .raw files, that compose the image, must be located in a single directory and must all have the same "**root**" name followed by .**TrackNum** followed by .**Side** followed .**raw**. This is the standard naming convention produced by the dtc program. For example the directory contains the files: *awesome.00.0.raw*, *awesome.00.1.raw*, *awesome.01.0.raw* etc. To read all these files you just need to click **any** of the raw files in the directory and all the other related files will be automatically read.

There are three methods to specify the location of a floppy disk image in Aufit:

- You can use the ***Load Image*** buttons. An open file dialog box will be displayed and you just need to specify the file to load. The name of the last file opened is saved (even between sessions) and you can use the ***Reload*** button to reload the last specified image.
- You can drag a floppy image file from the Windows Explorer and drop it into the Aufit program main window.
- You can double click on an image file associated with the Aufit program. This will start the program and load the image.

The load operation is performed in two phases:

- First the file(s) is (are) read: very IO intensive operation
- Then the file is analyzed: very CPU intensive operation

These two operations are IO and CPU intensive and therefore can take some times to execute. To maximize performance the program is multi-threaded and will use as many processors / threads available (up to 170 threads).

✎ Side Note: To fully benefit from the ***Aufit*** stream analysis you need to sample an Atari floppy disk with a minimum of at least **three** revolutions for each track but **five** is the recommended value. Please refer to the imaging tools documentation to create FD images with 3 or more revolutions.

Command Line Arguments (Aufit auto-mode)

The Aufit program can be invoked with command arguments, in that case the program run in "auto-mode". The following arguments are accepted:

- **-disk_view**: This argument is used to request Aufit to produce a picture of the disk image structure. When a disk view is requested the optional **–scale** argument allow to specify a scaling factor to the produce image.
- **-scale <scale_value>**: This arguments is only useful when the **–disk_view** argument is used. The *scale_value* is used to scale the image produced. By default the scale is 1.2 but if you specify for example a scale of 2.0 to create an image with much more details. On the contrary a scale of 0.8 will produce a smaller size image well suited for a Web site.
- **-protections**: This argument is used to request Aufit to produce a text file that lists all the protections detected.
- **-save_image**: This argument is used to request Aufit to produce a **.stx** (Pasti) file of the FD.
- **-suffix <suffix_name>**: The "*suffix_name*" argument is used to compose the name of the output files produced by Aufit in auto-mode (see below).

These arguments must be followed by the name of the input image file. If this name contains spaces it must be enclosed in double quotes.

When optional argument are specified with the command line (other than the image file name) the Aufit program is automatically run in Auto-mode. The different operations requested by the arguments are executed and the program terminates. During execution of Aufit in auto-mode it is recommended not to touch Aufit's GUI.

For example the following line:

```
Aufit.exe -disk_view -scale 2.0 -save_image -suffix aufit_1.0 "c:\awesome disk1.scp"
```

Invokes Aufit in auto-mode requesting a disk image picture and a stx pasti file.

The name of the output files produced are the following:

- *Disk image*: base_name.disk_view.suffix_name.png
- *Protections*: base_name.protections.suffix_name.txt
- *STX file*: base_name.image.suffix_name.stx

The base name depends of the type of the input image.

- For an scp files the base name is directly the scp name. For example if the input is **c:\awesome\awesome_d1.scp** the base name is also **c:\awesome\awesome_d1.scp**.
- Kryoflux raw files are located in a directory like: **c:\awesome\awesome_d1** that contains files track00.0.raw, track00.1.raw, track01.0.raw etc. In that case the base name is **c:\awesome\awesome_d1.raw**


Examples of output:

```
c:\awesome\awesome_d1.disk_view.aufit_1.0.png
c:\awesome\awesome_d1.scp.disk_view.aufit_1.0.png
```

It is therefore possible to create a batch file that, for example, finds the floppy disk images to process in a directory tree and invoke Aufit with the right parameters.

As batch files are not easy to write I also provide the **BatchAufit** program, with a nice GUI, that automatically invokes Aufit with the appropriate parameters for processing a tree of FD images. Please refer to BatchAufit Program for more information.

Selecting a specific track



Once the FD image is loaded the information for the first track of the disk is displayed in the different graphs. In the top left corner of the Aufit window you find two grids (one for each side of the floppy) that are composed of track selection buttons.

Each grid element correspond to a track and the color of the background used gives information about the analyzed track:

- *Lime (green)* for normal tracks,
- *Orange* for protected tracks,
- *Blue* for tracks without normal sector but that have data following a 3 sync mark sequence. This usually indicates a data track,
- *Yellow* for tracks with possible data detected but no sync sequence,
- *Slate gray* for unformatted/empty tracks,
- *White* indicates tracks that have not be imaged.

The currently selected track button is identified with a larger black border around the button. Leaving the mouse over a button display the track number.

You can click on any button of the track grid (except non imaged track) to select a specific track. Once the track grids are "active" (for example by clicking one track selection button) you can change selection from one button to its neighbor by using the four ***direction keys*** (left, right, up, down) of your keyboard.


Selecting a new track will update the different views.

Selecting a specific revolution


You can select a specific revolution among the one sampled with the **+** and **-** buttons located at the upper right corner of the program window. Selecting a specific revolution affects the information displayed in the different graphs.

The Histogram Graph

The histogram graph, located at the right of the selection grid, represents the repartition of the flux transitions. Normally you should see three pics at 4, 6, and 8 microseconds.




It is sometimes interesting to click the "**Logarithmic Scale**" check box to switch to a logarithmic scale on the Y axis. This allow to see information not visible on a linear scale. For example with the game Dungeon Master you will see that the histogram has a lot of entries between 4 and 6 microsecond due to the "sliding fluxes" pattern used as a protection for this game.



The Information display

The information tab is used to display information about the read and analyzed track. For example for each track it indicates the entropy, the number of fluxes, and the histogram size (max flux value).




On top of the information mentioned above, each time you select a specific track, the protections used for this track are displayed. The content of this window can be cleared / saved with the corresponding button.

The Track View tab

Flux Transitions Chart

The unprocessed flux transitions (i.e. flux directly read from the file) are displayed as a ***scattered chart***. A standard track contains about 40000 flux transitions and by default all the flux transitions are displayed. To speed up the display time, for example on a slower machine, you can uncheck the **Detail** check box in upper right corner, this will force to display only 10000 flux transitions (about ¼ of the flux transitions). In the upper right of this chart you have two check boxes called ***A1*** & ***C2***. These check boxes are used to enable/disable the display of the **A1** ($4489) and **0xC2** ($5224) Sync Marks respectively as they would be detected by the WD1772 using a ***Read Track*** command (i.e. with the sync detector *activated at all time*). You need to refresh the display to see or hide the sync marks. By default the **A1** sync marks (red lines) are displayed and the **C2** sync marks (blue lines) are not displayed.




There is a check box button in the upper right corner of the Aufit window called **Limit Flux**. By default this button is checked for unformatted track and is unchecked for formatted track but you can change its state at all time. Both the Histogram chart and the Flux Chart use this checkbox and there content will be updated accordingly.

Limiting flux display to 10 µs is very useful when the track contains long flux transitions (like with NFA) to keep the graph readable. Information about the currently selected track are displayed at the top of this graph.

Bit Width Chart

The Bit Width chart displays the width of decoded half bit as computed by the internal WD1772 DPLL clock. The nominal bit width is 2000ns but this value can vary a lot for over / under clocked sectors / tracks.



This graph displays a smoothed running average of the bit width computed by the DPLL. The Y scale is automatically adjusted.

The Bit Width normally stays relatively stable around the 2000ns period but for protection like Copylock usually the values goes from 2000 to 2100 (5% increase) inside a sector. Some protections overclock or underclock the complete track.

In some specific cases like unformatted track/sector the period can go up to 2200ns or down to 1800ns, reaching the 10% limits of the DPLL.

Data Graph

This graph displays all the sectors found on a track:

- The ID field is displayed in yellow (you need to zoom to see it),
- The Intra-gap field is displayed in light green,
- The Data field is displayed in blue.



The data field color can change from Blue to


- Aqua (lighter blue) for under clocked sector,
- Deep Sky Blue for overclocked sectors,
- Purple for sector with bit width variation (e.g. speedlock).

Data sectors with fuzzy bits have an orange border and data sectors with CRC error have a red border.

If you place the cursor over a sector in the data graph, a tool tip shows up and detailed information about the sector is displayed.

The Data graph information uses a complex algorithm (mixture of read track, read address, and read sector) to display correctly "complex" tracks containing protection like: Sector within sector, tracks with large number of sectors, tracks with one sector, etc.

"Out of band" flux transitions (e.g. larger than 8300 µs) usually indicates splice bytes. It is difficult to see them in the transition graph and therefore they are displayed as dotted lines in the data graph (only if located in the GAP area). If you hover the cursor over one of this dotted line a tool tip shows up and indicates the exact position and the length of this out of band transition.



Zooming and Panning in the Track view

When the **flux chart** is not zoomed you can use the left mouse button to define a zoom area (zoom in both in x and y directions). Click on a first point to start the definition of the area, keep the mouse button down and move to a second point to define a zoom area. A rubber band box is drawn that delimitates the area and when the left button is released the graph is zoomed in the area defined. The scales displayed on both x and y axis are automatically adjusted function of the zoom factor.

Once zoomed a click with the left button allow to pan the graph. Click any point in the flux graph with the left button and while keeping the button down move the cursor. The image of the graph dynamically moves with the cursor. When you release the mouse button, the graph and the axis position are updated.

You can further **zoom-in** or **zoom-out** by using the mouse wheel.

If you want to reset the graphs to un-zoomed state click anywhere in the Flux chart with the right mouse button (this is also the way to force a redisplay).

Note that the same zoom factor is used to update the **flux chart**, the **clock chart**, and the **data chart**. Therefore these three graphs always stay synchronized.


You must place the mouse on top of the **flux chart** to pan and zoom the charts.

The Disk View tab

The **Disk View** tab allow to display the layout of the two sides of the floppy disk.

The following colors are used:

- The ID field of a sector is in Yellow (hard to see)
- The Intra-gap of a sector is in light green
- The Data field of a sector is displayed:
  - In Deep sky blue by default
  - In Blue for over clocked sector
  - In Aqua for under clocked segment
  - In Purple for sector with bit-rate variation (e.g. speedlock)
- Data sector with CRC error and/or Fuzzy bytes are displayed in Orange
- No Flux region are displayed in Red
- Unformatted track in Gray
- Data track in Blue
- Track with "data in band" but no sync in Yellow
- Data bits outside normal range are displayed in White



It is possible to save the layout picture with 3 resolutions (high, medium, low).

Selecting a track highlight the track in the Disk View.

The Data View tab

The Data view allow to display information about the layout, the read track content, and the read sectors content of the currently selected track.

The data view contains

- A ***MFM*** check box on bottom left. This check box allow to display the content of the buffers with an extra line that displays the content of the MFM register.
- The ***Save*** button allow to save the content of data view in .rtf format. This format allow to keep the formatting information (color, font etc.) and it must be loaded with a program like Microsoft Word.
- The ***Layout, Track, Sectors*** buttons are used to display the track information as explain below.

Track Layout

The track layout allow to see the layout of the selected track. This information is displayed in an array if you click the ***Layout*** button.


M:\Atari\FDIMAGES\FLUX_KF_Done\Airborne Ranger\KF\Airborne Ranger disk A.raw
Track 00.0 6277 bytes has 12 sectors

ID Field			GAP	Data Field					GAP
Sector	Position	CRC	Bytes	Size	Position	Length	CRC	Fuzzy	Bytes
1	637	OK	34	512	2043	16482	OK	No	32
2	19641	OK	34	512	21038	16415	OK	No	32
3	38566	OK	35	512	39989	16401	OK	No	31
4	57498	OK	34	512	58900	16445	OK	No	32
5	76460	OK	34	512	77857	16443	OK	No	32
6	95421	OK	34	512	96827	16438	OK	No	32
7	114378	OK	34	512	115775	16405	OK	No	32
8	133296	OK	35	512	134724	16415	OK	No	31
9	152222	OK	34	512	153621	16426	OK	No	32
10	171161	OK	34	512	172560	16424	OK	No	32
11	190103	OK	28	512	191315	16480	BAD	Yes	367
12	191700	OK	30	512	192972	16487	BAD	Yes	0

- We first have information about the ID field:
  - The sector number
  - The start position of the ID field in microseconds
  - A flag to indicate if the CRC of the ID field is good or not
- Then we have the number of bytes in the GAP located between the ID and Data field. This number includes the post-id gap, the pre-data gap including the 3 sync marks. For more information refer to Standard 9-10-11 Sectors of 512 Bytes Format
- Then we have information about Data fields
  - The Number of bytes of the sector
  - The start position of the Data field in microseconds
  - The time length of the sector in microseconds.
  - A flag to indicate if the CRC of the Data field is good or not
  - A flag to indicate if the Data field has fuzzy bytes
- Then we have the number of bytes in the GAP located between a sector and the next sector. This number includes the post-data gap, the pre-id gap including the 3 sync marks. For more information refer to Standard 9-10-11 Sectors of 512 Bytes Format.

Track Buffer

The track buffer displays the content of the selected track as they would have been read by the ***Read Track Command*** of the WD1772. The buffer is displayed if you click the ***Track*** button.



The data bytes are displayed by group of 16 with the following information:

- The first number is the position of the byte in the buffer (decimal value)
- The second number is the half bit-width of the first byte of the line. If the width is 2.5% above normal the period is displayed in blue, if the period is 2.5% below normal it is displayed in red.
- The third number is the starting position of the first byte of the line in microsecond relative to the index of the track.
- 16 bytes are displayed in hexadecimal format
- The corresponding 16 ASCII characters for the 16 bytes.

Colors and font style are used to provide additional information.

Background color:

- Light blue for invalid characters (F5-F7) into gaps
- Coral for no flux area (MFM 0x0000 / 0xFFFF)
- Yellow for Sync characters (MFM 0x4489 and 0x5224)
- Light green for bytes located inside an ID field or a Data field.

Character color:

- Red for 0x4489 Sync characters (A1)
- Navy blue for 0x5224Sync characters (C2)
- Blue for ID bytes
- Black for Data and intra-gap byte and for inter-gap byte

Bold characters:

- For Sync characters (MFM 0x4489 and 0x5224)
- For Id field content

Sectors Buffer

The sector buffer is displayed if you click the ***Sector*** button.

The sector buffer displays the content of the selected track as they would have been read by the ***Read Address*** and ***Read Sector*** commands of the WD1772.

But it also includes information that can't be read by the WD1772: the GAP contents. This information is most of the time **different** from what is read with the read track command because of the false sync problem of the WD1772.

The information for each sector is displayed like this

```
Sector 11
ID Field: IAM=FE T=00 H=00 S=0B L=02 CRC=A425 Good
   START Bit=95357 Byte=5960 Time=190,10 ms
   LENGTH Bit=112 Byte=7 Time=223,66 µs
Inner GAP Field:
   START Bit=95469 Byte=5967 Time=190,33 ms
   LENGTH Bit=496 Byte=28 Time=987,94 µs
05967  1988 190327  4E 4E 4E 4E 4E 4E 4E 4E 4E 4E 4E 4E 4E 4E 4E 4E   NNNNNNNNNNNNNNNN
05983  2000 190837  4E 4E 4E 4E 4E 4E 00 00 00 00 00 00               NNNNNN......
DATA Field: DAM=FB 512 bytes start at 191315µs length 16480 µs  CRC=FFFF Bad Fuzzy sector
   START Bit=95965 Byte=5998 Time=191,32 ms
   LENGTH Bit=8240 Byte=512 Time=16480,59 µs
05998  2000 191348  00 00 00 00 00 00 00 00 A1 A1 A1 FE 00 00 0C 02   ........¡¡¡þ....
06014  1984 191859  BC 33 4E 4E 4E 4E 4E 4E 4E 78 54 C5 BC 66 2B   ¼3NNNNNNNNxTÅ¼f+
06030  1984 192368  71 BD 4E 4E 4E 4E 4E 4E 4E FF FF FF FF FF FE   q½NNNNNNNNÿÿÿÿÿþ
06046  2000 192880  14 14 14 00 FF FF FF FF FF FF FF FF FF FF FF   ....ÿÿÿÿÿÿÿÿÿÿÿÿ
06062  1984 193388  FF FF FF FF FF FF FF FF FF FF FF FF FF FF FF   ÿÿÿÿÿÿÿÿÿÿÿÿÿÿÿÿ
06078  1984 193897  FF FF FF FF FF FF FF FF FF C0 00 00 00 00 00   ÿÿÿÿÿÿÿÿÿÀ.....
06094  1992 194192  00 00 00 00 00 00 00 00 00 00 00 00 00 00 00   ...............
06110  1992 194192  00 00 00 00 00 00 00 00 00 00 00 00 00 00 00   ...............
06126  1992 194192  00 00 00 00 00 00 00 00 00 00 00 00 00 00 00   ...............
06142  1992 194192  00 00 00 00 00 00 00 00 00 00 00 00 00 00 00   ...............
06158  1992 194192  00 00 00 00 00 00 00 00 00 00 00 00 00 00 00   ...............
06174  1992 194192  00 00 00 00 00 00 00 00 00 00 00 00 00 00 00   ...............
06190  1992 194192  00 00 00 00 00 00 00 00 00 00 00 00 00 00 00   ...............
06206  1992 194192  00 00 00 00 00 00 00 00 00 00 00 00 00 00 00   ...............
06222  1992 194192  00 00 00 00 00 00 00 00 00 00 00 00 00 00 00   ...............
06238  1992 194192  00 00 00 00 00 00 00 00 00 00 00 00 00 00 00   ...............
06254  1984 199525  90 90 90 90 90 90 90 90 90 90 90 90 90 90 90   ...............
06270  1984 200035  90 90 90 90 90 90 90 FF FF FF FF FF FF FF 0A   .......ÿÿÿÿÿÿÿ.
06286  2000 200549  0A 0A 00 FF FF FE 7C 10 80 10 90 90 90 90 90   ...ÿÿþ|.........
06302  2000 201056  90 90 90 90 90 90 90 90 90 90 90 90 90 90 FF
```

For each sector we have

- A description for the ID Field
- A description for the Inner GAP Field
- A description for the Data field
- A description for the Post data Gap field

The ID Field description

```
ID Field: IAM=FE T=00 H=00 S=01 L=02 CRC=6FCA Good
   START Bit=317 Byte=20 Time=0,64 ms
   LENGTH Bit=112 Byte=7 Time=223,57 µs
```

The description includes a line with the IAM (ID Address Mark) value, the Track (T) value, the Head (H) value, the Sector (S) value, the encoded data Length value (L), the CRC value, an indication showing if the CRC is good or not. All these values are displayed in hexadecimal.

Followed by the start position of the ID field relative to the index pulse and the length of the ID sector field expressed in bits, bytes, and time.

The Inner Gap field description

```
Inner GAP Field:
   START Bit=429 Byte=27 Time=0,86 ms
   LENGTH Bit=592 Byte=34 Time=1182,32 µs
00027  2000 000861  4E 4E 4E 4E 4E 4E 4E 4E 4E 4E 4E 4E 4E 4E 4E 4E   NNNNNNNNNNNNNNNN
00043  2000 001372  4E 4E 4E 4E 4E 4E 00 00 00 00 00 00 00 00 00 00   NNNNNN..........
00059  2000 001885  00 00                                             ..
```

The inner gap field contains the bytes in the gap field located between the ID field and the data field. Aufit continue to read the bytes directly following the end of the ID field without resynchronization. These bytes normally correspond to what has been written on the track and are usually different from what would have been read by the read track command because of the 0x5224 resynchronization that happen during this command.

The start position of the GAP field relative to the index pulse and the length of the GAP field are provided expressed in bits, bytes, and time.

This is followed by the content of the GAP buffer. The bytes are displayed by group of 16 with the following information:

- The first number is the position of the byte in the track (decimal value)
- The second number is the half bit cell width of the first byte of the line. If the period is 2.5% above normal the period is displayed in blue, if the period is 2.5% below normal it is displayed in red.
- The third number is the position of the first byte of the line in microsecond relative to the index of the track.
- 16 bytes are displayed in hexadecimal
- The corresponding 16 ASCII characters for the 16 bytes.

The Data field description

```
DATA Field: DAM=FB 512 bytes start at 21038µs length 16415µs CRC=D902 Good
   START Bit=10525 Byte=658 Time=21,04 ms
   LENGTH Bit=8240 Byte=512 Time=16415,45 µs
00658  1984 021072  00 00 00 FF 4F 00 05 60 00 FF 8F 00 09 A0 00 0B   ...ÿO..`.ÿ... ..
00674  1984 021581  C0 00 0D E0 00 0F 00 01 11 20 01 13 40 01 15 60   À..à..... ..@..`
00690  1984 022089  01 17 80 01 19 A0 01 1B C0 01 1D E0 01 1F 00 02   ..... ..À..à....
00706  1989 022598  21 20 02 23 40 02 25 60 02 27 80 02 29 A0 02 2B   ! .#@.%`.'..) .+
00722  1984 023109  C0 02 2D E0 02 2F 00 03 31 20 03 33 40 03 35 60   À.-à./..1 .3@.5`
00738  1984 023616  03 37 80 03 39 A0 03 3B C0 03 3D E0 03 3F 00 04   .7..9 .;À.=à.?..
…
01090  1984 034844  21 F1 FF FF 4F 12 25 61 12 27 81 12 29 A1 12 2B   !ñÿÿO.%a.'..)¡.+
01106  1984 035354  C1 12 2D E1 12 2F 01 13 31 21 13 33 41 13 35 61   Á.-á./..1!.3A.5a
01122  1984 035863  13 37 81 13 39 A1 13 3B C1 13 3D E1 13 3F 01 14   .7..9¡.;Á.=á.?..
01138  1984 036372  41 21 14 FF 4F 14 FF FF FF 47 F1 FF 49 A1 14 4B   A!.ÿO.ÿÿÿGñÿI¡.K
01154  1984 036880  C1 14 4D E1 14 4F 01 15 FF 2F 15 53 41 15 55 61   Á.Má.O..ÿ/.SA.Ua
```

A line indicates the DAM (Data Address Mark) value, the number of bytes of the sector (without the 3 bytes for the DAM and CRC), the position and length in microseconds, the CRC value, a flag to indicate if the CRC is good or not, and a flag to indicate if the sector contains fuzzy bytes.

The start position of the Data field relative to the index pulse and the length of the Data field are provided expressed in bits, bytes, and time.

This is followed by the content of the DATA buffer.

The color used to display the bytes are explained in Track Buffer.

If some fuzzy bytes have been found in a sector a "fuzzy mask" buffer is also displayed.

```
Sector 11 Contains Fuzzy bytes
5998 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00
6014 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00
6030 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00
6046 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00
…
6222 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00
6238 00 00 00 00 00 00 00 00 00 00 00 00 00 00 81 5E
6254 DE DE DE DE DE DE DE DE DE DE DE DE DE DE DE DE
6270 DE DE DE DE DE DE DE FF FF FF FF FF FF FF FF AB
6286 AB AB FE FF FF FF 7E DA EF 5E DE DE DE DE DE DE
6302 DE DE DE DE DE DE DE DE DE DE DE DE DE DE DE FF
…
```

To find fuzzy bytes the Aufit program read the same sector multiple times from different revolutions. If the content of a byte in the same position is different the mask value is the result of a **xor** operation.

```
Mask[offset] = (Sector_read_1[offset] ^ Sector_read_2[offset])
```

Thus same value (1&1 or 0&0) gives a result of zero and different value (0&1 or 1&0) gives a result of one.

For example if the same byte is read one time as 0000 1111 and the next time as 0101 0101 the mask will be 0101 1010.

This mask can then be used to emulate fuzzy bits as follow:

```
FuzzyByte[offset] = (Sector[offset] & Mask[offset]) | (rand() & Mask[offset])
```

Where rand() is a function that randomly returns true or false.

The Post data Gap Field

```
Post GAP Field:
   START Bit=9261 Byte=579 Time=18,53 ms
   LENGTH Bit=560 Byte=32 Time=1115,28 µs
00579  1988 018525  4E 4E 4E 4E 4E 4E 4E 4E 4E 4E 4E 4E 4E 4E 4E 4E   NNNNNNNNNNNNNNNN
00595  1988 019035  4E 4E 4E 4E 4E 4E 4E 4E 00 00 00 00 00 00 00 00   NNNNNNNN........
```

The post data gap field contains the bytes in the gap located after the data field. Aufit continue to read the bytes directly following the end of the DATA field without resynchronization. These bytes normally correspond to what has been written on the track and are usually different from what would have been read by the read track command because of the 0x5224 resynchronization that happen during this command.

The start position of the GAP field relative to the index pulse and the length of the GAP field are provided expressed in bits, bytes, and time.

This is followed by the content of the GAP buffer.

Saving Data View content

For any of the data view buffer (Layout / Track / Sectors) it is possible to save the buffer in RTF format using the ***Save*** button.

The RTF format allow to keep all formatting information for example the font weight, the color, etc.

You can use a RTF reader like Microsoft Word to load the RTF format and save it for example in PDF.

The Master View tab

TODO

The Analysis tab

Currently the Analysis view only contains the protection analysis. Other analysis will be added at later time.

Protection Analysis

To perform a protection analysis just click the ***Protections*** button. The result of the analysis of all the track is displayed:

To save the result of analysis in text format you can use the ***Save*** button.

```
Protection analysis for M:\Atari\FDIMAGES\FLUX\Dragonflight\SCP\Dragonflight - A.scp

T00.0 hidden data in GAP (dragonflight)
T00.0 S1 invalid head/side number 48 (IHN)
T00.0 S2 invalid head/side number 48 (IHN)
T00.0 S3 invalid head/side number 48 (IHN)
T00.0 S4 invalid head/side number 48 (IHN)
T00.0 S5 invalid head/side number 48 (IHN)
T00.0 S6 invalid head/side number 48 (IHN)
T00.0 S7 invalid head/side number 48 (IHN)
T00.0 S8 invalid head/side number 48 (IHN)
T00.0 S9 invalid head/side number 48 (IHN)
T00.0 S10 invalid head/side number 48 (IHN)
T01.0 hidden data in GAP (dragonflight)
T01.0 S1 invalid track number 178 (ITN)
T01.0 S1 invalid head/side number 48 (IHN)
T01.0 S2 invalid track number 178 (ITN)
T01.0 S2 invalid head/side number 48 (IHN)
T01.0 S3 invalid track number 178 (ITN)
T01.0 S3 invalid head/side number 48 (IHN)
T01.0 S4 invalid track number 178 (ITN)
T01.0 S4 invalid head/side number 48 (IHN)
T01.0 S5 invalid track number 178 (ITN)
T01.0 S5 invalid head/side number 48 (IHN)
T01.0 S6 invalid track number 178 (ITN)
```

The following protections are currently analyzed.

- Track Protections
  - SHT Short track
  - LGT Long track
  - NFA (No Flux Area)
  - SHT-DBI Shifted track Data beyond index
  - SHT-DOI Shifted track Data over index,
  - SHT-IBI Shifted track ID beyond index,
  - SHT-IOI Shifted track ID over index
  - IDG Invalid data into GAP
  - HDG Hidden data into Gap : "Dragonflight & Jupiter Masterdrive protections
  - ISS Invalid Sync Sequence
- Sector Protections
  - DSN Duplicate sector number
  - IIF-NDI Invalid ID Field Nonstandard IAM
  - IIF-ITN Invalid ID Field Invalid track number
  - IIF-IHN Invalid ID Field Invalid Head Number
  - IIF-ISN Invalid ID Field Invalid Sector number
  - IIF-ISL Invalid ID Field Invalid sector Length
  - IIF-ICE Invalid ID Field ID CRC error
  - SWS Sector within sector
  - DCE Data CRC Error

- FZS Fuzzy Sector
- NSD Nonstandard DAM
- LGS Long sector
- SHS Short sector
- SBV Sector bit rate variation
- SND Sector with no data
- Non sequential sector number (for ST format)
- Nonstandard sector size (for ST format)

For more details about these protections please refer to my document **Atari Floppy Disk Copy Protection**.

Note that protections are also analyzed in other views when a Track is selected. You can see the result in the Information window. Remember that a track that contains protection or error is displayed in Orange in the track grid.

Format Analysis

TODO

The Save Image tab

When you select this tab you are presented with information about the possible format you can use to save the current image.

Currently two families of formats exist:

- The non-protected formats includes: ST, MSA, DIM
- The protected format: STX, IPF

✎ Aufit includes an auto-recovery feature. When you write the content of a floppy disk that contains sector's errors the program will try to recover the information about this sector from another revolution.

You first have to select the output format you want to use from a combo box on the left. If it is not possible to use a specific format with the current data (for example ST format for floppy disk using protection) it will be grayed.

When you click the ***Write Image*** button a form open and ask you the location and the name of the file to write. If the file already exist a window will pop up and ask you if you want to replace the existing file.

As soon as you close this form the output file is written and some information is displayed in the main window including error recovered and potential problems.

✎ Reminder: In order to produce a correct file you must use images with data for at least three revolutions but a value of five is recommended especially for floppies in bad condition.

If not enough data (revolutions) have been imaged a window will pop up and warn you. You are still offer the capability to force writing the file.

Normally single sided / double sided detection is performed automatically by Aufit. If you are getting error messages in Steem that an image of a track is missing on side 1 of the floppy image you may need to force Aufit to write file for double sided disk. For that matter please check the ***Force DS*** check Box.

When the ***Optimize*** check box is checked (the default) Aufit will write "compressed" file (smaller file size) for the STX and MSA format.


The ***Debug*** and ***WriteSync*** check boxes are for debug purpose and normally you do not have to use them.

BatchAufit Program

As mentioned in the Auto-mode & Command Line Arguments section it is possible to run the Aufit program in batch mode to automatically produce specific outputs without user intervention.

The BatchAufit program allows to automatically detect all FD images located inside a directory tree and to invoke the Aufit program in auto-mode for all the detected images not yet processed.


The GUI is composed of three area



The top area contains a button that allow to specify the root directory of the tree where you want to search for Kryoflux and SCP FD images. When the ***Root Directory*** button is clicked a dialog box opens that allow to specify the location of the root directory. Once specified the name of the root directory is displayed in a text box on the right of the ***Reload*** button. The ***Reload*** button allow to re-read the last specified tree location. This information is saved between sessions and therefore it is possible to continue the processing of images in separate sessions.

The top area also contains a ***Save Log*** button that allow to save the content of the display area. This allow to save for example the result of analysis of a tree or the result of running Aufit in batch mode.

As soon as the root directory is specified with the ***Root Directory*** or ***Reload*** buttons the content tree is analyzed and all the Kryoflux and SCP images are detected and displayed in the middle area.



An indication of the Total number of FD images as well as an indication on the number of already analyzed images is displayed. In the above example we can see that 118 images have been detected and that 10 of them have already been processed.

In the bottom area you will find several checkboxes that allow to specify if you want Aufit to create ***Disk View***, ***Protections***, and ***Save Image*** (pasti image). This is followed by three text boxes that allow to specify the suffix to be used when creating the output files, the scale to be used when creating disk view files, and the max time BatchAufit waits for Aufit to complete before processing next image (the value -1 means wait un-definitively).

At the bottom of the GUI are four buttons:

- The **Start** button allows to start the batch execution of Aufit. A progress bar indicates the percentage of images already processed.
- The **Stop** button allow to stop the execution of the batch process. BatchAufit waits for the execution of Aufit on a current image to terminate then stops. As the program detect what images has already been processed it is possible to stop and restart the execution where it was stopped (even in different run of BatchAufit).
- The **Clean All** button removes all the output files created by running Aufit in batch mode. You should use this command with care!
- The **Exit** button terminates the program

Sometimes you may want to ignore specific subtrees inside the directory tree to analyze. In that case you can place a file called **aufit.ignore.txt** to indicate that you do not want the current directory and all its subdirectories to be analyzed.

Checking Quality of generated images

This section discuss several questions around the quality of Floppy Disk images created with devices like KryoFlux or SuperCard Pro.

To some extent the quality of the image is only related to the floppy drives and floppy disks conditions and therefore independent of the imaging device used.

Cleaning

The first thing you want to do before imaging floppy disks is to clean the floppy drive head and a make sure you have spotlessly clean floppy disk.

Cleaning the floppy drive head and cleaning the diskette can make a big difference

First always clean the floppy drive head using dedicated cleaning kits as this is a very easy to do operation.

Cleaning a floppy disk is a much more painful operation and therefore you can try to image the diskette without cleaning. If during analysis, as explained below, you find problems on the disk image you should clean the floppy diskette. The recommended way is to wipe the surface of the floppy diskette using a Q-Tip impregnated with head cleaning liquid. Normally this liquid evaporate quickly but you can use the other side of the Q-Tip to help dry the liquid in excess. There are numerous site and videos on the net that explain in detail these operations.

Important things to know when cleaning a floppy diskette:

- The side with an etiquette is the "second logical side" (side/head 1) of the diskette
- The side with the hub that engages with the drive motor is the "first logical side" (side/head 0) of the diskette.

So if you find problems on side/head 0 you need to clean the side without the etiquette (what I refer as the back side) and if you find problems with side/head 1 you need to clean the side with the etiquette (what I refer as the front side).

Analyzing Images

Now let's move on the heart of the subject:

- How do I find if the image I have done is of good enough quality?

For that matter we use the ***Aufit*** program.


You first need to read the image you have created as explain in Reading Image Files section.

When the program read the image it already display useful information in the Track grids as the background color of each track is an indication of possible problem:

- A "normal" track has a light green background,
- an unformatted track has a light gray, and
- a track with potential problem is displayed in yellow.

At this stage only a quick Shannon Entropy analysis is done on the flux transitions histogram and a yellow color usually indicates track with partially unformatted areas or incorrectly imaged track but always require a more complete analysis.


For examples here is the result of reading an image of Sherman M4.



We can see that we have several tracks with a yellow background. If we click on some of these tracks we will find that in fact they are corrects.

But if we click on track 66 we can see than sector one has a lot of "dirty" flux transitions. Thanks to the DPLL these variations can be corrected and we are able to read the sector correctly. This is indicated by the fact that all the sectors read without CRC error.

But if we select the track 73 and zoom on the first sector area we can see that we also have dirty flux transitions, but here the DPLL is not capable to decode the information correctly.



In this case we can see that the first sector is read with fuzzy bytes (orange box in data chart and indication in the information window). In fact if we further analyze the problem we can find, in the fuzzy mask buffer that only **two** bytes at position 206 and 214 vary between revolutions! This also why it is recommended to sample at least four revolutions as **Aufit** always checks fuzzy bytes by comparing the data read for all available revolutions.

```
Fuzzy bytes for sector 1
00000  2000 003505  00 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00  ................
00016  2000 004013  00 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00  ................
00032  2015 004526  00 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00  ................
00048  2015 005040  00 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00  ................
00064  2005 005554  00 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00  ................
00080  2015 006068  00 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00  ................
00096  2010 006582  00 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00  ................
00112  2018 007097  00 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00  ................
00128  2031 007614  00 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00  ................
00144  2005 008128  00 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00  ................
00160  2005 008644  00 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00  ................
00176  2015 009160  00 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00  ................
00192  2015 009676  00 00 00 00 00 00 00 00 00 00 00 00 00 00 01 00  ................
00208  2015 010192  00 00 00 00 00 00 01 00 00 00 00 00 00 00 00 00  ................
00224  2020 010709  00 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00  ................
```

In this case it seems obvious that is error is not part of a protection but due to a problem on the floppy diskette. In such case you should try to clean the diskette and image it again.

We can even look further at the problem. If we click the **Sectors Buffer** command we can see that on some of the revolutions the CRC is good and on some other revolutions the CRC is bad. Normally a fuzzy byte always result in a CRC error. Therefore this indicates that on some revolutions we have read the correct information. Currently Aufit is not able to use this information to create a working Past file but I may implement this feature in the future.

- You need to be aware that on an Atari system when reading sectors from a diskette an automatic retry is performed anytime a sector is not read correctly. This retry is transparent to the user and is used more often than you think.
- Therefore when you have problem clean the floppy and recreate new image, and if this still fails try to recreate the image several times. If the floppy is only marginally not read this may allow you to create a good image.

In order to find all possible problems you first need to run the **Protection** command and for each "protected track" (displayed with a red background in the track grid) you need to check if the problem comes from known protection or from "dirty flux transitions". Unfortunately it seems very difficult to find out about bad images automatically and this is why you need to do a visual inspection using the different features of the Aufit program.

Program History

- V1.1.5671 – July 12, 2015
  - Added iconized buttons for Update and Help with code behind to check for new version and display user's manual.
  - Huge change: In the Data view the sector button now displays GAP buffers. The Gap fields contains the bytes located after the ID and the DATA fields. Aufit continue to read the bytes directly following the end of the ID/DATA fields without resynchronization.
  - Splice lines are now limited to flux above 4% in GAP only => red for inner and blue for post gap
  - Fix bug of wrong section detection in random flux.
  - BatchAufit project is now ClickOnce application and Aufit.exe is now automatically installed with BatchAufit.
  - Invalid sync sequence protection is now detected.
  - Major reformatting of the protection messages + added ISS
- V1.0 May 2015
  - Improve support of Aufit batch mode
  - BatchAufit : Lots of GUI changes + Added reload button (use last saved directory) + added button to save log file + added MaxProcessTime (default -1). Maximum wait time before Aufit is killed + log now includes: start time, elapsed time, and cpu time + processed, succeeded, failed + renamed suffix to 1.0 + Icon for executable...
  - Save last loaded image name. This allow to reload last analyzed image on next run.
  - Added image name + Aufit version in disk image
  - Processing of line argument to enter batch mode
  - Miscellaneous fixes in Buffer & Disk display
  - Added drawing of splice line (when flux out of range) in Data chart.
  - Added detection of jupiterMasterDRive and dragonflight protections
- V0.9 February 2015
  - Support for MSA and ST output format
  - Detection of Drzgonflight & Masterdrive protections
  - Improved display of several charts
- V0.8 January 2015 - Data View
  - Bug fix: DSR + FDC (see todo)
  - GUI cleaning + Bug fixes (GAP - FDC)
  - removed file association create too many problems
  - Save Window size and position
  - Test Click once publishing
  - Buffer Windows are gone replaced by the Data View tab with better functionalities.
- V0.7 January 2015 - Auto recovery - Improve Disk view - Lots of bug fix - Auto safe mode for really bad images
  - Added auto safe mode (safe but slower mode) when sector not found + Analysis GUI + Speed DiskGui + Bug fixes
  - Fix DSR bug on sync seq, FDC detect sync at edge of index + bug fixes
  - Fixed 0.6.5476.33179: Crackdown 2D = KF Sector not found

- Fixed 0.6.5476.18307: Computer Hits V2 - SCP D2 sector missing on some tracks
- Crackdown SCP D1&D2 crash
- Auto-recovery feature added to automatically write good pasti
- Fixed 0.6.5473.34262: Chicago 90 crash
- Fixed 0.6.5472.17463: Gunship SCP track 21.0 Bad Fuzzy report first sect due to NFA!
- Fixed 0.6.5473.16121: Barbarian scp d2 invalid file content error cannot display
- Fix bug Kickoff 2 SCP NFA not decoded correctly (again cant display right info)
- Fix bug NFA not working for Dr. Doom Revenge (now NFA handled at read time)
- *** NOTE *** SCP file does not provide information about index position in flux Therefore it is impossible to do something clean when we have NFA over index
- Fix bug sector not found due to unformatted sectors Crossbow D1, RoadBlaster
- improve Disk View (cursor display) & speedup Track View

▪ V0.6 December 2014 Freeze for Beta release to Brume

▪ V0.5 December 2014 Major rewrite of Aufit internals

- Fix non-working STX for Jupiter master drive, Gunship, P-47
- http://www.atari-forum.com/viewtopic.php?f=102&t=25854&start=525#p263646
- http://www.atari-forum.com/viewtopic.php?f=102&t=25854&start=250#p248282
- http://www.atari-forum.com/viewtopic.php?f=102&t=25854&start=275#p248377
- Fixed nasty bug in DSR for Skateball game
- New Disk Layout display design
- New Main window layout using tabs for: Track view, Disk view, Content, Analysis, Save
- Specify file/dir to read = from menu, drag and drop, double click
- Drawing disk layout now uses multi-threading now reading and processing of flux data is using heavy multi-threading
- Added out of band flux display in Disk layout window
- code and documentation cleaning
- detection of ID over index on top of data over/beyond index
- optimization of STX file using data from track for sector (save space)
- support for stream file drop in main window
- protections rewritten completely - uses new flags on new DS
- capability to save pictures of main screen and Disk layout
- Handle correctly intra sector bit width variation
- FDC speed improvement: all sectors read in one pass in most cases
- removed read directory and dependency on Ookii.Dialogs.Wpf.dll
- This version uses new "packed" data structures to be prepared to interface with IPF lib.

  - now flux samples are stored in ns and speed correction is done at reading time
  - Completely rewritten FDC module with more clean routines
  - use modified version of the DSR from IPF library thanks to IFW from SPS
  - changed clock reference to half bit width
  - removed rev=0 capability
- V0.4b - March 1, 2014 Color scheme changed, improve disk data, fix pre sync data problem, and fix fuzzy assertion error in compare mode.
- V0.3a February 17, 2014 Check for incomplete information when writing Pasti. Corrected NFA display, improved FDC emulation. More robust: should be able to read corrupted Floppy Disk
- V0.2c January 22, 2014 – Bug fixes on Pasti Files generated
- V0.2a January 18, 2014 – Major change is the capability to write Pasti files. This is still experimental. Bug fixes and better read track report. Now Buffer display uses the currently displayed revolution. This allow to compare the decoded data for the different revolutions.
- V0.1b January 9, 2014 – Fixed one very nasty and tough to find bug. In .Net framework when you click a form to select a file the click event is not flushed and you get it back as a button click ... Also improved memory usage.
- V0.1a January 9, 2014 – Compared to initial release Protection analysis has been added. So only missing initial features is Pasti write capability.
  Known problems: Run out of memory easily, GUI freeze with DISK DATA command.
- V0.0 January 6, 2014 – Initial alpha release on request.