

# Administration Guide

Uyuni 4.0

March 16, 2019



## Table of Contents

GNU Free Documentation License		1
Introduction		8
Image Building and Management		9
Image Building Overview	 	9
Container Images	 	9
OS Images	 	17
Listing Image Profiles Available for Building	 	26
Live Patching with SUSE Manager		27
Introduction	 	27
Initial Setup Requirements	 	27
Live Patching Setup	 	27
Cloning Channels	 	28
Removing Non-live Kernel Patches from the Cloned Channels	 	29
Promoting Channels	 	29
Applying Live Patches to a Kernel	 	30
Monitoring with Icinga		31
Introduction	 	31
Installation and Basic Configuration	 	31
Icinga and NRPE Quickstart	 	33
Monitoring Systemd Services	 	37
Using the check_suma_patches Plugin	 	42
Using the check_suma_lastevent Plugin		
Additional Resources	 	44
Kubernetes		45
Prerequisites	 	45
Requirements		
Register Kubernetes as a Virtual Host Manager		
View the List of Nodes in a Cluster		
Obtain Runtime Data about Images	 	46
Build an image for deployment in Kubernetes	 	46
Import a Previously Deployed Image in Kubernetes	 	46
Obtain Additional Runtime Data	 	47
Rebuild a Previously Deployed Image in Kubernetes		
Role Based Access Control Permissions and Certificate Data	 	47
Virtualization		49
Autoinstalling VM Guests	 	49
Managing VM Guests	 	57
Virtual Hosts	 	58
Inventorying vCenter/vSphere ESXi Hosts with Uyuni	 	58
Security		62
Setup a Minion to Master Validation Fingerprint		
Signing Repository Metadata	 	62
Authentication Methods		65
Authentication Via PAM		
Authentication Via eDirectory and PAM	 	66
Example Quest VAS Active Directory Authentication Template	 	66

Using a Custom SSL Certificate	68
Prerequisites	68
Setup	
Using a Custom Certificate with SUSE Manager Proxy	
Backup and Restore	70
Backing up Uyuni	70
Administering the Database with smdba	
Database Backup with smdba	
Restoring from Backup	
Archive Log Settings	
Retrieving an Overview of Occupied Database Space	
Moving the Database	
Recovering from a Crashed Root Partition	
Database Connection Information	
Optimization and Scalability	78
Optimizing Apache and Tomcat	78
Big Scale Deployment (1000 Minions or More)	80
Troubleshooting	83
Registering Cloned Salt Minions	83
Registering Cloned Traditional Systems	84
Typical OSAD/jabberd Challenges	86
Gathering Information with spacewalk-report	89
RPC Connection Timeout Settings	
Client/Server Package Inconsistency	
Corrupted Repository Data	
Unable to Get Local Issuer Certificate	92
AutoYast Example File	93
Minimalist AutoYaST Profile for Automated Installations and Useful Enhancements	93

## **GNU Free Documentation License**

Copyright © 2000, 2001, 2002 Free Software Foundation, Inc. 51 Franklin St, Fifth Floor, Boston, MA 02110-1301 USA. Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

### 0. PREAMBLE

The purpose of this License is to make a manual, textbook, or other functional and useful document "free" in the sense of freedom: to assure everyone the effective freedom to copy and redistribute it, with or without modifying it, either commercially or noncommercially. Secondarily, this License preserves for the author and publisher a way to get credit for their work, while not being considered responsible for modifications made by others.

This License is a kind of "copyleft", which means that derivative works of the document must themselves be free in the same sense. It complements the GNU General Public License, which is a copyleft license designed for free software.

We have designed this License in order to use it for manuals for free software, because free software needs free documentation: a free program should come with manuals providing the same freedoms that the software does. But this License is not limited to software manuals; it can be used for any textual work, regardless of subject matter or whether it is published as a printed book. We recommend this License principally for works whose purpose is instruction or reference.

### 1. APPLICABILITY AND DEFINITIONS

This License applies to any manual or other work, in any medium, that contains a notice placed by the copyright holder saying it can be distributed under the terms of this License. Such a notice grants a worldwide, royalty-free license, unlimited in duration, to use that work under the conditions stated herein. The "Document", below, refers to any such manual or work. Any member of the public is a licensee, and is addressed as "you". You accept the license if you copy, modify or distribute the work in a way requiring permission under copyright law.

A "Modified Version" of the Document means any work containing the Document or a portion of it, either copied verbatim, or with modifications and/or translated into another language.

A "Secondary Section" is a named appendix or a front-matter section of the Document that deals exclusively with the relationship of the publishers or authors of the Document to the Document's overall subject (or to related matters) and contains nothing that could fall directly within that overall subject. (Thus, if the Document is in part a textbook of mathematics, a Secondary Section may not explain any mathematics.) The relationship could be a matter of historical connection with the subject or with related matters, or of legal, commercial, philosophical, ethical or political position regarding them.

The "Invariant Sections" are certain Secondary Sections whose titles are designated, as being those of Invariant Sections, in the notice that says that the Document is released under this License. If a section does not fit the above definition of Secondary then it is not allowed to be designated as Invariant. The Document may contain zero Invariant Sections. If the Document does not identify any Invariant Sections

then there are none.

The "Cover Texts" are certain short passages of text that are listed, as Front-Cover Texts or Back-Cover Texts, in the notice that says that the Document is released under this License. A Front-Cover Text may be at most 5 words, and a Back-Cover Text may be at most 25 words.

A "Transparent" copy of the Document means a machine-readable copy, represented in a format whose specification is available to the general public, that is suitable for revising the document straightforwardly with generic text editors or (for images composed of pixels) generic paint programs or (for drawings) some widely available drawing editor, and that is suitable for input to text formatters or for automatic translation to a variety of formats suitable for input to text formatters. A copy made in an otherwise Transparent file format whose markup, or absence of markup, has been arranged to thwart or discourage subsequent modification by readers is not Transparent. An image format is not Transparent if used for any substantial amount of text. A copy that is not "Transparent" is called "Opaque".

Examples of suitable formats for Transparent copies include plain ASCII without markup, Texinfo input format, LaTeX input format, SGML or XML using a publicly available DTD, and standard-conforming simple HTML, PostScript or PDF designed for human modification. Examples of transparent image formats include PNG, XCF and JPG. Opaque formats include proprietary formats that can be read and edited only by proprietary word processors, SGML or XML for which the DTD and/or processing tools are not generally available, and the machine-generated HTML, PostScript or PDF produced by some word processors for output purposes only.

The "Title Page" means, for a printed book, the title page itself, plus such following pages as are needed to hold, legibly, the material this License requires to appear in the title page. For works in formats which do not have any title page as such, "Title Page" means the text near the most prominent appearance of the work's title, preceding the beginning of the body of the text.

A section "Entitled XYZ" means a named subunit of the Document whose title either is precisely XYZ or contains XYZ in parentheses following text that translates XYZ in another language. (Here XYZ stands for a specific section name mentioned below, such as "Acknowledgements", "Dedications", "Endorsements", or "History".) To "Preserve the Title" of such a section when you modify the Document means that it remains a section "Entitled XYZ" according to this definition.

The Document may include Warranty Disclaimers next to the notice which states that this License applies to the Document. These Warranty Disclaimers are considered to be included by reference in this License, but only as regards disclaiming warranties: any other implication that these Warranty Disclaimers may have is void and has no effect on the meaning of this License.

#### 2. VERBATIM COPYING

You may copy and distribute the Document in any medium, either commercially or noncommercially, provided that this License, the copyright notices, and the license notice saying this License applies to the Document are reproduced in all copies, and that you add no other conditions whatsoever to those of this License. You may not use technical measures to obstruct or control the reading or further copying of the copies you make or distribute. However, you may accept compensation in exchange for copies. If you distribute a large enough number of copies you must also follow the conditions in section 3.

You may also lend copies, under the same conditions stated above, and you may publicly display copies.

## 3. COPYING IN QUANTITY

If you publish printed copies (or copies in media that commonly have printed covers) of the Document, numbering more than 100, and the Document's license notice requires Cover Texts, you must enclose the copies in covers that carry, clearly and legibly, all these Cover Texts: Front-Cover Texts on the front cover, and Back-Cover Texts on the back cover. Both covers must also clearly and legibly identify you as the publisher of these copies. The front cover must present the full title with all words of the title equally prominent and visible. You may add other material on the covers in addition. Copying with changes limited to the covers, as long as they preserve the title of the Document and satisfy these conditions, can be treated as verbatim copying in other respects.

If the required texts for either cover are too voluminous to fit legibly, you should put the first ones listed (as many as fit reasonably) on the actual cover, and continue the rest onto adjacent pages.

If you publish or distribute Opaque copies of the Document numbering more than 100, you must either include a machine-readable Transparent copy along with each Opaque copy, or state in or with each Opaque copy a computer-network location from which the general network-using public has access to download using public-standard network protocols a complete Transparent copy of the Document, free of added material. If you use the latter option, you must take reasonably prudent steps, when you begin distribution of Opaque copies in quantity, to ensure that this Transparent copy will remain thus accessible at the stated location until at least one year after the last time you distribute an Opaque copy (directly or through your agents or retailers) of that edition to the public.

It is requested, but not required, that you contact the authors of the Document well before redistributing any large number of copies, to give them a chance to provide you with an updated version of the Document.

### 4. MODIFICATIONS

You may copy and distribute a Modified Version of the Document under the conditions of sections 2 and 3 above, provided that you release the Modified Version under precisely this License, with the Modified Version filling the role of the Document, thus licensing distribution and modification of the Modified Version to whoever possesses a copy of it. In addition, you must do these things in the Modified Version:

- A. Use in the Title Page (and on the covers, if any) a title distinct from that of the Document, and from those of previous versions (which should, if there were any, be listed in the History section of the Document). You may use the same title as a previous version if the original publisher of that version gives permission.
- B. List on the Title Page, as authors, one or more persons or entities responsible for authorship of the modifications in the Modified Version, together with at least five of the principal authors of the Document (all of its principal authors, if it has fewer than five), unless they release you from this requirement.
- C. State on the Title page the name of the publisher of the Modified Version, as the publisher.

- D. Preserve all the copyright notices of the Document.
- E. Add an appropriate copyright notice for your modifications adjacent to the other copyright notices.
- F. Include, immediately after the copyright notices, a license notice giving the public permission to use the Modified Version under the terms of this License, in the form shown in the Addendum below.
- G. Preserve in that license notice the full lists of Invariant Sections and required Cover Texts given in the Document's license notice.
- H. Include an unaltered copy of this License.
- I. Preserve the section Entitled "History", Preserve its Title, and add to it an item stating at least the title, year, new authors, and publisher of the Modified Version as given on the Title Page. If there is no section Entitled "History" in the Document, create one stating the title, year, authors, and publisher of the Document as given on its Title Page, then add an item describing the Modified Version as stated in the previous sentence.
- J. Preserve the network location, if any, given in the Document for public access to a Transparent copy of the Document, and likewise the network locations given in the Document for previous versions it was based on. These may be placed in the "History" section. You may omit a network location for a work that was published at least four years before the Document itself, or if the original publisher of the version it refers to gives permission.
- K. For any section Entitled "Acknowledgements" or "Dedications", Preserve the Title of the section, and preserve in the section all the substance and tone of each of the contributor acknowledgements and/or dedications given therein.
- L. Preserve all the Invariant Sections of the Document, unaltered in their text and in their titles. Section numbers or the equivalent are not considered part of the section titles.
- M. Delete any section Entitled "Endorsements". Such a section may not be included in the Modified Version.
- N. Do not retitle any existing section to be Entitled "Endorsements" or to conflict in title with any Invariant Section.
- O. Preserve any Warranty Disclaimers.

If the Modified Version includes new front-matter sections or appendices that qualify as Secondary Sections and contain no material copied from the Document, you may at your option designate some or all of these sections as invariant. To do this, add their titles to the list of Invariant Sections in the Modified Version's license notice. These titles must be distinct from any other section titles.

You may add a section Entitled "Endorsements", provided it contains nothing but endorsements of your Modified Version by various parties—for example, statements of peer review or that the text has been approved by an organization as the authoritative definition of a standard.

You may add a passage of up to five words as a Front-Cover Text, and a passage of up to 25 words as a Back-Cover Text, to the end of the list of Cover Texts in the Modified Version. Only one passage of Front-Cover Text and one of Back-Cover Text may be added by (or through arrangements made by) any one entity. If the Document already includes a cover text for the same cover, previously added by you or by arrangement made by the same entity you are acting on behalf of, you may not add another; but you may replace the old one, on explicit permission from the previous publisher that added the old one.

The author(s) and publisher(s) of the Document do not by this License give permission to use their names for publicity for or to assert or imply endorsement of any Modified Version.

### 5. COMBINING DOCUMENTS

You may combine the Document with other documents released under this License, under the terms defined in section 4 above for modified versions, provided that you include in the combination all of the Invariant Sections of all of the original documents, unmodified, and list them all as Invariant Sections of your combined work in its license notice, and that you preserve all their Warranty Disclaimers.

The combined work need only contain one copy of this License, and multiple identical Invariant Sections may be replaced with a single copy. If there are multiple Invariant Sections with the same name but different contents, make the title of each such section unique by adding at the end of it, in parentheses, the name of the original author or publisher of that section if known, or else a unique number. Make the same adjustment to the section titles in the list of Invariant Sections in the license notice of the combined work.

In the combination, you must combine any sections Entitled "History" in the various original documents, forming one section Entitled "History"; likewise combine any sections Entitled "Acknowledgements", and any sections Entitled "Dedications". You must delete all sections Entitled "Endorsements".

### 6. COLLECTIONS OF DOCUMENTS

You may make a collection consisting of the Document and other documents released under this License, and replace the individual copies of this License in the various documents with a single copy that is included in the collection, provided that you follow the rules of this License for verbatim copying of each of the documents in all other respects.

You may extract a single document from such a collection, and distribute it individually under this License, provided you insert a copy of this License into the extracted document, and follow this License in all other respects regarding verbatim copying of that document.

### 7. AGGREGATION WITH INDEPENDENT WORKS

A compilation of the Document or its derivatives with other separate and independent documents or works, in or on a volume of a storage or distribution medium, is called an "aggregate" if the copyright resulting from the compilation is not used to limit the legal rights of the compilation's users beyond what the individual works permit. When the Document is included in an aggregate, this License does not apply to the other works in the aggregate which are not themselves derivative works of the Document.

If the Cover Text requirement of section 3 is applicable to these copies of the Document, then if the Document is less than one half of the entire aggregate, the Document's Cover Texts may be placed on covers that bracket the Document within the aggregate, or the electronic equivalent of covers if the Document is in electronic form. Otherwise they must appear on printed covers that bracket the whole aggregate.

### 8. TRANSLATION

Translation is considered a kind of modification, so you may distribute translations of the Document under the terms of section 4. Replacing Invariant Sections with translations requires special permission from their copyright holders, but you may include translations of some or all Invariant Sections in addition to the original versions of these Invariant Sections. You may include a translation of this License, and all the license notices in the Document, and any Warranty Disclaimers, provided that you also include the original English version of this License and the original versions of those notices and disclaimers. In case of a disagreement between the translation and the original version of this License or a notice or disclaimer, the original version will prevail.

If a section in the Document is Entitled "Acknowledgements", "Dedications", or "History", the requirement (section 4) to Preserve its Title (section 1) will typically require changing the actual title.

### 9. TERMINATION

You may not copy, modify, sublicense, or distribute the Document except as expressly provided for under this License. Any other attempt to copy, modify, sublicense or distribute the Document is void, and will automatically terminate your rights under this License. However, parties who have received copies, or rights, from you under this License will not have their licenses terminated so long as such parties remain in full compliance.

### 10. FUTURE REVISIONS OF THIS LICENSE

The Free Software Foundation may publish new, revised versions of the GNU Free Documentation License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns. See <a href="http://www.gnu.org/copyleft/">http://www.gnu.org/copyleft/</a>.

Each version of the License is given a distinguishing version number. If the Document specifies that a particular numbered version of this License "or any later version" applies to it, you have the option of following the terms and conditions either of that specified version or of any later version that has been published (not as a draft) by the Free Software Foundation. If the Document does not specify a version number of this License, you may choose any version ever published (not as a draft) by the Free Software Foundation.

## ADDENDUM: How to use this License for your documents

Copyright (c) YEAR YOUR NAME.

Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.2 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled{ldquo}GNU Free Documentation License{rdquo}.

If you have Invariant Sections, Front-Cover Texts and Back-Cover Texts, replace the "with...Texts." line with this:

with the Invariant Sections being LIST THEIR TITLES, with the Front-Cover Texts being LIST, and with the Back-Cover Texts being LIST.

If you have Invariant Sections without Cover Texts, or some other combination of the three, merge those two alternatives to suit the situation.

If your document contains nontrivial examples of program code, we recommend releasing these examples in parallel under your choice of free software license, such as the GNU General Public License, to permit their use in free software.



8/95 Introduction | Uyuni 4.0

## Image Building and Management


## Image Building Overview

Uyuni enables system administrators to build containers, systems, and virtual images. Uyuni helps with creating Image Stores and managing Image Profiles.

Uyuni supports two distinct build types:

- Dockerfile-for more information, see Container Images
- Kiwi image system-for more information, see OS Images

## **Container Images**



## Requirements

The containers feature is available for Salt minions running SUSE Linux Enterprise Server 12 or later. Before you begin, ensure your environment meets these requirements:

- An existing external GitHub or internal GitLab repository containing a Dockerfile and configuration scripts (example scripts are provided in this chapter).
- A properly configured image registry.



#### Registry Provider Solutions

If you require a private image registry you can use an open source solution such as Portus. For additional information on setting up Portus as a registry provider, see the Portus Documentation.

For more information on Containers or CaaS Platform, see:

- SUSE Linux Enterprise Server 12 SP3 Docker Guide
- SUSE CaaS Platform 2 Documentation

### Creating a Build Host

To build images with Uyuni, you will need to create and configure a build host. Container build hosts are Salt minions running SUSE Linux Enterprise 12 or later. This section guides you though the initial configuration for a build host.

From the Uyuni Web UI perform these steps to configure a build host.

- 1. Select a minion to be designated as a build host from the Systems > Overview page.
- 2. From the System Details page for the selected minion assign the containers modules by going to Software > Software Channels and enabling SLE-Module-Containers12-Pool and SLE-Module-Containers12-Updates. Confirm by clicking [ Change Subscriptions ].
- 3. From the **System Details** > **Properties** page, enable Add-on System Type and Container Build Host and confirm by clicking [ **Update Properties** ].
- 4. Install all required packages by applying Highstate. From the system details page select **States** > **Highstate** and click Apply Highstate. Alternatively, apply Highstate from the Uyuni Server command line:

salt '\$your\_minion' state.highstate


### Define Container Build Channels with an Activation Key

Create an activation key associated with the channel that your images will use.



## Relationship Between Activation Keys and Image Profiles

To build containers, you will need an activation key that is associated with a channel other than "SUSE Manager Default".



- 1. Select Main Menu > Systems > Activation Keys.
- 2. Click [ Create Key ].
- 3. Enter a Description and a Key name. Use the drop-down menu to select the Base Channel to associate with this key.
- 4. Confirm with [ Create Activation Key ].


For more information, see [bp.key.managment].

## Creating an Image Store

Define a location to store all of your images by creating an Image Store.



- 1. Select Main Menu > Images > Stores.
- 2. Click **Create** to create a new store.



- 3. Uyuni currently provides support only for the Registry store type. Define a name for the image store in the Label field.
- 4. Provide the path to your image registry by filling in the URI field, as a fully qualified domain name (FQDN) for the container registry host (whether internal or external).

```
registry.example.com
```

The Registry URI can also be used to specify an image store on a used registry.

```
registry.example.com:5000/myregistry/myproject
```

5. Click [ Create ] to add the new image store.


## Creating an Image Profile

Manage Image Profile from the Image Profile page.



Procedure: Create an Image Profile

1. To create an image profile select **Image** > **Profiles** and click [ **Create** ].



2. Provide a name for the image profile by filling in the Label field.



Only lowercase characters are permitted in container labels. If your container image tag is in a format such as myproject/myimage, make sure your image store registry URI contains the /myproject suffix.

- 3. Use a Dockerfile as the Image Type
- 4. Use the drop-down menu to select your registry from the Target Image Store field.
- 5. Enter a Github or Gitlab repository URL (http, https, or token authentication) in the Path field using one of the following formats:

#### Github Path Options

• Github single user project repository

https://github.com/USER/project.git#branchname:folder

• Github organization project repository

https://github.com/ORG/project.git#branchname:folder

• Github token authentication:

If your git repository is private and not publicly accessible, you need to modify the profile's git URL to include authentication. Use this URL format to authenticate with a Github token:

https://USER:<AUTHENTICATION\_TOKEN>@github.com/USER/project.git#master:/container/

#### Gitlab Path Options

• Gitlab single user project repository

https://gitlab.example.com/USER/project.git#master:/container/

• Gitlab groups project repository

https://gitlab.example.com/GROUP/project.git#master:/container/

• Gitlab token authentication If your git repository is private and not publicly accessible, you need to modify the profile's git URL to include authentication. Use this URL format to authenticate with a Gitlab token:

https://gitlab-citoken:<AUTHENTICATION\_TOKEN>@gitlab.example.com/USER/project.git#master:/container/



#### Specifying a Github or Gitlab Branch

If a branch is not specified, the **master** branch will be used by default. If a **folder** is not specified the image sources (**Dockerfile** sources) are expected to be in the root directory of the Github or Gitlab checkout.

1. Select an Activation Key. Activation Keys ensure that images using a profile are assigned to the correct channel and packages.



#### Relationship Between Activation Keys and Image Profiles

When you associate an activation key with an image profile you are ensuring any image using the profile will use the correct software channel and any packages in the channel.

2. Click the [ Create ] button.

## Example Dockerfile and add\_packages Script

This section contains an example Dockerfile. You specify a Dockerfile that will be used during image building when creating an image profile. A Dockerfile and any associated scripts should be stored within an internal or external Github or Gitlab repository:



#### Required Dockerfile Lines



The Dockerfile provides access to a specific repository version served by Uyuni. This example Dockerfile is used by Uyuni to trigger a build job on a build host minion. The ARG parameters ensure that the image that is built is associated with the desired repository version served by Uyuni. The ARG parameters also allow you to build image versions of SUSE Linux Enterprise Server which may differ from the version of SUSE Linux Enterprise Server used by the build host itself.

For example: The ARG repo parameter and the echo command pointing to the repository file, creates and then injects the correct path into the repository file for the desired channel version.

The repository version is determined by the activation key that you assigned to your image profile.

```
FROM registry.example.com/sles12sp2
MAINTAINER Tux Administrator "tux@example.com"
### Begin: These lines Required for use with {productname}
ARG repo
ARG cert
# Add the correct certificate
RUN echo "$cert" > /etc/pki/trust/anchors/RHN-ORG-TRUSTED-SSL-CERT.pem
# Update certificate trust store
RUN update-ca-certificates
# Add the repository path to the image
RUN echo "$repo" > /etc/zypp/repos.d/susemanager:dockerbuild.repo
### End: These lines required for use with {productname}
# Add the package script
ADD add_packages.sh /root/add_packages.sh
# Run the package script
RUN /root/add packages.sh
# After building remove the repository path from image
RUN rm -f /etc/zypp/repos.d/susemanager:dockerbuild.repo
```

This is an example add\_packages.sh script for use with your Dockerfile:

```
#!/bin/bash
set -e

zypper --non-interactive --gpg-auto-import-keys ref

zypper --non-interactive in python python-xml aaa_base aaa_base-extras net-tools timezone vim
less sudo tar
```


### Packages Required for Inspecting Your Images



To inspect images and provide the package and product list of a container to the Uyuni Web UI you will need to install python and python-xml within the container. If these packages remain uninstalled, your images will still build, but the package and product list will be unavailable from the Web UI.

## Building an Image

There are two ways to build an image. You can select **Images > Build** from the left navigation bar, or click the build icon in the **Images > Profiles** list.



#### Procedure: Build an Image

- 1. For this example select **Images > Build**.
- 2. Add a different tag name if you want a version other than the default latest (only relevant to containers).
- 3. Select Build Profile and Build Host.



#### **Profile Summary**

Notice the **Profile Summary** to the right of the build fields. When you have selected a build profile, detailed information about the selected profile will be displayed in this area.

4. To schedule a build click the [ Build ] button.

## Importing an Image

You can import and inspect arbitrary images. Select **Images** > **Images** from the left navigation bar. Complete the text boxes of the **Import** dialog. Once it has processed, the imported image will be listed on the **Images** page.

#### Procedure: Import an Image

- 1. From Images > Images click [ Import ] to open the Import Image dialog.
- 2. In the Import Image dialog complete these fields:

### **Image store**

The registry from where the image will be pulled for inspection.

#### Image name

The name of the image in the registry.

### **Image version**

The version of the image in the registry.

#### **Build host**

The build host that will pull and inspect the image.

#### **Activation key**

The activation key that provides the path to the software channel that the image will be inspected with.

For confirmation, click [ Import ].

The entry for the image is created in the database, and an Inspect Image action on Uyuni is scheduled.

Once it has been processed, you can find the imported image in the Images list. It has a different icon in the Build column, to indicate that the image is imported (see screenshot). The status icon for the imported image can also be seen on the Overview tab for the image.

### Troubleshooting

These are some known problems that you might encounter when working with images:

- HTTPS certificates to access the registry or the git repositories should be deployed to the minion by a custom state file.
- SSH git access using Docker is currently unsupported. You may test it, but SUSE will not provide support.
- If the python and python-xml packages are not installed in your images during the build process, Salt cannot run within the container and reporting of installed packages or products will fail. This will result in an UNKNOWN update status.

## **OS** Images

OS images are built by the Kiwi image system. They can be of various types: PXE, QCOW2, LiveCD images, and others.

For more information about the Kiwi build system, see the Kiwi documentation.

17/95 OS Images | Uyuni 4.0

## Requirements

The Kiwi image building feature is available for Salt minions running SUSE Linux Enterprise Server 12. It is currently not supported to build SUSE Linux Enterprise 15 images.

Kiwi image configuration files and configuration scripts must be accessible in one of these locations:

- Git repository
- · HTTP hosted tarball
- Local build host directory

Example scripts are provided in the following sections.



#### Hardware Requirements for Hosts Running OS Images


Hosts running OS images built with Kiwi need at least 1 GB of RAM. Disk space depends on the actual size of the image. For more information, see the documentation of the underlying system.


## Creating a Build Host

To build all kinds of images with Uyuni, create and configure a build host. OS image build hosts are Salt minions running SUSE Linux Enterprise Server 12 (SP3 or later). This procedure will guide you though the initial configuration for a build host.

From the Uyuni Web UI perform these steps to configure a build host:

- Select a minion that will be designated as a build host from the Main Menu > Systems > Overview page.
- 2. From the **System Details** > **Properties** page, enable the Add-on System Type: OS Image Build Host and confirm with [ **Update Properties** ].





- 3. From the **System Details** > **Software** > **Software Channels** page, enable SLE-Manager-Tools12-Pool and SLE-Manager-Tools12-Updates (or a later version). Schedule and click [ **Confirm** ].
- 4. Install Kiwi and all required packages by applying Highstate. From the system details page select **States > Highstate** and click [ **Apply Highstate** ]. Alternatively, apply Highstate from the Uyuni Server command line:

```
salt '$your_minion' state.highstate
```

### Uyuni Web Server Public Certificate RPM

Build host provisioning copies the Uyuni certificate RPM to the build host. This certificate is used for accessing repositories provided by Uyuni.

The certificate is packaged in RPM by the mgr-package-rpm-certificate-osimage package script. The package script is called automatically during a new Uyuni installation.

When you upgrade the <code>spacewalk-certs-tools</code> package, the upgrade scenario will call the package script using the default values. However if the certificate path was changed or unavailable, you will need to call the package script manually using <code>--ca-cert-full-path</code> <code><path\_to\_certificate></code> after the upgrade procedure has finished.

#### Listing 1. Package script call example

/usr/sbin/mgr-package-rpm-certificate-osimage **--ca-cert-full-path** /root/ssl-build/RHN-ORG-TRUSTED-SSL-CERT

19 / 95 OS Images | Uyuni 4.0

The RPM package with the certificate is stored in a salt-accessible directory such as /usr/share/susemanager/salt/images/rhn-org-trusted-ssl-cert-osimage-1.0-1.noarch.rpm.

The RPM package with the certificate is provided in the local build host repository /var/lib/Kiwi/repo.

The RPM Package with the Uyuni Certificate Must Be Specified in the Build Source

Make sure your build source Kiwi configuration contains rhn-org-trusted-ssl-cert-osimage as a required package in the bootstrap section.



Listing 2. config.xml

```
continuous contin
```


### Define Kiwi Build Channels with an Activation Key


Create an activation key associated with the channel that your images will use. Activation keys are mandatory for OS Image building.



Relationship Between Activation Keys and Image Profiles

To build OS Images, you will need an activation key that is associated with a channel other than "SUSE Manager Default".





- 1. In the Web UI, select Main Menu > Systems > Activation Keys.
- 2. Click Create Key.
- 3. Enter a Description, a Key name, and use the drop-down box to select a Base Channel to associate with the key.
- 4. Confirm with [ Create Activation Key ].

For more information, see [bp.key.managment].

### **Image Store**

OS images can require a significant amount of storage space. Therefore, we recommended that the OS image store is located on a partition of its own or on a btrfs subvolume, separate from the root partition. By default, the image store will be located at /Srv/www/os-images.

Image stores for Kiwi build type



Image stores for Kiwi build type, used to build system, virtual and other images, are not supported yet.

Images are always stored in /srv/www/os-images/<organization id>
and are accessible via HTTP/HTTPS https://<susemanager\_host>/osimages/<organization id>

21/95 OS Images | Uyuni 4.0


## Creating an Image Profile

Manage Image Profiles using the Web UI.



#### Procedure: Create an Image Profile

1. To create an image profile select from Main Menu > Images > Images > Profiles and click [ Create ].



- 2. In the Label field, provide a name for the Image Profile.
- 3. Use Kiwi as the Image Type.
- 4. Image store is automatically selected.
- 5. Enter a Config URL to the directory containing the Kiwi configuration files:
  - a. Git URI
  - b. HTTPS tarball
  - c. Path to build host local directory
- 6. Select an Activation Key. Activation keys ensure that images using a profile are assigned to the correct channel and packages.



#### Relationship Between Activation Keys and Image Profiles

When you associate an activation key with an image profile you are ensuring any image using the profile will use the correct software channel and any packages in the channel.

7. Confirm with the [ Create ] button.

22 / 95 OS Images | Uyuni 4.0

#### Source format options

• Git/HTTP(S) URL to the repository

URL to the Git repository containing the sources of the image to be built. Depending on the layout of the repository the URL can be:

https://github.com/SUSE/manager-build-profiles

You can specify a branch after the # character in the URL. In this example, we use the master branch:

https://github.com/SUSE/manager-build-profiles#master

You can specify a directory that contains the image sources after the : character. In this example, we use OSImage/POS\_Image-JeOS6:

https://github.com/SUSE/manager-build-profiles#master:OSImage/POS\_Image-JeOS6

• HTTP(S) URL to the tarball

URL to the tar archive, compressed or uncompressed, hosted on the webserver.

https://myimagesourceserver.example.org/MyKiwiImage.tar.gz

• Path to the directory on the build host

Enter the path to the directory with the Kiwi build system sources. This directory must be present on the selected build host.

/var/lib/Kiwi/MyKiwiImage

## Example of Kiwi sources

Kiwi sources consist at least of config.xml. Usually config.sh and images.sh are present as well. Sources can also contain files to be installed in the final image under the root subdirectory.

For information about the Kiwi build system, see the Kiwi documentation.

SUSE provides examples of fully functional image sources at the SUSE/manager-build-profiles public GitHub repository.


OS Images | Uyuni 4.0

Listing 3. Example of JeOS config.xml

```
<?xml version="1.0" encoding="utf-8"?>
<image schemaversion="6.1" name="POS Image JeOS6">
     <description type="system">
         <author>Admin User</author>
         <contact>noemail@example.com</contact>
          <specification>SUSE Linux Enterprise 12 SP3 JeOS/specification>
     </description>
     conces>
         <version>6.0.0
         <packagemanager>zypper</packagemanager>
         <bootsplash-theme>SLE</bootsplash-theme>
         <bootloader-theme>SLE</bootloader-theme>
         <locale>en_US</locale>
         <keytable>us.map.gz</keytable>
         <timezone>Europe/Berlin</timezone>
         <hwclock>utc</hwclock>
         <rpm-excludedocs>true</rpm-excludedocs>
         <type boot="saltboot/suse-SLES12" bootloader="grub2" checkprebuilt="true"</pre>
compressed="false" filesystem="ext3" fsmountoptions="acl" fsnocheck="true" image="pxe"
kernelcmdline="quiet"></type>
    </preferences>
             CUSTOM REPOSITORY
    <repository type="rpm-dir">
<source path="this://repo"/>
     </repository>
     <packages type="image">
         <package name="patterns-sles-Minimal"/>
<package name="aaa_base-extras"/> <!-- wouldn't be SUSE without that ;-) -->
<package name="kernel-default"/>
<package name="salt-minion"/></package name="salt-minion"/></package name="salt-minion"/></package name="salt-minion"/></package name="salt-minion"/></package name="salt-minion"/>
     </packages>
     <packages type="bootstrap">
         <package name="sles-release"/>
         <!-- this certificate package is required to access {productname} repositories
               and is provided by {productname} automatically -->
         <package name="rhn-org-trusted-ssl-cert-osimage" bootinclude="true"/>
    </packages>
     <packages type="delete">
         <package name="mtools"/>
<package name="initviocons"/>
     </packages>
</image>
```

## Building an Image

There are two ways to build an image using the Web UI. Either select Main Menu > Images > Build, or click the build icon in the Main Menu > Images > Profiles list.



Procedure: Build an Image

- 1. Select Main Menu > Images > Build.
- 2. Add a different tag name if you want a version other than the default latest (applies only to containers).
- 3. Select the Image Profile and a Build Host.



Profile Summary

A Profile Summary is displayed to the right of the build fields. When you have selected a build profile detailed information about the selected profile will show up in this area.

4. To schedule a build, click the [ **Build** ] button.

## **Image Inspection and Salt Integration**

After the image is successfully built, the inspection phase begins. During the inspection phase SUSE Manager collects information about the image:

- · List of packages installed in the image
- Checksum of the image
- Image type and other image details



If the built image type is PXE, a Salt pillar will also be generated. Image pillars are stored in the /srv/susemanager/pillar\_data/images/ directory and the Salt subsystem can access details about the generated image. Details include where the pillar is located and provided, image checksums, information needed for network boot, and more.

The generated pillar is available to all connected minions.

## **Troubleshooting**

Building an image requires of several dependent steps. When the build fails, investigation of salt states results can help you to identify the source of the failure. Usual checks when the build fails:

25 / 95 OS Images | Uyuni 4.0

- The build host can access the build sources
- There is enough disk space for the image on both the build host and the Uyuni server
- The activation key has the correct channels associated with it
- The build sources used are valid
- The RPM package with the Uyuni public certificate is up to date and available at /usr/share/susemanager/salt/images/rhn-org-trusted-ssl-cert-osimage-1.0-1.noarch.rpm.

For more on how to refresh a public certificate RPM, see Creating a Build Host.

#### Limitations

The section contains some known issues when working with images.

- HTTPS certificates used to access the HTTP sources or Git repositories should be deployed to the minion by a custom state file, or configured manually.
- Importing Kiwi-based images is not supported.

## Listing Image Profiles Available for Building

To list images available for building select **Main Menu** > **Images** > **Images**. A list of all images will be displayed.



Displayed data about images includes an image Name, its Version and the build Status. You will also see the image update status with a listing of possible patch and package updates that are available for the image.

Clicking the [ **Details** ] button on an image will provide a detailed view including an exact list of relevant patches and a list of all packages installed within the image.



The patch and the package list is only available if the inspect state after a build was successful.

## Live Patching with SUSE Manager

### Introduction

Under normal circumstances a system needs to be rebooted after a kernel update. SLE Live Patching allows you skipping the reboot by applying a subset of Linux kernel releases injected via kGraft live patching technology.

In the following sections you will learn how to use SLE Live Patching to avoid the typical reboot requirement after updating a system kernel.

For in depth information covering kGraft use, see <a href="https://www.suse.com/documentation/sles-12/singlehtml/book\_sle\_admin/book\_sle\_admin.html#cha.kgraft">https://www.suse.com/documentation/sles-12/singlehtml/book\_sle\_admin/book\_sle\_admin.html#cha.kgraft</a>.

## **Initial Setup Requirements**

To work with SLE Live Patching the following expectations are assumed:

- Uyuni fully updated.
- At least 1 Salt Minion running SLES 12 SP1 or later and registered with Uyuni .
- The matching SLES 12 SPx channels including the SLE Live Patching child channel fully synced.

## Live Patching Setup

1. Subscribe all systems to be managed via live patching to your fully synced live patching child channels within your systems base channel by browsing to **Software > Software Channels**. Select both live patching channels and change subscription.




When subscribing to a channel that contains a product, the product package will automatically be installed on traditionally registered systems and added to the package state on Salt managed systems. For Salt managed systems please apply the highstate to push these changes to your systems.



1. Use the search field listed under **Software** > **Packages** > **Install** to install the latest kgraft package


to all systems to be managed via live patching.



1. Apply the highstate to enable live patching:



1. Once the highstate has been applied on Salt systems or the package has been installed on traditional systems browse to the systems details page for confirmation that live patching has been enabled. You can check the live patching state listed under the **System Info** > **Kernel** table field:



## **Cloning Channels**

It is considered best practice to clone a vendor channel that will be modified into a new channel with one of the following prefix names: dev, testing, and prod. In the following procedure you will clone the default vendor channel into a new channel named dev-sles12-sp3-pool-x86\_64 using the command line.

1. Open a terminal and as root enter:

```
# spacewalk-manage-channel-lifecycle --list-channels
Spacewalk Username: admin
Spacewalk Password:
Channel tree:

1. sles{sles-version}-sp{sp-ver}-pool-x86_64
    \__ sle-live-patching{sles-version}-pool-x86_64-sp{sp-ver}\__ sle-live-
patching{sles-version}-updates-x86_64-sp{sp-ver}\__ sle-manager-tools{sles-version}-
pool-x86_64-sp{sp-ver}\__ sle-manager-tools{sles-version}-updates-x86_64-sp{sp-ver}\__ sles{sles-version}-sp{sp-ver}-updates-x86_64
```

2. Now use the *--init* argument to automatically create a new development clone of the original vendor channel:

```
spacewalk-manage-channel-lifecycle --init -c sles{sles-version}-sp{sp-ver}-pool-x86_64
```

## Removing Non-live Kernel Patches from the Cloned Channels

In the following procedure you will remove all kernel patch updates located in the dev-sles12 -spSP3 -updates-x86\_64 channel that require a reboot. You created dev-sles12 -spSP3 -updates-x86\_64 during [proc.live.patching.clones].

1. Check the current kernel version in use on your client:

```
# uname -r
3.12.62-60.64.8-default
```

- 2. From the Uyuni Web UI select **Software > Manage Software Channels > Overview > dev-sles12-sp3-updates-x86\_64 > Patches > List/Remove** . Type kernel in the search field. Find the kernel version that matches the kernel in use on your minion.
- 3. Remove all kernel update versions that are later than the current kernel.
- 4. Your channel is now ready to promote for testing SLE Live Patching.

## **Promoting Channels**

The following procedure will guide you through promoting and cloning a development channel to a testing channel. You will change the subscription from the dev repositories on your client to the new testing channel repositories. You will also add the SLE Live Patching child channels to your client.

1. Promote and clone the dev-sles12 -spSP3 -pool-x86\_64 to a new testing channel:

```
{prompt.root}spacewalk-manage-channel-lifecycle -promote -c dev-sles{sles-version}-
sp{sp-ver}-pool-x86_64
```

2. From the Uyuni Web UI under the Systems > 1 tab select your client system to view the

menu:System Details[ page. Select Software > Software Channels . From the Software Channels page you can edit which channels a system is subscribed to. Select the new base software channel, in this case it should be test-sles12-sp3-pool-x86\_64 . Click the Confirm > ] button to switch the Base Software Channel and finalize it by clicking the menu:Modify Base Software Channel[ button.

3. From the Software Channels > ] page select and add both SLE Live Patching child channels by clicking the menu: Change Subscriptions[ button.

## Applying Live Patches to a Kernel

The following procedure will guide you through selecting and viewing available CVE Patches (Common Vulnerabilities and Exposures) then applying these kernel updates using the new SLE Live Patching feature.

1. Select your SLES 12 SPSP3 minion from the **Systems** > ] **page to view its menu:System Details**[. Once you have added the SLES 12 SPSP3 Updates child channel to your client, you should see several <code>Critical</code> software updates available. Click on <code>Critical</code> to see a list of available patches. Select any of these patches listed with the following synopsis: *Important: Security update for the Linux kernel*. All fixed security bugs will be listed along with their number. For example:(CVE-2016-8666)



#### Reboot Icon

Normal or non-live kernel patches always require a reboot. In Uyuni these are represented by a Reboot Required icon located next to the Security shield icon.

2. You can search for individual CVE's by selecting the **Audit** tab from the navigation menu. Try searching for CVE-2016-8666. You will see that the patch is available in the vendor update channel and the systems it applies to will be listed.





Not all security issues can be fixed by applying a live patch. Some security issues can only be fixed by applying a full kernel update and will required a reboot. The assigned CVE numbers for these issues are not included in live patches. A CVE audit will display this requirement.

## Monitoring with Icinga

### Introduction

This chapter provides guidance on the setup of an Icinga server using SLES 12 SP3. For more information, see the Official Icinga documentation: http://docs.icinga.org/latest/en/.

## Installation and Basic Configuration

Icinga packages are found in the SLE-Manager-Tools12-Updates x86\_64.



#### Icinga Installation Location

Do not install Icinga on the Uyuni server. Install Icinga on a stand-alone SUSE Linux Enterprise client.

#### Procedure: Installation and Basic Configuration

- 1. Register the new client with Uyuni and subscribe it to the Uyuni client and update channels. SLES 12 and later include these channels by default.
- 2. Install the required Icinga packages on the new client:

```
zypper in icinga icinga-idoutils-pgsql postgresql postgresql94-server \
monitoring-plugins-all apache2
```

3. Edit the /etc/icinga/objects/contacts.cfg file and add the email address which you will use for reciving alerts.

4. Enable postgres on boot and start the database:

```
systemctl enable postgresql.service systemctl start postgresql.service
```

5. Create the database and user for Icinga:

31/95 Introduction | Uyuni 4.0

```
>psql
postgres=# ALTER USER postgres WITH PASSWORD '<newpassword>';
postgres=# CREATE USER icinga;
postgres=# ALTER USER icinga WITH PASSWORD 'icinga';
postgres=# CREATE DATABASE icinga;
postgres=# GRANT ALL ON DATABASE icinga TO icinga;
postgres=# \q
exit
```

6. Adjust client authentication rights located in /var/lib/pgsql/data/pg\_hba.conf to match the following:

```
# TYPE
        DATABASE
                         USER
                                          ADDRESS
                                                                   METHOD
                        icinga
local
        icinga
                                                                  trust
                        postgres
local
                                                                  ident
        all
# "local" is for Unix domain socket connections only
local
        all
                                                                   trust
# IPv4 local connections:
                                          127.0.0.1/32
host
        all
                         all
                                                                   trust
# IPv6 local connections:
host
        all
                         all
                                          ::1/128
                                                                   trust
# Allow replication connections from localhost, by a user with the
# replication privilege.
#local
         replication
                                                                    peer
                          postgres
#host
         replication
                          postgres
                                           127.0.0.1/32
                                                                     ident
         replication
#host
                          postgres
                                           ::1/128
                                                                     ident
```



#### Placement of Authentication Settings

Ensure the local entries for icinga authentication settings are placed above all other local entries or you will get an error when configuring the database schema. The entries in pg\_hba.conf are read from top to bottom.

7. Reload the Postgres service:

```
systemctl reload postgresql.service
```

8. Configure the database schema by running the following command in /usr/share/doc/packages/icinga-idoutils-pgsql/pgsql/:

```
psql -U icinga -d icinga < pgsql.sql
```

9. Edit the following lines in /etc/icinga/ido2db.cfg to switch from the default setting of mysql to postgres:

```
vi /etc/icinga/ido2db.cfg
db_servertype=pgsql
db_port=5432
```



#### Open Firewall Port

Allow port 5432 through your firewall or you will not be able to access the WebGUI.

10. Create an icinga admin account for logging into the web interface:

```
htpasswd -c /etc/icinga/htpasswd.users icingaadmin
```

11. Enable and start all required services:

```
systemctl enable icinga.service
systemctl start icinga.service
systemctl enable ido2db.service
systemctl start ido2db.service
systemctl enable apache2.service
systemctl start apache2.service
```

12. Login to the WebGUI at: http://localhost/icinga.

This concludes setup and initial configuration of Icinga.

## Icinga and NRPE Quickstart

The following sections provides an overview on monitoring your Uyuni server using Icinga. You will add Uyuni as a host to Icinga and use a Nagios script/plugin to monitor running services via NRPE (Nagios Remote Plugin Executor). This section does not attempt to cover all monitoring solutions Icinga has to offer but should help you get started.

Procedure: Adding Uyunito Icinga for Monitoring

1. On your Uyuni server install the required packages:

```
zypper install nagios-nrpe susemanager-nagios-plugin insserv nrpe monitoring-plugins-nrpe
```

2. Modify the NRPE configuration file located at:

```
/etc/nrpe.cfg
```

Edit or add the following lines:

```
server_port=5666
nrpe_user=nagios
nrpe_group=nagios
allowed_hosts=Icinga.example.com
dont_blame_nrpe=1
command[check_systemd.sh]=/usr/lib/nagios/plugins/check_systemd.sh $ARG1$
```

#### Variable definitions:

#### server\_port

The variable Server\_port defines the port nrpe will listen on. The default port is 5666. This port must be opened in your firewall.

#### nrpe\_user

The variables nrpe\_user and nrpe\_group control the user and group IDs that nrpe will run under. Uyuni probes need access to the database, therefore nrpe requires access to database credentials stored in /etc/rhn/rhn.conf. There are multiple ways to achieve this. You may add the user nagios to the group www (this is already done for other IDs such as tomcat); alternatively you can simply have nrpe run with the effective group ID www in /etc/rhn/rhn.conf.

### allowed\_hosts

The variable allowed\_hosts defines which hosts nrpe will accept connections from. Enter the FQDN or IP address of your Icinga server here.

#### dont\_blame\_nrpe

The use of variable dont\_blame\_nrpe is unavoidable in this example. nrpe commands by default will not allow arguments being passed due to security reasons. However, in this example you should pass the name of the host you want information on to nrpe as an argument. This action is only possible when setting the variable to 1.

### command[check\_systemd.sh]

You need to define the command(s) that nrpe can run on Uyuni. To add a new nrpe command specify a command call by adding command followed by square brackets containing the actual nagios/icinga plugin name. Next define the location of the script to be called on your Uyuni server. Finally the variable \$ARG1\$ will be replaced by the actual host the Icinga server would like information about. In the example above, the command is named check\_systemd.sh. You can specify any name you like but keep in mind the command name is the actual script stored in /usr/lib/nagios/plugins/ on your Uyuni server. This name must also match your probe definition on the Icinga server. This will be described in greater detail later in the chapter. The check\_systemd.sh script/plugin will also be provided in a later section.

3. One your configuration is complete load the new nrpe configuration as root with:

```
systemctl start nrpe
```

This concludes setup of nrpe.

## Add a Host to Icinga

To add a new host to Icinga create a host.cfg file for each host in /etc/icinga/conf.d/. For example susemanager.cfg:

```
define host {
  host_name
                       susemanager
  alias
                       SUSE Manager
  address
                       192.168.1.1
  check_period
                       24x7
  check_interval
  retry_interval
                       1
  max_check_attempts
                       10
                       check-host-alive
  check_command
}
```



Place the host IP address you want to add to Icinga on the Address line.

After adding a new host restart Icinga as root to load the new configuation:

```
systemctl restart icinga
```

## Adding Services to Icinga

To add services for monitoring on a specific host define them by adding a service definition to your host.cfg file located in /etc/icinga/conf.d. For example you can monitor if a systems SSH service is running with the following service definition.

After adding any new services restart Icinga as root to load the new configuration:

```
systemctl restart icinga
```

# Creating Icinga Hostgroups

You can create hostgroups to simplify and visualize hosts logically. Create a hostgroups.cfg file located in /etc/icinga/conf.d/ and add the following lines:

```
define hostgroup {
  hostgroup_name ssh_group
  alias ssh group
  members susemanager,mars,jupiter,pluto,examplehost4
}
```

The members variable should contain the host\_name from within each host.cfg file you created to represent your hosts. Every time you add an additional host by creating a host.cfg ensure you add the host\_name to the members list of included hosts if you want it to be included within a logical hostgroup.

After adding several hosts to a hostgroup restart Icinga as root to load the new configuration:

```
systemctl restart icinga
```

## Creating Icinga Servicegroups

You can create logical groupings of services as well. For example if you would like to create a group of essential Uyuni services which are running define them within a Servicegroups.cfg file placed in /etc/icinga/conf.d/:

Within each host's host.cfg file add a service to a servicegroup with the following variable:

All services that include the Servicegroups variable and the name of the servicegroup will be added to the specified servicegroup. After adding services to a servicegroup restart Icinga as root to load the new configuation:

```
systemctl restart icinga
```

# **Monitoring Systemd Services**

The following section provides information on monitoring uptime of critical Uyuni services.

Procedure: Monitoring Running Systemd Services

1. As root create a new plugin file called check\_systemd.sh in /usr/lib/nagios/plugins/ on your Uyuni server:

```
vi /usr/lib/nagios/plugins/ check_systemd.sh
```

2. For this example you will use an opensource community script to monitor Systemd services. You may also wish to write your own.

```
#!/bin/bash
# Copyright (C) 2016 Mohamed El Morabity <melmorabity@fedoraproject.com>
# This module is free software: you can redistribute it and/or modify it under
 the terms of the GNU General Public License as published by the Free Software
 Foundation, either version 3 of the License, or (at your option) any later
 version.
 This software is distributed in the hope that it will be useful, but WITHOUT
 ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS
# FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.
# You should have received a copy of the GNU General Public License along with
# this program. If not, see <http://www.gnu.org/licenses/>.
PLUGINDIR=$(dirname $0)
. $PLUGINDIR/utils.sh
if [ $# -ne 1 ]; then
echo "Usage: ${0##*/} <service name>" >82
    exit $STATE_UNKNOWN
fi
service=$1
status=$(systemctl is-enabled $service 2>/dev/null)
r=$?
if [ -z "$status" ]; then
    echo "ERROR: service $service doesn't exist"
    exit $STATE_CRITICAL
fi
if [ $r -ne 0 ]; then
    echo "ERROR: service $service is $status"
    exit $STATE_CRITICAL
fi
systemctl --quiet is-active $service
if [ $? -ne 0 ]; then
    echo "ERROR: service $service is not running"
    exit $STATE_CRITICAL
echo "OK: service $service is running"
exit $STATE_OK
```

A current version of this script can be found at: https://github.com/melmorabity/nagios-plugin-systemd-service/blob/master/check\_systemd\_service.sh



#### Non-supported 3rd Party Plugin

The script used in this example is an external script and is not supported by SUSE.

Always check to ensure scripts are not modified or contain malicous code before using them on production machines.

3. Make the script executable:

```
chmod 755 check_systemd.sh
```

4. On your SUSE manager server add the following line to the nrpe.cfg located at /etc/nrpe.cfg:

```
# SUSE Manager Service Checks
command[check_systemd.sh]=/usr/lib/nagios/plugins/check_systemd.sh $ARG1$
```

This will allow the Icinga server to call the plugin via nrpe on Uyuni.

5. Provide proper permissions by adding the script to the sudoers file:

```
visudo
```

```
nagios ALL=(ALL) NOPASSWD:/usr/lib/nagios/plugins/check_systemd.sh
Defaults:nagios !requiretty
```

You can also add permissions to the entire plugin directory instead of allowing permissions for individual scripts:

```
nagios ALL=(ALL) NOPASSWD:/usr/lib/nagios/plugins/
```

6. On your Icinga server define the following command within /etc/icinga/objects/commands.cfg:

```
define command {
      command_name check-systemd-service
      command_line /usr/lib/nagios/plugins/check_nrpe -H $HOSTADDRESS$ -c
      check_systemd.sh -a $ARG1$
}
```

- 7. Now you will add the following critical services to be montitored to your Uyuni host file:
  - o auditlog-keeper.service
  - o jabberd.service
  - spacewalk-wait-for-jabberd.service
  - o tomcat.service
  - o spacewalk-wait-for-tomcat.service
  - o salt-master.service
  - salt-api.service
  - spacewalk-wait-for-salt.service
  - apache2.service
  - o osa-dispatcher.service
  - o rhn-search.service
  - o cobblerd.service
  - taskomatic.service
  - spacewalk-wait-for-taskomatic.service

On your Icinga server add the following service blocks to your Uyuni host file <code>susemanager.cfg</code> file located in <code>/etc/icinga/conf.d/</code>. (This configuration file was created in the previous section <code>Adding a Host to Icinga.</code>)

```
# Monitor Audit Log Keeper
define service {
                               generic-service
       use
       host_name
                               susemanager
       check_interval
       active_checks_enabled
                               Audit Log Keeper Service
       service_description
       servicegroups
                               SUSE Manager Essential Services
       check_command
                               check-systemd-service!auditlog-keeper.service
}
# Monitor Jabberd
define service {
       use
                               generic-service
       host name
                               susemanager
       check interval
       active_checks_enabled
       service_description
                               Jabberd Service
       servicegroups
                               SUSE Manager Essential Services
       check_command
                               check-systemd-service!jabberd.service
# Monitor Spacewalk Wait for Jabberd
define service{
                               generic-service
       use
       host name
                               susemanager
       check_interval
```

```
active checks enabled
                               Spacewalk Wait For Jabberd Service
       service_description
                               SUSE Manager Essential Services
       servicegroups
       check command
                               check-systemd-service!spacewalk-wait-for-
jabberd.service
# Monitor Tomcat
define service{
                               generic-service
       lise
       host_name
                               susemanager
       check_interval
       active_checks_enabled
       service_description
                               Tomcat Service
                               SUSE Manager Essential Services
       servicegroups
       check_command
                               check-systemd-service!tomcat.service
}
# Monitor Spacewalk Wait for Tomcat
define service{
       use
                               generic-service
       host_name
                               susemanager
       check_interval
       active_checks_enabled
       service_description
                               Spacewalk Wait For Tomcat Service
       servicegroups
                               SUSE Manager Essential Services
       check_command
                               check-systemd-service!spacewalk-wait-for-
tomcat.service
# Monitor Salt Master
define service{
       use
                               generic-service
       host_name
                               susemanager
       check_interval
       active checks enabled
       service description
                               Salt Master Service
                               SUSE Manager Essential Services
       servicegroups
       check_command
                               check-systemd-service!salt-master.service
# Monitor Salt API
define service{
                               generic-service
       use
       host_name
                               susemanager
       check_interval
       active_checks_enabled
                               Salt API Service
       service_description
                               SUSE Manager Essential Services
       servicegroups
       check_command
                               check-systemd-service!salt-api.service
}
# Monitor Spacewalk Wait for Salt
define service{
       use
                               generic-service
       host name
                               susemanager
       check_interval
       active_checks_enabled
       service_description
                               Spacewalk Wait For Salt Service
                               SUSE Manager Essential Services
       servicegroups
       check_command
                               check-systemd-service!spacewalk-wait-for-salt.service
}
# Monitor apache2
define service{
                               generic-service
       host name
                               susemanager
       check_interval
```

```
active checks enabled
                               Apache2 Service
       service_description
       servicegroups
                               SÜSE Manager Essential Services
                               check-systemd-service!apache2.service
       check command
}
# Monitor osa dispatcher
define service{
                               generic-service
       IISE
       host name
                               susemanager
       check_interval
       active_checks_enabled
       service_description
                               Osa Dispatcher Service
                               SUSE Manager Essential Services
       servicegroups
                               check-systemd-service!osa-dispatcher.service
       check_command
}
# Monitor rhn search
define service{
       use
                               generic-service
       host name
                               susemanager
       check_interval
       active_checks_enabled
       service_description
                               RHN Search Service
       servicegroups
                               SUSE Manager Essential Services
       check_command
                               check-systemd-service!rhn-search.service
# Monitor Cobblerd
define service{
                               generic-service
       use
       host_name
                               susemanager
       check_interval
       active_checks_enabled
                               Cobblerd Service
       service_description
                               SUSE Manager Essential Services
       servicegroups
       check command
                               check-systemd-service!cobblerd.service
}
# Monitor taskomatic
define service{
       use
                               generic-service
       host_name
                               susemanager
       check_interval
       active_checks_enabled
       service_description
                               Taskomatic Service
                               SUSE Manager Essential Services
       servicegroups
                               check-systemd-service!taskomatic.service
       check_command
}
# Monitor wait for taskomatic
define service{
       use
                               generic-service
       host_name
                               susemanager
       check interval
       active checks enabled
                               Spacewalk Wait For Taskomatic Service
       service_description
       servicegroups
                               SUSE Manager Essential Services
       check_command
                               check-systemd-service!spacewalk-wait-for-
taskomatic.service
```

Each of these service blocks will be passed as the check-systemd-service!\$ARG1\$ variable to SUSE manager server via nrpe. You probably noticed the servicegroups parameter was also included. This adds each service to a servicegroup and has been defined in a

## servicesgroups.cfg file located in /etc/icinga/conf.d/:

```
define servicegroup {
    servicegroup_name SUSE Manager Essential Services
    alias Essential Services
}
```

8. Restart Icinga:

```
systemctl restart icinga
```

# Using the check\_suma\_patches Plugin

You can use the check\_suma\_patches plugin to check if any machines connected to Uyuni as clients require a patch or an update. The following procedure will guide you through the setup of the check\_suma\_patches plugin.

Procedure: Setup check\_suma\_patches

1. On your Uyuni server open /etc/nrpe.cfg and add the following lines:

```
# SUSE Manager check_patches
command[check_suma_patches]=sudo /usr/lib/nagios/plugins/check_suma_patches $ARG1$
```

2. On your Icinga server open /etc/icinga/objects/commands.cfg and define the following command:

3. On your Icinga server open any of your Uyuni client host configration files located at /etc/icinga/conf.d/clients.cfg and add the following service definition:

4. In the above service definition notice that this host is included in the servicegroup labeled *Client Patch Status*. Add the following servicegroup definition to /etc/icinga/conf.d/servicegroups.cfg to create a servicegroup:

- 5.
- ° OK:System is up to date
- Warning: At least one patch or package update is available
- Critical:At least one security/critical update is available
- Unspecified: The host cannot be found in the SUSE Manager database or the host name is not unique

This concludes setup of the check\_suma\_patches plugin.

# Using the check\_suma\_lastevent Plugin

You can use the check\_suma\_lastevent plugin to display the last action executed on any host.

The following procedure will guide you through the setup of the check\_suma\_patches plugin.

Procedure: Setup check\_suma\_lastevent

1. On your Uyuni server open /etc/nrpe.cfg and add the following lines:

```
# Check SUSE Manager Hosts last events
command[check_events]=sudo /usr/lib/nagios/plugins/check_suma_lastevent $ARG1$
```

2. On the Icinga server open /etc/icinga/objects/commands.cfg and add the following lines:

```
define command {
        command_name check_events
        command_line /usr/lib/nagios/plugins/check_nrpe -H manager.suse.de -c $ARG1$
    -a $HOSTNAME$
}
```

3. On your Icinga server add the following line to a host.cfg service definition:

- 4. Status will be reported as follows:
  - OK:Last action completed successfully

- ° Warning: Action is currently in progress
- Critical:Last action failed
- o Unspecified:The host cannot be found in the Uyuni database or the host name is not unique

This concludes setup of the check\_suma\_lastevent plugin.

## **Additional Resources**

For more information, see Icinga's official documentation located at http://docs.icinga.org/latest/en.

For some excellent time saving configuration tips and tricks not covered in this guide, see the following section located within the official documentation: http://docs.icinga.org/latest/en/objecttricks.html




# **Kubernetes**

# **Prerequisites**

The prerequisites listed below should be met before proceeding.

- At least one Kubernetes or \_SUSE CaaS Platform \_ cluster available on your network
- Uyuni configured for container management



• virtual-host-gatherer-Kubernetes package installed on your Uyuni server

## Requirements

- Kubernetes version 1.5.0 or higher. Alternatively use SUSE CaaS Platform (SUSE CaaS Platform includes Kubernetes 1.5.0 by default)
- Docker version 1.12 or higher on the container build host



To enable all Kubernetes related features within the Web UI, the virtual-host-gatherer-Kubernetes package must be installed.

# Register Kubernetes as a Virtual Host Manager

*Kubernetes* clusters are registered with SUSE Manager as virtual host managers. Registration and authorization begins with importing a kubeconfig file using Kubernetes official command line tool kubectl.

Procedure: Registering a Kubernetes Cluster with Uyuni

- 1. Select **Systems** > **Virtual Host Managers** from the navigation menu.
- 2. Expand the Create dropdown in the upper right corner of the page and select **Kubernetes Cluster**.
- 3. Input a label for the new Virtual Host Manager.
- 4. Select the kubeconfig file which contains the required data for the Kubernetes cluster.
- 5. Select the correct *context* for the cluster, as specified in the kubeconfig file.
- 6. Click Create.

### View the List of Nodes in a Cluster

- 1. Select **Systems** > **Virtual Host Managers** from the navigation menu.
- 2. Select the desired Kubernetes cluster to view it.

45 / 95 Prerequisites | Uyuni 4.0

- 3. Node data is not refreshed during registration. To refresh node data, click on Schedule refresh data.
- 4. Refresh the browser. If the node data is not available wait a few moments and try again.

# Obtain Runtime Data about Images

See the following steps to find runtime data for images.

- 1. Select **Images** > **Images** from the navigation menu.
- 2. In the image list table, take notice of the new runtime columns. These are labeled: Revision, Runtime and Instances. Initially these columns will not provide useful data.
  - Revision: An artificial sequence number which increments on every rebuild for manager-built images, or on every reimport for externally built images.
  - ° Runtime: Overall status of the running instances of the image throughout the registered clusters. The status can be one of the following:
    - All instances are consistent with SUSE Manager: All the running instances are running the same build of the image as tracked by SUSE Manager.
    - Outdated instances found: Some of the instances are running an older build of the image. A
      redeploy of the image into the pod may be required.
    - No information: The checksum of the instance image does not match the image data contained in SUSE Manager. A redeploy of the image into the pod may be required.
  - Instances: Number of instances running this image across all the clusters registered in SUSE Manager. A breakdown of numbers can be seen by clicking on the pop-up icon next to the number.

# Build an image for deployment in Kubernetes

The following steps will help you build an image for deployment in Kubernetes.

- 1. Under **Images** > **Stores**, create an image store.
- 2. Under **Images** > **Profiles**, create an image profile (with a Dockerfile which is suitable to deploy to Kubernetes).
- 3. Under Images > Build, build an image with the new profile and wait for the build to finish.
- 4. Deploy the image into one of the registered Kubernetes clusters (via kubect1).
- 5. Notice the updated data in Runtime and Instances columns in the respective image row.

# Import a Previously Deployed Image in Kubernetes

The following steps will guide you through importing a previously deployed image in Kubernetes.

- 1. Select an image that has already been deployed to any of your registered Kubernetes clusters.
- 2. Add the registry owning the image to SUSE Manager as an image store.
- 3. Select **Images** > **Images** , click **Import** from the top-right corner, fill in the form fields and click **Import**.
- 4. Notice the updated data in Runtime and Instances columns in the respective image row.

### Obtain Additional Runtime Data

The following steps will help you find additional runtime data.

- 1. Select to **Images** > **Images** , click the **Details** button on the right end of a row which has running instances.
- 2. Under the Overview tab, notice the data in Runtime and Instances fields under Image Info section.
- 3. Select the Runtime tab.
- 4. Here is a breakdown of the Kubernetes pods running this image in all the registered clusters including the following data:
  - Pod name
  - · Namespace which the pod resides in
  - The runtime status of the container in the specific pod. Status icons are explained in the preceding example.

# Rebuild a Previously Deployed Image in Kubernetes

The following steps will guide you through rebuilding an image which has been deployed to a Kubernetes cluster.

- 1. Go to **Images** > **Images** , click the Details button on the right end of a row which has running instances. The image must be manager-built.
- 2. Click the Rebuild button located under the Build Status section and wait for the build to finish.
- 3. Notice the change in the Runtime icon and title, reflecting the fact that now the instances are running a previous build of the image.

### Role Based Access Control Permissions and Certificate Data



Currently, only kubeconfig files containing all embedded certificate data may be used with SUSE Manager

The API calls from Uyuni are:

- GET /api/v1/pods
- GET /api/v1/nodes

According to this list, the minimum recommended permissions for Uyuni should be as follows:

• A ClusterRole to list all the nodes:

```
resources: ["nodes"]
verbs: ["list"]
```

• A ClusterRole to list pods in all namespaces (role binding must not restrict the namespace):

```
resources: ["pods"]
verbs: ["list"]
```

Due to a a 403 response from /pods, the entire cluster will be ignored by SUSE Manager.

For more information on working with RBAC Authorization see: https://kubernetes.io/docs/admin/authorization/rbac/

# Virtualization

Uyuni allows you to autoinstall and manage Xen and KVM VM Guests on a registered VM Host Server. To autoinstall a VM Guest, an autoinstallable distribution and an autoinstallation profile (AutoYaST or Kickstart) need to exist on Uyuni. VM Guests registered with Uyuni can be managed like "regular" machines. In addition, basic VM Guest management tasks such as (re)starting and stopping or changing processor and memory allocation can be carried out using Uyuni.

The following documentation is valid in the context of traditional clients. Salt minions must be treated differently:

• Autoinstallation is not supported, but creation of a guest from a template disk image is supported.



#### Limitation to Xen and KVM Guests

Autoinstalling and managing VM Guests via Uyuni is limited to Xen and KVM guests. Uyuni uses libvirt for virtual machine management. Currently, virtual machines from other virtualization solutions such as VMware\* or VirtualBox\*, are recognized as VM Guests, but cannot be managed from within Uyuni.

# **Autoinstalling VM Guests**

With Uyuni you can automatically deploy Xen and KVM VM Guests using AutoYaST or Kickstart profiles. It is also possible to automatically register the VM Guests, so they can immediately be managed by Uyuni.

## Requirements on Uyuni

Setting up and managing VM Guests with Uyuni does not require special configuration options. However, you need to provide activation keys for the VM Host Server and the VM Guests, an autoinstallable distribution and an autoinstallation profile. To automatically register VM Guests with Uyuni, a bootstrap script is needed.

#### **Activation Keys**

Just like any other client, VM Host Server and VM Guests need to be registered with Uyuni using activation keys. Find details on how to set up activation keys at [create.act.keys]. While there are no special requirements for a VM Guest key, at least the following requirements must be met for the VM Host Server activation key.

#### VM Host Server Activation Key: Minimum Requirements

- Entitlements: Provisioning, Virtualization Platform.
- Packages: rhn-virtualization-host, osad.

If you want to manage the VM Host Server system from Uyuni (for example, by executing remote scripts), the package rhncfg-actions needs to be installed as well.

#### Setting up an Autoinstallable Distribution

To autoinstall clients from Uyuni, you need to provide an "autoinstallable distribution", also referred to as autoinstallable tree or installation source. This installation source needs to be made available through the file system of the Uyuni host. It can for example be a mounted local or remote directory or a "loop-mounted" ISO image. It must match the following requirements:

• Kernel and initrd location:

#### Red Hat Enterprise Linux / Generic RPM

- images/pxeboot/vmlinuz
- images/pxeboot/initrd.img

#### **SUSE**

- boot/arch/loader/initrd
- boot/arch/loader/linux
  - The Base Channel needs to match the autoinstallable distribution.

#### Autoinstallation package sources



There is a fundamental difference between Red Hat Enterprise Linux and SUSE systems regarding the package sources for autoinstallation. The packages for a Red Hat Enterprise Linux installation are being fetched from the **Base Channel**. Packages for installing SUSE systems are being fetched from the autoinstallable distribution.

As a consequence, the autoinstallable distribution for a SUSE system has to be a complete installation source (same as for a regular installation).

#### Procedure: Creating Autoinstallable Distribution

- Make sure an installation source is available from a local directory. The data source can be any kind
  of network resource, a local directory or an ISO image (which has to be "loop-mounted"). Files and
  directories must be world readable.
- 2. Log in to the Uyuni Web UI and navigate to **Systems** > **Autoinstallation** > **Distributions** > **Create Distribution**.
- 3. Fill out the form Create Autoinstallable Distribution as follows:

### Distribution Label

Choose a unique name for the distribution. Only letters, numbers, hyphens, periods, and underscores are allowed; the minimum length is 4 characters. This field is mandatory.

### Tree Path

Absolute local disk path to installation source. This field is mandatory.

### Base Channel

Channel matching the installation source. This channel is the package source for non-SUSE installations. This field is mandatory.

### Installer Generation

Operating system version matching the installation source. This field is mandatory.

### Kernel Options

Options passed to the kernel when booting for the installation. There is no need to specify the install= parameter since it will automatically be added. Moreover, the parameters self\_update=0 pt.options=self\_update are added automatically to prevent AutoYaST from updating itself during the system installation. This field is optional.

### Post Kernel Options

Options passed to the kernel when booting the installed system for the first time. This field is optional.

4. Save your settings by clicking [ Create Autoinstallable Distribution ].

To edit an existing Autoinstallable Distribution, go to Systems > Autoinstallation > Distributions and click on a Label. Save your settings by clicking [Update Autoinstallable Distribution].

#### Providing an Autoinstallation Profile

Autoinstallation profiles (AutoYaST or Kickstart files) contain all the installation and configuration data needed to install a system without user intervention. They may also contain scripts that will be executed after the installation has completed.

All profiles can be uploaded to Uyuni and be edited afterwards. Kickstart profiles can also be created from scratch with Uyuni.

A minimalist AutoYaST profile including a script for registering the client with Uyuni is listed in Minimalist AutoYaST Profile for Automated Installations and Useful Enhancements. For more information, examples and HOWTOs on AutoYaST profiles, refer to SUSE Linux Enterprise AutoYaST (https://www.suse.com/documentation/sles-12/book\_autoyast/data/book\_autoyast.html). For more information on Kickstart profiles, refer to your Red Hat Enterprise Linux documentation.

### SUSE Linux Enterprise 15 Systems

You need the installation media to setup the distribution. Starting with version 15, there is only one installation media. You will use the same one for SLES, SLED, and all the other SUSE Linux Enterprise 15 based products.

In the AutoYaST profile specify which product is to be installed. For installing SUSE Linux Enterprise Server use the following snippet in autoyast.xml:

Then then specify all the required modules as add-on in autoyast.xml. This is a minimal SLE-Product-SLES15-Pool selection that will result in a working installation and can be managed by Uyuni:

- SLE-Manager-Tools15-Pool
- SLE-Manager-Tools15-Updates
- SLE-Module-Basesystem15-Pool
- SLE-Module-Basesystem15-Updates
- SLE-Product-SLES15-Updates

It is also recommended to add the following modules:

- SLE-Module-Server-Applications15-Pool
- SLE-Module-Server-Applications 15-Updates

#### **Uploading an Autoinstallation Profile**

- Log in to the Uyuni Web interface and open Systems > Autoinstallation > Profiles > Upload New Kickstart/AutoYaST File.
- 2. Choose a unique name for the profile. Only letters, numbers, hyphens, periods, and underscores are allowed; the minimum length is 6 characters. This field is mandatory.
- 3. Choose an Autoinstallable Tree from the drop-down menu. If no Autoinstallable Tree is available, you need to add an Autoinstallable Distribution. Refer to Setting up an Autoinstallable Distribution for instructions.
- 4. Choose a Virtualization Type from the drop-down menu. KVM and Xen (para-virtualized and fully-virtualized) are available. Do not choose Xen Virtualized Host here.
- 5. Scroll down to the File to Upload dialog, click [Browse] to select it, then click [Upload File].
- 6. The uploaded file will be displayed in the File Contents section, where you can edit it.
- 7. Click [ Create ] to store the profile.

To edit an existing profile, go to **Systems** > **Autoinstallation** > **Profiles** and click on a Label. Make the desired changes and save your settings by clicking [ **Create** ].

#### Editing existing Kickstart profiles



If you are changing the Virtualization Type of an existing Kickstart profile, it may also modify the bootloader and partition options, potentially overwriting any user customizations. Be sure to review the Partitioning tab to verify these settings when changing the Virtualization Type.

#### **Creating a Kickstart Profile**



Currently it is only possible to create autoinstallation profiles for Red Hat Enterprise Linux systems. If installing a SUSE Linux Enterprise Server system, you need to upload an existing AutoYaST profile as described in Uploading an Autoinstallation Profile.

- 1. Log in to the Uyuni Web interface and go to **Systems > Autoinstallation > Profiles > Create New Kickstart File.**
- 2. Choose a unique name for the profile. The minimum length is 6 characters. This field is mandatory.
- 3. Choose a Base Channel. This channel is the package source for non-SUSE installations and must match the Autoinstallable Tree. This field is mandatory.
- 4. Choose an Autoinstallable Tree from the drop-down menu. If no Autoinstallable Tree is available, you need to add an Autoinstallable Distribution. Refer to Setting up an Autoinstallable Distribution for instructions.
- 5. Choose a Virtualization Type from the drop-down menu. KVM and Xen (para-virtualized and fully-virtualized) are available. Do not choose Xen Virtualized Host here.
- 6. Click the [ Next ] button.
- 7. Select the location of the distribution files for the installation of your VM Guests. There should already be a Default Download Location filled out and selected for you on this screen. Click the [ Next ] button.
- 8. Choose a root password for the VM Guests. Click the [ Finish ] button to generate the profile.

This completes Kickstart profile creation. After generating a profile, you are taken to the newly-created Kickstart profile. You may browse through the various tabs of the profile and modify the settings as you see fit, but this is not necessary as the default settings should work well for the majority of cases.

### Adding a Registration Script to the Autoinstallation Profile

A VM Guest that is autoinstalled does not get automatically registered. Adding a section to the autoinstallation profile that invokes a bootstrap script for registration will fix this. The following procedure describes adding a corresponding section to an AutoYaST profile. Refer to your Red Hat Enterprise Linux documentation for instructions on adding scripts to a Kickstart file.

1. First, provide a bootstrap script on the Uyuni:

- Create a bootstrap script for VM Guests on the Uyuni as described in [generate.bootstrap.script].
- One of Log in as root to the konsole of Uyuni and go to /Srv/www/htdocs/pub/bootstrap. Copy bootstrap.sh (the bootstrap script created in the previous step) to for example, bootstrap\_vm\_guests.sh in the same directory.
- Edit the newly created file according to your needs. The minimal requirement is to include the
  activation key for the VM Guests (see Activation Keys for details). We strongly recommend to
  also include one or more GPG keys (for example, your organization key and package signing
  keys).
- 2. Log in to the Uyuni Web interface and go to **Systems** > **Autoinstallation** > **Profiles**. Click on the profile that is to be used for autoinstalling the VM Guests to open it for editing.

Scroll down to the **File Contents** section where you can edit the AutoYaST XML file. Add the following snippet at the end of the XML file right before the closing 
/profile> tag and replace the given IP address with the address of the Uyuni server. See Minimalist AutoYaST Profile for Automated Installations and Useful Enhancements for an example script.



### Only one <SCripts> section allowed

If your AutoYaST profile already contains a <scripts> section, do not add a second one, but rather place the <script> part above within the existing <scripts> section!

3. Click **Update** to save the changes.

### VM Host Server Setup

A VM Host Server system serving as a target for autoinstalling VM Guests from Uyuni must be capable of running guest operating systems. This requires either KVM or Xen being properly set up. For installation instructions for SUSE Linux Enterprise Server systems refer to the *SLES Virtualization Guide* available from <a href="https://www.suse.com/documentation/sles-12/book\_virt/data/book\_virt.html">https://www.suse.com/documentation/sles-12/book\_virt/data/book\_virt.html</a>. For instructions on setting up a Red Hat Enterprise Linux VM Host Server refer to your Red Hat Enterprise Linux documentation.

Since Uyuni uses libvirt for VM Guest installation and management, the libvirtd needs to run on the VM Host Server. The default libvirt configuration is sufficient to install and manage VM Guests

from Uyuni. However, in case you want to access the VNC console of a VM Guest as a non-root user, you need to configure libvirt appropriately. Configuration instructions for libvirt on SUSE Linux Enterprise Server are available in the *SLES Virtualization Guide* available from <a href="https://www.suse.com/documentation/sles-12/book\_virt/data/book\_virt.html">https://www.suse.com/documentation/sles-12/book\_virt/data/book\_virt.html</a> available from <a href="http://www.suse.com/documentation/sles-11/">http://www.suse.com/documentation/sles-11/</a>. For instructions for a Red Hat Enterprise Linux VM Host Server refer to your Red Hat Enterprise Linux documentation.

Apart from being able to serve as a host for KVM or Xen guests, which are managed by libvirt, a VM Host Server must be registered with Uyuni.

- 1. Make sure either KVM or Xen is properly set up.
- 2. Make sure the libvirtd is running.
- 3. Register the VM Host Server with Uyuni:
  - Create a bootstrap script on the Uyuni as described in [generate.bootstrap.script].
  - Download the bootstrap script from susemanager.example.com/pub/bootstrap/bootstrap.sh to the VM Host Server.
  - Edit the bootstrap script according to your needs. The minimal requirement is to include the
    activation key for the VM Host Server (see Activation Keys for details). We strongly
    recommend to also include one or more GPG keys (for example, your organization key and
    package signing keys).
  - Execute the bootstrap script to register the VM Host Server.

### VM Host Server setup on Salt clients

If the VM Host Server is registered as a Salt minion, a final configuration step is needed in order to gather all the guest VMs defined on the VM Host Server:

- 1. From the **System Details** > **Properties** page, enable the Add-on System Type Virtualization Host and confirm with [ **Update Properties** ].
- 2. Schedule a Hardware Refresh. On the **System Details > Hardware** page click [ **Schedule Hardware Refresh** ].

#### VM Host Server setup on Traditional clients

Once the registration process is finished and all packages have been installed, enable the <code>OSad</code> (Open Source Architecture Daemon). On a SUSE Linux Enterprise Server system this can be achieved by running the following commands as user root:

```
systemctl stop rhnsd
systemctl disable rhnsd
```

```
systemctl enable osad systemctl start osad
```



### osad*Together with* rhnsd

The rhnsd daemon checks for scheduled actions every four hours, so it can take up to four hours before a scheduled action is carried out. If many clients are registered with Uyuni, this long interval ensures a certain level of load balancing since not all clients act on a scheduled action at the same time.

However, when managing VM Guests, you usually want actions like rebooting a VM Guest to be carried out immediately. Adding OSad ensures that. The OSad daemon receives commands over the jabber protocol from Uyuni and commands are instantly executed. Alternatively you may schedule actions to be carried out at a fixed time in the future (whereas with rhnsd you can only schedule for a time in the future plus up to four hours).

## **Autoinstalling VM Guests**

Once all requirements on the Uyuni and the VM Host Server are met, you can start to autoinstall VM Guests on the host. Note that VM Guests will not be automatically registered with Uyuni, therefore we strongly recommend to modify the autoinstallation profile as described in Adding a Registration Script to the Autoinstallation Profile. VM Guests need to be registered to manage them with Uyuni. Proceed as follows to autoinstall a VM Guest.





It is not possible to install more than one VM Guest at a time on a single VM Host Server. When scheduling more than one autoinstallation with Uyuni make sure to choose a timing, that starts the next installation after the previous one has finished. If a guest installation starts while another one is still running, the running installation will be cancelled.

- 1. In the Web UI click the Main Menu > Systems > Systems tab.
- 2. Click the VM Host Server's name to open its System Status page.
- 3. Open the form for creating a new VM Guest by clicking **Virtualization** > **Provisioning**. Fill out the form by choosing an autoinstallation profile and by specifying a name for the VM Guest (must not already exist on VM Host Server). Choose a proxy if applicable and enter a schedule. To change the VM Guest's hardware profile and configuration options, click [ **Advanced Options** ].
- 4. Finish the configuration by clicking [Schedule Autoinstallation and Finish]. The Session Status page opens for you to monitor the autoinstallation process.

#### Checking the Installation Log

To view the installation log, click **Events** > **History** on the **Session Status** page. On the **System History Event** page you can click a **Summary** entry to view a detailed log.



In case an installation has failed, you can [ **Reschedule** ] it from this page once you have corrected the problem. You do not have to configure the installation again.

If the event log does not contain enough information to locate a problem, log in to the VM Host Server console and read the log file for your package manager. If you are using the rhnsd, you may alternatively immediately trigger any scheduled actions by calling rhn\_check on the VM Host Server. Increase the command's verbosity by using the options -v, -vv, or -vvv, respectively.

# Managing VM Guests

Basic VM Guest management actions such as restarting or shutting down a virtual machine as well as changing the CPU and memory allocation can be carried out in the Uyuni Web interface if the following requirements are met:

- VM Host Server must be a KVM or Xen host.
- libvirtd must be running on VM Host Server.
- VM Host Server must be registered with Uyuni.

In addition, if you want to see the profile of the VM Guest, install packages, etc., you must also register it with Uyuni.

All actions can be triggered in the Uyuni Web UI from the Virtualization page of the VM Host Server. Navigate to this page by clicking the Main Menu > Systems > Systems. On the resulting page, click the VM Host Server's name and then on Virtualization. This page lists all VM Guests for this host, known to Uyuni.

## Displaying a VM Guest 's Profile

Click the name of a VM Guest on the VM Host Server's Virtualization page to open its profile page with detailed information about this guest. For details, refer to [ref.webui.systems.systems].

A profile page for a virtual system does not differ from a regular system's profile page. You can perform the same actions (for example, installing software or changing its configuration).

# Starting, Stopping, Suspending and Resuming a VM Guest

To start, stop, restart, suspend, or resume a VM Guest, navigate to the VM Host Server's Virtualization page. Click the corresponding action button in the row of the VM Guest.

Alternatively, check one or more Guests listed in the table and click the corresponding button above the table. [Confirm] the action on the displayed popup dialog.

#### Automatically restarting a VM Guest



Automatically restarting a VM Guest when the VM Host Server reboots is not enabled by default on VM Guests and cannot be configured from Uyuni. Refer to your KVM or Xen documentation. Alternatively, you may use libvirt to enable automatic reboots.

## Changing the CPU or RAM allocation of a VM Guest

To change the CPU or RAM allocation of a VM Guest navigate to the VM Host Server's Virtualization page. Click the [Edit] button on the VM Guest row. Change the values to the desired ones in the next page and click the [Update] button to apply.

The memory allocation can be changed on the fly, provided the memory ballooning driver is installed on the VM Guest. If this is not the case, or if you want to change the CPU allocation, you need to shutdown the guest first. Refer to Starting, Stopping, Suspending and Resuming a VM Guest for details.

You can also perform more advanced VM Guest editing tasks on Salt minions, such as adding or removing disks and network interfaces, and changing the display type.

### Deleting a VM Guest



Deleting a VM Guest is only possible on Salt minions, not on traditional clients.

To delete a VM Guest, navigate to the VM Host Server's Virtualization page. Click the [ **Delete** ] button on the VM Guest row. Alternatively, check one or more **Guests** listed in the table and click the [ **Delete** ] button above the table. [ **Confirm** ] the action on the displayed popup dialog.

## Displaying VM Guest graphical console

In order to be able to display a VM Guest VNC or Spice graphical console, the virtual host corresponding port needs to be reachable by the server. The VM Guest graphics settings also have to listen on at least the virtual host address. This is the default for any VM Guest created using the web interface.

### Virtual Hosts

# Inventorying vCenter/vSphere ESXi Hosts with Uyuni

### Introduction

Foreign virtual hosts (such as vCenter and vSphere ESXi) can be inventoried using the Virtual Host Manager. From the vSphere Client you can define roles and permissions for vCenter and vSphere ESXi

58 / 95 Virtual Hosts | Uyuni 4.0

users allowing vSphere objects and resources to be imported and inventoried by Uyuni. Objects and resources are then displayed as foreign hosts on the Uyuni **Systems** > **Virtual Systems** page.

The following sections will guide you through:

- Requirements
- Overview of permissions and roles
- · Adding vCenter and vSphere ESXi hosts to Uyuni

### Requirements

This table displays the default API communication port and required access rights for inventorying objects and resources:

Ports / Permissions	Description
443	Default port that Uyuni uses to access the ESXi API for obtaining infrastructure data
read-only	All vCenter/ESXi objects and resources that should be inventoried by the Virtual Host Manager should be at least assigned the <i>read-only</i> role. Mark objects and resources with <i>no-access</i> to exclude them from the inventory.

### Permissions and Roles Overview

This section will guide you through assigning user permissions and roles in vCenter/ESXi.

A user is someone who has been authorized to access an ESXi host. The Virtual Host Manager (located on the SUSE Manager server) will inventory ESXi data defined by assigned roles and permissions on a user account.

For example: The user *John* has been assigned the *read-only* access role to all servers and datacenters in his company with one exception. John's account has been assigned the *no-access* role on the company's *Financial Database server*. You decide to use John's user account and add the ESXi host to SUSE Manager. During the inventory the *Financial Database server* will be excluded.

Keep user access roles in mind when planning to add ESXi hosts to SUSE manager. Note that SUSE Manager will not inventory any objects or resources assigned with the *no-access* role on any user account.



#### User Roles/Permissions

When planning to add new ESXi hosts to SUSE Manager, consider if the roles and permissions assigned users require need to be inventoried by SUSE Manager.

# Adding New Users and Assigning Roles

See the official vSphere documentation on adding new users and assigning roles.

• Authentication and User Management

## Inventorying vCenter/vSphere ESXi Hosts

This procedure guides you through inventorying a VSphere ESXi host with Uyuni.

- 1. From the Uyuni Web UI select **Main Menu** > **Systems** > **Virtual Host Managers** from the left navigation bar.
- 2. From the upper right corner of the Virtual Host Managers page select [ Create ] VMWare-based.
- 3. From the *Add a VMware-based Virtual Host Manager* page complete these fields with your ESXi host data:

#### Label

Custom name for your Virtual Host Manager

#### Hostname

Fully-qualified domain name (FQDN) or host IP address

#### **Port**

Default ESXi API port

### Username


Assign a username



Remember that only objects and resources which match a user's defined role will be inventoried. Set the user's role on objects and resources you want inventoried to *read-only*.

#### **Password**

ESXi users password



- 4. Click the [ Create ] button.
- 5. From the **Systems** > **Virtual Host Managers** page select the new Virtual Host manager.
- 6. From the Virtual Host Managers > Properties page click the [ Refresh ] button.



If you do not refresh the data from a new Virtual Host Manager, host data will not be inventoried and therefore will not be displayed under **Systems** > **Virtual Systems**.

7. View inventoried ESXi host objects and resources by selecting Systems > Virtual Systems .



# Security

# Setup a Minion to Master Validation Fingerprint

In highly secure network configurations you may wish to ensure your minions are connecting a specific master. To setup validation from minion to master enter the masters fingerprint within the /etc/salt/minion configuration file. See the following procedure:

1. On the master enter the following command as root and note the fingerprint:

```
salt-key -F master
```

On your minion, open the minion configuration file located in /etc/salt/minion. Uncomment the following line and enter the masters fingerprint replacing the example fingerprint:

```
master_finger: 'ba:30:65:2a:d6:9e:20:4f:d8:b2:f3:a7:d4:65:11:13'
```

2. Restart the salt-minion service:

```
# systemctl restart salt-minion
```

For more information on configuring security from a minion see: https://docs.saltstack.com/en/latest/ref/configuration/minion.html

# Signing Repository Metadata

# Generate a Custom GPG key

To sign repository metadata a custom GPG key is required. Create a new GPG key as root via the following steps.

```
$> gpg --gen-key
Please select what kind of key you want:
   (1) RSA and RSA (default)
   (2) DSA and Elgamal
   (3) DSA (sign only)
(4) RSA (sign only)
Your selection? 1
RSA keys may be between 1024 and 4096 bits long.
What keysize do you want? (2048)
Requested keysize is 2048 bits
Please specify how long the key should be valid.
         0 = key does not expire
      <n> = key expires in n days
      <n>w = key expires in n weeks
      <n>m = key expires in n months
      <n>y = key expires in n years
Key is valid for? (0)
Key does not expire at all
Is this correct? (y/N) y
GnuPG needs to construct a user ID to identify your key.
Real name: company sign key
Email address: company@example.com
You selected this USER-ID:
    "company sign key <company@example.com>"
Change (N)ame, (C)omment, (E)mail or (O)kay/(Q)uit? O
You need a Passphrase to protect your secret key.
gpg: key 607FABDB marked as ultimately trusted
public and secret key created and signed.
gpg: checking the trustdb
gpg: 3 marginal(s) needed, 1 complete(s) needed, PGP trust model
gpg: depth: 0 valid: 1 signed: 0 trust: 0-, 0q, 0n, 0m, 0f, 1u
     2048R/607FABDB 2018-07-09
      Key fingerprint = ACF5 4698 EC70 FD6A F8C9 942B A7A1 9301 607F ABDB
uid
          [ultimate] company sign key <company@example.com>
      2048R/A812FA62 2018-07-09
sub
```

# Configure signing metadata

There are two configuration files which needs to be changed to enable signing of metadata.

- 1. /etc/rhn/signing.conf to specify KEYID and PASSPHRASE
- 2. /etc/rhn/rhn.conf to enable signing metadata

Example for /etc/rhn/signing.conf:

```
KEYID="607FABDB"

GPGPASS="MySecretPassword"
```

To enable signing of metadata please add the following in /etc/rhn/rhn.conf:

```
sign_metadata = 1
```

All spacewalk services must be restarted after modifying 'rhn.conf'.

## Regenerate all metadata

After enabling signing metadata, all metadata needs to be re-generated. This can be done with a small SQL script:

```
$> spacewalk-sql -i
psql (9.6.9)
Type "help" for help.

susemanager=# insert into rhnRepoRegenQueue (id, CHANNEL_LABEL, REASON, FORCE)
susemanager-# (select sequence_nextval('rhn_repo_regen_queue_id_seq'), C.label, 'changed
signing of metadata', 'Y' from rhnChannel C);
INSERT 0 40
susemanager=# \q
$>
```

## Trust the GPG key on all clients

When this feature is enabled, all clients have to trust the new GPG key. If the new GPG key is not imported on the client, installation or updating of packages is not possible.

1. Export the GPG key and make it availabel in the 'pub/' directory.

```
# gpg --batch --export -a -o <output filename> <KEYID>
$> gpg --batch --export -a -o /srv/www/htdocs/pub/company.key 607FABDB
```

2. Import the GPG key on all clients

This can be done using a remote command on all clients

```
# rpm --import http://<server.domain.top/pub/keyname.key
$> rpm --import http://suma-refhead-srv.mgr.suse.de/pub/company.key
```



**Tip** 

For salt managed systems it might make sense to use a state to trust GPG keys.

# **Authentication Methods**

### **Authentication Via PAM**

As security measures become increasingly complex, SUSE Manager supports network-based authentication systems via Pluggable Authentication Modules (PAM). PAM is a suite of libraries that allows to integrate SUSE Manager with a centralized authentication mechanism, thus eliminating the need to remember multiple passwords. SUSE Manager supports LDAP, Kerberos, and other network-based authentication systems via PAM. To enable SUSE Manager to use PAM in your organization's authentication infrastructure, follow the steps below.

1. Set up a PAM service file (default location: /etc/pam.d/susemanager) then enforce its use by adding the following line to /etc/rhn/rhn.conf:

```
pam_auth_service = susemanager
```



This assumes the PAM service file is named susemanager.

- 2. To enable a new or existing user to authenticate with PAM, proceed to the **Create User** page and select the checkbox labeled Pluggable Authentication Modules (PAM) positioned below the password and password confirmation fields.
- 3. To authenticate a SLES system against Kerberos add the following lines to /etc/pam.d/susemanager:

```
#%PAM-1.0
auth include common-auth
account include common-account
password include common-password
session include common-session
```



To register a Red Hat Enterprise Linux System against Kerberos add the following lines to /etc/pam.d/susemanager

```
#%PAM-1.0

auth required pam_env.so

auth sufficient pam_krb5.so no_user_check

auth required pam_deny.so

account required pam_krb5.so no_user_check
```

+

YaST can now be used to configure PAM, when packages such as yast2-ldap-client and yast2-kerberos-client are installed; for detailed information on configuring PAM, see the SUSE Linux Enterprise Server Security Guide <a href="https://www.suse.com/documentation/sles-12/book\_security/data/">https://www.suse.com/documentation/sles-12/book\_security/data/</a>

part\_auth.html. This example is not limited to Kerberos; it is generic and uses the current server configuration. Note that only network based authentication services are supported.



#### Changing Passwords

Changing the password on the SUSE Manager Web interface changes only the local password on the SUSE Manager server. But this password may not be used at all if PAM is enabled for that user. In the above example, for instance, the Kerberos password will not be changed.

# Authentication Via eDirectory and PAM

1. First check to ensure eDirectory authentication is working with your current OS for example:

```
#getent passwd
```

2. If users are returned from eDirectory then create the following file:

```
# cat /etc/pam.d/susemanager
```

3. And add the following content:

```
#%PAM-1.0
auth include common-auth
account include common-account
password include common-password
session include common-session
#
```

4. Finally add the following lines to the Uyuni conf file:

```
# grep -i pam /etc/rhn/rhn.conf
pam_auth_service = susemanager
```

5. You may now create users with the same id that appears on eDirectory and mark the Use PAM check-box from the SUSE Manager WebUI.

# Example Quest VAS Active Directory Authentication Template

If you are using Quest VAS for active directory authentication, you can use the following /etc/pam.d/susemanager file.

#%PAM-1.0
auth required pam\_env.so
auth sufficient pam\_vas3.so no\_user\_check
auth requisite pam\_vas3.so echo\_return
auth required pam\_deny.so
account required pam\_vas3.so no\_user\_check



# Using a Custom SSL Certificate

The following section will guide you through using a custom certificate with Uyuni 4.0 and SUSE Manager Proxy 4.0.

## **Prerequisites**

The following list provides requirements for using a custom certificate.

- A Certificate Authority (CA) SSL public certificate file
- A Web server SSL private key file
- A Web server SSL public certificate file
- · Key and Certificate files must be in PEM format



#### Hostname and SSL Keys

The hostname of the web server's SSL keys and relevant certificate files must match the hostname of the machine which they will be deployed on.



#### Intermediate Certificates

In case you want to use CAs with intermediate certificates, merge the intermediate and root CA certificates into one file. It is important that the intermediate certificate comes first within the combined file.

# Setup

After completing YaST firstboot procedures, export your current environment variables and point them to the correct SSL files to be imported. Running these commands will make the default certificate obsolete after executing the yast2 susemanagersetup command. For more information on YaST firstboot, see <a href="https://www.suse.com/documentation/suse-manager-3/singlehtml/suse\_manager21/book\_susemanager\_install/book\_susemanager\_install.html#sec.manager.inst.setup.">https://www.suse.com/documentation/suse-manager-3/singlehtml/suse\_manager21/book\_susemanager\_install/book\_susemanager\_install.html#sec.manager.inst.setup.</a>

1. Export the environment variables and point to the SSL files to be imported:

```
export CA_CERT=`path_to_CA_certificate_file`export
SERVER_KEY=`path_to_web_server_key`export SERVER_CERT=`path_to_web_server_certificate`
```

2. Execute Uyuni setup with

```
yast2 susemanagersetup
```

Proceed with the default setup. Upon reaching the Certificate Setup window during YaST installation, fill in random values, as these will be overridden with the values specified in

68 / 95 Prerequisites | Uyuni 4.0

### [bp.cert.custom.setup.proc.export].



Shell Requirements

Make sure that you execute yast2 Susemanagersetup from within the same shell the environment variables were exported from.

# Using a Custom Certificate with SUSE Manager Proxy

After completing the installation with yast found in [advanced.topics.proxy.quickstart] continue with a modified [at.manager.proxy.run.confproxy] procedure:

- 1. Execute configure-proxy.sh.
- 2. When prompted with:

Do you want to import existing certificates?

Answer with y.

3. Continue by following the script prompts.

# Backup and Restore

Back up your Uyuni installation regularly, in order to prevent data loss. Because Uyuni relies on a database as well as the installed program and configurations, it is important to back up all components of your installation. This chapter contains information on the files you need to back up, and introduces the smdba tool to manage database backups. It also contains information about restoring from your backups in the case of a system failure.



#### Backup Space Requirements

Regardless of the backup method you use, you must have available at least three times the amount of space your current installation uses. Running out of space can result in backups failing, so check this often.

### Backing up Uyuni

The most comprehensive method for backing up your Uyuni installation is to back up the relevant files and directories. This can save you time in administering your backup, and can be faster to reinstall and resynchronize in the case of failure. However, this method requires significant disk space and could take a long time to perform the backup.

If you want to only back up the required files and directories, use this list:



To make this process simpler, and more comprehensive, we recommend backing up the entire /etc and /root directories, not just the ones specified here.

- /etc/cobbler/
- /etc/dhcp.conf
- /etc/fstab and any ISO mountpoints you require.
- /etc/rhn/
- /etc/salt
- /etc/sudoers
- /etc/sysconfig/rhn/
- /root/.gnupg/
- /root/.ssh
  - This file exists if you are using an SSH tunnel or SSH push. You will also need to have saved a copy of the id-susemanager key.
- /root/ssl-build/
- /srv/pillar
- /srv/salt

- /srv/tftpboot/
- /srv/www/cobbler
- /srv/www/htdocs/pub/
- /var/lib/cobbler/
- /var/lib/rhn/kickstarts/
- /var/spacewalk/
- Any directories containing custom data (such as scripts, Kickstart profiles, AutoYaST, and custom RPMs).



You will also need to back up your database, which you can do by copying /var/spacewalk/db-backup or by using the smdba tool, which is explained later in this chapter.

#### Procedure: Restore from a Manual Backup

- 1. Re-install Uyuni
- 2. Re-synchronize your installation with the mgr-sync tool.
- 3. You can choose to re-register your product, or skip the registration and SSL certificate generation sections.
- 4. Re-install the /root/ssl-build/rhn-org-httpd-ssl-key-pair-MACHINE\_NAME-VER-REL.noarch.rpm package.
- 5. Schedule the re-creation of search indexes next time the rhn-search service is started:

rcrhn-search cleanindex

6. If you did not have /var/spacewalk/packages/ in your backup, but the source repository still exists, you can restore it by performing a complete channel synchronization.

# Administering the Database with smdba

The smdba tool is used for managing a local PostgreSQL database. It allows you to back up and restore your database, and manage backups. It can also be used to check the status of your database, and perform administration tasks, such as restarting.



The smdba tool works with local PostgreSQL databases only, it will not work with remotely accessed databases, or Oracle databases.



The smdba tool requires sudo access, in order to execute system changes. Ensure you have enabled sudo access for the admin user before you begin, by checking the /etc/sudoers file for this line:

```
admin ALL=(postgres) /usr/bin/smdba
```

Check the runtime status of your database with the smdba db-status command. This command will return either online or offline:

```
smdba db-status
Checking database core... online
```

Starting and stopping the database can be performed with smdba db-start and smdba db-stop

```
smdba db-start
Starting core... done

smdba db-stop
Stopping the SUSE Manager database...
Stopping core: done
```

### Database Backup with smdba

The smdba tool performs a continuous archiving backup. This backup method combines a log of every change made to the database during the current session, with a series of more traditional backup files. When a crash occurs, the database state is first restored from the most recent backup file on disk, then the log of the current session is replayed exactly, to bring the database back to a current state. A continuous archiving backup with smdba is performed with the database running, so there is no need for downtime.

This method of backing up is stable and generally creates consistent snapshots, however it can take up a lot of storage space. Ensure you have at least three times the current database size of space available for backups. You can check your current database size by navigating to /var/lib/pgsql/ and running df -h.

The smdba tool also manages your archives, keeping only the most recent backup, and the current archive of logs. The log files can only be a maximum file size of 16 MB, so a new log file will be created once the files reach this size. Every time you create a new backup, previous backups will be purged to release disk space. We recommend you use Cron to schedule your smdba backups to ensure that your storage is managed effectively, and you always have a backup ready in case of failure.

# Performing a Manual Database Backup

The smdba tool can be run directly from the command line. We recommend you run a manual database

backup immediately after installation, or if you have made any significant changes to your configuration.



When Smdba is run for the first time, or if you have changed the location of the backup, it will need to restart your database before performing the archive. This will result in a small amount of downtime. Note that regular database backups will not require any downtime.

#### Procedure: Performing a Manual Database Backup

- 1. Allocate permanent storage space for your backup. In this procedure, we will be using an NFS share located at /var/spacewalk/. This will become a permanent target for your backup, so ensure it will remain accessible by your server at all times.
- 2. In your backup location, create a directory for the backup:

```
sudo -u postgres mkdir /var/spacewalk/db-backup
```

Or, as root:

```
install -d -o postgres /var/spacewalk/db-backup
```

3. Ensure you have the correct permissions set on the backup location:

```
chown postgres:postgres /var/spacewalk/db-backup
```

4. To run a backup for the first time, run the smdba backup-hot command with the enable option set. This will create the backup in the specified directory, and, if necessary, restart the database:

```
smdba backup-hot --enable=on --backup-dir=/var/spacewalk/db-backup
```

5. Check that the backup files exist in the /mnt/backup/database directory, to ensure that your backup has been successful.

#### Scheduling Automatic Backups

You do not need to shut down your system in order to perform a database backup with Smdba. However, because it is a large operation, database performance can slow down while the backup is running. We recommend you schedule regular database backups for a low-traffic period, to minimize disruption.



Ensure you have at least three times the current database size of space available for backups. You can check your current database size by navigating to /var/lib/pqsql/ and running df -h.

Procedure: Scheduling Automatic Backups

1. Create a directory for the backup, and set the appropriate permissions:

```
# mkdir /var/spacewalk/db-backup
# chown -R postgres:postgres /var/spacewalk/db-backup
# chmod 700 /var/spacewalk/db-backup
```

2. Open /etc/cron.d/db-backup-mgr, or create it if it doesn't exist, and add the following line to create the cron job:

```
0 2 * * * root /usr/bin/smdba backup-hot --enable=on --backup-dir=/var/spacewalk/db -backup
```

3. Check the backup directory regularly to ensure the backups are working as expected.

# Restoring from Backup

The Smdba tool can be used to restore from backup in the case of failure.

Procedure: Restoring from Backup

1. Shutdown the database:

```
smdba db-stop
```

2. Start the restore process and wait for it to complete:

```
smdba backup-restore start
```

3. Restart the database:

```
smdba db-start
```

4. Check if there are differences between the RPMs and the database.

```
spacewalk-data-fsck
```

### **Archive Log Settings**

In SUSE Manager with an embedded database, archive logging is enabled by default. This feature allows the database management tool Smdba to perform hot backups.

With archive log enabled, even more data is stored on the hard disk:

• Postgresql maintains a limited number of archive logs. Using the default configuration, approx. 64 files with a size of 16 MiB are stored.

Creating a user and syncing the channels:

- SLES12-SP2-Pool-x86\_64
- SLES12-SP2-Updates-x86\_64
- SLE-Manager-Tools12-Pool-x86\_64-SP2
- SLE-Manager-Tools12-Updates-x86\_64-SP2

Postgresql will generate an additional ~1 GB of data. So it is important to think about a backup strategy and create a backups in a regular way.

Archive logs are stored at:

/var/lib/pgsql/data/pg\_xlog/(postgresql)

### Retrieving an Overview of Occupied Database Space

Database administrators may use the subcommand Space-overview to get a report about occupied table spaces, for example:

The following command is available for Postgresql. For a more detailed report, use the Space-tables subcommand. It lists the table and its size, for example:

```
smdba space-tables
SUSE Manager Database Control. Version 1.5.2
Copyright (c) 2012 by SUSE Linux Products GmbH
Table
                                        Size
public.all_primary_keys
                                         0 bytes
public.all_tab_columns
                                         0 bytes
public.allserverkeywordsincereboot
                                         0 bytes
public.dblink_pkey_results
                                         0 bytes
                                         8192 bytes
public.dual
public.evr_t
                                         0 bytes
                                         32 kB
public.log
```

### Moving the Database

It is possible to move the database to another location. For example if your database storage space is running low. The following procedure will guide you through moving the database to a new location for use by SUSE Manager.

Procedure: Moving the Database

1. The default storage location for SUSE Manager is: /var/lib/pgsql/. You would like to move it, for example to: /storage/postgres/. To begin, stop the running database with:

```
# rcpostgresql stop
```

Shutdown running spacewalk services with:

```
# spacewalk-service stop
```

2. Copy the current working directory structure with the following syntax:

```
cp [OPTION]... SOURCE... DIRECTORY
```

using the -a, --archive option. For example:

```
# cp -ar /var/lib/pgsql/ /storage/postgres/
```

This command will copy the contents of /var/lib/pgsql/ to /storage/postgres/pgsql/.



The contents of the /var/lib/pgsql needs to remain the same or the SUSE Manager database may malfunction. You also should ensure there is enough available disk space.

3. Mount the new database directory with:

```
# mount /storage/postgres/pgsql
```

4. Make sure ownership is postgres:postgres and not root:root by changing to the new directory and running the following command:

```
/var/lib/pgsql/ # cd /storage/postgres/pgsql/
/storage/postgres/pgsql/ # l
total 8
drwxr-x--- 4 postgres postgres 47 Jun 2 14:35 ./
```

- 5. Add the new database mount location to your servers fstab by editing etc/fstab.
- 6. Start the database with:

```
# rcpostgresql start
```

Start spacewalk-services with:

```
# spacewalk-service start
```

### Recovering from a Crashed Root Partition

This section provides guidance on restoring your server after its root partition has crashed. This section assumes you have setup your server similar to the procedure explained in Getting Started guide with separate partitions for the database and for channels mounted at  $\var/\lib/pgsql$  and  $\var/\spacewalk/$ .

Procedure: Recovering from a Crashed Root Partition

- 1. Start by installing SLES12 SP2 and the SUSE Manager Extension. Do not mount the /var/spacewalk and /var/lib/pgsql partitions.
- 2. Once installation of SUSE Manager has completed shutdown services with spacewalk-service shutdown and the database with rcpostgresql stop.
- 3. Mount your /var/spacewalk and /var/lib/pgsql partitions and restore the directories listed in section one.
- 4. Start SUSE Manager services and the database with spacewalk-services start and rcpostgresql start
- 5. SUSE Manager should now operate normally without loss of your database or synced channels.

#### **Database Connection Information**

The information for connecting to the SUSE Manager database is located in /etc/rhn/rhn.conf:

```
db_backend = postgresql
db_user = susemanager
db_password = susemanager
db_name = susemanager
db_host = localhost
db_port = 5432
db_ssl_enabled =
```

# Optimization and Scalability

### Optimizing Apache and Tomcat

#### Altering Apache and Tomcat Parameters



Apache and Tomcat Parameters should only be modified with support or consulting as these parameters can have severe and catastrophic performance impacts on your server when improperly adjusted. SUSE will not be able to provide support for catastrophic failure when these advanced parameters are modified without consultation. Tuning values for Apache httpd and Tomcat requires that you align these parameters with your server hardware. Furthermore testing of these altered values should be performed within a test environment.

### Apache's httpd MaxClients Parameter

The MaxClients setting determines the number of Apache httpd processes, and thus limits the number of client connections that can be made at the same time (SUSE Manager uses the pre-fork MultiProcessing Modules). The default value for MaxClients in SUSE Manager is 150. If you need to set the MaxClients value greater than 150, Apache httpd's ServerLimit setting and Tomcat's maxThreads must also be increased accordingly (see below).



The Apache httpd MaxClients parameter must always be less or equal than Tomcat's maxThreads parameter!

If the MaxClients value is reached while the software is running, new client connections will be queued and forced to wait, this may result in timeouts. You can check the Apache httpd's error.log for details:

[error] Server reached MaxClients setting, consider increasing the MaxClients setting

The default MaxClients parameter can be overridden on SUSE Manager by editing the server-tuning.conf file located at /etc/apache2/. For example server-tuning.conf file:

```
# prefork MPM
   <IfModule prefork.c>
            # number of server processes to start
           # http://httpd.apache.org/docs/2.2/mod/mpm_common.html#startservers
           # minimum number of server processes which are kept spare
# http://httpd.apache.org/docs/2.2/mod/prefork.html#minspareservers
           MinSpareServers
           # maximum number of server processes which are kept spare
           # http://httpd.apache.org/docs/2.2/mod/prefork.html#maxspareservers
           MaxSpareServers
           # highest possible MaxClients setting for the lifetime of the Apache process.
           # http://httpd.apache.org/docs/2.2/mod/mpm common.html#serverlimit
           ServerLimit
            # maximum number of server processes allowed to start
            # http://httpd.apache.org/docs/2.2/mod/mpm_common.html#maxclients
                                150
           # maximum number of requests a server process serves
           # http://httpd.apache.org/docs/2.2/mod/mpm common.html#maxrequestsperchild
           MaxRequestsPerChild 10000
   </IfModule>
```



Whenever the Apache httpd MaxClients parameter is changed, the ServerLimit must also be updated to the same value, or the change will have no effect.

#### Tomcat's maxThreads Parameter

Tomcat's maxThreads represents the maximum number of request processing threads that it will create. This value determines the maximum number of simultaneous requests that it is able to handle. All HTTP requests to the SUSE Manager server (from clients, browsers, XMLRPC API scripts, etc.) are handled by Apache httpd, and some of them are routed to Tomcat for further processing. It is thus important that Tomcat is able to serve the same amount of simultaneous requests that Apache httpd is able to serve in the worst case. The default value for SUSE Manager is 200 and should always be equal or greater than Apache httpd's MaxClients. The maxThreads value is located within the Server.xml file located at /etc/tomcat/.

Example relevant lines in **Server.xml**:

```
<Connector port="8009" protocol="AJP/1.3" redirectPort="8443" URIEncoding="UTF-8"
address="127.0.0.1" maxThreads="200" connectionTimeout="20000"/>
<Connector port="8009" protocol="AJP/1.3" redirectPort="8443" URIEncoding="UTF-8"
address="::1" maxThreads="200" connectionTimeout="20000"/>
```

#### **Tuning Notes**

When configuring Apache httpd's MaxClients and Tomcat's maxThreads parameters you should also take into consideration that each HTTP connection will need one or more database connections. If the RDBMS is not able to serve an adequate amount of connections, issues will arise. See the following equation for a rough calculation of the needed amount of database connections:



#### Where:

- 3 is the number of Java processes the server runs with pooled connections (Tomcat, Taskomatic and Search)
- java\_max is the maximum number of connections per Java pool (20 by default, changeable in /etc/rhn/rhn.conf via the hibernate.c3p0.max\_size parameter)
- apache\_max is Apache httpd's MaxClients
- 60 is the maximum expected number of extra connections for local processes and other uses

### Big Scale Deployment (1000 Minions or More)

In the following sections find considerations about a big scale deployment. In this context, a big scale compromises 1000 minions or more.

#### General Recommendations

SUSE recommends the following in a big scale Uyuni deployment:

- Uyuni servers should have at least 8 recent x86 cores, 32 GiB of RAM, and, most important, fast I/O devices such as at least an SSD (2 SSDs in RAID-0 are strongly recommended).
- Proxies with many minions (hundreds) should have at least 2 recent x86 cores and 16 GiB of RAM.
- Use one SUSE Manager Proxy per 500-1000 clients. Keep into account that download time depends on network capacity. Here is a rough example calculation with physical link speed of 1 GB/s:

```
400 Megabytes * 3000 / 119 Megabyte/s / 60
= 169 Minutes
```

This is:

Size of updates \* Number of minions / Theoretical download speed / 60

- Depending on hardware you can accept hundreds of minion keys.
- Plan time for onboarding minions- at least one hour per 1000 minions.
- It is not recommended onboarding more than approx. 1000 minions directly to the Uyuni server-proxies should be used instead. This is because every minion can use up to 3 TCP connections simultaneously, and too many TCP connections can cause performance issues.
- If the following error appears in output of dmesg, you probably have an excessive number of minions attached to a single Uyuni server or proxy for the ARP cache to contain all of their addresses:

```
kernel: neighbour table overflow
```

In that case, increase the ARP cache values via Sysctl, for example, by adding the following lines to /etc/sysctl.conf:

```
net.ipv4.neigh.default.gc_thresh1 = 4096
net.ipv4.neigh.default.gc_thresh2 = 8192
net.ipv4.neigh.default.gc_thresh3 = 16384
net.ipv4.neigh.default.gc_interval = 60
net.ipv4.neigh.default.gc_stale_time = 120
```



#### Start Small and Scale Up

Always start small and scale up gradually. Keep the server monitored in order to identify possible issues early.

### **Tuning Proposals**

SUSE proposes the following tuning settings in a big scale Uyuni deployment:

- Increase the maximum Tomcat heap memory to face a potentially long queue of Salt return results. Set 8 GiB instead of the current default 1 GiB: parameter Xmx16 in /etc/sysconfig/tomcat (affects onboarding and Action execution).
- Increase the number of Taskomatic workers, allowing to parallelize work on a high number of separate jobs. Set parameter org.quartz.threadPool.threadCount = 100 in /etc/rhn/rhn.conf (affects onboarding and staging).
- Allow Taskomatic to check for runnable jobs more frequently to reduce latency. Set parameter org.quartz.scheduler.idleWaitTime = 1000 in /etc/rhn/rhn.conf (affects onboarding, staging and Action execution).
- Increase Tomcat's Salt return result workers to allow parallelizing work on a high number of Salt return results. Set parameter java.message\_queue\_thread\_pool\_size = 100 in /etc/rhn/rhn.conf (affects patching).
- Increase the number of PostgreSQL connections available to Java applications (Tomcat, Taskomatic) according to the previous parameters, otherwise extra workers will starve waiting for a connection.

Set parameter hibernate.c3p0.max\_size = 150 in /etc/rhn/rhn.conf (affects all minion operations). Make sure enough PostgreSQL connections are configured before changing this parameter - refer to smdba system-check autotuning --help to get automatic tuning of the PostgreSQL configuration file while changing the number of available connections. Additional manual tuning is usually not necessary but might be required depending on scale and exact use cases.

- Increase the number of Taskomatic's minion-action-executor worker threads allowing to parallelize the scheduling of Actions to minions. Set parameter taskomatic.com.redhat.rhn.taskomatic.task.MinionActionExecutor.parallel \_threads = 8 in /etc/rhn/rhn.conf (affects all minion operations, especially staging).
- Increase Salt's presence ping timeouts if responses might come back later than the defaults. Set parameters java.salt\_presence\_ping\_timeout = 20 and java.salt\_presence\_ping\_gather\_job\_timeout = 20 in /etc/rhn/rhn.conf (affects all minion operations).
- Increase the number of Salt master workers so that more requests can run in parallel (otherwise Tomcat and Taskomatic workers will starve waiting for the Salt API, and Salt will not be able to serve files timely). Set parameter worker\_threads: 100 in /etc/salt/master.d/susemanager.conf (affects onboarding and patching).
  - Increase this parameter further if file management states fail with the error "Unable to manage file: Message timed out"
  - Note that Salt master workers can consume significant amounts of RAM (typically about 70 MB per worker). It is recommended to keep usage monitored when increasing this value and to do so in relatively small increments (eg. 20) until failures are no longer produced.
- Disable daily comparison of configuration files. Click on **Admin** > **Task Schedules**, then on the [compare-configs-default] link, then on the [Disable Schedule] button and finally on [Delete Schedule].
- Increase the maximum heap memory for the search daemon to be able to index many minions. Set 4 GiB instead of the current default 512 MB: add rhn-search.java.maxmemory=4096 in /etc/rhn/rhn.conf (affects background indexing only).

Note that increasing the number of Postgres connections will require more RAM, make sure the Uyuni server is monitored and swap is never used.

Also note the above settings should be regarded as guidelines-they have been tested to be safe but care should be exercised when changing them, and consulting support is highly recommended.

# **Troubleshooting**

This chapter provides guidance on registering cloned systems with SUSE Manager. This includes both Salt and Traditional clients. For more information, see <a href="https://www.novell.com/support/kb/doc.php?">https://www.novell.com/support/kb/doc.php?</a> id=7012170.

### Registering Cloned Salt Minions

Procedure: Registering a Cloned Salt Minion with SUSE Manager

Quick Tips

1. Clone your system (for example using the existing cloning mechanism of your favorite Hypervisor)





Each step in this section is performed on the cloned system, this procedure does not manipulate the original system, which will still be registered to SUSE Manager. The cloned virtual machine should have a different UUID from the original (this UUID is generated by your hypervisor) or SUSE Manager will overwrite the original system data with the new one.

2. Make sure your machines have different hostnames and IP addresses, also check that /etc/hosts contains the changes you made and the correct host entries.

The next step you take will depend on the Operating System of the clone.

The following scenario can occur after on-boarding cloned Salt minions. If after accepting all cloned minion keys from the onboarding page and you see only one minion on the System Overview page, this is likely due to these machines being clones of the original and using a duplicate machine-id. Perform the following steps to resolve this conflict based on OS.

#### Procedure: SLES 12 Registering Salt Clones

1. SLES 12: If your machines have the same machine ids then delete the file on each minion and recreate it:

```
# rm /etc/machine-id
# rm /var/lib/dbus/machine-id
# dbus-uuidgen --ensure
# systemd-machine-id-setup
```

#### Procedure: SLES 11 Registering Salt Clones

1. SLES 11: As there is no systemd machine id, generate one from dbus:

```
# rm /var/lib/dbus/machine-id
# dbus-uuidgen --ensure
```

If your machines still have the same minion id then delete the minion\_id file on each minion (FQDN will

be used when it is regenerated on minion restart):

```
# rm /etc/salt/minion_id
```

Finally delete accepted keys from Onboarding page and system profile from SUSE Manager, and restart the minion with:

```
# systemctl restart salt-minion
```

You should be able to re-register them again, but each minion will use a different '/etc/machine-id' and should now be correctly displayed on the System Overview page.

### Registering Cloned Traditional Systems

This section provides guidance on troubleshooting cloned traditional systems registered via bootstrap.

Procedure: Registering a Cloned System with SUSE Manager (Traditional Systems)

1. Clone your system (using your favorite hypervisor.)

#### Quick Tips



Each step in this section is performed on the cloned system, this procedure does not manipulate the original system, which will still be registered to SUSE Manager. The cloned virtual machine should have a different UUID from the original (this UUID is generated by your hypervisor) or SUSE Manager will overwrite the original system data with the new one.

- 2. Change the Hostname and IP addresses, also make sure /etc/hosts contains the changes you made and the correct host entries.
- 3. Stop rhnsd daemon with:

```
# /etc/init.d/rhnsd stop
```

or alternativly:

- # rcrhnsd stop
- 4. Stop osad with:

```
# /etc/init.d/osad stop
```

or alternativly:

```
# rcosad stop
```

5. Remove the osad authentification configuration file and the systemid with:

```
# rm -f /etc/sysconfig/rhn/{osad-auth.conf,systemid}
```

The next step you take will depend on the Operating System of the clone.

Procedure: SLES 12 Registering A Cloned Traditional System

1.

If your machines have the same machine ids then delete the file on each client and recreate it:

```
# rm /etc/machine-id
# rm /var/lib/dbus/machine-id
# dbus-uuidgen --ensure
# systemd-machine-id-setup
```

2. Remove the following credential files:

```
# rm -f /etc/zypp/credentials.d/{SCCcredentials,NCCcredentials}
```

3. Re-run the bootstrap script. You should now see the cloned system in SUSE Manager without overwriting the system it was cloned from.

Procedure: SLES 11 Registering A Cloned Traditional System

1. Continued from section 1 step 5:

```
# suse_register -E
```

(--erase-local-regdata, Erase all local files created from a previous executed registration. This option make the system look like never registered)

2. Re-run the bootstrap script. You should now see the cloned system in SUSE Manager without overwriting the system it was cloned from.

Procedure: SLES 10 Registering A Cloned Traditional System

1. Continued from section 1 step 5:

```
# rm -rf /etc/{zmd,zypp}
```

2.

3.

```
# rm -rf /var/lib/zmd/
```

4. Re-run the bootstrap script. You should now see the cloned system in SUSE Manager without overwriting the system it was cloned from.

Procedure: RHEL 5,6 and 7

1. Continued from section 1 step 5:

```
# rm -f /etc/NCCcredentials
```

2. Re-run the bootstrap script. You should now see the cloned system in SUSE Manager without overwriting the system it was cloned from.

### Typical OSAD/jabberd Challenges

This section provides answers for typical issues regarding OSAD and jabberd.

### Open File Count Exceeded

SYMPTOMS: OSAD clients cannot contact the SUSE Manager Server, and jabberd requires long periods of time to respond on port 5222.

CAUSE: The number of maximum files that a jabber user can open is lower than the number of connected clients. Each client requires one permanently open TCP connection and each connection requires one file handler. The result is jabberd begins to queue and refuse connections.

CURE: Edit the /etc/security/limits.conf to something similar to the following: jabbersoftnofile<#clients + 100> jabberhardnofile<#clients + 1000>

This will vary according to your setup. For example in the case of 5000 clients: jabbersoftnofile5100 jabberhardnofile6000

Ensure you update the /etc/jabberd/c2s.xml max\_fds parameter as well. For example:  $<max_fds>6000</max_fds>$ 

**EXPLANATION:** The soft file limit is the limit of the maximum number of open files for a single process. In SUSE Manager the highest consuming process is c2s, which opens a connection per client. 100 additional files are added, here, to accommodate for any non-connection file that c2s requires to work correctly. The hard limit applies to all processes belonging to the jabber user, and accounts for open files

from the router, s2s and sm processes additionally.

#### jabberd Database Corruption

SYMPTOMS: After a disk is full error or a disk crash event, the jabberd database may have become corrupted. jabberd may then fail to start during spacewalk-service start:

```
Starting spacewalk services...
Initializing jabberd processes...
Starting router
Starting sm startproc: exit status of parent of /usr/bin/sm: 2
failed
Terminating jabberd processes...
```

/var/log/messages shows more details:

```
jabberd/sm[31445]: starting up
jabberd/sm[31445]: process id is 31445, written to /var/lib/jabberd/pid/sm.pid
jabberd/sm[31445]: loading 'db' storage module
jabberd/sm[31445]: db: corruption detected! close all jabberd processes and run db_recover
jabberd/router[31437]: shutting down
```

CURE: Remove the jabberd database and restart. Jabberd will automatically re-create the database:

```
spacewalk-service stop
rm -Rf /var/lib/jabberd/db/*
spacewalk-service start
```

An alternative approach would be to test another database, but SUSE Manager does not deliver drivers for this:

```
rcosa-dispatcher stop
rcjabberd stop
cd /var/lib/jabberd/db
rm *
cp /usr/share/doc/packages/jabberd/db-setup.sqlite .
sqlite3 sqlite.db < db-setup.sqlite
chown jabber:jabber *
rcjabberd start
rcosa-dispatcher start
```

### Capturing XMPP Network Data for Debugging Purposes

If you are experiencing bugs regarding OSAD, it can be useful to dump network messages in order to help with debugging. The following procedures provide information on capturing data from both the client and server side.

Procedure: Server Side Capture

1. Install the topdump package on the SUSE Manager Server as root: zypper in topdump

- 2. Stop the OSA dispatcher and Jabber processes with rcosa-dispatcher stop and rcjabberd stop.
- 3. Start data capture on port 5222: tcpdump -s 0 port 5222 -w server\_dump.pcap
- 4. Start the OSA dispatcher and Jabber processes: rcosa-dispatcher start and rcjabberd start.
- 5. Open a second terminal and execute the following commands: rcosa-dispatcher start and rcjabberd start.
- 6. Operate the SUSE Manager server and clients so the bug you formerly experienced is reproduced.
- 7. Once you have finished your capture re-open terminal 1 and stop the capture of data with: CTRL+c

#### Procedure: Client Side Capture

- 1. Install the tcpdump package on your client as root: zypper in tcpdump
- 2. Stop the OSA process: rcosad stop.
- 3. Begin data capture on port 5222: tcpdump -s 0 port 5222 -w client\_client\_dump.pcap
- 4. Open a second terminal and start the OSA process: rcosad start
- 5. Operate the SUSE Manager server and clients so the bug you formerly experienced is reproduced.
- 6. Once you have finished your capture re-open terminal 1 and stop the capture of data with: CTRL+c

#### **Engineering Notes: Analyzing Captured Data**

This section provides information on analyzing the previously captured data from client and server.

- 1. Obtain the certificate file from your SUSE Manager server: /etc/pki/spacewalk/jabberd/server.pem
- 2. Edit the certificate file removing all lines before ----BEGIN RSA PRIVATE KEY-----, save it as key.pem
- 3. Install Wireshark as root with: zypper in wireshark
- 4. Open the captured file in wireshark.
- 5. From **Eidt** > **]menu:Preferences**[ select SSL from the left pane.
- 6. Select RSA keys list: Edit > ]menu:New[
  - · IP Address any
  - Port: 5222
  - Protocol: xmpp
  - Key File: open the key.pem file previously edited.
  - Password: leave blank

For more information see also:

- https://wiki.wireshark.org/SSL
- https://bugs.wireshark.org/bugzilla/show\_bug.cgi?id=3444

### Gathering Information with spacewalk-report

The spacewalk-report command is used to produce a variety of reports for system administrators. These reports can be helpful for taking inventory of your entitlements, subscribed systems, users, and organizations. Using reports is often simpler than gathering information manually from the SUSE Manager Web UI, especially if you have many systems under management.



#### spacewalk-reports Package

To use spacewalk-report, you must have the **spacewalk-reports** package installed.

spacewalk-report allows administrators to organize and display reports about content, systems, and user resources across SUSE Manager. Using spacewalk-report, you can receive reports on:

- 1. System Inventory: lists all of the systems registered to SUSE Manager.
- 2. Entitlements: lists all organizations on SUSE Manager, sorted by system or channel entitlements.
- 3. Patches: lists all the patches relevant to the registered systems and sorts patches by severity, as well as the systems that apply to a particular patch.
- 4. Users: lists all the users registered to SUSE Manager and any systems associated with a particular user.

**spacewalk-report** allows administrators to organize and display reports about content, systems, and user resources across SUSE Manager. To get the report in CSV format, run the following at the command line of your SUSE Manager server.

spacewalk-report report\_name

The following reports are available:

Table 1. Spacewalk-report Reports

Report	Invoked as	Description
Channel Packages	channel-packages	List of packages in a channel.
Channel Report	channels	Detailed report of a given channel.
Cloned Channel Report	cloned-channels	Detailed report of cloned channels.

### Gathering Information with spacewalk-report

Report	Invoked as	Description
Custom Info	custom-info	System custom information.
Entitlements	entitlements	Lists all organizations on SUSE Manager with their system or channel entitlements.
Patches in Channels	errata-channels	Lists of patches in channels.
Patches Details	errata-list	Lists all patches that affect systems registered to SUSE Manager.
All patches	errata-list-all	Complete list of all patches.
Patches for Systems	errata-systems	Lists applicable patches and any registered systems that are affected.
Host Guests	host-guests	List of host-guests mapping.
Inactive Systems	inactive-systems	List of inactive systems.
System Inventory	inventory	List of systems registered to the server, together with hardware and software information.
Kickstart Trees	kickstartable-trees	List of kickstartable trees.
All Upgradable Versions	packages-updates-all	List of all newer package versions that can be upgraded.
Newest Upgradable Version	packages-updates-newest	List of only newest package versions that can be upgraded.
Result of SCAP	scap-scan	Result of OpenSCAP sccdf eval.
Result of SCAP	scap-scan-results	Result of OpenSCAP sccdf eval, in a different format.
System Data	splice-export	System data needed for splice integration.
System Groups	system-groups	List of system groups.
Activation Keys for System Groups	system-groups-keys	List of activation keys for system groups.
Systems in System Groups	system-groups-systems	List of systems in system groups.
System Groups Users	system-groups-users	Report of system groups users.
Installed Packages	system-packages- installed	List of packages installed on systems.
Users in the System	users	Lists all users registered to SUSE Manager.
Systems administered	users-systems	List of systems that individual users can administer.

For more information about an individual report, run Spacewalk-report with the option --info or --list-fields-info and the report name. The description and list of possible fields in the report will be shown.

For further information on program invocations and options, see the Spacewalk-report(8) man page as well as the --helpparameter of the Spacewalk-report.

### **RPC Connection Timeout Settings**

RPC connection timeouts are configurable on the Uyuni server, SUSE Manager Proxy server, and the clients. For example, if package downloads take longer then expected, you can increase timeout values. Spacewalk-proxy restart should be run after the setting is added or modified.

Set the following variables to a value in seconds specifying how long an RPC connection may take at maximum:

#### Server -/etc/rhn/rhn.conf

```
server.timeout ='number'
```

#### Proxy Server -/etc/rhn/rhn.conf

```
proxy.timeout ='number'
```

#### SUSE Linux Enterprise Server Clients (using zypp-plugin-spacewalk) -/etc/zypp/zypp.conf

```
## Valid values: [0,3600]
## Default value: 180
download.transfer_timeout = 180
```

This is the maximum time in seconds that a transfer operation is allowed to take. This is useful for preventing batch jobs from hanging for hours due to slow networks or links going down. If limiting operations to less than a few minutes, you risk aborting perfectly normal operations.

#### Red Hat Enterprise Linux Clients (using yum-rhn-plugin ) -/etc/yum.conf

```
timeout =`number`
```

### Client/Server Package Inconsistency

In some cases, updates are available in the web interface, but not appearing on the client. If you schedule an update on the client, it will fail with an error stating that no updates are available. This can be caused

by a metadata regeneration problem, or because update packages have been locked.

The notice that updates are available will appear immediately, but new metadata is only generated on the server after synchronizing. In this case, an inconsistency can occur if taskomatic crashes, or because taskomatic is still running and creating new metadata.

To address this issue, check the /var/log/rhn/rhn\_taskomatic\_daemon.log file to determine if any processess are still running, or an exception which could indicate a crash. In the case of a crash, restart taskomatic.

Check package locks and exclude lists to determine if packages are locked or excluded on the client:

On Expanded Support Platform, check /etc/yum.conf and search for exclude=.

On SUSE Linux Enterprise Server, use the **Zypper locks** command.

### Corrupted Repository Data

If the information in /var/cache/rhn/repodata/sles12-sp3-updates-x86\_64 becomes out of date, it will cause problems with updating the server. The repository data file can be regenerated using the spacemd command:

Procedure: Rebuild repodata file

- 1. Remove all files from /var/cache/rhn/repodata/sles12-sp3-updates-x86\_64
- 2. Regenerate the file with spacecmd softwarechannel\_regenerateyumcache sles12-sp3-updates-x86\_64

#### Unable to Get Local Issuer Certificate

Some older bootstrap scripts will will create a link to the local certificate in the wrong place, which can cause problems with zypper returning an Unrecognized error about the local issuer certificate. In this case, ensure that the link to the local issuer certificate has been created in /etc/ssl/certs/, and consider updating your bootstrap scripts.

# AutoYast Example File

# Minimalist AutoYaST Profile for Automated Installations and Useful Enhancements

The AutoYaST profile in this section installs a SUSE Linux Enterprise Server system with all default installation options including a default network configuration using DHCP. After the installation is finished, a bootstrap script located on the Uyuni server is executed in order to register the freshly installed system with Uyuni. You need to adjust the IP address of the Uyuni server, the name of the bootstrap script, and the root password according to your environment:

```
<user>
...
<username>root</username>
  <user_password>`linux`</user_password>
  </user>
<location>http://`192.168.1.1`/pub/bootstrap/`my_bootstrap.sh`</location>
```

The complete AutoYaST file:

```
<?xml version="1.0"?>
<!DOCTYPE profile>
file xmlns="http://www.suse.com/1.0/yast2ns"
         xmlns:config="http://www.suse.com/1.0/configns">
 <general>
  <mode>
   <confirm config:type="boolean">false</confirm>
  </mode>
 </general>
 <networking>
  <keep_install_network config:type="boolean">true</keep_install_network>
 </networking>
 <software>
  <install_recommended config:type="boolean">true</install_recommended>
   <patterns config:type="list">
    <pattern>base</pattern>
   </patterns>
 </software>
 <users config:type="list">
  <user>
   <encrypted config:type="boolean">false</encrypted>
   <fullname>root</fullname>
   <gid>0</gid>
   <home>/root</home>
   <password_settings>
    <expire></expire>
    <flag></flag>
    <inact></inact>
    <max></max>
    <min></min>
    <warn></warn>
   </password_settings>
   <shell>/bin/bash</shell>
   <uid>0</uid>
   <username>root</username>
   <user password>linux</user password>
  </user>
 </users>
 <scripts>
  <init-scripts config:type="list">
   <script>
    <interpreter>shell</interpreter>
    <le><location>http://192.168.1.1/pub/bootstrap/my_bootstrap.sh</location>
   </script>
  </init-scripts>
 </scripts>
</profile>
```

Use this enhancement fragment to add child channels:

```
<add-on>
  <add_on_products config:type="list">
        ask_on_error config:type="boolean">true</ask_on_error>
        <ask_on_error config:type="boolean">true</ask_on_error>
        <ask_on_error config:type="boolean">true</ask_on_error>
        <ask_on_error config:type="boolean">true</ask_on_error>
        <ask_on_error>
        <ask_on_error<
ask_on_error>
        <ask_on_error>
        <ask_on_error<
ask_on_error>
        <ask_on_error<
ask_on_error>
        <ask_on_error<
ask_on_error>
        <ask_on_error<
ask_on_error>
        <ask_on_error<
ask_on_error>
        <ask_on_error<
ask_on_error>
        <ask_on_error<
ask_on_error<
ask_on_error
```

Replace channel-label and distribution-label with the correct labels (such as sles11-sp1-updates-x86\_64 and sles11-sp2-x86\_64). Ensure that the distribution label corresponds to the Autoinstallable Distribution. Set the variables (such as \$c\_server) according to your environment. For information about variables, see [s4-sm-system-kick-dist-variables].

#### Add the Updates Channel

It is required that you add the updates tools channel to the <add-on> AutoYaST snippet section. This ensures your systems are provided with an up-to-date version of the <code>libzypp</code> package. If you do not include the updates tools channel, you will encounter 400 errors. In this example, the (DISTRIBUTION\_NAME) is replaced with the name of the autoinstallation distribution, as created previously, from <code>Systems</code> > <code>Autoinstallation</code> > <code>Distributions</code>



