Table Of Contents

Table Of Contents	1
Method # 1: GUI tool system-config-network	2
Method # 2: Command line tool system-config-network-tui	
Method #3: Edit configuration files stored in /etc/sysconfig/network-scripts/	
See also	

nixCraft: Linux Tips, Hacks, Tutorials, And Ideas In Blog Format http://www.cyberciti.biz/

Home > Faq > Networking

Howto Red hat enterprise Linux 5 configure the network card

Posted by Vivek Gite <vivek@nixcraft.com>

Q. I've installed Red Hat enterprise Linux 5 and now added one more LAN card (NIC). How do I configure the network card from the command line? I can see 2nd my network card detected while booting the IBM server.



A. Red hat Linux provides following tools to make changes to Network configuration such as add new card, assign IP address, change DNS server etc.

- [a] GUI tool (X Windows required) system-config-network
- [b] Command line text based GUI tool (No X Windows required) system-config-network
- [c] Edit configuration files stored in /etc/sysconfig/network-scripts/ directory.

Following instructions are compatible with


- (1) Cent OS Linux
- (2) Fedora Core Linux
- (3) Red Hat Enterprise Linux (RHEL) 3/4/5

Note: If you are using Debian or Ubuntu Linux, please see this configuration [2] howto.


Method # 1: GUI tool system-config-network

Type the following command at shell prompt (open x terminal):

\$ system-config-network &



You will see Window as above. Now select your Ethernet card (eth0 or eth1) and click on Edit button. You can now setup IP address, netmask, default gateway and other properties.



You can obtain IP address using DHCP or setup manually. Once IP address assigned, click on **Ok** button to save the changes. You can activate card by clicking on Activate button.

Method # 2: Command line tool system-config-network-tui

If you don't have X windows GUI installed type the following command at shell prompt:

system-config-network-tui &



(click to enlarge image)

You will see text based GUI as above. Select your Ethernet card (eth0 or eth1) and hit [Enter] or [F12] special key.



(click to enlarge image)

You can obtain IP address using DHCP or setup manually. Once IP address assigned, click on **Ok** button to save the changes

Method #3: Edit configuration files stored in /etc/sysconfig/network-scripts/

You can configure network card by editing text files stored in /etc/sysconfig/network-scripts/ directory. First change directory to /etc/sysconfig/network-scripts/:

```
# cd /etc/sysconfig/network-scripts/
```

You need to edit / create files as follows:

- /etc/sysconfig/network-scripts/ifcfg-eth0 : First Ethernet card configuration file
- /etc/sysconfig/network-scripts/ifcfg-eth1 : Second Ethernet card configuration file

To edit/create first NIC file, type command:

```
# vi ifcfg-eth0
```

Append/modify as follows:

```
# Intel Corporation 82573E Gigabit Ethernet Controller (Copper)
DEVICE=eth0
BOOTPROTO=static
DHCPCLASS=
HWADDR=00:30:48:56:A6:2E
IPADDR=10.10.29.66
NETMASK=255.255.255.192
ONBOOT=yes
```

Save and close the file. Define default gateway (router IP) and hostname in /etc/sysconfig//network file:

```
# vi /etc/sysconfig/network
```

Append/modify configuration as follows:

```
NETWORKING=yes
HOSTNAME=www1.nixcraft.in
GATEWAY=10.10.29.65
```

Save and close the file. Restart networking:

```
# /etc/init.d/network restart
```

Make sure you have correct DNS server defined in /etc/resolv.conf file:

```
# vi /etc/resolv.conf
```

Setup DNS Server as follows:

```
nameserver 10.0.80.11
nameserver 10.0.80.12
nameserver 202.67.222.222
```

Save and close the file. Now you can ping the gateway/other hosts:

```
$ ping 10.0.80.12
```

Output:

```
PING 10.0.80.12 (10.0.80.12) 56(84) bytes of data.
64 bytes from 10.0.80.12: icmp_seq=1 ttl=251 time=0.972 ms
64 bytes from 10.0.80.12: icmp_seq=2 ttl=251 time=1.11 ms
```

You can also check for Internet connectivity with nslookup or host command:

```
$ nslookup cyberciti.biz
```

See also 5/5

Output:

Server: 10.0.80.11 Address: 10.0.80.11#53

Non-authoritative answer:
Name: cyberciti.biz
Address: 75.126.43.232

You can also use host command:

```
$ host nixcraft.in
```

Output:

```
nixcraft.in has address 75.126.43.232 nixcraft.in mail is handled by 10 mail.nixcraft.in.
```

See also

=> Howto configure Ubuntu Linux/Debian Linux network configuration [2]

4000+ howtos and counting! Want to read more Linux / UNIX howtos, tips and tricks? Subscribe to our <u>daily email</u> newsletter or <u>weekly newsletter</u> to make sure you don't miss a single tip/tricks. Alternatively, subscribe via <u>RSS/XML</u> feed.

Article printed from Frequently Asked Questions About Linux / UNIX: http://www.cyberciti.biz/faq/

URL to article: http://www.cyberciti.biz/faq/rhel-centos-fedoracore-linux-network-card-configuration/

URLs in this post:

- [1] Image: http://www.cyberciti.biz/faq/faq/category/redhat-and-friends/
- [2] this configuration: http://www.cyberciti.biz/faq/tips/howto-ubuntu-linux-convert-dhcp-network-configuration-to-static-ip-configuration.html
- [3] Image: http://www.cyberciti.biz/faq/wp-content/uploads/2007/04/network-sysconfig-tui-0.jpg
- [4] Image: http://www.cyberciti.biz/faq/wp-content/uploads/2007/04/network-sysconfig-tui-1.jpg

Copyright © 2006-2010 <u>nixCraft</u>. All rights reserved. This print / pdf version is for personal non-commercial use only. More details http://www.cyberciti.biz/tips/copyright.