Table Of Contents	1/2
Table Of Contents	
Table Of Contents	1

Table Of Contents 2/2

## nixCraft: Linux Tips, Hacks, Tutorials, And Ideas In Blog Format <a href="http://www.cyberciti.biz/">http://www.cyberciti.biz/</a>

Home > Faq > Linux

## Configure a system to automount a Samba share with /etc/fstab

Posted by Vivek Gite <vivek@nixcraft.com>

As <u>explained</u> [1] <u>earlier</u> [1] you can use the mount command to mount a remote windows partition or a windows share under Linux.

/etc/fstab file contains static information about the filesystems. The file fstab contains descriptive information about the various file systems. fstab is only read by programs, and not written; it is the duty of the system administrator to properly create and maintain this file.

To mount a Samba share to be mounted when a Linux system comes up after reboot edit the /etc/fstab file and put entry as follows for your Windows/Samba share:

//ntserver/share /mnt/samba smbfs username=username,password=password 0 0

For example, if you want to mount a share called //ntserver/docs then you need to write following entry in /etc/fstab file:

```
//ntserver/docs /mnt/samba smbfs username=docsadm,password=D1Y4x9sw 0 0
```

## Where,

- //ntserver/docs: Windows 2003/NT/Samba share name
- /mnt/samba: Local mount point (you may need to create this directory first)
- smbfs: File system type (samba file system)
- username=docsadm,password=D1Y4x9sw: Share username and password

Open file /etc/fstab using vi text editor:

```
# vi /etc/fstab
```

Append line //ntserver/docs /mnt/samba smbfs username=docsadm,password=D1Y4x9sw 0 0, at the end your file should read as follows:

```
proc
                                         defaults
                                                          0
                                                                  0
                                 proc
/dev/hdb1
                                         defaults, errors=remount-ro 0
                                                                              1
                                 ext3
/dev/hdb2
                                                          0
                                                                  0
                none
                                 swap
/dev/hdc
                /media/cdrom0
                                 iso9660 ro,user,noauto 0
//ntserver/docs /mnt/samba
                                         username=docsadm,password=D1Y4x9sw 0 0
```

Replace sharename, username and password with your actual parameters.

4000+ howtos and counting! Want to read more Linux / UNIX howtos, tips and tricks? Subscribe to our <u>daily email</u> newsletter or <u>weekly newsletter</u> to make sure you don't miss a single tip/tricks. Alternatively, subscribe via <u>RSS/XML</u> feed.

Article printed from Frequently Asked Questions About Linux / UNIX: http://www.cyberciti.biz/faq/

URL to article: http://www.cyberciti.biz/faq/configure-a-system-to-automount-a-samba-share-with-etcfstab/URLs in this post:

 $[1] \ explained: \ \textbf{http://www.cyberciti.biz/nixcraft/vivek/blogger/2004/04/how-to-mount-remote-windows-partition.php}$ 

Consists @ 2006 2010 of Confi All Salar consist of All Salar consists of All Salar consi