# **Table Of Contents**


Table Of Contents	. 1
Task: View Current Speed and Duplex Settings	
ifconfig command to change speed and duplex settings	
Make speed and duplex settings permanent	

nixCraft: Linux Tips, Hacks, Tutorials, And Ideas In Blog Format <a href="http://www.cyberciti.biz/">http://www.cyberciti.biz/</a>

Home > Faq > FreeBSD

## FreeBSD Set Speed Duplex For My Network Card (NIC)

Posted by Vivek Gite <vivek@nixcraft.com>





A. ethtool is not required on FreeBSD. By default, the NIC auto-negotiates the speed and duplex of the connection. Make sure port speed set correctly on your switch. You need use the ifconfig command to configure the speed and duplex settings on the adapter. You also need to update your /etc/rc.conf file to set speed and duplex configuration.

# Task: View Current Speed and Duplex Settings

Simply, use ifconfig command, enter:

```
# ifconfig em0
# ifconfig interface-name
# ifconfig | grep media
```

### Output:

```
em0: flags=8843 mtu 1500
    options=b
    inet 10.10.1.2 netmask 0xffffffc0 broadcast 10.10.1.29
    ether 00:30:48:93:1e:9a
    media: Ethernet 10baseT/UTP
    status: active
```

# ifconfig command to change speed and duplex settings

General syntax is as follows to set 10Mbps full-duplex:

```
ifconfig <interface-name> <IP_address> media 10baseTX mediaopt full-duplex
```

Set 100Mbps full-duplex, enter:

```
ifconfig <interface-name> <IP_address> media 100baseTX mediaopt full-duplex
```

Set 1000Mbps full-duplex, enter:

```
ifconfig <interface-name> <IP_address> media 1000baseTX mediaopt full-duplex
```

For example, set interface em0 with IP 10.10.1.2 to 100Mbps full duplex, enter:

```
# ifconfig em0 10.10.1.2 media 100baseTX mediaopt full-duplex
```

If the interface is currently forced to 100 full duplex, in order to change to half duplex you must type the following command:

```
# ifconfig em0 10.10.1.2 media 100baseTX -mediaopt full-duplex
```

The -mediaopt option disable the specified media options (full-duplex) on the interface i.e. go back to half duplex.

# Make speed and duplex settings permanent

To make configuration changes persistence, update /etc/rc.conf file. Open config file using text editor, enter:

# vi /etc/rc.conf

#### Find line that read as follows:

ifconfig\_interfacename="...."

## To set em0 interface to 10Mbps full, enter:

ifconfig\_em0="inet x.x.x.x netmask y.y.y.y media 10baseT/UTP mediaopt full-duplex"

### To set em0 interface to 100Mbps full, enter:

ifconfig\_em0="inet x.x.x.x netmask y.y.y.y media 100baseTX mediaopt full-duplex"

## To set em0 interface to 1000Mbps full, enter:

ifconfig\_em0="inet x.x.x.x netmask y.y.y.y media 1000baseTX mediaopt full-duplex"

Make sure you replace x.x.x.x and y.y.y.y with actual IP and netmask address. Here is entry from my own personal FreeBSD workstation:

ifconfig\_em0="inet 10.10.1.2 netmask 255.255.255.0 media 100baseT/UTP mediaopt full-duplex"

### Save and close the file. Restart the networking:

# /etc/rc.d/netif restart

4000+ howtos and counting! Want to read more Linux / UNIX howtos, tips and tricks? Subscribe to our <u>daily email</u> newsletter or <u>weekly newsletter</u> to make sure you don't miss a single tip/tricks. Alternatively, subscribe via <u>RSS/XML</u> feed.

Article printed from Frequently Asked Questions About Linux / UNIX: http://www.cyberciti.biz/faq/

URL to article: http://www.cyberciti.biz/faq/howto-configure-freebsd-full-half-duplex-speed/

URLs in this post:

- [1] Image: http://www.cyberciti.biz/faq/faq/category/freebsd/
- [2] ethtool to set an Ethernet card speed and duplex: http://www.cyberciti.biz/faq/linux-change-the-speed-and-duplex-settings-of-an-ethernet-card/

Copyright © 2006-2010 <u>nixCraft</u>. All rights reserved. This print / pdf version is for personal non-commercial use only. More details <a href="http://www.cyberciti.biz/tips/copyright">http://www.cyberciti.biz/tips/copyright</a>.