Table Of Contents

Table Of Contents	. 1
Step # 1: Edit supfile	. 2
Step # 2: Grab FreeBSD 8 Base System	. 2
Step # 3: Build FreeBSD 8 Base System	
Step # 4: Build FreeBSD 8 Kernel	
Step # 5: Reboot And Boot Into A Single User Mode	
A Note About Remote FreeBSD Server Using KVM	
Step # 6: Merge Configuration Files	. 4
Step # 7: Install FreeBSD 8 Base System	. 5
Step # 8: Verify New Installation	. 5
Step # 9: Upgrade Ports (Applications)	
References:	

Step # 1: Edit supfile 2/6

nixCraft: Linux Tips, Hacks, Tutorials, And Ideas In Blog Format http://www.cyberciti.biz/

Home > Faq > FreeBSD

HowTo: Upgrade FreeBSD 7.2 To FreeBSD 8 Using csup

Posted by Vivek Gite <vivek@nixcraft.com>

How do I upgrade FreeBSD 7.2 to FreeBSD 8 stable using csup source code method including all ports?



Contents

Build FreeBSD 8 Kernel ^[5]
 Boot Into A Single User Mode ^[6]

Install FreeBSD 8 Base [8]
 Verify Installation [9]

Edit supfile [2]
 Grab Base Source [3]

3. Build FreeBSD 8 [4]

6. Configuration Files [7]

9. <u>Upgrade Ports</u> [10] 10. <u>References</u> [11]

csup is a general-purpose network file updating package. It is extremely fast program. Make sure you backup all data, MySQL / PGSQL database, and configuration file before attempting upgrade procedure.

Source-based upgrades from previous versions are well supported and recommend to gain full control of your FreeBSD 8 kernel and base systems. I'm going to assume that the:

- [a] You are root user
- [b] You are using portsnap and portmaster [12] to manage FreeBSD ports .
- [c] You made a backup of existing data.

Step # 1: Edit supfile

Make a copy of existing supfile, enter:

- # cp /usr/share/examples/cvsup/standard-supfile /root/supfile.8
 # vi /root/supfile.8
- Set host name which specifies the server host which will supply the file updates to your computer. You must set it to one of the CVSup mirror sites listed in the FreeBSD $\underline{page}^{[13]}$

```
*default host=cvsup1.us.FreeBSD.org
```

Set release tag to stable 8:

```
*default release=cvs tag=RELENG_8_0
```

Save and close the file.

Step # 2: Grab FreeBSD 8 Base System

Type the following command:

```
# csup /root/supfile.8
```

Read all last minute updating information for FreeBSD 8, enter:

```
# vi /usr/src/UPDATING
```

Step # 3: Build FreeBSD 8 Base System

You can enable or disable certain features such as NIS, ATM, BLUETOOTH and much more (see src.conf(5) man page). Edit /etc/src.conf and disable required features from base system:

```
WITHOUT_ATM=yes
WITHOUT_CALENDAR=yes
WITHOUT_GAMES=yes
WITHOUT_14B=yes
```

```
WITHOUT_IPFILTER=yes
WITHOUT_LPR=yes
WITHOUT_LPR=yes
WITHOUT_NETCAT=yes
WITHOUT_NIS=yes
WITHOUT_RCMDS=yes
WITHOUT_SENDMAIL=yes
WITHOUT_WPA_SUPPLICANT_EAPOL=yes
WITHOUT_ZFS=yes
WITHOUT_BLUETOOTH=yes
```

Note you can skip /etc/src.conf and build the entire system. To build FreeBSD 8 system, enter:

```
# cd /usr/src
# make cleanworld && make cleandir
# make buildworld
```

Step # 4: Build FreeBSD 8 Kernel

You need to edit your kernel config file which is located at /usr/src/sys/`uname -p`/conf, enter:

```
# cd /usr/src/sys/`uname -p`/conf
# ls -1
```

The default file name is GENERIC. Edit GENERIC or your own custom kernel file (e.g., NIXCRAFT), enter:

```
# vi GENERIC
```

OR

```
# vi NIXCRAFT
```

My sample kernel config file:

```
include GENERIC
ident www303
options SMP
nodevice ugen
nodevice uhid
nodevice ulpt
nodevice umass
nodevice ums
nodevice ural
nodevice urio
nodevice uscanner
nodevice aue
nodevice axe
nodevice cdce
nodevice cue
nodevice kue
nodevice rue
options CONSPEED=19200
options QUOTA
# pf firewall specific
device pf
device pflog
device pfsync
options
               ALTQ
                             # Class Bases Queuing (CBQ)
# Random Early Detection (RED)
               ALTQ_CBQ
options
              ALTQ_RED
options
options
              ALTQ_RIO
                               # RED In/Out
options
               ALTQ_HFSC
                               # Hierarchical Packet Scheduler (HFSC)
options
              ALTQ_PRIQ
                               # Priority Queuing (PRIQ)
               ALTQ_NOPCC
options
                               # Required for SMP build
# Turn on device polling for em driver
options DEVICE_POLLING
options HZ=1000
```

Make changes as per your setup. Finally, build and install the FreeBSD 8 kernel, run:

```
# make buildkernel
# make installkernel
```

OR use your custom kernel config name (e.g., NIXCRAFT), run:

```
# make buildkernel KERNCONF=NIXCRAFT
# make installkernel KERNCONF=NIXCRAFT
```

Step # 5: Reboot And Boot Into A Single User Mode

To reboot the system, enter:

```
# reboot
```

To boot into a single user hit 4 key at boot loader prompt:



Fig.01: FreeBSD Boot Loader Menu

A Note About Remote FreeBSD Server Using KVM

You need to boot into a single user mode <u>using KVM to</u> finish entire upgrade procedure. KVM will not work in a single user mode. However, you can load usb.ko and other modules to get kvm support under single user mode. Press [Enter] key at the boot loader. Connect to your remote FreeBSD box using KVM client and issue reboot command. At FreeBSD boot menu press [Spacebar] key to pause default booting. Press 6 to boot to loader prompt. Type the following commands to load KVM support and boot into a single user mode:

```
load usb.ko
set boot_serial=NO
set boot_multicons=NO
set console=vidconsole
boot -s
```

Once logged into a single user mode, mount all your ufs partitions, enter:

```
# mount -a -t ufs
```

Step # 6: Merge Configuration Files

The mergemaster utility is designed to aid you in updating the various configuration and other files associated with FreeBSD. To install sys configuration files that are required by the new base system. To compare only files known to be essential to the success of install world, enter:

mergemaster -p

Step # 7: Install FreeBSD 8 Base System

Type the following commands:

```
# cd /usr/src
# make installworld
```

Finally merge your configuration files, enter:

```
# mergemaster -i
```

WARNING! Be careful with /etc/passwd, /etc/group and other files in base system. Verify each file before installing new version or merging exiting configuration files.

Finally, reboot the box:

reboot

Step #8: Verify New Installation

Type the following command:

```
# uname -a
# tail -f /var/log/messages
# grep 'something' /path/to/log/file
```

Step # 9: Upgrade Ports (Applications)

Type the following command:

```
# portsnap fetch update
# vi /usr/ports/UPDATING
# portmaster -Da
```

Reboot the box again and make sure everything is working fine, enter:

```
# reboot
```

Finally, delete old libraries, enter:

```
# cd /usr/src
# make delete-old
```

References:

- Read /usr/src/Makefile, /usr/src/UPDATING, and /usr/ports/UPDATING.
- man pages: portsnap, make, mergemaster, and src.conf
- FreeBSD handbook Rebuilding "world" [15] chapter.

4000+ howtos and counting! Want to read more Linux / UNIX howtos, tips and tricks? Subscribe to our <u>daily email</u> newsletter or <u>weekly newsletter</u> to make sure you don't miss a single tip/tricks. Alternatively, subscribe via <u>RSS/XML</u> feed.

Article printed from Frequently Asked Questions About Linux / UNIX: http://www.cyberciti.biz/faq/

URL to article: http://www.cyberciti.biz/faq/freebsd-8-upgrade-tutorial/

URLs in this post:

[1] Image: http://www.cyberciti.biz/faq/category/freebsd/

[2] Edit supfile: #step1

[3] Grab Base Source: #step2[4] Build FreeBSD 8: #step3

[5] Build FreeBSD 8 Kernel: #step4[6] Boot Into A Single User Mode: #step5

[7] Configuration Files: #step6
[8] Install FreeBSD 8 Base: #step7
[9] Verify Installation: #step8
[10] Upgrade Ports: #step9
[11] References: #step10

[12] portsnap and portmaster: http://www.cyberciti.biz/tips/howto-keep-freebsd-system-upto-date.html

[13] page: http://www.freebsd.org/doc/handbook/mirrors.html

[14] Image: http://www.cyberciti.biz/faq/freebsd-8-upgrade-tutorial/freebsd-boot/

[15] Rebuilding "world": http://www.freebsd.org/doc/en_US.ISO8859-1/books/handbook/makeworld.html

Copyright © 2006-2010 <u>nixCraft</u>. All rights reserved. This print / pdf version is for personal non-commercial use only. More details http://www.cyberciti.biz/tips/copyright.