Table Of Contents	1/3
Table Of Contents	
Table Of Contents	1

Table Of Contents 2/3

# nixCraft: Linux Tips, Hacks, Tutorials, And Ideas In Blog Format <a href="http://www.cyberciti.biz/">http://www.cyberciti.biz/</a>

Home > Faq > EMail Servers

## Postfix limit incoming or receiving email rate

Posted by Vivek Gite <vivek@nixcraft.com>

Q. I have noticed that spammers continually try to make a connection (email flooding attack). How do I enforce a number of limits on incoming mail so that I can protect hosted email domains?

A. Postfix (smtpd daemon) can enforce a number of limits on incoming email. This will stop email flooding attacks.

A bot connects to your Postfix email server and sends garbage commands or spam, attempting to crash your server. You can limit:

- => The length of lines in a message and so on
- => The size of messages
- => The number of recipients for a single delivery

Try following directives in your postfix main.cf config file:

smtpd\_error\_sleep\_time - The SMTP server response delay after a client has made more than
\$smtpd\_soft\_error\_limit errors, and fewer than smtpd\_hard\_error\_limit errors, without delivering mail.

**smtpd\_soft\_error\_limit**: The number of errors a remote SMTP client is allowed to make without delivering mail before the Postfix SMTP server slows down all its responses.

**smtpd\_hard\_error\_limit**: The maximal number of errors a remote SMTP client is allowed to make without delivering mail. The Postfix SMTP server disconnects when the limit is exceeded.

#### Open config file

```
# vi main.cf
```

### Append following directives:

```
smtpd_error_sleep_time = 1s
smtpd_soft_error_limit = 10
smtpd_hard_error_limit = 20
```

#### Save and restart/reload postfix configuration

```
# /etc/init.d/postfix restart
```

Postfix waits one second before each error such as HELO command not provided or FQDN hostname does not exists etc After 10 such errors postfix will start to increase delay. If error limits touches 20 Postfix will disconnect client.

You can see this in action from /var/log/maillog file:

```
Dec 15 16:50:59 server postfix/anvil[20799]: statistics: max connection rate 1/60s for (smt Dec 15 16:50:59 server postfix/anvil[20799]: statistics: max connection count 1 for (smtp:8 Dec 15 16:50:59 server postfix/anvil[20799]: statistics: max cache size 2 at Dec 15 16:47:3
```

4000+ howtos and counting! Want to read more Linux / UNIX howtos, tips and tricks? Subscribe to our <u>daily email</u> newsletter or <u>weekly newsletter</u> to make sure you don't miss a single tip/tricks. Alternatively, subscribe via <u>RSS/XML</u> feed.

Table Of Contents 3/3

URL to article: http://www.cyberciti.biz/faq/postfix-limit-incoming-or-receiving-email-rate/

 $Copyright @ 2006-2010 ~ \underline{nixCraft}. ~ All ~ rights ~ reserved. ~ This ~ print / ~ pdf ~ version ~ is for personal non-commercial use only. ~ More \\ ~ details ~ \underline{http://www.cyberciti.biz/tips/copyright}.$