


Figure 8.44 Carnot engine

Carnot's cycle:

The working substance is subjected to four successive reversible processes forming what is called Carnot's cycle.

Let the initial pressure, volume of the working substance be P_1, V_1.

Step A to B: Quasi-static isothermal expansion from (P_1, V_1, T_H) to (P_2, V_2, T_H):

The cylinder is placed on the source. The heat (Q_H) flows from source to the working substance (ideal gas) through the bottom of the cylinder. Since the process is isothermal, the internal energy of the working substance will not change. The input heat increases the volume of the gas. The piston is allowed to move out very slowly(quasi-statically). It is shown in the figure 8.47(a).

W_1 is the work done by the gas in expanding from volume V_1 to volume V_2 with a decrease of pressure from P_1 to P_2. This is represented by the P-V diagram along the path AB as shown in the Figure 8.45.




Figure 8.45 PV diagram for Carnot cycle

Then the work done by the gas (working substance) is given by

$$\therefore Q_H = W_{A\to B} = \int_{V_1}^{V_2} PdV$$

Since the process occurs quasi-statically, the gas is in equilibrium with the source till it reaches the final state. The work done in the isothermal expansion is given by the equation (8.34)

$$W_{A\to B} = \mu RT_H \ln\left(\frac{V_2}{V_1}\right) = \text{Area under the curve AB} \qquad (8.56)$$

This is shown in Figure 8.46 (a)




Figure 8.46 Work done in Carnot cycle

UNIT-8(XI-Physics_Vol-2).indd 145 02-01-2023 15:26:14