

Q 搜索

作室手册 3.7.0 Topics **〉**

Qt设计工作室手册 > 发短信

发短信

可以使用多个不同的文本组件向 UI 添加只读或可编辑的文本,例如标题或标签以及带有占位符文本的文本输入字段。"**文本**"组件添加格式化文本,"**文本编辑**"组件添加多行编辑,"**文本输入**"组件添加单个可编辑行字段。

您可以选择要使用的字体,并为每个文本字符串指定广泛的属性,例如以磅或像素为单位的大小、样式名称、 强调、对齐方式和间距。

有关详细信息,请观看以下视频:

若要创建带背景的标签,请使用 Qt **快速控件>组件**中提供的**标签**组件。该模块还包含用于创建**文本字段**和**文本 区域控件的**组件。它们与基本组件的不同之处在于,通用样式应用于它们,并且您可以为它们指定占位符文本。

使用富文本

您可以在**文本和文本**输入组件中使用 RTF。若要打开富文本编辑器,请选择**"属性">"字符**>文本"中的"**②**(**编** 辑)"按钮。








在富文本编辑器中, 您可以:

- > 强调文本
- > 创建超链接
- > 对齐文本
- > 创建项目符号列表和编号列表
-) 指定文本颜色
- > 选择文本字体
- > 设置字体大小
-)创建表



Marking Strings for Translation

To support translators, mark the strings that should be translated. In **Properties > Character > Text**, select **tr**.






If you use text IDs instead of plain text, change the default call to . Select **Edit** > **Preferences** > **Qt Quick** > **Qt Quick Designer**, and then select the **qsTrId()** radio button in the **Internationalization** group. For more information about text ID based translations, see Qt Linguist Manual: Text ID Based Translations.qsTrId()

To preserve the context when editing the text or to change the context by setting a binding on the text property, change the default call to by selecting the qsTranslate() radio button.qsTranslate()

For more information, see Internationalization and Localization with Qt Quick.

Character Properties

You can set font properties in the **Character** section in **Properties**. For each string that you enter in the **Text** field, you can select the font to use in the **Font** field and specify the size, emphasis, alignment, and spacing of the text. Specify the font size in either points or pixels in the **Size** field.



To display custom fonts in the list of available fonts in the Font field, you need to first add them to Assets:

- 1. Select **Assets** > + .
- 2. Select the font file, and then select **Open**.
- 3. Select the location where the file will be saved in the Add Resources dialog.
- 4. Select OK.



If you set a style name in the **Style name** field, the font is matched against the style name instead of the values set in the **Weight** and **Emphasis** fields.

The value of the **Word spacing** field changes the default spacing between individual words, whereas the value of the **Letter spacing** field changes the spacing between individual letters in a word. A positive value increases the spacing by a corresponding amount of pixels, while a negative value decreases it.

The value of the Line height field sets the line height for the text. In the Line height mode field in the Text Extras section, select FixedHeight to set the line height in pixels or ProportionalHeight (default) to set the spacing proportionally to the line (as a multiplier). For example, set to 2 for double spacing.

Text Alignment

You can align text components horizontally and vertically. By default, text is vertically aligned to the top. Horizontal alignment follows the natural alignment of the text. By default, left-to-right text like English is aligned to the left side of the text area, whereas right-to-left text like Arabic is aligned to the right side of the text area.

You can align text to the left, right, top, or bottom, and center it horizontally or vertically. You can justify horizontal text.

For a single line of text, the size of the text is the area of the text. In this common case, all alignments are equivalent. To center a text in its parent, use anchoring or bind the width of the text component to that of the parent. For more information, see Setting Bindings.

Text and Style Colors

You can set the color of the text itself and a secondary color used by text styles.


For the **Text Edit** and **Text Input** components, you can also set the color of selected text and the text highlight color that is used behind selections in the **Selected text color** and **Selection color** fields.

For the **Text Field** and **Text Area** controls, you can also set the color of the placeholder text.

For more information about selecting colors, see Picking Colors. You can only set solid colors for text components.

Advanced Text Properties

The height and width of a text component are determined automatically depending on the values of the properties you set, to accommodate the length of the string that you specify in the **Text** field and the font size, for example. You can specify additional properties for formatting text in the **Text Extras** section.







The value of the **Size mode** field specifies how the font size of the displayed text is determined. Select **FixedSize** to use the size specified in the **Size** field in the **Character** section in pixels or points.

Select **HorizontalFit** or **VerticalFit** to use the largest size up to the size specified that fits the width or height of the component. Select **Fit** to use the largest size up to the size specified that fits within the width and height of the component. The font size of fitted text has a minimum bound specified by the **Min size** field and maximum bound specified by the **Size** field.

Wrapping and Eliding Text

In the **Wrap mode** field, you can wrap the text to the text component's width. The text will only wrap if you set an explicit width for the text component. By default, text is not wrapped. Select **WordWrap** to restrict wrapping to word boundaries only. Select **WrapAnywhere** to enable wrapping at any point on a line, even if it occurs in the middle of a word. Select **Wrap** to wrap at a word boundary, if possible, or at the appropriate point on the line, even in the middle of a word.

You can use the **Elide** property with the **Wrap** option to fit a single line of plain text to a set width. Select **ElideRight**, and set the **Max line count** or the text component height (in the **H** field). If you set both, the maximum line count will apply unless the lines do not fit in the height allowed.

If the text is a multi-length string, and you set the **Elide** property value to something else than **ElideNone**, the first string that fits will be used, otherwise the last will be elided.

Multi-length strings are ordered from longest to shortest, separated by the Unicode *String Terminator* character .U009C

Formatting Text

Text can be either in plain text or rich text format, depending on the value you set in the **Format** field. If you select **AutoText** and the the first line of text contains an HTML tag, the text is treated as rich text. Rich text supports a subset of HTML 4 described on the Supported HTML Subset. Note that plain text offers better performance than rich text.

Rendering Text

In the **Render type** field, you can override the default rendering type for a text component. Select **NativeRendering** if you prefer text to look native on the target platform and do not require advanced features such as transformation of the text. Using rotation or scaling in combination with native rendering leads to poor and sometimes pixelated results.

If you select **NativeRendering**, you can set the hinting preference in the **Hinting** field in the **Font Extras** section:


- **PreferDefaultHinting** uses the default hinting level for the target platform.
- **PreferNoHinting** renders text without hinting the outlines of the glyphs, if possible.
- > **PreferVerticalHinting** renders text with no horizontal hinting, but aligns glyphs to the pixel grid in the vertical direction, if possible.
- PreferFullHinting renders text with hinting in both horizontal and vertical directions.

Note: This property only describes a preference, as the full range of hinting levels are not supported on all of Qt's supported platforms.



navancea i one i ioperaco

You can specify additional properties for fonts in the **Font Extras** section.



In the **Capitalization** field, select **MixedCase** for normal text rendering where no capitalization changes are applied. You can also set the text in all upper or lower case, or use small caps. The **Capitalize** option renders the first character of each word as an uppercase character.

You can set the font style in the **Style** field to **Outline**, **Raised**, or **Sunken**. The color that you pick in the **Style color** field is used as the outline color for outlined text, and as the shadow color for raised or sunken text.


To use kerning when drawing text with the selected font, select the **Auto kerning** check box.

Sometimes, a font will apply complex rules to a set of characters in order to display them correctly. In some writing systems, such as Brahmic scripts, this is required in order for the text to be legible but in others, such as Latin script, it is merely a cosmetic feature. Such features are disabled by default to improve performance. If they are required, select the **Prefer shaping** check box.

Text Input

You can use the Text Edit and Text Input components to add text fields where users can enter text.

The **Text Input** component displays a single line of editable plain text, whereas the **Text Edit** component displays a block of editable, formatted text. Both components are used to accept text input.







Entering Passwords

You can set properties for Text Input components that make them suitable for entering passwords.

In the Input mask field, you can create an input mask that contains mask and meta characters and separators between them. When created or cleared, the text edit or input is filled with a copy of the input mask string, where the meta characters have been removed, and the mask characters have been replaced with the blank character. For example, in an input field for an IP address, you could use the following mask (with the underscore as the blank character): . For more information about creating input masks, see the documentation for QLineEdit::inputMask.000.000.000.000; _

In the **Echo mode** field, select **Password** to display platform-dependent password mask characters instead of the actual characters that users enter. Select **PasswordEchoOnEdit** to display characters as users enter them. The mask character is displayed in the **Password character** field.

Entering Text

You can specify how users can enter text into text edit or input fields.

In the Maximum length field, set the maximum number of characters that users can enter.

The value of the **Auto scroll** check box determines whether the text edit or input should scroll when the text is longer than the width of the field.

If the **Overwrite mode** check box is selected, existing text is overwritten, character-for-character by new text. Otherwise, new text is inserted at the cursor position, displacing existing text. By default, new text does not overwrite existing text.

To prevent users from changing the text, select the **Read only** check box.

Selecting Text

In the **Selection mode** field, you can specify whether individual characters or whole words are selected when selecting text with a pointer device.

Select the **Select by mouse** check box to enable users to use the mouse to select text in some platform-specific way. For some platforms this may not be an appropriate interaction because it may conflict with how the text needs to behave inside a **Flickable** component, for example.

For a **Text Edit** component, you can select the **Select by keyboard** check box to enable users to use the keyboard to select text even if the edit field is read-only. If this property is set to , users cannot use the keyboard to select text even if it is editable. false

Focus




by deradic, the cursor becomes visible when the text edit or input gains active rocus, so that other properties can be bound to whether the cursor is currently shown. Because the value of the **Cursor visible** property gets set and unset automatically, any value you set yourself may be overwritten.

If the **Persistent selection** check box is selected, a text edit or input keeps its selection when active focus moves to another component.

Tabs and Margins

You can specify additional properties for formatting a block of text in a **Text Edit** component.



In the **Tab stop distance** field, set the default distance, in device units, between tab stops.

In the **Text margin** field, set the margin around the text in pixels.

Padding

The values of the properties in the **Padding** section specify the padding around the content. The individual padding properties adopt the value of the **Global** field, unless you set them explicitly.





rendered, it will appear clipped.

Placeholder Text

For **Text Field** and **Text Area** controls, you can specify text to display in a field before users enter text into it. Specify the text in the **Placeholder text** field and its color in the **Placeholder color** field.



Select the **Hover** check box to enable the text field to accept hover events.

Summary of Text Components

The following table lists the components that you can use to add text to UIs. The *Location* column contains the tab name where you can find the component in **Components**. The *MCU* column indicates which components are supported on MCUs.

Icon	Name	Location	MCU	Purpose
₪	Label	Qt Quick Controls		A text label with inherited styling and font.
T	Text	Default Components - Basic	✓	Formatted read-only text.
\equiv	Text Area	Qt Quick Controls		Multiple lines of editable formatted text.
T	Text Edit	Default Components - Basic		A single line of editable formatted text that can be validated.
	Text Field	Qt Quick Controls		A single line of editable plain text.
T	Text Input	Default Components - Basic		A single line of editable plain text that can be validated.

< Shapes Images >





Contact Us

Company

About Us

Investors

Newsroom

Careers

Office Locations

Licensing

Terms & Conditions

Open Source

FAQ

Support

Support Services

Professional Services

Partners

Training

For Customers

Support Center

Downloads

Qt Login

Contact Us

Customer Success

Community

Contribute to Qt

Forum

Wiki

Downloads

Marketplace

2022 The Ot Company

Feedback Sign In