Last update: 06 Feb 2016

Motsognir – The mighty gopher server

User manual

Written by Mateusz Viste



http://motsognir.sourceforge.net
gopher://gopher.viste.fr/1/projects/motsognir/

Motsognir manual - Table of Contents

Table of Contents

Introduction	3
Installation	
Configuration file	5
Directory listings	9
Gophermaps	10
Files listing	11
Sub-gophermap scripts	11
Per-user gopher directories	
CGI support	13
Let's see how CGI works	13
How to enable CGI support in Motsognir	14
PHP support	15
How to enable PHP support in Motsognir	15
Example	15
Caps.txt support	16
Serving different content on multiple domain names	17
Security considerations	18
Run Motsognir as a non-privileged (non-root) user	18
Choose your file permissions wisely	18
Use paranoid mode if you are (really) paranoid	18
Trap the daemon inside a chroot jail	
Frequently asked questions (FAQ)	20
Legal mumbo-iumbo.	21

Motsognir manual - Introduction

Introduction

Motsognir is a robust, reliable and easy to install open-source gopher server for Unix-like (POSIX) systems. Motsognir is a standalone daemon that supports server-side CGI applications and PHP scripts, is plainly compatible with UTF-8 filesystems, and is entirely written in ANSI C without external dependencies. It supports both IPv4 and IPv6 'out of the box', without requiring any special configuration.

Gopher is a distributed document search and retrieval network protocol designed for the Internet. Its goal is to function as an improved form of Anonymous FTP, enhanced with hyperlinking features similar to that of the World Wide Web.

I wrote Motsognir primarily for fun, but it appears to have become a strong, full-featured gopher server implementation with some very nice points: easy to install, lightweight, portable, secure...

The Motsognir gopher server is meant to be used for small projects (like home servers), but should scale well on bigger architectures just as well. All the configuration is done via a single configuration file, which has very reasonable defaults. That makes Motsognir easily maintainable, and allows the administrator to have full knowledge of what features are allowed/enabled on the server.

Motsognir manual - Installation

Installation

Installing Motsognir is very easy on most systems, since it comes packaged as a part of the operating system on many Linux and BSD distributions. However, if your operating system doesn't provide a plug & play motsognir package, then you will have to install it manually.

In the first place, you will have to build it. Assuming you have the basic GNU development tools installed (make, gcc), building Motsognir should be as straight-forward as:

make

This will generate a 'motsognir' executable, that you will need to install on your system, then:

make install

Now, all you have to do is edit your /etc/motsognir.conf file to make it suit your needs, and then launch motsognir:

/usr/sbin/motsognir

Note: If you wish to store the motsognir.conf file outside of /etc/, or under a different filename, then you will have to instruct motsognir about its location every time your run it:

/usr/sbin/motsognir --config /my/custom/location/motsognir.conf

Alternatively, you could also modify the default location of the configuration file during compilation, using the -DCONFIGFILE=/etc/somefile.conf compile-time parameter.

Configuration file

Motsognir's configuration file is located by default in /etc/motsognir.conf (unless the default location has been modified at compile-time using the -DCONFIGFILE define), and should be readable by the user which will run the motsognir service. The configuration file is a plain-text file, containing some tokens with values. All lines beginning with the "#" character are ignored (and can be used to put some comments in the configuration file).

If any of the parameter is missing from the configuration file, or have an empty value, Motsognir will use a default value instead. Here below is an example of a self-explanatory configuration file.

```
CONFIGURATION FILE FOR THE MOTSOGNIR GOPHER SERVER
## Server's hostname ##
# The hostname the gopher server is reachable at. This setting is highly
# recommended, because the gopher protocol is heavily relying on
# self-pointing links. If not declared, the server's IP address will be used
# instead.
#GopherHostname=gopher.example.com
## Gopher TCP port ##
# The TCP port on which the public Gopher server listens on.
# Usually, gopher servers are published on port 70. Default: 70.
GopherPort=70
## Bind on IP address ##
# Set this 'bind' parameter to the IP address you'd like Motsognir to listen
# on. Note, that this parameter must be either an IPv6 address, or an IPv4
# address written in IPv4-mapped IPv6 notation (for ex. "::FFFF:10.0.0.1").
# If not specified, Motsognir will listen on all available IP addresses.
# This setting might be useful if you have a multihomed server, and you would
# like to serve different content for each IP address.
# Examples:
# bind=2001:DB8:135:A0E3::2
# bind=::FFFF:192.168.0.3
bind=
## Root directory ##
# That's the local path to Gopher resources. Note, that if you use
# a chroot configuration, you must provide here the virtual path
# instead of the real one.
# The default path is /var/gopher/
GopherRoot=/var/gopher/
```

Motsognir manual - Configuration file

```
## Allowed public directories ##
# In specific situations, it may happen that you'd like to be able to serve
# files from outside of your gopher root (typically, if you used symlinks
# inside your gopher root, that points to other places of the file system).
# By default Motsognir won't allow such resources to be served, since requests
# that try to access anything outside of the gopher root are considered as
# potentially malicious. However, if you do want to serve content from outside
# your gopher root, then fill in below the list of directories that are
# allowed to be served. Items of this list should be separated by a ':' char.
# Example: PubDirList=/srv/files:/var/lib/stuff:/tmp
PubDirList=
## User home directories ##
# If you'd like to serve gopher content from user directories, using the
# classic / user/ URL scheme, then define the user directories location here
# below. The configured location must contain a 'xs' tag, which will be
# substituted with the username by motsognir. This must be an absolute path.
# If nothing is configured, then support for serving content from user
# directories won't be available. Example:
# UserDir=/home/%s/public_gopher/
UserDir=
## chroot configuration ##
# If you'd like to put Motsognir inside a chroot jail, configure here
# the chroot directory that shall be used.
# By default no chroot is used.
chroot=
## Paranoid mode ##
# For paranoidal security, you might want to enable "Paranoid mode". In this
# mode, Motsognir accepts to serve only files with permissions set to "world
# readable".
# Possible values: 0 (disabled) or 1 (enabled). Disabled by default.
ParanoidMode=0
## Activate the verbose mode ##
# Here you can enable/disable the verbose mode. In verbose mode,
# Motsognir will generate much more logs. This is useful only in
# debug situations.
# Possible values: 0 (disabled) or 1 (enabled). Disabled by default.
Verbose=0
## CGI support ##
# The line below enables/disables CGI support. Read the manual
# for details.
# Possible values: 0 (disabled) or 1 (enabled). Disabled by default.
GopherCg iSupport=0
## PHP support ##
# There you can enable PHP support.
# Possible values: 0 (disabled) or 1 (enabled). Disabled by default.
GopherPhpSupport=0
## Sub-gophermap scripts ##
# If you'd like to use sub-gophermap scripts in your gophermaps, set
```

Motsognir manual - Configuration file

```
# SubGophermaps.
# Possible values: 0 (disabled) or 1 (enabled). Disabled by default.
SubGophermaps=0
## Secondary URL-delimiting char
# By default, only the '?' char is recognized as a delimiter between an
# object and the query that must be run on the object. With this parameter,
# you can define an additional character that will be equivalent to '?'. This
# character must be provided in a numerical form, as an ASCII value.
# Example for the hash (#) character:
# SecUrlDelim=35
SecUrlDelim=
## Run as another user ##
# If you start motsognir under a root account, you might want to configure
# it so it drops root privileges as soon as it doesn't need them anymore and
# switches to another user. This is recommended for increased security,
# unless you already run Motsognir as a non-root user.
# To do so, provide here the username of the user that Motsognir should run
# as. Default = no value.
RunAsUser=
## Default gophermap #
# If you wish that your server would use a default gophermap when displaying
# a directory that do not have a gophermap, you can specify here a path to
# the gophermap file you'd like to use.
DefaultGophermap=
## HTTP error file
# When Motsognir receives a HTTP request, it answers with a HTTP error,
# along with a html message indicating why it is wrong. If you'd like to use
# a custom html file, you can set it here. Note, that the specified file is
# loaded when Motsognir's starts. If you modify the file afterwards, you'll
# need to restart the Motsognir process for the file to be reloaded.
# Example: HttpErrFile=/etc/motsognir-httperr.html
HttpErrFile=
## Caps.txt support ##
# Caps.txt is a specific file-like selector, which allows a gopher client to
# know more about the server's implementation (for example what the path's
# delimiter is, where is the server located, etc). When enabled, Motsognir
# will answer with caps-compatible data to requests for "/caps.txt".
# Caps support is enabled by default (CapsSupport=1).
CapsSupport=1
## Caps additionnal informations ##
# If Caps support is enabled, you can specify there some additional
# informations about your server. These informations will be served
# to gopher clients along with the CAPS.TXT data.
# Example:
  CapsServerArchitecture=Linux/i386
  CapsServerDescription=This is my server
  CapsServerGeolocationString=Dobrogoszcz, Poland
  CapsServerDefaultEncoding=UTF-8
CapsServerArchitecture=
```

Motsognir manual - Configuration file

CapsServerDescription=

```
CapsServerGeolocationString=
CapsServerDefaultEncoding=

## Extension to filetype mapping ##

# Motsognir looks at file's extensions to advertise the proper gopher resource

# type. If the default mapping is not suiting you, you can load a custom

# mapping using a separate configuration file called an 'extmap', and declare

# it below. The extmap file is a simple text file, where every line provides

# a mapping for a single file extension, in such format:

# txt:0

# pdf:P

# gif:g

# Note: Extensions in the extmap file are processes in a case-insensitive way.

ExtMapFile=

# [End of file here]
```

Directory listings

As any other gopher server, Motsognir will present to gopher clients listings of available directories with a specific presentation. A specific requirement of the Gopher protocol is that it needs to provide a "type" for every resource. To detect that gopher type, Motsognir is simply basing on the file's extension. Below is a table containing the default relations between gopher filetypes and real file extensions, as used by Motsognir:

Gopher type	Description	Files binded to this gopher type
0	Plain text file	*.txt
1	Directory listing	All directories
2	CSO search query	-
3	Error message	-
4	BinHex encoded text file	-
5	Binary (PC-DOS) archive file	-
6	UUEncoded text file	-
7	Search engine query	-
8	Telnet session pointer	-
9	Binary file	All files which doesn't fit into any other category
g	GIF image file	*.gif
h	HTML file	*.htm, *.html
i	Informational message	-
I	Image file (other than GIF)	*.jpg, *.jpeg, *.png, *.bmp, *.pcx, *.ico, *.tif, *.tiff, *.svg, *.eps
S	Audio file	*.mp3, *.mp2, *.wav, *.mid, *.wma, *.flac, *.mpc, *.aiff, *.aac
Р	PDF file	*.pdf
M	MIME encoded message	-
;	Video file	-

Motsognir manual - Directory listings

Note, that the above relations can be overwritten using a custom extension mapping ('extmap') file, declared within Motsognir's configuration file using the ExtMapFile directive. Example:

ExtMapFile=/etc/motsognir.extmap

Gophermaps

There are situations when you would like to have the absolute control on how the server will display a directory. That's why Motsognir supports gophermaps. If Motsognir finds a file called "gophermap" (without any extension) in a directory, then it doesn't check the directory content, and simply outputs to the user the content of the gophermap. Note, that if you enable CGI and/or PHP support, Motsognir will also look for respectively gophermap.cgi and gophermap.php files. A gophermap file contains gopher entries as described by the RFC 1436. There's an example of a gophermap file (of course <tab> have to be replaced by real tabs):

```
iWelcome to my gopher server!<tab>fake<tab>null<tab>0
i<tab>fake<tab>null<tab>0
0About my server<tab>/about.txt<tab>mygopher.domain.net<tab>70
1Download<tab>/download<tab>mygopher.domain.net<tab>70
1A link to a friend's server<tab><tab>friend.domain.net<tab>70
hMy Website<tab>URL:http://mywebsite.com<tab><tab>
```

You can omit the server's address and server's port parts in your gophermap files (unless these are dynamically generated via CGI or PHP). If you don't specify a port, Motsognir provides the one your server is using (usually 70). If you don't specify a host, Motsognir provides your server's hostname. If you specify a relative selector (not beginning by a / character) instead of an absolute path, Motsognir sticks on the path of the currently browsed directory (but only if the host part is omitted, or pointing to your own server).

Therefore, a simpler form of the above gophermap could look like that:

```
iWelcome to my gopher server!
i
0About my server<tab>about.txt
1Download<tab>download
1A link to a friend's server<tab>friend.domain.net<tab>70
hMy Website<tab>URL:http://mywebsite.com
```

Motsognir manual - Gophermaps

Files listing

A specific feature of Motsognir regarding gophermap files is its ability to generate a dynamic file listing inside a gophermap, using a special %FILES% directive. Example:

Motsognir provides you with a feature that allows you to set a server-wide gophermap to be used by any directory that do not have its own gophermap. This is the 'default' gophermap. The default gophermap have to be declared in the Motsognir's configuration file, via the 'DefaultGophermap' directive.

Sub-gophermap scripts

Another feature of Motsognir is its ability to run scripts from within existing gophermaps. Such scripts are called "sub-gophermap scripts", because they are supposed to output a partial gophermap that will be inserted into our actual gophermap. A sub-gophermap script must be declared in the gophermap with a '=' gopher type. Here below is an example of how such sub-gophermap script would be called:

```
iHello, World! My current uptime is: =/bin/gopher-uptime.sh
```

Note, that for sub-gophermap scripts to run, Motsognir must be configured to allow their execution, via the SubGophermaps configuration directive:

```
SubGophermaps=1
```

It's also worth noting that sub-gophermap scripts will be executed regardless of their extension, as long as their executability bit is set. Hence no need to name them with a *.cgi extension.

Motsognir manual - Per-user gopher directories

Per-user gopher directories

On systems with multiple users, each user can be permitted to have public gopher content in their home directory using the UserDir directive. Visitors to a URL like gopher://example.com/~username/ will get content out of the home directory of the user "username", out of the subdirectory specified by the UserDir directive.

Note that, by default, access to such per-user directories is not enabled. You can enable access when using UserDir by setting a line like this:

UserDir=/home/%s/public_gopher/

Note, that the UserDir configuration must obey a few rules:

- it must be an absolute path (ie. it has to begin with a '/'),
- it must contain a '%s' tag. This tag is replaced with the username by Motsognir.

Motsognir manual - CGI support

CGI support

Motsognir supports CGI applications, that allow to run custom scripts and programs interacting with gopher clients.

Let's see how CGI works.

Each time a client requests the URL corresponding to your CGI program, the server will execute it in real-time, then the output of your program will go more or less directly to the client. In fact, when it comes to answer to the client, the CGI application will output a gopher response (ie. a plain text file for file type #0, a directory listing for file type #1, etc...). This response will be catched by Motsognir, and forwarded to the gopher client as being the request's answer.

The Motsognir gopher server provides some information to the CGI application, by setting some environment variables. Note, that for security reasons – and unlike some other CGI implementations - Motsognir will never feed CGI scripts with any command-line parameters.

Motsognir will set several environment variables, which can be read by the called CGI script. Here is the complete list of these variables:

QUERY_STRING The URL parameters or query, as provided by the client QUERY_STRING_URL The client's URL parameter QUERY_STRING_SEARCH The client's search query SERVER_SOFTWARE The name and version of the server software The server's hostname, DNS alias, or IP address, used SERVER_NAME for self-referencing links GATEWAY_INTERFACE The revision of the CGI specification, as supported by the server The IP address of the remote client REMOTE_ADDR REMOTE_HOST Same as REMOTE_ADDR SCRIPT NAME Script name (for self-referencing links) SERVER_PORT The port number to which the request was sent

Note, that the QUERY_STRING variable will contain data inputed by the user. For type #7 items, it will contain the search string (on type #7 items, the gopher client usually asks the user for a query, using some kind of pop-up). For any other item's type, the QUERY_STRING variable will contain the part of the URL after the first "?" character (if any). For example, for a request on "gopher://mygopher.server.com/0/myprog.cgi?hellothere", the QUERY_STRING variable will contain the data "hellothere".

It is also possible to use search items (type #7) with a "?" URL - in such case, the CGI script will be able to read both queries separately via QUERY_STRING_URL and QUERY_STRING_SEARCH.

Motsognir manual - CGI support

How to enable CGI support in Motsognir

If you would like to use CGI applications on your Motsognir server, you will have to enable CGI support in the Motsognir's configuration file (GopherCgiSupport = 1). You will also have to make sure that your CGI programs are specifically named with a *.cgi extension (the only exception being CGI scripts called from within gophermaps – these are executed regardless of their actual extension).

Motsognir manual - PHP support

PHP support

PHP is a very popular scripting language in the web world. You can use it with gopher, too! Motsognir provides PHP support since its v1.0. The PHP concept is very similar to CGI (historically, PHP was in fact born as a set of custom CGI scripts), therefore you are advised to read the chapter about CGI first. Most of it applies to PHP as well.

The main difference is that instead of trying to directly execute PHP files, Motsognir will feed them to your system's php interpreter, and collect the result.

To pass data to your PHP application, you will have to rely on the QUERY_STRING environment variable.

How to enable PHP support in Motsognir

First of all, make sure that php is available on your system. Then, simply enable the parameter in Motsognir's configuration file (GopherPhpSupport = 1). Note, that all your php files must have the extension *.php to be recognized by Motsognir.

Example

Here below is a simple example of a PHP file that could be used as a dynamic (PHP) gophermap with Motsognir.

```
<?php
echo "iHello, this is a php-driven gophermap\tx\tx\t0\r\n";
echo "i\tx\tx\t0\r\n";
echo "iCurrent date is " . date(DATE_RFC822) . "\tx\tx\t0\r\n";
echo "iServer powered by {$_SERVER['SERVER_SOFTWARE']}\tx\tx\t0\r\n";
echo "i\tx\tx\t0\r\n";
echo "i\tx\tx\t0\r\n";
echo "1Go back\t\t{$_SERVER['SERVER_MAME']}\t{$_SERVER['SERVER_PORT']}\r\n";
?>
```

Caps.txt support

Motsognir supports caps.txt since version 0.99.1. Caps.txt is a file-like selector, which allows a gopher client to know more about the server's gopher implementation (like what is the path delimiter character, how are structured server's paths, what the server's location is, etc).

Caps.txt support is configurable via the Motsognir's configuration file, using following tokens:

```
## Caps.txt support ##
# Caps.txt is a specific file-like selector, which allows a gopher client to
# know more about the server's implementation (for example what the path's
# delimiter is, where is the server located, etc). When enabled, Motsognir
# will answer with caps-compatible data to requests for "/caps.txt".
# Caps support is enabled by default (CapsSupport=1).
CapsSupport=1
## Caps additionnal informations ##
# If Caps support is enabled, you can specify there some additional
# informations about your server. These informations will be served
# to gopher clients along with the CAPS.TXT data.
# Example:
  CapsServerArchitecture=Linux/i386
  CapsServerDescription=This is my server
  CapsServerGeolocationString=Dobrogoszcz, Poland
CapsServerArchitecture=
CapsServerDescription=
CapsServerGeolocationString=
```

If you would like to have full access to what Motsognir sends in Caps.txt data, then you might consider disabling the caps.txt support in Motsognir (CapsSupport=0), and simply host your own caps.txt file in the server's root. Here is an example of such custom caps.txt file:

CAPS
CapsVersion=1
ExpireCapsAfter=3600
PathDelimiter=/
PathIdentity=.
PathParent=..
PathParentDouble=FALSE
PathKeepPreDelimeter=FALSE
ServerSoftware=Motsognir
ServerSoftwareVersion=1.0
ServerArchitecture=Linux/i386
ServerDescription=This is my gopher server
ServerGeolocationString=Dobrogoszcz, Poland

Serving different content on multiple domain names

You have your gopher server up and running, and now you'd like to make use of several different domain names on it – and on each domain, different content should be served. In the http realm such thing is called "virtual hosting". The gopher protocol, however, doesn't have any provision for a similar mechanism. This doesn't mean that all hope is lost, though.

To work out the above situation, you will need to have multiple different IP addresses assigned to your gopher server (fortunately since IPv6 stepped in, having as many addresses as we need is not a problem anymore). Once this is done, then it's only a matter of 'binding' every one of your gopher domain names to a different IP address. The final step is running a dedicated instance of Motsognir on every IP address.

Example: Let's imagine that I own two domains: gopher.example.com and gopher.mydomain.net. For these domains, I'd like to serve gopher content from /srv/gopher.example.com/ and /srv/gopher.mydomain.net/, respectively.

Step 1: configure at least two different IP addresses on my gopher server, and declare them within my DNS zone to be used like this:

```
2001:DB8:410E:ABC::1 → gopher.example.com
2001:DB8:410E:ABC::2 → gopher.mydomain.net
```

Step 2: Prepare two different configuration files for Motsognir, with different "bind" and "GopherHostname" settings, like this:

/etc/motsognir-gopher.example.com.conf

```
GopherHostname=gopher.example.com
bind=2001:DB8:410E:ABC::1
...

/etc/motsognir-gopher.mydomain.net.conf
GopherHostname=gopher.mydomain.net
bind=2001:DB8:410E:ABC::2
...
```

Step 3: Run two instances of Motsognir, using your custom configuration files:

```
motsognir --config /etc/motsognir-gopher.example.com.conf
motsognir --config /etc/motsognir-gopher.mydomain.net.conf
```

Motsognir manual - Security considerations

Security considerations

Like with any unix daemon, there are a few security aspects that one should always keep in mind. Even the most carefully written programs can have bugs, some of which could be exploited by malicious persons. This is the reason why a system administrator should apply some security limitations even to simplest or most trusted daemons.

Run Motsognir as a non-privileged (non-root) user

A system daemon is usually not supposed to be run as root. In the (unlikely!) situation where an attacker would gain control over Motsognir, having the process running as an unprivileged user would greatly reduce the panel of harmful actions that could be performed on your server. However, there is a problem: you will usually want to run your gopher server under the standard TCP/70 port...and this being a low port requires the process to have root privileges. That's why Motsognir provides a special configuration option called 'RunAsUser'. This option allows to set the username we'd like Motsognir to use, and then, when Motsognir will be launched, it will first open ("bind") the listening port, and only then drop its privileges to switch to the configured user.

Choose your file permissions wisely

If your Motsognir server runs as a non-privileged user, then it makes much sense to limit permissions on files that it serves. If the gopher server is not supposed to modify a file, this file should be set as 'read-only' and owned by root. This way, even if Motsognir becomes compromised, it still won't be able to modify these files.

Use paranoid mode if you are (really) paranoid

By default, Motsognir will happily serve anything that is located somewhere in the gopher root path, and that is readable by the gopher-running user. To make things even more strict, you might want to use Motsognir's "Paranoid mode" (configurable in Motsognir's configuration file). In this mode, Motsognir will accept to serve only files that have "world readable" permissions set.

Motsognir manual - Security considerations

Trap the daemon inside a chroot jail

The principle of a chroot jail is simple: run a process inside a 'virtualized' environment with a modified root path (for example, mapping a chroot / on /srv/gopher/). This technique is used to make it impossible for the process to access any file outside the chroot jail. A process can need some files, like shared libraries, or configuration files, to run properly. If chrooting a process, one would need to put all these files into the chroot as well (and the process' executable file itself!). To avoid these problems, Motsognir provides a 'chroot' configuration parameter that, once set, will make Motsognir run, load its configuration, and only then perform a chroot to the designated directory.

Note, that if you use any kind of dynamic files (*.cgi or *.php), you will need to take care to put all dependencies of these applications inside the chroot jail, too. This includes a shell at /bin/sh, all system libs that your applications might require, etc. Often a working /proc will also be needed.

Frequently asked questions (FAQ)

Q: Does Motsognir support special (nationalized) character sets in file names?

A: Yes, it does. Motsognir implements support for UTF-8 encoded URLs, therefore it is able to handle any existing language. Note, that it requires the local server's filesystem to be using UTF-8 too, otherwise only the basic ASCII set will be handled.

Q: Can I use Motsognir for commercial purpose, or adapt it to my own needs?

A: Yes, you definitely can. Motsognir is released under the GNU/GPLv3 license, therefore everyone is free to use it, modify it, and even sell it. However, you can't claim that you are the author of this software, and you must provide the source code of any modification you do on it (and you can't EVER drop the GPL licensing).

Q: Is there any way to run server-side applications on Motsognir?

A: Motsognir supports executable CGI scripts, as well as PHP files. Both of these technologies allow you to run custom server-side scripts.

Q: What's the maximum file size that Motsognir can serve?

A: Motsognir itself can serve files which are up to 8 exbibytes (EiB) big. However, chances are that your filesystem will limit you much sooner (for example EXT3 supports files up to 2 TiB of size, while EXT4 supports files up to 16 TiB).

Q: What does "Motsognir" stand for?

A: In Norse mythology, Mótsognir is the father of the Dwarves. Mótsognir is the creation of Odin and his brothers, Vili and Vé, who fashioned him out of Ymir's blood and bones in the form of a maggot. He got a roughly humanoid appearance and a human-like intelligence, which the rest of the Dwarves later inherited. (source: wikipedia)

Q: Does Motsognir support the HTTP protocol?

A: No. Motsognir is a gopher server. Gopher is a protocol different from HTTP. However, if you send by mistake a HTTP request to Motsognir (for example using a URL like http://yourserver:70/), he will politely answer with a HTTP explanation message.

Q: Is this a real 'FAQ'?

A: No, I totally made up most of these questions.

Motsognir manual - Legal mumbo-jumbo

Legal mumbo-jumbo

Copyright © 2008-2016 Mateusz Viste http://motsognir.sourceforge.net gopher://gopher.viste.fr/1/projects/motsognir/



All rights reserved. This product or documentation is protected by copyright and is distributed under licenses restricting its use, copying, distribution and decompilation. See the GNU General Public License as published by the Free Software Foundation, either version 3 of the License, or (at your option) any later version for details.

The copyright owner gives no warranties and makes no representations about the contents of this manual and specifically disclaims warranties of merchantability or fitness to any purpose.

The copyright owner reserves the right to revise this manual and to make changes from time to time in its content without notifying any person of such revision or changes.

Graphic images

The image of the dwarf on the cover of this manual is based on the original work of Lorenz Frølich (1820-1908).

Trademarks

Unix is a registered trademark of UNIX System Laboratories, Inc. Windows, WindowsNT, and Win32 are registered trademarks of Microsoft Corp. All other product names mentioned herein are the trademarks of their respective owners.