ElmerPad Remote Host Server Setup and Connection Guide

To set up remote linking you will need to install the elmer-syncd remote host server on your Linux or Windows PC.

Download the Linux/Windows server executables from :
https://late-scene-3cfe.elmertjonez.workers.dev

The elmer-syncd remote server source code : https://github.com/ElmerWorks/elmer-syncd

This document describes setup on 1. Windows and 2. Linux

Appendix A shows how to set up Windows Firewall to allow the connection

1. WINDOWS :

1. Download the Windows installer elmer-syncd-setup.exe (in the .zip file elmer-syncd-install.zip).
You can also just run elmer-syncd.exe (also in the zip file), and start from Step 5.
Windows installation is preferred.

2. Run elmer-syncd-setup.exe as Administrator (rt-click Run as Administrator).
This will install elmer-syncd in c:\Program Files

3. Set up Firewall exemption :
For instructions refer to Appendix A of this document


4. Add ElmerSyncd to your Windows PATH:

- Press `Win + X` and select "System"
- Click "Advanced system settings"
- Click "Environment Variables..."
- Under "User variables", click "New..."
- Variable name: `PATH`
- Variable value: `C:\Program Files\ElmerSyncd`
- Click OK and close all dialogs

Elmer-syncd runs from the Windows PowerShell console.


5. Navigate to your sync folder. This is where you want to keep your remote files and subfolder. In this example the sync folder is C:\tmp\syncfiles.

6. Open Command Prompt or PowerShell




7. Get host IP address

Enter >elmer-syncd –show-ip to obtain host IP address
In this example IP address is 192.168.1.99
This will be entered in your Android remote link setup.




8. Start Elmer-Syncd remote server

Enter >elmer-syncd --allow-lan
When you see this output the server is running and can accept connection from Android.




9. Connect your Android ElmerPad app to the host IP address and port 12345


In ElmerPad enter F10>Desktop Sync or Alt-D



Enter connection settings : Host IP (from 7. Get Host IP), Port 12345, Token : mytoken

Press 1. Connect.






If successful the message “Connected to Host” will appear.
Options 5-8 will appear.
On Windows elmer-syncd console this message will appear.

10. Test by Pushing Remote File to Host

Enter some text in a file buffer. Then F10>Desktop Sync or Alt-D, 8. Save Buffer to Remote Host, give it a file name. If successful will see this message :









10. continued,

The saved file will now be on the remote host folder :



11. In the same manner can retrieve a file from the host into an ElmerPad buffer



2. LINUX :

Follow these steps to install on Linux. Once installed the elmer-syncd behavior on Linux is identical to Steps 7-11 above.

Dumb install :

Copy the Linux elmer-syncd executable to your linux machine from the zipfile elmer-syncd-install.zip

In a terminal console enter these commands

Make it executable
chmod +x elmer-syncd

Find your LAN IP for the Android app to connect
./elmer-syncd --show-ip

Run it (navigate to your sync folder first)
cd /path/to/sync/folder
./elmer-syncd --allow-lan

Or with specific root directory
./elmer-syncd --root /path/to/sync/folder --allow-lan

Proper Install Using install-elmer-syncd.sh :

What This Script Does
The `install-elmer-syncd.sh` script automates the installation of the elmer-syncd service on your Linux system. It:
- Copies the application to a system-wide location
- Sets up proper permissions
- Configures it to start automatically with your computer
- Optionally creates a dedicated system user

Prerequisites
- Linux system (any modern distribution)
- Administrator access (you'll need to enter your password)
- The elmer-syncd binary file (the compiled application)

How to Use It

Step 1: Open a Terminal

Step 2: Navigate to the Directory
Go to the directory where you have the `install-elmer-syncd.sh` script:
```bash
cd path/to/packaging/linux
```

Step 3: Run the Installation

Basic installation:
bash
./install-elmer-syncd.sh /path/to/elmer-syncd-binary

Replace `/path/to/elmer-syncd-binary` with the actual path to your downloaded elmer-syncd binary file.

Example:
bash
./install-elmer-syncd.sh ~/Downloads/elmer-syncd
With automatic user creation:
If you want the script to create a dedicated system user for elmer-syncd, add the `--create-user` flag:
bash
./install-elmer-syncd.sh /path/to/elmer-syncd-binary --create-user

Step 4: Enter Your Password
The script uses `sudo` commands, so you'll be prompted to enter your password. This is normal and required for system-level installation.

What Gets Installed

Component	Location	Purpose
Application	`/usr/local/bin/elmer-syncd`	The main elmer-syncd program
Configuration	`/etc/systemd/system/elmer-syncd.service`	Systemd service definition (auto-start settings)
Data Directory	`/var/lib/elmer-syncd`	Where the service stores its data

After Installation

Once the script completes, elmer-syncd will:
- Be installed on your system
- Start automatically when you boot your computer
- Be running right now

Verifying Installation

To check if elmer-syncd is running:
```bash
sudo systemctl status elmer-syncd
```

To view logs:
```bash
sudo journalctl -u elmer-syncd -f
```

Troubleshooting


Problem	Solution
"Permission denied"	Make sure you're running from a terminal and prepend `bash ` before the script name: `bash ./install-elmer-syncd.sh ...`
"Binary not found"	Double-check the path to your elmer-syncd binary is correct
"command not found"	Make sure you're in the correct directory with the script

Appendix A : How to set up Windows Firewall rule


You may need to create an exception for your Windows firewall to allow elmer-sycnd to communicate with host.

1. Open Windows Settings> Privacy&Security>Windows Security>Firewall&Network Protection


2. Advanced Settings




3. Click Inbound Rules




4. Click New Rule




5. In Rule Type Default is Program, click next




6. Set elmer-syncd path, browse to elmer-synd install folder, then click Next






7. Click Next for Allow Connection, Click Next



8. Allow to apply to network domains, click Next



9. Give the rule a name, Click Next. New Firewall rule is created.

