

YOU

You said Anydesk seems very slow.Now if we have tight vnc and I have a small aws server free tier using stuff... Anydesk seems very slow.Now if we have tight vnc and I have a small aws server free tier using stuff like frp can we find a way to connect laptops over the internet using tight vnc as it is better, just that it doesn't support direct internet access.lets build our own gateway to remote control instead of the unreliable anydesk.i am in nairobi and my mums laptop is in nanyuki

YOU

You said Anydesk seems very slow.Now if we have tight vnc and I have a small aws server free tier using stuff...

Yes, this architecture is completely viable and ideal for bypassing NAT/firewalls without relying on third-party cloud relays like AnyDesk.

GabrielTanner

By using FRP (Fast Reverse Proxy) hosted on your AWS Free Tier instance (EC2) as a middleman, your mother's laptop in Nanyuki can establish an outbound tunnel to AWS. You can then connect from Nairobi directly through AWS to reach her screen.

GabrielTanner

Network Architecture Overview

[Your Laptop] ---(VNC Viewer: 108.x.x.x:5900)---> [AWS EC2 Server]

(Nairobi Client) (Public IP: 108.x.x.x)

^

| (Tunnel via Port 7000)

v

[Mum's Laptop]

(Nanyuki Server + frpc)

AWS EC2 (Relay): Runs frps (FRP Server) listening on port 7000 (for tunnel control) and forwards VNC traffic on port 5900.

Mum's Laptop in Nanyuki: Runs TightVNC Server (listening locally on port 5900) and frpc (FRP Client). frpc dials out to AWS on port 7000 to register the reverse tunnel.

Your Laptop in Nairobi: Open TightVNC Viewer and connect directly to YOUR_AWS_PUBLIC_IP:5900.

Step-by-Step Configuration

Step 1: Prepare AWS EC2 Security Group

In your AWS EC2 console, edit the Inbound Rules for your EC2 instance's Security Group to open two ports:

TCP 7000: For FRP client authentication/control connection.

TCP 5900: For TightVNC viewer traffic.

SupportPRO

Step 2: Set up FRP Server (frps) on AWS EC2

Log into your Linux EC2 instance via SSH and download FRP:

Bash

```
wget https://github.com/fatedier/frp/releases/download/v0.58.0/frp_0.58.0_linux_amd64.tar.gz
```

```
tar -xvf frp_0.58.0_linux_amd64.tar.gz
```

```
cd frp_0.58.0_linux_amd64
```

Create or edit frps.toml (FRP configuration file):

Ini, TOML

```
bindPort = 7000
```

```
auth.token = "CreateASecureSecretTokenHere"
```

Start the server:

Bash

```
./frps -c ./frps.toml
```

(To keep it running in the background, run it inside tmux, screen, or set up a systemd service).

Step 3: Configure Mum's Laptop (Nanyuki)

Install TightVNC Server:

Download TightVNC for Windows.

SupportPRO

Install it and register it as a System Service so it stays active even if no user is logged in.

TightVNC

Set a strong VNC password during installation.

TightVNC

Install FRP Client (frpc):

Download the Windows release of FRP (e.g., frp_0.58.0_windows_amd64.zip) and extract it.

Edit frpc.toml in the extracted folder:

Ini, TOML

```
serverAddr = "YOUR_AWS_PUBLIC_IP"
```

```
serverPort = 7000
auth.token = "CreateASecureSecretTokenHere"
[[proxies]]
name = "tightvnc-nanyuki"
type = "tcp"
localIP = "127.0.0.1"
localPort = 5900
remotePort = 5900
```

Run FRP Client on Startup:

Open Command Prompt inside the FRP directory and test the connection:

DOS

```
frpc.exe -c frpc.toml
```

To make frpc run automatically on boot, create a Windows Service using NSSM (Non-Sucking Service Manager) or place a batch script in the shell:startup folder.

Step 4: Connect from Nairobi

Open TightVNC Viewer on your laptop.

SupportPRO

In the Remote Host field, enter:

Plaintext

```
YOUR_AWS_PUBLIC_IP:5900
```

Click Connect and input the VNC password set on your mum's laptop.

Important Optimizations for Performance & Security

Optimize TightVNC for Remote Connections:

In TightVNC Viewer options on your end:

Set color depth to 8-bit (256 colors) or 16-bit.

Enable Tight encoding and turn compression up to level 6–9.

Securing the VNC Connection:

Standard VNC traffic over port 5900 is unencrypted. To secure the stream:

Add transport.tls.enable = true to frpc.toml to encrypt the tunnel between Nanyuki and AWS.

Alternatively, restrict port 5900 in your AWS Security Group so it only accepts inbound connections from your specific Nairobi IP address.

YOU

You said give me direct link for frp_0.58.0_windows_amd64.zip
give me direct link for frp_0.58.0_windows_amd64.zip

YOU

You said give me direct link for frp_0.58.0_windows_amd64.zip

Direct download link for v0.58.0:

GitHub

https://github.com/fatedier/frp/releases/download/v0.58.0/frp_0.58.0_windows_amd64.zip

PowerShell Quick Download

Run this command in PowerShell on your mum's laptop to download and extract it into a folder named frp:

PowerShell

Invoke-WebRequest -Uri

"https://github.com/fatedier/frp/releases/download/v0.58.0/frp_0.58.0_windows_amd64.zip" -OutFile "frp.zip"

Expand-Archive -Path "frp.zip" -DestinationPath "C:\frp"

cd C:\frp\frp_0.58.0_windows_amd64

YOU

You said and also systemd service for frps
and also systemd service for frps

YOU

You said and also systemd service for frps

To set up frps as a background systemd service on your AWS Ubuntu/Debian Linux server:

Step 1: Place Files in Standard Directories

Move binary to /usr/local/bin:

Bash

```
sudo cp frps /usr/local/bin/
```

```
sudo chmod +x /usr/local/bin/frps
```

Move config file to /etc/frp/:

Bash

```
sudo mkdir -p /etc/frp
```

```
sudo cp frps.toml /etc/frp/
```

Step 2: Create the Service File

Open a new service configuration file:

Bash

```
sudo nano /etc/systemd/system/frps.service
```

Paste the following configuration:

Ini, TOML

[Unit]

Description=FRP Server Service

After=network-online.target

Wants=network-online.target

[Service]

Type=simple

ExecStart=/usr/local/bin/frps -c /etc/frp/frps.toml

Restart=on-failure

RestartSec=5s

[Install]

WantedBy=multi-user.target

Step 3: Enable and Start the Service

Reload systemd daemon, enable on boot, and start:

Bash

```
sudo systemctl daemon-reload
```

```
sudo systemctl enable --now frps
```

Verify status:

Bash

```
sudo systemctl status frps
```

(It should show active (running) in green text).

Useful Service Commands

View live logs: `sudo journalctl -u frps -f`

Restart service: `sudo systemctl restart frps`

Stop service: `sudo systemctl stop frps`

YOU

You said testing from my own laptop vm first, see what i get frps and frpc are all good
testing from my own laptop vm first, see what i get frps and frpc are all good

YOU

You said testing from my own laptop vm first, see what i get frps and frpc are all good

That infinite mirror / recursion effect happens because you are running the TightVNC Viewer on the exact same desktop/VM machine that is hosting the TightVNC Server!

JPG

When you view a desktop inside a viewer window on that same desktop, the viewer captures itself, which captures itself again, creating a visual feedback loop ("hall of mirrors").

JPG

What to do now:

Minimize or close TightVNC Viewer on that VM to break the visual feedback loop.

Test across two different environments:

Host Machine (Your physical laptop): Open TightVNC Viewer [here](#).

Guest Machine (VM): Runs TightVNC Server + FRP Client (frpc).

AWS EC2: Runs FRP Server (frps).

When you connect from your physical host laptop to `AWS_PUBLIC_IP:5900`, you will see your VM's desktop cleanly without the mirror loop!