

EDB Postgres Advanced Server .NET Connector Guide

Version 4.1.6.1

1	What's New	3
2	Requirements Overview	3
3	The EDB .NET Connector - Overview	4
4	Installing and Configuring the .NET Connector	5
5	Using the .NET Connector	23
6	Opening a Database Connection	24
7	Retrieving Database Records	32
8	Parameterized Queries	36
9	Inserting Records in a Database	38
10	Deleting Records in a Database	39
11	Using SPL Stored Procedures in your .NET Application	41
12	Using Advanced Queueing	53
13	Using a Ref Cursor in a .NET Application	67
14	Using Plugins	70
15	Using Object Types in .NET	77
16	Security and Encryption	82
16.1	Scram Compatibility	82
17	EDB .NET Connector Logging	83
18	API Reference	86

1 What's New

The following features are added to create EDB .NET Connector 4.1.6.1:

- Merged with the upstream Npgsql driver version 4.1.6. For more information about the merge updates, visit https://www.nuget.org/packages/Npgsql/4.1.6.
- Support for .NET Framework 4.7.2 and .NET Framework 4.8.

2 Requirements Overview

The following section details the supported platforms for the EDB .NET Connector.

Supported Server Versions and Platforms

The EDB .NET Connector is certified with Advanced Server version 9.5 and above.

The EDB .NET Connector graphical installers are supported on the following Windows platforms:

64-bit Windows:

- Windows Server 2019
- Windows Server 2016
- Windows Server 2012 R2
- Windows 10
- Windows 8.1

32-bit Windows:

Windows 10

Windows 8.1

3 The EDB .NET Connector - Overview

The EDB .NET Connector is a .NET data provider that allows a client application to connect to a database stored on an Advanced Server host. The .NET Connector accesses the data directly, allowing the client application optimal performance, a broad spectrum of functionality, and access to Advanced Server features.

The .NET Connector supports following frameworks:

- .NET Framework versions 4.6.1, 4.7.2 and 4.8
- .NET Standard 2.0 and 2.1
- .NET Core 3.0
- Entity Framework 6
- EDB VSIX

The .NET Class Hierarchy

The .NET Class Hierarchy contains a number of classes that you can use to create objects that control a connection to the Advanced Server database and manipulate the data stored on the server. The following are just a few of the most commonly used object classes:

EDBConnection

The EDBConnection class represents a connection to Advanced Server.

An EDBConnection object contains a ConnectionString that instructs the .NET client how to connect to an Advanced Server database.

EDBCommand

An EDBCommand object contains an SQL command that the client will execute against Advanced Server. Before you can execute an

EDBCommand object, you must link it to an EDBConnection object.

EDBDataReader

An EDBDataReader object provides a way to read an Advanced Server result set. You can use an EDBDataReader object to step through one row at a time, forward-only.

EDBDataAdapter


An EDBDataAdapter object links a result set to the Advanced Server database. You can modify values and use the EDBDataAdapter class to update the data stored in an Advanced Server database.

4 Installing and Configuring the .NET Connector


This chapter describes how to install and configure the EDB .NET Connector.

Installing the .NET Connector


You can use the EDB .NET Connector Installer (available from the EDB website) to add the .NET Connector to your system. After downloading the installer, right-click on the installer icon, and select Run As Administrator from the context menu. When prompted, select an installation language and click OK to continue to the Setup window.




Click Next to continue.



Use the Installation Directory dialog to specify the directory in which the connector will be installed, and click Next to continue.




Click Next on the Ready to Install dialog to start the installation; popup dialogs confirm the progress of the installation wizard.




When the wizard informs you that it has completed the setup, click the Finish button to exit the dialog.

You can also use StackBuilder Plus to add or update the connector on an existing Advanced Server installation; to open StackBuilder Plus, select StackBuilder Plus from the Windows Apps menu.



When StackBuilder Plus opens, follow the onscreen instructions.

Select the EnterpriseDB.Net Connector option from the Database Drivers node of the tree control.



Follow the directions of the onscreen wizard to add or update an installation of an EDB Connector.

Configuring the .NET Connector

Please see the following environment-specific sections for information about configuring the .NET Connector:

- Referencing the Library Files. General configuration information applicable to all components.
- .NET Framework 4.6.1 Instructions for configuring for use with .NET Framework 4.6.1.
- .NET Framework 4.7.2 Instructions for configuring for use with .NET Framework 4.7.2.
- .NET Framework 4.8 Instructions for configuring for use with .NET Framework 4.8.
- .NET Standard 2.0. Instructions for configuring for use with .NET Standard 2.0.

- .NET Standard 2.1. Instructions for configuring for use with .NET Standard 2.1.
- .NET Core 3.0 Instructions for configuring for use with .NET Core 3.0.
- **Entity Framework 6.** Instructions for configuring for use with **Entity** Framework.
- EDB VSIX. Instructions for configuring for use with EDB VSIX.

Referencing the Library Files

To reference library files with Microsoft Visual Studio:

- 1. Select the project in the Solution Explorer.
- 2. Select Add Reference from the Project menu.
- 3. When the Add Reference dialog box opens, browse to select the appropriate library files.

Optionally, the library files can be copied to the specified location.

Before you can use an EDB .NET class, you must import the namespace into your program. Importing a namespace makes the compiler aware of the classes available within the namespace. The namespace is:

EnterpriseDB.EDBClient

If you are using Entity Framework 6, the following additional namespace is required:

EntityFramework6.EntepriseDB.EDBClient

The method you use to include the namespace varies by the type of application you are writing. For example, the following command imports a namespace into an ASP.NET page:

```
<% import namespace="EnterpriseDB.EDBClient" %>
```

To import a namespace into a C# application, write:

```
using EnterpriseDB.EDBClient;
```

.NET Framework Setup

The following sections describe the setup for various .NET versions.

.NET Framework 4.6.1

If you are using .NET Framework version 4.6.1, the data provider installation path is:

C:\Program Files\edb\dotnet\net461\

You must add the following dependencies to your project:

EnterpriseDB.EDBClient.dll

Microsoft.Bcl.AsyncInterfaces.dll

System.Memory.dll

System.Numerics.Vectors.dll

System.Runtime.CompilerServices.Unsafe.dll

System.Runtime.dll

System.Text.Json.dll

System.Threading.Tasks.Extensions.dll

System.ValueTuple.dll

Depending upon the type of application you use, you may be required to import the namespace into the source code. See Referencing the Library Files for this and other information about referencing library files.

.NET Framework 4.7.2

If you are using .NET Framework version 4.7.2, the data provider installation path is:

C:\Program Files\edb\dotnet\net472\

You must add the following dependencies to your project:

EnterpriseDB.EDBClient.dll

Microsoft.Bcl.AsyncInterfaces.dll

System.Memory.dll

System.Numerics.Vectors.dll

System.Runtime.CompilerServices.Unsafe.dll

System.Text.Json.dll

System.Threading.Tasks.Extensions.dll

Depending upon the type of application you use, you may be required to import the namespace into the source code. See Referencing the Library Files for this and other information about referencing library files.

.NET Framework 4.8

If you are using .NET Framework version 4.8, the data provider installation path is:

C:\Program Files\edb\dotnet\net48\

You must add the following dependencies to your project:

EnterpriseDB.EDBClient.dll

Microsoft.Bcl.AsyncInterfaces.dll

System.Memory.dll

System.Numerics.Vectors.dll

System.Runtime.CompilerServices.Unsafe.dll

System.Text.Json.dll

System.Threading.Tasks.Extensions.dll

Depending upon the type of application you use, you may be required to import

the namespace into the source code. See Referencing the Library Files for this and other information about referencing library files.

.NET Standard 2.0

For .NET Standard Framework 2.0, the data provider installation path is:

C:\Program Files\edb\dotnet\netstandard2.0\

You must add the following dependencies to your project:

EnterpriseDB.EDBClient.dll

System.Threading.Tasks.Extensions.dll

System.Runtime.CompilerServices.Unsafe.dll

System.ValueTuple.dll

Note

If your target framework is .Net Core 2.0, then include the following file in your project:

System.Threading.Tasks.Extensions.dll

Depending upon the type of application you use, you may be required to import the namespace into the source code. See Referencing the Library Files for this and other information about referencing library files.

.NET Standard 2.1

For .NET Standard Framework 2.1, the data provider installation path is:

C:\Program Files\edb\dotnet\netstandard2.1\

The following shared library files are required:

EnterpriseDB.EDBClient.dll

System.Memory.dll

System.Runtime.CompilerServices.Unsafe.dll

System.Text.Json.dll

System.Threading.Tasks.Extensions.dll

System.ValueTuple.dll

Depending upon the type of application you use, you may be required to import the namespace into the source code. See Referencing the Library Files for this and other information about referencing library files.

.NET Core 3.0

If you are using .NET Core 3.0, the data provider installation path is:

C:\Program Files\edb\dotnet\netcoreapp3.0\

The following shared library files are required:

EnterpriseDB.EDBClient.dll

System.Threading.Tasks.Extensions.dll

System.Runtime.CompilerServices.Unsafe.dll

System.ValueTuple.dll

System.Memory.dll

Depending upon the type of application you use, you may be required to import the namespace into the source code. See Referencing the Library Files for this and other information about referencing library files.

Entity Framework 6

To configure the .NET Connector for use with Entity Framework, the data provider installation path is:

For net461

C:\Program Files\edb\dotnet\EF\net461

The following shared library file is required:

EntityFramework6.EnterpriseDB.EDBClient.dll

For net472

C:\Program Files\edb\dotnet\EF\net472

The following shared library file is required:

EntityFramework6.EnterpriseDB.EDBClient.dll

For net48

C:\Program Files\edb\dotnet\EF\net48

The following shared library file is required:

EntityFramework6.EnterpriseDB.EDBClient.dll

Note

Entity Framework can be used with the EnterpriseDB.EDBClient.dll library available in the net461, net472 and net48 subdirectories.

See Referencing the Library Files for information about referencing library files.

Add the <DbProviderFactories> entries for the ADO.NET driver for Postgres to the app.config file. Add the following entries:

<add name="EnterpriseDB.EDBClient"
invariant="EnterpriseDB.EDBClient"
description=".NET Data Provider for EnterpriseDB PostgreSQL"
type="EnterpriseDB.EDBClient.EDBFactory, EnterpriseDB.EDBClient,
Version=4.1.6.1, Culture=neutral, PublicKeyToken=5d8b90d52f46fda7"
support="FF"/>

In the project's app.config file add the following entry for provider services under the EntityFramework/providers tag:

orovider invariantName="EnterpriseDB.EDBClient"

```
type="EnterpriseDB.EDBClient.EDBServices,
EntityFramework6.EnterpriseDB.EDBClient">
```

The following is an example of the app.config file:

```
<?xml version="1.0" encoding="utf-8" ?>
<configuration>
 <configSections>
  <section name="entityFramework"</pre>
type="System.Data.Entity.Internal.ConfigFile.EntityFrameworkSection,
EntityFramework, Version=6.0.0.0, Culture=neutral,
PublicKeyToken=b77a5c561934e089" requirePermission="false"/>
 </configSections>
  <startup>
    <supportedRuntime version="v4.0" sku=".NETFramework,Version=v4.5"</pre>
/>
  </startup>
<entityFramework>
 cproviders>
   cprovider invariantName="EnterpriseDB.EDBClient"
type="EnterpriseDB.EDBClient.EDBServices,
EntityFramework6.EnterpriseDB.EDBClient"></provider>
 </entityFramework>
<system.data>
 <DbProviderFactories>
   <remove invariant="EnterpriseDB.EDBClient"/>
   <add name="EnterpriseDB Data Provider"
invariant="EnterpriseDB.EDBClient" support="FF" description=".Net Framework
Data Provider for Postgresql" type="EnterpriseDB.EDBClient.EDBFactory,
EnterpriseDB.EDBClient"/>
 </DbProviderFactories>
</system.data>
</configuration>
```

Note

Depending upon the type of application you are using, you may be required to import the namespace into the source code (see Referencing the Library Files).

For usage information about Entity Framework, refer to the Microsoft documentation.

EDB VSIX for Visual Studio 2015/2017/2019

The EDB Data Designer Extensibility Provider (EDB VSIX) is a component that integrates Advanced Server database access into Visual Studio, thus providing Visual Studio integrated features.

EDB VSIX allows you to connect to Advanced Server from within Visual Studio's Server Explorer and create a model from an existing database. Therefore, if Visual Studio features are desired, then EDB VSIX must be utilized.

EDB VSIX files are located in the following directory:

C:\Program Files\edb\dotnet\vsix

The files available at the above location are:

edb logo.ico EnterpriseDB.vsix SSDLToPqSQL.tt System.ValueTuple.dll

Installation and Configuration for Visual Studio 2015/2017/2019

Use the following steps to install and configure EDB VSIX.

Step 1: Install EDB VSIX to the desired version of Visual Studio with the EnterpriseDB.vsix installer.

If you already have an earlier version of the VSIX installed, we highly

recommended that you uninstall it to avoid conflicts.

It is no longer necessary or recommended to have EnterpriseDB.EDBClient in your global assembly cache (GAC).

Step 2: Relaunch Visual Studio and verify from the Tools > Extensions and Updates... menu that the EDB extension is installed.

Step 3: Use the gacutil utility at the Visual Studio Developers Command Line to add following libraries to the global assembly cache (GAC):

System.ValueTuple.dll
System.Threading.Tasks.Extensions.dll
System.Runtime.CompilerServices.Unsafe.dll
System.Memory.dll
Microsoft.Bcl.AsyncInterfaces.dll
System.Text.Json.dll

For example:

> gacutil.exe /i System.ValueTuple.dll

Step 4: From the Server Explorer, right-click on Data Connections, click Add Connection, and verify that the Enterprisedb Postgres Database data source is available.

Model First and Database First Usage

Step 1: Add the DbProviderFactories entries for the ADO.NET driver to the machine.config file. Include the following entries:

<add name="EnterpriseDB.EDBClient"
invariant="EnterpriseDB.EDBClient"
description=".NET Data Provider for EnterpriseDB PostgreSQL"
type="EnterpriseDB.EDBClient.EDBFactory, EnterpriseDB.EDBClient,
Version=4.1.6.1, Culture=neutral, PublicKeyToken=5d8b90d52f46fda7"
support="FF"/>

For the attribute-value pairs, the double-quoted strings should not contain excess white space characters, but be configured on a single line. The examples shown in this section may be split on multiple lines for clarity, but should actually be configured within a single line such as the following:

description=".NET Data Provider for EnterpriseDB PostgreSQL"

For 64-bit Windows, the machine.config file is in the following location:

C:\Windows\Microsoft.NET\Framework64\v4.0.30319\Config\machine.config

For 32-bit Windows, the machine.config file is in the following location:

C:\Windows\Microsoft.NET\Framework\v4.0.30319\Config\machine.config

Step 2: Place the DDL generation template **SSDLToPgSQL.tt** in the Visual Studio **EntityFramework Tools\DBGen** folder as shown in the following example:

C:\Program Files (x86)\Microsoft Visual Studio
14.0\Common7\IDE\Extensions\Microsoft\EntityFramework Tools\DBGen\

Note

Select this template SSDLToPgSQL.tt in your EDMX file properties.

Step 3: Add the EnterpriseDB.EDBClient.dll and EntityFramework6.EnterpriseDB.EDBClient.dll files to project references. see Referencing the Library Files for information about referencing library files.

Step 4: Configure your Entity Framework application in either of following two ways:

- Code-based
- Config-based.

Code-based

Define a class that inherits from DbConfiguration in the same assembly as your class inheriting DbContext. Ensure that you configure provider services, a provider factory, and a default connection factory as shown below:

```
using EnterpriseDB.EDBClient;
using System.Data.Entity;
class EDBConfiguration : DbConfiguration
{
```

```
public EDBConfiguration()
{
    var name = "EnterpriseDB.EDBClient";
    SetProviderFactory(providerInvariantName: name,
    providerFactory: EnterpriseDB.EDBClient.EDBFactory.Instance);
    SetProviderServices(providerInvariantName: name,
    provider: EnterpriseDB.EDBClient.EDBServices.Instance);
    SetDefaultConnectionFactory(connectionFactory: new
EnterpriseDB.EDBClient.EDBConnectionFactory());
}
```

Config-based

In the project's app.config file, add the following entry for provider services under the EntityFramework/providers tag:

The following is an example of the app.config file.

```
/>
  </startup>
 <entityFramework>
  cproviders>
   provider invariantName="EnterpriseDB.EDBClient"
type="EnterpriseDB.EDBClient.EDBServices,
EntityFramework6.EnterpriseDB.EDBClient"></provider>
  </entityFramework>
 <system.data>
  <DbProviderFactories>
   <remove invariant="EnterpriseDB.EDBClient"/>
   <add name="EnterpriseDB Data Provider"
invariant="EnterpriseDB.EDBClient" support="FF" description=".Net Framework
Data Provider for EDB Postgres" type="EnterpriseDB.EDBClient.EDBFactory,
EnterpriseDB.EDBClient"/>
  </DbProviderFactories>
 </system.data>
</configuration>
```

5 Using the .NET Connector

The sections that follow provide examples that demonstrate using the EDB object classes that are provided by the EDB .NET Connector that allow a .NET application to connect to and interact with an Advanced Server database.

To use the examples in this guide, place the .NET library files in the same directory as the compiled form of your application. All of the examples are written in C# and each is embedded in an ASP.NET page; the same logic and code would be applicable with other .NET applications (WinForm or console applications, for example).

Please create and save the following web.config file in the same directory as the sample code. The examples make use of the DB_CONN_STRING key from this configuration file to return a connection string from the Advanced Server host.

An Advanced Server connection string for an ASP.NET web application is stored in the web.config file. If you are writing an application that does not use ASP.NET, provide the connection information in an application configuration file (such as app.config).

6 Opening a Database Connection

An EDBConnection object is responsible for handling the communication between an instance of Advanced Server and a .NET application. Before you can access data stored in an Advanced Server database, you must create and open an EDBConnection.

The examples that follow demonstrate the basic steps for connecting to an instance of Advanced Server. You must:

- 1. Import the namespace EnterpriseDB.EDBClient.
- 2. Create an instance of EDBConnection.
- 3. Initialize the EDBConnection object by passing a connection string as a parameter to the constructor for the EDBConnection class.
- 4. Call the Open method of the EDBConnection object to open the connection.

Connection String Parameters

A valid connection string should specify location and authentication information for an Advanced Server instance. You must provide the connection string before opening the connection. A connection string must contain:

- The name or IP address of the server
- The name of the Advanced Server database
- The name of an Advanced Server user
- The password associated with that user

The following parameters may be included in the connection string:

CommandTimeout

CommandTimeout specifies the length of time (in seconds) to wait for a command to finish execution before throwing an exception. The default value is 20.

ConnectionLifeTime

Use ConnectionLifeTime to specify the length of time (in seconds) to wait before closing unused connections in the pool. The default value is 15.

Database

Use the **Database** parameter to specify the name of the database to which the application should connect. If a database name is not specified, the database name will default to the name of the connecting user.

Encoding

The **Encoding** parameter is obsolete; the parameter always returns the string unicode, and silently ignores attempts to set it.

Integrated Security

By default, Integrated Security is set to false, and Windows Integrated Security is disabled. Specify a value of true to use Windows Integrated Security.

Load Role Based Tables

Use Load Role Based Tables to load table OIDs based on role. This change only impacts the loading of table type OID, and not the composite type. The default value is false. Setting this parameter to true triggers the

new functionality.

MaxPoolSize

MaxPoolSize instructs EDBConnection to dispose of pooled connections when the pool exceeds the specified number of connections. The default value is 20.

MinPoolSize

MinPoolSize instructs EDBConnection to pre-allocate the specified number of connections with the server. The default value is 1.

Password

When using clear text authentication, specify the password that will be used to establish a connection with the server.

Pooling

By default, Pooling is set to true to enable connection pooling. Specify a value of false to disable connection pooling.

Port

The Port parameter specifies the port to which the application should connect.

Protocol

The specific protocol version to use (instead of automatic); specify an integer value of 2 or 3.

SearchPath

Use the SearchPath parameter to change the search path to named and public schemas.

Server

The name or IP address of the Advanced Server host.

SSL

By default, SSL is set to false; specify a value of true to attempt a secure connection.

sslmode

Use sslmode to specify an SSL connection control preference. sslmode can be:

prefer - Use SSL if possible.

require - Throw an exception if an SSL connection cannot be established.

allow - Connect without SSL. This parameter is not supported.

disable - Do not attempt an SSL connection. This is the default behavior.

SyncNotification

Use the SyncNotification parameter to specify that EDBDataprovider should use synchronous notifications. The default value is false.

Timeout

Timeout specifies the length of time (in seconds) to wait for an open connection. The default value is 15.

User Id

The User Id parameter specifies the user name that should be used for the connection.


Example - Opening a Database Connection using ASP.NET

The following example demonstrates how to open a connection to an instance of Advanced Server and then close the connection. The connection is established using the credentials specified in the DB_CONN_STRING configuration parameter (see Using the .Net Connector for an introduction to connection information and also see Connection String Parameters for connection parameters).

<% @ Page Language="C#" %>

```
<% @Import Namespace="EnterpriseDB.EDBClient" %>
<% @Import Namespace="System.Configuration" %>
<script language="C#" runat="server">
private void Page_Load(object sender, System.EventArgs e)
 string strConnectionString = ConfigurationManager.AppSettings
  ["DB CONN STRING"];
 EDBConnection conn = new EDBConnection(strConnectionString);
 try
  conn.Open();
  Response.Write("Connection opened successfully");
 }
 catch(EDBException exp)
  exp.ToString();
 finally
  conn.Close();
</script>
```

If the connection is successful, a browser will display the following:



Example - Opening a Database Connection from a Console Application

The following example opens a connection with an Advanced Server database using a console-based application.

Before writing the code for the console application, create an app.config file that stores the connection string to the database. Using a configuration file makes it convenient to update the connection string if the information changes.

Using your text editor of choice, enter the following code sample into a file:

```
using System;
using System.Data;
using EnterpriseDB.EDBClient;
using System.Configuration;
namespace EnterpriseDB
{
class EDB
{
```

```
static void Main(string[] args)
 {
    string strConnectionString = ConfigurationManager.AppSettings
   ["DB_CONN_STRING"];
   EDBConnection conn = new EDBConnection(strConnectionString);
   try
   conn.Open();
   Console.WriteLine("Connection Opened Successfully");
   catch(Exception exp)
   throw new Exception(exp.ToString());
   finally
  conn.Close();
}
```

Save the file as EDBConnection-Sample.cs and compile it with the following command:

csc /r:EnterpriseDB.EDBClient.dll /out:Console.exe EDBConnection-Sample.cs

Compiling the sample should generate a Console.exe file; you can execute the sample code by entering Console.exe. When executed, the console should verify that the:

Connection Opened Successfully

Example - Opening a Database Connection from a Windows Form Application

The following example demonstrates opening a database connection using a .NET WinForm application. To use the example, save the following code as WinForm-Example.cs in a directory that contains the library files.

```
using System;
using System.Windows.Forms;
using System.Drawing;
using EnterpriseDB.EDBClient;
namespace EDBTestClient
 class Win Conn
   static void Main(string∏ args)
   {
     Form frmMain = new Form();
     Button btnConn = new Button();
     btnConn.Location = new System.Drawing.Point(104, 64);
     btnConn.Name = "btnConn";
     btnConn.Text = "Open Connection";
      btnConn.Click += new System.EventHandler(btnConn Click);
     frmMain.Controls.Add(btnConn);
     frmMain.Text = "EnterpriseDB";
     Application.Run(frmMain);
   }
   private static void btnConn Click(object sender, System.EventArgs e)
      EDBConnection conn = null;
     try
     {
        string connectionString = "Server=10.90.1.29;port=5444;
        username=edb;password=edb;database=edb";
        conn = new EDBConnection(connectionString);
        conn.Open();
        MessageBox.Show("Connection Open");
```

```
}
catch(EDBException exp)
{
    MessageBox.Show(exp.ToString());
}
finally
{
    conn.Close();
}
}
```

Note that you must change the database connection string to point to the database that you want to connect to before compiling the file with the following command:

csc /r:EnterpriseDB.EDBClient.dll /out:WinForm.exe WinForm-Example.cs

This command should generate a WinForm.exe file within the same folder that the executable was compiled under. Invoking the executable will display:



7 Retrieving Database Records

You can use a SELECT statement to retrieve records from the database via a SELECT command. To execute a SELECT statement you must:

- Create and open a database connection.
- Create an EDBCommand object that represents the SELECT statement.
- Execute the command with the ExecuteReader() method of the

EDBCommand object returning a EDBDataReader

• Loop through the EDBDataReader displaying the results or binding the EDBDataReader to some control.

An EDBDataReader object represents a forward-only and read-only stream of database records, presented one record at a time. To view a subsequent record in the stream, you must call the Read() method of the EDBDataReader object.

The example that follows:

- 1. Imports the Advanced Server namespace: EnterpriseDB.EDBClient
- 2. Initializes an EDBCommand object with a SELECT statement.
- 3. Opens a connection to the database.
- 4. Executes the EDBCommand by calling the ExecuteReader method of the EDBCommand object.
- 1. Loops through the contents of the EDBDataReader object to display the records returned by the query within a WHILE loop.

The Read() method advances to the next record (if a record exists) and returns true if a record exists, or false to indicate that the EDBDataReader has reached the end of the result set.

```
<% @ Page Language="C#" %>
<% @Import Namespace="EnterpriseDB.EDBClient" %>
<% @Import Namespace="System.Data" %>
<% @Import Namespace="System.Configuration" %>
<% @Import Namespace="System.Configuration" %>
```

```
EDBDataReader drDept = cmdSelect.ExecuteReader();
   while(drDept.Read())
      Response.Write("Department Number: " + drDept["deptno"]);
      Response.Write("\tDepartment Name: " + drDept["dname"]);
      Response.Write("\tDepartment Location: " + drDept["loc"]);
      Response.Write("<br>");
   }
 }
 catch(Exception exp)
   Response.Write(exp.ToString());
 finally
   conn.Close();
 }
</script>
```

To exercise the sample code, save the code in your default web root directory in a file named:

```
selectEmployees.aspx
```

To invoke the program, open a web-browser, and browse to:

http://localhost/selectEmployees.aspx

Retrieving a Single Database Record

To retrieve a single result from a query, use the ExecuteScalar() method of the EDBCommand object. The ExecuteScalar() method returns the first value of the first column of the first row of the DataSet generated by the specified query.

```
<% @ Page Language="C#" %>
<% @Import Namespace="EnterpriseDB.EDBClient" %>
<% @Import Namespace="System.Data" %>
<% @Import Namespace="System.Configuration" %>
<script language="C#" runat="server">
private void Page Load(object sender, System.EventArgs e)
 string strConnectionString = ConfigurationManager.AppSettings
 ["DB CONN STRING"];
 EDBConnection conn = new EDBConnection(strConnectionString);
 try
 {
    conn.Open();
    EDBCommand cmd = new EDBCommand("SELECT MAX(sal) FROM
emp",conn);
    cmd.CommandType = CommandType.Text;
    int maxSal = Convert.ToInt32(cmd.ExecuteScalar());
    Response.Write("Emp Number: " + maxSal);
 catch(Exception exp)
  Response.Write(exp.ToString());
 finally
  conn.Close();
 }
</script>
```

Save the sample code in a file in a web root directory named:

selectscalar.aspx

To invoke the sample code, open a web-browser, and browse to:

http://localhost/selectScalar.aspx

Please note that the sample includes an explicit conversion of the value returned by the ExecuteScalar() method. The ExecuteScalar() method returns an object; to view the object, you must convert it into an integer value by using the Convert.ToInt32 method.

8 Parameterized Queries

A parameterized query is a query with one or more parameter markers embedded in the SQL statement. Before executing a parameterized query, you must supply a value for each marker found in the text of the SQL statement.

Parameterized queries are useful when you don't know the complete text of a query at the time you write your code. For example, the value referenced in a WHERE clause may be calculated from user input.

As demonstrated in the following example, you must declare the data type of each parameter specified in the parameterized query by creating an EDBParameter object and adding that object to the command's parameter collection. Then, you must specify a value for each parameter by calling the parameter's Value() function.

The example demonstrates use of a parameterized query with an UPDATE statement that increases an employee salary:

```
<% @ Page Language="C#" Debug="true"%>
<% @Import Namespace="EnterpriseDB.EDBClient" %>
<% @Import Namespace="System.Data" %>
<% @Import Namespace="System.Configuration" %>

<script language="C#" runat="server" >

private void Page_Load(object sender, System.EventArgs e)
```

```
string strConnectionString = ConfigurationManager.AppSettings
 ["DB CONN STRING"];
 EDBConnection conn = new EDBConnection(strConnectionString);
 string updateQuery = "UPDATE emp SET sal = sal+500 where empno = :ID";
 try {
   conn.Open();
   EDBCommand cmdUpdate = new EDBCommand(updateQuery,conn);
   cmdUpdate.Parameters.Add
   (new EDBParameter(":ID", EDBTypes.EDBDbType.Integer));
   cmdUpdate.Parameters[0].Value = 7788;
   cmdUpdate.ExecuteNonQuery();
   Response.Write("Record Updated");
 }
 catch(Exception exp) {
   Response.Write(exp.ToString());
 finally {
   conn.Close();
}
</script>
```

Save the sample code in a file in a web root directory named:

updateSalary.aspx

To invoke the sample code, open a web-browser, and browse to:

http://localhost/updateSalary.aspx

9 Inserting Records in a Database

You can use the ExecuteNonQuery() method of EDBCommand to add records to a database stored on an Advanced Server host with an INSERT command.

In the example that follows, the INSERT command is stored in the variable cmd. The values prefixed with a colon (:) are placeholders for EDBParameters that are instantiated, assigned values, and then added to the INSERT command's parameter collection in the statements that follow. The INSERT command is executed by the ExecuteNonQuery() method of the cmdInsert object.

The example adds a new employee to the emp table:

```
<% @ Page Language="C#" Debug="true"%>
<% @Import Namespace="EnterpriseDB.EDBClient" %>
<% @Import Namespace="System.Data" %>
<% @Import Namespace="System.Configuration" %>
<script language="C#" runat="server" >
private void Page Load(object sender, System.EventArgs e)
 string strConnectionString = ConfigurationManager.AppSettings
 ["DB CONN STRING"];
 EDBConnection conn = new EDBConnection(strConnectionString);
 try
  conn.Open();
  string cmd = "INSERT INTO emp(empno,ename) VALUES(:EmpNo,
:EName)";
  EDBCommand cmdInsert = new EDBCommand(cmd,conn);
  cmdInsert.Parameters.Add(new EDBParameter(":EmpNo",
```

```
EDBTypes.EDBDbType.Integer));
  cmdInsert.Parameters[0].Value = 1234;
  cmdInsert.Parameters.Add(new EDBParameter(":EName",
   EDBTypes.EDBDbType.Text));
  cmdInsert.Parameters[1].Value = "Lola";
  cmdInsert.ExecuteNonQuery();
  Response.Write("Record inserted successfully");
 }
 catch(Exception exp)
  {
   Response.Write(exp.ToString());
 finally
   conn.Close();
}
</script>
```

Save the sample code in a file in a web root directory named:

```
insertEmployee.aspx
```

To invoke the sample code, open a web-browser, and browse to:

http://localhost/insertEmployee.aspx

10 Deleting Records in a Database

You can use the ExecuteNonQuery() method of EDBCommand to delete

records from a database stored on an Advanced Server host with a DELETE statement.

In the example that follows, the <code>DELETE</code> command is stored in the variable <code>strDeleteQuery</code>. The code passes the employee number to the <code>Delete</code> command (specified by: <code>EmpNo</code>). The command is then executed using the <code>ExecuteNonQuery()</code> method. The following example deletes the employee inserted in the previous example:

```
<% @ Page Language="C#" Debug="true"%>
<% @Import Namespace="EnterpriseDB.EDBClient" %>
<% @Import Namespace="System.Data" %>
<% @Import Namespace="System.Configuration" %>
<script language="C#" runat="server" >
private void Page Load(object sender, System.EventArgs e)
 string strConnectionString = ConfigurationManager.AppSettings
 ["DB CONN STRING"];
 EDBConnection conn = new EDBConnection(strConnectionString);
 string strDeleteQuery = "DELETE FROM emp WHERE empno = :ID";
 try
   conn.Open();
   EDBCommand deleteCommand = new
EDBCommand(strDeleteQuery,conn);
   deleteCommand.Parameters.Add
   (new EDBParameter(":ID", EDBTypes.EDBDbType.Integer));
   deleteCommand.Parameters[0].Value = 1234;
   deleteCommand.ExecuteNonQuery();
   Response.Write("Record Deleted");
```

```
}
catch(Exception exp)
{
    Response.Write(exp.ToString());
}
finally
{
    conn.Close();
}
}
```

Save the sample code in a file in a web root directory named:

```
deleteEmployee.aspx
```

To invoke the sample code, open a web-browser, and browse to:

http://localhost/deleteEmployee.aspx

11 Using SPL Stored Procedures in your .NET Application

You can include SQL statements in an application in two ways:

- By adding the SQL statements directly in the .NET application code.
- By packaging the SQL statements in a stored procedure, and executing the stored procedure from the .NET application.

In some cases, a stored procedure can provide advantages over embedded SQL statements. Stored procedures support complex conditional and looping constructs that are difficult to duplicate with SQL statements embedded directly in an application.

You can also see a significant improvement in performance by using stored procedures; a stored procedure only needs to be parsed, compiled and optimized once on the server side, while a SQL statement that is included in an application may be parsed, compiled and optimized each time it is executed from a .NET application.

To use a stored procedure in your .NET application you must:

- 1. Create an SPL stored procedure on the Advanced Server host.
- 2. Import the EnterpriseDB.EDBClient namespace.
- 3. Pass the name of the stored procedure to the instance of the EDBCommand.
- 4. Change the EDBCommand.CommandType to CommandType.StoredProcedure.
- 5. Prepare() the command.
- 6. Execute the command.

Example - Executing a Stored Procedure without Parameters

Our sample procedure prints the name of department 10; the procedure takes no parameters, and returns no parameters. To create the sample procedure, invoke EDB-PSQL and connect to the Advanced Server host database. Enter the following SPL code at the command line:

```
CREATE OR REPLACE PROCEDURE list_dept10
IS

v_deptname VARCHAR2(30);
BEGIN

DBMS_OUTPUT.PUT_LINE('Dept No: 10');
SELECT dname INTO v_deptname FROM dept WHERE deptno = 10;
DBMS_OUTPUT.PUT_LINE('Dept Name: ' || v_deptname);
END;
```

When Advanced Server has validated the stored procedure it will echo CREATE PROCEDURE.

Using the EDBCommand Object to Execute a Stored Procedure

The CommandType property of the EDBCommand object is used to indicate the type of command being executed. The CommandType property is set to one of three possible CommandType enumeration values:

- Use the default Text value when passing a SQL string for execution.
- Use the StoredProcedure value, passing the name of a stored procedure for execution.
- Use the TableDirect value when passing a table name. This value passes back all records in the specified table.

The CommandText property must contain a SQL string, stored procedure name, or table name depending on the value of the CommandType property.

The following example executes the stored procedure:

```
<% @ Page Language="C#" Debug="true"%>
<% @Import Namespace="EnterpriseDB.EDBClient" %>
<% @Import Namespace="System.Data" %>
<% @Import Namespace="System.Configuration" %>
<script language="C#" runat="server" >
private void Page Load(object sender, System.EventArgs e)
 string strConnectionString = ConfigurationManager.AppSettings
 ["DB CONN STRING"];
 EDBConnection conn = new EDBConnection(strConnectionString);
 try
 {
   conn.Open();
   EDBCommand cmdStoredProc = new EDBCommand("list_dept10",conn);
   cmdStoredProc.CommandType = CommandType.StoredProcedure;
   cmdStoredProc.Prepare();
   cmdStoredProc.ExecuteNonQuery();
```

```
Response.Write("Stored Procedure Executed Successfully");

} catch(Exception exp)
{
   Response.Write(exp.ToString());
} finally
{
   conn.Close();
}
}
</script>
```

Save the sample code in a file in a web root directory named:

```
storedProc.aspx
```

To invoke the sample code, open a web-browser, and browse to:

http://localhost/storedProc.aspx

Example - Executing a Stored Procedure with IN Parameters

The following example demonstrates calling a stored procedure that includes IN parameters. To create the sample procedure, invoke EDB-PSQL and connect to the Advanced Server host database. Enter the following SPL code at the command line:

```
CREATE OR REPLACE PROCEDURE

EMP_INSERT
(
    pENAME IN VARCHAR,
    pJOB IN VARCHAR,
    pSAL IN FLOAT4,
    pCOMM IN FLOAT4,
    pDEPTNO IN INTEGER,
```

```
pMgr IN INTEGER
)
AS
DECLARE
CURSOR TESTCUR IS SELECT MAX(EMPNO) FROM EMP;
MAX_EMPNO INTEGER := 10;
BEGIN

OPEN TESTCUR;
FETCH TESTCUR INTO MAX_EMPNO;
INSERT INTO EMP(EMPNO,ENAME,JOB,SAL,COMM,DEPTNO,MGR)
VALUES(MAX_EMPNO+1,pENAME,pJOB,pSAL,pCOMM,pDEPTNO,pMgr);
CLOSE testcur;
END;
```

When Advanced Server has validated the stored procedure it wEDBTypes.EDBDbType.Floatill echo CREATE PROCEDURE.

Passing Input Values to a Stored Procedure

Calling a stored procedure that contains parameters is very similar to executing a stored procedure without parameters. The major difference is that when calling a parameterized stored procedure you must use the EDBParameter collection of the EDBCommand object. When the EDBParameter is added to the EDBCommand collection, properties such as ParameterName, DbType, Direction, Size, and Value are set.

The following example demonstrates the process of executing a parameterized stored procedure from a C#.

```
<% @ Page Language="C#" Debug="true"%>
<% @Import Namespace="EnterpriseDB.EDBClient" %>
<% @Import Namespace="System.Data" %>
<% @Import Namespace="System.Configuration" %>
<**script language="C#" runat="server" >

private void Page_Load(object sender, System.EventArgs e)
{
    string strConnectionString = ConfigurationManager.AppSettings
```

```
["DB CONN STRING"];
EDBConnection conn = new EDBConnection(strConnectionString);
string empName = "EDB";
string empJob = "Manager";
double salary = 1000;
double commission = 0.0;
             = 20;
int deptno
    manager = 7839;
int
try
{
  conn.Open();
  EDBCommand cmdStoredProc = new EDBCommand
  ("emp_insert(:EmpName,:Job,:Salary,:Commission,:DeptNo,
  :Manager)",conn);
  cmdStoredProc.CommandType = CommandType.StoredProcedure;
  cmdStoredProc.Parameters.Add(new EDBParameter
  ("EmpName", EDBTypes.EDBDbType.Varchar));
  cmdStoredProc.Parameters[0].Value = empName;
  cmdStoredProc.Parameters.Add(new EDBParameter
  ("Job", EDBTypes.EDBDbType.Varchar));
  cmdStoredProc.Parameters[1].Value = empJob;
  cmdStoredProc.Parameters.Add(new EDBParameter
  ("Salary", EDBTypes.EDBDbType.Real));
  cmdStoredProc.Parameters[2].Value = salary;
  cmdStoredProc.Parameters.Add(new EDBParameter
  ("Commission", EDBTypes.EDBDbType.Real));
  cmdStoredProc.Parameters[3].Value = commission;
  cmdStoredProc.Parameters.Add(new EDBParameter
  ("DeptNo", EDBTypes.EDBDbType.Integer));
  cmdStoredProc.Parameters[4].Value = deptno;
```

```
cmdStoredProc.Parameters.Add
   (new EDBParameter("Manager", EDBTypes.EDBDbType.Integer));
   cmdStoredProc.Parameters[5].Value = manager;
   cmdStoredProc.Prepare();
   cmdStoredProc.ExecuteNonQuery();
   Response.Write("Following Information Inserted Successfully
   <br/>br>");
   string empInfo = "Employee Name: " + empName + "<br>";
   empInfo += "Job: " + empJob + "<br>";
   empInfo += "Salary: " + salary + "<br>";
   empInfo += "Commission: " + commission + "<br>";
   empInfo += "Manager: " + manager + "<br>";
   Response.Write(empInfo);
 }
 catch(Exception exp)
{
   Response.Write(exp.ToString());
 finally
   conn.Close();
}
</script>
</script>
```

Save the sample code in a file in a web root directory named:

storedProcInParam.aspx

To invoke the sample code, open a web-browser, and browse to:

http://localhost/storedProcInParam.aspx

In the example, the body of the Page_Load method declares and instantiates an EDBConnection object. The sample then creates an EDBCommand object with the properties needed to execute the stored procedure.

The example then uses the Add method of the EDBCommand Parameter collection to add six input parameters.

EDBCommand cmdStoredProc = new EDBCommand
("emp_insert(:EmpName,:Job,:Salary,:Commission,:DeptNo,:Manager)",conn);
cmdStoredProc.CommandType = CommandType.StoredProcedure;

It assigns a value to each parameter before passing them to the EMP_INSERT stored procedure

The Prepare() method prepares the statement before calling the ExecuteNonQuery() method.

The ExecuteNonQuery method of the EDBCommand object executes the stored procedure. After the stored procedure has executed, a test record is inserted into the emp table and the values inserted are displayed on the webpage.

Example - Executing a Stored Procedure with IN, OUT, and INOUT Parameters

The previous example demonstrated how to pass IN parameters to a stored procedure; the following examples demonstrate how to pass IN values and return OUT values from a stored procedure.

Creating the Stored Procedure

The following stored procedure passes the department number, and returns the corresponding location and department name. To create the sample procedure, open the EDB-PSQL command line, and connect to the Advanced Server host database. Enter the following SPL code at the command line:

CREATE OR REPLACE PROCEDURE DEPT_SELECT

```
(
pDEPTNO IN INTEGER,
pDNAME OUT VARCHAR,
pLOC OUT VARCHAR
)
AS
DECLARE
CURSOR TESTCUR IS SELECT DNAME,LOC FROM DEPT;
REC RECORD;
BEGIN

OPEN TESTCUR;
FETCH TESTCUR INTO REC;

pDNAME := REC.DNAME;
pLOC := REC.LOC;

CLOSE testcur;
END;
```

When Advanced Server has validated the stored procedure it will echo CREATE PROCEDURE.

Receiving Output Values from a Stored Procedure

When retrieving values from OUT parameters you must explicitly specify the direction of out parameters as Output. You can retrieve the values from Output parameters in two ways:

- Call the ExecuteReader method of the EDBCommand and explicitly loop through the returned EDBDataReader, searching for the values of OUT parameters.
- Call the ExecuteNonQuery method of EDBCommand and explicitly get the value of a declared Output parameter by calling that EDBParameter value property.

In each method, you must declare each parameter, indicating the direction of the parameter (ParameterDirection.Input, ParameterDirection.Output or ParameterDirection.InputOutput). Before invoking the procedure, you must provide a value for each IN and INOUT parameter. After the procedure returns, you may retrieve the OUT and INOUT parameter values from the

command.Parameters[] array.

The following code listing demonstrates using the **ExecuteReader** method to retrieve a result set:

```
<% @ Page Language="C#" Debug="true"%>
<% @Import Namespace="EnterpriseDB.EDBClient" %>
<% @Import Namespace="System.Data" %>
<% @Import Namespace="System.Configuration" %>
<script language="C#" runat="server" >
private void Page_Load(object sender, System.EventArgs e)
 string strConnectionString =
    ConfigurationManager.AppSettings["DB CONN STRING"];
 EDBConnection conn = new EDBConnection(strConnectionString);
 try
  conn.Open();
  EDBCommand command = new EDBCommand("DEPT SELECT
     (:pDEPTNO,:pDNAME,:pLOC)", conn);
  command.CommandType = CommandType.StoredProcedure;
  command.Parameters.Add(new EDBParameter("pDEPTNO",
     EDBTypes.EDBDbType.Integer,10,"pDEPTNO",
     ParameterDirection.Input,false ,2,2,
     System.Data.DataRowVersion.Current,1));
  command.Parameters.Add(new EDBParameter("pDNAME",
     EDBTypes.EDBDbType.Varchar,10,"pDNAME",
     Parameter Direction. Output, false ,2,2,
     System.Data.DataRowVersion.Current,1));
  command.Parameters.Add(new EDBParameter("pLOC",
     EDBTypes.EDBDbType.Varchar,10,"pLOC",
     Parameter Direction. Output, false ,2,2,
```

```
System.Data.DataRowVersion.Current,1));
  command.Prepare();
  command.Parameters[0].Value = 10;
  EDBDataReader result = command.ExecuteReader();
  int fc = result.FieldCount;
  for (int i = 0; i < 3; i++)
    Console.WriteLine("RESULT[" + i + "]=" +
Convert.ToString(command.Parameters[i].Value));
    Console.WriteLine("\n");
  }
 }
 catch(EDBException exp)
  Response.Write(exp.ToString());
 finally
  conn.Close();
</script>
```

The following code listing demonstrates using the ExecuteNonQuery method to retrieve a result set:

```
<% @ Page Language="C#" Debug="true"%>
<% @Import Namespace="EnterpriseDB.EDBClient" %>
<% @Import Namespace="System.Data" %>
<% @Import Namespace="System.Configuration" %>
<script language="C#" runat="server" >
```

```
private void Page Load(object sender, System.EventArgs e)
 string strConnectionString = ConfigurationManager.AppSettings
 ["DB CONN STRING"];
 EDBConnection conn = new EDBConnection(strConnectionString);
 try
  conn.Open();
  EDBCommand command = new EDBCommand("DEPT_SELECT
   (:pDEPTNO,:pDNAME,:pLOC)", conn);
  command.CommandType = CommandType.StoredProcedure;
  command.Parameters.Add(new EDBParameter("pDEPTNO",
   EDBTypes.EDBDbType.Integer,10,"pDEPTNO",
   ParameterDirection.Input,false ,2,2,
   System.Data.DataRowVersion.Current,1));
  command.Parameters.Add(new EDBParameter("pDNAME",
   EDBTypes.EDBDbType.Varchar,10,"pDNAME",
   Parameter Direction. Output, false ,2,2,
   System.Data.DataRowVersion.Current,1));
  command.Parameters.Add(new EDBParameter("pLOC",
   EDBTypes.EDBDbType.Varchar,10,"pLOC",
   Parameter Direction. Output, false ,2,2,
   System.Data.DataRowVersion.Current,1));
  command.Prepare();
  command.Parameters[0].Value = 10;
  command.ExecuteNonQuery();
  Response.Write(command.Parameters["pDNAME"].Value.ToString());
  Response.Write(command.Parameters["pLOC"].Value.ToString());
 }
 catch(EDBException exp)
```

```
{
   Response.Write(exp.ToString());
}
finally
{
   conn.Close();
}
}
</script>
```

12 Using Advanced Queueing

EDB Postgres Advanced Server Advanced Queueing provides message queueing and message processing for the Advanced Server database. User-defined messages are stored in a queue; a collection of queues is stored in a queue table. You should first create a queue table before creating a queue that is dependent on it.

On the server side, procedures in the DBMS_AQADM package create and manage message queues and queue tables. Use the DBMS_AQ package to add or remove messages from a queue, or register or unregister a PL/SQL callback procedure. For more information about DBMS_AQADM, click here.

On the client side, application uses EDB.NET driver to enqueue/dequeue message.

Enqueueing or Dequeueing a Message

For more information about using Advanced Servers Advanced Queueing functionality, see the Database Compatibility for Oracle Developers Built-in Package Guide.

Server-Side Setup

To use Advanced Queueing functionality on your .NET application, you must first create a user defined type, queue table, and queue, and then start the queue on the database server. Invoke EDB-PSQL and connect to the Advanced Server host database. Use the following SPL commands at the command line:

Creating a User-defined Type

To specify a RAW data type, you should create a user-defined type. The following example demonstrates creating a user-defined type named as myxml.

CREATE TYPE myxml AS (value XML);

Creating the Queue Table

A queue table can hold multiple queues with the same payload type. The following example demonstrates creating a table named MSG QUEUE TABLE.

```
EXEC DBMS_AQADM.CREATE_QUEUE_TABLE
  (queue_table => 'MSG_QUEUE_TABLE',
    queue_payload_type => 'myxml',
    comment => 'Message queue table');
END;
```

Creating the Queue

The following example demonstrates creating a queue named MSG_QUEUE within the table MSG_QUEUE_TABLE.

```
BEGIN

DBMS_AQADM.CREATE_QUEUE ( queue_name => 'MSG_QUEUE',
queue_table => 'MSG_QUEUE_TABLE', comment => 'This queue contains
pending messages.');

END;
```

Starting the Queue

Once the queue is created, invoke the following SPL code at the command line to start a queue in the EDB database.

```
BEGIN

DBMS_AQADM.START_QUEUE

(queue_name => 'MSG_QUEUE');

END;
```

Client-side Example

Once you have created a user-defined type, followed by queue table and queue, start the queue. Then, you can enqueue or dequeue a message using EDB .Net drivers.

Enqueue a message:

To enqueue a message on your .NET application, you must:

- 1. Import the EnterpriseDB.EDBClient namespace.
- 2. Pass the name of the queue and create the instance of the EDBAQQueue.
- 3. Create the enqueue message and define a payload.
- 4. Call the queue. Enqueue method.

The following code listing demonstrates using the queue. Enqueue method:

Note

The following code creates the message and serializes it. This is just an example code and is not going to compile if copied as it is. It is the responsibility of the user to serialize the message as XML.

```
using EnterpriseDB.EDBClient;
using System;
using System.Collections.Generic;
using System.Linq;
using System.Text;
using System.Threading.Tasks;

namespace AQXml
{
    class MyXML
    {
```

```
public string value { get; set; }
  }
  class Program
  {
     static void Main(string∏ args)
       int messagesToSend = 1;
       if (args.Length > 0 && !string.IsNullOrEmpty(args[0]))
       {
          messagesToSend = int.Parse(args[0]);
       for (int i = 0; i < 5; i++)
          EnqueMsg("test message: " + i);
     }
   private static EDBConnection GetConnection()
       string connectionString =
"Server=127.0.0.1;Host=127.0.0.1;Port=5444;User
Id=enterprisedb;Password=test;Database=edb;Timeout=999";
       EDBConnection connection = new EDBConnection(connectionString);
       connection.Open();
       return connection;
     }
     private static string ByteArrayToString(byte[] byteArray)
       // Sanity check if it's null so we don't incur overhead of an exception
       if (byteArray == null)
          return string.Empty;
       try
       {
          StringBuilder hex = new StringBuilder(byteArray.Length * 2);
         foreach (byte b in byteArray)
```

```
{
           hex.AppendFormat("{0:x2}", b);
         }
         return hex.ToString().ToUpper();
      }
      catch
      {
         return string.Empty;
    }
    private static bool EnqueMsg(string msg)
    {
      EDBConnection con = GetConnection();
      using (EDBAQQueue queue = new EDBAQQueue("MSG QUEUE",
con))
      {
         queue.MessageType = EDBAQMessageType.Xml;
         EDBTransaction txn = queue.Connection.BeginTransaction();
         QueuedEntities.Message queuedMessage = new
QueuedEntities.Message() { MessageText = msg };
         try
           string rootElementName = queuedMessage.GetType().Name;
           if (rootElementName.IndexOf(".") != -1)
           {
             rootElementName = rootElementName.Split('.').Last();
           }
           string xml = new
Utils.XmlFragmentSerializer<QueuedEntities.Message>
().Serialize(queuedMessage);
           EDBAQMessage queMsg = new EDBAQMessage();
           queMsg.Payload = new MyXML { value = xml };
           queue.MessageType = EDBAQMessageType.Udt;
           queue.UdtTypeName = "myxml";
           queue.Enqueue(queMsg);
```

```
var messageId = ByteArrayToString((byte[])queMsg.MessageId);
       Console.WriteLine("MessageID: " + messageId);
       txn.Commit();
       queMsg = null;
       xml = null;
       rootElementName = null;
       return true;
    }
    catch (Exception ex)
    {
       txn?.Rollback();
       Console.WriteLine("Failed to enqueue message.");
       Console.WriteLine(ex.ToString());
       return false:
    }
    finally
       queue?.Connection?.Dispose();
}
```

Dequeueing a message

To dequeue a message on your .NET application, you must:

- 1. Import the EnterpriseDB.EDBClient namespace.
- 2. Pass the name of the gueue and create the instance of the EDBAQQueue.
- 3. Call the queue.Dequeue method.

Note

The following code creates the message and serializes it. This is just an example code and is not going to compile if copied as it is. It is the responsibility of the user to serialize the message as XML.

```
using System;
```

```
using System.Collections.Generic;
using System.Ling;
using System.Text;
using System. Threading. Tasks;
using EnterpriseDB.EDBClient;
namespace DequeueXML
{
  class MyXML
  {
    public string value { get; set; }
  class Program
  {
    static void Main(string∏ args)
    {
       DequeMsg();
    }
    private static EDBConnection GetConnection()
     {
       string connectionString =
"Server=127.0.0.1;Host=127.0.0.1;Port=5444;User
Id=enterprisedb;Password=test;Database=edb;Timeout=999";
       EDBConnection connection = new EDBConnection(connectionString);
       connection.Open();
       return connection;
    }
    private static string ByteArrayToString(byte[] byteArray)
       // Sanity check if it's null so we don't incur overhead of an exception
       if (byteArray == null)
       {
         return string.Empty;
       try
```

```
StringBuilder hex = new StringBuilder(byteArray.Length * 2);
         foreach (byte b in byteArray)
           hex.AppendFormat("{0:x2}", b);
         }
         return hex.ToString().ToUpper();
      catch
         return string.Empty;
    }
    public static void DequeMsg(int waitTime = 10)
    {
       EDBConnection con = GetConnection();
      using (EDBAQQueue queueListen = new
EDBAQQueue("MSG QUEUE", con))
         queueListen.UdtTypeName = "myxml";
         queueListen.DequeueOptions.Navigation =
EDBAQNavigationMode.FIRST MESSAGE;
         queueListen.DequeueOptions.Visibility =
EDBAQVisibility.ON_COMMIT;
         queueListen.DequeueOptions.Wait = 1;
         EDBTransaction txn = null;
         while (1 == 1)
           if (queueListen.Connection.State ==
System.Data.ConnectionState.Closed)
              queueListen.Connection.Open();
           string messageId = "Unknown";
           try
```

```
// the listen function is a blocking function. It will Wait the
specified waitTime or until a
               // message is received.
               Console.WriteLine("Listening...");
               string v = queueListen.Listen(null, waitTime);
               // If we are waiting for a message and we specify a Wait time,
               // then if there are no more messages, we want to just bounce
out.
               if (waitTime > -1 \&\& v == null)
                 Console.WriteLine("No message received during Wait
period.");
                 Console.WriteLine();
                 continue;
               }
               // once we're here that means a message has been detected in
the gueue. Let's deal with it.
               txn = queueListen.Connection.BeginTransaction();
               Console.WriteLine("Attempting to dequeue message...");
               // dequeue the message
               EDBAQMessage deqMsg;
               try
                 deqMsg = queueListen.Dequeue();
               catch (Exception ex)
                 if (ex.Message.Contains("ORA-25228"))
                 {
                    Console.WriteLine("Message was not there. Another
process must have picked it up.");
                    Console.WriteLine();
                    txn.Rollback();
                    continue;
                 }
                 else
```

```
{
                   throw;
              }
              messageId = ByteArrayToString((byte[])deqMsg.MessageId);
              if (degMsg != null)
              {
                Console.WriteLine("Processing received message...");
                // process the message payload
                MyXML obj = new MyXML();
                queueListen.Map<MyXML>(deqMsg.Payload, obj);
                QueuedEntities.Message msg = new
Utils.XmlFragmentSerializer<QueuedEntities.Message>
().Deserialize(obj.value);
                Console.WriteLine("Received Message:");
                Console.WriteLine("MessageID: " + messageId);
                Console.WriteLine("Message: " + msg.MessageText);
                Console.WriteLine("Enqueue Time" +
queueListen.MessageProperties.EnqueueTime);
                txn.Commit();
                Console.WriteLine("Finished processing message");
                Console.WriteLine();
              }
              else
                Console.WriteLine("Message was not dequeued.");
           catch (Exception ex)
           {
              Console.WriteLine("Failed To dequeue or process the
dequeued message.");
              Console.WriteLine(ex.ToString());
```

```
Console.WriteLine();
    if (txn != null)
    {
        txn.Rollback();
        if (txn != null)
        {
            txn.Dispose();
        }
     }
}
```

EDBAQ Classes

The following EDBAQ classes are used in this application:

EDBAQDequeueMode

The EDBAQDequeueMode class lists all the dequeuer modes available.

Value	Description
Browse	Read the message without locking.
Locked	Reads and gets a write lock on the message.
Remove	Deletes the message after reading. This is the default value.
Remove_NoData	Confirms receipt of the message.

EDBAQDequeueOptions

The EDBAQDequeueOptions class lists the options available when dequeuing a message.

Property	Description
ConsumerName	The name of the consumer for which to dequeue the message.
DequeueMode	This is set from EDBAQDequeueMode. It represents the locking behavior linked with the dequeue option.
Navigation	This is set from EDBAQNavigationMode. It represents the position of the message that will be fetched.
Visibility	This is set from EDBAQVisibility. It represents whether the new message is dequeued or not as part of the current transaction.
Wait	The wait time for a message as per the search criteria.
Msgid	The message identifier.
Correlation	The correlation identifier.
DeqCondition	The dequeuer condition. It is a Boolean expression.
Transformation	The transformation that will be applied before dequeuing the message.
DeliveryMode	The delivery mode of the dequeued message.

EDBAQEnqueueOptions

The EDBAQEnqueueOptions class lists the options available when enqueuing a message.

Property	Description
Visibility	This is set from EDBAQVisibility. It represents whether the new message is enqueued or not as part of the current transaction.
RelativeMsgid	The relative message identifier.
SequenceDeviation	The sequence when the message should be dequeued.
Transformation	The transformation that will be applied before enqueuing the message.
DeliveryMode	The delivery mode of the enqueued message.

EDBAQMessage

The EDBAQMessage class lists a message to be enqueued/dequeued.

Property	Description
Payload	The actual message to be queued.
Messageld	The ID of the queued message.

EDBAQMessageProperties

The EDBAQMessageProperties lists the message properties available.

Property	Description
Priority	The priority of the message.
Delay	The duration post which the message is available for dequeuing. This is specified in seconds.
Expiration	The duration for which the message is available for dequeuing. This is specified in seconds.
Correlation	The correlation identifier.
Attempts	The number of attempts taken to dequeue the message.
RecipientList	The receipients list that overthrows the default queue subscribers.
ExceptionQueue	The name of the queue where the unprocessed messages should be moved.
EnqueueTime	The time when the message was enqueued.
State	The state of the message while dequeue.
OriginalMsgid	The message identifier in the last queue.
TransactionGroup	The transaction group for the dequeued messages.
DeliveryMode	The delivery mode of the dequeued message.

EDBAQMessageState

The EDBAQMessageState class represents the state of the message during dequeue.

Value	Description
Expired	The message is moved to the exception queue.
Processed	The message is processed and kept.
Ready	The message is ready to be processed.

Value	Description
Waiting	The message is in waiting state. The delay is not reached.

EDBAQMessageType

The EDBAQMessageType class represents the types for payload.

Value	Description
Raw	The raw message type. Note: Currently, this payload type is not supported.
UDT	The user defined type message.
XML	The XML type message. Note: Currently, this payload type is not supported.

EDBAQNavigationMode

The EDBAQNavigationMode class represents the different types of navigation modes available.

Value	Description
First_Message	Returns the first available message that matches the search terms.
Next_Message	Returns the next available message that matches the search items.
Next_Transaction	Returns the first message of next transaction group.

EDBAQQueue

The EDBAQQueue class represents a SQL statement to execute DMBS_AQ functionality on a PostgreSQL database.

Property	Description

Property	Description
Connection	The connection to be used.
Name	The name of the queue.
MessageType	The message type that is enqueued/dequeued from this queue. For example EDBAQMessageType.Udt.
UdtTypeName	The user defined type name of the message type.
EnqueueOptions	The enqueue options to be used.
DequeuOptions	The dequeue options to be used.
MessageProperties	The message properties to be used.

EDBAQVisibility

The EDBAQVisibility class represents the visibility options available.

Value	Description
Immediate	The enqueue/dequeue is not part of the ongoing transaction.
On_Commit	The enqueue/dequeue is part of the current transaction.

Note

- To review the default options for the above parameters, click here.
- EDB Advanced Queueing functionality uses user-defined types for calling enqueue/dequeue operations. Server Compatibility Mode=NoTypeLoading cannot be used with Advanced Queueing because NoTypeLoading will not load any user-defined types.

Using a Ref Cursor in a .NET Application

A ref cursor is a cursor variable that contains a pointer to a query result set. The result set is determined by the execution of the OPEN FOR statement using the cursor variable. A cursor variable is not tied to a particular query like a static cursor. The same cursor variable may be opened a number of times with the OPEN FOR statement containing different queries and each time, a new

result set will be created for that query and made available via the cursor variable. There are two ways to declare a cursor variable:

- Use the SYS_REFCURSOR built-in data type to declare a weakly-typed ref cursor.
- Define a strongly-typed ref cursor that declares a variable of that type.

SYS_REFCURSOR is a ref cursor type that allows any result set to be associated with it. This is known as a weakly-typed ref cursor. The following example is a declaration of a weakly-typed ref cursor:

```
name SYS_REFCURSOR;
```

Following is an example of a strongly-typed ref cursor:

```
TYPE < cursor type_name > IS REF CURSOR RETURN emp%ROWTYPE;
```

Creating the Stored Procedure

The following sample code creates a stored procedure called refcur_inout_callee. To create the sample procedure, invoke EDB-PSQL and connect to the Advanced Server host database. Enter the following SPL code at the command line:

```
CREATE OR REPLACE PROCEDURE

refcur_inout_callee(v_refcur IN OUT SYS_REFCURSOR)

IS

BEGIN

OPEN v_refcur FOR SELECT ename FROM emp;

END;
```

To use the above defined procedure from .NET code, you must specify the data type of the ref cursor being passed as an IN parameter, as shown in the above script.

The following C# code uses the stored procedure to retrieve employee names from the emp table:

```
using System;
using System.Data;
using EnterpriseDB.EDBClient;
```

```
using System.Configuration;
namespace EDBRefCursor
  class EmpRefcursor
    [STAThread]
    static void Main(string∏ args)
    {
      string strConnectionString =
      ConfigurationManager.AppSettings["DB CONN STRING"];
      EDBConnection conn = new EDBConnection(strConnectionString);
      conn.Open();
      try
      {
         EDBTransaction tran = conn.BeginTransaction();
         EDBCommand command = new
EDBCommand("refcur inout callee",
           conn);
         command.CommandType = CommandType.StoredProcedure;
         command.Transaction = tran;
         command.Parameters.Add(new EDBParameter("refCursor",
           EDBTypes.EDBDbType.Refcursor, 10, "refCursor",
         ParameterDirection.InputOutput, false, 2, 2,
           System.Data.DataRowVersion.Current, null));
         command.Prepare();
         command.Parameters[0].Value = null;
         command.ExecuteNonQuery();
         String cursorName = command.Parameters[0].Value.ToString();
         command.CommandText = "fetch all in \"" + cursorName + "\"";
         command.CommandType = CommandType.Text;
         EDBDataReader reader =
           command.ExecuteReader(CommandBehavior.SequentialAccess);
         int fc = reader.FieldCount;
         while (reader.Read())
```

```
{
    for (int i = 0; i < fc; i++)
    {
        Console.WriteLine(reader.GetString(i));
    }
    reader.Close();
    tran.Commit();
}
    catch (Exception ex)
    {
        Console.WriteLine(ex.Message.ToString());
    }
}</pre>
```

The following .NET code snippet displays the result on the console:

```
for(int i = 0;i < fc; i++)
{
    Console.WriteLine(reader.GetString(i));
}</pre>
```

Please note that you must bind the EDBDbType.RefCursor type in EDBParameter() if you are using a ref cursor parameter.

14 Using Plugins

EDB .Net driver plugins are introduced to support the enhanced capabilities for different data types, which are otherwise not available in .Net. The different plugins available support:

- GeoJSON
- Json.NET

- Legacy PostGIS
- NetTopologySuite
- NodaTime
- Rawpostgis

The plugins support the use of spatial, data/time and Json types. The following sections detail the supported frameworks and data provider installation path for these plugins.

GeoJSON

If you are using the GeoJSON plugin on .NET Framework 4.6.1, the data provider installation path is:

C:\Program Files\edb\dotnet\plugins\GeoJSON\net461

The following shared library files are required:

EnterpriseDB.EDBClient.GeoJSON.dll GeoJSON.Net.dll Newtonsoft.Json.dll

If you are using the GeoJSON plugin on .NET Framework 4.7.2, the data provider installation path is:

C:\Program Files\edb\dotnet\plugins\GeoJSON\net472

The following shared library files are required:

EnterpriseDB.EDBClient.GeoJSON.dll GeoJSON.Net.dll Newtonsoft.Json.dll

If you are using the GeoJSON plugin on .NET Framework 4.8, the data provider installation path is:

C:\Program Files\edb\dotnet\plugins\GeoJSON\net48

The following shared library files are required:

EnterpriseDB.EDBClient.GeoJSON.dll GeoJSON.Net.dll

Newtonsoft.Json.dll

If you are using the GeoJSON plugin on .NET Standard 2.0, the data provider installation path is:

C:\Program Files\edb\dotnet\plugins\GeoJSON\netstandard2.0

The following shared library files are required:

EnterpriseDB.EDBClient.GeoJSON.dll

For detailed information about using the GeoJSON plugin, see the Npgsql documentation.

Json.NET

If you are using the Json.NET plugin on .NET Framework 4.6.1, the data provider installation path is:

C:\Program Files\edb\dotnet\plugins\Json.NET\net461

The following shared library files are required:

EnterpriseDB.EDBClient.Json.NET.dll Newtonsoft.Json.dll

If you are using the Json.NET plugin on .NET Framework 4.7.2, the data provider installation path is:

C:\Program Files\edb\dotnet\plugins\Json.NET\net472

The following shared library files are required:

EnterpriseDB.EDBClient.Json.NET.dll Newtonsoft.Json.dll

If you are using the Json.NET plugin on .NET Framework 4.8, the data provider installation path is:

C:\Program Files\edb\dotnet\plugins\Json.NET\net48

The following shared library files are required:

EnterpriseDB.EDBClient.Json.NET.dll Newtonsoft.Json.dll

If you are using the Json.NET plugin on .NET Standard 2.0, the data provider installation path is:

C:\Program Files\edb\dotnet\plugins\Json.NET\netstandard2.0

The following shared library files are required:

EnterpriseDB.EDBClient.Json.NET.dll

For detailed information about using the Json.NET plugin, see the Npgsql documentation.

LegacyPostGIS

If you are using the LegacyPostGIS plugin on .Net Framework 4.6.1, the data provider installation path is:

C:\Program Files\edb\dotnet\plugins\LegacyPostgis\net461

The following shared library files are required:

EnterpriseDB.EDBClient.LegacyPostgis.dll

If you are using the LegacyPostGIS plugin on .Net Framework 4.7.2, the data provider installation path is:

C:\Program Files\edb\dotnet\plugins\LegacyPostgis\net472

The following shared library files are required:

EnterpriseDB.EDBClient.LegacyPostgis.dll

If you are using the LegacyPostGIS plugin on .Net Framework 4.8, the data provider installation path is:

C:\Program Files\edb\dotnet\plugins\LegacyPostgis\net48

The following shared library files are required:

EnterpriseDB.EDBClient.LegacyPostgis.dll

If you are using the LegacyPostGIS plugin on .Net Standard 2.0, the data provider installation path is:

C:\Program Files\edb\dotnet\plugins\LegacyPostgis\netstandard2.0

The following shared library files are required:

EnterpriseDB.EDBClient.LegacyPostgis.dll

For detailed information about using the LegacyPostGIS plugin, see the Npgsql documentation.

NetTopologySuite

If you are using the NetTopologySuite plugin on .Net Framework 4.6.1, the data provider installation path is:

C:\Program Files\edb\dotnet\plugins\NetTopologySuite\net461

The following shared library files are required:

EnterpriseDB.EDBClient.NetTopologySuite.dll NetTopologySuite.dll NetTopologySuite.IO.PostGis.dll

If you are using the NetTopologySuite plugin on .Net Framework 4.7.2, the data provider installation path is:

C:\Program Files\edb\dotnet\plugins\NetTopologySuite\net472

The following shared library files are required:

EnterpriseDB.EDBClient.NetTopologySuite.dll GeoAPI.dll NetTopologySuite.dll NetTopologySuite.IO.PostGis.dll

If you are using the NetTopologySuite plugin on .Net Framework 4.8, the data provider installation path is:

C:\Program Files\edb\dotnet\plugins\NetTopologySuite\net48

The following shared library files are required:

EnterpriseDB.EDBClient.NetTopologySuite.dll GeoAPI.dll NetTopologySuite.dll NetTopologySuite.IO.PostGis.dll

If you are using the NetTopologySuite plugin on .Net Standard 2.0, the data provider installation path is:

C:\Program Files\edb\dotnet\plugins\NetTopologySuite\netstandard2.0

The following shared library files are required:

EnterpriseDB.EDBClient.NetTopologySuite.dll

For detailed information about using the NetTopologySuite type plugin, see the Npgsql documentation.

NodaTime

If you are using the NodaTime plugin on .Net Framework 4.6.1, the data provider installation path is:

C:\Program Files\edb\dotnet\plugins\NodaTime\net461

The following shared library files are required:

EnterpriseDB.EDBClient.NodaTime.dll NodaTime.dll

If you are using the NodaTime plugin on .Net Framework 4.7.2, the data provider installation path is:

C:\Program Files\edb\dotnet\plugins\NodaTime\net472

The following shared library files are required:

EnterpriseDB.EDBClient.NodaTime.dll

NodaTime.dll

If you are using the NodaTime plugin on .Net Framework 4.8, the data provider installation path is:

C:\Program Files\edb\dotnet\plugins\NodaTime\net48

The following shared library files are required:

EnterpriseDB.EDBClient.NodaTime.dll NodaTime.dll

If you are using the NodaTime plugin on .Net Standard 2.0, the data provider installation path is:

C:\Program Files\edb\dotnet\plugins\NodaTime\netstandard2.0

The following shared library files are required:

EnterpriseDB.EDBClient.NodaTime.dll

For detailed information about using the NodaTime plugin, see the Npgsql documentation.

RawPostGIS

If you are using the RawPostGIS plugin on .Net Framework 4.6.1, the data provider installation path is:

C:\Program Files\edb\dotnet\plugins\RawPostgis\net461

The following shared library files are required:

EnterpriseDB.EDBClient.RawPostgis.dll

If you are using the RawPostGIS plugin on .Net Framework 4.7.2, the data provider installation path is:

C:\Program Files\edb\dotnet\plugins\RawPostgis\net472

The following shared library files are required:

EnterpriseDB.EDBClient.RawPostgis.dll

If you are using the RawPostGIS plugin on .Net Framework 4.8, the data provider installation path is:

C:\Program Files\edb\dotnet\plugins\RawPostgis\net48

The following shared library files are required:

EnterpriseDB.EDBClient.RawPostgis.dll

If you are using the RawPostGIS type plugin on .Net Standard 2.0, the data provider installation path is:

C:\Program\Files\edb\dotnet\plugins\RawPostGis\netstandard2.0

The following shared library files are required:

EnterpriseDB.EDBClient.RawPostgis.dll

For detailed information about using the RawPostGIS plugin, see the documentation.

15 Using Object Types in .NET

The SQL CREATE TYPE command is used to create a user-defined object type, which is stored in the Advanced Server database.

These user-defined types can then be referenced within SPL procedures, SPL functions, and .NET programs.

The basic object type is created with the CREATE TYPE AS OBJECT command along with optional usage of the CREATE TYPE BODY command.

An example that demonstrates using an object type is shown in the following section.

Using an Object Type

To use an object type, you must first create the object type in the Advanced Server database. Object type addr_object_type defines the attributes of an address:

```
CREATE OR REPLACE TYPE addr_object_type AS OBJECT
(
    street    VARCHAR2(30),
    city    VARCHAR2(20),
    state    CHAR(2),
    zip    NUMBER(5)
);
```

Object type emp_obj_typ defines the attributes of an employee. Note that one of these attributes is object type ADDR_OBJECT_TYPE as previously described. The object type body contains a method that displays the employee information:

```
CREATE OR REPLACE TYPE emp obj typ AS OBJECT
             NUMBER(4),
  empno
             VARCHAR2(20),
  ename
            ADDR OBJECT TYPE,
  addr
  MEMBER PROCEDURE display emp(SELF IN OUT emp obj typ)
);
CREATE OR REPLACE TYPE BODY emp obj typ AS
 MEMBER PROCEDURE display emp (SELF IN OUT emp obj typ)
 IS
 BEGIN
  DBMS_OUTPUT_LINE('Employee No : ' || SELF.empno);
  DBMS OUTPUT.PUT LINE('Name : ' | SELF.ename);
  DBMS OUTPUT.PUT LINE('Street : ' | SELF.addr.street);
  DBMS OUTPUT.PUT LINE('City/State/Zip: ' || SELF.addr.city || ', ' ||
   SELF.addr.state || ' ' || LPAD(SELF.addr.zip,5,'0'));
 END;
END;
```

The following listing is a complete .NET program that uses these user-defined object types:

```
namespace ObjectTypesSample
{
  class Program
  {
    static void Main(string∏ args)
    {
      EDBConnection.GlobalTypeMapper.MapComposite<addr object type>
("enterprisedb.addr object type");
      EDBConnection.GlobalTypeMapper.MapComposite<emp obj typ>
("enterprisedb.emp obj typ");
      EDBConnection conn = new
EDBConnection("Server=localhost;Port=5444;database=test;User
ID=enterprisedb;password=<PASSWORD>;");
      try
         conn.Open();
         EDBCommand cmd = new
EDBCommand("emp obj typ.display emp", conn);
         cmd.CommandType =
System.Data.CommandType.StoredProcedure;
         EDBCommandBuilder.DeriveParameters(cmd);
         addr object type address = new addr object type()
         {
           street = "123 MAIN STREET",
           city = "EDISON",
           state = "NJ",
           zip = 8817
        };
         emp_obj_typ emp = new emp_obj_typ()
         {
           empno = 9001,
```

```
ename = "JONES",
         addr = address
       };
       cmd.Parameters[0].Value = emp;
       cmd.Prepare();
       cmd.ExecuteNonQuery();
       emp _obj_typ empOut = (emp_obj_typ)cmd.Parameters[0].Value;
       Console.WriteLine("Emp No: " + empOut.empno);
       Console.WriteLine("Emp Name: " + empOut.ename);
       Console.WriteLine("Emp Address Street: " + empOut.addr.street);
       Console.WriteLine("Emp Address City: " + empOut.addr.city);
       Console.WriteLine("Emp Address State: " + empOut.addr.state);
       Console.WriteLine("Emp Address Zip: " + empOut.addr.zip);
       Console.WriteLine("Emp No: " + empOut.empno);
    catch (EDBException exp)
       Console.WriteLine(exp.Message.ToString());
    finally
    {
       conn.Close();
  }
}
public class addr_object_type
{
  public string street;
  public string city;
  public string state;
  public decimal zip;
}
public class emp_obj_typ
{
  public decimal empno;
  public string ename;
```

```
public addr_object_type addr;
}
```

The following .NET types are defined to map to the types in Advanced Server:

```
public class addr_object_type
{
   public string street;
   public string city;
   public decimal zip;
}

public class emp_obj_typ
{
   public decimal empno;
   public string ename;
   public addr_object_type addr;
}
```

A call to EDBConnection.GlobalTypeMapper.MapComposite maps the .NET type to the Advanced Server types:

```
EDBConnection.GlobalTypeMapper.MapComposite<addr_object_type>
("enterprisedb.addr_object_type");
EDBConnection.GlobalTypeMapper.MapComposite<emp_obj_typ>
("enterprisedb.emp_obj_typ");
```

A call to EDBCommandBuilder.DeriveParameters() gets parameter information for a stored procedure. This allows you to just set the parameter values and call the stored procedure:

```
EDBCommandBuilder.DeriveParameters(cmd);
```

The value of the parameter is set by creating an object of the .NET type and assigning it to the Value property of the parameter:

```
addr_object_type address = new addr_object_type()
{
```

```
street = "123 MAIN STREET",
  city = "EDISON",
  state = "NJ",
  zip = 8817
};
emp_obj_typ emp = new emp_obj_typ()
{
  empno = 9001,
  ename = "JONES",
  addr = address
};
cmd.Parameters[0].Value = emp;
```

A call to cmd.ExecuteNonQuery() executes the call to the display_emp() method:

```
cmd.ExecuteNonQuery();
```

16 Security and Encryption

16.1 Scram Compatibility

The EDB .NET driver provides SCRAM-SHA-256 support for Advanced Server version 10 and above. This support is available from EDB .NET 4.0.2.1 release onwards.

17 EDB .NET Connector Logging

EDB .NET Connector supports the use of logging to help resolve issues with the .NET Connector when used in your application. The connector uses classes in the EnterpriseDB.EDBClient.Logging namespace for logging.

Console Logging to Standard Error

EnterpriseDB.EDBClient.Logqing.ConsoleLoggingProvider is a class that outputs error messages to STDERR. To use this class, include the following line in your application before using any of the Advanced Server .NET Connector APIs.

EnterpriseDB.EDBClient.Logging.EDBLogManager.Provider = new EnterpriseDB.EDBClient.Logging.ConsoleLoggingProvider(EDBLogLevel.Debug, true, true);

The following log levels are available:

- Trace
- Debug
- Info
- Warn
- Error
- Fatal

Writing a Custom Logger

If the console logging provider does not fulfill your requirements, you can write a custom logger by implementing the

EnterpriseDB.EDBClient.Logging.IEDBLoggingProvider interface, and extending the EnterpriseDB.EDBClient.Logging.EDBLogger class, for instance, writing your logs to a file. The following is a simple example of how to write a custom logger:

```
public class MyLoggingProvider : IEDBLoggingProvider
{
    string _logFile;
    readonly EDBLogLevel _minLevel;
    readonly bool _printLevel;
    readonly bool _printConnectorId;
```

```
public MyLoggingProvider(string logFile, EDBLogLevel minLevel =
EDBLogLevel.Info, bool printLevel = false, bool printConnectorId = false)
    {
       logFile = logFile;
       _minLevel = minLevel;
       printLevel = printLevel;
       printConnectorId = printConnectorId;
    }
    public EDBLogger CreateLogger(string name)
       return new MyLogger( logFile, minLevel, printLevel,
 printConnectorId);
    }
  }
class MyLogger: EDBLogger
  {
    string logFile;
    readonly EDBLogLevel minLevel;
    readonly bool printLevel;
    readonly bool printConnectorId;
    internal MyLogger(string logFile, EDBLogLevel minLevel, bool printLevel,
bool printConnectorId)
       logFile = logFile;
       minLevel = minLevel;
       _printLevel = printLevel;
       printConnectorId = printConnectorId;
    }
    public override bool IsEnabled(EDBLogLevel level) => level >= minLevel;
    public override void Log(EDBLogLevel level, int connectorId, string msg,
Exception exception = null)
    {
       if (!IsEnabled(level))
```

```
return;
  using (StreamWriter writer = new StreamWriter(_logFile, true))
     var sb = new StringBuilder();
     if ( printLevel)
     {
       sb.Append(level.ToString().ToUpper());
       sb.Append(' ');
     }
     if (_printConnectorId && connectorId != 0)
       sb.Append("[");
       sb.Append(connectorId);
       sb.Append("] ");
     }
     sb.AppendLine(msg);
     if (exception != null)
       sb.AppendLine(exception.ToString());
     writer.Write(sb.ToString());
  }
}
```

To use this custom logger, put the following line in your application before using any of the EDB .NET Connector APIs:

EDBLogManager.Provider = new MyLoggingProvider(filepath, EDBLogLevel.Debug, true, true);

18 API Reference

For information about using the API, see the Npgsql documentation.

Usage notes:

- When using the API, replace references to Npgsql with EnterpriseDB.EDBClient.
- When referring to classes, replace Npgsql with EDB. For example, use the EDBBinaryExporter class instead of the NpgsqlBinaryExporter class.