Contents

0 EDB Postgres Advanced Server	
1.0 EDB Postgres Advanced Server Installation Guide for Linux	5
1.1 'Introduction'	5
Typographical Conventions Used in this Guide	
1.2 Supported Platforms	
1.3.0 Requirements Overview	
Supported Platforms	
Linux Installation Prerequisites	
1.3.1 'Supported Platforms'	
1.3.2 'Linux Installation Prerequisites'	
1.4 Using a Package Manager to Install Advanced Server	
Installing Advanced Server on a Linux Host	
Creating a Repository Configuration File and Installing Advanced Server	
Advanced Server RPM Packages	
Updating an RPM Installation	
Installing Advanced Server on a Debian or Ubuntu Host	
Advanced Server Debian Packages	
Configuring a Package Installation	
Creating a Database Cluster and Starting the Service	21
Using a Service Configuration File on CentOS or Redhat 6.x	23
Modifying the Data Directory Location on CentOS or Redhat 7.x	25
Starting Multiple Postmasters with Different Clusters	25
Creating an Advanced Server Repository on an Isolated Network	
1.5 Installation Troubleshooting	
1.6 'Limitations'	
1.7 Managing an Advanced Server Installation	
Starting and Stopping Advanced Server and Supporting Components	
Controlling a Service on CentOS or RHEL 7.x	
Controlling a Service on CentOS or RHEL 6.x	
Controlling a Service on Debian 9x or Ubuntu 18.04	
Using pg_ctl to Control Advanced Server	
Configuring Component Services to AutoStart at System Reboot	
Modifying the postgresql.conf File	
Modifying the pg_hba.conf File	
Connecting to Advanced Server with psql	
1.8.0 'Using a Package Manager to Install Advanced Server'	
1.8.2 'Installing Advanced Server on a SLES Host'	
1.8.3.0 Installing Advanced Server on a Debian or Ubuntu Host	
1.8.4.0 'Configuring a Package Installation'	
1.9 'Installation Troubleshooting'	
1.10 Uninstalling Advanced Server	
Uninstalling an RPM Package	
Uninstalling Advanced Server Components on a Debian or Ubuntu Host	38
1.11 Conclusion	38
2.0 EDB Postgres Advanced Server Installation Guide for Windows	38
2.1 Requirements Overview	36
Windows Installation Prerequisites	łC
2.2.0 Installing Advanced Server with the Interactive Installer	łC
2.2.1 Performing a Graphical Installation on Windows	
2.2.2.0 Invoking the Graphical Installer from the Command Line	
2.2.2.1 Performing an Unattended Installation	
2.2.2.2 Performing an Installation with Limited Privileges	
2.2.2.3 Reference - Command Line Options	
2.2.3 Using StackBuilder Plus	
2.2.4 Using the Update Monitor	
2.2.5 Installation Troubleshooting	
2.3.0 Managing an Advanced Server Installation	
Starting and Stopping Advanced Server and Supporting Components	
2.3.1. Using the Windows Services Applet'	ır

2.3.2 Using pg_ctl to Control Advanced Server	
2.3.3 Controlling Server Startup Behavior on Windows	
2.4.0 Configuring Advanced Server	
2.4.1 Modifying the postgresql.conf File	
2.4.2 Modifying the pg_hba.conf File	
2.4.3 Setting Advanced Server Environment Variables	
2.4.4 Connecting to Advanced Server with psql	
2.4.5 Connecting to Advanced Server with the pgAdmin 4 Client	
2.5 Uninstalling Advanced Server	
Using Advanced Server Uninstallers at the Command Line	
2.6 Conclusion	
3.0 EDB Postgres Advanced Server Upgrade Guide	
3.1 Supported Platforms	
3.2 Limitations	
3.3.0 Upgrading an Installation With pg_upgrade	
3.3.1.0 Performing an Upgrade	
3.3.1.1 Linking versus Copying	
3.3.2.0 Invoking pg_upgrade	. 63
3.3.2.1 Command Line Options - Reference	. 64
3.3.3 Upgrading to Advanced Server 12	. 66
3.3.4 Upgrading a pgAgent Installation	. 72
3.3.5 pg_upgrade Troubleshooting	
Upgrade Error - There seems to be a postmaster servicing the cluster	
Upgrade Error - fe_sendauth: no password supplied	
Upgrade Error - New cluster is not empty; exiting	
Upgrade Error - Failed to load library	
3.3.6 Reverting to the Old Cluster	
3.4 Performing a Minor Version Update of an RPM Installation	
3.5 Using StackBuilder Plus to Perform a Minor Version Update	
4.0 Database Compatibility for Oracle Developers Reference Guide	
4.1.0 The SQL Language	
4.1.1.0 SQL Syntax	
4.1.1.1 Lexical Structure	
4.1.1.2 Identifiers and Key Words	
4.1.1.3 Constants	
String Constants	
Numeric Constants	
Constants of Other Types	77
4.1.1.4 Comments	
4.1.2.0 Data Types	
4.1.2.1 Numeric Types	
Integer Types	
Arbitrary Precision Numbers	
Floating-Point Types	
4.1.2.2 Character Types	
4.1.2.3 Binary Data	
4.1.2.4 'Date/Time Types'	
INTERVAL Types	
Date/Time Input	
Dates	
Times	
Time Stamps	
Date/Time Output	
Internals	
4.1.2.5 Boolean Types	
4.1.2.6 XML Type	
4.1.3.0 Functions and Operators	
4.1.3.1 Logical Operators	
4.1.3.2 Comparison Operators	
4.1.3.3 'Mathematical Functions and Operators'	
4.1.3.4 String Functions and Operators	90

Truncation of String Text Resulting from Concatenation	
SYS_GUID	
4.1.3.5 Pattern Matching String Functions	
REGEXP_COUNT	
REGEXP_INSTR	
REGEXP_SUBSTR	
4.1.3.6 Pattern Matching Using the LIKE Operator	
4.1.3.7 'Data Type Formatting Functions'	
IMMUTABLE TO_CHAR(TIMESTAMP, format) Function	
4.1.3.8 'Date/Time Functions and Operators'	
ADD_MONTHS	
EXTRACT	
MONTHS_BETWEEN	
NEXT_DAY	
NEW_TIME	
ROUND	
TRUNC	
CURRENT DATE/TIME	
NUMTODSINTERVAL	
NUMTOYMINTERVAL	
4.1.3.9 Sequence Manipulation Functions	
4.1.3.10 Conditional Expressions	
CASE	
COALESCE	
NULLIF	
NVL	
NVL2	
GREATEST and LEAST	
4.1.3.11 Aggregate Functions	
MEDIAN	
4.1.3.12 Subquery Expressions	
EXISTS	
IN	
NOT IN	
ANY/SOME	
ALL	
4.2 'System Catalog Tables'	
dual	
edb_dir	
edb_password_history	
edb_policy	
edb_profile	
edb_variable	
pg_synonym	
product_component_version	
4.3 Acknowledgements	
5.0 Database Compatibility for Oracle Developers Built-in Pa	
5.1 Introduction	
What's New	
5.2.1 Package Components	
Package Specification Syntax	
Package Body Syntax	
Creating the Package Specification	
Creating the Package Body	
5.2.3 Referencing a Package	
5.2.4 Osing Packages with Oser Delined Types	134

5.3.0 Built-In Packages	 		 	 		 		 				 		. 13	34
5.3.1 DBMS ALERT															
REGISTER															
REMOVE															
REMOVEALL															
SIGNAL															
WAITANY															
WAITONE			 	 		 		 				 		. 13	38
Comprehensive Example	 		 	 		 		 				 		. 13	39
5.3.2.0 DBMS AQ															
5.3.2.1 'ENQUEUE'															
5.3.2.2 'DEQUEUE'															
5.3.2.3 REGISTER															
5.3.2.4 'UNREGISTER'															
5.3.3.0 DBMS_AQADM															
5.3.3.1 ALTER_QUEUE	 		 	 		 		 				 		. 14	8
5.3.3.2 ALTER_QUEUE_TABLE	 		 	 		 		 				 		. 14	19
5.3.3.3 CREATE_QUEUE	 		 	 		 		 				 		. 15	50
5.3.3.4 CREATE_QUEUE_TABLE .															
5.3.3.5 DROP_QUEUE															
5.3.3.6 DROP_QUEUE_TABLE	 •	•	 	 	 •	 	•	 	•	•	 •	 •	•	. 15	ں د
5.3.3.7 PURGE_QUEUE_TABLE .															
5.3.3.8 START_QUEUE															
5.3.3.9 STOP_QUEUE															
5.3.4.0 DBMS_CRYPTO	 		 	 		 		 				 		. 15	6
5.3.4.1 DECRYPT			 	 		 		 				 		. 15	57
5.3.4.2 ENCRYPT															
5.3.4.3 HASH															
5.3.4.4 MAC															
5.3.4.5 RANDOMBYTES															
5.3.4.6 RANDOMINTEGER															
5.3.4.7 RANDOMNUMBER															
5.3.5.0 DBMS_JOB															
5.3.5.1 BROKEN	 		 	 		 		 				 		. 16	3
5.3.5.2 CHANGE	 		 	 		 		 				 		. 16	34
5.3.5.3 INTERVAL															
5.3.5.4 NEXT_DATE															
5.3.5.5 REMOVE															
5.3.5.6 RUN															
5.3.5.7 SUBMIT															
5.3.5.8 WHAT															
5.3.6.0 DBMS_LOB			 	 		 		 				 		. 16	8
5.3.6.1 APPEND	 		 	 		 		 				 		. 16	9
5.3.6.2 COMPARE	 		 	 		 		 				 		. 16	9
5.3.6.3 CONVERTTOBLOB															
5.3.6.4 CONVERTTOCLOB															
5.3.6.5 COPY															
5.3.6.6 ERASE															
5.3.6.7 GET_STORAGE_LIMIT															
5.3.6.8 GETLENGTH															
5.3.6.9 INSTR			 	 		 		 				 		. 17	'3
5.3.6.10 READ			 	 		 		 				 		. 17	′4
5.3.6.11 SUBSTR			 	 		 		 				 		. 17	' 4
5.3.6.12 TRIM															
5.3.6.13 WRITE															
5.3.6.14 WRITEAPPEND															
5.3.7 DBMS_LOCK															
SLEEP															
5.3.8.0 DBMS_MVIEW															
5.3.8.1 GET_MV_DEPENDENCIES			 	 		 		 				 		. 17	'6
5382 REFRESH														17	7

5.3.8.3 REFRESH_ALL_MVIEWS				
5.3.8.4 REFRESH_DEPENDENT		 	 	180
5.3.9 DBMS_OUTPUT		 	 	181
CHARARR		 	 	181
DISABLE		 	 	182
ENABLE		 	 	182
GET LINE		 	 	183
GET LINES				
NEW LINE				
PUT				
PUT LINE				
SERVEROUTPUT				
5.3.10.0 DBMS PIPE				
5.3.10.1 CREATE PIPE				
5.3.10.2 NEXT_ITEM_TYPE				
5.3.10.3 PACK_MESSAGE				
5.3.10.4 PURGE				
5.3.10.5 RECEIVE MESSAGE				
5.3.10.6 REMOVE PIPE				
5.3.10.7 RESET BUFFER				
5.3.10.8 SEND MESSAGE				
5.3.10.9 UNIQUE_SESSION_NAME				
5.3.10.10 UNPACK MESSAGE				
5.3.10.11 Comprehensive Example				
5.3.11 DBMS_PROFILER				
FLUSH_DATA				
GET_VERSION				
INTERNAL_VERSION_CHECK				
PAUSE_PROFILER				
RESUME_PROFILER				
START_PROFILER				
STOP_PROFILER				
Using DBMS_PROFILER				
Querying the DBMS_PROFILER Tables and View				
DBMS_PROFILER - Reference				
5.3.12 DBMS_RANDOM				
INITIALIZE				
NORMAL		 	 	212
RANDOM		 	 	212
SEED		 	 	212
SEED		 	 	213
STRING		 	 	213
TERMINATE		 	 	213
VALUE		 	 	214
VALUE		 	 	214
5.3.13 DBMS REDACT		 	 	214
Using DBMS_REDACT Constants and Function Parameter	rs	 	 	215
ADD_POLICY				
ALTER POLICY				
DISABLE POLICY				
ENABLE POLICY				
DROP_POLICY				
UPDATE_FULL_REDACTION_VALUES				
5.3.14 DBMS RLS				
ADD POLICY				
DROP POLICY				
ENABLE POLICY				
5.3.15.0 DBMS SCHEDULER				
5.3.15.1 'Using Calendar Syntax to Specify a Repeating Interval'				
5.3.15.2 CREATE_JOB				
5.3.15.3 CREATE PROGRAM				
SOURCE CHECKIE I IIV CHICANI I I I I I I I I I I I I I I I I I I		 	 	

5.3.15.4 CREATE_SCHEDULE	23	39
5.3.15.5 DEFINE_PROGRAM_ARGUMENT	24	40
5.3.15.6 DISABLE	24	41
5.3.15.7 DROP_JOB	24	42
5.3.15.8 DROP PROGRAM	24	42
5.3.15.9 DROP_PROGRAM_ARGUMENT	24	43
5.3.15.10 DROP_SCHEDULE		
5.3.15.11 ENABLE		
5.3.15.12 EVALUATE_CALENDAR_STRING	24	45
5.3.15.13 RUN_JOB		
5.3.15.14 SET JOB ARGUMENT VALUE	24	46
5.3.16 DBMS_SESSION		
SET ROLE		
5.3.17.0 DBMS SQL		
5.3.17.1 BIND VARIABLE		
5.3.17.2 BIND_VARIABLE_CHAR		
5.3.17.3 BIND VARIABLE RAW		
5.3.17.4 CLOSE CURSOR		
5.3.17.5 COLUMN VALUE		
5.3.17.6 COLUMN VALUE CHAR		
5.3.17.7 COLUMN_VALUE_RAW		
5.3.17.8 DEFINE_COLUMN		
5.3.17.9 DEFINE_COLUMN_CHAR		
5.3.17.10 DEFINE_COLUMN_RAW		
5.3.17.11 DESCRIBE COLUMNS		
5.3.17.12 EXECUTE		
5.3.17.13 EXECUTE_AND_FETCH		
5.3.17.14 FETCH_ROWS		
5.3.17.15 IS_OPEN		
5.3.17.16 LAST_ROW_COUNT		
5.3.17.17 OPEN_CURSOR		
5.3.17.18 PARSE		
5.3.18 DBMS_UTILITY		
LNAME_ARRAY		
UNCL_ARRAY	26	63
ANALYZE_DATABASE, ANALYZE SCHEMA and ANALYZE PART_OBJECT	26	33
CANONICALIZE	26	34
COMMA_TO_TABLE	26	36
DB_VERSION	26	37
EXEC_DDL_STATEMENT	26	37
FORMAT CALL STACK	26	38
GET CPU TIME		
GET DEPENDENCY		
GET HASH VALUE		
GET PARAMETER VALUE		
GET TIME		
NAME TOKENIZE		
TABLE TO COMMA		
5.3.19.0 UTL_ENCODE		
	/	
5 3 10 1 RASE64 DECODE	27	, –
5.3.19.1 BASE64_DECODE		75
5.3.19.2 BASE64_ENCODE	27	
5.3.19.2 BASE64_ENCODE	27	76
5.3.19.2 BASE64_ENCODE	27 27 27	76 76
5.3.19.2 BASE64_ENCODE	27 27 27	76 76 77
5.3.19.2 BASE64_ENCODE	27 27 27 27	76 76 77 78
5.3.19.2 BASE64_ENCODE	27 27 27 27 27	76 76 77 78 78
5.3.19.2 BASE64_ENCODE		76 77 78 78 79
5.3.19.2 BASE64_ENCODE 5.3.19.3 MIMEHEADER_DECODE 5.3.19.4 MIMEHEADER_ENCODE 5.3.19.5 QUOTED_PRINTABLE_DECODE 5.3.19.6 QUOTED_PRINTABLE_ENCODE 5.3.19.7 TEXT_DECODE 5.3.19.8 TEXT_ENCODE 5.3.19.9 UUDECODE		76 77 78 78 79
5.3.19.2 BASE64_ENCODE 5.3.19.3 MIMEHEADER_DECODE 5.3.19.4 MIMEHEADER_ENCODE 5.3.19.5 QUOTED_PRINTABLE_DECODE 5.3.19.6 QUOTED_PRINTABLE_ENCODE 5.3.19.7 TEXT_DECODE 5.3.19.8 TEXT_ENCODE 5.3.19.9 UUDECODE 5.3.19.10 UUENCODE		76 76 77 78 79 80 81
5.3.19.2 BASE64_ENCODE 5.3.19.3 MIMEHEADER_DECODE 5.3.19.4 MIMEHEADER_ENCODE 5.3.19.5 QUOTED_PRINTABLE_DECODE 5.3.19.6 QUOTED_PRINTABLE_ENCODE 5.3.19.7 TEXT_DECODE 5.3.19.8 TEXT_ENCODE 5.3.19.9 UUDECODE		76 76 77 78 78 79 80 81

	FCLOSE	
	FCLOSE_ALL	
	FCOPY	
	FFLUSH	
	FOPEN	
	FREMOVE	
	FRENAME	
	GET_LINE	
	IS OPEN	
	NEW LINE	
	PUT	
	PUT LINE	
	-	
- 0 0	PUTF	
5.3.2	21 UTL_HTTP	
	HTML_PIECES	
	REQ	
	RESP	
	BEGIN_REQUEST	
	END_REQUEST	
	END_RESPONSE	
	GET_BODY_CHARSET	
	GET FOLLOW REDIRECT	
	GET HEADER	
	GET_HEADER_BY_NAME	
	GET HEADER COUNT	
	GET RESPONSE	
	GET_RESPONSE_ERROR_CHECK	
	GET_TRANSFER_TIMEOUT	
	READ_LINE	
	READ_RAW	
	READ_TEXT	
	REQUEST	
	REQUEST_PIECES	
	SET BODY CHARSET	
	SET_FOLLOW_REDIRECT	
	SET HEADER	
	SET RESPONSE ERROR CHECK	
	SET TRANSFER TIMEOUT	
	WRITE LINE	
	WRITE RAW	
	—	
- 0 0	WRITE_TEXT	
5.3.2	22 UTL_MAIL	
	SEND	
	SEND_ATTACH_RAW	
	SEND_ATTACH_VARCHAR2	
5.3.2	23 UTL_RAW	
	CAST_TO_RAW	
	CAST_TO_VARCHAR2	
	CONCAT	
	CONVERT	
	LENGTH	
	SUBSTR	
E 2 0	24 UTL_SMTP	
J.J.Z		
	CONNECTION	
	REPLY/REPLIES	
	CLOSE_DATA	
	COMMAND	
	COMMAND_REPLIES	
	DATA	
	DATA	

HELP	
MAIL	318
NOOP	
OPEN_CONNECTION	319
OPEN_DATA	319
QUIT	320
RCPT	320
RSET	320
VRFY	
WRITE_DATA	
Comprehensive Example	
5.3.25 UTL_URL	
ESCAPE	
UNESCAPE	
5.4 Acknowledgements	
5.5 Conclusion	
6.0 Database Compatibility for Oracle Developers	
6.1.0 Introduction	
6.1.1 What's New	
6.1.2.0 Configuration Parameters Compatible with Oracle Databases	
6.1.2.1 edb redwood date	
6.1.2.2 edb_redwood_raw_names	
6.1.2.3 edb_redwood_strings	
6.1.2.4 edb_stmt_level_tx	
6.1.2.5 oracle_home	
6.1.3 About the Examples Used in this Guide	
6.2.0 SQL Tutorial	
6.2.1.0 Sample Database	
6.2.1.1 Sample Database Installation	
6.2.1.2 Sample Database Description	
6.2.2 Creating a New Table	
6.2.3 Populating a Table With Rows	
6.2.4 Querying a Table	
6.2.5 Joins Between Tables	
6.2.6 Aggregate Functions	
6.2.7 Updates	
6.2.8 Deletions	
6.2.9 The SQL Language	350
6.3.0 Advanced Concepts	350
6.3.1 Views	350
6.3.2 Foreign Keys	351
6.3.3 The ROWNUM Pseudo-Column	352
6.3.4 Synonyms	353
6.3.5.0 Hierarchical Queries	355
6.3.5.1 Defining the Parent/Child Relationship	356
6.3.5.2 Selecting the Root Nodes	
6.3.5.3 Organization Tree in the Sample Application	
6.3.5.4 Node Level	
6.3.5.5 Ordering the Siblings	
6.3.5.6 Retrieving the Root Node with CONNECT_BY_ROOT	
6.3.5.7 Retrieving a Path with SYS_CONNECT_BY_PATH	
6.3.6.0 Multidimensional Analysis	
6.3.6.1 ROLLUP Extension	
6.3.6.2 CUBE Extension	
6.3.6.3 GROUPING SETS Extension	
6.3.6.4 GROUPING Function	
6.3.6.5 'GROUPING ID Function'	
6.4.0 Profile Management	
6.4.1.0 Creating a New Profile	
6.4.1.1 Creating a Password Function	
6.4.2 'Altering a Profile'	
V.T.C MICHIU & LIVING	

6.4.3 Dropping a Profile	
6.4.4 Associating a Profile with an Existing Role	
6.4.5 Unlocking a Locked Account	
6.4.6 Creating a New Role Associated with a Profile	
6.4.7 Backing up Profile Management Functions	
6.5.0 Optimizer Hints	
6.5.1 'Default Optimization Modes'	
6.5.2 Access Method Hints	
6.5.3 Specifying a Join Order	
6.5.4 'Joining Relations Hints'	
6.5.5 Global Hints	
6.5.6 Using the APPEND Optimizer Hint	
6.5.7 Parallelism Hints	
6.5.8 'Conflicting Hints'	
6.6.0 dblink_ora	
6.6.1.0 dblink_ora Functions and Procedures	
6.6.1.1 dblink_ora_connect()	
6.6.1.2 dblink_ora_status()	
6.6.1.3 dblink_ora_disconnect()	
6.6.1.4 dblink_ora_record()	
6.6.1.5 dblink_ora_call()	
6.6.1.6 dblink_ora_exec()	
6.6.1.7 dblink_ora_copy()	
6.6.2 Calling dblink ora Functions	
6.7 Open Client Library	
6.8 Oracle Catalog Views	
6.9 Tools and Utilities	
6.10 ECPGPlus	
6.11 System Catalog Tables	
6.12 Conclusion	
	l_ 400
7.0 Database Compatibility for Oracle Developers Tools and Utilities Guid	
7.1 EDB*Loader	408
7.1 EDB*Loader	
7.1 EDB*Loader Data Loading Methods General Usage Building the EDB*Loader Control File EDB Loader Control File Examples Invoking EDB*Loader Exit Codes Direct Path Load Parallel Direct Path Load Remote Loading Updating a Table with a Conventional Path Load 7.2 EDB*Wrap Using EDB*Wrap to Obfuscate Source Code	
7.1 EDB*Loader	
7.1 EDB*Loader Data Loading Methods General Usage Building the EDB*Loader Control File EDB Loader Control File Examples Invoking EDB*Loader Exit Codes Direct Path Load Parallel Direct Path Load Remote Loading Updating a Table with a Conventional Path Load 7.2 EDB*Wrap Using EDB*Wrap to Obfuscate Source Code 7.3 Dynamic Runtime Instrumentation Tools Architecture (DRITA) Configuring and Using DRITA	
7.1 EDB*Loader Data Loading Methods General Usage Building the EDB*Loader Control File EDB Loader Control File Examples Invoking EDB*Loader Exit Codes Direct Path Load Parallel Direct Path Load Remote Loading Updating a Table with a Conventional Path Load 7.2 EDB*Wrap Using EDB*Wrap to Obfuscate Source Code 7.3 Dynamic Runtime Instrumentation Tools Architecture (DRITA) Configuring and Using DRITA DRITA Functions	
7.1 EDB*Loader Data Loading Methods General Usage Building the EDB*Loader Control File EDB Loader Control File Examples Invoking EDB*Loader Exit Codes Direct Path Load Parallel Direct Path Load Remote Loading Updating a Table with a Conventional Path Load 7.2 EDB*Wrap Using EDB*Wrap to Obfuscate Source Code 7.3 Dynamic Runtime Instrumentation Tools Architecture (DRITA) Configuring and Using DRITA DRITA Functions get_snaps()	
7.1 EDB*Loader Data Loading Methods General Usage Building the EDB*Loader Control File EDB Loader Control File Examples Invoking EDB*Loader Exit Codes Direct Path Load Parallel Direct Path Load Remote Loading Updating a Table with a Conventional Path Load 7.2 EDB*Wrap Using EDB*Wrap to Obfuscate Source Code 7.3 Dynamic Runtime Instrumentation Tools Architecture (DRITA) Configuring and Using DRITA DRITA Functions get_snaps() sys_rpt()	
7.1 EDB*Loader Data Loading Methods General Usage Building the EDB*Loader Control File EDB Loader Control File Examples Invoking EDB*Loader Exit Codes Direct Path Load Parallel Direct Path Load Remote Loading Updating a Table with a Conventional Path Load 7.2 EDB*Wrap Using EDB*Wrap to Obfuscate Source Code 7.3 Dynamic Runtime Instrumentation Tools Architecture (DRITA) Configuring and Using DRITA DRITA Functions get_snaps() sys_rpt() sess_rpt()	
7.1 EDB*Loader Data Loading Methods General Usage Building the EDB*Loader Control File EDB Loader Control File Examples Invoking EDB*Loader Exit Codes Direct Path Load Parallel Direct Path Load Remote Loading Updating a Table with a Conventional Path Load 7.2 EDB*Wrap Using EDB*Wrap to Obfuscate Source Code 7.3 Dynamic Runtime Instrumentation Tools Architecture (DRITA) Configuring and Using DRITA DRITA Functions get_snaps() sys_rpt() sess_rpt() sessid_rpt()	
7.1 EDB*Loader Data Loading Methods General Usage Building the EDB*Loader Control File EDB Loader Control File Examples Invoking EDB*Loader Exit Codes Direct Path Load Parallel Direct Path Load Remote Loading Updating a Table with a Conventional Path Load 7.2 EDB*Wrap Using EDB*Wrap to Obfuscate Source Code 7.3 Dynamic Runtime Instrumentation Tools Architecture (DRITA) Configuring and Using DRITA DRITA Functions get_snaps() sys_rpt() sess_rpt() sessid_rpt() sesshist_rpt()	
7.1 EDB*Loader Data Loading Methods General Usage Building the EDB*Loader Control File EDB Loader Control File Examples Invoking EDB*Loader Exit Codes Direct Path Load Parallel Direct Path Load Remote Loading Updating a Table with a Conventional Path Load 7.2 EDB*Wrap Using EDB*Wrap to Obfuscate Source Code 7.3 Dynamic Runtime Instrumentation Tools Architecture (DRITA) Configuring and Using DRITA DRITA Functions get_snaps() sys_rpt() sess_rpt() sessid_rpt() sesshist_rpt() purgesnap()	
7.1 EDB*Loader Data Loading Methods General Usage Building the EDB*Loader Control File EDB Loader Control File Examples Invoking EDB*Loader Exit Codes Direct Path Load Parallel Direct Path Load Remote Loading Updating a Table with a Conventional Path Load 7.2 EDB*Wrap Using EDB*Wrap to Obfuscate Source Code 7.3 Dynamic Runtime Instrumentation Tools Architecture (DRITA) Configuring and Using DRITA DRITA Functions get_snaps() sys_rpt() sess_rpt() sessid_rpt() sesshist_rpt()	
7.1 EDB*Loader Data Loading Methods General Usage Building the EDB*Loader Control File EDB Loader Control File Examples Invoking EDB*Loader Exit Codes Direct Path Load Parallel Direct Path Load Remote Loading Updating a Table with a Conventional Path Load 7.2 EDB*Wrap Using EDB*Wrap to Obfuscate Source Code 7.3 Dynamic Runtime Instrumentation Tools Architecture (DRITA) Configuring and Using DRITA DRITA Functions get_snaps() sys_rpt() sess_rpt() sessid_rpt() sesshist_rpt() purgesnap()	
7.1 EDB*Loader Data Loading Methods General Usage Building the EDB*Loader Control File EDB Loader Control File Examples Invoking EDB*Loader Exit Codes Direct Path Load Parallel Direct Path Load Remote Loading Updating a Table with a Conventional Path Load 7.2 EDB*Wrap Using EDB*Wrap to Obfuscate Source Code 7.3 Dynamic Runtime Instrumentation Tools Architecture (DRITA) Configuring and Using DRITA DRITA Functions get_snaps() sys_rpt() sess_rpt() sessid_rpt() sesshist_rpt() purgesnap() truncsnap() Simulating Statspack AWR Reports edbreport()	408 409 409 410 418 425 430 430 430 433 433 435 435 438 438 438 438 439 440 440 441 441 444
7.1 EDB*Loader Data Loading Methods General Usage Building the EDB*Loader Control File EDB Loader Control File Examples Invoking EDB*Loader Exit Codes Direct Path Load Parallel Direct Path Load Remote Loading Updating a Table with a Conventional Path Load 7.2 EDB*Wrap Using EDB*Wrap to Obfuscate Source Code 7.3 Dynamic Runtime Instrumentation Tools Architecture (DRITA) Configuring and Using DRITA DRITA Functions get_snaps() sys_rpt() sess_rpt() sessid_rpt() sesshist_rpt() purgesnap() truncsnap() Simulating Statspack AWR Reports	408 409 409 410 418 425 430 430 430 433 433 435 435 438 438 438 438 439 440 440 441 441 444
7.1 EDB*Loader Data Loading Methods General Usage Building the EDB*Loader Control File EDB Loader Control File Examples Invoking EDB*Loader Exit Codes Direct Path Load Parallel Direct Path Load Remote Loading Updating a Table with a Conventional Path Load 7.2 EDB*Wrap Using EDB*Wrap to Obfuscate Source Code 7.3 Dynamic Runtime Instrumentation Tools Architecture (DRITA) Configuring and Using DRITA DRITA Functions get_snaps() sys_rpt() sess_rpt() sessid_rpt() sesshist_rpt() purgesnap() truncsnap() Simulating Statspack AWR Reports edbreport()	408 409 409 410 418 425 430 430 430 433 435 435 435 438 438 439 440 440 441 441 442 444 445
7.1 EDB*Loader Data Loading Methods General Usage Building the EDB*Loader Control File EDB Loader Control File Examples Invoking EDB*Loader Exit Codes Direct Path Load Parallel Direct Path Load Remote Loading Updating a Table with a Conventional Path Load 7.2 EDB*Wrap Using EDB*Wrap to Obfuscate Source Code 7.3 Dynamic Runtime Instrumentation Tools Architecture (DRITA) Configuring and Using DRITA DRITA Functions get_snaps() sys_rpt() sessid_rpt() sesshist_rpt() purgesnap() truncsnap() Simulating Statspack AWR Reports edbreport() stat_db_rpt()	408 409 409 410 418 425 430 430 430 433 433 435 435 435 438 439 440 441 441 442 444 444 445 445
7.1 EDB*Loader	408 409 409 410 418 425 430 430 430 433 433 433 433 435 438 438 438 438 439 440 440 441 441 442 444 444 445

Performance Tuning Recommendations			
Event Descriptions		 4	458
7.4 Acknowledgements		 4	460
7.5 Conclusion		 	461
8.0 EDB Postgres Advanced Server ECPGPlus Guide			
8.1 ECPGPlus - Overview			
Installation and Configuration			
Constructing a Makefile			
ECPGPlus Command Line Options			
8.2 Using Embedded SQL			
Example - A Simple Query			
Using Indicator Variables			
Declaring Host Variables		 4	468
Example - Using a Cursor to Process a Result Set		 4	468
8.3 Using Descriptors			
Example - Using a Descriptor to Return Data			
8.4 Building and Executing Dynamic SQL Statements			
Example - Executing a Non-query Statement Without Parameters			
Example - Executing a Non-query Statement with a Specified Number of Placeholders			
Example - Executing a Query With a Known Number of Placeholders			
Example - Executing a Query With an Unknown Number of Variables			
8.5 Error Handling		 4	489
Error Handling with sqlca		 4	489
EXEC SQL WHENEVER		 4	491
8.6 Reference			
C-preprocessor Directives			
Compiling in PROC Mode			
Using the SELECT_ERROR Precompiler Option			
Compiling in non-PROC Mode			
Supported C Data Types			
Type Codes			
The SQLDA Structure			
ECPGPlus Statements			
ALLOCATE DESCRIPTOR		 4	499
CALL		 !	500
CLOSE			
COMMIT			
CONNECT			
DEALLOCATE DESCRIPTOR			
DECLARE CURSOR			
DECLARE DATABASE			
DECLARE STATEMENT			
DELETE			
DESCRIBE		 !	505
DESCRIBE DESCRIPTOR		 !	506
DISCONNECT		 !	507
EXECUTE		 !	507
EXECUTE DESCRIPTOR			
EXECUTEEND EXEC			
EXECUTE IMMEDIATE			
FETCH			
FETCH DESCRIPTOR			
GET DESCRIPTOR			
INSERT			
OPEN			
OPEN DESCRIPTOR			
PREPARE			
ROLLBACK			
SAVEPOINT			
SELECT			
SET CONNECTION	•		514 515

SET DESCRIPTOR	
UPDATE	. 518
WHENEVER	. 518
8.7 Conclusion	. 519
9.0 EDB Postgres Language Pack Guide	. 519
9.1 Supported Database Server Versions	. 520
9.2 Installing Language Pack	. 520
Invoking the Graphical Installer	
Installing Language Pack with StackBuilder Plus	
Configuring Language Pack on an Advanced Server Host	
Configuring Language Pack on Windows	
Configuring Language Pack on a PostgreSQL Host	
Configuring Language Pack on OSX	
9.3 Using the Procedural Languages	
PL/Perl	
PL/Python	
PL/Tcl	
9.4 Conclusion	
10.0 Index	
10.1.0 Introduction	
10.1.1 What's New	
10.1.2 Conventions Used in this Guide	
10.1.3 About the Examples Used in this Guide	
Sample Database Description	
10.2 Enhanced Compatibility Features	
Enabling Compatibility Features	
Stored Procedural Language	
Optimizer Hints	
Data Dictionary Views	
dblink_ora	
Profile Management	
Built-In Packages	
Open Client Library	
Utilities	
ECPGPlus	
Table Partitioning	
10.3.0 Configuration Parameters	
10.3.1 Setting Configuration Parameters	. 540
10.3.2 Summary of Configuration Parameters	
10.3.3.0 Configuration Parameters by Functionality	
10.3.3.1.0 Top Performance Related Parameters	
10.3.3.1.1 shared_buffers	
10.3.3.1.2 work_mem	
10.3.3.1.3 maintenance_work_mem	
10.3.3.1.4 wal_buffers	. 545
10.3.3.1.5 checkpoint_segments	. 545
10.3.3.1.6 checkpoint_completion_target	. 545
10.3.3.1.7 checkpoint_timeout	
10.3.3.1.8 max_wal_size	. 546
10.3.3.1.9 min_wal_size	. 546
10.3.3.1.10 bgwriter_delay	
10.3.3.1.11 seq_page_cost	
10.3.3.1.12 random_page_cost	
10.3.3.1.13 effective_cache_size	
10.3.3.1.14 synchronous_commit	
10.3.3.1.15 edb_max_spins_per_delay	
10.3.3.1.16 pg_prewarm.autoprewarm	
10.3.3.1.17 pg_prewarm.autoprewarm_interval	
10.3.3.2 Resource Usage / Memory	
edb dynatune	
edb dynatune profile	551

10.3.3.3 Resource Usage / EDB Resource Manager	
edb_max_resource_groups	
edb_resource_group	
10.3.3.4 Query Tuning	
enable_hints	
10.3.3.5 Query Tuning / Planner Method Configuration	
edb_enable_pruning	
10.3.3.6 Reporting and Logging / What to Log	
trace_hints	
edb_log_every_bulk_value	
10.3.3.7.0 Auditing Settings	
10.3.3.7.1 edb_audit	
10.3.3.7.2 edb_audit_directory	
10.3.3.7.3 edb_audit_filename	
10.3.3.7.4 edb_audit_rotation_day	
10.3.3.7.5 edb_audit_rotation_size	
10.3.3.7.6 edb_audit_rotation_seconds	
10.3.3.7.7 edb_audit_connect	
10.3.3.7.8 edb_audit_disconnect	
10.3.3.7.9 edb_audit_statement	. 557
10.3.3.7.10 edb_audit_tag	
10.3.3.7.11 edb_audit_destination	. 557
10.3.3.7.12 edb_log_every_bulk_value	
10.3.3.8 Client Connection Defaults / Locale and Formatting	
icu_short_form	. 558
10.3.3.9 Client Connection Defaults / Statement Behavior	. 559
default_heap_fillfactor	. 559
edb_data_redaction	. 559
10.3.3.10 Client Connection Defaults / Other Defaults	. 559
oracle_home	. 560
odbc_lib_path	. 560
10.3.3.11 Compatibility Options	. 560
edb_redwood_date	
edb_redwood_greatest_least	. 561
edb_redwood_strings	
edb stmt level tx	. 565
db_dialect	. 566
default with rowids	
optimizer_mode	. 567
10.3.3.12 Customized Options	
custom_variable_classes	
dbms_alert.max_alerts	
dbms_pipe.total_message_buffer	
index_advisor.enabled	
edb_sql_protect.enabled	
edb_sql_protect.level	
edb_sql_protect.max_protected_relations	
edb_sql_protect.max_protected_roles	
edb_sql_protect.max_queries_to_save	
edb_wait_states.directory	
edb_wait_states.retention_period	
edb_wait_states.sampling_interval	
edbldr.empty_csv_field	
utl_encode.uudecode_redwood	
utl_cricode:dudecode_redwood	
10.3.3.13 Ungrouped	
nls_length_semantics	
query_rewrite_enabled	
query_rewrite_integrity	
timed statistics	
10.4.0 Index Advisor	575

10.4.1 Index Advisor Components	
10.4.2 Index Advisor Configuration	577
10.4.3 Using Index Advisor	
Using the pg_advise_index Utility	
Using Index Advisor at the psql Command Line	
10.4.4 Reviewing the Index Advisor Recommendations	
Using the show_index_recommendations() Function	
Querying the index_advisor_log Table	
Querying the index_recommendations View	
10.4.5 Limitations	584
10.5 SQL Profiler	584
10.6 pgsnmpd	586
Configuring pgsnmpd	586
Setting the Listener Address	
Invoking pgsnmpd	587
Viewing pgsnmpd Help	587
Requesting Information from pgsnmpd	587
10.7.0 EDB Audit Logging	
10.7.1 Audit Logging Configuration Parameters	
10.7.2 Selecting SQL Statements to Audit	
Data Definition Language and Data Control Language Statements	
Data Manipulation Language Statements	
10.7.3 Enabling Audit Logging	
10.7.4 Audit Log File	
10.7.5 Using Error Codes to Filter Audit Logs	
10.7.6 Using Command Tags to Filter Audit Logs	
10.7.7 Redacting Passwords from Audit Logs	
10.8 Unicode Collation Algorithm	
Basic Unicode Collation Algorithm Concepts	
International Components for Unicode	
Locale Collations	
Collation Attributes	
Using a Collation	
10.9 EDB Resource Manager	
Creating and Managing Resource Groups	
CREATE RESOURCE GROUP	
ALTER RESOURCE GROUP	
DROP RESOURCE GROUP	
Assigning a Process to a Resource Group	
Removing a Process from a Resource Group	
Monitoring Processes in Resource Groups	
CPU Usage Throttling	
Setting the CPU Rate Limit for a Resource Group	
Example – Single Process in a Single Group	
Example – Multiple Processes in a Single Group	
Example – Multiple Processes in Multiple Groups	
Dirty Buffer Throttling	
Setting the Dirty Rate Limit for a Resource Group	
Example – Single Process in a Single Group	
Example – Multiple Processes in a Single Group	
Example – Multiple Processes in Multiple Groups	
System Catalogs	
edb_all_resource_groups	
edb_resource_group	
10.10 libpq C Library	
Using libpq with EnterpriseDB SPL	
REFCURSOR Support	
Array Binding	
PQBulkStart	
PQexecBulk	
PQBulkFinish	

PQexecBulkPrepared	634
Example Code (Using PQBulkStart, PQexecBulk, PQBulkFinish)	635
Example Code (Using PQexecBulkPrepared)	635
10.11 Debugger	636
Configuring the Debugger	637
Starting the Debugger	637
The Debugger Window	637
Main Debugger Window	
The Program Body Panel	638
The Tabs Panel	
The Stack Tab	638
Debugging a Program	639
Stepping Through the Code	639
Using Breakpoints	
Setting a Global Breakpoint for In-Context Debugging	640
Exiting the Debugger	641
10.12 Performance Analysis and Tuning	
Dynatune	
edb_dynatune	
edb_dynatune_profile	
EDB Wait States	
edb wait states data	
edb_wait_states_queries	
edb_wait_states_sessions	
edb_wait_states_samples	
edb_wait_states_purge	
10.13 EDB Clone Schema	
Setup Process	
Installing Extensions and PL/Perl	
Setting Configuration Parameters	
Installing EDB Clone Schema	
Creating the Foreign Servers and User Mappings	
EDB Clone Schema Functions	
localcopyschema	
localcopyschema_nb	
remotecopyschema	
remotecopyschema_nb	
process_status_from_log	
remove_log_file_and_job	
10.14 Enhanced SQL and Other Miscellaneous Features	
COMMENT	
Output of Function version()	
Logical Decoding on Standby	
10.15 System Catalog Tables	
edb_dir	
edb_all_resource_groups	
edb_policy	
edb profile	
edb_redaction_column	
edb_redaction_policy	
edb_resource_group	
edb_variable	
pg_synonym	
product_component_version	
10.16 Advanced Server Keywords	
10.17 Conclusion	

0 EDB Postgres Advanced Server

EDB Postgres Advanced Server

1.0 EDB Postgres Advanced Server Installation Guide for Linux

The *EDB Postgres Advanced Server Installation Guide* is a comprehensive guide to installing EDB Postgres Advanced Server (Advanced Server). In this guide you will find detailed information about:

- Software prerequisites for performing an Advanced Server 12 installation on a Linux host.
- Using a package manager to install and update Advanced Server and its supporting components or utilities on a Linux host.
- · Managing an Advanced Server installation.
- · Configuring an Advanced Server package installation.
- · Uninstalling Advanced Server and its components.

1.1 'Introduction'

The EDB Postgres Advanced Server Installation Guide is a comprehensive guide to installing EDB Postgres Advanced Server (Advanced Server). In this guide you will find detailed information about:

- Software prerequisites for Advanced Server 11 installation on a Linux host.
- Using a package manager to install and update Advanced Server and its supporting components or utilities on a Linux host.
- · Managing an Advanced Server installation.
- Configuring an Advanced Server package installation.
- · Uninstalling Advanced Server and its components.

Typographical Conventions Used in this Guide

Certain typographical conventions are used in this manual to clarify the meaning and usage of various commands, statements, programs, examples, etc. This section provides a summary of these conventions.

In the following descriptions, a *term* refers to any word or group of words that are language keywords, user-supplied values, literals, etc. A term's exact meaning depends upon the context in which it is used.

- Italic font introduces a new term, typically in the sentence that defines it for the first time.
- Fixed-width (mono-spaced) font is used for terms that must be given literally such as SQL commands, specific table and column names used in the examples, programming language keywords, etc. For example, SELECT * FROM emp;
- Italic fixed-width font is used for terms for which the user must substitute values in actual usage. For example, DELETE FROM table_name;
- A vertical pipe I denotes a choice between the terms on either side of the pipe. A vertical pipe is used to separate two or more alternative terms within square brackets (optional choices) or braces (one mandatory choice).

•	Square bracke	ts []	denote that one	or none of the	e enclosed terms	s may be s	ubstituted.	For example	١,
	[alb]	means c	hoose one of "a"	or "b" or neith	er of the two.				

- Braces {} denote that exactly one of the enclosed alternatives must be specified. For example, { a | b } means exactly one of "a" or "b" must be specified.

• Ellipses ... denote that the preceding term may be repeated. For example, [a l b] ... means that you may have the sequence, "b a a b a".

1.2 Supported Platforms

For information about the platforms and versions supported by Advanced Server, visit the EnterpriseDB website at:

https://www.enterprisedb.com/blog/edb-supported-products-and-platforms

Limitations

The following limitations apply to EDB Postgres Advanced Server:

- The data directory of a production database should not be stored on an NFS file system.
- The LLVM JIT package is supported on RHEL 7.x only. LLVM JIT is not supported on RHEL 6.x and PPC-LE 64 (running RHEL or CentOS 7.x).

1.3.0 Requirements Overview

The following sections detail the supported platforms and installation requirements for EDB Postgres Advanced Server 11.

Supported Platforms

The Advanced Server 11 RPM packages are supported on the following platforms:

64 bit Linux:

- Red Hat Enterprise Linux (x86_64) 6.x and 7.x
- CentOS (x86 64) 6.x and 7.x
- OEL Linux 6.x and 7.x
- PPC-LE 8 running RHEL or CentOS 7.x
- SLES 12
- Debian 9x
- Ubuntu 18.04
- IBM Power 9

Note: The data directory of a production database should not be stored on an NFS file system.

Linux Installation Prerequisites

You can use an RPM package to install Advanced Server and supporting components on a Linux host. Before installing Advanced Server, you must:

Install the EPEL Release Package

You can use yum to install the epel-release package:

```
yum -y install https://dl.fedoraproject.org/pub/epel/epel-release-latest-7.noarch.rpm
```

Please note that you may need to enable the [extras] repository definition in the CentOS-Base.repo file (located in /etc/yum.repos.d).

If yum cannot access a repository that contains epel-release, you will get an error message:

```
No package epel available. Error: Nothing to do
```

If you receive this error, you can download the EPEL rpm package, and install it manually. To manually install EPEL, download the rpm package, assume superuser privileges, navigate into the directory that contains the package, and install EPEL with the command:

yum install epel-release

You must also have credentials that allow access to the EnterpriseDB repository. For information about requesting credentials, visit:

https://info.enterprisedb.com/rs/069-ALB-3images/Repository%20Access%2004-09-2019.pdf

After receiving your repository credentials you can:

- 1. Create the repository configuration file.
- 2. Modify the file, providing your user name and password.
- 3. Install Advanced Server.

Linux-specific Software Requirements

You must install xterm, konsole, or gnome-terminal before executing any console-based program installed by EnterpriseDB installers.

Migration Toolkit or EDB*Plus Installation Prerequisites Before using an RPM to install Migration Toolkit or EDB*Plus, you must first install Java version 1.7 or later for Migration Toolkit and Java version 1.8 or later for EDB*Plus. On a Linux system, you can use the yum package manager to install Java. Open a terminal window, assume superuser privileges, and enter:

yum install java

Follow the onscreen instructions to complete the installation.

1.3.1 'Supported Platforms'

The Advanced Server 11 RPM packages are supported on the following platforms:

64 bit Linux:

- Red Hat Enterprise Linux (x86 64) 6.x and 7.x
- CentOS (x86_64) 6.x and 7.x
- OEL Linux 6.x and 7.x
- PPC-LE 8 running RHEL or CentOS 7.x
- SLES 12
- Debian 9x
- Ubuntu 18.04
- IBM Power 9

Note: The data directory of a production database should not be stored on an NFS file system.

1.3.2 'Linux Installation Prerequisites'

You can use an RPM package to install Advanced Server and supporting components on a Linux host. Before installing Advanced Server, you must:

Install the EPEL Release Package

You can use yum to install the epel-release package:

yum -y install https://dl.fedoraproject.org/pub/epel/epel-release-latest-7.noarch.rpm

Please note that you may need to enable the [extras] repository definition in the CentOS-Base.repo file located in /etc/yum.repos.d .

If yum cannot access a repository that contains epel-release, you will get an error message:

No package epel available. Error: Nothing to do

If you receive this error, you can download the EPEL rpm package, and install it manually. To manually install EPEL, download the rpm package, assume superuser privileges, navigate into the directory that contains the package, and install EPEL with the command:

yum install epel-release

You must also have credentials that allow access to the EnterpriseDB repository. For information about requesting credentials, visit:

https://info.enterprisedb.com/rs/069-ALB-3images/Repository%20Access%2004-09-2019.pdf

After receiving your repository credentials you can:

- 1. Create the repository configuration file.
- 2. Modify the file, providing your user name and password.
- 3. Install Advanced Server.

Linux-specific Software Requirements

You must install xterm, konsole, or gnome-terminal before executing any console-based program installed by EnterpriseDB installers.

Migration Toolkit or EDB*Plus Installation Prerequisites Before using an RPM to install Migration Toolkit or EDB*Plus, you must first install Java version 1.7 or later for Migration Toolkit and Java version 1.8 or later for EDB*Plus. On a Linux system, you can use the yum package manager to install Java. Open a terminal window, assume superuser privileges, and enter:

yum install java

Follow the onscreen instructions to complete the installation.

1.4 Using a Package Manager to Install Advanced Server

You can use the yum package manager to install Advanced Server or Advanced Server supporting components. yum will attempt to satisfy package dependencies as it installs a package, but requires access to the Advanced Server repositories. If your system does not have access to a repository via the Internet, you can use RPM to install an individual package or create a local repository, but you may be required to manually satisfy package dependencies.

Installing the server package creates a database superuser named enterprisedb . The user is assigned a user ID (UID) and a group ID (GID) of 26 . The user has no default password; use the passwd command to assign a password for the user. The default shell for the user is bash , and the user's home directory is /var/lib/edb/as12 .

By default, Advanced Server logging is configured to write files to the log subdirectory of the data directory, rotating the files each day and retaining one week of log entries. You can customize the logging behavior of the server by [modifying the postgresql.conf File](04_managing_an_advanced_server_installation#modifying_the_postgresqlco

The RPM installers place Advanced Server components in the directories listed in the table below:

Component	Location
Executables	/usr/edb/as12/bin
Libraries	/usr/edb/as12/lib
Cluster configuration files	/etc/edb/as12
Documentation	/usr/edb/as12/share/doc
Contrib	/usr/edb/as12/share/contr
Data	/var/lib/edb/as12/data
Logs	/var/log/as12
Lock files	/var/lock/as12
Log rotation file	/etc/logrotate.d/as12

Component	Location
Sudo configuration file	/etc/sudoers.d/as12
Binary to access VIP without sudo	/usr/edb/as12/bin/secure
Backup area	/var/lib/edb/as12/backups
Templates	/usr/edb/as12/share
Procedural Languages	/usr/edb/as12/lib or /usr/edb/as12/lib64
Development Headers	/usr/edb/as12/include
Shared data	/usr/edb/as12/share
Regression tests	/usr/edb/as12/lib/pgxs/src/test/regress
SGML Documentation	/usr/edb/as12/share/doc

Installing Advanced Server on a Linux Host

Before using an RPM package to install Advanced Server on a Linux host, you must:

Install Linux-specific Software

You must install xterm, konsole, or gnome-terminal before executing any console-based program installed by EnterpriseDB installers.

Install Migration Toolkit or EDB*Plus Installation Prerequisites (Optional)

Before using an RPM to install Migration Toolkit or EDBPlus, you must first install Java version 1.7 or later for Migration Toolkit and Java version 1.8 or later for EDBPlus. On a Linux system, you can use the yum package manager to install Java. Open a terminal window, assume superuser privileges, and enter:

yum install java

Follow the onscreen instructions to complete the installation.

Request Credentials to the EnterpriseDB Repository

You must have credentials that allow access to the EnterpriseDB repository. For information about requesting credentials, visit:

https://info.enterprisedb.com/rs/069-ALB-3images/Repository%20Access%2004-09-2019.pdf.

After receiving your repository credentials you can:

- 1. Create the repository configuration file.
- 2. Modify the file, providing your user name and password.
- 3. Install the repository keys and additional prerequisite software.
- 4. Install Advanced Server and supporting components.

Creating a Repository Configuration File and Installing Advanced Server

To create the repository configuration file, assume superuser privileges and invoke the following command:

yum -y install https://yum.enterprisedb.com/edb-repo-rpms/edb-repo-latest.noarch.rpm

The repository configuration file is named edb.repo . The file resides in /etc/yum.repos.d.

After creating the edb.repo file, use your choice of editor to set the value of the enabled parameter to 1, and replace the username and password placeholders in the baseurl specification with the name and password of a registered EnterpriseDB user.

```
[edb]
name=EnterpriseDB RPMs $releasever - $basearch
baseurl=https://<\ *username>*:<*password>*\ @yum.enterprisedb.com/edb/redhat/rhel-
$releasever-$basearch
enabled=1
gpgcheck=1
gpgkey=file:///etc/pki/rpm-gpg/ENTERPRISEDB-GPG-KEY
```

After saving your changes to the configuration file, you must download and install the repository keys:

1. Use the following command to download the repository key:

```
curl -o /etc/pki/rpm-gpg/ENTERPRISEDB-GPG-KEY https://yum.enterprisedb.com/ENTERPRISEDB-G
```

2. Use the following command to install the key:

```
rpm --import /etc/pki/rpm-gpg/ENTERPRISEDB-GPG-KEY
```

3. Use the following commands to install the prerequisite software:

```
# yum -y install epel-release
```

yum makecache

Then, you can use yum install command to install Advanced Server. For example, to install the server and its core components, use the command:

```
yum install edb-as12-server
```

When you install an RPM package that is signed by a source that is not recognized by your system, yum may ask for your permission to import the key to your local server. If prompted, and you are satisfied that the packages come from a trustworthy source, enter a y, and press Return to continue.

After installing Advanced Server, you must configure the installation. For more information, see [Configuring a Package Installation](02_using_a_package_manager_to_install_advanced_server#configuring_a_package_installation).

During the installation, yum may encounter a dependency that it cannot resolve. If it does, it will provide a list of the required dependencies that you must manually resolve.

Advanced Server RPM Packages

The tables that follow list the RPM packages that are available from EnterpriseDB. You can also use the yum search command to access a list of the packages that are currently available from your configured repository. Open a command line, assume superuser privileges, and enter:

[yum search](#package)

Where package is the search term that specifies the name (or partial name) of a package.

Please note: The available package list is subject to change.

The following table lists the packages for Advanced Server 12 supporting components.

Updating an RPM Installation

If you have an existing Advanced Server RPM installation, you can use yum to upgrade your repository configuration file and update to a more recent product version. To update the edb.repo file, assume superuser privileges and enter:

```
yum upgrade edb-repo
```

yum will update the edb.repo file to enable access to the current EDB repository, configured to connect with the credentials specified in your edb.repo file. Then, you can use yum to upgrade all packages whose names include the expression edb:

```
yum upgrade edb*
```

Please note that the yum upgrade command will only perform an update between minor releases; to update between major releases, you must use pg_upgrade.

For more information about using yum commands and options, enter yum --help on your command line, or visit:

 $https://access.red hat.com/documentation/en-US/Red_Hat_Enterprise_Linux/6/html/Deployment_Guide/ch-yum.html\\$

Installing Advanced Server on a Debian or Ubuntu Host

To install Advanced Server on a Debian or Ubuntu host, you must have credentials that allow access to the EnterpriseDB repository. To request credentials for the repository, visit:

https://www.enterprisedb.com/repository-access-request

The following steps will walk you through using the EnterpriseDB apt repository to install a debian package. When using the commands, replace the username and password with the credentials provided by EnterpriseDB.

1. Assume superuser privileges:

```
sudo su -
```

2. Configure the EnterpriseDB repository:

```
sh -c 'echo "deb https://\ <username>:<password>\ @apt.enterprisedb.com/$(lsb_release -cs
```

3. Add support to your system for secure APT repositories:

```
apt-get install apt-transport-https
```

4. Add the EBD signing key:

```
wget -q -0 - https://\ <username>:<password> @apt.enterprisedb.com/edb-deb.gpg.key \| apt
```

5. Update the repository metadata:

```
apt-get update
```

6. Install Debian package:

```
apt-get install edb-as12
```

Note

Some Advanced Server components require a Java installation. Before using a native package to add Migration Toolkit to your system, please ensure that Java version 7 is installed on your Advanced Server host. Before using a native package to install EDB*Plus, please ensure that Java version 8 or later is installed.

If you are installing an Advanced Server supporting component that requires Java (such as MTK or EDB*Plus), make sure that you install Java version 8 before installing the supporting components.

The Debian package manager places Advanced Server and supporting components in the directories listed in the following table:

Advanced Server Debian Packages

The table that follows lists some of the Debian packages that are available from EnterpriseDB. You can also use the apt list command to access a list of the packages that are currently available from your configured repository. Open a command line, assume superuser privileges, and enter:

```
apt list edb*
```

Please note: The available package list is subject to change.

Configuring a Package Installation

The packages that install the database server component create a service configuration file (on version 6.x hosts) or unit file (on version 7.x hosts), and service startup scripts.

Creating a Database Cluster and Starting the Service

The PostgreSQL initdb command creates a database cluster; when installing Advanced Server with an RPM package, the initdb executable is in /usr/edb/asx.x/bin . After installing Advanced Server, you must manually configure the service and invoke initdb to create your cluster. When invoking initdb , you can:

- · Specify environment options on the command line.
- Include the service command on RHEL or CentOS 6.x and use a service configuration file to configure the environment.
- Include the systemd service manager on RHEL or CentOS 7.x and use a service configuration file to configure the environment.

To review the initdb documentation, visit:

https://www.postgresql.org/docs/12/static/app-initdb.html

After specifying any options in the service configuration file, you can create the database cluster and start the service; these steps are platform specific.

On RHEL or CentOS 6.x

To create a database cluster in the PGDATA directory that listens on the port specified by the PGPORT environment variable specified in the service configuration file (described in [Using a Service Configuration File on CentOS or Redhat 6.x](#using_a_service_configuration_file_on_centos_or_redhat_6x)), assume root privileges, and invoke the service script:

```
service edb-as-12 initdb
```

You can also assign a locale to the cluster when invoking initdb. By default, initdb will use the value specified by the \$LANG operating system variable, but if you append a preferred locale when invoking the script, the cluster will use the alternate value. For example, to create a database cluster that uses simplified Chinese, invoke the command:

```
service edb-as-12 initdb zh_CH.UTF-8
```

After creating a database cluster, start the database server with the command:

service edb-as-12 start

On RHEL or CentOS 7.x

To invoke initdb on a RHEL or CentOS 7.x system, with the options specified in the service configuration file, assume the identity of the operating system superuser:

```
su - root
```

To initialize a cluster with the non-default values, you can use the PGSETUP_INITDB_OPTIONS environment variable by invoking the edb-as-12-setup cluster initialization script that resides under EPAS_Home/bin

To invoke initdb export the PGSETUP_INITDB_OPTIONS environment variable with the following command:

```
PGSETUP_INITDB_OPTIONS="-E UTF-8" /usr/edb/as12/bin/edb-as-12-setup initdb
```

After creating the cluster, use systemct1 to start, stop, or restart the service:

```
systemctl { start \| stop \| restart } edb-as-12
```

On Debian 9x or Ubuntu 18.04

You can initialize multiple clusters using the bundled scripts. To create a new cluster, assume root privileges, and invoke the bundled script:

```
/usr/bin/epas_createcluster 12 main2
```

To start a new cluster, use the following command:

```
/usr/bin/epas_ctlcluster 12 main2 start
```

To list all the available clusters, use the following command:

```
/usr/bin/epas_lsclusters
```

Note

The data directory is created under /var/lib/edb-as/12/main2 and configuration directory is created under /etc/edb-as/12/main/.

Using a Service Configuration File on CentOS or Redhat 6.x

On a CentOS or RedHat version 6.x host, the RPM installer creates a service configuration file named edb-as-12.sysconfig in /etc/sysconfig/edb/as12 (see Figure 4.1). Please note that options specified in the service configuration file are only enforced if initdb is invoked via the service command; if you manually invoke initdb (at the command line), you must specify the other options (such as the location of the data directory and installation mode) on the command line.

The Advanced Server service configuration file.

The file contains the following environment variables:

- PGENGINE specifies the location of the engine and utility executable files.
- PGPORT specifies the listener port for the database server.
- PGDATA specifies the path to the data directory.
- PGLOG specifies the location of the log file to which the server writes startup information.
- Use INITDBOPTS to specify any initdb option or options that you wish to apply to the new cluster. For more information, see [Specifying Cluster Options with INITDBOPTS](02_us-ing_a_package_manager_to_install_advanced_server#specifying_cluster_options_with_initdbopts).

You can modify the edb-as-12.sysconfig file before using the service command to invoke the startup script to change the listener port, data directory location, startup log location or installation mode. If you plan to create more than one instance on the same system, you may wish to copy the edb-as-12.sysconfig file (and the associated edb-as-12 startup script) and modify the file contents for each additional instance that resides on the same host.

Specifying Cluster Options with INITDBOPTS You can use the INITDBOPTS variable to specify your cluster configuration preferences. By default, the INITDBOPTS variable is commented out in the service configuration file; unless modified, when you run the service startup script, the new cluster will be created in a mode compatible with Oracle databases. Clusters created in this mode will contain a database named edb, and have a database superuser named enterprisedb.

Clusters created in PostgreSQL mode do not include compatibility features. To create a new cluster in PostgreSQL mode, remove the pound sign (#) in front of the INITDBOPTS variable, enabling the "--no-redwood-compat" option. Clusters created in PostgreSQL mode will contain a database named postgres, and have a database superuser named postgres.

If you initialize the database using Oracle compatibility mode, the installation includes:

- · Data dictionary views compatible with Oracle databases.
- Oracle data type conversions.
- Date values displayed in a format compatible with Oracle syntax.
- Support for Oracle-styled concatenation rules (if you concatenate a string value with a NULL value, the returned value is the value of the string).
- Support for the following Oracle built-in packages:

Functionality compatible with Oracle Databases
Provides the capability to register for, send, and receive alerts.
Provides the capability for the creation, scheduling, and managing of jobs.
Provides the capability to manage on large objects.
Provides the capability to send messages to a message buffer, or get messages from the message buff
Provides the capability to send messages through a pipe within or between sessions connected to the
Enables the implementation of Virtual Private Database on certain Advanced Server database objects.
Provides an application interface to the EnterpriseDB dynamic SQL functionality.

Package	Functionality compatible with Oracle Databases
dbms_utility	Provides various utility programs.
dbms_aqadm	Provides supporting procedures for Advanced Queueing functionality.
dbms_aq	Provides message queueing and processing for Advanced Server.
dbms_profiler	Collects and stores performance information about the PL/pgSQL and SPL statements that are execut
dbms_random	Provides a number of methods to generate random values.
dbms_redact	Enables the redacting or masking of data that is returned by a query.
dbms_lock	Provides support for the DBMS_LOCK.SLEEP procedure.
dbms_scheduler	Provides a way to create and manage jobs, programs, and job schedules.
dbms_crypto	Provides functions and procedures to encrypt or decrypt RAW, BLOB or CLOB data. You can also use
dbms_mview	Provides a way to manage and refresh materialized views and their dependencies.
dbms_session	Provides support for the DBMS_SESSION.SET_ROLE procedure.
utl_encode	Provides a way to encode and decode data.
utl_http	Provides a way to use the HTTP or HTTPS protocol to retrieve information found at an URL.
utl_file	Provides the capability to read from, and write to files on the operating system's file system.
utl_smtp	Provides the capability to send e-mails over the Simple Mail Transfer Protocol (SMTP).
utl_mail	Provides the capability to manage e-mail.
utl_url	Provides a way to escape illegal and reserved characters within an URL.
utl_raw	Provides a way to manipulate or retrieve the length of raw data types.

You may also specify multiple initdb options. For example, the following statement:

```
INITDBOPTS="--no-redwood-compat -U alice --locale=en_US.UTF-8"
```

Creates a database cluster (without compatibility features for Oracle) that contains a database named postgres that is owned by a user named alice; the cluster uses UTF-8 encoding.

In addition to the cluster configuration options documented in the PostgreSQL core documentation, Advanced Server supports the following initdb options:

```
--no-redwood-compat
```

Include the _--no-redwood-compat keywords to instruct the server to create the cluster in PostgreSQL mode. When the cluster is created in PostgreSQL mode, the name of the database superuser will be _postgres _, and Advanced Server's features compatible with Oracle databases will not be available to the cluster.

```
--redwood-like
```

Include the --redwood-like keywords to instruct the server to use an escape character (an empty string (")) following the LIKE (or PostgreSQL-compatible ILIKE) operator in a SQL statement that is compatible with Oracle syntax.

```
--icu-short-form
```

Include the --icu-short-form keywords to create a cluster that uses a default ICU (International Components for Unicode) collation for all databases in the cluster. For more information about Unicode collations, please refer to the EDB Postgres Advanced Server Guide available at:

https://www.enterprisedb.com/edb-docs

For more information about using initdb, and the available cluster configuration options, see the PostgreSQL Core Documentation available at:

https://www.postgresql.org/docs/12/static/app-initdb.html

You can also view online help for initdb by assuming superuser privileges and entering:

```
/<path_to_initdb_installation_directory>/initdb --help
```

Where path_to_initdb_installation_directory specifies the location of the initdb binary file.

Modifying the Data Directory Location on CentOS or Redhat 7.x

On a CentOS or RedHat version 7.x host, the unit file is named edb-as-12.service and resides in /usr/lib/systemd/system. The unit file contains references to the location of the Advanced Server data directory. You should avoid making any modifications directly to the unit file because it may be overwritten during package upgrades.

By default, data files reside under /var/lib/edb/as12/data directory. To use a data directory that resides in a non-default location, create a copy of the unit file under the /etc directory:

```
cp /usr/lib/systemd/system/edb-as-12.service /etc/systemd/system/
```

After copying the unit file to the new location, create the service file (/etc/systemd/system/edb-as-12.service) and include (/lib/systemd/system/edb-as-12.service) within the file.

Then, use the following command to reload systemd, updating the modified service scripts:

```
systemctl daemon-reload
```

Then, start the Advanced Server service with the following command:

```
systemctl start edb-as-12
```

For information about setting an environment variable, see the Database Compatibility for Oracle Developers Reference Guide.

Starting Multiple Postmasters with Different Clusters

You can configure Advanced Server to use multiple postmasters, each with its own database cluster. The steps required are version specific to the Linux host.

On RHEL or CentOS 6.x

The edb-as12-server-core RPM contains a script that starts the Advanced Server instance. The script can be copied, allowing you to run multiple services, with unique data directories and that monitor different ports. You must have root access to invoke or modify the script.

The example that follows creates a second instance on an Advanced Server host; the secondary instance is named secondary:

1. Create a hard link in /etc/rc.d/init.d (or equivalent location) to the edb-as-12 service (named secondary-edb-as-12):

```
ln edb-as-12 secondary-edb-as-12
```

Be sure to pick a name that is not already used in /etc/rc.d/init.d.

- 2. Create a file in /etc/sysconfig/edb/as12/ named secondary-edb-as-12. This file is where you would typically define PGDATA and PGOPTS. Since \$PGDATA/postgresql.conf will override many of these settings (except PGDATA) you might notice unexpected results on startup.
- 3. Create the target PGDATA directory.
- 4. Assume the identity of the Advanced Server database superuser (enterprisedb) and invoke initdb on the target PGDATA . For information about using initdb , please see the PostgreSQL Core Documentation available at:

https://www.postgresql.org/docs/12/static/app-initdb.html.

5. Edit the postgresql.conf file to specify the port, address, TCP/IP settings, etc. for the secondary instance.

6. Start the postmaster with the following command:

service secondary-edb-as-12 start

On RHEL or CentOS 7.x

The edb-as12-server-core RPM for version 7.x contains a unit file that starts the Advanced Server instance. The file allows you to start multiple services, with unique data directories and that monitor different ports. You must have root access to invoke or modify the script.

The example that follows creates an Advanced Server installation with two instances; the secondary instance is named secondary:

1. Make a copy of the default file with the new name. As noted at the top of the file, all modifications must reside under /etc . You must pick a name that is not already used in /etc/systemd/system .

cp /usr/lib/systemd/system/edb-as-12.service /etc/systemd/system/secondary-edb-as-12.

- 2. Edit the file, changing PGDATA to point to the new data directory that you will create the cluster against.
- 3. Create the target PGDATA with user enterprisedb.
- 4. Run initdb, specifying the setup script:

/usr/edb/as12/bin/edb-as-12-setup initdb secondary-edb-as-12

- 5. Edit the postgresql.conf file for the new instance, specifying the port, the IP address, TCP/IP settings, etc.
- 6. Make sure that new cluster runs after a reboot:

systemctl enable secondary-edb-as-12

7. Start the second cluster with the following command:

systemctl start secondary-edb-as-12

Creating an Advanced Server Repository on an Isolated Network

You can create a local repository to act as a host for the Advanced Server RPM packages if the server on which you wish to install Advanced Server (or supporting components) cannot directly access the EnterpriseDB repository. Please note that this is a high-level listing of the steps requires; you will need to modify the process for your individual network.

To create and use a local repository, you must:

1. Use yum to install the epel-release, yum-utils, and createrepo packages:

```
yum install epel-release
yum install yum-utils
yum install createrepo
```

2. Create a directory in which to store the repository:

```
mkdir /srv/repos
```

3. Copy the RPM installation packages to your local repository. You can download the individual packages or use a tarball to populate the repository. The packages are available from the EnterpriseDB repository at:

```
https://yum.enterprisedb.com/
```

4. Sync the RPM packages and create the repository.

```
reposync -r edbas12 -p /srv/repos createrepo /srv/repos
```

- 5. Install your preferred webserver on the host that will act as your local repository, and ensure that the repository directory is accessible to the other servers on your network.
- 6. On each isolated database server, configure yum to pull updates from the mirrored repository on your local network. For example, you might create a repository configuration file called /etc/yum.repos.d/edb-repo with connection information that specifies:

[edbas12]
name=EnterpriseDB Advanced Server 12
baseurl=https:yum.your_domain.com/edbas12
enabled=1
gpgcheck=0

After specifying the location and connection information for your local repository, you can use yum commands to install Advanced Server and its supporting components on the isolated servers. For example:

yum install edb-as12-server

For more information about creating a local yum repository, visit:

https://wiki.centos.org/HowTos/CreateLocalRepos

1.5 Installation Troubleshooting

Difficulty Displaying Java-based Applications

If you encounter difficulty displaying Java-based server features (controls or text not being displayed correctly, or blank windows), upgrading to the latest libxcb-xlib libraries should correct the problem on most distributions. Please visit the following link for other possible work-arounds:

http://bugs.sun.com/bugdatabase/view bug.do?bug id=6532373

The Installation Fails to Complete Due to Existing data Directory Contents

If an installation fails to complete due to an existing content in the data directory, the server will write an error message to the server logs:

A data directory is neither empty, or a recognisable data directory.

If you encounter a similar message, you should confirm that the data directory is empty; the presence of files (including the system-generated lost+found folder) will prevent the installation from completing. Either remove the files from the data directory, or specify a different location for the data directory before re-invoking the installer to complete the installation.

Difficulty Installing the EPEL Release Package

If you encounter difficulty when installing the EPEL release package, you can use the following command to install the epel-release package:

yum -y install https://dl.fedoraproject.org/pub/epel/epel-release-latest-7.noarch.rpm Please note that you may need to enable the <code>[extras]</code> repository definition in the <code>CentOS-Base.repo</code> file (located in <code>/etc/yum.repos.d</code>). If <code>yum</code> cannot access a repository that contains <code>epel-release</code> , you will get an error message:

No package epel available. Error: Nothing to do

If you receive this error, you can download the EPEL rpm package, and install it manually; download the rpm package, assume superuser privileges, navigate into the directory that contains the package, and install EPEL with the command:

yum install epel-release

1.6 'Limitations'

The following limitation applies to the EDB Postgres Advanced Server:

• The LLVM JIT package is supported on RHEL 7.x and SLES. LLVM JIT is not supported on RHEL 6.x and PPC-LE 64 (running RHEL or CentOS 7.x).

1.7 Managing an Advanced Server Installation

Unless otherwise noted, the commands and paths noted in the following section assume that you have performed an installation using the native packages.

Starting and Stopping Advanced Server and Supporting Components

A service is a program that runs in the background and requires no user interaction (in fact, a service provides no user interface); a service can be configured to start at boot time, or manually on demand. Services are best controlled using the platform-specific operating system service control utility. Many of the Advanced Server supporting components are services.

The following table lists the names of the services that control Advanced Server and services that control Advanced Server supporting components:

Advanced Server Component Name	Linux Service Name	Debian Service Name
Advanced Server pgAgent PgBouncer pgPool-II Slony EFM	edb-as-12 edb-pgagent-12 edb-pgbouncer-112 edb-pgpool-37 edb-slony-replication-12 efm-3.7	edb-as12-main edb-as12-pgagent edb-pgbouncer112 edb-pgpool37 edb-as12-slony-replication efm-3.7

You can use the Linux command line to control Advanced Server's database server and the services of Advanced Server's supporting components. The commands that control the Advanced Server service on a Linux platform are host specific.

Controlling a Service on CentOS or RHEL 7.x

If your installation of Advanced Server resides on version 7.x of RHEL and CentOS, you must use the systemctl command to control the Advanced Server service and supporting components.

The systemctl command must be in your search path and must be invoked with superuser privileges. To use the command, open a command line, and enter:

systemctl action service_name

Where:

service_name specifies the name of the service.

action specifies the action taken by the service command. Specify:

- · start to start the service.
- stop to stop the service.
- restart to stop and then start the service.
- status to discover the current status of the service.

Controlling a Service on CentOS or RHEL 6.x

On version 6.x of RHEL or CentOS Linux, you can control a service at the command line with the service command. The service command can be used to manage an Advanced Server cluster, as well as the

services of component software installed with Advanced Server.

Using the service command to change the status of a service allows the Linux service controller to keep track of the server status (the pg_ctl command does not alert the service controller to changes in the status of a server). The command must be in your search path and must be invoked with superuser privileges. Open a command line, and issue the command:

```
service service_name action
```

The Linux service command invokes a script (with the same name as the service) that resides in /etc/init.d. If your Linux distribution does not support the service command, you can call the script directly by entering:

/etc/init.d/service_name action

Where:

service_name specifies the name of the service.

action specifies the action taken by the service command. Specify:

- start to start the service.
- · stop to stop the service.
- condstop to stop the service without displaying a notice if the server is already stopped.
- restart to stop and then start the service.
- condrestart to restart the service without displaying a notice if the server is already stopped.
- try-restart to restart the service without displaying a notice if the server is already stopped.
- status to discover the current status of the service.

Controlling a Service on Debian 9x or Ubuntu 18.04

If your installation of Advanced Server resides on version 9x of Debian or 18.04 of Ubuntu, assume superuser privileges and invoke the following commands (using bundled scripts) to manage the service. Use the following commands to:

· Discover the current status of a service:

```
/usr/bin/epas_ctlcluster 12 main status
```

· Stop a service:

```
/usr/bin/epas_ctlcluster 12 main stop
```

· Restart a service:

```
/usr/bin/epas_ctlcluster 12 main restart
```

· Reload a service:

```
/usr/bin/epas_ctlcluster 12 main reload
```

• Control the component services:

```
systemctl restart edb-as@12-main
```

Using pg_ctl to Control Advanced Server

You can use the pg_ctl utility to control an Advanced Server service from the command line on any platform. pg_ctl allows you to start, stop, or restart the Advanced Server database server, reload the configuration parameters, or display the status of a running server. To invoke the utility, assume the identity of the cluster owner, navigate into the home directory of Advanced Server, and issue the command:

./bin/pg_ctl -D <data_directory action>

data_directory is the location of the data controlled by the Advanced Server cluster.

action specifies the action taken by the pg_ctl utility. Specify:

- start to start the service.
- stop to stop the service.
- restart to stop and then start the service.
- reload sends the server a SIGHUP signal, reloading configuration parameters
- status to discover the current status of the service.

For more information about using the pg_ctl utility, or the command line options available, please see the official PostgreSQL Core Documentation available at:

https://www.postgresql.org/docs/12/static/app-pg-ctl.html

Choosing Between pg_ctl and the service Command

You can use the pg_ctl utility to manage the status of an Advanced Server cluster, but it is important to note that pg_ctl does not alert the operating system service controller to changes in the status of a server, so it is beneficial to use the service command whenever possible.

Configuring Component Services to AutoStart at System Reboot

After installing, configuring, and starting the services of Advanced Server supporting components on a Linux system, you must manually configure your system to autostart the service when your system reboots. To configure a service to autostart on a Linux system, open a command line, assume superuser privileges, and enter the following command.

On a Redhat-compatible Linux system, enter:

/sbin/chkconfig *service_name* on

Where service_name specifies the name of the service.

Modifying the postgresql.conf File

Configuration parameters in the postgresql.conf file specify server behavior with regards to auditing, authentication, encryption, and other behaviors. On a RHEL or CentOS host, the postgresql.conf file resides in the data directory under your Advanced Server installation. On a Debian or Ubuntu host, server configuration files are located in the /etc/edb-as/12/main directory.

The postgresql.conf file.

Parameters that are preceded by a pound sign (#) are set to their default value (as shown in the parameter setting). To change a parameter value, remove the pound sign and enter a new value. After setting or changing a parameter, you must either reload or restart the server for the new parameter value to take effect.

Within the postgresql.conf file, some parameters contain comments that indicate change requires restart. To view a list of the parameters that require a server restart, execute the following query at the psql command line:

SELECT name FROM pg_settings WHERE context = 'postmaster';

Modifying the pg_hba.conf File

Appropriate authentication methods provide protection and security. Entries in the pg_hba.conf file specify the authentication method or methods that the server will use when authenticating connecting clients. Before connecting to the server, you may be required to modify the authentication properties specified in the pg_hba.conf file.

When you invoke the initdb utility to create a cluster, initdb creates a pg_hba.conf file for that cluster that specifies the type of authentication required from connecting clients.

The default authentication configuration specified in the pq_hba.conf file is:

The pg_hba.conf file.

To modify the pg_hba.conf file, open the file with your choice of editor. After modifying the authentication settings in the pg_hba.conf file, use the Linux command line to restart the server and apply the changes.

For more information about authentication, and modifying the pg_hba.conf file, see the PostgreSQL Core Documentation at:

https://www.postgresgl.org/docs/12/static/auth-pg-hba-conf.html

Managing Authentication on a Debian or Ubuntu Host

By default, the server is running with the peer or md5 permission on a Debian or Ubuntu host. You can change the authentication method by modifying the pg_hba.conf file, located in:

```
/etc/edb-as/12/main/pg_hba.conf
```

For more information about modifying the pg_hba.conf file, please review the PostgreSQL core documentation.

Connecting to Advanced Server with psql

psql is a command line client application that allows you to execute SQL commands and view the results. To open the psql client, the client must be in your search path. The executable resides in the bin directory, under your Advanced Server installation.

Use the following command and options to start the psql client:

psql -d edb -U enterprisedb

Where:

- -d specifies the database to which psql will connect;
- -U specifies the identity of the database user that will be used for the session.

For more information about using the command line client, please refer to the PostgreSQL Core Documentation at:

https://www.postgresql.org/docs/12/static/app-psql.html

1.8.0 'Using a Package Manager to Install Advanced Server'

You can use the yum package manager to install Advanced Server or Advanced Server supporting components. yum will attempt to satisfy package dependencies as it installs a package, but requires access to the Advanced Server repositories. If your system does not have access to a repository via the Internet, you can use RPM to install an individual package or create a local repository, but you may be required to manually satisfy package dependencies.

You must have credentials for the EnterpriseDB repository to install Advanced Server; to submit a request for credentials, visit:

[https://info.enterprisedb.com/rs/069-ALB-3images/Repository%20Access%2004-09-2019.pdf](https://info.enterprisedb.com/rs/069-ALB-3images/Repository Access 04-09-2019.pdf)

For a list of the RPM installers and Debian packages available from EnterpriseDB for Advanced Server and supporting components, see Section 4.1.1.

Installing the server package creates a database superuser named enterprisedb. The user is assigned a user ID (UID) and a group ID (GID) of 26. The user has no default password; use the passwd command

to assign a password for the user. The default shell for the user is bash, and the user's home directory is /var/lib/edb/as11.

By default, Advanced Server logging is configured to write files to the log subdirectory of the data directory, rotating the files each day and retaining one week of log entries. You can customize the logging behavior of the server by modifying the postgresql.conf file; for more information about modifying the postgresql.conf file, please see Section 6.2.

The RPM installers place Advanced Server components in the directories listed in the table below:

Component	Location
Executables	/usr/edb/as11/bin
Libraries	/usr/edb/as11/lib
Cluster configuration files	/etc/edb/as11
Documentation	/usr/edb/as11/share/doc
Contrib	/usr/edb/as11/share/contrib
Data	/var/lib/edb/as11/data
Logs	/var/log/as11
Lock files	/var/lock/as11
Log rotation file	/etc/logrotate.d/as11
Sudo configuration file	/etc/sudoers.d/as11
Binary to access VIP without sudo	/usr/edb/as11/bin/secure
Backup area	/var/lib/edb/as11/backups
Templates	/usr/edb/as11/share
Procedural Languages	/usr/edb/as11/lib or /usr/edb/as11/lib64
Development Headers	/usr/edb/as11/include
Shared data	/usr/edb/as11/share
Regression tests	/usr/edb/as11/lib/pgxs/src/test/regress
SGML Documentation	/usr/edb/as11/share/doc

The Debian package place Advanced Server and supporting components in the directories listed in the following table:

Debian Package Component	Location
Server	/usr/lib/edb-as/11/
Data and Configuration Directory	/var/lib/edb-as/11/main
/etc/edb-as/11/main/	
pgAgent	/usr/lib/edb-as/11
Pgpool	/usr/edb/pgpool3.7/
Postgis	/usr/lib/edb-as/11/
PGSNMPD	/usr/lib/edb-as/11
Slony Replication	/usr/lib/edb-as/11
pgBouncer	/usr/edb/pgbouncer1.9/
pgBouncer Configuration Files	/etc/edb/pgbouncer1.9/pgbouncer.ini
<pre>/etc/edb/pgbouncer1.9/userlist.txt</pre>	
SQL-Profiler	/usr/lib/edb-as/11/lib
SQL-Protect	/usr/lib/edb-as/11/lib
SSLUTILS	/usr/lib/edb-as/11/lib
PL-PERL	/usr/lib/edb-as/11/lib
PL-PYTHON	/usr/lib/edb-as/11/lib
PLTCL	/usr/lib/edb-as/11/lib

Debian Package Component	Location
EFM	/usr/edb/efm-3.2
JDBC	/usr/edb/jdbc
MTK	/usr/edb/migrationtoolkit/

edb-pgpool37	This package contains the pgPool-II installer. pgPool pro
edb-jdbc	The edb-jdbc package includes the .jar files needed
edb-migrationtoolkit	The edb-migrationtoolkit package installs Migra
edb-oci	The edb-oci package installs the EnterpriseDB Ope
edb-oci-devel	This package installs the OCI include files; install this pa
edb-odbc	This package installs the driver needed for applications
edb-odbc-devel	This package installs the ODBC include files; install this
edb-pgbouncer19	This package contains PgBouncer (a lightweight connec
ppas-xdb	This package contains the xDB installer; xDB provides a
ppas-xdb-console	This package provides support for xDB.
ppas-xdb-libs	This package provides support for xDB.
ppas-xdb-publisher	This package provides support for xDB.
ppas-xdb-subscriber	This package provides support for xDB.
edb-pem	The edb-pem package installs Management Tool that
edb-pem-agent	This package is an agent component of Postgres Enterp
edb-pem-docs	This package contains documentation for various langua
edb-pem-server	This package contains server components of Postgres E
edb-efm32 edb-efm31 edb-efm30	This package installs EDB Failover Manager that adds f
edb-bart edb-bart20	This package installs the Backup and Recovery Tool (BA
libevent-edb libiconv-edb libevent-edb-d	These packages contain supporting library files.

1.8.2 'Installing Advanced Server on a SLES Host'

You must have credentials that allow access to the EnterpriseDB repository to install Advanced Server on a SLES host. To request credentials for the repository, visit:

https://www.enterprisedb.com/repository-access-request

You can use the zypper package manager to install Advanced Server or Advanced Server supporting components on an SLES host. zypper will attempt to satisfy package dependencies as it installs a package, but some components require access to specific repositories that are not hosted at EnterpriseDB.

To add Advanced Server or supporting components, use the following commands to add EnterpriseDB repository configuration files to your SLES host:

zypper addrepo https://zypp.enterprisedb.com/suse/epas11-sles.repo

zypper addrepo https://zypp.enterprisedb.com/suse/epas-sles-tools.repo

zypper addrepo https://zypp.enterprisedb.com/suse/epas-sles-dependencies.repo

Each command creates a repository configuration file in the /etc/zypp/repos.d directory. The files are named:

- edbas11suse.repo
- edbasdependencies.repo

edbastools.repo

After creating the repository configuration files, use the zypper refresh command to refresh the metadata on your SLES host to include the EnterpriseDB repositories.

/etc/zypp/repos.d # zypper refresh

Repository 'Devel project of Java packages for openSUSE: Factory (SLE_12_SP3)' is up to date.

Repository 'SLE-Module-Legacy12-Pool' is up to date.

Repository 'SLE-Module-Legacy12-Updates' is up to date.

Repository 'SLES12-12-0' is up to date.

Repository 'SLES12-Pool' is up to date.

Repository 'SLES12-Updates' is up to date.

Repository 'SLE-SDK12-Pool' is up to date.

Repository 'SLE-SDK12-Updates' is up to date.

Repository 'SUSE-PackageHub-12' is up to date.

Repository 'SUSE-PackageHub-12-Pool' is up to date.

Repository 'wxWidgets Packages (SLE_12_SP3)' is up to date.

Repository 'Various compilers (SLE_12_SP3)' is up to date.

Retrieving repository 'EDB Postgres Advanced Server 11 12 - x86_64' metadata ----

Authentication required for 'https://zypp.enterprisedb.com/11/suse/suse-12-x86_64'

User Name:

Password:

Retrieving repository 'EDB Postgres Advanced Server 11 12 - x86_64' metadata.....

Building repository 'EDB Postgres Advanced Server 11 12 - x86_64' cache.....

Retrieving repository 'EDB Postgres Advanced Server Dependencies 12 - x86_64' metadata......

Building repository 'EDB Postgres Advanced Server Dependencies 12 - x86_64' cache.....

Retrieving repository 'EDB Postgres Advanced Server Tools 12 - x86_64' metadata.....

Building repository 'EDB Postgres Advanced Server Tools 12 - x86_64' cache......

All repositories have been refreshed.

When prompted for a User Name and Password, provide your connection credentials for the EnterpriseDB repository. If you need credentials, contact EnterpriseDB at:

https://www.enterprisedb.com/general-inquiry-form

Before installing EDB Postgres Advanced Server or supporting components, you must also add SUSEConnect and the SUSE Package Hub extension to the SLES host and register the host with SUSE, allowing access to SUSE repositories. Use the commands:

zypper install SUSEConnect

SUSEConnect -p PackageHub/12/x86_64

SUSEConnect -p sle-sdk/12/x86_64

For detailed information about registering a SUSE host, visit:

https://www.suse.com/support/kb/doc/?id=7016626

The following sections provide information about the specific repositories that are not hosted by EnterpriseDB, but that provide software that satisfies dependencies for each listed component. Please note that after adding repository access, you should use the zypper refresh command to process the repository content:

zypper refresh

Java Components:

Please note that only OpenJDK (version 1.8) is supported on SLES hosts of Java components. Before using an RPM package to add Advanced Server or a supporting component that requires Java, use zypper to add supporting repository locations to your system.

Use the commands:

zypper addrepo http://download.opensuse.org/repositories/Java:/Factory/SLE_12_SP2/Java:Factory

zypper refresh

Then, to install the server and its core components, invoke the command:

zypper install edb-as11

Slony:

If you are using a package to add Slony to a SLES host, please note that you must add access to the Perl repository:

For SLES 12 SP2:

zypper addrepo http://download.opensuse.org/repositories/devel:languages:perl/SLE_12_SP2/deve

For SLES 12 SP3:

zypper addrepo http://download.opensuse.org/repositories/devel:languages:perl/SLE_12_SP3/deve

Then:

zypper refresh

PostGIS:

When using an RPM package to add PostGIS to a SLES host, you must add the following repository:

zypper addrepo "http://download.opensuse.org/repositories/server:/Kolab:/3.3/SLE_12/server:Ko

Then:

zypper refresh

pgAgent:

When adding the pgAgent packages to a SLES host, you must add access to the wxWidgets repository:

For SLES 12 SP2:

SUSEConnect -p sle-module-legacy/12/x86_64

SUSEConnect -p sle-sdk/12/x86_64

zypper addrepo http://download.opensuse.org/repositories/X11:/wxWidgets/SLE_12_SP2/X11:wxWidgets

For SLES 12 SP3:

SUSEConnect -p sle-module-legacy/12/x86_64

SUSEConnect -p sle-sdk/12/x86_64

zypper addrepo http://download.opensuse.org/repositories/X11:/wxWidgets/SLE_12_SP3/X11:wxWidgets

Then:

zypper refresh

PEM Server and PEM Agent:

When adding the PEM Server and PEM Agent to a SLES host, you must add access to the wxWidgets repository:

For SLES 12 SP2:

SUSEConnect -p sle-module-legacy/12/x86_64

SUSEConnect -p sle-sdk/12/x86_64

zypper addrepo https://download.opensuse.org/repositories/Apache:Modules/SLE_12_SP2/Apache:Modul

zypper addrepo http://download.opensuse.org/repositories/Cloud:/OpenStack:/Newton:/cisco-apic

For SLES 12 SP3:

SUSEConnect -p sle-module-legacy/12/x86_64

SUSEConnect -p sle-sdk/12/x86_64

zypper addrepo https://download.opensuse.org/repositories/Apache:Modules/SLE_12_SP3/Apache:Modul

zypper addrepo http://download.opensuse.org/repositories/Cloud:/OpenStack:/Newton:/cisco-apic

Then:

zypper refresh zypper install edb-pem-server

The PEM server installer includes a script (configure-pem-server.sh) to help automate the configuration process for RPM installations. The script is installed in the /usr/edb/pem/bin directory. To invoke the script, use the command:

/usr/edb/pem/bin/configure-pem-server.sh

BART:

When installing BART on a SLES host, you must add the SUSE SDK as well as the Archiving repository:

SUSEConnect -p sle-sdk/12/x86_64

zypper addrepo https://download.opensuse.org/repositories/Archiving/SLE_12_SP3/Archiving.repo

Then:

zypper refresh

LLVM JIT:

When installing LLVM JIT on a SLES host, you must add the following repository to your system:

zypper addrepo https://download.opensuse.org/repositories/devel:/tools:/compiler/SLE_12_SP3/devel

Then:

zypper refresh

Updating Components on a SLES Host:

To update components installed with zypper, use the zypper update command.

1.8.3.0 Installing Advanced Server on a Debian or Ubuntu Host

To install Advanced Server on a Debian or Ubuntu host, you must have credentials that allow access to the EnterpriseDB repository. To request credentials for the repository, visit:

https://www.enterprisedb.com/repository-access-request

The following steps will walk you through using the EnterpriseDB apt repository to install a debian package. When using the commands, replace the username and password with the credentials provided by EnterpriseDB.

- 1. Assume superuser privileges: sudo su -
- 2. Configure the EnterpriseDB repository: sh -c 'echo "deb https://username:password@apt.enterprisedb
- 3. Add support to your system for secure APT repositories: apt-get install apt-transport-https
- 4. Add the EBD signing key: wget -q -0 https://username:password @apt.enterprisedb.com/edb-deb.
- 5. Update the repository metadata: apt-get update
- 6. Install Debian package: apt-get install edb-as11

Note: The OpenJDK version 10 is supported on a Debian or Ubuntu host of Java components. Before using a debian package to add Advanced Server or a supporting component such as MTK or EDB*Plus that requires Java, make sure to install Java version 8 on your system to support EDB Java-based components.

	 	ı

1.8.4.0 'Configuring a Package Installation'

The packages that install the database server component create a service configuration file (on version 6.x hosts) or unit file (on version 7.x hosts), and service startup scripts.

1.9 'Installation Troubleshooting'

Difficulty Displaying Java-based Applications

If you encounter difficulty displaying Java-based server features (controls or text not being displayed correctly, or blank windows), upgrading to the latest libxcb-xlib libraries should correct the problem on most distributions. Please visit the following link for other possible work-arounds:

http://bugs.sun.com/bugdatabase/view_bug.do?bug_id=6532373

The Installation Fails to Complete Due to Existing data Directory Contents

If an installation fails to complete due to existing content in the data directory, the server will write an error message to the server logs:

A data directory is neither empty, or a recognisable data directory.

If you encounter a similar message, you should confirm that the data directory is empty; the presence of files (including the system-generated lost+found folder) will prevent the installation from completing. Either remove the files from the data directory, or specify a different location for the data directory before re-invoking the installer to complete the installation.

1.10 Uninstalling Advanced Server

Note that after uninstalling Advanced Server, the cluster data files remain intact and the service user persists. You may manually remove the cluster data and service user from the system.

Uninstalling an RPM Package

You can use variations of the rpm or yum command to remove installed packages. Note that removing a package does not damage the Advanced Server data directory.

Include the e option when invoking the rpm command to remove an installed package; the command syntax is:

[rpm -e](#package_name)

Where package_name is the name of the package that you would like to remove.

You can use the yum remove command to remove a package installed by yum. To remove a package, open a terminal window, assume superuser privileges, and enter the command:

[yum remove](#package_name)

Where package_name is the name of the package that you would like to remove.

Note

yum and RPM will not remove a package that is required by another package. If you attempt to remove a package that satisfies a package dependency, yum or RPM will provide a warning.

To uninstall Advanced Server and its dependent packages; use the following command:

[yum remove](#edb-as12-server*)

Uninstalling Advanced Server Components on a Debian or Ubuntu Host

1. To uninstall Advanced Server, invoke the following command:

apt-get remove <edb-as12-server>*

Please note: The configuration files and data directory remains intact.

2. To uninstall Advanced Server, configuration files, and data directory, invoke the following command:

[apt-get purge](#edb-as12-server*)

1.11 Conclusion

EDB Postgres Advanced Server Installation Guide for Linux

Copyright © 2007 - 2020 EnterpriseDB Corporation. All rights reserved.

EnterpriseDB Corporation 34 Crosby Drive, Suite 201, Bedford, MA 01730, USA

T +1 781 357 3390 F +1 978 467 1307 E info@enterprisedb.com www.enterprisedb.com

• EDB designs, establishes coding best practices, reviews, and verifies input validation for the logon UI for EDB products where present. EDB follows the same approach for additional input components, however the nature of the product may require that it accepts freeform SQL, WMI or other strings to be entered and submitted by trusted users for which limited validation is possible. In such cases it is not possible to prevent users from entering incorrect or otherwise dangerous inputs.

- EDB reserves the right to add features to products that accept freeform SQL, WMI or other potentially dangerous inputs from authenticated, trusted users in the future, but will ensure all such features are designed and tested to ensure they provide the minimum possible risk, and where possible, require superuser or equivalent privileges.
- EDB does not that warrant that we can or will anticipate all potential threats and therefore our process cannot fully guarantee that all potential vulnerabilities have been addressed or considered.
- 1.12.0 Managing an Advanced Server Installation
- 1.12.1.1 Controlling a Service on CentOS or RHEL 7.x
- 1.12.1.2 Controlling a Service on CentOS or RHEL 6.x
- 1.12.1.3 Controlling a Service on Debain 9x or Ubuntu 18.04
- 1.12.1.4 Using pg_ctl to Control Advanced Server
- 1.12.1.5 Configuring Component Services to AutoStart at System Reboot
- 1.12.2 Modifying the postgresql.conf File
- 1.12.3 Modifying the pg_hba.conf File
- 1.12.4 Connecting to Advanced Server with psgl
- 1.13.0 Uninstalling Advanced Server
- 1.13.1 Uninstalling an RPM Package
- 1.13.2 Uninstalling Advanced Server Components on a Debian or Ubuntu Host

2.0 EDB Postgres Advanced Server Installation Guide for Windows

The EDB Postgres Advanced Server Installation Guide is a comprehensive guide to installing EDB Postgres Advanced Server (Advanced Server). In this guide you will find detailed information about:

- · Software prerequisites for Advanced Server 12 installation on Windows.
- Graphical installation options available through the interactive setup wizard on Windows.
- Managing an Advanced Server installation.
- Configuring an Advanced Server package installation.
- Uninstalling Advanced Server and its components.

2.1 Requirements Overview

For information about the platforms and versions supported by Advanced Server, visit the EnterpriseDB website at:

https://www.enterprisedb.com/blog/edb-supported-products-and-platforms

Limitations

The following limitations apply to EDB Postgres Advanced Server:

• The data directory of a production database should not be stored on an NFS file system.

Windows Installation Prerequisites

User Privileges

To perform an Advanced Server installation on a Windows system, you must have administrator privileges. If you are installing Advanced Server on a Windows system that is configured with User Account Control enabled, you can assume sufficient privileges to invoke the graphical installer by right clicking on the name of the installer and selecting Run as administrator from the context menu.

Windows-specific Software Requirements

You should apply Windows operating system updates before invoking the Advanced Server installer. If (during the installation process) the installer encounters errors, exit the installation, and ensure that your version of Windows is up-to-date before restarting the installer.

Migration Toolkit or EDB*Plus Installation Pre-requisites

Before using a StackBuilder Plus to install Migration Toolkit or EDB*Plus, you must first install Java (version 1.8 or later). If you are using Windows, Java installers and instructions are available online at:

http://www.java.com/en/download/manual.jsp

2.2.0 Installing Advanced Server with the Interactive Installer

You can use the Advanced Server interactive installer to install Advanced Server on Windows. The interactive installer is available from the EnterpriseDB website at:

https://www.enterprisedb.com/advanced-downloads

You can invoke the graphical installer in different installation modes to perform an Advanced Server installation:

- For information about using the graphical installer, see [Performing a Graphical Installation on Windows 1(02 installing advanced server with the interactive installer/01 performing a graphical installation on windows
- For information about performing an unattended installation, see [Performing an Unattended Installation](02 installing advanced server with the interactive installer/02 invoking the graphical installer from the comm
- For information about performing an installation with limited privileges, see [Performing an Installation with Limited Privileges] (02 installing advanced server with the interactive installer/02 invoking the graphical installer
- For information about the command line options you can include when invoking the installer, see [Reference Command Line Options](02_installing_advanced_server_with_the_interactive_installer/02_invoking_the_graph

During the installation, the graphical installer copies a number of temporary files to the location specified by the TEMP environment variable. You can optionally specify an alternate location for the temporary files by modifying the TEMP environment variable.

If invoking the installer from the command line, you can set the value of the variable on the command line. Use the command:

SET TEMP=temp_file_location

Where temp_file_location specifies the alternate location for the temporary files and must match the permissions with the TEMP environment variable.

Note

If you are invoking the installer to perform a system upgrade, the installer will preserve the configuration options specified during the previous installation.

Setting Cluster Preferences during a Graphical Installation

During an installation, the graphical installer invokes the PostgreSQL initdb utility to initialize a cluster. If you are using the graphical installer, you can use the INITDBOPTS environment variable to specify your initdb preferences. Before invoking the graphical installer, set the value of INITDBOPTS at the command line, specifying one or more cluster options. For example:

SET INITDBOPTS= -k -E=UTF-8

If you specify values in INITDBOPTS that are also provided by the installer (such as the -D option, which specifies the installation directory), the value specified in the graphical installer will supersede the value if specified in INITDBOPTS .

For more information about using initdb cluster configuration options, see the PostgreSQL Core Documentation available at:

https://www.postgresql.org/docs/12/static/app-initdb.html

In addition to the cluster configuration options documented in the PostgreSQL core documentation, Advanced Server supports the following initdb options:

--no-redwood-compat

Include the --no-redwood-compat keywords to instruct the server to create the cluster in PostgreSQL mode. When the cluster is created in PostgreSQL mode, the name of the database superuser will be postgres, the name of the default database will be postgres, and Advanced Server's features compatible with Oracle databases will not be available to the cluster.

--redwood-like

Include the --redwood-like keywords to instruct the server to use an escape character (an empty string (")) following the LIKE (or PostgreSQL compatible ILIKE) operator in a SQL statement that is compatible with Oracle syntax.

--icu-short-form

Include the --icu-short-form keywords to create a cluster that uses a default ICU (International Components for Unicode) collation for all databases in the cluster. For more information about Unicode collations, please refer to the EDB Postgres Advanced Server Guide available at:

https://www.enterprisedb.com/edb-docs

2.2.1 Performing a Graphical Installation on Windows

A graphical installation is a quick and easy way to install Advanced Server 12 on a Windows system. Use the wizard's dialogs to specify information about your system and system usage; when you have completed the dialogs, the installer performs an installation based on the selections made during the setup process.

To invoke the wizard, you must have administrator privileges. Assume administrator privileges, and double-click the edb-as12-server-12.x.x-x-windows-x64 executable file.

Note

To install Advanced Server on some versions of Windows, you may be required to right click on the file icon and select Run as Administrator from the context menu to invoke the installer with Administrator privileges.

When the Language Selection popup opens, select an installation language and click OK to continue to the Setup window.

The Advanced Server installer Welcome window

Click Next to continue.

The EnterpriseDB License Agreement opens.

The EnterpriseDB License Agreement

Carefully review the license agreement before highlighting the appropriate radio button; click Next to continue.

The Installation Directory window opens.

The Installation Directory window

By default, the Advanced Server installation directory is:

C:\Program Files\edb\as12

You can accept the default installation location, and click Next to continue, or optionally click the File Browser icon to open the Browse For Folder dialog to choose an alternate installation directory. Note

The data directory of a production database should not be stored on an NFS file system.

The Select Components window

The Select Components window contains a list of optional components that you can install with the Advanced Server Setup wizard. You can omit a module from the Advanced Server installation by deselecting the box next to the components name.

The Setup wizard can install the following components while installing Advanced Server 12:

EDB Postgres Advanced Server

Select the EDB Postgres Advanced Server option to install Advanced Server 12.

pgAdmin 4

Select the pgAdmin 4 option to install the pgAdmin 4 client. pgAdmin 4 provides a powerful graphical interface for database management and monitoring.

StackBuilder Plus

The StackBuilder Plus utility is a graphical tool that can update installed products, or download and add supporting modules (and the resulting dependencies) after your Advanced Server setup and installation completes. See [Using StackBuilder Plus](../02_installing_advanced_server_with_the_interactive_installer/03_using_stackbuilder_plus#using_stackbuilder_plus) for more information about StackBuilder Plus.

Command Line Tools

The Command Line Tools option installs command line tools and supporting client libraries including:

- libpq
- psql
- EDB*Loader
- · ecpgPlus
- pg_basebackup, pg_dump, and pg_restore
- pg_bench
- · and more.

Note

The Command Line Tools are required if you are installing Advanced Server or pgAdmin 4.

After selecting the components you wish to install, click Next to open the Additional Directories window.

The Additional Directories window

By default, the Advanced Server data files are saved to:

C:\Program Files\edb\as12\data

The default location of the Advanced Server Write-Ahead Log (WAL) Directory is:

C:\Program Files\edb\as12\data\pg_wal

Advanced Server uses write-ahead logs to promote transaction safety and speed transaction processing; when you make a change to a table, the change is stored in shared memory and a record of the change is written to

the write-ahead log. When you perform a COMMIT, Advanced Server writes contents of the write-ahead log to disk.

Accept the default file locations, or use the File Browser icon to select an alternate location; click Next to continue to the Advanced Server Dialect window.

The Advanced Server Dialect window

Use the drop-down listbox on the Advanced Server Dialect window to choose a server dialect. The server dialect specifies the compatibility features supported by Advanced Server.

By default, Advanced Server installs in Compatible with Oracle mode; you can choose between Compatible with Oracle and Compatible with PostgreSQL installation modes.

Compatible with Oracle

If you select Compatible with Oracle, the installation will include the following features:

- Data dictionary views that is compatible with Oracle databases.
- · Oracle data type conversions.
- Date values displayed in a format compatible with Oracle syntax.
- Support for Oracle-styled concatenation rules (if you concatenate a string value with a NULL value, the returned value is the value of the string).
- Schemas (dbo and sys) compatible with Oracle databases added to the SEARCH_PATH .
- · Support for the following Oracle built-in packages:

Package	Functionality compatible with Oracle Databases
dbms_alert	Provides the capability to register for, send, and receive alerts.
dbms_job	Provides the capability for the creation, scheduling, and managing of jobs.
dbms_lob	Provides the capability to manage on large objects.
dbms_output	Provides the capability to send messages to a message buffer, or get messages from the message buff
dbms_pipe	Provides the capability to send messages through a pipe within or between sessions connected to the s
dbms_rls	Enables the implementation of Virtual Private Database on certain Advanced Server database objects.
dbms_sql	Provides an application interface to the EnterpriseDB dynamic SQL functionality.
dbms_utility	Provides various utility programs.
dbms_aqadm	Provides supporting procedures for Advanced Queueing functionality.
dbms_aq	Provides message queueing and processing for Advanced Server.
dbms_profiler	Collects and stores performance information about the PL/pgSQL and SPL statements that are execute
dbms_random	Provides a number of methods to generate random values.
dbms_redact	Enables the redacting or masking of data that is returned by a query.
dbms_lock	Provides support for the DBMS_LOCK.SLEEP procedure.
dbms_scheduler	Provides a way to create and manage jobs, programs, and job schedules.
dbms_crypto	Provides functions and procedures to encrypt or decrypt RAW, BLOB or CLOB data. You can also use
dbms_mview	Provides a way to manage and refresh materialized views and their dependencies.
dbms_session	Provides support for the DBMS_SESSION.SET_ROLE procedure.
utl_encode	Provides a way to encode and decode data.
utl_http	Provides a way to use the HTTP or HTTPS protocol to retrieve information found at an URL.
utl_file	Provides the capability to read from, and write to files on the operating system's file system.
utl_smtp	Provides the capability to send e-mails over the Simple Mail Transfer Protocol (SMTP).
utl_mail	Provides the capability to manage e-mail.
utl_url	Provides a way to escape illegal and reserved characters within an URL.

This is not a comprehensive list of the compatibility features for Oracle included when Advanced Server is installed in Compatible with Oracle mode; for more information, see the *Database Compatibility for Oracle Developer's Guide* available from the EnterpriseDB website at:

Provides a way to manipulate or retrieve the length of raw data types.

https://www.enterprisedb.com/edb-docs

utl raw

If you choose to install in Compatible with Oracle mode, the Advanced Server superuser name is enterprisedb .

Compatible with PostgreSQL

If you select Compatible with PostgreSQL , Advanced Server will exhibit compatibility with PostgreSQL version 12. If you choose to install in Compatible with PostgreSQL mode, the default Advanced Server superuser name is postgres .

For detailed information about PostgreSQL functionality, visit the official PostgreSQL website at:

http://www.postgresql.org

After specifying a configuration mode, click Next to continue to the Password window.

The Password window

Advanced Server uses the password specified on the Password window for the database superuser. The specified password must conform to any security policies existing on the Advanced Server host.

After you enter a password in the Password field, confirm the password in the Retype Password field, and click Next to continue.

The Additional Configuration window opens.

The Additional Configuration window

Use the fields on the Additional Configuration window to specify installation details:

- Use the Port field to specify the port number that Advanced Server should listen to for connection requests from client applications. The default is 5444 .
- If the Locale field is set to [Default locale], Advanced Server uses the system locale as the working locale. Use the drop-down listbox next to Locale to specify an alternate locale for Advanced Server.
- By default, the Setup wizard installs corresponding sample data for the server dialect specified by the compatibility mode (Oracle or PostgreSQL) . Clear the check box next to Install sample tables and procedures if you do not wish to have sample data installed.

After verifying the information on the Additional Configuration window, click Next to open the Dynamic Tuning: Server Utilization window.

The graphical Setup wizard facilitates performance tuning via the Dynatune Dynamic Tuning feature. Dynatune functionality allows Advanced Server to make optimal usage of the system resources available on the host machine on which it is installed.

The Dynatune Dynamic Tuning: Server Utilization window

The edb_dynatune configuration parameter determines how Advanced Server allocates system resources. Use the radio buttons on the Server Utilization window to set the initial value of the edb_dynatune configuration parameter:

- Select Development to set the value of edb_dynatune to 33. A low value dedicates the least amount of the host machine's resources to the database server. This is a good choice for a development machine
- Select General Purpose to set the value of edb_dynatune to 66. A mid-range value dedicates a moderate amount of system resources to the database server. This would be a good setting for an application server with a fixed number of applications running on the same host as Advanced Server.
- Select Dedicated to set the value of edb_dynatune to 100. A high value dedicates most of the system resources to the database server. This is a good choice for a dedicated server host.

After the installation is complete, you can adjust the value of edb_dynatune by editing the postgresql.conf file, located in the data directory of your Advanced Server installation. After editing the postgresql.conf file, you must restart the server for your changes to take effect.

Select the appropriate setting for your system, and click Next to continue to the Dynatune Dynamic Tuning: Workloa window.

The Dynatune Dynamic Tuning: Workload Profile window

Use the radio buttons on the Workload Profile window to specify the initial value of the edb_dynatune_profile configuration parameter. The edb_dynatune_profile parameter controls performance-tuning aspects based on the type of work that the server performs.

- Select Transaction Processing (OLTP systems) to specify an edb_dynatune_profile value of oltp . Recommended when Advanced Server is supporting heavy online transaction processing.
- Select General Purpose (OLTP and reporting workloads) to specify an edb_dynatune_profile value of mixed . Recommended for servers that provide a mix of transaction processing and data reporting.
- Select Reporting (Complex queries or OLAP workloads) to specify an edb_dynatune_profile value of reporting. Recommended for database servers used for heavy data reporting.

After the installation is complete, you can adjust the value of edb_dynatune_profile by editing the postgresql.conf file, located in the data directory of your Advanced Server installation. After editing the postgresql.conf file, you must restart the server for your changes to take effect.

For more information about edb_dynatune and other performance-related topics, see the *EDB Postgres Advanced Server Guide* available from the EnterpriseDB website at:

https://www.enterprisedb.com/edb-docs

Click Next to continue. The Update Notification Service window opens.

The Update Notification Service window

When enabled, the update notification service notifies you of any new updates and security patches available for your installation of Advanced Server.

By default, Advanced Server is configured to start the service when the system boots; clear the Install Update Notification Service check box, or accept the default, and click Next to continue.

The Pre Installation Summary opens.

The Pre Installation Summary

The Pre Installation Summary provides an overview of the options specified during the Setup process. Review the options before clicking Next; click Back to navigate back through the dialogs and update any options.

The Ready to Install window confirms that the installer has the information it needs about your configuration preferences to install Advanced Server. Click Next to continue.

The Ready to Install window

Installing Advanced Server

As each supporting module is unpacked and installed, the module's installation is confirmed with a progress bar.

Before the Setup wizard completes the Advanced Server installation, it offers to Launch StackBuilder Plus at exit

The Setup wizard offers to Launch StackBuilder Plus at exit

You can clear the StackBuilder Plus check box and click Finish to complete the Advanced Server installation, or accept the default and proceed to StackBuilder Plus.

EDB Postgres StackBuilder Plus is included with the installation of Advanced Server and its core supporting components. StackBuilder Plus is a graphical tool that can update installed products, or download and add supporting modules (and the resulting dependencies) after your Advanced Server setup and installation completes. See [Using StackBuilder Plus](../02_installing_advanced_server_with_the_interactive_installer/03_using_stackbuilder_plus for more information about StackBuilder Plus.

2.2.2.0 Invoking the Graphical Installer from the Command Line

The command line options of the Advanced Server installer offer functionality for Windows systems that reside in situations where a graphical installation may not work because of limited resources or privileges. You can:

- Include the _-mode_unattended option when invoking the installer to perform an installation without user input.
- Invoke the installer with the --extract-only option to perform a minimal installation when you don't hold the privileges required to perform a complete installation.

Not all command line options are suitable for all situations. For a complete reference guide to the command line options, see [Reference - Command Line Options](../02_installing_advanced_server_with_the_interactive_installer/02_invo Note

If you are invoking the installer from the command line to perform a system upgrade, the installer will ignore command line options, and preserve the configuration of the previous installation.

2.2.2.1 Performing an Unattended Installation

To specify that the installer should run without user interaction, include the --mode unattended command line option. In unattended mode, the installer uses one of the following sources for configuration parameters:

- command line options (specified when invoking the installer)
- parameters specified in an option file
- · Advanced Server installation defaults

You can embed the non-interactive Advanced Server installer within another application installer; during the installation process, a progress bar allows the user to view the progression of the installation.

You must have administrative privileges to install Advanced Server using the --mode unattended option. If you are using the --mode unattended option to install Advanced Server with a client, the calling client must be invoked with superuser or administrative privileges.

To start the installer in unattended mode, navigate to the directory that contains the executable file, and enter:

edb-as12-server-12.x.x-x-windows-x64.exe --mode unattended --superpassword database_superuser_paservicepassword system_password

When invoking the installer, include the --servicepassword option to specify an operating system password for the user installing Advanced Server.

Use the --superpassword option to specify a password that conforms to the password security policies defined on the host; enforced password policies on your system may not accept the default password (enterprisedb).

2.2.2.2 Performing an Installation with Limited Privileges

To perform an abbreviated installation of Advanced Server without access to administrative privileges, invoke the installer from the command line and include the --extract-only option. The --extract-only option extracts the binary files in an unaltered form, allowing you to experiment with a minimal installation of Advanced Server.

If you invoke the installer with the --extract-only options, you can either manually create a cluster and start the service, or run the installation script. To manually create the cluster, you must:

- Use initdb to initialize the cluster
- Configure the cluster
- Use pg_ctl to start the service

For more information about the initdb and pg_ctl commands, please see the PostgreSQL Core Documentation at:

https://www.postgresql.org/docs/12/static/app-initdb.html https://www.postgresql.org/docs/12/static/app-pq-ctl.html

If you include the <code>--extract-only</code> option, the installer steps through a shortened form of the <code>Setup</code> wizard. During the brief installation process, the installer generates an installation script that can be later used to complete a more complete installation. You must have administrative privileges to invoke the installation script.

The installation script:

- · Initializes the database cluster if the cluster is empty.
- Configures the server to start at boot-time.
- Establishes initial values for Dynatune (dynamic tuning) variables.

The scripted Advanced Server installation does not create menu shortcuts or provide access to EDB Postgres StackBuilder Plus, and no modifications are made to registry files. The Advanced Server Update Monitor will not detect components installed by the scripted installation, and will not issue alerts for available updates to those components.

To perform a limited installation and generate an installation script, download and unpack the Advanced Server installer. Navigate into the directory that contains the installer, and invoke the installer with the command:

```
edb-as12-server-12.x.x-x-windows.exe --extract-only yes
```

A dialog opens, prompting you to choose an installation language. Select a language for the installation from the drop-down listbox, and click OK to continue. The Setup Wizard opens.

The Welcome window

Click Next to continue.

Specify an installation directory

On Windows, the default Advanced Server installation directory is:

```
C:\Program Files\edb\as12
```

You can accept the default installation location and click Next to continue to the Ready to Install window, or optionally click the File Browser icon to choose an alternate installation directory.

The Setup wizard is ready to install Advanced Server

Click Next to proceed with the Advanced Server installation. During the installation, progress bars and popups mark the installation progress. The installer notifies you when the installation is complete.

The Advanced Server installation is complete

After completing the minimal installation, you can execute a script to initialize a cluster and start the service. The script is (by default) located in:

```
C:\Program Files\edb
```

To execute the installation script, open a command line and assume administrative privileges. Navigate to the directory that contains the script, and execute the command:

cscript runAsAdmin.vbs

The installation script executes at the command line, prompting you for installation configuration information. The default configuration value is displayed in square braces immediately before each prompt; update the default value or press Enter to accept the default value and continue.

Performing a Scripted Installation

The following dialog is an example of a scripted installation. The actual installation dialog may vary, and will reflect the options specified during the installation.

Specify the installation directory is the directory where Advanced Server is installed:

```
Please enter the installation directory [ C:\Program Files\edb\as12 ] :
```

Specify the directory in which Advanced Server data will be stored:

```
Please enter the data directory path: [C:\Program Files\edb\as12\data ] :
```

Specify the WAL directory (where the write-ahead log will be written):

```
Please enter the Write-Ahead Log (WAL) directory path:
  [C:\Program Files\edb\as12\data\pg_wal]:
```

The database mode specifies the database dialect with which the Advanced Server installation is compatible. The optional values are oracle or postgresql.

```
Please enter database mode: [ oracle ] :
```

Compatible with Oracle Mode

Specify oracle mode to include the following functionality:

- Data dictionary views and data type conversions compatible with Oracle databases.
- Date values displayed in a format compatible with Oracle syntax.
- Oracle-styled concatenation rules (if you concatenate a string value with a NULL value, the returned value is the value of the string).
- Schemas (dbo and sys) compatible with Oracle databases added to the SEARCH_PATH .
- · Support for the Oracle built-in packages.

If you choose to install in Compatible with Oracle mode, the Advanced Server superuser name is enterprisedb .

Compatible with PostgreSQL Mode

Specify postgresql to install Advanced Server with complete compatibility with Postgres version 12.

For more information about PostgreSQL functionality, see the PostgreSQL Core Documentation available at:

```
https://www.enterprisedb.com/edb-docs
```

If you choose to install in Compatible with PostgreSQL mode, the Advanced Server superuser name is postgres .

Specify a port number for the Advanced Server listener to listen on:

```
NOTE: We will not be able to examine, if port is currently used by other application. Please enter port: [ 5444 ] :
```

Specify a locale for the Advanced Server installation. If you accept the DEFAULT value, the locale defaults to the locale of the host system.

```
Please enter the locale: [ DEFAULT ] :
```

You can optionally install sample tables and procedures. Press Return, or enter Y to accept the default and install the sample tables and procedures; enter an n and press Return to skip this step.

```
Install sample tables and procedures? (Y/n): [ Y ] :
```

Specify a password for the database superuser. By default, the database superuser is named enterprisedb

Please enter the password for the SuperUser(enterprisedb): [] :

Specify a password for the service account user.

Please enter the password for the ServiceAccount(enterprisedb): []:

The server utilization value is used as an initial value for the edb_dynatune configuration parameter. edb_dynatune determines how Advanced Server allocates system resources.

- A low value dedicates the least amount of the host machine's resources to the database server; a low value is a good choice for a development machine.
- A mid-range value dedicates a moderate amount of system resources to the database server. A midrange value is a good setting for an application server with a fixed number of applications running on the same host as Advanced Server.
- A high value dedicates most of the system resources to the database server. This is a good choice for a
 dedicated server host.

Specify a value between 1 and 100:

Please enter the Server Utilization: [66] :

After the installation is complete, you can adjust the value of edb_dynatune by editing the postgresql.conf file, located in the data directory of your Advanced Server installation. After editing the postgresql.conf file, you must restart the server for the changes to take effect.

The workload profile value is used as an initial value for the edb_dynatune_profile configuration parameter. edb_dynatune_profile controls performance-tuning based on the type of work that the server performs.

- Specify oltp if the server will be supporting heavy online transaction workloads.
- Specify mixed if the server will provide a mix of transaction processing and data reporting.
- Specify reporting if the database server will be used for heavy data reporting.

Specify a value between 1 and 100:

Please enter the Workload Profile: [oltp] :

After the installation is complete, you can adjust the value of edb_dynatune_profile by editing the postgresql.conf file, located in the data directory of your Advanced Server installation, and restarting the server.

After processing, the Advanced Server installation is complete.

2.2.2.3 Reference - Command Line Options

You can optionally include the following parameters for an Advanced Server installation on the command line, or in a configuration file when invoking the Advanced Server installer.

--create_samples { yes | no }

Use the --create_samples option to specify whether the installer should create the sample tables and procedures for the database dialect specified with the --databasemode parameter. The default is yes .

--databasemode { oracle | postgresql }

Use the --databasemode parameter to specify a database dialect. The default is oracle.

--datadir data_directory

Use the --datadir parameter to specify a location for the cluster's data directory. data_directory is the name of the directory; include the complete path to the desired directory.

--debuglevel { 0 | 1 | 2 | 3 | 4 }

Use the --debuglevel parameter to set the level of detail written to the debug_log file (see --debugtrace). Higher values produce more detail in a longer trace file. The default is 2.

--debugtrace debug_log

Use the --debugtrace parameter to troubleshoot installation problems. debug_log is the name of the file that contains troubleshooting details.

--disable-components component_list

Use the --disable-components parameter to specify a list of Advanced Server components to exclude from the installation. By default, component_list contains " (the empty string). component_list is a comma-separated list containing one or more of the following components:

dbserver

EDB Postgres Advanced Server 12.

pgadmin4

The EDB Postgres pgAdmin 4 provides a powerful graphical interface for database management and monitoring.

--enable_acledit { 1 | 0 }

The --enable_acledit 1 option instructs the installer to grant permission to the user specified by the --serviceaccount option to access the Advanced Server binaries and data directory. By default, this option is disabled if --enable_acledit 0 is specified or if the --enable_acledit option is completely omitted.

Note

Specification of this option is valid only when installing on Windows. The --enable_acledit 1 option should be specified when a discretionary access control list (DACL) needs to be set for allowing access to objects on which Advanced Server is to be installed. See the following for information on a DACL:

https://msdn.microsoft.com/en-us/library/windows/desktop/aa446597(v=vs.85).aspx

In order to perform future operations such as upgrading Advanced Server, access to the data directory must exist for the service account user specified by the --serviceaccount option. By specifying the --enable_acledit 1 option, access to the data directory by the service account user is provided.

--enable-components component_list

Although this option is listed when you run the installer with the --help option, the --enable-components parameter has absolutely no effect on which components are installed. All components will be installed regardless of what is specified in component_list. In order to install only specific selected components, you must use the --disable-components parameter previously described in this section to list the components you do not want to install.

--extract-only { yes | no }

Include the --extract-only parameter to indicate that the installer should extract the Advanced Server binaries without performing a complete installation. Superuser privileges are not required for the --extract-only option. The default value is no .

--help

Include the --help parameter to view a list of the optional parameters.

```
--installer-language { en | ja | zh_CN | zh_TW | ko }
```

Use the --installer-language parameter to specify an installation language for Advanced Server. The default is en .

en specifies English.

ja specifies Japanese

zh_CN specifies Chinese Simplified.

zh_TW specifies Traditional Chinese.

ko specifies Korean.

--install_runtimes { yes | no } (Windows only.)

Include --install_runtimes to specify whether the installer should install the Microsoft Visual C++ runtime libraries. Default is yes .

--locale locale

Specifies the locale for the Advanced Server cluster. By default, the installer will use to the locale detected by initdb.

--mode { unattended }

Use the --mode unattended parameter to specify that the installer should perform an installation that requires no user input during the installation process.

--optionfile config_file

Use the --optionfile parameter to specify the name of a file that contains the installation configuration parameters. config_file must specify the complete path to the configuration parameter file.

--prefix installation_dir/as12.x

Use the --prefix parameter to specify an installation directory for Advanced Server. The installer will append a version-specific sub-directory (that is, as12) to the specified directory. The default installation directory is:

C:\Program Files\edb\as12

--serverport port_number

Use the --serverport parameter to specify a listener port number for Advanced Server.

If you are installing Advanced Server in unattended mode, and do not specify a value using the --serverport parameter, the installer will use port 5444, or the first available port after port 5444 as the default listener port.

--server_utilization {33 | 66 | 100}

Use the --server_utilization parameter to specify a value for the edb_dynatune configuration parameter. The edb_dynatune configuration parameter determines how Advanced Server allocates system resources.

 A value of 33 is appropriate for a system used for development. A low value dedicates the least amount of the host machine's resources to the database server.

- A value of 66 is appropriate for an application server with a fixed number of applications. A mid-range value dedicates a moderate amount of system resources to the database server. The default value is 66.
- A value of 100 is appropriate for a host machine that is dedicated to running Advanced Server. A high value dedicates most of the system resources to the database server.

When the installation is complete, you can adjust the value of edb_dynatune by editing the postgresql.conf file, located in the data directory of your Advanced Server installation. After editing the postgresql.conf file, you must restart the server for the changes to take effect.

--serviceaccount user_account_name

Use the --serviceaccount parameter to specify the name of the user account that owns the server process.

- If --databasemode is set to oracle (the default), the default value of --service account is enterprisedb .
- If --databasemode is postgresql , the default value of --serviceaccount is set to postgres .

Please note that for security reasons, the --serviceaccount parameter must specify the name of an account that does not hold administrator privileges.

If you specify both the --serviceaccount option and the --enable_acledit 1 option when invoking the installer, the database service and pgAgent will use the same service account, thereby having the required permissions to access the Advanced Server binaries and data directory.

Note

Specification of the --enable_acledit option is permitted only when installing on Windows.

Note

If you do not include the --serviceaccount option when invoking the installer, the NetworkService account will own the database service, and the pgAgent service will be owned by either enterprised or postgres (depending on the installation mode).

--servicename service_name

Use the --servicename parameter to specify the name of the Advanced Server service. The default is edb-as-12.

--servicepassword user_password

Use --servicepassword to specify the OS system password. If unspecified, the value of --servicepassword defaults to the value of --superpassword .

--superaccount super_user_name

Use the --superaccount parameter to specify the user name of the database superuser.

- If --databasemode is set to oracle (the default), the default value of --superaccount is enterprisedb .
- If --databasemode is set to postgresql , the default value of --superaccount is set to postgres .

--superpassword superuser_password

Use --superpassword to specify the database superuser password. If you are installing in non-interactive mode, --superpassword defaults to enterprisedb.

--unattendedmodeui { none | minimal | minimalWithDialogs }

Use the --unattendedmodeui parameter to specify installer behavior during an unattended installation.

Include --unattendedmodeui none to specify that the installer should not display progress bars during the Advanced Server installation.

Include --unattendedmodeui minimal to specify that the installer should display progress bars during the installation process. This is the default behavior.

Include --unattendedmodeui minimalWithDialogs to specify that the installer should display progress bars and report any errors encountered during the installation process (in additional dialogs).

--version

Include the --version parameter to retrieve version information about the installer:

EDB Postgres Advanced Server 12 --- Built on 2018-03-15 00:04:00 IB: 15.12.1-201511121057

```
--workload_profile {oltp | mixed | reporting}
```

Use the --workload_profile parameter to specify an initial value for the edb_dynatune_profile configuration parameter. edb_dynatune_profile controls aspects of performance-tuning based on the type of work that the server performs.

- Specify oltp if the Advanced Server installation will be used to support heavy online transaction processing workloads.
- The default value is oltp .
- Specify mixed if Advanced Server will provide a mix of transaction processing and data reporting.
- Specify reporting if Advanced Server will be used for heavy data reporting.

After the installation is complete, you can adjust the value of edb_dynatune_profile by editing the postgresql.conf file, located in the data directory of your Advanced Server installation.

After editing the postgresql.conf file, you must restart the server for the changes to take effect.

For more information about edb_dynatune and other performance-related topics, see the EDB Postgres Advanced Server Guide available at:

https://www.enterprisedb.com/edb-docs

2.2.3 Using StackBuilder Plus

Please note: StackBuilder Plus is supported only on Windows systems.

The StackBuilder Plus utility provides a graphical interface that simplifies the process of updating, downloading, and installing modules that complement your Advanced Server installation. When you install a module with StackBuilder Plus, StackBuilder Plus automatically resolves any software dependencies.

You can invoke StackBuilder Plus at any time after the installation has completed by selecting the StackBuilder Plus menu option from the Apps menu. Enter your system password (if prompted), and the StackBuilder Plus welcome window opens.

The StackBuilder Plus welcome window

Use the drop-down listbox on the welcome window to select your Advanced Server installation.

StackBuilder Plus requires Internet access; if your installation of Advanced Server resides behind a firewall (with restricted Internet access), StackBuilder Plus can download program installers through a proxy server. The module provider determines if the module can be accessed through an HTTP proxy or an FTP proxy; currently, all updates are transferred via an HTTP proxy and the FTP proxy information is not used.

If the selected Advanced Server installation has restricted Internet access, use the Proxy Servers on the Welcome window to open the Proxy servers dialog.

The Proxy Servers dialog

Enter the IP address and port number of the proxy server in the HTTP proxy on the Proxy Servers dialog. Currently, all StackBuilder Plus modules are distributed via HTTP proxy (FTP proxy information is ignored). Click 0K to continue.

The StackBuilder Plus module selection window

The tree control on the StackBuilder Plus module selection window displays a node for each module category.

Expand a module, and highlight a component name in the tree control to review a detailed description of the component. To add one or more components to the installation or to upgrade a component, check the box to the left of a module name and click Next.

StackBuilder Plus confirms the packages selected.

A summary window displays a list of selected packages

Use the browse icon (...) to the right of the Download directory field to open a file selector, and choose an alternate location to store the downloaded installers. Click Next to connect to the server and download the required installation files.

When the download completes, a window opens that confirms the installation files have been downloaded and are ready for installation.

Confirmation that the download process is complete

You can check the box next to Skip Installation, and select Next to exit StackBuilder Plus without installing the downloaded files, or leave the box unchecked and click Next to start the installation process.

Each downloaded installer has different requirements. As the installers execute, they may prompt you to confirm acceptance of license agreements, to enter passwords, and provide configuration information.

During the installation process, you may be prompted by one (or more) of the installers to restart your system. Select No or Restart Later until all installations are completed. When the last installation has completed, reboot the system to apply all of the updates.

You may occasionally encounter packages that don't install successfully. If a package fails to install, Stack-Builder Plus will alert you to the installation error with a popup dialog, and write a message to the log file at %TEMP%.

StackBuilder Plus confirms the completed installation

When the installation is complete, StackBuilder Plus will alert you to the success or failure of the installations of the requested packages. If you were prompted by an installer to restart your computer, reboot now.

2.2.4 Using the Update Monitor

The Update Monitor utility polls the EnterpriseDB website and alerts you to security updates and enhancements for Windows hosts as they become available. Update Monitor is automatically installed by the graphical installer.

When Update Monitor is actively monitoring, the Postgres elephant icon is displayed in the system tray.

The Update Monitor icon

If you have installed more than one version of Advanced Server, Update Monitor watches for updates and alerts for all installed versions. When Update Monitor finds an update or alert, it displays an alert symbol to let you know that an update or alert is available for one of the Advanced Server installations.

The Update Monitor icon displays an alert

Right click on the symbol to access the Update Monitor context menu.

The Update Monitor context menu

Click Install components to open StackBuilder Plus, and check for component updates. See [Using StackBuilder Plus](../02_installing_advanced_server_with_the_interactive_installer/03_using_stackbuilder_plus#using_stackbuild

If one or more alerts are available for your Advanced Server installation, the context menu displays the alert count. Select View alerts to display the EnterpriseDB Advanced Server Alerts window.

An EnterpriseDB Technical alert

The technical alert will provide information about updates and issues that might impact your installation.

- Click Run StackBuilder Plus to open StackBuilder Plus and install relevant software updates.
- · Click Next to access each successive alert.

When you have reviewed all of the alerts, the icon no longer displays the alert symbol; use the X icon in the upper-right corner of the dialog to close Update Monitor.

2.2.5 Installation Troubleshooting

Difficulty Displaying Java-based Applications

If you encounter difficulty displaying Java-based server features (controls or text not being displayed correctly, or blank windows), upgrading to the latest libxcb-xlib libraries should correct the problem on most distributions. Please visit the following link for other possible work-arounds:

http://bugs.sun.com/bugdatabase/view_bug.do?bug_id=6532373

--mode unattended Authentication Errors

Authentication errors from component modules during unattended installations may indicate that the specified values of --servicepassword or --superpassword may be incorrect.

Errors During an Advanced Server Installation

If you encounter an error during the installation process, exit the installation, and ensure that your version of Windows is up-to-date. After applying any outstanding operating system updates, re-invoke the Advanced Server installer.

The Installation Fails to Complete Due to Existing Data Directory Contents

If an installation fails to complete due to existing content in the data directory, the server will write an error message to the server logs:

A data directory is neither empty, or a recognisable data directory.

If you encounter a similar message, you should confirm that the data directory is empty; the presence of files (including the system-generated lost+found folder) will prevent the installation from completing. Either remove the files from the data directory, or specify a different location for the data directory before re-invoking the installer to complete the installation.

2.3.0 Managing an Advanced Server Installation

Unless otherwise noted, the commands and paths noted in the following section assume that you have performed an installation with the interactive installer.

Starting and Stopping Advanced Server and Supporting Components

A service is a program that runs in the background and requires no user interaction (in fact, a service provides no user interface); a service can be configured to start at boot time, or manually on demand. Services are best controlled using the platform-specific operating system service control utility. Many of the Advanced Server supporting components are services.

The following table lists the names of the services that control Advanced Server and services that control Advanced Server supporting components:

Advanced Server Component Name	Windows Service Name
Advanced Server pgAgent PgBouncer Slony	edb-as-12 EDB Postgres Advanced Server 12 Scheduling Agent edb-pgbouncer-1.12 edb-slony-replication-12

You can use the command line or the Windows Services applet to control Advanced Server's database server and the services of Advanced Server's supporting components on a Windows host.

2.3.1 'Using the Windows Services Applet'

The Windows operating system includes a graphical service controller that offers control of Advanced Server and the services associated with Advanced Server components. The Services utility can be accessed through the Administrative Tools section of the Windows Control Panel.

The Advanced Server service in the Windows Services window

The Services window displays an alphabetized list of services; the edb-as-12 service controls Advanced Server.

- Use the Stop the service option to stop the instance of Advanced Server. Please note that any user (or client application) connected to the Advanced Server instance will be abruptly disconnected if you stop the service.
- Use the Start the service option to start the Advanced Server service.
- Use the Pause the service option to tell Advanced Server to reload the server configuration parameters without disrupting user sessions for many of the configuration parameters. See [Configuring Advanced Server](../04_configuring_advanced_server/#configuring_advanced_server) for more information about the parameters that can be updated with a server reload.
- Use the Restart the service option to stop and then start the Advanced Server. Please note that any user sessions will be terminated when you stop the service. This option is useful to reset server parameters that only take effect on server start.

2.3.2 Using pg_ctl to Control Advanced Server

You can use the pg_ctl utility to control an Advanced Server service from the command line on any platform. pg_ctl allows you to start, stop, or restart the Advanced Server database server, reload the configuration parameters, or display the status of a running server. To invoke the utility, assume the identity of the cluster owner, navigate into the home directory of Advanced Server, and issue the command:

./bin/pg_ctl -D data_directory action

data_directory

data_directory is the location of the data controlled by the Advanced Server cluster.

action

action specifies the action taken by the pg_ctl utility. Specify:

- start to start the service.
- stop to stop the service.
- restart to stop and then start the service.
- reload sends the server a SIGHUP signal, reloading configuration parameters
- status to discover the current status of the service.

For more information about using the pg_ctl utility, or the command line options available, please see the official PostgreSQL Core Documentation available at:

https://www.postgresql.org/docs/12/static/app-pg-ctl.html

2.3.3 Controlling Server Startup Behavior on Windows

You can use the Windows Services utility to control the startup behavior of the server. Right click on the name of the service you wish to update, and select Properties from the context menu to open the Properties dialog.

Use the drop-down listbox in the Startup type field to specify how the Advanced Server service will behave when the host starts.

Specifying Advanced Server's startup behavior

- Specify Automatic (Delayed Start) to instruct the service controller to start after boot.
- Specify Automatic to instruct the service controller to start and stop the server whenever the system starts or stops.
- Specify Manual to instruct the service controller that the server must be started manually.
- Specify Disabled to instruct the service controller to disable the service; after disabling the service, you must stop the service or restart the server to make the change take effect. Once disabled, the server's status cannot be changed until Startup type is reset to Automatic (Delayed Start)

,	Automatic	, or	Manual
		,	

2.4.0 Configuring Advanced Server

You can easily update parameters that determine the behavior of Advanced Server and supporting components by modifying the following configuration files:

- The postgresql.conf file determines the initial values of Advanced Server configuration parameters.
- The pq_hba.conf file specifies your preferences for network authentication and authorization.
- The pg_ident.conf file maps operating system identities (user names) to Advanced Server identities (roles) when using ident -based authentication.

You can use your editor of choice to open a configuration file, or on Windows navigate through the EDB Postgres menu to open a file.

Accessing the configuration files through the Windows system menu

2.4.1 Modifying the postgresql.conf File

Configuration parameters in the postgresql.conf file specify server behavior with regards to auditing, authentication, encryption, and other behaviors. The postgresql.conf file resides in the data directory under your Advanced Server installation.

The postgresql.conf file

Parameters that are preceded by a pound sign (#) are set to their default value (as shown in the parameter setting). To change a parameter value, remove the pound sign and enter a new value. After setting or changing a parameter, you must either *reload* or *restart* the server for the new parameter value to take effect.

Within the postgresql.conf file, some parameters contain comments that indicate change requires restart. To view a list of the parameters that require a server restart, execute the following query at the psql command line:

SELECT name FROM pg_settings WHERE context = 'postmaster';

2.4.2 Modifying the pg hba.conf File

Appropriate authentication methods provide protection and security. Entries in the pg_hba.conf file specify the authentication method or methods that the server will use when authenticating connecting clients. Before connecting to the server, you may be required to modify the authentication properties specified in the pg_hba.conf file.

When you invoke the initdb utility to create a cluster, initdb creates a pg_hba.conf file for that cluster that specifies the type of authentication required from connecting clients. The following figure displays the default authentication configuration specified in the pg_hba.conf file.

The pg_hba.conf file

To modify the pg_hba.conf file, open the file with your choice of editor. After modifying the authentication settings in the pg_hba.conf file, use the Windows services utility to restart the server and apply the changes.

For more information about authentication, and modifying the pg_hba.conf file, see the PostgreSQL Core Documentation at:

https://www.postgresql.org/docs/12/static/auth-pg-hba-conf.html

2.4.3 Setting Advanced Server Environment Variables

The graphical installer provides a script that simplifies the task of setting environment variables for Windows users. The script sets the environment variables for your current shell session; when your shell session ends, the environment variables are destroyed. You may wish to invoke pgplus_env.bat from your system-wide shell startup script, so that environment variables are automatically defined for each shell session.

The pgplus_env script is created during the Advanced Server installation process and reflects the choices made during installation. To invoke the script, open a command line and enter:

C:\Program Files\edb\as12\pgplus_env.bat

As the pgplus_env.bat script executes, it sets the following environment variables:

PATH="C:\Program Files\edb\as12\bin";%PATH%

EDBHOME=C:\Program Files\edb\as12

PGDATA=C:\Program Files\edb\as12\data

PGDATABASE=edb

REM @SET PGUSER=enterprisedb

PGPORT=5444

PGLOCALEDIR=C:\Program Files\edb\as12\share\locale

If you have used an installer created by EnterpriseDB to install PostgreSQL, the pg_env script performs the same function:

C:\Progra~1\PostgreSQL\12\pg_env.bat

As the pg_env.bat script executes on PostgreSQL, it sets the following environment variables:

PATH="C:\Program Files\PostgreSQL\12\bin";%PATH%

PGDATA=C:\Program Files\PostgreSQL\12\data

PGDATABASE=postgres PGUSER=postgres PGPORT=5432

PGLOCALEDIR=C:\Program Files\PostgreSQL\12\share\locale

2.4.4 Connecting to Advanced Server with psql

psql is a command line client application that allows you to execute SQL commands and view the results. To open the psql client, the client must be in your search path. The executable resides in the bin directory, under your Advanced Server installation.

Use the following command and options to start the psql client:

psql -d edb -U enterprisedb

Connecting to the server

Where:

- -d specifies the database to which psql will connect;
- -U specifies the identity of the database user that will be used for the session.

If you have performed an installation with the interactive installer, you can access the psql client by selecting EDB-PSQL from the EDB Postgres menu. When the client opens, provide connection information for your session.

For more information about using the command line client, please refer to the PostgreSQL Core Documentation at:

https://www.postgresql.org/docs/12/static/app-psql.html

2.4.5 Connecting to Advanced Server with the pgAdmin 4 Client

pgAdmin 4 provides an interactive graphical interface that you can use to manage your database and database objects. Easy-to-use dialogs and online help simplify tasks such as object creation, role management, and granting or revoking privileges. The tabbed browser panel provides quick access to information about the object currently selected in the pgAdmin tree control.

The client is distributed with the graphical installer. To open pgAdmin, select pgAdmin4 from the EDB Postgres menu. The client opens in your default browser.

The pgAdmin 4 client Dashboard

To connect to the Advanced Server database server, expand the Servers node of the Browser tree control, and right click on the EDB Postgres Advanced Server node. When the context menu opens, select Connect Server . The Connect to Server dialog opens.

The Connect to Server dialog

Provide the password associated with the database superuser in the Password field, and click OK to connect.

Connecting to an Advanced Server database

When the client connects, you can use the Browser tree control to retrieve information about existing database objects, or to create new objects. For more information about using the pgAdmin client, use the Help drop-down menu to access the online help files.

59

2.5 Uninstalling Advanced Server

Note that after uninstalling Advanced Server, the cluster data files remain intact and the service user persists. You may manually remove the cluster data and service user from the system.

Using Advanced Server Uninstallers at the Command Line

The Advanced Server interactive installer creates an uninstaller that you can use to remove Advanced Server or components that reside on a Windows host. The uninstaller is created in C:\Program Files\edb\as12 . To open the uninstaller, assume superuser privileges, navigate into the directory that contains the uninstaller, and enter:

uninstall-edb-as12-server.exe

The uninstaller opens.

The Advanced Server uninstaller

You can remove the Entire application (the default), or select the radio button next to Individual components to select components for removal; if you select Individual components, a dialog will open, prompting you to select the components you wish to remove. After making your selection, click Next.

Acknowledge that dependent components are removed first

If you have elected to remove components that are dependent on Advanced Server, those components will be removed first; click Yes to acknowledge that you wish to continue.

Progress bars are displayed as the software is removed. When the uninstallation is complete, an Info dialog opens to confirm that Advanced Server (and/or its components) has been removed.

The uninstallation is complete		

2.6 Conclusion

EDB Postgres Advanced Server Installation Guide for Windows

Copyright © 2007 - 2020 EnterpriseDB Corporation. All rights reserved.

EnterpriseDB Corporation 34 Crosby Drive, Suite 201, Bedford, MA 01730, USA

T +1 781 357 3390 F +1 978 467 1307 E info@enterprisedb.com www.enterprisedb.com

- EDB designs, establishes coding best practices, reviews, and verifies input validation for the logon UI for EDB products where present. EDB follows the same approach for additional input components, however the nature of the product may require that it accepts freeform SQL, WMI or other strings to be entered and submitted by trusted users for which limited validation is possible. In such cases it is not possible to prevent users from entering incorrect or otherwise dangerous inputs.
- EDB reserves the right to add features to products that accept freeform SQL, WMI or other potentially dangerous inputs from authenticated, trusted users in the future, but will ensure all such features are designed and tested to ensure they provide the minimum possible risk, and where possible, require superuser or equivalent privileges.
- EDB does not that warrant that we can or will anticipate all potential threats and therefore our process cannot fully guarantee that all potential vulnerabilities have been addressed or considered.

3.0 EDB Postgres Advanced Server Upgrade Guide

The EDB Postgres Advanced Server Upgrade Guide is a comprehensive guide about upgrading EDB Postgres Advanced Server (Advanced Server). In this guide you will find detailed information about using:

- pg_upgrade to upgrade from an earlier version of Advanced Server to Advanced Server 12.
- yum to perform a minor version upgrade on a Linux host.

StackBuilder Plus to perform a minor version upgrade on a Windows host.

3.1 Supported Platforms

Advanced Server version 12 is supported on the following platforms:

64 bit Linux:

- Red Hat Enterprise Linux (x86_64) 6.x and 7.x
- CentOS (x86 64) 6.x and 7.x
- OEL Linux 6.x and 7.x
- PPC-LE 8 running RHEL or CentOS 7.x
- SLES 12

64 bit Windows platforms:

- · Windows Server 2016
- Windows Server 2012 R2
- · Windows Server 2019

3.2 Limitations

- The data directory of a production database should not be stored on an NFS file system.
- The pg_upgrade utility cannot upgrade a partitioned table if a foreign key refers to the partitioned table.
- If you are upgrading from the version 9.4 server or a lower version of Advanced Server, and you use partitioned tables that include a SUBPARTITION BY clause, you must use pg_dump and pg_restore to upgrade an existing Advanced Server installation to a later version of Advanced Server. To upgrade, you must:
 - 1. Use pq_dump to preserve the content of the subpartitioned table.
 - 2. Drop the table from the Advanced Server 9.4 database or a lower version of Advanced Server database.
 - 3. Use pg_upgrade to upgrade the rest of the Advanced Server database to a more recent version.
 - 4. Use pg_restore to restore the subpartitioned table to the latest upgraded Advanced Server database.
- If you perform an upgrade of the Advanced Server installation, you must rebuild any hash-partitioned table on the upgraded server.

3.3.0 Upgrading an Installation With pg upgrade

While minor upgrades between versions are fairly simple and require only the installation of new executables, past major version upgrades has been both expensive and time consuming. pg_upgrade facilitates migration between any version of Advanced Server (version 9.0 or later), and any subsequent release of Advanced Server that is supported on the same platform.

Without pg_upgrade , to migrate from an earlier version of Advanced Server to Advanced Server 12, you must export all of your data using pg_dump , install the new release, run initdb to create a new cluster, and then import your old data.

pg_upgrade can reduce both the amount of time required and the disk space required for many major-version upgrades.

The pg_upgrade utility performs an in-place transfer of existing data between Advanced Server and any subsequent version.

Several factors determine if an in-place upgrade is practical:

- The on-disk representation of user-defined tables must not change between the original version and the upgraded version.
- The on-disk representation of data types must not change between the original version and the upgraded version.
- To upgrade between major versions of Advanced Server with pg_upgrade , both versions must share a common binary representation for each data type. Therefore, you cannot use pg_upgrade to migrate from a 32-bit to a 64-bit Linux platform.

Before performing a version upgrade, pg_upgrade will verify that the two clusters (the old cluster and the new cluster) are compatible.

If the upgrade involves a change in the on-disk representation of database objects or data, or involves a change in the binary representation of data types, pg_upgrade will be unable to perform the upgrade; to upgrade, you will have to pg_dump the old data and then import that data into the new cluster.

The pg_upgrade executable is distributed with Advanced Server 12, and is installed as part of the Database Server component; no additional installation or configuration steps are required.

3.3.1.0 Performing an Upgrade

To upgrade an earlier version of Advanced Server to the current version, you must:

- Install the current version of Advanced Server. The new installation must contain the same supporting server components as the old installation.
- Empty the target database or create a new target cluster with initdb.
- Place the pg_hba.conf file for both databases in trust authentication mode (to avoid authentication conflicts).
- · Shut down the old and new Advanced Server services.
- Invoke the pg_upgrade utility.

When pg_upgrade starts, it performs a compatibility check to ensure that all required executables are present and contain the expected version numbers. The verification process also checks the old and new \$PGDATA directories to ensure that the expected files and subdirectories are in place. If the verification process succeeds, pg_upgrade starts the old postmaster and runs pg_dumpall --schema-only to capture the metadata contained in the old cluster. The script produced by pg_dumpall is used in a later step to recreate all user-defined objects in the new cluster.

Note that the script produced by pg_dumpall recreates only user-defined objects and not system-defined objects. The new cluster will *already* contain the system-defined objects created by the latest version of Advanced Server.

After extracting the metadata from the old cluster, pg_upgrade performs the bookkeeping tasks required to sync the new cluster with the existing data.

pg_upgrade runs the pg_dumpall script against the new cluster to create (empty) database objects of the same shape and type as those found in the old cluster. Then, pg_upgrade links or copies each table and index from the old cluster to the new cluster.

If you are upgrading from a version of Advanced Server prior to 9.5 to Advanced Server 12 and have installed the edb_dblink_oci or edb_dblink_libpq extension, you must drop the extension before performing an upgrade. To drop the extension, connect to the server with the psql or PEM client, and invoke the commands:

```
DROP EXTENSION edb_dblink_oci;
DROP EXTENSION edb_dblink_libpq;
```

When you have completed upgrading, you can use the CREATE EXTENSION command to add the current versions of the extensions to your installation.

3.3.1.1 Linking versus Copying

When invoking pg_upgrade, you can use a command-line option to specify whether pg_upgrade should copy or *link* each table and index in the old cluster to the new cluster.

Linking is much faster because pg_upgrade simply creates a second name (a hard link) for each file in the cluster; linking also requires no extra workspace because pg_upgrade does not make a copy of the original data. When linking the old cluster and the new cluster, the old and new clusters share the data; note that after starting the new cluster, your data can no longer be used with the previous version of Advanced Server.

If you choose to copy data from the old cluster to the new cluster, <code>pg_upgrade</code> will still reduce the amount of time required to perform an upgrade compared to the traditional <code>dump/restore</code> procedure. <code>pg_upgrade</code> uses a file-at-a-time mechanism to copy data files from the old cluster to the new cluster (versus the row-by-row mechanism used by <code>dump/restore</code>). When you use <code>pg_upgrade</code>, you avoid building indexes in the new cluster; each index is simply copied from the old cluster to the new cluster. Finally, using a <code>dump/restore</code> procedure to upgrade requires a great deal of workspace to hold the intermediate text-based dump of all of your data, while <code>pg_upgrade</code> requires very little extra workspace.

Data that is stored in user-defined tablespaces is not copied to the new cluster; it stays in the same location in the file system, but is copied into a subdirectory whose name reflects the version number of the new cluster. To manually relocate files that are stored in a tablespace after upgrading, move the files to the new location and update the symbolic links (located in the pg_tblspc directory under your cluster's data directory) to point to the files.

3.3.2.0 Invoking pg_upgrade

When invoking pg_upgrade , you must specify the location of the old and new cluster's PGDATA and executable (/bin) directories, as well as the name of the Advanced Server superuser, and the ports on which the installations are listening. A typical call to invoke pg_upgrade to migrate from Advanced Server 11 to Advanced Server 12 takes the form:

pq_upgrade

- --old-datadir <path_to_11_data_directory>
- --new-datadir <path_to_12_data_directory>
- --user <superuser_name>
- --old-bindir <path_to_11_bin_directory>
- --new-bindir <path_to_12_bin_directory>
- --old-port <11_port> --new-port <12_port>

Where:

[--old-datadir](#path_to_11_data_directory)

Use the --old-datadir option to specify the complete path to the data directory within the Advanced Server 11 installation.

[--new-datadir](#path_to_12_data_directory)

Use the --new-datadir option to specify the complete path to the data directory within the Advanced Server 12 installation.

[--username](#superuser_name)

Include the --username option to specify the name of the Advanced Server superuser. The superuser name should be the same in both versions of Advanced Server. By default, when Advanced Server is installed in Oracle mode, the superuser is named enterprisedb. If installed in PostgreSQL mode, the superuser is named postgres.

If the Advanced Server superuser name is not the same in both clusters, the clusters will not pass the pg_upgrade consistency check.

```
[--old-bindir](#path_to_11_bin_directory)
```

Use the --old-bindir option to specify the complete path to the bin directory in the Advanced Server 11 installation.

```
[--new-bindir](#path_to_12_bin_directory)
```

Use the --new-bindir option to specify the complete path to the bin directory in the Advanced Server 12 installation.

```
[--old-port](#11_port)
```

Include the --old-port option to specify the port on which Advanced Server 11 listens for connections.

```
[--new-port](#12_port)
```

Include the --new-port option to specify the port on which Advanced Server 12 listens for connections.

3.3.2.1 Command Line Options - Reference

pg_upgrade accepts the following command line options; each option is available in a long form or a short form:

[-b](#path_to_old_bin_directory)

[--old-bindir](#path_to_old_bin_directory)

Use the -b or --old-bindir keyword to specify the location of the old cluster's executable directory.

[-B](#path_to_new_bin_directory)

[--new-bindir](#path_to_new_bin_directory)

Use the -B or --new-bindir keyword to specify the location of the new cluster's executable directory.

- C

--check

Include the -c or --check keyword to specify that pg_upgrade should perform a consistency check on the old and new cluster without performing a version upgrade.

[-d](#path_to_old_data_directory)

[--old-datadir](#path_to_old_data_directory)

Use the -d or --old-datadir keyword to specify the location of the old cluster's data directory.

[-D](#path_to_new_data_directory)

[--new-datadir](#path_to_new_data_directory)

Use the -D or --new-datadir keyword to specify the location of the new cluster's data directory.

Data that is stored in user-defined tablespaces is not copied to the new cluster; it stays in the same location in the file system, but is copied into a subdirectory whose name reflects the version number of the new cluster. To manually relocate files that are stored in a tablespace after upgrading, you must move the files to the new location and update the symbolic links (located in the pg_tblspc directory under your cluster's data directory) to point to the files.

-j

--jobs

Include the -j or --jobs keyword to specify the number of simultaneous processes or threads to use during the upgrade.

-k

--link

Include the -k or --link keyword to create a hard link from the new cluster to the old cluster.

See [Linking versus Copying](../../03_upgrading_an_installation_with_pg_upgrade/01_performing_an_upgrade/01_lir for more information about using a symbolic link.

[-o](#options)

[--old-options](#options)

Use the _o or _-old-options keyword to specify options that will be passed to the old postgres command. Enclose options in single or double quotes to ensure that they are passed as a group.

[-O](#options)

[--new-options](#options)

Use the -0 or --new-options keyword to specify options to be passed to the new postgres command. Enclose options in single or double quotes to ensure that they are passed as a group.

[-p](#old_port_number)

[--old-port](#old_port_number)

Include the -p or --old-port keyword to specify the port number of the Advanced Server installation that you are upgrading.

[-P](#new port number)

[--new-port](#new_port_number)

Include the P or --new-port keyword to specify the port number of the new Advanced Server installation.

Note

If the original Advanced Server installation is using port number 5444 when you invoke the Advanced Server 12 installer, the installer will recommend using listener port 5445 for the new installation of Advanced Server.

-r

--retain

During the upgrade process, pg_upgrade creates four append-only log files; when the upgrade is completed, pg_upgrade deletes these files. Include the -r or --retain option to specify that the server should retain the pg_upgrade log files.

[-U](#user_name)

[--username](#user_name)

Include the -U or --username keyword to specify the name of the Advanced Server database superuser. The same superuser must exist in both clusters.

-V

--verbose

Include the -v or --verbose keyword to enable verbose output during the upgrade process.

```
-V
-version
Use the -V or --version keyword to display version information for pg_upgrade .
-?
-h
--help
Use -?, -h or --help options to display pg_upgrade help information.
```

3.3.3 Upgrading to Advanced Server 12

You can use pg_upgrade to upgrade from an existing installation of Advanced Server into the cluster built by the Advanced Server 12 installer or into an alternate cluster created using the initdb command. In this section, we will provide the details of upgrading into the cluster provided by the installer.

The basic steps to perform an upgrade into an empty cluster created with the <code>initdb</code> command are the same as the steps to upgrade into the cluster created by the Advanced Server 12 installer, but you can omit Step 2 (*Empty the* edb database), and substitute the location of the alternate cluster when specifying a target cluster for the upgrade.

If a problem occurs during the upgrade process, you can revert to the previous version. See [Reverting to the old cluster](../03_upgrading_an_installation_with_pg_upgrade/06_reverting_to_the_old_cluster#reverting_to_the_old_cluster) Section for detailed information about this process.

You must be an operating system superuser or Windows Administrator to perform an Advanced Server upgrade.

Step 1 - Install the New Server

Install Advanced Server 12, specifying the same non-server components that were installed during the previous Advanced Server installation.

The new cluster and the old cluster must reside in different directories.

Step 2 - Empty the target database

The target cluster must not contain any data; you can create an empty cluster using the initdb command, or you can empty a database that was created during the installation of Advanced Server 12. If you have installed Advanced Server in PostgreSQL mode, the installer creates a single database named postgres; if you have installed Advanced Server in Oracle mode, it creates a database named postgres and a database named edb.

The easiest way to empty the target database is to drop the database and then create a new database. Before invoking the DROP DATABASE command, you must disconnect any users and halt any services that are currently using the database.

On Windows, navigate through the Control Panel to the Services manager; highlight each service in the Services list, and select Stop .

On Linux, open a terminal window, assume superuser privileges, and manually stop each service; for example, if you are on Linux 6.x, invoke the following command to stop the pgAgent service:

```
service edb-pgagent-12 stop
```

After stopping any services that are currently connected to Advanced Server, you can use the EDB-PSQL command line client to drop and create a database. When the client opens, connect to the database as the database superuser; if prompted, provide authentication information. Then, use the following command to drop your database:

```
DROP DATABASE <database_name>;
```

Where <database_name> is the name of the database.

Then, create an empty database based on the contents of the template1 database.

CREATE DATABASE <database_name>;

Step 3 - Set both servers in trust mode

During the upgrade process, pg_upgrade will connect to the old and new servers several times; to make the connection process easier, you can edit the pg_hba.conf file, setting the authentication mode to trust. To modify the pg_hba.conf file, navigate through the Start menu to the EDB Postgres menu; to the Advanced Server menu, and open the Expert Configuration menu; select the Edit pg_hba.conf menu option to open the pg_hba.conf file.

You must allow trust authentication for the previous Advanced Server installation, and Advanced Server 12 servers. Edit the pg_hba.conf file for both installations of Advanced Server as shown in the following figure.

Configuring Advanced Server to use trust authentication.

After editing each file, save the file and exit the editor.

If the system is required to maintain md5 authentication mode during the upgrade process, you can specify user passwords for the database superuser in a password file (pgpass.conf on Windows, .pgpass on Linux). For more information about configuring a password file, see the PostgreSQL Core Documentation.

Step 4 - Stop All Component Services and Servers

Before you invoke pg_upgrade , you must stop any services that belong to the original Advanced Server installation, Advanced Server 12, or the supporting components. This ensures that a service will not attempt to access either cluster during the upgrade process.

The services that are most likely to be running in your installation are:

Service:	On Linux:	On Windows:
Postgres Plus Advanced Server 9.0	ppas-9.0	ppas-9.0
Postgres Plus Advanced Server 9.1	ppas-9.1	ppas-9.1
Postgres Plus Advanced Server 9.2	ppas-9.2	ppas-9.2
Postgres Plus Advanced Server 9.3	ppas-9.3	ppas-9.3
Postgres Plus Advanced Server 9.4	ppas-9.4	ppas-9.4
Postgres Plus Advanced Server 9.5	ppas-9.5	ppas-9.5
EnterpriseDB Postgres Advanced Server 9.6	edb-as-9.6	edb-as-9.6
EnterpriseDB Postgres Advanced Server 10	edb-as-10	edb-as-10
EnterpriseDB Postgres Advanced Server 11	edb-as-11	edb-as-11
EnterpriseDB Postgres Advanced Server 12	edb-as-12	edb-as-12
Advanced Server 9.0 Scheduling Agent	ppasAgent-90	Postgres Plus Advanced
Advanced Server 9.1 Scheduling Agent	ppasAgent-91	Postgres Plus Advanced
Advanced Server 9.2 Scheduling Agent	ppas-agent-9.2	Postgres Plus Advanced
Advanced Server 9.3 Scheduling Agent	ppas-agent-9.3	Postgres Plus Advanced
Advanced Server 9.4 Scheduling Agent	ppas-agent-9.4	Postgres Plus Advanced
Advanced Server 9.5 Scheduling Agent	ppas-agent-9.5	Postgres Plus Advanced
Advanced Server 9.6 Scheduling Agent (pgAgent)	edb-pgagent-9.6	EnterpriseDB Postgres /
Infinite Cache 9.2	ppas-infinitecache-9.2	N/A
Infinite Cache 9.3	ppas-infinitecache-9.3	N/A
Infinite Cache 9.4	ppas-infinitecache	N/A
Infinite Cache 9.5	ppas-infinitecache	N/A
Infinite Cache 9.6	edb-icache	N/A
Infinite Cache 10	edb-icache	N/A
PgBouncer 9.0	pgbouncer-90	pgbouncer-90
PgBouncer 9.1	pgbouncer-91	pgbouncer-91
PgBouncer 9.2	pgbouncer-9.2	pgbouncer-9.2
PgBouncer 9.3	pgbouncer-9.3	pgbouncer-9.3

Service:	On Linux:	On Windows:
PgBouncer	Pgbouncer	Pgbouncer
PgBouncer 1.6	ppas-pgbouncer-1.6 or ppas-pgbouncer16	ppas-pgbouncer-1.6
PgBouncer 1.7	edb-pgbouncer-1.7	edb-pgbouncer-1.7
PgPool 9.2	ppas-pgpool-9.2	N/A
PgPool 9.3	ppas-pgpool-9.3	N/A
PgPool	ppas-pgpool	N/A
PgPool 3.4	ppas-pgpool-3.4 or ppas-pgpool34 or	N/A
pgPool-II	edb-pgpool-3.5	N/A
Slony 9.2	ppas-replication-9.2	ppas-replication-9.2
Slony 9.3	ppas-replication-9.3	ppas-replication-9.3
Slony 9.4	ppas-replication-9.4	ppas-replication-9.4
Slony 9.5	ppas-replication-9.5	ppas-replication-9.5
Slony 9.6	edb-slony-replication-9.6	edb-slony-replication-9.6
xDB Publication Server 9.0	edb-xdbpubserver-90	Publication Service 90
xDB Publication Server 9.1	edb-xdbpubserver-91	Publication Service 91
xDB Subscription Server	edb-xdbsubserver-90	Subscription Service 90
xDB Subscription Server	edb-xdbsubserver-91	Subscription Service 91
EDB Replication Server v6.x	edb-xdbpubserver	Publication Service for x
EDB Subscription Server v6.x	edb-xdbsubserver	Subscription Service for

To stop a service on Windows:

Open the Services applet; highlight each Advanced Server or supporting component service displayed in the list, and select Stop.

To stop a service on Linux:

Open a terminal window and manually stop each service at the command line.

Step 5 for Linux only - Assume the identity of the cluster owner

If you are using Linux, assume the identity of the Advanced Server cluster owner. (The following example assumes Advanced Server was installed in the default, compatibility with Oracle database mode, thus assigning enterprisedb as the cluster owner. If installed in compatibility with PostgreSQL database mode, postgres is the cluster owner.)

su - enterprisedb

Enter the Advanced Server cluster owner password if prompted. Then, set the path to include the location of the pg_upgrade executable:

export PATH=\$PATH:/usr/edb/as12/bin

During the upgrade process, pg_upgrade writes a file to the current working directory of the enterprisedb user; you must invoke pg_upgrade from a directory where the enterprisedb user has write privileges.

After performing the above commands, navigate to a directory in which the enterprisedb user has sufficient privileges to write a file.

cd /tmp

Proceed to Step 6.

Step 5 for Windows only - Assume the identity of the cluster owner

If you are using Windows, open a terminal window, assume the identity of the Advanced Server cluster owner and set the path to the pq_upqrade executable.

If the [--serviceaccount](#service_account_user) parameter was specified during the initial installation of Advanced Server, then](#service_account_user) is the Advanced Server cluster owner and is the user RUNAS' command.

```
RUNAS /USER:<service_account_user> "CMD.EXE"
SET PATH=%PATH%;C:\Program Files\edb\as12\bin
```

During the upgrade process, pg_upgrade writes a file to the current working directory of the service account user; you must invoke pg_upgrade from a directory where the service account user has write privileges. After performing the above commands, navigate to a directory in which the service account user has sufficient privileges to write a file.

cd %TFMP%

Proceed to Step 6.

If the --serviceaccount parameter was omitted during the initial installation of Advanced Server, then the default owner of the Advanced Server service and the database cluster is NT AUTHORITY\NetworkService

When NT AUTHORITY\NetworkService is the service account user, the RUNAS command may not be usable as it prompts for a password and the NT AUTHORITY\NetworkService account is not assigned a password. Thus, there is typically a failure with an error message such as, "Unable to acquire user password".

Under this circumstance a Windows utility program named PsExec must be used to run CMD.EXE as the service account NT AUTHORITY\NetworkService.

The PsExec program must be obtained by downloading PsTools , which is available at the following site: https://technet.microsoft.com/en-us/sysinternals/bb897553.aspx.

You can then use the following command to run CMD. EXE as NT AUTHORITY\NetworkService, and then set the path to the $pq_upqrade$ executable.

```
psexec.exe -u "NT AUTHORITY\NetworkService" CMD.EXE
SET PATH=%PATH%;C:\Program Files\edb\as12\bin
```

During the upgrade process, pg_upgrade writes a file to the current working directory of the service account user; you must invoke pg_upgrade from a directory where the service account user has write privileges. After performing the above commands, navigate to a directory in which the service account user has sufficient privileges to write a file.

cd %TEMP%

Proceed with Step 6.

Step 6 - Perform a consistency check

Before attempting an upgrade, perform a consistency check to assure that the old and new clusters are compatible and properly configured. Include the --check option to instruct pg_upgrade to perform the consistency check.

The following example demonstrates invoking pg_upgrade to perform a consistency check on Linux:

```
pg_upgrade -d /var/lib/edb/as11/data
```

- -D /var/lib/edb/as12/data -U enterprisedb
- -b /usr/edb/as11/bin -B /usr/edb/as12/bin -p 5444 -P 5445 --check

If the command is successful, it will return *Clusters are compatible*.

If you are using Windows, you must quote any directory names that contain a space:

```
pg_upgrade.exe
```

- -d "C:\Program Files\ PostgresPlus\11AS \data"
- -D "C:\Program Files\edb\\as12\data" -U enterprisedb

```
-b "C:\Program Files\PostgresPlus\11AS\bin"
```

```
-B "C:\Program Files\edb\as12\bin" -p 5444 -P 5445 --check
```

During the consistency checking process, pg_upgrade will log any discrepancies that it finds to a file located in the directory from which pg_upgrade was invoked. When the consistency check completes, review the file to identify any missing components or upgrade conflicts. You must resolve any conflicts before invoking pg_upgrade to perform a version upgrade.

If pg_upgrade alerts you to a missing component, you can use StackBuilder Plus to add the component that contains the component. Before using StackBuilder Plus, you must restart the Advanced Server 12 service. After restarting the service, open StackBuilder Plus by navigating through the Start menu to the Advanced Server 12 menu, and selecting StackBuilder Plus . Follow the onscreen advice of the StackBuilder Plus wizard to download and install the missing components.

When pg_upgrade has confirmed that the clusters are compatible, you can perform a version upgrade.

Step 7 - Run pg_upgrade

After confirming that the clusters are compatible, you can invoke pg_upgrade to upgrade the old cluster to the new version of Advanced Server.

On Linux:

```
pg_upgrade -d /var/lib/edb/as11/data
```

- -D /var/lib/edb/as12/data -U enterprisedb
- -b /usr/edb/as11/bin -B /usr/edb/as12/bin -p 5444 -P 5445

On Windows:

```
pg_upgrade.exe -d "C:\Program Files\PostgresPlus\11AS\data"
```

- -D "C:\Program Files\edb\as12\data" -U enterprisedb
- -b "C:\Program Files\PostgresPlus\11AS\bin"
- -B "C:\Program Files\edb\as12\bin" -p 5444 -P 5445

pg_upgrade will display the progress of the upgrade onscreen:

\$ pg_upgrade -d /var/lib/edb/as11/data -D /var/lib/edb/as12/data -U
enterprisedb -b /usr/edb/as11/bin -B /usr/edb/as12/bin -p 5444 -P 5445
Performing Consistency Checks

Checking current, bin, and data directories
Checking cluster versions
Checking database user is a superuser
Checking for prepared transactions
Checking for reg* system OID user data types

Checking for contrib/isn with bigint-passing mismatch ok Creating catalog dump ok Checking for presence of required libraries ok

Checking database user is a superuser ok Checking for prepared transactions ok

If pg_upgrade fails after this point, you must re-initdb the new cluster before continuing.

Performing Upgrade

Analyzing all rows in the new cluster

ok

ok

ok

ok

ok

ok

Freezing all rows on the new cluster Deleting files from new pg_clog	ok ok
Copying old pg_clog to new server	ok
Setting next transaction ID for new cluster	ok
Resetting WAL archives	ok
Setting frozenxid counters in new cluster	ok
Creating databases in the new cluster	ok
Adding support functions to new cluster	ok
Restoring database schema to new cluster	ok
Removing support functions from new cluster	ok
Copying user relation files	ok
Setting next OID for new cluster	ok
Creating script to analyze new cluster	ok
Creating script to delete old cluster	ok

Upgrade Complete

Optimizer statistics are not transferred by pg_upgrade so, once you start the new server, consider running: analyze_new_cluster.sh

Running this script will delete the old cluster's data files: delete_old_cluster.sh

While pg_upgrade runs, it may generate SQL scripts that handle special circumstances that it has encountered during your upgrade. For example, if the old cluster contains large objects, you may need to invoke a script that defines the default permissions for the objects in the new cluster. When performing the pre-upgrade consistency check pg_upgrade will alert you to any script that you may be required to run manually.

You must invoke the scripts after pg_upgrade completes. To invoke the scripts, connect to the new cluster as a database superuser with the EDB-PSQL command line client, and invoke each script using the \i\i\i\ option:

```
\i <complete_path_to_script/script.sql>
```

It is generally unsafe to access tables referenced in rebuild scripts until the rebuild scripts have completed; accessing the tables could yield incorrect results or poor performance. Tables not referenced in rebuild scripts can be accessed immediately.

If $pg_upgrade$ fails to complete the upgrade process, the old cluster will be unchanged, except that \$PGDATA/global/pg_control is renamed to pg_control.old and each tablespace is renamed to tablespace.old. To revert to the pre-invocation state:

- 1. Delete any tablespace directories created by the new cluster.
- 2. Rename \$PGDATA/global/pg_control , removing the .old suffix.
- 3. Rename the old cluster tablespace directory names, removing the .old suffix.
- 4. Remove any database objects (from the new cluster) that may have been moved before the upgrade failed.

After performing these steps, resolve any upgrade conflicts encountered before attempting the upgrade again.

When the upgrade is complete, pg_upgrade may also recommend vacuuming the new cluster, and will provide a script that allows you to delete the old cluster.

Note

Before removing the old cluster, ensure that the cluster has been upgraded as expected, and that you have preserved a backup of the cluster in case you need to revert to a previous version.

Step 8 - Restore the authentication settings in the pg hba.conf file

If you modified the pg_hba.conf file to permit trust authentication, update the contents of the pg_hba.conf file to reflect your preferred authentication settings.

Step 9 - Move and identify user-defined tablespaces (Optional)

If you have data stored in a user-defined tablespace, you must manually relocate tablespace files after upgrading; move the files to the new location and update the symbolic links (located in the pg_tblspc directory under your cluster's data directory) to point to the files.

3.3.4 Upgrading a pgAgent Installation

If your existing Advanced Server installation uses pgAgent, you can use a script provided with the Advanced Server 12 installer to update pgAgent. The script is named dbms_job.upgrade.script.sql , and is located in the /share/contrib/ directory under your Advanced Server installation.

If you are using pg_upgrade to upgrade your installation, you should:

- 1. Perform the upgrade.
- 2. Invoke the dbms_job.upgrade.script.sql script to update the catalog files. If your existing pgAgent installation was performed with a script, the update will convert the installation to an extension.

3.3.5 pg_upgrade Troubleshooting

The troubleshooting tips in this section address problems you may encounter when using pg_upgrade .

Upgrade Error - There seems to be a postmaster servicing the cluster

If pg_upgrade reports that a postmaster is servicing the cluster, please stop all Advanced Server services and try the upgrade again.

Upgrade Error - fe_sendauth: no password supplied

If pg_upgrade reports an authentication error that references a missing password, please modify the pg_hba.conf files in the old and new cluster to enable trust authentication, or configure the system to use a pgpass.conf file.

Upgrade Error - New cluster is not empty; exiting

If pg_upgrade reports that the new cluster is not empty, please empty the new cluster. The target cluster may not contain any user-defined databases.

Upgrade Error - Failed to load library

If the original Advanced Server cluster included libraries that are not included in the Advanced Server 12 cluster, pg_upgrade will alert you to the missing component during the consistency check by writing an entry to the loadable_libraries.txt file in the directory from which you invoked pg_upgrade. Generally, for missing libraries that are not part of a major component upgrade, perform the following steps:

- Restart the Advanced Server service.
 Use StackBuilder Plus to download and install the missing module. Then:
- 2. Stop the Advanced Server service.
- 3. Resume the upgrade process: invoke pg_upgrade to perform consistency checking.
- 4. When you have resolved any remaining problems noted in the consistency checks, invoke pg_upgrade to perform the data migration from the old cluster to the new cluster.

3.3.6 Reverting to the Old Cluster

The method used to revert to a previous cluster varies with the options specified when invoking pg_upgrade .

- If you specified the --check option when invoking pg_upgrade, an upgrade has not been performed, and no modifications have been made to the old cluster; you can re-use the old cluster at any time.
- If you included the --link option when invoking pg_upgrade, the data files are shared between the old and new cluster after the upgrade completes. If you have started the server that is servicing the new cluster, the new server has written to those shared files and it is unsafe to use the old cluster.
- If you ran pg_upgrade without the --link specification or have not started the new server, the old cluster is unchanged, except that the .old suffix has been appended to the \$PGDATA/global/pg_control and tablespace directories.
- To reuse the old cluster, delete the tablespace directories created by the new cluster and remove the .old suffix from \$PGDATA/global/pg_control and the old cluster tablespace directory names and restart the server that services the old cluster.

3.4 Performing a Minor Version Update of an RPM Installation

If you used an RPM package to install Advanced Server or its supporting components, you can use yum to perform a minor version upgrade to a more recent version. To review a list of the package updates that are available for your system, open a command line, assume root privileges, and enter the command:

[yum check-update](#package_name)

Where <package_name> is the search term for which you wish to search for updates. Please note that you can include wild-card values in the search term. To use yum update to install an updated package, use the command:

[yum update](#package_name)

Where <package_name> is the name of the package you wish to update. Include wild-card values in the update command to update multiple related packages with a single command. For example, use the following command to update all packages whose names include the expression | edb | :

yum update edb*

Note

The yum update command will only perform an update between minor releases; to update between major releases, you must use pg_upgrade .

For more information about using yum commands and options, enter yum --help on your command line, or visit:

 $https://access.red hat.com/documentation/en-US/Red_Hat_Enterprise_Linux/6/html/Deployment_Guide/ch-yum.html$

3.5 Using StackBuilder Plus to Perform a Minor Version Update

The StackBuilder Plus utility provides a graphical interface that simplifies the process of updating, downloading, and installing modules that complement your Advanced Server installation. When you install a module with StackBuilder Plus, StackBuilder Plus automatically resolves any software dependencies.

Note

StackBuilder Plus is supported only on Windows systems.

You can invoke StackBuilder Plus at any time after the installation has completed by selecting the StackBuilder Plus menu option from the Apps menu. Enter your system password (if prompted), and the StackBuilder Plus welcome window opens (shown in the following figure).

The StackBuilder Plus Welcome Window

Use the drop-down listbox on the welcome window to select your Advanced Server installation.

StackBuilder Plus requires Internet access; if your installation of Advanced Server resides behind a firewall (with restricted Internet access), StackBuilder Plus can download program installers through a proxy server. The module provider determines if the module can be accessed through an HTTP proxy or an FTP proxy; currently, all updates are transferred via an HTTP proxy and the FTP proxy information is not used.

If the selected Advanced Server installation has restricted Internet access, use the Proxy Servers on the Welcome to StackBuilder Plus Window! to open the Proxy servers dialog (shown in the following figure).

The Proxy servers dialog

Enter the IP address and port number of the proxy server in the HTTP proxy on the Proxy servers dialog. Currently, all StackBuilder Plus modules are distributed via HTTP proxy (FTP proxy information is ignored). Click 0K to continue.

The StackBuilder Plus module selection window

The tree control on the StackBuilder Plus module selection window (shown in the following figure) displays a node for each module category. To perform an Advanced Server update, expand the Database Server module in the tree control and check the box to the left of the Advanced Server upgraded version. Then, click Next

If prompted, enter your email address and password on the StackBuilder Plus registration window (shown in the following figure).

The StackBuilder Plus registration window

A summary window displays a list of selected packages

StackBuilder Plus confirms the packages selected. The Selected packages dialog will display the name and version of the installer; click Next to continue.

When the download completes, a window opens that confirms the installation files have been downloaded and are ready for installation.

Confirmation that the download process is complete

You can check the box next to Skip Installation, and select Next to exit StackBuilder Plus without installing the downloaded files, or leave the box unchecked and click Next to start the installation process.

StackBuilder Plus confirms the completed installation

When the upgrade is complete, StackBuilder Plus will alert you to the success or failure of the installation of the requested package. If you were prompted by an installer to restart your computer, reboot now.

Note

If the update fails to install, StackBuilder Plus will alert you to the installation error with a popup dialog and write a message to the log file at <code>%TEMP%</code> .

4.0 Database Compatibility for Oracle Developers Reference Guide

Database Compatibility for Oracle means that an application runs in an Oracle environment as well as in the EDB Postgres Advanced Server (Advanced Server) environment with minimal or no changes to the application code.

This guide provides reference material about the compatible data types supported by Advanced Server. Reference information about:

- Compatible SQL Language syntax is provided in the Database Compatibility for Oracle Developers SQL Guide.
- Compatible Catalog Views is provided in the Database Compatibility for Oracle Developers Catalog View Guide.

Developing an application that is compatible with Oracle databases in the Advanced Server requires special attention to which features are used in the construction of the application. For example, developing a compatible application means selecting:

- Data types to define the application's database tables that are compatible with Oracle databases
- SQL statements that are compatible with Oracle SQL
- System and built-in functions for use in SQL statements and procedural logic that are compatible with Oracle databases
- Stored Procedure Language (SPL) to create database server-side application logic for stored procedures, functions, triggers, and packages
- System catalog views that are compatible with Oracle's data dictionary

For detailed information about Advanced Server's compatibility features and extended functionality, please see the complete library of Advanced Server documentation, available at:

https://www.enterprisedb.com/resources/product-documentation

4.1.0 The SQL Language

The following sections describe the subset of the Advanced Server SQL language compatible with Oracle databases. The following SQL syntax, data types, and functions work in both EDB Postgres Advanced Server and Oracle.

The Advanced Server documentation set includes syntax and commands for extended functionality (functionality that does not provide database compatibility for Oracle or support Oracle-styled applications) that is not included in this guide.

This section is organized into the following sections:

- · General discussion of Advanced Server SQL syntax and language elements
- · Data types
- Built-in functions

4.1.1.0 SQL Syntax

This section describes the general syntax of SQL. It forms the foundation for understanding the following chapters that include detail about how the SQL commands are applied to define and modify data.

4.1.1.1 Lexical Structure

SQL input consists of a sequence of commands. A command is composed of a sequence of tokens , terminated by a semicolon (;). The end of the input stream also terminates a command. Which tokens are valid depends on the syntax of the particular command.

A token can be a key word , an identifier , a quoted identifier , a literal (or constant), or a special character symbol. Tokens are normally separated by whitespace (space, tab, new line), but need not be if there is no ambiguity (which is generally only the case if a special character is adjacent to some other token type).

Additionally, comments can occur in SQL input. They are not tokens -they are effectively equivalent to whitespace.

For example, the following is (syntactically) valid SQL input:

```
SELECT * FROM MY_TABLE;
UPDATE MY_TABLE SET A = 5;
INSERT INTO MY_TABLE VALUES (3, 'hi there');
```

This is a sequence of three commands, one per line (although this is not required; more than one command can be on a line, and commands can usually be split across lines).

The SQL syntax is not very consistent regarding what tokens identify commands and which are operands or parameters. The first few tokens are generally the command name, so in the above example we would usually speak of a SELECT, an UPDATE, and an INSERT command. But for instance the UPDATE command always requires a SET token to appear in a certain position, and this particular variation of INSERT also requires a VALUES token in order to be complete. The precise syntax rules for each command are described in Database Compatibility for Oracle Developers SQL Guide.

4.1.1.2 Identifiers and Key Words

Tokens such as SELECT, UPDATE, or VALUES in the example above are examples of key words, that is, words that have a fixed meaning in the SQL language. The tokens MY_TABLE and A are examples of identifiers. They identify names of tables, columns, or other database objects, depending on the command they are used in. Therefore they are sometimes simply called, names. Key words and identifiers have the same lexical structure, meaning that one cannot know whether a token is an identifier or a key word without knowing the language.

SQL identifiers and key words must begin with a letter (α -z or A-Z). Subsequent characters in an identifier or key word can be letters, underscores, digits (\emptyset -9), dollar signs (\$), or number signs (\$).

Identifier and key word names are case insensitive. Therefore

```
UPDATE MY_TABLE SET A = 5;
```

can equivalently be written as:

```
uPDaTE my_TabLE SeT a = 5;
```

A convention often used is to write key words in upper case and names in lower case, e.g.,

```
UPDATE my_table SET a = 5;
```

There is a second kind of identifier: the delimited identifier or quoted identifier. It is formed by enclosing an arbitrary sequence of characters in double-quotes ("). A delimited identifier is always an identifier, never a key word. So "select" could be used to refer to a column or table named "select", whereas an unquoted select would be taken as a key word and would therefore provoke a parse error when used where a table or column name is expected. The example can be written with quoted identifiers like this:

```
UPDATE "my_table" SET "a" = 5;
```

Quoted identifiers can contain any character, except the character with the numeric code zero.

To include a double quote, use two double quotes. This allows you to construct table or column names that would otherwise not be possible (such as ones containing spaces or ampersands). The length limitation still applies.

Quoting an identifier also makes it case-sensitive, whereas unquoted names are always folded to lower case. For example, the identifiers F00 , foo , and "foo" are considered the same by Advanced Server, but "Foo" and "F00" are different from these three and each other. The folding of unquoted names to lower case is not compatible with Oracle databases. In Oracle syntax, unquoted names are folded to upper case: for example, foo is equivalent to "F00" not "foo". If you want to write portable applications you are advised to always quote a particular name or never quote it.

4.1.1.3 Constants

The kinds of implicitly-typed constants in Advanced Server are strings and numbers. Constants can also be specified with explicit types, which can enable more accurate representation and more efficient handling by the system. These alternatives are discussed in the following subsections.

String Constants

A string constant in SQL is an arbitrary sequence of characters bounded by single quotes ('), for example 'This is a string'. To include a single-quote character within a string constant, write two adjacent single quotes, e.g. 'Dianne''s horse'. Note that this is not the same as a double-quote character (").

Numeric Constants

Numeric constants are accepted in these general forms:

```
digits
digits.[digits][e[+-]digits]
[digits].digits[e[+-]digits]
digitse[+-]digits
```

where digits is one or more decimal digits (0 through 9). At least one digit must be before or after the decimal point, if one is used. At least one digit must follow the exponent marker (e), if one is present. There may not be any spaces or other characters embedded in the constant. Note that any leading plus or minus sign is not actually considered part of the constant; it is an operator applied to the constant.

These are some examples of valid numeric constants:

```
42
3.5
4.
.001
5e2
1.925e-3
```

A numeric constant that contains neither a decimal point nor an exponent is initially presumed to be type INTEGER if its value fits in type INTEGER (32 bits); otherwise it is presumed to be type BIGINT if its value fits in type BIGINT (64 bits); otherwise it is taken to be type NUMBER. Constants that contain decimal points and/or exponents are always initially presumed to be type NUMBER.

The initially assigned data type of a numeric constant is just a starting point for the type resolution algorithms. In most cases the constant will be automatically coerced to the most appropriate type depending on context. When necessary, you can force a numeric value to be interpreted as a specific data type by casting it as described in the following section.

Constants of Other Types

CAST

A constant of an arbitrary type can be entered using the following notation:

```
CAST('string' AS type)
```

The string constant's text is passed to the input conversion routine for the type called type. The result is a constant of the indicated type. The explicit type cast may be omitted if there is no ambiguity as to the type the constant must be (for example, when it is assigned directly to a table column), in which case it is automatically coerced.

CAST can also be used to specify runtime type conversions of arbitrary expressions.

CAST (MULTISET)

```
MULTISET is an extension to CAST that converts subquery results into a nested table type. The synopsis is:
```

```
CAST ( MULTISET ( < subquery > ) AS < datatype > )
```

Where subquery is a query returning one or more rows and datatype is a nested table type.

CAST(MULTISET) is used to store a collection of data in a table.

Example

```
The following example demonstrates using MULTISET:
edb=# CREATE OR REPLACE TYPE project_table_t AS TABLE OF VARCHAR2(25);
CREATE TYPE
edb=# CREATE TABLE projects (person_id NUMBER(10), project_name VARCHAR2(20));
CREATE TABLE
edb=# CREATE TABLE pers_short (person_id NUMBER(10), last_name VARCHAR2(25));
CREATE TABLE
edb=# INSERT INTO projects VALUES (1, 'Teach');
edb=# INSERT INTO projects VALUES (1, 'Code');
INSERT 0 1
edb=# INSERT INTO projects VALUES (2, 'Code');
INSERT 0 1
edb=# INSERT INTO pers_short VALUES (1, 'Morgan');
INSERT 0 1
edb=# INSERT INTO pers_short VALUES (2, 'Kolk');
INSERT 0 1
edb=# INSERT INTO pers_short VALUES (3, 'Scott');
INSERT 0 1
edb=# COMMIT;
COMMIT
edb=# SELECT e.last_name, CAST(MULTISET(
edb(#
        SELECT p.project_name
edb(#
        FROM projects p
        WHERE p.person_id = e.person_id
edb(#
        ORDER BY p.project_name) AS project_table_t)
edb(#
edb-# FROM pers_short e;
last_name | project_table_t
           | {Code,Teach}
Morgan
 Kolk
           | {Code}
 Scott
           | {}
(3 rows)
```

4.1.1.4 Comments

A comment is an arbitrary sequence of characters beginning with double dashes and extending to the end of the line, e.g.:

```
-- This is a standard SOL comment
```

Alternatively, C-style block comments can be used:

```
/* multiline comment
* block
*/
```

where the comment begins with /* and extends to the matching occurrence of */.

4.1.2.0 Data Types

The following table shows the built-in general-purpose data types.

Table - Data Types

4.1.2.1 Numeric Types

Numeric types consist of four-byte integers, four-byte and eight-byte floating-point numbers, and fixed-precision decimals. The following table lists the available types.

Table - Numeric Types

Name	Storage Size	Description	Range
BINARY_INTEGER	4 bytes	Signed integer, Alias for INTEGER	-2,147,483,648 to
DOUBLE PRECISION	8 bytes	Variable-precision, inexact	15 decimal digits
INTEGER	4 bytes	Usual choice for integer	-2,147,483,648 to
NUMBER	Variable	User-specified precision, exact	Up to 1000 digits
NUMBER(p [, s])	Variable	Exact numeric of maximum precision, p, and optional scale, s	Up to 1000 digits
PLS_INTEGER	4 bytes	Signed integer, Alias for INTEGER	-2,147,483,648 to
REAL	4 bytes	Variable-precision, inexact	6 decimal digits p
ROWID	8 bytes	Signed 8 bit integer.	-9223372036854

The following sections describe the types in detail.

Integer Types

The BINARY_INTEGER, INTEGER, PLS_INTEGER, and ROWID types store whole numbers (without fractional components) as specified in Table Numeric Types. Attempts to store values outside of the allowed range will result in an error.

Arbitrary Precision Numbers

The type, NUMBER, can store practically an unlimited number of digits of precision and perform calculations exactly. It is especially recommended for storing monetary amounts and other quantities where exactness is required. However, the NUMBER type is very slow compared to the floating-point types described in the next section.

In what follows we use these terms: The scale of a NUMBER is the count of decimal digits in the fractional part, to the right of the decimal point. The precision of a NUMBER is the total count of significant digits in the whole number, that is, the number of digits to both sides of the decimal point. So the number 23.5141 has a precision of 6 and a scale of 4. Integers can be considered to have a scale of zero.

Both the precision and the scale of the NUMBER type can be configured. To declare a column of type NUMBER use the syntax

NUMBER(precision, scale)

The precision must be positive, the scale zero or positive. Alternatively,

NUMBER(precision)

selects a scale of 0. Specifying NUMBER without any precision or scale creates a column in which numeric values of any precision and scale can be stored, up to the implementation limit on precision. A column of this kind will not coerce input values to any particular scale, whereas NUMBER columns with a declared scale will coerce input values to that scale. (The SQL standard requires a default scale of 0, i.e., coercion to integer precision. For maximum portability, it is best to specify the precision and scale explicitly.)

If the precision or scale of a value is greater than the declared precision or scale of a column, the system will attempt to round the value. If the value cannot be rounded so as to satisfy the declared limits, an error is raised.

Floating-Point Types

The data types REAL and DOUBLE PRECISION are inexact, variable-precision numeric types. In practice, these types are usually implementations of IEEE Standard 754 for Binary Floating-Point Arithmetic (single and double precision, respectively), to the extent that the underlying processor, operating system, and compiler support it.

Inexact means that some values cannot be converted exactly to the internal format and are stored as approximations, so that storing and printing back out a value may show slight discrepancies. Managing these errors and how they propagate through calculations is the subject of an entire branch of mathematics and computer science and will not be discussed further here, except for the following points:

If you require exact storage and calculations (such as for monetary amounts), use the NUMBER type instead.

If you want to do complicated calculations with these types for anything important, especially if you rely on certain behavior in boundary cases (infinity, underflow), you should evaluate the implementation carefully.

Comparing two floating-point values for equality may or may not work as expected.

On most platforms, the REAL type has a range of at least 1E-37 to 1E+37 with a precision of at least 6 decimal digits. The DOUBLE PRECISION type typically has a range of around 1E-307 to 1E+308 with a precision of at least 15 digits. Values that are too large or too small will cause an error. Rounding may take place if the precision of an input number is too high. Numbers too close to zero that are not representable as distinct from zero will cause an underflow error.

Advanced Server also supports the SQL standard notations FLOAT and FLOAT(p) for specifying inexact numeric types. Here, p specifies the minimum acceptable precision in binary digits. Advanced Server accepts FLOAT(1) to FLOAT(24) as selecting the REAL type, while FLOAT(25) to FLOAT(53) as selecting DOUBLE PRECISION . Values of p outside the allowed range draw an error. FLOAT with no precision specified is taken to mean DOUBLE PRECISION .

4.1.2.2 Character Types

The following table lists the general-purpose character types available in Advanced Server.

Table - Character Types

Name Description

CHAR[(n)] Fixed-length character string, blank-padded to the size specified by *n*

CLOB Large variable-length up to 1 GB

LONG Variable unlimited length.

NVARCHAR(n) Variable-length national character string, with limit. NVARCHAR2(n) Variable-length national character string, with limit.

STRING Alias for VARCHAR2.

VARCHAR(n) Variable-length character string, with limit (considered deprecated, but supported for compatibility)

VARCHAR2(n) Variable-length character string, with limit

Where n is a positive integer; these types can store strings up to n characters in length. An attempt to assign a value that exceeds the length of n will result in an error, unless the excess characters are all spaces, in which case the string will be truncated to the maximum length.

The storage requirement for data of these types is the actual string plus 1 byte if the string is less than 127 bytes, or 4 bytes if the string is 127 bytes or greater. In the case of CHAR, the padding also requires storage. Long strings are compressed by the system automatically, so the physical requirement on disk may be less. Long values are stored in background tables so they do not interfere with rapid access to the shorter column values.

The database character set determines the character set used to store textual values.

CHAR

If you do not specify a value for n, n will default to 1. If the string to be assigned is shorter than n, values of type CHAR will be space-padded to the specified width (n), and will be stored and displayed that way.

Padding spaces are treated as semantically insignificant. That is, trailing spaces are disregarded when comparing two values of type CHAR, and they will be removed when converting a CHAR value to one of the other string types.

If you explicitly cast an over-length value to a CHAR(n) type, the value will be truncated to n characters without raising an error (as specified by the SQL standard).

VARCHAR, VARCHAR2, NVARCHAR and NVARCHAR2

If the string to be assigned is shorter than n, values of type VARCHAR, VARCHAR2, NVARCHAR and NVARCHAR2 will store the shorter string without padding.

Note that trailing spaces are semantically significant in VARCHAR values.

If you explicitly cast a value to a VARCHAR type, an over-length value will be truncated to n characters without raising an error (as specified by the SQL standard).

CLOB

You can store a large character string in a CL0B type. CL0B is semantically equivalent to VARCHAR2 except no length limit is specified. Generally, you should use a CL0B type if the maximum string length is not known.

The longest possible character string that can be stored in a CLOB type is about 1 GB.

Note: The CLOB data type is actually a DOMAIN based on the PostgreSQL TEXT data type. For information on a DOMAIN, see the PostgreSQL core documentation at:

https://www.postgresql.org/docs/12/static/sql-createdomain.html

Thus, usage of the CLOB type is limited by what can be done for TEXT such as a maximum size of approximately 1 GB.

For usage of larger amounts of data, instead of using the CLOB data type, use the PostgreSQL Large Objects feature that relies on the pg_largeobject system catalog. For information on large objects, see the PostgreSQL core documentation at:

https://www.postgresql.org/docs/12/static/largeobjects.html

4.1.2.3 Binary Data

The following data types allows storage of binary strings.

Table - Binary Large Object

Name Storage Size

BINARY The length of the binary string.

BLOB The actual binary string plus 1 byte if the binary string is less than 127 bytes, or 4 bytes if the binary string is

VARBINARY The length of the binary string

A binary string is a sequence of octets (or bytes). Binary strings are distinguished from characters strings by two characteristics: First, binary strings specifically allow storing octets of value zero and other "non-printable" octets (defined as octets outside the range 32 to 126). Second, operations on binary strings process the actual bytes, whereas the encoding and processing of character strings depends on locale settings.

4.1.2.4 'Date/Time Types'

The following discussion of the date/time types assumes that the configuration parameter, edb_redwood_date, has been set to TRUE whenever a table is created or altered.

Advanced Server supports the date/time types shown in the following table.

Table - Date/Time Types

When DATE appears as the data type of a column in the data definition language (DDL) commands, CREATE TABLE or ALTER TABLE, it is translated to TIMESTAMP at the time the table definition is stored in the database. Thus, a time component will also be stored in the column along with the date.

When DATE appears as a data type of a variable in an SPL declaration section, or the data type of a formal parameter in an SPL procedure or an SPL function, or the return type of an SPL function, it is always translated to TIMESTAMP and thus can handle a time component if present.

TIMESTAMP accepts an optional precision value p which specifies the number of fractional digits retained in the seconds field. The allowed range of p is from 0 to 6 with the default being 6.

When TIMESTAMP values are stored as double precision floating-point numbers (currently the default), the effective limit of precision may be less than 6. TIMESTAMP values are stored as seconds before or after midnight 2000-01-01. Microsecond precision is achieved for dates within a few years of 2000-01-01, but the precision degrades for dates further away. When TIMESTAMP values are stored as eight-byte integers (a compile-time option), microsecond precision is available over the full range of values. However eight-byte integer timestamps have a more limited range of dates than shown above: from 4713 BC up to 294276 AD.

TIMESTAMP (p) WITH TIME ZONE is similar to TIMESTAMP (p), but includes the time zone as well.

INTERVAL Types

INTERVAL values specify a period of time. Values of INTERVAL type are composed of fields that describe the value of the data. The following table lists the fields allowed in an INTERVAL type:

Table - Interval Types

Field Name	INTERVAL Values Allowed
YEAR	Integer value (positive or negative)
MONTH	0 through 11
DAY	Integer value (positive or negative)
HOUR	0 through 23
MINUTE	0 through 59
SECOND	0 through 59.9(p) where 9(p) is the precision of fractional seconds

The fields must be presented in descending order – from YEARS to MONTHS , and from DAYS to HOURS , MINUTES and then SECONDS .

Advanced Server supports two INTERVAL types compatible with Oracle databases.

The first variation supported by Advanced Server is INTERVAL DAY TO SECOND [(p)]. INTERVAL DAY TO SECOND stores a time interval in days, hours, minutes and seconds.

p specifies the precision of the second field.

Advanced Server interprets the value:

INTERVAL '1 2:34:5.678' DAY TO SECOND(3)

as 1 day, 2 hours, 34 minutes, 5 seconds and 678 thousandths of a second.

Advanced Server interprets the value:

INTERVAL '1 23' DAY TO HOUR

as 1 day and 23 hours.

Advanced Server interprets the value:

INTERVAL '2:34' HOUR TO MINUTE

as 2 hours and 34 minutes.

Advanced Server interprets the value:

INTERVAL '2:34:56.129' HOUR TO SECOND(2)

as 2 hours, 34 minutes, 56 seconds and 13 thousandths of a second. Note that the fractional second is rounded up to 13 because of the specified precision.

The second variation supported by Advanced Server that is compatible with Oracle databases is INTERVAL YEAR TO MONTH. This variation stores a time interval in years and months.

Advanced Server interprets the value:

INTERVAL '12-3' YEAR TO MONTH

as 12 years and 3 months.

Advanced Server interprets the value:

INTERVAL '456' YEAR(2)

as 12 years and 3 months.

Advanced Server interprets the value:

INTERVAL '300' MONTH

as 25 years.

Date/Time Input

Date and time input is accepted in ISO 8601 SQL-compatible format, the Oracle default dd-M0N-yy format, as well as a number of other formats provided that there is no ambiguity as to which component is the year, month, and day. However, use of the T0_DATE function is strongly recommended to avoid ambiguities.

Any date or time literal input needs to be enclosed in single quotes, like text strings. The following SQL standard syntax is also accepted:

type 'value'

type is either DATE or TIMESTAMP .

value is a date/time text string.

Dates

The following table shows some possible input formats for dates, all of which equate to January 8, 1999.

Table - Date Input

Example
January 8, 1999
1999-01-08
1999-Jan-08
Jan-08-1999
08-Jan-1999
08-Jan-99
Jan-08-99

19990108 990108

The date values can be assigned to a DATE or TIMESTAMP column or variable. The hour, minute, and seconds fields will be set to zero if the date value is not appended with a time value.

Times

Some examples of the time component of a date or time stamp are shown in the following table.

Table - Time Input

Example	Description
04:05:06.789	ISO 8601
04:05:06	ISO 8601
04:05	ISO 8601
040506	ISO 8601
04:05 AM	Same as 04:05; AM does not affect value
04:05 PM	Same as 16:05; input hour must be <= 12

Time Stamps

Valid input for time stamps consists of a concatenation of a date and a time. The date portion of the time stamp can be formatted according to any of the examples shown in Table 2-7. The time portion of the time stamp can be formatted according to any of examples shown in Table 2-8.

The following is an example of a time stamp which follows the Oracle default format.

08-JAN-99 04:05:06

The following is an example of a time stamp which follows the ISO 8601 standard.

1999-01-08 04:05:06

Date/Time Output

The default output format of the date/time types will be either (dd-MON-yy) referred to as the Redwood date style , compatible with Oracle databases, or (yyyy-mm-dd) referred to as the ISO 8601 format, depending upon the application interface to the database. Applications that use JDBC such as SQL Interactive always present the date in ISO 8601 form. Other applications such as PSQL present the date in Redwood form.

The following table shows examples of the output formats for the two styles, Redwood and ISO 8601.

Table - Date/Time Output Styles

Description	Example
Redwood style	31-DEC-05 07:37:16
ISO 8601/SQL standard	1997-12-17 07:37:16

Internals

Advanced Server uses Julian dates for all date/time calculations. Julian dates correctly predict or calculate any date after 4713 BC based on the assumption that the length of the year is 365.2425 days.

4.1.2.5 Boolean Types

Advanced Server provides the standard SQL type B00LEAN . B00LEAN can have one of only two states: TRUE or FALSE . A third state, UNKNOWN , is represented by the SQL NULL value.

Table - Boolean Type

Name	Storage Size	Description
BOOLEAN	1 byte	Logical Boolean (true/false)

The valid literal value for representing the true state is TRUE. The valid literal for representing the false state is FALSE.

4.1.2.6 XML Type

The XMLTYPE data type is used to store XML data. Its advantage over storing XML data in a character field is that it checks the input values for well-formedness, and there are support functions to perform type-safe operations on it.

The XML type can store well-formed "documents", as defined by the XML standard, as well as "content" fragments, which are defined by the production XMLDecl? content in the XML standard. Roughly, this means that content fragments can have more than one top-level element or character node.

Note: Oracle does not support the storage of content fragments in XMLTYPE columns.

The following example shows the creation and insertion of a row into a table with an XMLTYPE column.

4.1.3.0 Functions and Operators

Advanced Server provides a large number of functions and operators for the built-in data types.

4.1.3.1 Logical Operators

The usual logical operators are available: AND, OR, NOT

SQL uses a three-valued Boolean logic where the null value represents "unknown". Observe the following truth tables:

Table - AND/OR Truth Table

а	b	a AND b	a OR b
True	True	True	True
True	False	False	True

True	Null	Null	True
False	False	False	False
False	Null	False	Null
Null	Null	Null	Null

Table - NOT Truth Table

а	NOT a
True	False
False	True
Null	Null

The operators AND and OR are commutative, that is, you can switch the left and right operand without affecting the result.

4.1.3.2 Comparison Operators

The usual comparison operators are shown in the following table.

Table - Comparison Operators

Operator	Description
<	Less than
>	Greater than
<=	Less than or equal to
>=	Greater than or equal to
=	Equal
\Diamond	Not equal
!=	Not equal

Comparison operators are available for all data types where this makes sense. All comparison operators are binary operators that return values of type BOOLEAN; expressions like 1 < 2 < 3 are not valid (because there is no < operator to compare a Boolean value with 3).

In addition to the comparison operators, the special BETWEEN 'construct is available.

a BETWEEN
$$x$$
 AND y

is equivalent to

$$a >= x AND a <= y$$

Similarly,

is equivalent to

There is no difference between the two respective forms apart from the CPU cycles required to rewrite the first one into the second one internally.

To check whether a value is or is not null, use the constructs

expression IS NOT NULL

Do not write expression = NULL because NULL is not "equal to" NULL. (The null value represents an unknown value, and it is not known whether two unknown values are equal.) This behavior conforms to the SQL standard.

Some applications may expect that expression = NULL returns true if expression evaluates to the null value. It is highly recommended that these applications be modified to comply with the SQL standard.

4.1.3.3 'Mathematical Functions and Operators'

Mathematical operators are provided for many Advanced Server types. For types without common mathematical conventions for all possible permutations (e.g., date/time types) the actual behavior is described in subsequent sections.

The following table shows the available mathematical operators.

Table - Mathematical Operators

Note: If the db_dialect configuration parameter in the postgresql.conf file is set to redwood, then division of a pair of INTEGER data types does not result in a truncated value. Any fractional result is retained as shown by the following example:

This behavior is compatible with Oracle databases where there is no native INTEGER data type specification is internally converted to NUMBER(38), which results in retaining any fractional result.

If the <code>db_dialect</code> configuration parameter is set to <code>postgres</code> , then division of a pair of <code>INTEGER</code> data types results in a truncated value as shown by the following example:

```
edb=# SET db_dialect TO postgres;
SET
edb=# SHOW db_dialect;
db_dialect
------
postgres
(1 row)
edb=# SELECT CAST('10' AS INTEGER) / CAST('3' AS INTEGER) FROM dual;
?column?
------
3
(1 row)
```

This behavior is compatible with PostgreSQL databases where division involving any pair of SMALLINT, or BIGINT data types results in truncation of the result. The same truncated result is returned by Advanced Server when db_dialect is set to postgres as shown in the previous example.

Note however, that even when db_dialect is set to redwood, only division with a pair of INTEGER

data types results in no truncation of the result. Division that includes only SMALLINT or BIGINT data types, with or without an INTEGER data type, does result in truncation in the PostgreSQL fashion without retaining the fractional portion as shown by the following where INTEGER and SMALLINT are involved in the division:

```
edb=# SHOW db_dialect;
db_dialect
------
redwood
(1 row)
edb=# SELECT CAST('10' AS INTEGER) / CAST('3' AS SMALLINT) FROM dual;
?column?
------
3
(1 row)
```

The following table shows the available mathematical functions. Many of these functions are provided in multiple forms with different argument types. Except where noted, any given form of a function returns the same data type as its argument. The functions working with DOUBLE PRECISION data are mostly implemented on top of the host system's C library; accuracy and behavior in boundary cases may therefore vary depending on the host system.

Table - Mathematical Functions

Function	Return Type
ABS(x)	Same as x
CEIL(DOUBLE PRECISION or NUMBER)	Same as input
EXP(DOUBLE PRECISION or NUMBER)	Same as input
FLOOR(DOUBLE PRECISION or NUMBER)	Same as input
LN(DOUBLE PRECISION or NUMBER)	Same as input
LOG(b NUMBER, x NUMBER)	NUMBER
MOD(y, x)	Same as argument types
NVL(x, y)	Same as argument types; where both arg
POWER(a DOUBLE PRECISION, b DOUBLE PRECISION)	DOUBLE PRECISION
POWER(a NUMBER, b NUMBER)	NUMBER
ROUND(DOUBLE PRECISION or NUMBER)	Same as input
ROUND(v NUMBER, s INTEGER)	NUMBER
SIGN(DOUBLE PRECISION or NUMBER)	Same as input
SQRT(DOUBLE PRECISION or NUMBER)	Same as input
TRUNC(DOUBLE PRECISION or NUMBER)	Same as input
TRUNC(v NUMBER, s INTEGER)	NUMBER
WIDTH_BUCKET(op NUMBER, b1 NUMBER, b2 NUMBER, count INTEGER)	INTEGER

The following table shows the available trigonometric functions. All trigonometric functions take arguments and return values of type DOUBLE PRECISION .

Table - Trigonometric Functions

Function	Description
ACOS(x)	Inverse cosine
ASIN(x)	Inverse sine
ATAN(x)	Inverse tangent
ATAN2(x, y)	Inverse tangent of x/y
COS(x)	Cosine
SIN(x)	Sine
TAN(x)	Tangent

4.1.3.4 String Functions and Operators

This section describes functions and operators for examining and manipulating string values. Strings in this context include values of the types CHAR, VARCHAR2, and CLOB. Unless otherwise noted, all of the functions listed below work on all of these types, but be wary of potential effects of automatic padding when using the CHAR type. Generally, the functions described here also work on data of non-string types by converting that data to a string representation first.

Table - SQL String Functions and Operators

Function	Return Type	Description
string		string
CONCAT(string, string)	CLOB	String concatenation
HEXTORAW(varchar2)	RAW	Converts a VARCHAR2 value to a RAW value
RAWTOHEX(raw)	VARCHAR2	Converts a RAW value to a HEXADECIMAL value
INSTR(string, set, [start [, occurrence]])	INTEGER	Finds the location of a set of characters in a string, starting at po
INSTRB(string, set)	INTEGER	Returns the position of the set within the string. Returns 0 if set
INSTRB(string, set, start)	INTEGER	Returns the position of the set within the string, beginning at sta
INSTRB(string, set, start, occurrence)	INTEGER	Returns the position of the specified occurrence of set within the
LOWER(string)	CLOB	Convert string to lower case
SUBSTR(string, start [, count])	CLOB	Extract substring starting from start and going for count charact
SUBSTRB(string, start [, count])	CLOB	Same as SUBSTR except start and count are in number of byte
SUBSTR2(string, start [, count])	CLOB	Alias for SUBSTR.
SUBSTR2(string, start [, count])	CLOB	Alias for SUBSTRB.
SUBSTR4(string, start [, count])	CLOB	Alias for SUBSTR.
SUBSTR4(string, start [, count])	CLOB	Alias for SUBSTRB.
SUBSTRC(string, start [, count])	CLOB	Alias for SUBSTR.
SUBSTRC(string, start [, count])	CLOB	Alias for SUBSTRB.
TRIM([LEADING	TRAILING	BOTH] [characters] FROM string)
LTRIM(string [, set])	CLOB	Removes all the characters specified in set from the left of a giv
RTRIM(string [, set])	CLOB	Removes all the characters specified in set from the right of a g
UPPER(string)	CLOB	Convert string to upper case

Additional string manipulation functions are available and are listed in the following table. Some of them are used internally to implement the SQL-standard string functions listed in Table 2-17.

Table - Other String Functions

Function	Return Type
ASCII(string)	INTEGER
CHR(INTEGER)	CLOB
DECODE(expr, expr1a, expr1b [, expr2a, expr2b] [, default])	Same as argument types of expr1b, expr2b,, default
INITCAP(string)	CLOB
LENGTH	INTEGER
LENGTHC	INTEGER
LENGTH2	INTEGER
LENGTH4	INTEGER
LENGTHB	INTEGER
LPAD(string, length INTEGER [, fill])	CLOB
REPLACE(string, search_string [, replace_string]	CLOB
RPAD(string, length INTEGER [, fill])	CLOB
TRANSLATE(string, from, to)	CLOB

Truncation of String Text Resulting from Concatenation with NULL

Note: This section describes a functionality that is not compatible with Oracle databases, which may lead to some inconsistency when converting data from Oracle to Advanced Server.

For Advanced Server, when a column value is NULL , the concatenation of the column with a text string may result in either of the following:

- · Return of the text string
- Disappearance of the text string (that is, a null result)

The result is dependent upon the data type of the NULL column and the way in which the concatenation is done.

If one uses the string concatenation operator 'II', then the types that have implicit coercion to text as listed in Table Data Types with Implicit Coercion to Text will not truncate the string if one of the input parameters is NULL, whereas for other types it will truncate the string unless the explicit type cast is used (that is, ::text). Also, to see the consistent behavior in the presence of nulls, one can use the CONCAT function.

The following query lists the data types that have implicit coercion to text:

```
SELECT castsource::regtype, casttarget::regtype, castfunc::regproc,
    CASE castcontext
        WHEN 'e' THEN 'explicit'
        WHEN 'a' THEN 'implicit in assignment'
        WHEN 'i' THEN 'implicit in expressions'
END as castcontext,
    CASE castmethod
        WHEN 'f' THEN 'function'
        WHEN 'i' THEN 'input/output function'
        WHEN 'b' THEN 'binary-coercible'
    END as castmethod
FROM pg_cast
    WHERE casttarget::regtype::text = 'text'
    AND castcontext='i';
```

The result of the query is listed in the following table:

Table - Data Types with Implicit Coercion to Text

castsource	casttarget	castfunc	castcontext	castmethod
character	text	pg_catalog.text	implicit in expressions	function
character varying	text	-	implicit in expressions	binary-coercible
"char"	text	pg_catalog.text	implicit in expressions	function
name	text	pg_catalog.text	implicit in expressions	function
pg_node_tree	text	-	implicit in expressions	binary-coercible
pg_ndistinct	text	-	implicit in expressions	input/output function
pg_dependencies	text	-	implicit in expressions	input/output function
integer	text	-	implicit in expressions	input/output function
smallint	text	-	implicit in expressions	input/output function
oid	text	-	implicit in expressions	input/output function
date	text	-	implicit in expressions	input/output function
double precision	text	-	implicit in expressions	input/output function
real	text	-	implicit in expressions	input/output function
time with time zone	text	-	implicit in expressions	input/output function
time without time zone	text	-	implicit in expressions	input/output function
timestamp with time zone	text	-	implicit in expressions	input/output function
interval	text	-	implicit in expressions	input/output function
bigint	text	-	implicit in expressions	input/output function
numeric	text	-	implicit in expressions	input/output function
timestamp without time zone	text	-	implicit in expressions	input/output function
record	text	-	implicit in expressions	input/output function
boolean	text	pg_catalog.text	implicit in expressions	function
bytea	text	-	implicit in expressions	input/output function

For information on the column output, see the pg_cast system catalog in the PostgreSQL core documentation available at:

https://www.postgresgl.org/docs/12/static/catalog-pg-cast.html

So for example, data type UUID is not in this list and therefore does not have the implicit coercion to text. As

a result, certain concatenation attempts with a NULL UUID column results in a truncated text result.

```
The following table is created for this example with a single row with all NULL column values.
```

```
CREATE TABLE null_concat_types (
    boolean_type
                     BOOLEAN,
    uuid_type
                     UUID,
                     CHARACTER
    char_type
);
INSERT INTO null_concat_types VALUES (NULL, NULL, NULL);
Columns boolean_type and char_type have the implicit coercion to text while column uuid_type
does not.
Thus, string concatenation with the concatenation operator 'II' against columns boolean_type or
char_type results in the following:
SELECT 'x=' || boolean_type || 'y' FROM null_concat_types;
 ?column?
x=y
(1 row)
SELECT 'x=' || char_type || 'y' FROM null_concat_types;
?column?
-----
X=Y
(1 row)
But concatenation with column uuid_{type} results in the loss of the x= string:
SELECT 'x=' || uuid_type || 'y' FROM null_concat_types;
 ?column?
_____
(1 row)
However, using explicit casting with ::text prevents the loss of the x= string:
SELECT 'x=' || uuid_type::text || 'y' FROM null_concat_types;
 ?column?
 x=y
(1 row)
Using the CONCAT function also preserves the x = string:
SELECT CONCAT('x=',uuid_type) || 'y' FROM null_concat_types;
?column?
_____
X=V
```

Thus, depending upon the data type of a NULL column, explicit casting or the CONCAT function should be used to avoid loss of some text string.

(1 row)

SYS GUID

The SYS_GUID function generates and returns a globally unique identifier; the identifier takes the form of 16 bytes of RAW data. The SYS_GUID function is based on the uuid-ossp module to generate universally unique identifiers. The synopsis is:

```
SYS_GUID()
```

Example

The following example adds a column to the table EMP, inserts a unique identifier, and returns a 16-byte RAW value:

4.1.3.5 Pattern Matching String Functions

Advanced Server offers support for the REGEXP_COUNT , REGEXP_INSTR and REGEXP_SUBSTR functions. These functions search a string for a pattern specified by a regular expression, and return information about occurrences of the pattern within the string. The pattern should be a POSIX-style regular expression; for more information about forming a POSIX-style regular expression, please refer to the core documentation at:

https://www.postgresql.org/docs/12/static/functions-matching.html

REGEXP COUNT

REGEXP_COUNT searches a string for a regular expression, and returns a count of the times that the regular expression occurs. The signature is:

```
INTEGER REGEXP_COUNT
(
    srcstr TEXT,
    pattern TEXT,
    position DEFAULT 1
    modifier DEFAULT NULL
)
```

Parameters

srcstr

srcstr specifies the string to search.

pattern

pattern specifies the regular expression for which REGEXP_COUNT will search.

position

position is an integer value that indicates the position in the source string at which REGEXP_COUNT will begin searching. The default value is 1.

modifier

modifier specifies values that control the pattern matching behavior. The default value is NULL . For a complete list of the modifiers supported by Advanced Server, see the PostgreSQL core documentation available at:

Example

In the following simple example, REGEXP_COUNT returns a count of the number of times the letter i is used in the character string 'reinitializing':

```
edb=# SELECT REGEXP_COUNT('reinitializing', 'i', 1) FROM DUAL;
regexp_count
-----
5
(1 row)
```

In the first example, the command instructs REGEXP_COUNT begins counting in the first position; if we modify the command to start the count on the 6th position:

```
edb=# SELECT REGEXP_COUNT('reinitializing', 'i', 6) FROM DUAL;
regexp_count
-----
3
(1 row)
```

REGEXP_COUNT returns 3; the count now excludes any occurrences of the letter i that occur before the 6th position.

REGEXP_INSTR

REGEXP_INSTR searches a string for a POSIX-style regular expression. This function returns the position within the string where the match was located. The signature is:

```
INTEGER REGEXP_INSTR
(

srcstr TEXT,
pattern TEXT,
position INT DEFAULT 1,
occurrence INT DEFAULT 1,
returnparam INT DEFAULT 0,
modifier TEXT DEFAULT NULL,
subexpression INT DEFAULT 0,
)
```

Parameters:

srcstr

srcstr specifies the string to search.

pattern

pattern specifies the regular expression for which REGEXP_INSTR will search.

position

position specifies an integer value that indicates the start position in a source string. The default value is 1.

occurrence

occurrence specifies which match is returned if more than one occurrence of the pattern occurs in the string that is searched. The default value is 1.

returnparam

returnparam is an integer value that specifies the location within the string that REGEXP_INSTR should return. The default value is 0. Specify:

0 to return the location within the string of the first character that matches pattern .

A value greater than 0 to return the position of the first character following the end of the pattern .

modifier

modifier specifies values that control the pattern matching behavior. The default value is NULL . For a complete list of the modifiers supported by Advanced Server, see the PostgreSQL core documentation available at:

https://www.postgresql.org/docs/12/static/functions-matching.html

subexpression

subexpression is an integer value that identifies the portion of the pattern that will be returned by REGEXP_INSTR . The default value of subexpression is 0.

If you specify a value for subexpression, you must include one (or more) set of parentheses in the pattern that isolate a portion of the value being searched for. The value specified by subexpression indicates which set of parentheses should be returned; for example, if subexpression is 2, REGEXP_INSTR will return the position of the second set of parentheses.

Example

In the following simple example, REGEXP_INSTR searches a string that contains the a phone number for the first occurrence of a pattern that contains three consecutive digits:

```
edb=# SELECT REGEXP_INSTR('800-555-1212', '[0-9][0-9][0-9]', 1, 1) FROM DUAL;
regexp_instr
-----
1
(1 row)
```

The command instructs REGEXP_INSTR to return the position of the first occurrence. If we modify the command to return the start of the second occurrence of three consecutive digits:

```
edb=# SELECT REGEXP_INSTR('800-555-1212', '[0-9][0-9][0-9]', 1, 2) FROM DUAL;
regexp_instr
-----
5
(1 row)
```

REGEXP_INSTR returns 5; the second occurrence of three consecutive digits begins in the 5th position.

REGEXP_SUBSTR

The REGEXP_SUBSTR function searches a string for a pattern specified by a POSIX compliant regular expression. REGEXP_SUBSTR returns the string that matches the pattern specified in the call to the function. The signature of the function is:

```
TEXT REGEXP_SUBSTR
(
srcstr TEXT,
pattern TEXT,
position INT DEFAULT 1,
occurrence INT DEFAULT 1,
modifier TEXT DEFAULT NULL,
subexpression INT DEFAULT 0
)
```

Parameters:

srcstr

srcstr specifies the string to search.

pattern

pattern specifies the regular expression for which REGEXP_SUBSTR will search.

position

position specifies an integer value that indicates the start position in a source string. The default value is 1.

occurrence

occurrence specifies which match is returned if more than one occurrence of the pattern occurs in the string that is searched. The default value is 1.

modifier

modifier specifies values that control the pattern matching behavior. The default value is NULL . For a complete list of the modifiers supported by Advanced Server, see the PostgreSQL core documentation available at:

https://www.postgresql.org/docs/12/static/functions-matching.html

subexpression

subexpression is an integer value that identifies the portion of the pattern that will be returned by REGEXP_SUBSTR . The default value of subexpression is 0 .

If you specify a value for subexpression, you must include one (or more) set of parentheses in the pattern that isolate a portion of the value being searched for. The value specified by subexpression indicates which set of parentheses should be returned; for example, if subexpression is 2, REGEXP_SUBSTR will return the value contained within the second set of parentheses.

Example

In the following simple example, REGEXP_SUBSTR searches a string that contains a phone number for the first set of three consecutive digits:

```
edb=# SELECT REGEXP_SUBSTR('800-555-1212', '[0-9][0-9][0-9]', 1, 1) FROM DUAL;
regexp_substr
------
800
(1 row)
```

It locates the first occurrence of three digits and returns the string (800); if we modify the command to check for the second occurrence of three consecutive digits:

```
edb=# SELECT REGEXP_SUBSTR('800-555-1212', '[0-9][0-9][0-9]', 1, 2) FROM DUAL; regexp_substr ______ 555 (1 row)

REGEXP_SUBSTR returns 555, the contents of the second substring.
```

4.1.3.6 Pattern Matching Using the LIKE Operator

Advanced Server provides pattern matching using the traditional SQL LIKE operator. The syntax for the LIKE operator is as follows.

```
string LIKE pattern [ ESCAPE escape-character ]
string NOT LIKE pattern [ ESCAPE escape-character ]
```

Every pattern defines a set of strings. The LIKE expression returns TRUE if string is contained in the set of strings represented by pattern. As expected, the NOT LIKE expression returns FALSE if LIKE returns TRUE, and vice versa. An equivalent expression is NOT (string LIKE pattern).

If pattern does not contain percent signs or underscore, then the pattern only represents the string itself; in that case LIKE acts like the equals operator. An underscore (_) in pattern stands for (matches) any single character; a percent sign (%) matches any string of zero or more characters.

Some examples:

```
'abc' LIKE 'abc' true
'abc' LIKE 'a%' true
'abc' LIKE '_b_' true
'abc' LIKE 'c' false
```

LIKE 'pattern matches always cover the entire string. To match a pattern anywhere within a string, the pattern must therefore start and end with a percent sign.

To match a literal underscore or percent sign without matching other characters, the respective character in pattern must be preceded by the escape character. The default escape character is the backslash but a different one may be selected by using the ESCAPE clause. To match the escape character itself, write two escape characters.

Note that the backslash already has a special meaning in string literals, so to write a pattern constant that contains a backslash you must write two backslashes in an SQL statement. Thus, writing a pattern that actually matches a literal backslash means writing four backslashes in the statement. You can avoid this by selecting a different escape character with ESCAPE; then a backslash is not special to LIKE anymore. (But it is still special to the string literal parser, so you still need two of them.)

It's also possible to select no escape character by writing ESCAPE '' . This effectively disables the escape mechanism, which makes it impossible to turn off the special meaning of underscore and percent signs in the pattern.

4.1.3.7 'Data Type Formatting Functions'

The Advanced Server formatting functions described in the following table provide a powerful set of tools for converting various data types (date/time, integer, floating point, numeric) to formatted strings and for converting from formatted strings to specific data types. These functions all follow a common calling convention: the first argument is the value to be formatted and the second argument is a string template that defines the output or input format.

Table - Formatting Functions

In an output template string (for TO_CHAR), there are certain patterns that are recognized and replaced with appropriately-formatted data from the value to be formatted. Any text that is not a template pattern is simply copied verbatim. Similarly, in an input template string (for anything but TO_CHAR), template patterns identify the parts of the input data string to be looked at and the values to be found there.

If you do not specify a date, month, or year when calling TO_TIMESTAMP or TO_DATE, then by default the output format considers the first date of a current month or current year respectively. In the following example, date, month, and year is not specified in the input string; TO_TIMESTAMP and TO_DATE returns a default value of the first date of a current month and current year.

```
01-JUL-19 12:00:00
(1 row)
```

The following table shows the template patterns available for formatting date values using the TO_CHAR, TO_DATE, and TO_TIMESTAMP functions.

Table - Template Date/Time Format Patterns

Certain modifiers may be applied to any template pattern to alter its behavior. For example, FMMonth is the Month pattern with the FM modifier. The following table shows the modifier patterns for date/time formatting.

Table - Template Pattern Modifiers for Date/Time Formatting

Modifier	Description	Example
FM prefix	Fill mode (suppress padding blanks and zeros)	FMMonth
TH suffix	Uppercase ordinal number suffix	DDTH
th suffix	Lowercase ordinal number suffix	DDth
FX prefix	Fixed format global option (see usage notes)	FX Month DD Day
SP suffix	Spell mode	DDSP

Usage notes for date/time formatting:

- FM suppresses leading zeroes and trailing blanks that would otherwise be added to make the output of a pattern fixed-width.
- TO_TIMESTAMP and TO_DATE skip multiple blank spaces in the input string if the FX option is not used. FX must be specified as the first item in the template. For example TO_TIMESTAMP('2000 JUN', 'YYYYY MON') is correct, but TO_TIMESTAMP('2000 JUN', 'FXYYYY MON') returns an error, because TO_TIMESTAMP expects one space only.
- Ordinary text is allowed in TO_CHAR templates and will be output literally.
- In conversions from string to timestamp or date , the CC field is ignored if there is a YYY , YYYY or Y, YYYY field. If CC is used with YY or Y then the year is computed as (CC-1)*100+YY.

The following table shows the template patterns available for formatting numeric values.

Table - Template Patterns for Numeric Formatting

Pattern	Description
9	Value with the specified number of digits
0	Value with leading zeroes
. (period)	Decimal point
, (comma)	Group (thousand) separator
\$	Dollar sign
PR	Negative value in angle brackets
S	Sign anchored to number (uses locale)
L	Currency symbol (uses locale)
D	Decimal point (uses locale)
G	Group separator (uses locale)
MI	Minus sign specified in right-most position (if number < 0)
RN or rn	Roman numeral (input between 1 and 3999)
V	Shift specified number of digits (see notes)

Usage notes for numeric formatting:

• 9 results in a value with the same number of digits as there are 9s . If a digit is not available it outputs a space.

TH does not convert values less than zero and does not convert fractional numbers.

V effectively multiplies the input values by 10n, where n is the number of digits following V. TO_CHAR does not support the use of V combined with a decimal point. (E.g., 99.9V99 is not allowed.)

The following table shows some examples of the use of the TO_CHAR and TO_DATE functions.

Table - TO_CHAR Examples

Expression	Result
TO_CHAR(CURRENT_TIMESTAMP, 'Day, DD HH12:MI:SS')	'Tuesday , 06 05:39:18'
TO_CHAR(CURRENT_TIMESTAMP, 'FMDay, FMDD HH12:MI:SS')	'Tuesday, 6 05:39:18'
TO_CHAR(-0.1, '99.99')	'10'
TO_CHAR(-0.1, 'FM9.99')	'1'
TO_CHAR(0.1, '0.9')	' 0.1'
TO_CHAR(12, '9990999.9')	' 0012.0'
TO_CHAR(12, 'FM9990999.9')	'0012.'
TO_CHAR(485, '999')	' 485'
TO_CHAR(-485, '999')	'-485'
TO_CHAR(1485, '9,999')	' 1,485'
TO_CHAR(1485, '9G999')	' 1,485'
TO_CHAR(148.5, '999.999')	' 148.500'
TO_CHAR(148.5, 'FM999.999')	'148.5'
TO_CHAR(148.5, 'FM999.990')	'148.500'
TO_CHAR(148.5, '999D999')	' 148.500'
TO_CHAR(3148.5, '9G999D999')	' 3,148.500'
TO_CHAR(-485, '999S')	'485-'
TO_CHAR(-485, '999MI')	'485-'
TO_CHAR(485, '999MI')	'485 '
TO_CHAR(485, 'FM999MI')	'485'
TO_CHAR(-485, '999PR')	'<485>'
TO_CHAR(485, 'L999')	'\$ 485'
TO_CHAR(485, 'RN')	' CDLXXXV'
TO_CHAR(485, 'FMRN')	'CDLXXXV'
TO_CHAR(5.2, 'FMRN')	'V'
TO_CHAR(12, '99V999')	' 12000'
TO_CHAR(12.4, '99V999')	' 12400'
TO_CHAR(12.45, '99V9')	' 125'

IMMUTABLE TO_CHAR(TIMESTAMP, format) Function

There are certain cases of the TO_CHAR function that can result in usage of an IMMUTABLE form of the function. Basically, a function is IMMUTABLE if the function does not modify the database, and the function returns the same, consistent value dependent upon only its input parameters. That is, the settings of configuration parameters, the locale, the content of the database, etc. do not affect the results returned by the function.

For more information about function volatility categories VOLATILE , STABLE , and IMMUTABLE , please see the PostgreSQL Core documentation at:

https://www.postgresql.org/docs/12/static/xfunc-volatility.html

A particular advantage of an IMMUTABLE function is that it can be used in the CREATE INDEX command to create an index based on that function.

In order for the TO_CHAR function to use the IMMUTABLE form the following conditions must be satisfied:

- The first parameter of the TO_CHAR function must be of data type TIMESTAMP .
- The format specified in the second parameter of the TO_CHAR function must not affect the return value of the function based on factors such as language, locale, etc. For example a format of 'YYYY-MM-DD HH24:MI:SS' can be used for an IMMUTABLE form of the function since, regardless of locale settings, the result of the function is the date and time expressed solely in numeric form.

However, a format of 'DD-MON-YYYY' cannot be used for an IMMUTABLE form of the function because the 3-character abbreviation of the month may return different results depending upon the locale setting.

Format patterns that result in a non-immutable function include any variations of spelled out or abbreviated months (MONTH, MON), days (DAY, DY), median indicators (AM, PM), or era indicators (BC, AD)

For the following example, a table with a TIMESTAMP column is created.

```
CREATE TABLE ts_tbl (ts_col TIMESTAMP);
```

The following shows the successful creation of an index with the IMMUTABLE form of the TO_CHAR function.

```
edb=# CREATE INDEX ts_idx ON ts_tbl (TO_CHAR(ts_col,'YYYY-MM-DD HH24:MI:SS'));
CREATE INDEX
```

edb=# \dS ts_idx

Index "public.ts_idx"
Column | Type | Definition

to_char | character varying | to_char(ts_col, 'YYYY-MM-DD HH24:MI:SS'::character varying)
btree, for table "public.ts_tbl"

The following results in an error because the format specified in the TO_CHAR function prevents the use of the IMMUTABLE form since the 3-character month abbreviation, MON, may result in different return values based on the locale setting.

```
edb=# CREATE INDEX ts_idx_2 ON ts_tbl (TO_CHAR(ts_col, 'DD-MON-YYYY'));
ERROR: functions in index expression must be marked IMMUTABLE
```

4.1.3.8 'Date/Time Functions and Operators'

Table - Date/Time Functions shows the available functions for date/time value processing, with details appearing in the following subsections. The following table illustrates the behaviors of the basic arithmetic operators (+, -) . For formatting functions, refer to Section - IMMUTABLE TO_CHAR(TIMESTAMP, format) Function <imm. You should be familiar with the background information on date/time data types from Section - Date/Time Type

Table - Date/Time Operators

Operator	Example	Result
plus (+)	DATE '2001-09-28' + 7	05-OCT-01 00:00:00
plus (+)	TIMESTAMP '2001-09-28 13:30:00' + 3	01-OCT-01 13:30:00
minus (-)	DATE '2001-10-01' – 7	24-SEP-01 00:00:00
minus (-)	TIMESTAMP '2001-09-28 13:30:00' - 3	25-SEP-01 13:30:00
minus (-)	TIMESTAMP '2001-09-29 03:00:00' - TIMESTAMP '2001-09-27 12:00:00'	@ 1 day 15 hours

In the date/time functions of the following table the use of the $\,$ DATE $\,$ and $\,$ TIMESTAMP $\,$ data types are interchangeable.

Table - Date/Time Functions

ADD MONTHS

The ADD_MONTHS functions adds (or subtracts if the second parameter is negative) the specified number of months to the given date. The resulting day of the month is the same as the day of the month of the given date except when the day is the last day of the month in which case the resulting date always falls on the last day of the month.

Any fractional portion of the number of months parameter is truncated before performing the calculation.

```
If the given date contains a time portion, it is carried forward to the result unchanged.
The following are examples of the ADD_MONTHS function.
SELECT ADD_MONTHS('13-JUN-07',4) FROM DUAL;
     add_months
 13-OCT-07 00:00:00
(1 row)
SELECT ADD_MONTHS('31-DEC-06',2) FROM DUAL;
     add_months
 28-FEB-07 00:00:00
(1 row)
SELECT ADD_MONTHS('31-MAY-04',-3) FROM DUAL;
     add months
 29-FEB-04 00:00:00
(1 row)
EXTRACT
The EXTRACT function retrieves subfields such as year or hour from date/time values. The EXTRACT
function returns values of type DOUBLE PRECISION . The following are valid field names:
YEAR
    The year field
SELECT EXTRACT(YEAR FROM TIMESTAMP '2001-02-16 20:38:40') FROM DUAL;
 date_part
      2001
(1 row)
MONTH
    The number of the month within the year (1 - 12)
SELECT EXTRACT(MONTH FROM TIMESTAMP '2001-02-16 20:38:40') FROM DUAL;
 date_part
          2
(1 row)
DAY
    The day (of the month) field (1 - 31)
SELECT EXTRACT(DAY FROM TIMESTAMP '2001-02-16 20:38:40') FROM DUAL;
 date_part
        16
(1 row)
HOUR
```

The hour field (0 - 23)

```
SELECT EXTRACT(HOUR FROM TIMESTAMP '2001-02-16 20:38:40') FROM DUAL;
 date_part
_____
        20
(1 row)
MINUTE
    The minutes field (0 - 59)
SELECT EXTRACT(MINUTE FROM TIMESTAMP '2001-02-16 20:38:40') FROM DUAL;
 date_part
        38
(1 row)
SECOND
    The seconds field, including fractional parts (0 - 59)
SELECT EXTRACT(SECOND FROM TIMESTAMP '2001-02-16 20:38:40') FROM DUAL;
 date_part
        40
(1 row)
```

MONTHS BETWEEN

The MONTHS_BETWEEN function returns the number of months between two dates. The result is a numeric value which is positive if the first date is greater than the second date or negative if the first date is less than the second date.

The result is always a whole number of months if the day of the month of both date parameters is the same, or both date parameters fall on the last day of their respective months.

The following are some examples of the MONTHS_BETWEEN function.

12

(1 row)

NEXT_DAY

The NEXT_DAY function returns the first occurrence of the given weekday strictly greater than the given date. At least the first three letters of the weekday must be specified - e.g., SAT . If the given date contains a time portion, it is carried forward to the result unchanged.

The following are examples of the NEXT_DAY function.

```
SELECT NEXT_DAY(TO_DATE('13-AUG-07','DD-MON-YY'),'SUNDAY') FROM DUAL;
```

```
next_day
-----19-AUG-07 00:00:00
(1 row)
```

SELECT NEXT_DAY(TO_DATE('13-AUG-07','DD-MON-YY'),'MON') FROM DUAL;

```
next_day
------
20-AUG-07 00:00:00
(1 row)
```

NEW_TIME

The NEW_TIME function converts a date and time from one time zone to another. NEW_TIME returns a value of type DATE . The syntax is:

NEW_TIME(DATE, time_zone1, time_zone2)

time_zone1 and time_zone2 must be string values from the Time Zone column of the following table:

Table - Time Zones

Time Zone	Offset from UTC	Description
AST	UTC+4	Atlantic Standard Time
ADT	UTC+3	Atlantic Daylight Time
BST	UTC+11	Bering Standard Time
BDT	UTC+10	Bering Daylight Time
CST	UTC+6	Central Standard Time
CDT	UTC+5	Central Daylight Time
EST	UTC+5	Eastern Standard Time
EDT	UTC+4	Eastern Daylight Time
GMT	UTC	Greenwich Mean Time
HST	UTC+10	Alaska-Hawaii Standard Time
HDT	UTC+9	Alaska-Hawaii Daylight Time
MST	UTC+7	Mountain Standard Time
MDT	UTC+6	Mountain Daylight Time
NST	UTC+3:30	Newfoundland Standard Time
PST	UTC+8	Pacific Standard Time
PDT	UTC+7	Pacific Daylight Time
YST	UTC+9	Yukon Standard Time
YDT	UTC+8	Yukon Daylight Time

Following is an example of the NEW_TIME function:

SELECT NEW_TIME(TO_DATE('08-13-07 10:35:15','MM-DD-YY HH24:MI:SS'),'AST', 'PST') "Pacific Standa

Pacific Standard Time

```
-----
13-AUG-07 06:35:15
(1 row)
```

ROUND

The ROUND function returns a date rounded according to a specified template pattern. If the template pattern is omitted, the date is rounded to the nearest day. The following table shows the template patterns for the ROUND function.

Table - Template Date Patterns for the ROUND Function

Pattern CC, SCC SYYY, YYYY, YEAR, SYEAR, YYY, YY, Y IYYY, IYY, IY, I Q MONTH, MON, MM, RM WW IW W DDD, DD, J DAY, DY, D HH, HH12, HH24	Description Returns January 1, cc01 where cc is first 2 digits of the given year if last 2 digit Returns January 1, yyyy where yyyy is rounded to the nearest year; rounds do Rounds to the beginning of the ISO year which is determined by rounding dow Returns the first day of the quarter determined by rounding down if the month a Returns the first day of the specified month if the day of the month is on or prio Round to the nearest date that corresponds to the same day of the week as th Round to the nearest date that corresponds to the same day of the week as th Rounds to the start of the nearest day; 11:59:59 AM or earlier rounds to the sta Round to the nearest Sunday Round to the nearest hour
MI	Round to the nearest minute

Following are examples of usage of the ROUND function.

The following examples round to the nearest hundred years.

```
SELECT TO_CHAR(ROUND(TO_DATE('1950','YYYY'),'CC'),'DD-MON-YYYY') "Century" FROM DUAL;
   Century
01-JAN-1901
(1 row)
SELECT TO_CHAR(ROUND(TO_DATE('1951','YYYY'),'CC'),'DD-MON-YYYY') "Century" FROM DUAL;
   Century
01-JAN-2001
(1 row)
The following examples round to the nearest year.
SELECT TO_CHAR(ROUND(TO_DATE('30-JUN-1999', 'DD-MON-YYYY'), 'Y'), 'DD-MON-YYYY') "Year" FROM DUAL;
```

```
Year
_____
01-JAN-1999
(1 row)
```

SELECT TO_CHAR(ROUND(TO_DATE('01-JUL-1999','DD-MON-YYYY'),'Y'),'DD-MON-YYYY') "Year" FROM DUAL;

```
Year
01-JAN-2000
(1 row)
```

The following examples round to the nearest ISO year. The first example rounds to 2004 and the ISO year for 2004 begins on December 29th of 2003. The second example rounds to 2005 and the ISO year for 2005

```
begins on January 3rd of that same year.
```

```
(An ISO year begins on the first Monday from which a 7 day span, Monday thru Sunday, contains at least 4 days of the new year. Thus, it is possible for the beginning of an ISO year to start in December of the prior year.)
```

```
SELECT TO_CHAR(ROUND(TO_DATE('30-JUN-2004','DD-MON-YYYY'),'IYYY'),'DD-MON-YYYY') "ISO Year" FROM
  ISO Year
 29-DEC-2003
(1 row)
SELECT TO_CHAR(ROUND(TO_DATE('01-JUL-2004','DD-MON-YYYY'),'IYYY'),'DD-MON-YYYY') "ISO Year" FROM
  ISO Year
 03-JAN-2005
(1 row)
The following example round to the nearest quarter:
SELECT ROUND(TO_DATE('15-FEB-07','DD-MON-YY'),'Q') "Quarter" FROM DUAL;
      Ouarter
 01-JAN-07 00:00:00
(1 row)
SELECT ROUND(TO_DATE('16-FEB-07','DD-MON-YY'),'Q') "Quarter" FROM DUAL;
      Quarter
 01-APR-07 00:00:00
(1 row)
The following example round to the nearest month:
SELECT ROUND(TO_DATE('15-DEC-07','DD-MON-YY'),'MONTH') "Month" FROM DUAL;
       Month
 01-DEC-07 00:00:00
(1 row)
SELECT ROUND(TO_DATE('16-DEC-07','DD-MON-YY'),'MONTH') "Month" FROM DUAL;
       Month
 01-JAN-08 00:00:00
(1 row)
The following examples round to the nearest week. The first day of 2007 lands on a Monday so in the first
example, January 18th is closest to the Monday that lands on January 15th. In the second example, January
19th is closer to the Monday that falls on January 22nd.
SELECT ROUND(TO_DATE('18-JAN-07','DD-MON-YY'),'WW') "Week" FROM DUAL;
        Week
 15-JAN-07 00:00:00
(1 row)
```

SELECT ROUND(TO_DATE('19-JAN-07','DD-MON-YY'),'WW') "Week" FROM DUAL;

```
______
 22-JAN-07 00:00:00
(1 row)
The following examples round to the nearest ISO week. An ISO week begins on a Monday. In the first example,
January 1, 2004 is closest to the Monday that lands on December 29, 2003. In the second example, January
2, 2004 is closer to the Monday that lands on January 5, 2004.
SELECT ROUND(TO_DATE('01-JAN-04','DD-MON-YY'),'IW') "ISO Week" FROM DUAL;
      ISO Week
 29-DEC-03 00:00:00
(1 row)
SELECT ROUND(TO_DATE('02-JAN-04','DD-MON-YY'),'IW') "ISO Week" FROM DUAL;
      ISO Week
 05-JAN-04 00:00:00
(1 row)
The following examples round to the nearest week where a week is considered to start on the same day as the
first day of the month.
SELECT ROUND(TO_DATE('05-MAR-07','DD-MON-YY'),'W') "Week" FROM DUAL;
 08-MAR-07 00:00:00
(1 row)
SELECT ROUND(TO_DATE('04-MAR-07','DD-MON-YY'),'W') "Week" FROM DUAL;
        Week
 01-MAR-07 00:00:00
(1 row)
The following examples round to the nearest day.
SELECT ROUND(TO_DATE('04-AUG-07 11:59:59 AM', 'DD-MON-YY HH:MI:SS AM'), 'J') "Day" FROM DUAL;
 04-AUG-07 00:00:00
(1 row)
SELECT ROUND(TO_DATE('04-AUG-07 12:00:00 PM', 'DD-MON-YY HH:MI:SS AM'), 'J') "Day" FROM DUAL;
        Day
 05-AUG-07 00:00:00
(1 row)
The following examples round to the start of the nearest day of the week (Sunday).
SELECT ROUND(TO_DATE('08-AUG-07','DD-MON-YY'),'DAY') "Day of Week" FROM DUAL;
    Day of Week
 05-AUG-07 00:00:00
(1 row)
```

Week

```
SELECT ROUND(TO_DATE('09-AUG-07','DD-MON-YY'),'DAY') "Day of Week" FROM DUAL;
   Day of Week
-----
 12-AUG-07 00:00:00
(1 row)
The following examples round to the nearest hour.
SELECT TO_CHAR(ROUND(TO_DATE('09-AUG-07 08:29','DD-MON-YY HH:MI'),'HH'),'DD-MON-
YY HH24:MI:SS') "Hour" FROM DUAL;
       Hour
 09-AUG-07 08:00:00
(1 row)
SELECT TO_CHAR(ROUND(TO_DATE('09-AUG-07 08:30','DD-MON-YY HH:MI'),'HH'),'DD-MON-
YY HH24:MI:SS') "Hour" FROM DUAL;
       Hour
______
09-AUG-07 09:00:00
(1 row)
The following examples round to the nearest minute.
SELECT TO_CHAR(ROUND(TO_DATE('09-AUG-07 08:30:29','DD-MON-YY HH:MI:SS'),'MI'),'DD-
MON-YY HH24:MI:SS') "Minute" FROM DUAL;
      Minute
09-AUG-07 08:30:00
(1 row)
SELECT TO_CHAR(ROUND(TO_DATE('09-AUG-07 08:30:30','DD-MON-YY HH:MI:SS'),'MI'),'DD-
MON-YY HH24:MI:SS') "Minute" FROM DUAL;
      Minute
09-AUG-07 08:31:00
(1 row)
```

TRUNC

The TRUNC function returns a date truncated according to a specified template pattern. If the template pattern is omitted, the date is truncated to the nearest day. The following table shows the template patterns for the TRUNC function.

Table - Template Date Patterns for the TRUNC Function

Pattern	Description
CC, SCC	Returns January 1, cc 01 where cc is first 2 digits of the given year
SYYY, YYYY, YEAR, SYEAR, YYY, YY, Y	Returns January 1, yyyy where yyyy is the given year
IYYY, IYY, IY, I	Returns the start date of the ISO year containing the given date
Q	Returns the first day of the quarter containing the given date
MONTH, MON, MM, RM	Returns the first day of the specified month
WW	Returns the largest date just prior to, or the same as the given date that corres
IW	Returns the start of the ISO week containing the given date
W	Returns the largest date just prior to, or the same as the given date that corres
DDD, DD, J	Returns the start of the day for the given date
DAY, DY, D	Returns the start of the week (Sunday) containing the given date
HH, HH12, HH24	Returns the start of the hour

Following are examples of usage of the TRUNC function.

The following example truncates down to the hundred years unit.

```
SELECT TO_CHAR(TRUNC(TO_DATE('1951','YYYY'),'CC'),'DD-MON-YYYY') "Century" FROM DUAL;
```

```
Century
-----
01-JAN-1901
(1 row)
```

The following example truncates down to the year.

```
SELECT TO_CHAR(TRUNC(TO_DATE('01-JUL-1999', 'DD-MON-YYYY'), 'Y'), 'DD-MON-YYYY') "Year" FROM DUAL;
```

```
Year
-----01-JAN-1999
(1 row)
```

The following example truncates down to the beginning of the ISO year.

SELECT TO_CHAR(TRUNC(TO_DATE('01-JUL-2004','DD-MON-YYYY'),'IYYY'),'DD-MON-YYYY') "ISO Year" FROM

```
ISO Year
-----29-DEC-2003
(1 row)
```

The following example truncates down to the start date of the quarter.

```
SELECT TRUNC(TO_DATE('16-FEB-07','DD-MON-YY'),'Q') "Quarter" FROM DUAL;
```

```
Quarter
-----01-JAN-07 00:00:00
(1 row)
```

The following example truncates to the start of the month.

```
SELECT TRUNC(TO_DATE('16-DEC-07','DD-MON-YY'),'MONTH') "Month" FROM DUAL;
```

```
Month
-----01-DEC-07 00:00:00
(1 row)
```

The following example truncates down to the start of the week determined by the first day of the year. The first day of 2007 lands on a Monday so the Monday just prior to January 19th is January 15th.

```
SELECT TRUNC(TO_DATE('19-JAN-07', 'DD-MON-YY'), 'WW') "Week" FROM DUAL;
```

The following example truncates to the start of an ISO week. An ISO week begins on a Monday. January 2, 2004 falls in the ISO week that starts on Monday, December 29, 2003.

```
SELECT TRUNC(TO_DATE('02-JAN-04','DD-MON-YY'),'IW') "ISO Week" FROM DUAL;
```

```
ISO Week
-----
```

```
29-DEC-03 00:00:00 (1 row)
```

The following example truncates to the start of the week where a week is considered to start on the same day as the first day of the month.

SELECT TRUNC(TO_DATE('21-MAR-07','DD-MON-YY'),'W') "Week" FROM DUAL;

The following example truncates to the start of the day.

SELECT TRUNC(TO_DATE('04-AUG-07 12:00:00 PM', 'DD-MON-YY HH:MI:SS AM'), 'J') "Day" FROM DUAL;

```
Day
-----04-AUG-07 00:00:00
(1 row)
```

The following example truncates to the start of the week (Sunday).

SELECT TRUNC(TO_DATE('09-AUG-07','DD-MON-YY'),'DAY') "Day of Week" FROM DUAL;

```
Day of Week
------
05-AUG-07 00:00:00
(1 row)
```

The following example truncates to the start of the hour.

SELECT TO_CHAR(TRUNC(TO_DATE('09-AUG-07 08:30','DD-MON-YY HH:MI'),'HH'),'DD-MON-YY HH24:MI:SS') "Hour" FROM DUAL;

```
Hour
-----09-AUG-07 08:00:00
(1 row)
```

The following example truncates to the minute.

SELECT TO_CHAR(TRUNC(TO_DATE('09-AUG-07 08:30:30','DD-MON-YY HH:MI:SS'),'MI'),'DD-MON-YY HH24:MI:SS') "Minute" FROM DUAL;

```
Minute
-----09-AUG-07 08:30:00
(1 row)
```

CURRENT DATE/TIME

Advanced Server provides a number of functions that return values related to the current date and time. These functions all return values based on the start time of the current transaction.

- CURRENT_DATE
- CURRENT_TIMESTAMP
- LOCALTIMESTAMP
- LOCALTIMESTAMP(precision)

CURRENT_DATE returns the current date and time based on the start time of the current transaction. The value of CURRENT_DATE will not change if called multiple times within a transaction.

SELECT CURRENT_DATE FROM DUAL;

```
date
-----
06-AUG-07
```

CURRENT_TIMESTAMP returns the current date and time. When called from a single SQL statement, it will return the same value for each occurrence within the statement. If called from multiple statements within a transaction, may return different values for each occurrence. If called from a function, may return a different value than the value returned by current_timestamp in the caller.

```
SELECT CURRENT_TIMESTAMP, CURRENT_TIMESTAMP FROM DUAL;
```

```
current_timestamp | current_timestamp
-----02-SEP-13 17:52:29.261473 +05:00 | 02-SEP-13 17:52:29.261474 +05:00
```

LOCALTIMESTAMP can optionally be given a precision parameter which causes the result to be rounded to that many fractional digits in the seconds field. Without a precision parameter, the result is given to the full available precision.

```
SELECT LOCALTIMESTAMP FROM DUAL;
```

Since these functions return the start time of the current transaction, their values do not change during the transaction. This is considered a feature: the intent is to allow a single transaction to have a consistent notion of the "current" time, so that multiple modifications within the same transaction bear the same time stamp. Other database systems may advance these values more frequently.

NUMTODSINTERVAL

The NUMTODSINTERVAL function converts a numeric value to a time interval that includes day through second interval units. When calling the function, specify the smallest fractional interval type to be included in the result set. The valid interval types are DAY, HOUR, MINUTE, and SECOND.

The following example converts a numeric value to a time interval that includes days and hours:

NUMTOYMINTERVAL

The NUMTOYMINTERVAL function converts a numeric value to a time interval that includes year through month interval units. When calling the function, specify the smallest fractional interval type to be included in the result set. The valid interval types are YEAR and MONTH.

The following example converts a numeric value to a time interval that includes years and months:

4.1.3.9 Sequence Manipulation Functions

This section describes Advanced Server's functions for operating on sequence objects. Sequence objects (also called sequence generators or just sequences) are special single-row tables created with the CREATE SEQUENCE command. A sequence object is usually used to generate unique identifiers for rows of a table. The sequence functions, listed below, provide simple, multiuser-safe methods for obtaining successive sequence values from sequence objects.

```
sequence.NEXTVAL sequence.CURRVAL
```

sequence is the identifier assigned to the sequence in the CREATE SEQUENCE command. The following describes the usage of these functions.

NEXTVAL

Advance the sequence object to its next value and return that value. This is done atomically: even if multiple sessions execute NEXTVAL concurrently, each will safely receive a distinct sequence value.

CURRVAL

Return the value most recently obtained by NEXTVAL for this sequence in the current session. (An error is reported if NEXTVAL has never been called for this sequence in this session.) Notice that because this is returning a session-local value, it gives a predictable answer whether or not other sessions have executed NEXTVAL since the current session did.

If a sequence object has been created with default parameters, NEXTVAL calls on it will return successive values beginning with 1. Other behaviors can be obtained by using special parameters in the command.

Important: To avoid blocking of concurrent transactions that obtain numbers from the same sequence, a NEXTVAL operation is never rolled back; that is, once a value has been fetched it is considered used, even if the transaction that did the NEXTVAL later aborts. This means that aborted transactions may leave unused "holes" in the sequence of assigned values.

4.1.3.10 Conditional Expressions

The following section describes the SQL-compliant conditional expressions available in Advanced Server.

CASE

The SQL CASE expression is a generic conditional expression, similar to if/else statements in other languages:

```
CASE WHEN condition THEN result

[ WHEN ... ]

[ ELSE result ]

FND
```

CASE clauses can be used wherever an expression is valid. condition is an expression that returns a BOOLEAN result. If the result is TRUE then the value of the CASE expression is the result that follows the condition. If the result is FALSE any subsequent WHEN clauses are searched in the same manner. If no WHEN condition is TRUE then the value of the CASE expression is the result in the ELSE clause. If the ELSE clause is omitted and no condition matches, the result is null.

An example:

```
SELECT * FROM test;
 а
 1
 2
 3
(3 rows)
SELECT a,
    CASE WHEN a=1 THEN 'one'
         WHEN a=2 THEN 'two'
         ELSE 'other'
    END
FROM test;
a I case
---+----
 1 | one
 2 I two
 3 | other
(3 rows)
```

The data types of all the result expressions must be convertible to a single output type.

The following "simple" CASE expression is a specialized variant of the general form above:

```
CASE expression
WHEN value THEN result
[ WHEN ... ]
[ ELSE result ]
END
```

The expression is computed and compared to all the value specifications in the WHEN clauses until one is found that is equal. If no match is found, the result in the ELSE clause (or a null value) is returned.

The example above can be written using the simple CASE syntax:

(3 rows)

A CASE expression does not evaluate any subexpressions that are not needed to determine the result. For example, this is a possible way of avoiding a division-by-zero failure:

```
SELECT ... WHERE CASE WHEN x \Leftrightarrow 0 THEN y/x > 1.5 ELSE false END;
```

COALESCE

The COALESCE function returns the first of its arguments that is not null. Null is returned only if all arguments are null.

```
COALESCE(value [, value2 ] ... )
```

It is often used to substitute a default value for null values when data is retrieved for display or further computation. For example:

```
SELECT COALESCE(description, short_description, '(none)') ...
```

Like a CASE expression, COALESCE will not evaluate arguments that are not needed to determine the result; that is, arguments to the right of the first non-null argument are not evaluated. This SQL-standard function provides capabilities similar to NVL and IFNULL, which are used in some other database systems.

NULLIF

The NULLIF function returns a null value if value1 and value2 are equal; otherwise it returns value1

NULLIF(value1, value2)

This can be used to perform the inverse operation of the COALESCE example given above:

SELECT NULLIF(value1, '(none)') ...

If value1 is (none), return a null, otherwise return value1.

NVL

The NVL function returns the first of its arguments that is not null. NVL evaluates the first expression; if that expression evaluates to NULL, NVL returns the second expression.

```
NVL(expr1, expr2)
```

The return type is the same as the argument types; all arguments must have the same data type (or be coercible to a common type). NVL returns NULL if all arguments are NULL.

The following example computes a bonus for non-commissioned employees, If an employee is a commissioned employee, this expression returns the employees commission; if the employee is not a commissioned employee (that is, his commission is NULL), this expression returns a bonus that is 10% of his salary.

```
bonus = NVL(emp.commission, emp.salary * .10)
```

NVL2

NVL2 evaluates an expression, and returns either the second or third expression, depending on the value of the first expression. If the first expression is not NULL, NVL2 returns the value in expr2; if the first expression is NULL, NVL2 returns the value in expr3.

```
NVL2(expr1, expr2, expr3)
```

The return type is the same as the argument types; all arguments must have the same data type (or be coercible to a common type).

The following example computes a bonus for commissioned employees - if a given employee is a commissioned employee, this expression returns an amount equal to 110% of his commission; if the employee is not a commissioned employee (that is, his commission is NULL), this expression returns 0.

bonus = NVL2(emp.commission, emp.commission * 1.1, 0)

GREATEST and LEAST

The GREATEST and LEAST functions select the largest or smallest value from a list of any number of expressions.

```
GREATEST(value [, value2 ] ... )
LEAST(value [, value2 ] ... )
```

The expressions must all be convertible to a common data type, which will be the type of the result. Null values in the list are ignored. The result will be null only if all the expressions evaluate to null.

Note that GREATEST and LEAST are not in the SQL standard, but are a common extension.

4.1.3.11 Aggregate Functions

Aggregate functions compute a single result value from a set of input values. The built-in aggregate functions are listed in the following tables.

Table - General-Purpose Aggregate Functions

Function	Argument Type	Return Type
AVG(expression) COUNT(*)	INTEGER, REAL, DOUBLE PRECISION, NUMBER	NUMBER for any integer type, DOUR
COUNT(expression)	Any	BIGINT
MAX(expression)	Any numeric, string, date/time, or bytea type	Same as argument type
MIN(expression)	Any numeric, string, date/time, or bytea type	Same as argument type
SUM(expression)	INTEGER, REAL, DOUBLE PRECISION, NUMBER	BIGINT for SMALLINT or INTEGER :

It should be noted that except for COUNT, these functions return a null value when no rows are selected. In particular, SUM of no rows returns null, not zero as one might expect. The COALESCE function may be used to substitute zero for null when necessary.

The following table shows the aggregate functions typically used in statistical analysis. (These are separated out merely to avoid cluttering the listing of more-commonly-used aggregates.) Where the description mentions N, it means the number of input rows for which all the input expressions are non-null. In all cases, null is returned if the computation is meaningless, for example when N is zero.

Table - Aggregate Functions for Statistics

Function	Argument Type	Return Type
CORR(Y, X)	DOUBLE PRECISION	DOUBLE PRECISION
COVAR_POP(Y, X)	DOUBLE PRECISION	DOUBLE PRECISION
COVAR_SAMP(Y, X)	DOUBLE PRECISION	DOUBLE PRECISION
REGR_AVGX(Y, X)	DOUBLE PRECISION	DOUBLE PRECISION
REGR_AVGY(Y, X)	DOUBLE PRECISION	DOUBLE PRECISION
REGR_COUNT(Y, X)	DOUBLE PRECISION	DOUBLE PRECISION
REGR_INTERCEPT(Y, X)	DOUBLE PRECISION	DOUBLE PRECISION
REGR_R2(Y, X)	DOUBLE PRECISION	DOUBLE PRECISION
REGR_SLOPE(Y, X)	DOUBLE PRECISION	DOUBLE PRECISION
REGR_SXX(Y, X)	DOUBLE PRECISION	DOUBLE PRECISION
REGR_SXY(Y, X)	DOUBLE PRECISION	DOUBLE PRECISION
REGR_SYY(Y, X)	DOUBLE PRECISION	DOUBLE PRECISION
STDDEV(expression)	INTEGER, REAL, DOUBLE PRECISION, NUMBER	DOUBLE PRECISION for floating-p
STDDEV_POP(expression)	INTEGER, REAL, DOUBLE PRECISION, NUMBER	DOUBLE PRECISION for floating-p
STDDEV_SAMP(expression)	INTEGER, REAL, DOUBLE PRECISION, NUMBER	DOUBLE PRECISION for floating-p
VARIANCE(expression)	INTEGER, REAL, DOUBLE PRECISION, NUMBER	DOUBLE PRECISION for floating-p
VAR_POP(expression)	INTEGER, REAL, DOUBLE PRECISION, NUMBER	DOUBLE PRECISION for floating-p
VAR_SAMP(expression)	INTEGER, REAL, DOUBLE PRECISION, NUMBER	DOUBLE PRECISION for floating-p

LISTAGG

Advanced Server has added the LISTAGG function to support string aggregation. LISTAGG is an aggregate function that concatenates data from multiple rows into a single row in an ordered manner. You can optionally include a custom delimiter for your data.

The LISTAGG function mandates the use of an ORDER BY clause under a WITHIN GROUP clause to concatenate values of the measure column, and then generate the ordered aggregated data.

Purpose

- LISTAGG can be used without any grouping. In this case, the LISTAGG function operates on all rows in a table and returns a single row.
- LISTAGG can be used with the GROUP BY clause. In this case, the LISTAGG function operates on each group and returns an aggregated output for each group.
- LISTAGG can be used with the OVER clause. In this case, the LISTAGG function partitions a query result set into groups based on the expression in the query_partition_by_clause and then aggregates data in each group.

Synopsis

LISTAGG(measure_expr [, delimiter]) WITHIN GROUP(order_by_clause) [OVER query_partition_by_cl

Parameters

measure_expr

measure_expr (mandatory) specifies the column or expression that assigns a value to aggregate.

NULL values are ignored.

delimiter

delimiter (optional) specifies a string that separates the concatenated values in the result row. The delimiter can be a NULL value, string, character literal, column name, or constant expression. If ignored, the LISTAGG function uses a NULL value by default.

order_by_clause

order_by_clause (mandatory) determines the sort order in which the concatenated values are returned.

query_partition_by_clause

query_partition_by_clause (optional) allows LISTAGG function to be used as an analytic function and sets the range of records for each group in the OVER clause.

Return Type

The LISTAGG function returns a string value.

Examples

The following example concatenates the values in the EMP table and lists all the employees separated by a delimiter comma.

First, create a table named EMP and then insert records into the EMP table.

```
edb=# CREATE TABLE EMP
             (EMPNO NUMBER(4) NOT NULL,
edb-#
edb(#
              ENAME VARCHAR2(10),
edb(#
              JOB VARCHAR2(9),
edb(#
              MGR NUMBER(4),
              HIREDATE DATE,
edb(#
              SAL NUMBER(7, 2),
edb(#
edb(#
              COMM NUMBER(7, 2),
edb(#
              DEPTNO NUMBER(2));
```

```
CREATE TABLE
edb=# INSERT INTO EMP VALUES
edb-#
               (7499, 'ALLEN',
                                 'SALESMAN', 7698,
edb(#
               TO_DATE('20-FEB-1981', 'DD-MON-YYYY'), 1600,
                                                                300, 30);
INSERT 0 1
edb=# INSERT INTO EMP VALUES
               (7521, 'WARD',
                                 'SALESMAN',
                                             7698,
edb-#
               TO_DATE('22-FEB-1981', 'DD-MON-YYYY'), 1250,
edb(#
                                                              500, 30);
INSERT 0 1
edb=# INSERT INTO EMP VALUES
               (7566, 'JONES',
edb-#
                                 'MANAGER',
                                               7839.
               TO_DATE('2-APR-1981', 'DD-MON-YYYY'), 2975, NULL, 20);
edb(#
INSERT 0 1
edb=# INSERT INTO EMP VALUES
edb-#
               (7654, 'MARTIN', 'SALESMAN', 7698,
               TO_DATE('28-SEP-1981', 'DD-MON-YYYY'), 1250, 1400, 30);
edb(#
INSERT 0 1
edb=# INSERT INTO EMP VALUES
edb-#
               (7698, 'BLAKE',
                               'MANAGER', 7839,
               TO_DATE('1-MAY-1981', 'DD-MON-YYYY'),
                                                        2850, NULL, 30);
edb(#
INSERT 0 1
edb=# SELECT LISTAGG(ENAME, ',') WITHIN GROUP (ORDER BY ENAME) FROM EMP;
               listagg
ALLEN, BLAKE, JONES, MARTIN, WARD
(1 row)
The following example uses PARTITION BY clause with LISTAGG in EMP table and generates output
based on a partition by DEPTNO that applies to each partition and not on the entire table.
edb=# SELECT DISTINCT DEPTNO, LISTAGG(ENAME, ',') WITHIN GROUP (ORDER BY ENAME) OVER(PARTITION BY
 deptno |
                   listagg
     30 | ALLEN, BLAKE, MARTIN, WARD
     20 | JONES
(2 rows)
The following example is identical to the previous example, except it includes the GROUP BY clause.
edb=# SELECT DEPTNO, LISTAGG(ENAME, ',') WITHIN GROUP (ORDER BY ENAME) FROM EMP GROUP BY DEPTNO;
 deptno I
                   listagg
     20 | JONES
     30 | ALLEN, BLAKE, MARTIN, WARD
(2 rows)
```

MEDIAN

The MEDIAN function that calculates the middle value of an expression from a given range of values; NULL values are ignored. The MEDIAN function returns an error if a query does not reference the user-defined table.

Purpose

- MEDIAN can be used without any grouping. In this case, the MEDIAN function operates on all rows in a table and returns a single row.
- MEDIAN can be used with the OVER clause. In this case, the MEDIAN function partitions a query result set into groups based on the expression specified in the PARTITION BY clause and then aggregates data in each group.

Synopsis

```
MEDIAN( median_expression ) [ OVER ( [ PARTITION BY... ] ) ]
```

Parameters

median_expression

median_expression (mandatory) is a target column or expression that the MEDIAN function operates on and returns a median value. It can be a numeric, datetime, or interval data type.

PARTITION BY

PARTITION BY clause (optional) allows a MEDIAN function to be used as an analytic function and sets the range of records for each group in the OVER clause.

Return Types

The return type is determined by the input data type of expression. The following table illustrates the return type for each input type.

Table - Input Types

Input Type	Return Type
NUMERIC	NUMERIC
FLOAT, DOUBLE PRECISION	DOUBLE PRECISION
REAL	REAL
INTERVAL	INTERVAL
DATE	DATE
TIMESTAMP	TIMESTAMP
TIMESTAMPTZ	TIMESTAMPTZ

Examples

In the following example, a query returns the median salary for each department in the EMP table:

```
edb=# SELECT * FROM EMP;
```

•			_		_		hiredate						•
7369 l	SMITH	İ	CLERK	İ	7902	İ	17-DEC-80 00:00:0 20-FEB-81 00:00:0	0	800.00	İ		İ	20
7521 l	WARD		SALESMAN	1	7698		22-FEB-81 00:00:0	0	1250.00		500.00		30
7566 l	JONES		MANAGER	1	7839		02-APR-81 00:00:0	0	2975.00				20
7654 l	MARTIN	-	SALESMAN	I	7698		28-SEP-81 00:00:0	0	1250.00	1	1400.00	1	30
(5 rows)													

```
edb=# SELECT MEDIAN (SAL) FROM EMP;
median
-----
1250
(1 row)
```

The following example uses PARTITION BY clause with MEDIAN in EMP table and returns the median salary based on a partition by DEPTNO:

edb=# SELECT EMPNO, ENAME, DEPTNO, MEDIAN (SAL) OVER (PARTITION BY DEPTNO) FROM EMP; empno | ename | deptno | median

```
7369 | SMITH | 20 | 1887.5
7566 | JONES | 20 | 1887.5
7499 | ALLEN | 30 | 1250
7521 | WARD | 30 | 1250
7654 | MARTIN | 30 | 1250
(5 rows)
```

The MEDIAN function can be compared with PERCENTILE_CONT . In the following example, MEDIAN

generates the same result as PERCENTILE_CONT:

4.1.3.12 Subquery Expressions

This section describes the SQL-compliant subquery expressions available in Advanced Server. All of the expression forms documented in this section return Boolean (TRUE/FALSE) results.

EXISTS

The argument of EXISTS is an arbitrary SELECT statement, or subquery. The subquery is evaluated to determine whether it returns any rows. If it returns at least one row, the result of EXISTS is TRUE; if the subquery returns no rows, the result of EXISTS is FALSE.

EXISTS(subquery)

The subquery can refer to variables from the surrounding query, which will act as constants during any one evaluation of the subquery.

The subquery will generally only be executed far enough to determine whether at least one row is returned, not all the way to completion. It is unwise to write a subquery that has any side effects (such as calling sequence functions); whether the side effects occur or not may be difficult to predict.

Since the result depends only on whether any rows are returned, and not on the contents of those rows, the output list of the subquery is normally uninteresting. A common coding convention is to write all EXISTS tests in the form EXISTS(SELECT 1 WHERE ...) . There are exceptions to this rule however, such as subqueries that use INTERSECT .

This simple example is like an inner join on deptno, but it produces at most one output row for each dept row, even though there are multiple matching emp rows:

SELECT dname FROM dept WHERE EXISTS (SELECT 1 FROM emp WHERE emp.deptno = dept.deptno);

```
dname
-----ACCOUNTING
RESEARCH
SALES
(3 rows)
```

IN

The right-hand side is a parenthesized subquery, which must return exactly one column. The left-hand expression is evaluated and compared to each row of the subquery result. The result of IN is TRUE if any equal subquery row is found. The result is FALSE if no equal row is found (including the special case where the subquery returns no rows).

```
expression IN (subquery)
```

Note that if the left-hand expression yields NULL , or if there are no equal right-hand values and at least one right-hand row yields NULL , the result of the IN construct will be NULL , not FALSE . This is in accordance with SQL's normal rules for Boolean combinations of null values.

As with EXISTS, it's unwise to assume that the subquery will be evaluated completely.

NOT IN

The right-hand side is a parenthesized subquery, which must return exactly one column. The left-hand expression is evaluated and compared to each row of the subquery result. The result of NOT IN is TRUE if only unequal subquery rows are found (including the special case where the subquery returns no rows). The result is FALSE if any equal row is found.

```
expression NOT IN (subquery)
```

Note that if the left-hand expression yields NULL , or if there are no equal right-hand values and at least one right-hand row yields NULL , the result of the NOT IN construct will be NULL , not TRUE . This is in accordance with SQL's normal rules for Boolean combinations of null values.

As with EXISTS, it's unwise to assume that the subquery will be evaluated completely.

ANY/SOME

The right-hand side is a parenthesized subquery, which must return exactly one column. The left-hand expression is evaluated and compared to each row of the subquery result using the given operator, which must yield a Boolean result. The result of ANY is TRUE if any true result is obtained. The result is FALSE if no true result is found (including the special case where the subquery returns no rows).

```
expression operator ANY (subquery) expression operator SOME (subquery)
```

SOME is a synonym for ANY. IN is equivalent to = ANY.

Note that if there are no successes and at least one right-hand row yields NULL for the operator's result, the result of the ANY construct will be NULL, not FALSE. This is in accordance with SQL's normal rules for Boolean combinations of null values.

As with EXISTS, it's unwise to assume that the subquery will be evaluated completely.

ALL

The right-hand side is a parenthesized subquery, which must return exactly one column. The left-hand expression is evaluated and compared to each row of the subquery result using the given operator, which must yield a Boolean result. The result of ALL is TRUE if all rows yield true (including the special case where the subquery returns no rows). The result is FALSE if any false result is found. The result is NULL if the comparison does not return FALSE for any row, and it returns NULL for at least one row.

expression operator ALL (subquery)

NOT IN is equivalent to \Leftrightarrow ALL . As with EXISTS , it's unwise to assume that the subquery will be evaluated completely.

4.2 'System Catalog Tables'

The following system catalog tables contain definitions of database objects. The layout of the system tables is subject to change; if you are writing an application that depends on information stored in the system tables, it would be prudent to use an existing catalog view, or create a catalog view to isolate the application from changes to the system table.

dual

dual is a single-row, single-column table that is provided for compatibility with Oracle databases only.

Column	Туре	Modifiers	Description
dummy	VARCHAR2(1)		Provided for compatibility only.

edb dir

The edb_dir table contains one row for each alias that points to a directory created with the create directory command. A directory is an alias for a pathname that allows a user limited access to the host file system.

You can use a directory to fence a user into a specific directory tree within the file system. For example, the UTL_FILE package offers functions that permit a user to read and write files and directories in the host file system, but only allows access to paths that the database administrator has granted access to via a create directory command.

Column	Туре	Modifiers	Description
dirname dirowner dirpath diracl	"name" oid text aclitem[]	not null not null	The name of the alias. The OID of the user that owns the alias. The directory name to wh

edb_password_history

The edb_password_history table contains one row for each password change. The table is shared across all databases within a cluster.

Column	Туре	References	Description
passhistroleid passhistpassword passhistpasswordsetat	oid text timestamptz	pg_authid.oid	The ID of a role. Role pa

edb_policy

The edb_policy table contains one row for each policy.

edb_profile

The edb_profile table stores information about the available profiles. edb_profiles is shared across all databases within a cluster.

Column

oid prfname prffailedloginattempts prfpasswordlocktime prfpasswordlifetime prfpasswordgracetime prfpasswordreusetime prfpasswordverifyfuncdb prfpasswordverifyfunc

edb_variable

The edb_variable table contains one row for each package level variable (each variable declared within a package).

pg_synonym

The pg_synonym table contains one row for each synonym created with the CREATE SYNONYM command or CREATE PUBLIC SYNONYM command.

Column	Туре	Modifiers	Description
synname	"name"	not null	The name of the synonym.
synnamespace	oid	not null	Replaces synowner. Contains the OID of the pg_namespace row where the
synowner	oid	not null	The OID of the user that owns the synonym.
synobjschema	"name"	not null	The schema in which the referenced object is defined.
synobjname synlink	"name" text	not null	The name of the referenced object. The (optional) name of the database I

product component version

The product_component_version table contains information about feature compatibility; an application can query this table at installation or run time to verify that features used by the application are available with this deployment.

Column	Туре	Description
product version status	character varying (74) character varying (74) character varying (74)	The name of the product. The version number of the product. The status of the release.

4.3 Acknowledgements

The PostgreSQL 8.3, 8.4, 9.0, 9.1, 9.2, 9.3, 9.4, 9.5, 9.6, 10, 11, and 12. Documentation provided the baseline for the portions of this guide that are common to PostgreSQL, and is hereby acknowledged:

Portions of this EnterpriseDB Software and Documentation may utilize the following copyrighted material, the use of which is hereby acknowledged.

PostgreSQL Documentation, Database Management System

PostgreSQL is Copyright © 1996-2018 by the PostgreSQL Global Development Group and is distributed under the terms of the license of the University of California below.

Postgres95 is Copyright © 1994-5 by the Regents of the University of California.

Permission to use, copy, modify, and distribute this software and its documentation for any purpose, without fee, and without a written agreement is hereby granted, provided that the above copyright notice and this paragraph and the following two paragraphs appear in all copies.

IN NO EVENT SHALL THE UNIVERSITY OF CALIFORNIA BE LIABLE TO ANY PARTY FOR DIRECT, INDIRECT, SPECIAL, INCIDENTAL, OR CONSEQUENTIAL DAMAGES, INCLUDING LOST PROFITS, ARISING OUT OF THE USE OF THIS SOFTWARE AND ITS DOCUMENTATION, EVEN IF THE UNIVERSITY OF CALIFORNIA HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

THE UNIVERSITY OF CALIFORNIA SPECIFICALLY DISCLAIMS ANY WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTIC-ULAR PURPOSE. THE SOFTWARE PROVIDED HEREUNDER IS ON AN "AS-IS" BASIS, AND THE UNIVERSITY OF CALIFORNIA HAS NO OBLIGATIONS TO PROVIDE MAINTENANCE, SUPPORT, UPDATES, ENHANCEMENTS, OR MODIFICATIONS.

4.4 Conclusion

EDB Postgres Advanced Server Database Compatibility for Oracle Developer's Reference Guide

Copyright © 2007 - 2020 EnterpriseDB Corporation.

All rights reserved.

EnterpriseDB Corporation

34 Crosby Drive, Suite 201, Bedford, MA 01730, USA

T +1 781 357 3390 F +1 978 467 1307 E

info@enterprisedb.com

www.enterprisedb.com

 EDB designs, establishes coding best practices, reviews, and verifies input validation for the logon UI for EDB Postgres products where present. EDB follows the same approach for additional input components, however the nature of the product may require that it accepts freeform SQL, WMI or other strings to be entered and submitted by trusted users for which limited validation is possible. In such cases it is not possible to prevent users from entering incorrect or otherwise dangerous inputs.

- EDB reserves the right to add features to products that accept freeform SQL, WMI or other potentially dangerous inputs from authenticated, trusted users in the future, but will ensure all such features are designed and tested to ensure they provide the minimum possible risk, and where possible, require superuser or equivalent privileges.
- EDB does not that warrant that we can or will anticipate all potential threats and therefore our process cannot fully guarantee that all potential vulnerabilities have been addressed or considered.

5.0 Database Compatibility for Oracle Developers Built-in Packages Guide

5.1 Introduction

Database Compatibility for Oracle means that an application runs in an Oracle environment as well as in the EDB Postgres Advanced Server (Advanced Server) environment with minimal or no changes to the application code. This guide focuses solely on the features that are related to the package support provided by Advanced Server.

For more information about using other compatibility features offered by Advanced Server, please see the complete set of Advanced Server guides, available at:

https://www.enterprisedb.com/edb-docs/

What's New

The following database compatibility for Oracle features have been added to Advanced Server 11 to create Advanced Server 12:

- Advanced Server introduces COMPOUND TRIGGERS, which are stored as a PL block that executes in response to a specified triggering event. For information, see the *Database Compatibility for Oracle Developer's Guide*.
- Advanced Server now supports new DATA DICTIONARY VIEWS that provide information compatible
 with the Oracle data dictionary views. For information, see the Database Compatibility for Oracle Developer's Reference Guide.
- Advanced Server has added the LISTAGG function to support string aggregation that concatenates data from multiple rows into a single row in an ordered manner. For information, see the *Database Compatibility* for Oracle Developer's Reference Guide.
- Advanced Server now supports CAST(MULTISET) function, allowing subquery output to be CAST to a nested table type. For information, see the *Database Compatibility for Oracle Developer's Reference Guide*.
- Advanced Server has added the MEDIAN function to calculate a median value from the set of provided values. For information, see the *Database Compatibility for Oracle Developer's Reference Guide*.
- Advanced Server has added the SYS_GUID function to generate and return a globally unique identifier in the form of 16-bytes of RAW data. For information, see the *Database Compatibility for Oracle Developer's Reference Guide*.
- Advanced Server now supports an Oracle-compatible SELECT UNIQUE clause in addition to an existing SELECT DISTINCT clause. For information, see the *Database Compatibility for Oracle Developer's Reference Guide*.
- Advanced Server has re-implemented default_with_rowids to create a table that includes a
 ROWID column in the newly created table. For information, see the EDB Postgres Advanced Server
 Guide
- Advanced Server now supports logical decoding on the standby server, which allows creating a logical replication slot on a standby, independently of a primary server. For information, see the EDB Postgres Advanced Server Guide.
- Advanced Server introduces INTERVAL PARTITIONING, which allows a database to automatically create partitions of a specified interval as new data is inserted into a table. For information, see the Database Compatibility for Oracle Developer's Guide.

Note

Database Compatibility for Oracle Developer's Guide, Database Compatibility for Oracle Developer's Reference Guide, and EDB Postgres Advanced Server Guides are available at:

https://www.enterprisedb.com/edb-docs/

5.2.0 Packages

This chapter discusses the concept of packages in Advanced Server. A *package* is a named collection of functions, procedures, variables, cursors, user-defined record types, and records that are referenced using a common qualifier – the package identifier. Packages have the following characteristics:

- Packages provide a convenient means of organizing the functions and procedures that perform a related purpose. Permission to use the package functions and procedures is dependent upon one privilege granted to the entire package. All of the package programs must be referenced with a common name.
- Certain functions, procedures, variables, types, etc. in the package can be declared as public. Public entities are visible and can be referenced by other programs that are given EXECUTE privilege on the package. For public functions and procedures, only their signatures are visible the program names, parameters if any, and return types of functions. The SPL code of these functions and procedures is not accessible to others, therefore applications that utilize a package are dependent only upon the information available in the signature not in the procedural logic itself.
- Other functions, procedures, variables, types, etc. in the package can be declared as private. Private
 entities can be referenced and used by function and procedures within the package, but not by other
 external applications. Private entities are for use only by programs within the package.
- Function and procedure names can be overloaded within a package. One or more functions/procedures can be defined with the same name, but with different signatures. This provides the capability to create identically named programs that perform the same job, but on different types of input.

5.2.1 Package Components

Packages consist of two main components:

- The package specification: This is the public interface, (these are the elements which can be referenced
 outside the package). We declare all database objects that are to be a part of our package within the
 specification.
- The *package body*: This contains the actual implementation of all the database objects declared within the package specification.

The package body implements the specifications in the package specification. It contains implementation details and private declarations which are invisible to the application. You can debug, enhance or replace a package body without changing the specifications. Similarly, you can change the body without recompiling the calling programs because the implementation details are invisible to the application.

Package Specification Syntax

The package specification defines the user interface for a package (the API). The specification lists the functions, procedures, types, exceptions and cursors that are visible to a user of the package.

The syntax used to define the interface for a package is:

```
CREATE [ OR REPLACE ] PACKAGE <package_name>
[ <authorization_clause> ]
{ IS | AS }
[ <declaration>; ] ...
[ <procedure_or_function_declaration> ] ...
END [ <package_name> ] ;
```

```
Where <authorization_clause> :=
>{ AUTHID DEFINER } | { AUTHID CURRENT_USER }
Where cprocedure_or_function_declaration> :=
> < procedure_declaration> | <function_declaration>
Where cedure_declaration> :=
    Where <function_declaration> :=
    FUNCTION <func_name> [ <argument_list> ]
    [RETURN](#rettype>[DETERMINISTIC]; \[ <restriction_pragma);]</pre>
Where <argument_list> :=
    ( <argument_declaration> [, ...])
Where <argument_declaration> :=
> <argname> [ IN | IN OUT | OUT ] <argtype> [ DEFAULT <value> ]
Where <restriction_pragma> :=
    PRAGMA RESTRICT_REFERENCES ( <name>, <restrictions>)
Where <restrictions> :=
    <restriction> [, ... ]
```

Parameters

<package_name>

<package_name> is an identifier assigned to the package - each package must have a name
unique within the schema.

AUTHID DEFINER

If you omit the AUTHID clause or specify AUTHID DEFINER, the privileges of the package owner are used to determine access privileges to database objects.

AUTHID CURRENT_USER

If you specify AUTHID CURRENT_USER, the privileges of the current user executing a program in the package are used to determine access privileges.

<declaration>

<declaration> can be any of the following:

- · Variable Declaration
- · Record Declaration
- · Collection Declaration
- REF CURSOR and Cursor Variable Declaration
- TYPE Definitions for Records, Collections, and REF CURSORs
- Exception

· Object Variable Declaration

```
oc_name>
```

The name of a public procedure.

```
<argname>
```

The name of an argument. The argument is referenced by this name within the function or procedure body.

```
IN | IN OUT | OUT
```

The argument mode. IN declares the argument for input only. This is the default. IN OUT allows the argument to receive a value as well as return a value. OUT specifies the argument is for output only.

```
<argtype>
```

The data type(s) of an argument. An argument type may be a base data type, a copy of the type of an existing column using %TYPE, or a user-defined type such as a nested table or an object type. A length must not be specified for any base type - for example, specify VARCHAR2, not VARCHAR2(10).

The type of a column is referenced by writing <tablename.columnname> %TYPE; using this can sometimes help make a procedure independent from changes to the definition of a table.

```
[DEFAULT](#value)
```

The DEFAULT clause supplies a default value for an input argument if one is not supplied in the invocation.

DEFAULT may not be specified for arguments with modes IN OUT or OUT.

```
<func_name>
```

The name of a public function.

```
<rettype>
```

The return data type.

DETERMINISTIC

DETERMINISTIC is a synonym for IMMUTABLE . A DETERMINISTIC function cannot modify the database and always reaches the same result when given the same argument values; it does not do database lookups or otherwise use information not directly present in its argument list. If you include this clause, any call of the function with all-constant arguments can be immediately replaced with the function value.

<restriction>

The following keywords are accepted for compatibility and ignored:

RNDS

RNPS

TRUST

WNDS

WNPS

Package Body Syntax

Package implementation details reside in the package body; the package body may contain objects that are not visible to the package user. Advanced Server supports the following syntax for the package body:

```
CREATE [ OR REPLACE ] PACKAGE BODY <package_name>
    { IS | AS }
    [ <private_declaration>; ] ...
    [ <procedure_or_function_definition> ] ...
    [ <package_initializer> ]
    END [ <package_name> ];
```

```
Where cprocedure_or_function_definition> :=
> cedure_definition> | <function_definition>
Where cedure_definition> :=
    [ <options_list> ]
       { IS | AS }
           cprocedure_body>
        Where cedure_body> :=
    [ PRAGMA AUTONOMOUS_TRANSACTION; ]
   [ <declaration> ;][, ...]
    BEGIN
       <statement> ; [...]
        [ EXCEPTION
           {WHEN <exception> [OR <exception>] [...]] THEN <statement>; }
       [...]
   1
Where <function_definition> :=
    FUNCTION <func_name> [ <argument_list> ]
        RETURN <rettype> [ DETERMINISTIC ]
        [ <options_list> ]
       { IS | AS }
       <function_body>
        END [ <func_name> ];
Where <function_body> :=
    [ PRAGMA AUTONOMOUS_TRANSACTION; ]
    [ <declaration> ;][, ...]
    BEGIN
       <statement> ;[...]
   [ EXCEPTION
       { WHEN <exception> [ OR <exception> ] [...] THEN <statement>; }
       [...]
   1
Where <argument_list> :=
```

```
( <argument_declaration> [, ...])
Where <argument_declaration> :=
> <argname> [ IN | IN OUT | OUT ] <argtype> [ DEFAULT <value> ]
Where <options_list> :=
     <option> [...]
Where <option> :=
     STRICT
     LEAKPROOF
     PARALLEL { UNSAFE | RESTRICTED | SAFE }
    [COST](#execution_cost)
    [ROWS](#result_rows)
     SET <config_param> { TO <value> | = <value> | FROM CURRENT }
Where <package_initializer> :=
     BFGTN
         <statement;> [...]
     END:
```

Parameters

<package_name>

<package_name> is the name of the package for which this is the package body. There must be
an existing package specification with this name.

```
<private_declaration>
```

<private_declaration> is an identifier of a private variable that can be accessed by any
procedure or function within the package. There can be zero, one, or more private variables.
<private_declaration> can be any of the following:

- · Variable Declaration
- Record Declaration
- · Collection Declaration
- REF CURSOR and Cursor Variable Declaration
- TYPE Definitions for Records, Collections, and REF CURSORs
- Exception
- · Object Variable Declaration

oc_name>

The name of the procedure being created.

PRAGMA AUTONOMOUS_TRANSACTION

PRAGMA AUTONOMOUS_TRANSACTION is the directive that sets the procedure as an autonomous transaction.

<declaration>

A variable, type, REF CURSOR , or subprogram declaration. If subprogram declarations are included, they must be declared after all other variable, type, and REF CURSOR declarations.

<statement>

An SPL program statement. Note that a DECLARE - BEGIN - END block is considered an SPL statement unto itself. Thus, the function body may contain nested blocks.

<exception>

An exception condition name such as NO_DATA_FOUND, OTHERS, etc.

<func name>

The name of the function being created.

<rettype>

The return data type, which may be any of the types listed for <argtype> . As for <argtype> , a length must not be specified for <rettype> .

DETERMINISTIC

Include DETERMINISTIC to specify that the function will always return the same result when given the same argument values. A DETERMINISTIC function must not modify the database.

Note

The DETERMINISTIC keyword is equivalent to the PostgreSQL IMMUTABLE option.

Note

If DETERMINISTIC is specified for a public function in the package body, it must also be specified for the function declaration in the package specification. (For private functions, there is no function declaration in the package specification.)

PRAGMA AUTONOMOUS_TRANSACTION

PRAGMA AUTONOMOUS_TRANSACTION is the directive that sets the function as an autonomous transaction.

<declaration>

A variable, type, REF CURSOR, or subprogram declaration. If subprogram declarations are included, they must be declared after all other variable, type, and REF CURSOR declarations.

<argname>

The name of a formal argument. The argument is referenced by this name within the procedure body.

IN | IN OUT | OUT

The argument mode. IN declares the argument for input only. This is the default. IN OUT allows the argument to receive a value as well as return a value. OUT specifies the argument is for output only.

<argtype>

The data type(s) of an argument. An argument type may be a base data type, a copy of the type of an existing column using %TYPE, or a user-defined type such as a nested table or an object type. A length must not be specified for any base type - for example, specify VARCHAR2, not VARCHAR2(10).

The type of a column is referenced by writing <tablename>. <columnname>`%TYPE ; using this can sometimes help make a procedure independent from changes to the definition of a table.

[DEFAULT](#value)

The DEFAULT clause supplies a default value for an input argument if one is not supplied in the procedure call. DEFAULT may not be specified for arguments with modes IN OUT or OUT.

Please note: the following options are not compatible with Oracle databases; they are extensions to Oracle package syntax provided by Advanced Server only.

STRICT

The STRICT keyword specifies that the function will not be executed if called with a NULL argument; instead the function will return NULL .

LEAKPR00F

The LEAKPROOF keyword specifies that the function will not reveal any information about arguments, other than through a return value.

PARALLEL { UNSAFE | RESTRICTED | SAFE }

The PARALLEL clause enables the use of parallel sequential scans (parallel mode). A parallel sequential scan uses multiple workers to scan a relation in parallel during a query in contrast to a serial sequential scan.

When set to UNSAFE, the procedure or function cannot be executed in parallel mode. The presence of such a procedure or function forces a serial execution plan. This is the default setting if the PARALLEL clause is omitted.

When set to RESTRICTED, the procedure or function can be executed in parallel mode, but the execution is restricted to the parallel group leader. If the qualification for any particular relation has anything that is parallel restricted, that relation won't be chosen for parallelism.

When set to SAFE, the procedure or function can be executed in parallel mode with no restriction.

<execution_cost>

<execution_cost> specifies a positive number giving the estimated execution cost for the function, in units of cpu_operator_cost . If the function returns a set, this is the cost per returned row. The default is 0.0025 .

`<result_rows>

<result_rows> is the estimated number of rows that the query planner should expect the function
to return. The default is 1000 .

SET

Use the SET clause to specify a parameter value for the duration of the function:

<config_param> specifies the parameter name.

<value> specifies the parameter value.

FROM CURRENT guarantees that the parameter value is restored when the function ends.

<package_initializer>

The statements in the <package_initializer> are executed once per user's session when the package is first referenced.

Note

The STRICT, LEAKPROOF, PARALLEL, COST, ROWS and SET keywords provide extended functionality for Advanced Server and are not supported by Oracle.

5.2.2 Creating Packages

A package is not an executable piece of code; rather it is a repository of code. When you use a package, you actually execute or make reference to an element within a package.

Creating the Package Specification

The package specification contains the definition of all the elements in the package that can be referenced from outside of the package. These are called the public elements of the package, and they act as the package interface. The following code sample is a package specification:

```
-- Package specification for the 'emp_admin' package.
CREATE OR REPLACE PACKAGE emp_admin
T۲
   FUNCTION get_dept_name (
     p_deptno NUMBER DEFAULT 10
)
   RETURN VARCHAR2;
   FUNCTION update_emp_sal (
     p_empno NUMBER,
     p_raise NUMBER
)
   RETURN NUMBER;
   PROCEDURE hire_emp (
                        NUMBER,
     p_empno
     p_ename
                        VARCHAR2,
     p_job
                        VARCHAR2,
                        NUMBER,
     p_sal
                        DATE
                                  DEFAULT
                                             sysdate,
     p_hiredate
                        NUMBER
                                  DEFAULT
     p_comm
                                             0,
                        NUMBER,
     p_mgr
                        NUMBER
                                  DEFAULT
                                             10
    p_deptno
    );
   PROCEDURE fire_emp (
     p_empno NUMBER
);
END emp_admin;
```

This code sample creates the <code>emp_admin</code> package specification. This package specification consists of two functions and two stored procedures. We can also add the <code>OR REPLACE</code> clause to the <code>CREATE PACKAGE</code> statement for convenience.

Creating the Package Body

The body of the package contains the actual implementation behind the package specification. For the above emp_admin package specification, we shall now create a package body which will implement the specifications. The body will contain the implementation of the functions and stored procedures in the specification.

```
RETURN v_dname;
EXCEPTION
    WHEN NO DATA FOUND THEN
        DBMS_OUTPUT.PUT_LINE('Invalid department number ' || p_deptno);
        RETURN '';
END;
-- Function that updates an employee's salary based on the
-- employee number and salary increment/decrement passed
-- as IN parameters. Upon successful completion the function
-- returns the new updated salary.
FUNCTION update_emp_sal (
                   IN NUMBER.
    p_empno
                   IN NUMBER
    p_raise
RETURN NUMBER
    v_sal
                   NUMBER := 0;
BEGIN
    SELECT sal INTO v_sal FROM emp WHERE empno = p_empno;
    v_sal := v_sal + p_raise;
    UPDATE emp SET sal = v_sal WHERE empno = p_empno;
    RETURN v_sal;
EXCEPTION
  WHEN NO_DATA_FOUND THEN
      DBMS_OUTPUT.PUT_LINE('Employee ' || p_empno || ' not found');
      RETURN -1;
  WHEN OTHERS THEN
      DBMS_OUTPUT.PUT_LINE('The following is SQLERRM:');
      DBMS_OUTPUT.PUT_LINE(SQLERRM);
      DBMS_OUTPUT.PUT_LINE('The following is SQLCODE:');
      DBMS_OUTPUT.PUT_LINE(SQLCODE);
      RETURN -1;
END;
-- Procedure that inserts a new employee record into the 'emp' table.
  PROCEDURE hire_emp (
                      NUMBER,
  p_empno
  p_ename
                      VARCHAR2,
                      VARCHAR2,
   p_job
                      NUMBER,
   p_sal
                      DATE
                             DEFAULT sysdate,
   p_hiredate
                      NUMBER DEFAULT 0,
   p_comm
                      NUMBER,
   p_mgr
                      NUMBER DEFAULT 10
   p_deptno
)
AS
BEGIN
   INSERT INTO emp(empno, ename, job, sal, hiredate, comm, mgr, deptno)
      VALUES(p_empno, p_ename, p_job, p_sal,
             p_hiredate, p_comm, p_mgr, p_deptno);
END;
-- Procedure that deletes an employee record from the 'emp' table based
-- on the employee number.
PROCEDURE fire_emp (
    p_empno NUMBER
)
```

```
AS
BEGIN
DELETE FROM emp WHERE empno = p_empno;
END;
END;
```

5.2.3 Referencing a Package

To reference the types, items and subprograms that are declared within a package specification, we use the dot notation. For example:

```
<package_name>.<type_name>
<package_name>.<item_name>
<package_name.<subprogram_name</pre>
```

To invoke a function from the emp_admin package specification, we will execute the following SQL command.

```
SELECT emp_admin.get_dept_name(10) FROM DUAL;
```

Here we are invoking the <code>get_dept_name</code> function declared within the package <code>emp_admin</code> . We are passing the department number as an argument to the function, which will return the name of the department. Here the value returned should be <code>ACCOUNTING</code> , which corresponds to department number <code>10</code> .

5.2.4 Using Packages With User Defined Types

The following example incorporates the various user-defined types discussed in earlier chapters within the context of a package.

The package specification of emp_rpt shows the declaration of a record type, emprec_typ, and a weakly-typed REF CURSOR, emp_refcur, as publicly accessible along with two functions and two procedures. Function, open_emp_by_dept, returns the REF CURSOR type, EMP_REFCUR. Procedures, fetch_emp and close_refcur, both declare a weakly-typed REF CURSOR as a formal parameter.

```
CREATE OR REPLACE PACKAGE emp_rpt
   TYPE emprec_typ IS RECORD (
       empno
                   NUMBER(4),
       ename
                   VARCHAR(10)
   TYPE emp_refcur IS REF CURSOR;
   FUNCTION get_dept_name (
       p_deptno
                   IN NUMBER
   ) RETURN VARCHAR2;
   FUNCTION open_emp_by_dept (
       p_deptno
                   IN emp.deptno%TYPE
   ) RETURN EMP_REFCUR;
   PROCEDURE fetch_emp (
       p_refcur
                   IN OUT SYS_REFCURSOR
   PROCEDURE close_refcur (
                   IN OUT SYS_REFCURSOR
       p_refcur
   END emp_rpt;
```

The package body shows the declaration of several private variables - a static cursor, dept_cur , a table type, depttab_typ , a table variable, t_dept , an integer variable, t_dept_max , and a record variable, r_emp .

```
CREATE OR REPLACE PACKAGE BODY emp_rpt
    CURSOR dept_cur IS SELECT * FROM dept;
    TYPE depttab_typ IS TABLE of dept%ROWTYPE
        INDEX BY BINARY_INTEGER;
    t_dept
                   DEPTTAB_TYP:
    t_dept_max
                   INTEGER := 1;
    r_emp
                   EMPREC_TYP;
    FUNCTION get_dept_name (
       p_deptno
                  IN NUMBER
    ) RETURN VARCHAR2
    IS
    BEGIN
        FOR i IN 1..t_dept_max LOOP
            IF p_deptno = t_dept(i).deptno THEN
               RETURN t_dept(i).dname;
           END IF;
        END LOOP;
       RETURN 'Unknown';
  END;
  FUNCTION open_emp_by_dept(
                   IN emp.deptno%TYPE
    p_deptno
  ) RETURN EMP_REFCUR
    emp_by_dept EMP_REFCUR;
  BEGIN
    OPEN emp_by_dept FOR SELECT empno, ename FROM emp
       WHERE deptno = p_deptno;
    RETURN emp_by_dept;
  END;
  PROCEDURE fetch_emp (
     )
  IS
  BEGIN
      DBMS_OUTPUT.PUT_LINE('EMPNO ENAME');
     DBMS_OUTPUT.PUT_LINE('----');
     L00P
         FETCH p_refcur INTO r_emp;
         EXIT WHEN p_refcur%NOTFOUND;
         DBMS_OUTPUT.PUT_LINE(r_emp.empno || ' ' || r_emp.ename);
      END LOOP;
  END;
  PROCEDURE close_refcur (
      p_refcur
                  IN OUT SYS_REFCURSOR
  )
  IS
  BEGIN
      CLOSE p_refcur;
  END;
BEGIN
 OPEN dept_cur;
  L00P
```

```
FETCH dept_cur INTO t_dept(t_dept_max);
    EXIT WHEN dept_cur%NOTFOUND;
    t_dept_max := t_dept_max + 1;
END LOOP;
CLOSE dept_cur;
    t_dept_max := t_dept_max - 1;
END emp_rpt;
```

This package contains an initialization section that loads the private table variable, t_dept , using the private static cursor, dept_cur.t_dept serves as a department name lookup table in function, get_dept_name

Function, open_emp_by_dept returns a REF CURSOR variable for a result set of employee numbers and names for a given department. This REF CURSOR variable can then be passed to procedure, fetch_emp, to retrieve and list the individual rows of the result set. Finally, procedure, close_refcur, can be used to close the REF CURSOR variable associated with this result set.

The following anonymous block runs the package function and procedures. In the anonymous block's declaration section, note the declaration of cursor variable, v_emp_cur, using the package's public REF CURSOR type, EMP_REFCUR. v_emp_cur contains the pointer to the result set that is passed between the package function and procedures.

```
DECLARE
   v_deptno dept.deptno%TYPE DEFAULT 30;
   v_emp_cur emp_rpt.EMP_REFCUR;
BEGIN
   v_emp_cur := emp_rpt.open_emp_by_dept(v_deptno);
   DBMS_OUTPUT.PUT_LINE('EMPLOYEES IN DEPT #' || v_deptno ||
       ': ' || emp_rpt.get_dept_name(v_deptno));
   emp_rpt.fetch_emp(v_emp_cur);
   DBMS_OUTPUT.PUT_LINE('******************************):
   DBMS_OUTPUT.PUT_LINE(v_emp_cur%ROWCOUNT || ' rows were
   retrieved');
   emp_rpt.close_refcur(v_emp_cur);
END;
The following is the result of this anonymous block.
EMPLOYEES IN DEPT #30: SALES
EMPNO ENAME
7499 ALLEN
7521 WARD
7654 MARTIN
7698 BLAKE
7844 TURNER
7900 JAMES
********
6 rows were retrieved
```

The following energymous block illustra

The following anonymous block illustrates another means of achieving the same result. Instead of using the package procedures, fetch_emp and close_refcur, the logic of these programs is coded directly into the anonymous block. In the anonymous block's declaration section, note the addition of record variable, r_emp, declared using the package's public record type, EMPREC_TYP.

```
': ' || emp_rpt.get_dept_name(v_deptno));
  DBMS_OUTPUT.PUT_LINE('EMPNO ENAME');
  DBMS_OUTPUT.PUT_LINE('----');
  L00P
      FETCH v_emp_cur INTO r_emp;
      EXIT WHEN v_emp_cur%NOTFOUND;
      DBMS_OUTPUT.PUT_LINE(r_emp.empno | | ' ' | |
      r_emp.ename);
  END LOOP;
  DBMS_OUTPUT.PUT_LINE(v_emp_cur%ROWCOUNT || ' rows were retrieved');
  CLOSE v_emp_cur;
END;
The following is the result of this anonymous block.
EMPLOYEES IN DEPT #30: SALES
EMPNO ENAME
7499 ALLEN
7521 WARD
7654 MARTIN
7698 BLAKE
7844 TURNER
7900 JAMES
********
6 rows were retrieved
```

5.2.5 Dropping a Package

The syntax for deleting an entire package or just the package body is as follows:

If the keyword, BODY, is omitted, both the package specification and the package body are deleted - i.e., the entire package is dropped. If the keyword, BODY, is specified, then only the package body is dropped. The package specification remains intact.
is the identifier of the package to be dropped.

Following statement will destroy only the package body of <emp_admin> :

```
DROP PACKAGE BODY emp_admin;
```

The following statement will drop the entire <emp_admin> package:

DROP PACKAGE emp_admin;

5.3.0 Built-In Packages

This chapter describes the built-in packages that are provided with Advanced Server. For certain packages, non-superusers must be explicitly granted the EXECUTE privilege on the package before using any of the package's functions or procedures. For most of the built-in packages, EXECUTE privilege has been granted to PUBLIC by default.

For information about using the GRANT command to provide access to a package, please see the *Database Compatibility for Oracle Developers Reference Guide*, available at:

https://www.enterprisedb.com/edb-docs

All built-in packages are owned by the special sys user which must be specified when granting or revoking privileges on built-in packages:

5.3.1 DBMS ALERT

The DBMS_ALERT package provides the capability to register for, send, and receive alerts. The following table lists the supported procedures:

Function/Procedure	Return Type	Description
REGISTER(<name>)</name>	n/a	Register to be able to rece
REMOVE(<name>)</name>	n/a	Remove registration for th
REMOVEALL	n/a	Remove registration for al
<pre>SIGNAL(<name>, <message>)</message></name></pre>	n/a	Signals the alert named,
<pre>WAITANY(<name> OUT, <message> OUT, <status> OUT, <timeout>)</timeout></status></message></name></pre>	n/a	Wait for any registered ale
<pre>WAITONE(<name>, <message. <status="" out,=""> OUT, <timeout>)</timeout></message.></name></pre>	n/a	Wait for the specified aler

Advanced Server's implementation of DBMS_ALERT is a partial implementation when compared to Oracle's version. Only those functions and procedures listed in the table above are supported.

Advanced Server allows a maximum of 500 concurrent alerts. You can use the dbms_alert.max_alerts GUC variable (located in the postgresql.conf file) to specify the maximum number of concurrent alerts allowed on a system.

To set a value for the dbms_alert.max_alerts variable, open the postgresql.conf file (located by default in /opt/PostgresPlus/10AS/data) with your choice of editor, and edit the dbms_alert.max_alerts parameter as shown:

```
dbms_alert.max_alerts = <alert_count>
```

<alert_count>

alert_count specifies the maximum number of concurrent alerts. By default, the value of dbms_alert.max_alerts is 100 . To disable this feature, set dbms_alert.max_alerts to 0 .

For the dbms_alert.max_alerts GUC to function correctly, the custom_variable_classes parameter must contain dbms_alerts :

```
custom_variable_classes = 'dbms_alert, ...'
```

After editing the postgresql.conf file parameters, you must restart the server for the changes to take effect.

DBMS_ALERT_Register

REGISTER

The REGISTER procedure enables the current session to be notified of the specified alert.

REGISTER(<name> VARCHAR2)

Parameters

<name>

Name of the alert to be registered.

Examples

The following anonymous block registers for an alert named, alert_test, then waits for the signal.

```
DECLARE
                      VARCHAR2(30) := 'alert_test';
   v_name
                      VARCHAR2(80);
   v_msg
                      INTEGER;
   v_status
                      NUMBER(3) := 120;
   v_timeout
BEGIN
   DBMS_ALERT.REGISTER(v_name);
   DBMS_OUTPUT.PUT_LINE('Registered for alert ' || v_name);
   DBMS_OUTPUT.PUT_LINE('Waiting for signal...');
   DBMS_ALERT.WAITONE(v_name, v_msg, v_status, v_timeout);
   DBMS_OUTPUT.PUT_LINE('Alert name : ' || v_name);
                                         : ' || v_msg);
   DBMS_OUTPUT.PUT_LINE('Alert msg
   DBMS_OUTPUT.PUT_LINE('Alert status : ' || v_status);
DBMS_OUTPUT.PUT_LINE('Alert timeout: ' || v_timeout || ' seconds');
   DBMS_ALERT.REMOVE(v_name);
END;
Registered for alert alert_test
Waiting for signal...
DBMS_ALERT_Remove
```

REMOVE

The REMOVE procedure unregisters the session for the named alert.

REMOVE(<name> VARCHAR2)

Parameters

<name>

Name of the alert to be unregistered.

REMOVEALL

The REMOVEALL procedure unregisters the session for all alerts.

REMOVEALL

SIGNAL

The SIGNAL procedure signals the occurrence of the named alert.

SIGNAL(<name> VARCHAR2, <message> VARCHAR2)

Parameters

<name>

Name of the alert.

<message>

Information to pass with this alert.

Examples

The following anonymous block signals an alert for alert_test.

```
DECLARE
    v_name    VARCHAR2(30) := 'alert_test';
BEGIN
    DBMS_ALERT.SIGNAL(v_name,'This is the message from ' || v_name);
    DBMS_OUTPUT.PUT_LINE('Issued alert for ' || v_name);
END;
Issued alert for alert test
```

WAITANY

```
The WAITANY procedure waits for any of the registered alerts to occur.
```

```
\label{eq:waitany} \textbf{WAITANY}(\mbox{<name}>\mbox{ OUT VARCHAR2, <message}>\mbox{ OUT VARCHAR2 ,}
```

```
<status> OUT INTEGER, <timeout> NUMBER)
```

Parameters

<name>

Variable receiving the name of the alert.

```
<message>
```

Variable receiving the message sent by the SIGNAL procedure.

VARCHAR2(30);

```
<status>
```

Status code returned by the operation. Possible values are: 0 – alert occurred; 1 – timeout occurred.

<timeout>

Time to wait for an alert in seconds.

Examples

The following anonymous block uses the WAITANY procedure to receive an alert named, alert_test or any_alert:

```
DECLARE
```

v_name

```
VARCHAR2(80);
    v_msg
                     INTEGER;
    v_status
    v_timeout
                     NUMBER(3) := 120;
BEGIN
   DBMS_ALERT.REGISTER('alert_test');
   DBMS_ALERT.REGISTER('any_alert');
   DBMS_OUTPUT.PUT_LINE('Registered for alert alert_test and any_alert');
   DBMS_OUTPUT.PUT_LINE('Waiting for signal...');
   DBMS_ALERT.WAITANY(v_name, v_msg, v_status, v_timeout);
   DBMS_OUTPUT.PUT_LINE('Alert name : ' || v_name);
                                      : ' | | v_msa);
   DBMS_OUTPUT.PUT_LINE('Alert msg
   DBMS_OUTPUT.PUT_LINE('Alert status : ' || v_status);
   DBMS_OUTPUT.PUT_LINE('Alert timeout: ' || v_timeout || ' seconds');
   DBMS_ALERT.REMOVEALL;
END;
```

Registered for alert alert_test and any_alert Waiting for signal...

An anonymous block in a second session issues a signal for any_alert:

```
DECLARE
```

```
v_name VARCHAR2(30) := 'any_alert';
BEGIN
   DBMS_ALERT.SIGNAL(v_name,'This is the message from ' || v_name);
   DBMS_OUTPUT.PUT_LINE('Issued alert for ' || v_name);
END:
```

Issued alert for any_alert

Control returns to the first anonymous block and the remainder of the code is executed:

```
Registered for alert alert_test and any_alert Waiting for signal...
Alert name : any_alert
```

```
Alert msg : This is the message from any_alert
```

Alert status: 0

Alert timeout: 120 seconds

WAITONE

The WAITONE procedure waits for the specified registered alert to occur.

Parameters

<name>

Name of the alert.

<message>

Variable receiving the message sent by the SIGNAL procedure.

<status>

Status code returned by the operation. Possible values are: 0 – alert occurred; 1 – timeout occurred.

<timeout>

Time to wait for an alert in seconds.

Examples

The following anonymous block is similar to the one used in the WAITANY example except the WAITONE procedure is used to receive the alert named, alert_test.

```
DECLARE
```

```
VARCHAR2(30) := 'alert_test';
   v_name
                     VARCHAR2(80);
   v_msg
   v_status
                     INTEGER;
    v_timeout
                     NUMBER(3) := 120;
BEGIN
   DBMS_ALERT.REGISTER(v_name);
   DBMS_OUTPUT.PUT_ DBMS_ALERT.REGISTER(v_name);
   DBMS_OUTPUT.PUT_LINE('Registered for alert ' || v_name);
   DBMS_OUTPUT.PUT_LINE('Waiting for signal...');
   DBMS_ALERT.WAITONE(v_name,v_msg,v_status,v_timeout);
   DBMS_OUTPUT.PUT_LINE('Alert name : ' || v_name);
                                    : ' || v_msq);
   DBMS_OUTPUT.PUT_LINE('Alert msg
   DBMS_OUTPUT.PUT_LINE('Alert status : ' || v_status):
   DBMS_OUTPUT.PUT_LINE('Alert timeout: ' || v_timeout || ' seconds');
   DBMS_ALERT.REMOVE(v_name);LINE('Registered for alert ' || v_name);
   DBMS_OUTPUT.PUT_LINE('Waiting for signal...');
   DBMS_ALERT.WAITONE(v_name,v_msg,v_status,v_timeout);
   DBMS_OUTPUT.PUT_LINE('Alert name : ' || v_name);
                                     : ' | | v_msg);
   DBMS_OUTPUT.PUT_LINE('Alert msg
   DBMS_OUTPUT.PUT_LINE('Alert status : ' || v_status);
   DBMS_OUTPUT.PUT_LINE('Alert timeout: ' || v_timeout || ' seconds');
   DBMS_ALERT.REMOVE(v_name);
   END;
   Registered for alert alert_test
   Waiting for signal...
```

Signal sent for alert_test sent by an anonymous block in a second session:

DECLARE

```
v_name VARCHAR2(30) := 'alert_test';
```

```
BEGIN

DBMS_ALERT.SIGNAL(v_name, 'This is the message from ' || v_name);

DBMS_OUTPUT.PUT_LINE('Issued alert for ' || v_name);

END;

Issued alert for alert_test

First session is alerted, control returns to the anonymous block, and the remainder of the code is executed:

Registered for alert alert_test

Waiting for signal...

Alert name : alert_test

Alert msg : This is the message from alert_test

Alert status : 0

Alert timeout: 120 seconds

DBMS_ALERT_Comprehensive_example
```

Comprehensive Example

The following example uses two triggers to send alerts when the dept table or the emp table is changed. An anonymous block listens for these alerts and displays messages when an alert is received.

The following are the triggers on the dept and emp tables:

```
CREATE OR REPLACE TRIGGER dept_alert_trig
   AFTER INSERT OR UPDATE OR DELETE ON dept
DECLARE
     v_action
                     VARCHAR2(25);
BEGIN
   IF INSERTING THEN
       v_action := ' added department(s) ';
   ELSIF UPDATING THEN
       v_action := ' updated department(s) ';
   ELSIF DELETING THEN
       v_action := ' deleted department(s) ';
   END IF;
   DBMS_ALERT.SIGNAL('dept_alert', USER || v_action || 'on ' ||
       SYSDATE);
END;
CREATE OR REPLACE TRIGGER emp_alert_trig
     AFTER INSERT OR UPDATE OR DELETE ON emp
DECLARE
     v_action
                     VARCHAR2(25);
BEGIN
   IF INSERTING THEN
       v_action := ' added employee(s) ';
   ELSIF UPDATING THEN
       v_action := ' updated employee(s) ';
   ELSIF DELETING THEN
       v_action := ' deleted employee(s) ';
   END IF;
   DBMS_ALERT.SIGNAL('emp_alert', USER || v_action || 'on ' ||
       SYSDATE);
END;
```

The following anonymous block is executed in a session while updates to the dept and emp tables occur in other sessions:

```
VARCHAR2(30);
     v_name
     v_msq
                      VARCHAR2(80);
     v_status
                      INTEGER:
     v_timeout
                      NUMBER(3) := 60;
BEGIN
     DBMS_ALERT.REGISTER(v_dept_alert);
     DBMS_ALERT.REGISTER(v_emp_alert);
     DBMS_OUTPUT.PUT_LINE('Registered for alerts dept_alert and emp_alert');
     DBMS_OUTPUT.PUT_LINE('Waiting for signal...');
     L00P
         DBMS_ALERT.WAITANY(v_name, v_msg, v_status, v_timeout);
         EXIT WHEN v_status != 0;
         DBMS_OUTPUT.PUT_LINE('Alert name : ' || v_name);
         DBMS_OUTPUT.PUT_LINE('Alert msg : ' || v_msg);
DBMS_OUTPUT.PUT_LINE('Alert status : ' || v_status);
         DBMS_OUTPUT.PUT_LINE('-----' ||
       '----');
     END LOOP:
     DBMS_OUTPUT.PUT_LINE('Alert status : ' || v_status);
     DBMS_ALERT.REMOVEALL;
END:
Registered for alerts dept alert and emp alert Waiting for signal...
The following changes are made by user, mary:
INSERT INTO dept VALUES (50, 'FINANCE', 'CHICAGO');
INSERT INTO emp (empno, ename, deptno) VALUES (9001, 'JONES', 50);
INSERT INTO emp (empno, ename, deptno) VALUES (9002, 'ALICE', 50);
The following change is made by user, john:
INSERT INTO dept VALUES (60, 'HR', 'LOS ANGELES');
The following is the output displayed by the anonymous block receiving the signals from the triggers:
Registered for alerts dept_alert and emp_alert
Waiting for signal...
Alert name : dept_alert
Alert msg : mary added department(s) on 25-0CT-07 16:41:01
Alert status: 0
Alert name : emp_alert
Alert msq : mary added employee(s) on 25-0CT-07 16:41:02
Alert status: 0
Alert name : dept_alert
Alert msg : john added department(s) on 25-0CT-07 16:41:22
Alert status : 0
Alert status : 1
```

5.3.2.0 DBMS AQ

EDB Postgres Advanced Server Advanced Queueing provides message queueing and message processing for the Advanced Server database. User-defined messages are stored in a queue; a collection of queues is stored in a queue table. Procedures in the DBMS_AQADM package create and manage message queues and queue tables. Use the DBMS_AQ package to add messages to a queue or remove messages from a queue, or register or unregister a PL/SQL callback procedure.

Advanced Server also provides extended (non-compatible) functionality for the DBMS_AQ package with SQL commands. Please see the *Database Compatibility for Oracle Developers Reference Guide* for detailed information about the following SQL commands:

- ALTER QUEUE
- ALTER QUEUE TABLE
- CREATE QUEUE
- CREATE QUEUE TABLE
- DROP QUEUE
- DROP QUEUE TABLE

The DBMS_AQ package provides procedures that allow you to enqueue a message, dequeue a message, and manage callback procedures. The supported procedures are:

Function/Procedure	Return Type	Description
ENQUEUE	n/a	Post a message to a queue.
DEQUEUE	n/a	Retrieve a message from a queue if or when a message is available.
REGISTER	n/a	Register a callback procedure.
UNREGISTER	n/a	Unregister a callback procedure.

Advanced Server's implementation of DBMS_AQ is a partial implementation when compared to Oracle's version. Only those procedures listed in the table above are supported.

Advanced Server supports use of the constants listed below:

Constant	Description
DBMS_AQ.BROWSE (0)	Read the message without locking.
DBMS_AQ.LOCKED (1)	This constant is defined, but will return an error if used.
DBMS_AQ.REMOVE (2)	Delete the message after reading; the default.
DBMS_AQ.REMOVE_NODATA (3)	This constant is defined, but will return an error if used.
DBMS_AQ.FIRST_MESSAGE (0)	Return the first available message that matches the search terms.
DBMS_AQ.NEXT_MESSAGE (1)	Return the next available message that matches the search terms.
DBMS_AQ.NEXT_TRANSACTION (2)	This constant is defined, but will return an error if used.
DBMS_AQ.FOREVER (-1)	Wait forever if a message that matches the search term is not found, the d
DBMS_AQ.NO_WAIT (0)	Do not wait if a message that matches the search term is not found.
DBMS_AQ.ON_COMMIT (0)	The dequeue is part of the current transaction.
DBMS_AQ.IMMEDIATE (1)	This constant is defined, but will return an error if used.
DBMS_AQ.PERSISTENT (0)	The message should be stored in a table.
DBMS_AQ.BUFFERED (1)	This constant is defined, but will return an error if used.
DBMS_AQ.READY (0)	Specifies that the message is ready to process.
DBMS_AQ.WAITING (1)	Specifies that the message is waiting to be processed.
DBMS_AQ.PROCESSED (2)	Specifies that the message has been processed.
DBMS_AQ.EXPIRED (3)	Specifies that the message is in the exception queue.
DBMS_AQ.NO_DELAY (0)	This constant is defined, but will return an error if used
DBMS_AQ.NEVER (NULL)	This constant is defined, but will return an error if used
DBMS_AQ.NAMESPACE_AQ (0)	Accept notifications from DBMS_AQ queues.
DBMS_AQ.NAMESPACE_ANONYMOUS (1)	This constant is defined, but will return an error if used

The DBMS_AQ configuration parameters listed in the following table can be defined in the <code>postgresql.conf</code> file. After the configuration parameters are defined, you can invoke the DBMS_AQ package to use and manage messages held in queues and queue tables.

Parameter	Description
dbms_aq.max_workers	The maximum number of workers to run.
<pre>dbms_aq.max_idle_time</pre>	The idle time a worker must wait before exiting.
<pre>dbms_aq.min_work_time</pre>	The minimum time a worker can run before exiting.
<pre>dbms_aq.launch_delay</pre>	The minimum time between creating workers.
<pre>dbms_aq.batch_size</pre>	The maximum number of messages to process in a single transaction. The default
<pre>dbms_aq.max_databases</pre>	The size of DBMS_AQ's hash table of databases. The default value is 1024.

5.3.2.1 'ENQUEUE'

The ENQUEUE procedure adds an entry to a queue. The signature is:

```
ENQUEUE(
```

```
<queue_name> IN VARCHAR2 ,
<enqueue_options> IN DBMS_AQ.ENQUEUE_OPTIONS_T ,
<message_properties> IN DBMS_AQ.MESSAGE_PROPERTIES_T ,
<payload IN <type_name> ,
<msqid> OUT RAW)
```

Parameters

<queue_name>

The name (optionally schema-qualified) of an existing queue. If you omit the schema name, the server will use the schema specified in the SEARCH_PATH. Please note that unlike Oracle, unquoted identifiers are converted to lower case before storing. To include special characters or use a case-sensitive name, enclose the name in double quotes.

For detailed information about creating a queue, please see DBMS_AQADM. CREATE_QUEUE .

```
<enqueue_options>
```

```
<enqueue_options> is a value of the type, enqueue_options_t :

DBMS_AQ.ENQUEUE_OPTIONS_T IS RECORD(
   visibility BINARY_INTEGER DEFAULT ON_COMMIT,
   relative_msgid RAW(16) DEFAULT NULL,
   sequence_deviation BINARY INTEGER DEFAULT NULL,
   transformation VARCHAR2(61) DEFAULT NULL,
   delivery_mode PLS_INTEGER NOT NULL DEFAULT PERSISTENT);
```

Currently, the only supported parameter values for enqueue_options_t are:

visibility	ON_COMMIT .
delivery_mode	PERSISTENT
sequence_deviation	NULL
transformation	NULL
relative_msgid	NULL

```
<message_properties>
<message_properties> is a value of the type, message_properties_t :
message_properties_t IS RECORD(
  priority INTEGER,
  delay INTEGER,
  expiration INTEGER,
  correlation CHARACTER VARYING(128) COLLATE pg_catalog."C",
```

```
attempts INTEGER,
 recipient_list "AQ$_RECIPIENT_LIST_T",
 exception_queue CHARACTER VARYING(61) COLLATE pg_catalog."C",
 enqueue_time TIMESTAMP WITHOUT TIME ZONE,
 state INTEGER,
 original_msgid BYTEA,
 transaction_group CHARACTER VARYING(30) COLLATE pg_catalog."C",
 delivery_mode INTEGER
DBMS_AQ.PERSISTENT);
The supported values for message_properties_t are:
<payload>
    Use the <payload> parameter to provide the data that will be associated with the queue entry.
    The payload type must match the type specified when creating the corresponding queue table (see
     DBMS_AQADM.CREATE_QUEUE_TABLE ).
<msgid>
    Use the <msgid> parameter to retrieve a unique (system-generated) message identifier.
Example
The following anonymous block calls
                                  DBMS_AQ.ENQUEUE, adding a message to a queue named
work_order :
DECLARE
 enqueue_options
                     DBMS_AQ.ENQUEUE_OPTIONS_T;
 message_properties DBMS_AQ.MESSAGE_PROPERTIES_T;
                     raw(16);
 message_handle
 payload
                     work_order;
BEGIN
 payload := work_order('Smith', 'system upgrade');
DBMS_AQ.ENQUEUE(
 queue_name
                     => 'work_order',
 enqueue_options
                     => enqueue_options,
 message_properties => message_properties,
 payload
                     => payload,
 msgid
                     => message_handle
   );
END;
5.3.2.2 'DEQUEUE'
The DEQUEUE procedure dequeues a message. The signature is:
     DEQUEUE(
         <queue_name> IN VARCHAR2 ,
         <dequeue_options> IN DBMS_AQ.DEQUEUE_OPTIONS_T,
         <message_properties> OUT DBMS_AQ.MESSAGE_PROPERTIES_T,
         <payload> OUT type_name ,
```

<msqid> OUT RAW)

Parameters

```
<queue_name>
```

The name (optionally schema-qualified) of an existing queue. If you omit the schema name, the server will use the schema specified in the SEARCH_PATH. Please note that unlike Oracle, unquoted identifiers are converted to lower case before storing. To include special characters or use a case-sensitive name, enclose the name in double quotes.

For detailed information about creating a queue, please see DBMS_AQADM.CREATE_QUEUE .

```
<dequeue_options>
     <dequeue_options> is a value of the type, dequeue_options_t :
DEQUEUE_OPTIONS_T IS RECORD(
  consumer_name CHARACTER VARYING(30),
  dequeue_mode INTEGER,
  navigation INTEGER,
  visibility INTEGER,
  wait INTEGER,
  msgid BYTEA,
  correlation CHARACTER VARYING(128),
  deq_condition CHARACTER VARYING(4000),
  transformation CHARACTER VARYING(61),
  delivery_mode INTEGER);
Currently, the supported parameter values for dequeue_options_t are:
<message_properties>
<message_properties> is a value of the type, message_properties_t :
message_properties_t IS RECORD(
  priority INTEGER,
  delay INTEGER,
  expiration INTEGER,
```

correlation CHARACTER VARYING(128) COLLATE pg_catalog."C",

exception_queue CHARACTER VARYING(61) COLLATE pg_catalog."C",

transaction_group CHARACTER VARYING(30) COLLATE pg_catalog."C",

The supported values for message_properties_t are:

recipient_list "AQ\$_RECIPIENT_LIST_T".

enqueue_time TIMESTAMP WITHOUT TIME ZONE,

attempts INTEGER,

state INTEGER,

original_msgid

original_msgid BYTEA,

delivery_mode INTEGER
DBMS_AQ.PERSISTENT);

priority If the queue table definition includes a sort_list that references priority, this parameter affe delay Specify the number of seconds that will pass before a message is available for dequeueing or expiration Use the expiration parameter to specify the number of seconds until a message expires. correlation Use correlation to specify a message that will be associated with the entry; the default is NULL This is a system-maintained value that specifies the number of attempts to dequeue the message attempts recipient_list This parameter is not supported. Use the exception_queue parameter to specify the name of an exception queue to which a exception_queue enqueue_time enqueue_time is the time the record was added to the queue; this value is provided by the st This parameter is maintained by DBMS_AQ; state can be: DBMS_AQ.WAITING - the delay h state

This parameter is accepted for compatibility and ignored.

transaction_group This parameter is accepted for compatibility and ignored.

delivery_mode This parameter is not supported; specify a value of DBMS_AQ.PERSISTENT .

<payload>

Use the <payload> parameter to retrieve the payload of a message with a dequeue operation. The payload type must match the type specified when creating the queue table.

<msgid>

Use the <msgid> parameter to retrieve a unique message identifier.

Example

The following anonymous block calls DBMS_AQ.DEQUEUE , retrieving a message from the queue and a payload:

DECLARE

```
dequeue_options
                     DBMS_AQ.DEQUEUE_OPTIONS_T;
  message_properties DBMS_AQ.MESSAGE_PROPERTIES_T;
  message_handle
                     raw(16);
  payload
                     work_order;
BEGIN
  dequeue_options.dequeue_mode := DBMS_AQ.BROWSE;
  DBMS_AQ.DEQUEUE(
                       => 'work_queue',
    queue_name
    dequeue_options => dequeue_options,
    message_properties => message_properties,
    payload
                    => payload,
   msgid
                       => message_handle
  );
  DBMS_OUTPUT.PUT_LINE(
  'The next work order is [' || payload.subject || '].'
  );
END;
The payload is displayed by DBMS_OUTPUT.PUT_LINE .
```

5.3.2.3 REGISTER

Use the REGISTER procedure to register an email address, procedure or URL that will be notified when an item is enqueued or dequeued. The signature is:

```
REGISTER(
```

```
<reg_list> IN SYS.AQ$_REG_INFO_LIST ,
<count> IN NUMBER)
```

Parameters

```
<reg_list>
```

<reg_list> is a list of type AQ\$_REG_INFO_LIST ; that provides information about each subscription that you would like to register. Each entry within the list is of the type AQ\$_REG_INFO , and may contain:

```
Y{0.2}
<count>
<count> is the number of entries in <reg_list> .
```

Example

The following anonymous block calls DBMS_AQ.REGISTER, registering procedures that will be notified when an item is added to or removed from a queue. A set of attributes (of sys.aq\$_reg_info type) is provided for each subscription identified in the DECLARE section:

```
DECLARE
   subscription1 sys.aq\_req_info;
   subscription2 sys.aq\_req_info;
   subscription3 sys.aq$_reg_info;
   subscriptionlist sys.aq$_reg_info_list;
BEGIN
  subscription1 := sys.aq$_reg_info('q', DBMS_AQ.NAMESPACE_AQ,
'plsql://assign_worker?PR=0',HEXTORAW('FFFF'));
  subscription2 := sys.aq$_reg_info('q', DBMS_AQ.NAMESPACE_AQ,
'plsql://add_to_history?PR=1',HEXTORAW('FFFF'));
  subscription3 := sys.aq\reg_info('q', DBMS_AQ.NAMESPACE_AQ,
'plsql://reserve_parts?PR=2',HEXTORAW('FFFF'));
  subscriptionlist := sys.aq$_reg_info_list(subscription1,
subscription2, subscription3);
  dbms_aq.register(subscriptionlist, 3);
commit;
   END:
```

The subscriptionlist is of type sys.aq\$_reg_info_list, and contains the previously described sys.aq\$_reg_info objects. The list name and an object count are passed to dbms_aq.register.

5.3.2.4 'UNREGISTER'

Use the UNREGISTER procedure to turn off notifications related to enqueueing and dequeueing. The signature is:

Parameter

```
<reg_list>
```

<reg_list> is a list of type AQ\$_REG_INFO_LIST ; that provides information about each subscription that you would like to register. Each entry within the list is of the type AQ\$_REG_INFO , and may contain:

<count>

```
<count> is the number of entries in <reg_list> .
```

Example

The following anonymous block calls DBMS_AQ.UNREGISTER , disabling the notifications specified in the example for DBMS_AQ.REGISTER :

DECLARE

```
subscription1 sys.aq\_req_info;
   subscription2 sys.aq$_reg_info;
   subscription3 sys.aq$_reg_info;
   subscriptionlist sys.aq$_reg_info_list;
BEGIN
   subscription1 := sys.aq\req_info('a', DBMS_AQ.NAMESPACE_AQ,
'plsql://assign_worker?PR=0',HEXTORAW('FFFF'));
   subscription2 := sys.aq$_reg_info('q', DBMS_AQ.NAMESPACE_AQ,
'plsql://add_to_history?PR=1',HEXTORAW('FFFF'));
   subscription3 := sys.aq\_reg_info('q', DBMS_AQ.NAMESPACE_AQ,
'plsql://reserve_parts?PR=2',HEXTORAW('FFFF'));
   subscriptionlist := sys.aq\_reg_info_list(subscription1,
 subscription2, subscription3);
   dbms_aq.unregister(subscriptionlist, 3);
   commit:
  END:
```

The subscriptionlist is of type sys.aq\$_reg_info_list, and contains the previously described sys.aq\$_reg_info objects. The list name and an object count are passed to dbms_aq.unregister.

5.3.3.0 **DBMS_AQADM**

EDB Postgres Advanced Server Advanced Queueing provides message queueing and message processing for the Advanced Server database. User-defined messages are stored in a queue; a collection of queues is stored in a queue table. Procedures in the DBMS_AQADM package create and manage message queues and queue tables. Use the DBMS_AQ package to add messages to a queue or remove messages from a queue, or register or unregister a PL/SQL callback procedure.

Advanced Server also provides extended (non-compatible) functionality for the DBMS_AQ package with SQL commands. Please see the *Database Compatibility for Oracle Developers Reference Guide* for detailed information about the following SQL commands:

- ALTER QUEUE
- ALTER QUEUE TABLE
- CREATE QUEUE
- CREATE QUEUE TABLE
- DROP QUEUE
- DROP QUEUE TABLE

The DBMS_AQADM package provides procedures that allow you to create and manage queues and queue tables.

Function/Procedure	Return Type	Description
ALTER_QUEUE	n/a	Modify an existing queue.
ALTER_QUEUE_TABLE	n/a	Modify an existing queue table.
CREATE_QUEUE	n/a	Create a queue.
CREATE_QUEUE_TABLE	n/a	Create a queue table.
DROP_QUEUE	n/a	Drop an existing queue.
DROP_QUEUE_TABLE	n/a	Drop an existing queue table.

Function/Procedure	Return Type	Description
PURGE_QUEUE_TABLE	n/a	Remove one or more messages from a queue table.
START_QUEUE	n/a	Make a queue available for enqueueing and dequeueing procedures.
STOP_QUEUE	n/a	Make a queue unavailable for enqueueing and dequeueing procedures

Advanced Server's implementation of DBMS_AQADM is a partial implementation when compared to Oracle's version. Only those functions and procedures listed in the table above are supported.

Advanced Server supports use of the arguments listed below:

Constant	Description			For Pa	
DBMS_AQADM.TRANSACTIONAL(1)	This cons	This constant is defined, but will return an error if used.			
DBMS_AQADM.NONE(0)	Use to sp	Use to specify message grouping for a queue table.			messa
DBMS_AQADM.NORMAL_QUEUE(0)	Use with	create_queue	to speci	fy queue_type .	queue
DBMS_AQADM.EXCEPTION_QUEUE (1)	Use with	create_queue	to specify	queue_type .	queue
<pre>DBMS_AQADM.INFINITE(-1)</pre>	Use with	create_queue	to specify	retention_time	. reten
DBMS_AQADM.PERSISTENT (0)	The mess	sage should be st	ored in a tal	ole.	enque
DBMS_AQADM.BUFFERED (1)	This constant is defined, but will return an error if used.		enque		
<pre>DBMS_AQADM.PERSISTENT_OR_BUFFERED (2)</pre>	This constant is defined, but will return an error if used.		enque		
DBMS_AQADM.EXCEPTION_QUEUE (1) DBMS_AQADM.INFINITE(-1) DBMS_AQADM.PERSISTENT (0) DBMS_AQADM.BUFFERED (1)	Use with Use with The mess This cons	create_queue create_queue sage should be st stant is defined, bu	to specify to specify ored in a tal ut will return	queue_type . retention_time ple. an error if used.	que ret enq enq

5.3.3.1 ALTER_QUEUE

Use the ALTER_QUEUE procedure to modify an existing queue. The signature is:

ALTER_QUEUE(

```
<max_retries> IN NUMBER DEFAULT NULL ,
<retry_delay> IN NUMBER DEFAULT 0
<retention_time> IN NUMBER DEFAULT 0 ,
<auto_commit> IN BOOLEAN DEFAULT TRUE)
<comment> IN VARCHAR2 DEFAULT NULL ,
```

Parameters

<queue_name>

The name of the new queue.

<max_retries>

<max_retries> specifies the maximum number of attempts to remove a message with a dequeue
statement. The value of <max_retries> is incremented with each ROLLBACK statement.
When the number of failed attempts reaches the value specified by <max_retries> , the message
is moved to the exception queue. Specify 0 to indicate that no retries are allowed.

<retry_delay>

<retry_delay> specifies the number of seconds until a message is scheduled for re-processing
after a ROLLBACK . Specify 0 to indicate that the message should be retried immediately (the
default).

```
<retention_time>
```

<retention_time> specifies the length of time (in seconds) that a message will be stored after
being dequeued. You can also specify 0 (the default) to indicate the message should not be
retained after dequeueing, or INFINITE to retain the message forever.

```
<auto_commit>
```

This parameter is accepted for compatibility and ignored.

<comment>

<comment> specifies a comment associated with the queue.

Example

The following command alters a queue named work_order , setting the retry_delay parameter to 5 seconds:

```
EXEC DBMS_AQADM.ALTER_QUEUE(queue_name => 'work_order', retry_delay
=> 5);
```

5.3.3.2 ALTER QUEUE TABLE

Use the ALTER_QUEUE_TABLE procedure to modify an existing queue table.

The signature is:

Parameters

```
<queue_table>
```

The (optionally schema-qualified) name of the queue table.

<comment>

Use the <comment> parameter to provide a comment about the queue table.

instance>

<primary_instance> is accepted for compatibility and stored, but is ignored.

<secondary_instance>

<secondary_instance> is accepted for compatibility, but is ignored.

Example

The following command modifies a queue table named work_order_table:

```
EXEC DBMS_AQADM.ALTER_QUEUE_TABLE
         (queue_table => 'work_order_table', comment => 'This queue table
contains work orders for the shipping department.');
```

The queue table is named work_order_table; the command adds a comment to the definition of the queue table.

5.3.3.3 CREATE QUEUE

Use the CREATE_QUEUE procedure to create a queue in an existing queue table. The signature is:

```
CREATE_QUEUE(
```

```
<queue_name> IN VARCHAR2

<queue_table> IN VARCHAR2 ,

<queue_type> IN BINARY_INTEGER DEFAULT NORMAL_QUEUE ,

<max_retries> IN NUMBER DEFAULT 5 ,

<retry_delay> IN NUMBER DEFAULT 0

<retention_time> IN NUMBER DEFAULT 0 ,

<dependency_tracking> IN BOOLEAN DEFAULT FALSE ,

<comment> IN VARCHAR2 DEFAULT NULL ,

<auto_commit> IN BOOLEAN DEFAULT TRUE)</a>
```

Parameters

<queue_name>

The name of the new queue.

<queue_table>

The name of the table in which the new queue will reside.

<queue_type>

The type of the new queue. The valid values for <queue_type> are:

DBMS_AQADM.NORMAL_QUEUE - This value specifies a normal queue (the default).

DBMS_AQADM. EXCEPTION_QUEUE — This value specifies that the new queue is an exception queue. An exception queue will support only dequeue operations.

<max_retries>

<max_retries> specifies the maximum number of attempts to remove a message with a dequeue
statement. The value of <max_retries> is incremented with each ROLLBACK statement.
When the number of failed attempts reaches the value specified by <max_retries> , the message
is moved to the exception queue. The default value for a system table is 0 ; the default value for
a user created table is 5 .

<retry_delay>

<retry_delay> specifies the number of seconds until a message is scheduled for re-processing
after a ROLLBACK . Specify 0 to indicate that the message should be retried immediately (the
default).

<retention_time>

<retention_time> specifies the length of time (in seconds) that a message will be stored after
being dequeued. You can also specify 0 (the default) to indicate the message should not be
retained after dequeueing, or INFINITE to retain the message forever.

```
<dependency_tracking>
```

This parameter is accepted for compatibility and ignored.

```
<comment>
```

<comment> specifies a comment associated with the queue.

```
<auto_commit>
```

This parameter is accepted for compatibility and ignored.

Example

```
The following anonymous block creates a queue named work_order in the work_order_table table:

BEGIN

DBMS_AQADM.CREATE_QUEUE ( queue_name => 'work_order', queue_table => 'work_order_table', comment => 'This queue contains pending work orders.');

END;
```

5.3.3.4 CREATE_QUEUE_TABLE

```
Use the CREATE_QUEUE_TABLE procedure to create a queue table. The signature is:
```

Parameters

```
<queue_table>
```

The (optionally schema-qualified) name of the queue table.

```
<queue_payload_type>
```

The user-defined type of the data that will be stored in the queue table. Please note that to specify a RAW data type, you must create a user-defined type that identifies a RAW type.

```
<storage_clause>
```

```
Use the <storage_clause> parameter to specify attributes for the queue table. Please note
    that only the TABLESPACE option is enforced; all others are accepted for compatibility and ignored.
    Use the TABLESPACE clause to specify the name of a tablespace in which the table will be created.
    <storage_clause> may be one or more of the following:
    TABLESPACE <tablespace_name>, PCTFREE integer, PCTUSED integer,
    INITRANS integer, MAXTRANS integer or [STORAGE](#storage_option).
    <storage_option> may be one or more of the following:
    MINEXTENTS integer, MAXEXTENTS integer, PCTINCREASE integer,
    INITIAL <size_clause>, NEXT, FREELISTS integer, OPTIMAL
    <size_clause>, BUFFER_POOL {KEEP|RECYCLE|DEFAULT} .
<sort_list>
    <sort_list> controls the dequeueing order of the queue; specify the names of the column(s)
    that will be used to sort the queue (in ascending order). The currently accepted values are the
    following combinations of enq_time and priority:
    ena_time, priority
    priority, enq_time
    priority
    enq_time
<multiple_consumers>
    <multiple_consumers> queue tables is not supported.
<message_grouping>
    If specified, <message_grouping> must be NONE .
<comment>
    Use the <comment> parameter to provide a comment about the queue table.
<auto commit>
    <auto_commit> is accepted for compatibility, but is ignored.
instance>
    <primary_instance> is accepted for compatibility and stored, but is ignored.
<secondary_instance>
    <secondary_instance> is accepted for compatibility, but is ignored.
<compatible>
    <compatible> is accepted for compatibility, but is ignored.
<secure>
    <secure> is accepted for compatibility, but is ignored.
```

Example

```
The following anonymous block first creates a type ( work_order ) with attributes that hold a name (a VARCHAR2 ), and a project description (a TEXT ). The block then uses that type to create a queue table:

BEGIN
```

```
CREATE TYPE work_order AS (name VARCHAR2, project TEXT, completed BOOLEAN);
EXEC DBMS_AQADM.CREATE_QUEUE_TABLE
        (queue_table => 'work_order_table',
        queue_payload_type => 'work_order',
        comment => 'Work order message queue table');
```

END;

The queue table is named work_order_table , and contains a payload of a type work_order . A comment notes that this is the Work order message queue table .

5.3.3.5 DROP QUEUE

Use the DROP_QUEUE procedure to delete a queue. The signature is:

Parameters

```
<queue_name>
```

The name of the queue that you wish to drop.

```
<auto_commit>
```

<auto_commit> is accepted for compatibility, but is ignored.

Example

The following anonymous block drops the queue named work_order:

```
BEGIN
```

```
DBMS_AQADM.DROP_QUEUE(queue_name => 'work_order');
END;
```

5.3.3.6 DROP_QUEUE_TABLE

Use the DROP_QUEUE_TABLE procedure to delete a queue table. The signature is:

Parameters

```
<queue_table>
```

The (optionally schema-qualified) name of the queue table.

<force>

The <force> keyword determines the behavior of the DROP_QUEUE_TABLE command when dropping a table that contain entries:

If the target table contains entries and force is FALSE, the command will fail, and the server will issue an error.

If the target table contains entries and force is TRUE, the command will drop the table and any dependent objects.

```
<auto_commit>
```

<auto_commit> is accepted for compatibility, but is ignored.

Example

The following anonymous block drops a table named work_order_table:

```
BEGIN
```

```
DBMS_AQADM.DROP_QUEUE_TABLE ('work_order_table', force => TRUE);
END;
```

5.3.3.7 PURGE QUEUE TABLE

Use the PURGE_QUEUE_TABLE procedure to delete messages from a gueue table. The signature is:

Parameters

```
<queue_table>
```

<queue_table> specifies the name of the queue table from which you are deleting a message.

```
<purge_condition>
```

Use <purge_condition> to specify a condition (a SQL WHERE clause) that the server will evaluate when deciding which messages to purge.

```
<purge_options>
```

<purge_options> is an object of the type aq\$_purge_options_t . An aq\$_purge_options_t object contains:

Attribute	Туре	Description	
Block	Boolean	Specify TRUE if an	exclusive lock should be held on all queues within the table; the de
delivery_mode	INTEGER	<delivery_mode></delivery_mode>	specifies the type of message that will be purged. The only accept

Example

The following anonymous block removes any messages from the work_order_table with a value in the completed column of YES:

```
DECLARE
```

```
purge_options dbms_aqadm.aq$_purge_options_t;
BEGIN
   dbms_aqadm.purge_queue_table('work_order_table', 'completed = YES',
```

```
purge_options);
END;
```

5.3.3.8 START_QUEUE

Use the START_QUEUE procedure to make a queue available for enqueuing and dequeueing.

The signature is:

```
START_QUEUE(
     <queue_name> IN VARCHAR2 ,
     <enqueue> IN BOOLEAN DEFAULT TRUE ,
     <dequeue> IN BOOLEAN DEFAULT TRUE)
```

Parameters

```
<queue_name>
```

<queue_name> specifies the name of the queue that you are starting.

<enqueue>

Specify TRUE to enable enqueueing (the default), or FALSE to leave the current setting unchanged.

<dequeue>

Specify TRUE to enable dequeueing (the default), or FALSE to leave the current setting unchanged.

Example

The following anonymous block makes a queue named work_order available for enqueueing:

```
BEGIN
DBMS_AQADM.START_QUEUE
(queue_name => 'work_order);
END;
```

5.3.3.9 STOP QUEUE

Use the STOP_QUEUE procedure to disable enqueuing or dequeueing on a specified queue.

The signature is:

```
STOP_QUEUE(
    <queue_name> IN VARCHAR2 ,
    <enqueue> IN BOOLEAN DEFAULT TRUE ,
    <dequeue> IN BOOLEAN DEFAULT TRUE ,
    <wait> IN BOOLEAN DEFAULT TRUE)
```

Parameters

```
<queue_name>
```

<queue_name> specifies the name of the queue that you are stopping.

<enqueu>

Specify TRUE to disable enqueueing (the default), or FALSE to leave the current setting unchanged.

<dequeue>

Specify TRUE to disable dequeueing (the default), or FALSE to leave the current setting unchanged.

<wait>

Specify TRUE to instruct the server to wait for any uncompleted transactions to complete before applying the specified changes; while waiting to stop the queue, no transactions are allowed to enqueue or dequeue from the specified queue. Specify FALSE to stop the queue immediately.

Example

The following anonymous block disables enqueueing and dequeueing from the queue named work_order:

REGTN

DBMS_AQADM.STOP_QUEUE(queue_name =>'work_order', enqueue=>TRUE,
dequeue=>TRUE, wait=>TRUE);
END;

Enqueueing and dequeueing will stop after any outstanding transactions complete.

5.3.4.0 DBMS_CRYPTO

The DBMS_CRYPTO package provides functions and procedures that allow you to encrypt or decrypt RAW, BLOB or CLOB data. You can also use DBMS_CRYPTO functions to generate cryptographically strong random values.

The following table lists the DBMS_CRYPTO Functions and Procedures.

Function/Procedure	Return Type	Description
<pre>DECRYPT(src, typ, key, iv)</pre>	RAW	Decrypts RAW data.
DECRYPT(dst INOUT, src, typ, key, iv)	N/A	Decrypts BLOB data.
DECRYPT(dst INOUT, src, typ, key, iv)	N/A	Decrypts CLOB data.
<pre>ENCRYPT(src, typ, key, iv)</pre>	RAW	Encrypts RAW data.
<pre>ENCRYPT(dst INOUT, src, typ, key, iv)</pre>	N/A	Encrypts BLOB data.
<pre>ENCRYPT(dst INOUT, src, typ, key, iv)</pre>	N/A	Encrypts CLOB data.
HASH(src, typ)	RAW	Applies a hash algorithm to RAW data.
HASH(src)	RAW	Applies a hash algorithm to CLOB data.
MAC(src, typ, key)	RAW	Returns the hashed MAC value of the given RAW d
MAC(src, typ, key)	RAW	Returns the hashed MAC value of the given CLOB
RANDOMBYTES(number_bytes)	RAW	Returns a specified number of cryptographically strong
RANDOMINTEGER()	INTEGER	Returns a random INTEGER .
RANDOMNUMBER()	NUMBER	Returns a random NUMBER.

DBMS_CRYPTO functions and procedures support the following error messages:

```
ORA-28239 - DBMS_CRYPTO.KeyNull
ORA-28829 - DBMS_CRYPTO.CipherSuiteNull
```

ORA-28827 - DBMS_CRYPTO.CipherSuiteInvalid

Unlike Oracle, Advanced Server will not return error 0RA-28233 if you re-encrypt previously encrypted information.

Please note that RAW and BLOB are synonyms for the PostgreSQL BYTEA data type, and CLOB is a

```
synonym for TEXT.
```

5.3.4.1 DECRYPT

The DECRYPT function or procedure decrypts data using a user-specified cipher algorithm, key and optional initialization vector. The signature of the DECRYPT function is:

```
DECRYPT
```

```
(<src> IN RAW, <typ> IN INTEGER, <key> IN RAW, <iv> IN RAW DEFAULT NULL) RETURN RAW
```

The signature of the DECRYPT procedure is:

```
DECRYPT
```

```
(<dst> INOUT BLOB, <src> IN BLOB, <typ> IN INTEGER, <key> IN RAW ,
<iv> IN RAW DEFAULT NULL)
```

or

DECRYPT

```
(<dst> INOUT CLOB, <src> IN CLOB, <typ> IN INTEGER, <key> IN RAW , <iv> IN RAW DEFAULT NULL)
```

When invoked as a procedure, DECRYPT returns BLOB or CLOB data to a user-specified BLOB.

Parameters

<dst>

<dst> specifies the name of a BLOB to which the output of the DECRYPT procedure will be
written. The DECRYPT procedure will overwrite any existing data currently in <dst> .

<src>

<src> specifies the source data that will be decrypted. If you are invoking DECRYPT as a function, specify RAW data; if invoking DECRYPT as a procedure, specify BLOB or CLOB data.

<typ>

<typ> specifies the block cipher type and any modifiers. This should match the type specified when the <src> was encrypted. Advanced Server supports the following block cipher algorithms, modifiers and cipher suites:

Block Cipher Algorithms

Block Cipher Modifiers	
ENCRYPT_AES128	CONSTANT INTEGER := 6;
ENCRYPT_AES	CONSTANT INTEGER := 4;
ENCRYPT_3DES	CONSTANT INTEGER := 3;
ENCRYPT_DES	CONSTANT INTEGER := 1;

CHAIN_CBC CONSTANT INTEGER := 256; CHAIN_ECB CONSTANT INTEGER := 768;

Block Cipher Padding Modifiers

PAD_PKCS5 CONSTANT INTEGER := 4096; PAD_NONE CONSTANT INTEGER := 8192;

Block Cipher Suites

DES_CBC_PKCS5 CONSTANT INTEGER := ENCRYPT_DES + CHAIN_CBC + PAD_PKCS5;

Block Cipher Algorithms

```
DES3_CBC_PKCS5 CONSTANT INTEGER := ENCRYPT_3DES + CHAIN_CBC + PAD_PKCS5;
AES_CBC_PKCS5 CONSTANT INTEGER := ENCRYPT_AES + CHAIN_CBC + PAD_PKCS5;
```

<key>

<key> specifies the user-defined decryption key. This should match the key specified when the <src> was encrypted.

<iv>

<iv> (optional) specifies an initialization vector. If an initialization vector was specified when the <src> was encrypted, you must specify an initialization vector when decrypting the <src> . The default is NULL .

Examples

The following example uses the DBMS_CRYPTO.DECRYPT function to decrypt an encrypted password retrieved from the passwords table:

```
CREATE TABLE passwords
(
   principal VARCHAR2(90) PRIMARY KEY, -- username
   ciphertext RAW(9) -- encrypted password
);
CREATE FUNCTION get_password(username VARCHAR2) RETURN RAW AS
           INTEGER := DBMS_CRYPTO.DES_CBC_PKCS5;
           RAW(128) := 'my secret key';
 key
           RAW(100) := 'my initialization vector';
 iv
 password RAW(2048);
 BEGIN
   SELECT ciphertext INTO password FROM passwords WHERE principal =
   RETURN dbms_crypto.decrypt(password, typ, key, iv);
 END;
```

Note that when calling DECRYPT , you must pass the same cipher type, key value and initialization vector that was used when ENCRYPTING the target.

5.3.4.2 **ENCRYPT**

The ENCRYPT function or procedure uses a user-specified algorithm, key, and optional initialization vector to encrypt RAW, BLOB or CLOB data. The signature of the ENCRYPT function is:

ENCRYPT

```
(<src> IN RAW, <typ> IN INTEGER, <key> IN RAW , <iv> IN RAW DEFAULT NULL) RETURN RAW
```

The signature of the ENCRYPT procedure is:

```
ENCRYPT
```

```
(<dst> INOUT BLOB, <src> IN BLOB, <typ> IN INTEGER, <key> IN RAW ,
<iv> IN RAW DEFAULT NULL)
```

or

```
ENCRYPT
```

```
(<dst> INOUT BLOB, <src> IN CLOB, <typ> IN INTEGER, <key> IN RAW , <iv> IN RAW DEFAULT NULL)
```

When invoked as a procedure, ENCRYPT returns BLOB or CLOB data to a user-specified BLOB.

Parameters

<dst>

<dst> specifies the name of a BLOB to which the output of the ENCRYPT procedure will be
written. The ENCRYPT procedure will overwrite any existing data currently in <dst> .

<Src>

<src> specifies the source data that will be encrypted. If you are invoking ENCRYPT as a function, specify RAW data; if invoking ENCRYPT as a procedure, specify BLOB or CLOB data.

<typ>

<typ> specifies the block cipher type that will be used by ENCRYPT, and any modifiers. Advanced Server supports the block cipher algorithms, modifiers and cipher suites listed below:

Block Cipher Algorithms

ENCRYPT_DES	CONSTANT INTEGER := 1;
ENCRYPT_3DES	CONSTANT INTEGER := 3;
ENCRYPT_AES	CONSTANT INTEGER := 4;
ENCRYPT_AES128	CONSTANT INTEGER := 6;
Block Cipher Modifiers	
CHAIN_CBC	CONSTANT INTEGER := 256;
CHAIN_ECB	CONSTANT INTEGER := 768;
Block Cipher Padding Modifiers	
PAD_PKCS5	CONSTANT INTEGER := 4096;
PAD_NONE	CONSTANT INTEGER := 8192;
Block Cipher Suites	
DES_CBC_PKCS5	<pre>CONSTANT INTEGER := ENCRYPT_DES + CHAIN_CBC + PAD_PKCS5;</pre>
DES3_CBC_PKCS5	<pre>CONSTANT INTEGER := ENCRYPT_3DES + CHAIN_CBC + PAD_PKCS5;</pre>
AES_CBC_PKCS5	<pre>CONSTANT INTEGER := ENCRYPT_AES + CHAIN_CBC + PAD_PKCS5;</pre>

<key>

<key> specifies the encryption key.

<iv>

<iv> (optional) specifies an initialization vector. By default, <iv> is NULL.

Examples

The following example uses the DBMS_CRYPTO.DES_CBC_PKCS5 Block Cipher Suite (a pre-defined set of algorithms and modifiers) to encrypt a value retrieved from the passwords table:

```
CREATE TABLE passwords

(
    principal VARCHAR2(90) PRIMARY KEY, -- username
    ciphertext RAW(9) -- encrypted password
);
CREATE PROCEDURE set_password(username VARCHAR2, cleartext RAW) AS
```

ENCRYPT uses a key value of my secret key and an initialization vector of my initialization vector when encrypting the password; specify the same key and initialization vector when decrypting the password.

5.3.4.3 HASH

The HASH function uses a user-specified algorithm to return the hash value of a RAW or CLOB value. The HASH function is available in three forms:

```
HASH
( <src> IN RAW, <typ> IN INTEGER) RETURN RAW

HASH
( <src> IN CLOB, <typ> IN INTEGER) RETURN RAW
```

Parameters

<Src>

<src> specifies the value for which the hash value will be generated. You can specify a RAW , a BLOB , or a CLOB value.

<typ>

<typ> specifies the HASH function type. Advanced Server supports the HASH function types listed below:

HASH Fund	ctions				
HASH_MD4		CONSTANT	INTEGER	:=	1;
HASH_MD5		CONSTANT	INTEGER	:=	2;
HASH_SH1		CONSTANT	INTEGER	:=	3;

Examples

The following example uses DBMS_CRYPTO.HASH to find the md5 hash value of the string, cleartext source :

DECLARE

```
typ INTEGER := DBMS_CRYPTO.HASH_MD5;
hash_value RAW(100);
BEGIN
hash_value := DBMS_CRYPTO.HASH('cleartext source', typ);
```

nusn_value := DBMS_CRTPTO.HASH(Cleartext Source , typ);

END;

5.3.4.4 MAC

The MAC function uses a user-specified MAC function to return the hashed MAC value of a RAW or CLOB value. The MAC function is available in three forms:

```
MAC
```

```
(<src> IN RAW, <typ> IN INTEGER, <key> IN RAW) RETURN RAW
```

MAC

```
(<src> IN CLOB, <typ> IN INTEGER, <key> IN RAW) RETURN RAW
```

Parameters

<src>

<src> specifies the value for which the MAC value will be generated. Specify a RAW , BLOB
, or CLOB value.

<typ>

<typ> specifies the MAC function used. Advanced Server supports the MAC functions listed below.

MAC Functions		
HMAC_MD5	CONSTANT INTEGER	:= 1;
HMAC_SH1	CONSTANT INTEGER	:= 2;

<key>

<key> specifies the key that will be used to calculate the hashed MAC value.

Examples

The following example finds the hashed MAC value of the string cleartext source:

```
DECLARE
```

```
typ INTEGER := DBMS_CRYPTO.HMAC_MD5;
key RAW(100) := 'my secret key';
mac_value RAW(100);
BEGIN
```

```
mac_value := DBMS_CRYPTO.MAC('cleartext source', typ, key);
```

END;

DBMS_CRYPTO.MAC uses a key value of my secret key when calculating the MAC value of cleartext source .

5.3.4.5 RANDOMBYTES

The RANDOMBYTES function returns a RAW value of the specified length, containing cryptographically random bytes. The signature is:

```
RANDOMBYTES
```

```
(<number_bytes> IN INTEGER) RETURNS RAW
```

Parameter

```
<number_bytes>
```

<number_bytes> specifies the number of random bytes to be returned

Examples

The following example uses RANDOMBYTES to return a value that is 1024 bytes long:

```
DECLARE
  result RAW(1024);
BEGIN
  result := DBMS_CRYPTO.RANDOMBYTES(1024);
END;
```

5.3.4.6 RANDOMINTEGER

The RANDOMINTEGER() function returns a random INTEGER between 0 and 268,435,455. The signature is:

RANDOMINTEGER() RETURNS INTEGER

Examples

The following example uses the RANDOMINTEGER function to return a cryptographically strong random INTEGER value:

```
DECLARE
  result INTEGER;
BEGIN
  result := DBMS_CRYPTO.RANDOMINTEGER();
  DBMS_OUTPUT.PUT_LINE(result);
END;
```

5.3.4.7 RANDOMNUMBER

The RANDOMNUMBER() function returns a random NUMBER between 0 and 268,435,455. The signature is:

RANDOMNUMBER() RETURNS NUMBER

Examples

The following example uses the RANDOMNUMBER function to return a cryptographically strong random number:

```
DECLARE
  result NUMBER;
BEGIN
  result := DBMS_CRYPTO.RANDOMNUMBER();
  DBMS_OUTPUT.PUT_LINE(result);
END;
```

5.3.5.0 DBMS JOB

The DBMS_JOB package provides for the creation, scheduling, and managing of jobs. A job runs a stored procedure which has been previously stored in the database. The SUBMIT procedure is used to create and store a job definition. A job identifier is assigned to a job along with its associated stored procedure and the attributes describing when and how often the job is to be run.

This package relies on the pgAgent scheduler. By default, the Advanced Server installer installs pgAgent, but you must start the pgAgent service manually prior to using DBMS_JOB. If you attempt to use this package to schedule a job after un-installing pgAgent, DBMS_JOB will throw an error. DBMS_JOB verifies that pgAgent is installed, but does not verify that the service is running.

The following table lists the supported DBMS_JOB procedures:

Function/Procedure	Return Type	Descrip
<pre>BROKEN(<job>, <broken> [, <next_date>])</next_date></broken></job></pre>	n/a	Specify
<pre>CHANGE(<job, <what="">, <next_date>, <interval, force="" instance,="">)</interval,></next_date></job,></pre>	n/a	Change
<pre>INTERVAL(<job>, <interval>)</interval></job></pre>	n/a	Set the
<pre>NEXT_DATE(<job>, <next_date>)</next_date></job></pre>	n/a	Set the I
REMOVE(<job>)</job>	n/a	Delete tl
RUN(<job>)</job>	n/a	Forces e
<pre>SUBMIT(<job> OUT, <what> [, <next_date> [, <interval> [, <no_parse>]]])</no_parse></interval></next_date></what></job></pre>	n/a	Creates
<pre>WHAT(<job>, <what>)</what></job></pre>	n/a	Change

Advanced Server's implementation of DBMS_J0B is a partial implementation when compared to Oracle's version. Only those functions and procedures listed in the table above are supported.

Before using DBMS_JOB, a database superuser must create the pgAgent extension. Use the psql client to connect to a database and invoke the command:

```
CREATE EXTENSION pgagent;
```

When and how often a job is run is dependent upon two interacting parameters — <next_date> and <interval> . The <next_date> parameter is a date/time value that specifies the next date/time when the job is to be executed. The <interval> parameter is a string that contains a date function that evaluates to a date/time value.

Just prior to any execution of the job, the expression in the <interval> parameter is evaluated. The resulting value replaces the <next_date> value stored with the job. The job is then executed. In this manner, the expression in <interval> is repeatedly re-evaluated prior to each job execution, supplying the <next_date> date/time for the next execution.

The following examples use the following stored procedure, <code>job_proc</code> , which simply inserts a timestamp into table, <code>jobrun</code> , containing a single <code>VARCHAR2</code> column.

5.3.5.1 BROKEN

The BROKEN procedure sets the state of a job to either broken or not broken. A broken job cannot be executed except by using the RUN procedure.

```
BROKEN(<job> BINARY_INTEGER, <broken> BOOLEAN [, <next_date> DATE ])
```

Parameters

```
<job>
```

Identifier of the job to be set as broken or not broken.

<broken>

If set to TRUE the job's state is set to broken. If set to FALSE the job's state is set to not broken. Broken jobs cannot be run except by using the RUN procedure.

```
<next_date>
```

Date/time when the job is to be run. The default is SYSDATE .

Examples

Set the state of a job with job identifier 104 to broken:

```
BEGIN
DBMS_JOB.BROKEN(104,true);
END;
Change the state back to not broken:
BEGIN
DBMS_JOB.BROKEN(104,false);
END;
```

5.3.5.2 CHANGE

The CHANGE procedure modifies certain job attributes including the stored procedure to be run, the next date/time the job is to be run, and how often it is to be run.

Parameters

<job>

Identifier of the job to modify.

<what>

Stored procedure name. Set this parameter to null if the existing value is to remain unchanged.

<next_date>

Date/time when the job is to be run next. Set this parameter to null if the existing value is to remain unchanged.

<interval>

Date function that when evaluated, provides the next date/time the job is to run. Set this parameter to null if the existing value is to remain unchanged.

<instance>

This argument is ignored, but is included for compatibility.

<force>

This argument is ignored, but is included for compatibility.

Examples

Change the job to run next on December 13, 2007. Leave other parameters unchanged.

BEGIN

```
DBMS_JOB.CHANGE(104,NULL,TO_DATE('13-DEC-07','DD-MON-YY'),NULL, NULL,
NULL);
```

END;

5.3.5.3 INTERVAL

The INTERVAL procedure sets the frequency of how often a job is to be run.

INTERVAL(<job> BINARY_INTEGER, <interval> VARCHAR2)

Parameters

<job>

Identifier of the job to modify.

<interval>

Date function that when evaluated, provides the next date/time the job is to be run. If <interval> is NULL and the job is complete, the job is removed from the queue.

Examples

Change the job to run once a week:

BEGIN

```
DBMS_JOB.INTERVAL(104, 'SYSDATE + 7');
```

END;

5.3.5.4 NEXT DATE

The NEXT_DATE procedure sets the date/time of when the job is to be run next.

```
NEXT_DATE(<job> BINARY_INTEGER, <next_date> DATE)
```

Parameters

<job>

Identifier of the job whose next run date is to be set.

<next_date>

Date/time when the job is to be run next.

Examples

Change the job to run next on December 14, 2007:

BEGIN

```
DBMS_JOB.NEXT_DATE(104, TO_DATE('14-DEC-07','DD-MON-YY'));
```

END;

5.3.5.5 REMOVE

The REMOVE procedure deletes the specified job from the database. The job must be resubmitted using the SUBMIT procedure in order to have it executed again. Note that the stored procedure that was associated with the job is not deleted.

REMOVE(<job> BINARY_INTEGER)

Parameter

```
<job>
```

Identifier of the job that is to be removed from the database.

Examples

Remove a job from the database:

BEGIN

```
DBMS_JOB.REMOVE(104);
```

END;

5.3.5.6 RUN

The RUN procedure forces the job to be run, even if its state is broken.

```
RUN(<job> BINARY_INTEGER)
```

Parameter

<job>

Identifier of the job to be run.

Examples

Force a job to be run.

BEGIN

DBMS_JOB.RUN(104);

END;

5.3.5.7 SUBMIT

The SUBMIT procedure creates a job definition and stores it in the database. A job consists of a job identifier, the stored procedure to be executed, when the job is to be first run, and a date function that calculates the next date/time the job is to be run.

```
SUBMIT(<job> OUT BINARY_INTEGER, <what> VARCHAR2
```

```
[, <next_date> DATE [, <interval> VARCHAR2 [, <no_parse> BOOLEAN ]]])
```

Parameters

<job>

Identifier assigned to the job.

<what>

Name of the stored procedure to be executed by the job.

<next_date>

Date/time when the job is to be run next. The default is SYSDATE .

<interval>

Date function that when evaluated, provides the next date/time the job is to run. If <interval> is set to null, then the job is run only once. Null is the default.

```
<no_parse>
```

If set to TRUE, do not syntax-check the stored procedure upon job creation – check only when the job first executes. If set to FALSE, check the procedure upon job creation. The default is FALSE

Note

The <no_parse> option is not supported in this implementation of SUBMIT() . It is included for compatibility only.

Examples

The following example creates a job using stored procedure, job_proc . The job will execute immediately and run once a day thereafter as set by the <interval> parameter, SYSDATE + 1 .

5.3.5.8 WHAT

The WHAT procedure changes the stored procedure that the job will execute.

```
WHAT(<job> BINARY_INTEGER, <what> VARCHAR2)
```

Parameters

<job>

Identifier of the job for which the stored procedure is to be changed.

<what>

Name of the stored procedure to be executed.

Examples

Change the job to run the list_emp procedure:

BEGIN

```
DBMS_JOB.WHAT(104,'list_emp;');
```

END;

5.3.6.0 DBMS LOB

The DBMS_LOB package provides the capability to operate on large objects. The following table lists the supported functions and procedures:

```
Function/Procedure
APPEND(<dest_lob> IN OUT, <src_lob>)
COMPARE(<lob_1>, <lob_2> [, <amount> [, <offset_1> [, <offset_2> ]]])
CONVERTOBLOB(<dest_lob> IN OUT, <src_clob>, <amount>, <dest_offset> IN OUT, <src_offset> IN OUT
CONVERTTOCLOB(<dest_lob> IN OUT, <src_blob>, <amount>, <dest_offset> IN OUT, <src_offset> IN OUT
COPY(<dest_lob> IN OUT, <src_lob>, <amount> [, <dest_offset> [, <src_offset> ]])
ERASE(lob_loc IN OUT, <amount> IN OUT [, <offset> ])
GET_STORAGE_LIMIT(<lob_loc>)
GETLENGTH(<lob_loc>)
INSTR(<lob_loc>, <pattern> [, <offset> [, <nth> ]])
READ(<lob_loc>, <amount> IN OUT, <offset>, <buffer> OUT)
SUBSTR(<lob_loc> [, <amount> [, <offset> ]])
TRIM(<lob_loc> IN OUT, <amount>, <offset>, <buffer>)
WRITE(<lob_loc> IN OUT, <amount>, <offset>, <buffer>)
WRITEAPPEND(<lob_loc> IN OUT, <amount>, <buffer>)
```

Advanced Server's implementation of DBMS_LOB is a partial implementation when compared to Oracle's version. Only those functions and procedures listed in the table above are supported.

The following table lists the public variables available in the package.

Public Variables	Data Type	Value
compress off	INTEGER	0
compress_on	INTEGER	1
deduplicate_off	INTEGER	0
deduplicate_on	INTEGER	4
default_csid	INTEGER	0
default_lang_ctx	INTEGER	0
encrypt_off	INTEGER	0
encrypt_on	INTEGER	1
file_readonly	INTEGER	0
lobmaxsize	INTEGER	1073741823
lob_readonly	INTEGER	0
lob_readwrite	INTEGER	1
no_warning	INTEGER	0
opt_compress	INTEGER	1
opt_deduplicate	INTEGER	4
opt_encrypt	INTEGER	2
warn_inconvertible_char	INTEGER	1

In the following sections, lengths and offsets are measured in bytes if the large objects are BLOBs . Lengths and offsets are measured in characters if the large objects are CLOBs .

5.3.6.1 APPEND

The APPEND procedure provides the capability to append one large object to another. Both large objects must be of the same type.

APPEND(<dest_lob> IN OUT { BLOB | CLOB }, <src_lob> { BLOB | CLOB })

Parameters

<dest lob>

Large object locator for the destination object. Must be the same data type as <src_lob> .

<src_lob>

Large object locator for the source object. Must be the same data type as <dest_lob> .

5.3.6.2 COMPARE

The COMPARE procedure performs an exact byte-by-byte comparison of two large objects for a given length at given offsets. The large objects being compared must be the same data type.

```
<status> INTEGER COMPARE(<lob_1> { BLOB | CLOB } ,
```

> <lob_2> { BLOB | CLOB }

[, <amount> INTEGER [, <offset_1> INTEGER [, <offset_2> INTEGER]]])

Parameters

<lob_1>

Large object locator of the first large object to be compared. Must be the same data type as <lob_2> .

<lob_2>

Large object locator of the second large object to be compared. Must be the same data type as <lob_1> .

<amount>

If the data type of the large objects is BLOB, then the comparison is made for <amount> bytes. If the data type of the large objects is CLOB, then the comparison is made for <amount> characters. The default is the maximum size of a large object.

<offset_1>

Position within the first large object to begin the comparison. The first byte/character is offset 1. The default is 1.

<offset_2>

Position within the second large object to begin the comparison. The first byte/character is offset 1. The default is 1.

<status>

5.3.6.3 CONVERTTOBLOB

The CONVERTTOBLOB procedure provides the capability to convert character data to binary.

CONVERTTOBLOB(<dest_lob> IN OUT BLOB, <src_clob> CLOB,

<amount> INTEGER, <dest_offset> IN OUT INTEGER ,

<src_offset> IN OUT INTEGER, <blob_csid> NUMBER ,

<lang_context> IN OUT INTEGER, <warning> OUT INTEGER)

Parameters

<dest_lob>

BLOB large object locator to which the character data is to be converted.

<src_clob>

CLOB large object locator of the character data to be converted.

<amount>

Number of characters of <src_clob> to be converted.

<dest_offset> IN

Position in bytes in the destination BLOB where writing of the source CLOB should begin. The first byte is offset 1.

<dest_offset> OUT

Position in bytes in the destination BLOB after the write operation completes. The first byte is offset 1.

<src_offset> IN

Position in characters in the source CLOB where conversion to the destination BLOB should begin. The first character is offset 1.

<src_offset> OUT

Position in characters in the source CLOB after the conversion operation completes. The first character is offset 1.

<blob_csid>

Character set ID of the converted, destination BLOB.

<larg_context> IN

Language context for the conversion. The default value of 0 is typically used for this setting.

<lang_context> OUT

Language context after the conversion completes.

<warning>

0 if the conversion was successful, 1 if an inconvertible character was encountered.

5.3.6.4 CONVERTTOCLOB

The CONVERTTOCLOB procedure provides the capability to convert binary data to character.

CONVERTTOCLOB(<dest_lob> IN OUT CLOB, <src_blob> BLOB ,

```
<amount> INTEGER, <dest_offset> IN OUT INTEGER,
<src_offset> IN OUT INTEGER, <blob_csid> NUMBER,
<lang_context> IN OUT INTEGER, <warning> OUT INTEGER)
```

Parameters

<dest_lob>

CLOB large object locator to which the binary data is to be converted.

<src_blob>

BLOB large object locator of the binary data to be converted.

<amount>

Number of bytes of <src_blob> to be converted.

<dest_offset> IN

Position in characters in the destination CLOB where writing of the source BLOB should begin. The first character is offset 1.

<dest_offset> OUT

Position in characters in the destination CLOB after the write operation completes. The first character is offset 1.

<src_offset> IN

Position in bytes in the source BLOB where conversion to the destination CLOB should begin. The first byte is offset 1.

<src_offset> OUT

Position in bytes in the source BLOB after the conversion operation completes. The first byte is offset 1.

<blood>

Character set ID of the converted, destination CLOB .

<lang_context> IN

Language context for the conversion. The default value of 0 is typically used for this setting.

<lang_context> OUT

Language context after the conversion completes.

<warning>

0 if the conversion was successful, 1 if an inconvertible character was encountered.

5.3.6.5 COPY

The COPY procedure provides the capability to copy one large object to another. The source and destination large objects must be the same data type.

<amount> INTEGER

[, <dest_offset> INTEGER [, <src_offset> INTEGER]])

Parameters

<dest_lob>

Large object locator of the large object to which <src_lob> is to be copied. Must be the same
data type as <src_lob> .

<src_lob>

Large object locator of the large object to be copied to <dest_lob> . Must be the same data type as <dest_lob> .

<amount>

Number of bytes/characters of <src_lob> to be copied.

<dest_offset>

Position in the destination large object where writing of the source large object should begin. The first position is offset 1. The default is 1.

<src_offset>

Position in the source large object where copying to the destination large object should begin. The first position is offset 1. The default is 1.

5.3.6.6 ERASE

The ERASE procedure provides the capability to erase a portion of a large object. To erase a large object means to replace the specified portion with zero-byte fillers for BLOBs or with spaces for CLOBs. The actual size of the large object is not altered.

> ERASE(<lob_loc> IN OUT { BLOB | CLOB }, <amount> IN OUT INTEGER

[, <offset> INTEGER])

Parameters

<lob_loc>

Large object locator of the large object to be erased.

<amount> IN

Number of bytes/characters to be erased.

<amount> OUT

Number of bytes/characters actually erased. This value can be smaller than the input value if the end of the large object is reached before <amount> bytes/characters have been erased.

<offset>

Position in the large object where erasing is to begin. The first byte/character is position 1. The default is 1.

5.3.6.7 GET STORAGE LIMIT

The GET_STORAGE_LIMIT function returns the limit on the largest allowable large object.

<size> INTEGER GET_STORAGE_LIMIT(<lob_loc> BLOB)

<size> INTEGER GET_STORAGE_LIMIT(<lob_loc< CLOB)</pre>

Parameters

<size>

Maximum allowable size of a large object in this database.

<lob_loc>

This parameter is ignored, but is included for compatibility.

5.3.6.8 GETLENGTH

The GETLENGTH function returns the length of a large object.

<amount> INTEGER GETLENGTH(<lob_loc> BLOB)

<amount> INTEGER GETLENGTH(<lob_loc> CLOB)

Parameters

<lob_loc>

Large object locator of the large object whose length is to be obtained.

<amount>

Length of the large object in bytes for BLOBs or characters for CLOBs .

5.3.6.9 INSTR

The INSTR function returns the location of the nth occurrence of a given pattern within a large object.

> <position> INTEGER INSTR(<lob_loc> { BLOB | CLOB } ,

<pattern> { RAW | VARCHAR2 } [, <offset> INTEGER [, <nth> INTEGER]])

Parameters

<lob_loc>

Large object locator of the large object in which to search for pattern.

<pattern>

Pattern of bytes or characters to match against the large object, lob. <pattern> must be RAW if <lob_loc> is a BLOB . pattern must be VARCHAR2 if <lob_loc> is a CLOB .

<offset>

Position within <lob_loc> to start search for <pattern> . The first byte/character is position 1. The default is 1.

<nth>

Search for $\,$ <pattern> $\,$, $\,$ <nth> $\,$ number of times starting at the position given by $\,$ <offset> $\,$. The default is 1.

<position>

Position within the large object where <pattern< appears the nth time specified by <nth< starting from the position given by <offset> .

5.3.6.10 READ

The READ procedure provides the capability to read a portion of a large object into a buffer.

> READ(<lob_loc> { BLOB | CLOB }, <amount> IN OUT BINARY_INTEGER ,

> <offset> INTEGER, <buffer> OUT { RAW | VARCHAR2 })

Parameters

<lob_loc>

Large object locator of the large object to be read.

<amount> IN

Number of bytes/characters to read.

<amount> OUT

Number of bytes/characters actually read. If there is no more data to be read, then <amount> returns 0 and a DATA_NOT_FOUND exception is thrown.

<offset>

Position to begin reading. The first byte/character is position 1.

<buffer>

Variable to receive the large object. If $<lob_loc>$ is a BLOB , then <buffer> must be RAW . If $<lob_loc>$ is a CLOB , then <buffer> must be VARCHAR2 .

5.3.6.11 SUBSTR

The SUBSTR function provides the capability to return a portion of a large object.

> <data> { RAW | VARCHAR2 } SUBSTR(<lob_loc> { BLOB | CLOB }

[, <amount> INTEGER [, <offset> INTEGER]])

Parameters

<lob_loc>

Large object locator of the large object to be read.

<amount>

Number of bytes/characters to be returned. Default is 32,767.

<offset>

Position within the large object to begin returning data. The first byte/character is position 1. The default is 1.

<data>

Returned portion of the large object to be read. If $<lob_loc>$ is a BLOB , the return data type is RAW . If $<lob_loc>$ is a CLOB , the return data type is VARCHAR2 .

174

5.3.6.12 TRIM

The TRIM procedure provides the capability to truncate a large object to the specified length.

> TRIM(<lob_loc> IN OUT { BLOB | CLOB }, <newlen> INTEGER)

Parameters

<lob_loc>

Large object locator of the large object to be trimmed.

<newlen>

Number of bytes/characters to which the large object is to be trimmed.

5.3.6.13 WRITE

The WRITE procedure provides the capability to write data into a large object. Any existing data in the large object at the specified offset for the given length is overwritten by data given in the buffer.

Parameters

<lob_loc>

Large object locator of the large object to be written.

<amount>

The number of bytes/characters in <buffer> to be written to the large object.

<offset>

The offset in bytes/characters from the beginning of the large object (origin is 1) for the write operation to begin.

<buffer>

Contains data to be written to the large object. If $<lob_loc>$ is a BLOB , then <buffer> must be RAW . If $<lob_loc>$ is a CLOB , then <buffer> must be VARCHAR2 .

5.3.6.14 WRITEAPPEND

The WRITEAPPEND procedure provides the capability to add data to the end of a large object.

```
> WRITEAPPEND(<lob_loc> IN OUT { BLOB | CLOB } ,
```

> <amount> BINARY_INTEGER, <buffer> { RAW | VARCHAR2 })

Parameters

<lob_loc>

Large object locator of the large object to which data is to be appended.

<amount>

Number of bytes/characters from <buffer> to be appended the large object.

<buffer>

Data to be appended to the large object. If $<lob_loc>$ is a BLOB , then <buffer> must be RAW. If $<lob_loc>$ is a CLOB , then <buffer> must be VARCHAR2 .

5.3.7 DBMS_LOCK

Advanced Server provides support for the DBMS_LOCK.SLEEP procedure.

Function/Procedure	Return Type	Description		
<pre>SLEEP(<seconds>)</seconds></pre>	n/a	Suspends a session for the specified number of	<seconds></seconds>	

Advanced Server's implementation of DBMS_LOCK is a partial implementation when compared to Oracle's version. Only DBMS_LOCK.SLEEP is supported.

SLEEP

The SLEEP procedure suspends the current session for the specified number of seconds.

SLEEP(<seconds> NUMBER)

Parameters

<seconds>

<seconds> specifies the number of seconds for which you wish to suspend the session.
<seconds> can be a fractional value; for example, enter 1.75 to specify one and three-fourths of a second.

5.3.8.0 DBMS MVIEW

Use procedures in the DBMS_MVIEW package to manage and refresh materialized views and their dependencies. Advanced Server provides support for the following DBMS_MVIEW procedures:

Procedure

GET_MV_DEPENDENCIES(<list> VARCHAR2, <deplist> VARCHAR2);

REFRESH(<list> VARCHAR2, <method> VARCHAR2, <rollback_seg> VARCHAR2, <push_deferred_rpc> BOOM REFRESH(<tab> dbms_utility.uncl_array, <method> VARCHAR2, <rollback_seg> VARCHAR2, <push_deferred_rpc> BINARY_INTEGER, <method> VARCHAR2, <rollback_seg> VARCHAR2, <rollback_seg> VARCHAR2, <rollback_seg> VARCHAR2, <method> VARCHAR2, <method< VARCHAR2, <method< VARCHAR2, <method</p>
REFRESH_DEPENDENT(<number_of_failures> BINARY_INTEGER, <list> VARCHAR2, <method</p>
VARCHAR2, <method> VARCHAR2, <method</p>
REFRESH_DEPENDENT(<number_of_failures> BINARY_INTEGER, <tab> dbms_utility.uncl_array, <method> <method> <method</p>

Advanced Server's implementation of DBMS_MVIEW is a partial implementation when compared to Oracle's version. Only those functions and procedures listed in the table above are supported.

5.3.8.1 GET MV DEPENDENCIES

When given the name of a materialized view, GET_MV_DEPENDENCIES returns a list of items that depend on the specified view. The signature is:

GET_MV_DEPENDENCIES(

t> IN VARCHAR2,

```
<deplist> OUT VARCHAR2);
```

Parameters

```
st>
```

st> specifies the name of a materialized view, or a comma-separated list of materialized view names.

```
<deplist>
```

<deplist> is a comma-separated list of schema-qualified dependencies. <deplist> is a
VARCHAR2 value.

Examples

The following example:

```
DECLARE
  deplist VARCHAR2(1000);
BEGIN
  DBMS_MVIEW.GET_MV_DEPENDENCIES('public.emp_view', deplist);
  DBMS_OUTPUT.PUT_LINE('deplist: ' || deplist);
END;
```

Displays a list of the dependencies on a materialized view named public.emp_view .

5.3.8.2 REFRESH

Use the REFRESH procedure to refresh all views specified in either a comma-separated list of view names, or a table of DBMS_UTILITY.UNCL_ARRAY values. The procedure has two signatures; use the first form when specifying a comma-separated list of view names:

REFRESH(

Use the second form to specify view names in a table of DBMS_UTILITY.UNCL_ARRAY values:

REFRESH(

```
<tab> IN OUT DBMS_UTILITY.UNCL_ARRAY,
<method> IN VARCHAR2 DEFAULT NULL,
<rollback_seg> IN VARCHAR2 DEFAULT NULL,
```

```
<push_deferred_rpc> IN BOOLEAN DEFAULT TRUE,
  <refresh_after_errors> IN BOOLEAN DEFAULT FALSE,
  <purge_option> IN NUMBER DEFAULT 1,
  <parallelism> IN NUMBER DEFAULT 0,
  <heap_size> IN NUMBER DEFAULT 0,
  <atomic_refresh> IN BOOLEAN DEFAULT TRUE,
  <nested> IN BOOLEAN DEFAULT FALSE);
rs

st> is a VARCHAR2 value that specifies the name of a magnetic state.
```

Parameters

st>

is a VARCHAR2 value that specifies the name of a materialized view, or a commaseparated list of materialized view names. The names may be schema-qualified.

<tab>

<tab> is a table of DBMS_UTILITY.UNCL_ARRAY values that specify the name (or names) of a materialized view.

<method>

<method> is a VARCHAR2 value that specifies the refresh method that will be applied to the specified view (or views). The only supported method is C; this performs a complete refresh of the view.

<rollback_seg>

<rollback_seg> is accepted for compatibility and ignored. The default is NULL .

<push_deferred_rpc>

<push_deferred_rpc> is accepted for compatibility and ignored. The default is TRUE .

<refresh_after_errors>

<refresh_after_errors> is accepted for compatibility and ignored. The default is FALSE .

<purge_option>

<purge_option> is accepted for compatibility and ignored. The default is 1 .

<parallelism>

<parallelism> is accepted for compatibility and ignored. The default is 0 .

<heap_size> IN NUMBER DEFAULT 0 ,

<heap_size> is accepted for compatibility and ignored. The default is 0 .

<atomic_refresh>

<atomic_refresh> is accepted for compatibility and ignored. The default is TRUE.

<nested>

<nested> is accepted for compatibility and ignored. The default is FALSE .

Examples

The following example uses DBMS_MVIEW.REFRESH to perform a COMPLETE refresh on the public.emp_view materialized view:

```
EXEC DBMS_MVIEW.REFRESH(list => 'public.emp_view', method => 'C');
```

5.3.8.3 REFRESH_ALL_MVIEWS

Use the REFRESH_ALL_MVIEWS procedure to refresh any materialized views that have not been refreshed since the table or view on which the view depends has been modified. The signature is:

```
REFRESH_ALL_MVIEWS(
    <number_of_failures> OUT BINARY_INTEGER,
    <method< IN VARCHAR2 DEFAULT NULL,</pre>
   <rollback_seg> IN VARCHAR2 DEFAULT NULL,
   <refresh_after_errors> IN BOOLEAN DEFAULT FALSE,
```

<atomic_refresh> IN BOOLEAN DEFAULT TRUE);

Parameters

```
<number_of_failures>
```

<number_of_failures> is a BINARY_INTEGER that specifies the number of failures that occurred during the refresh operation.

<method>

<method> is a VARCHAR2 value that specifies the refresh method that will be applied to the specified view (or views). The only supported method is C; this performs a complete refresh of the view.

```
<rollback_seg>
```

<rollback_seq> is accepted for compatibility and ignored. The default is NULL .

```
<refresh after errors>
```

<refresh_after_errors> is accepted for compatibility and ignored. The default is FALSE .

```
<atomic refresh>
```

<atomic_refresh> is accepted for compatibility and ignored. The default is TRUE.

Examples

The following example performs a COMPLETE refresh on all materialized views:

```
DECLARE
  errors INTEGER;
  DBMS_MVIEW.REFRESH_ALL_MVIEWS(errors, method => 'C');
END;
Upon completion, errors contains the number of failures.
```

179

5.3.8.4 REFRESH DEPENDENT

Use the REFRESH_DEPENDENT procedure to refresh all material views that are dependent on the views specified in the call to the procedure. You can specify a comma-separated list or provide the view names in a table of DBMS_UTILITY.UNCL_ARRAY values.

Use the first form of the procedure to refresh all material views that are dependent on the views specified in a comma-separated list:

REFRESH_DEPENDENT(

```
<number_of_failures> OUT BINARY_INTEGER,
to IN VARCHAR2,
<method> IN VARCHAR2 DEFAULT NULL,
<rollback_seg> IN VARCHAR2 DEFAULT NULL
<refresh_after_errors> IN BOOLEAN DEFAULT FALSE,
<atomic_refresh> IN BOOLEAN DEFAULT TRUE,
<nested> IN BOOLEAN DEFAULT FALSE);
```

Use the second form of the procedure to refresh all material views that are dependent on the views specified in a table of DBMS_UTILITY.UNCL_ARRAY values:

REFRESH_DEPENDENT(

```
<number_of_failures> OUT BINARY_INTEGER,
<tab> IN DBMS_UTILITY.UNCL_ARRAY,
<method> IN VARCHAR2 DEFAULT NULL,
<rollback_seg> IN VARCHAR2 DEFAULT NULL,
<refresh_after_errors> IN BOOLEAN DEFAULT FALSE,
<atomic_refresh> IN BOOLEAN DEFAULT TRUE,
<nested> IN BOOLEAN DEFAULT FALSE);
```

Parameters

```
<number_of_failures>
```

<number_of_failures> is a BINARY_INTEGER that contains the number of failures that occurred during the refresh operation.

t>

is a VARCHAR2 value that specifies the name of a materialized view, or a commaseparated list of materialized view names. The names may be schema-qualified.

<tab>

<tab> is a table of DBMS_UTILITY.UNCL_ARRAY values that specify the name (or names) of a materialized view.

<method>

<method> is a VARCHAR2 value that specifies the refresh method that will be applied to the specified view (or views). The only supported method is C; this performs a complete refresh of the view.

Examples

The following example performs a COMPLETE refresh on all materialized views dependent on a materialized view named emp_view that resides in the public schema:

```
DECLARE
    errors INTEGER;
BEGIN
    DBMS_MVIEW.REFRESH_DEPENDENT(errors, list => 'public.emp_view',
    method =>
'C');
END;
Upon completion, errors contains the number of failures.
```

5.3.9 DBMS_OUTPUT

The DBMS_OUTPUT package provides the capability to send messages (lines of text) to a message buffer, or get messages from the message buffer. A message buffer is local to a single session. Use the DBMS_PIPE package to send messages between sessions.

The procedures and functions available in the DBMS_OUTPUT package are listed in the following table.

Function/Procedure	Return Type	Description
DISABLE	n/a	Disable the capability to send and receive messa
<pre>ENABLE(<buffer_size>)</buffer_size></pre>	n/a	Enable the capability to send and receive messa
<pre>GET_LINE(<line> OUT, <status> OUT)</status></line></pre>	n/a	Get a line from the message buffer.
<pre>GET_LINES(<lines> OUT, <numlines> IN OUT)</numlines></lines></pre>	n/a	Get multiple lines from the message buffer.
NEW_LINE	n/a	Puts an end-of-line character sequence.
<pre>PUT(<item>)</item></pre>	n/a	Puts a partial line without an end-of-line characte
<pre>PUT_LINE(<item>)</item></pre>	n/a	Puts a complete line with an end-of-line character
SERVEROUTPUT(<stdout>)</stdout>	n/a	Direct messages from PUT, PUT_LINE, or

The following table lists the public variables available in the DBMS_OUTPUT package.

Public Variables	Data Type	Value	Description
chararr	TABLE		For message lines.

CHARARR

The CHARARR is for storing multiple message lines.

TYPE chararr IS TABLE OF VARCHAR2(32767) INDEX BY BINARY_INTEGER; DBMS_OUTPUT_DISABLE

DISABLE

The DISABLE procedure clears out the message buffer. Any messages in the buffer at the time the DISABLE procedure is executed will no longer be accessible. Any messages subsequently sent with the PUT, PUT_LINE, or NEW_LINE procedures are discarded. No error is returned to the sender when the PUT, PUT_LINE, or NEW_LINE procedures are executed and messages have been disabled.

Use the ENABLE procedure or SERVEROUTPUT(TRUE) procedure to re-enable the sending and receiving of messages.

DISABLE

Examples

This anonymous block disables the sending and receiving messages in the current session.

BEGIN

```
DBMS_OUTPUT.DISABLE;
END;
DBMS_OUTPUT_ENABLE
```

ENABLE

The ENABLE procedure enables the capability to send messages to the message buffer or retrieve messages from the message buffer. Running SERVEROUTPUT(TRUE) also implicitly performs the ENABLE procedure.

The destination of a message sent with PUT, PUT_LINE, or NEW_LINE depends upon the state of SERVEROUTPUT.

- If the last state of SERVEROUTPUT is TRUE, the message goes to standard output of the command line.
- If the last state of SERVEROUTPUT is FALSE, the message goes to the message buffer.

```
ENABLE [ (<buffer_size> INTEGER) ]
```

Parameter

```
<buffer_size>
```

Maximum length of the message buffer in bytes. If a <buffer_size> of less than 2000 is specified, the buffer size is set to 2000.

Examples

The following anonymous block enables messages. Setting SERVEROUTPUT(TRUE) forces them to standard output.

```
BEGIN
   DBMS_OUTPUT.ENABLE;
   DBMS_OUTPUT.SERVEROUTPUT(TRUE);
   DBMS_OUTPUT.PUT_LINE('Messages enabled');
END;
```

Messages enabled

The same effect could have been achieved by simply using SERVEROUTPUT(TRUE) .

```
BEGIN
    DBMS_OUTPUT.SERVEROUTPUT(TRUE);
    DBMS_OUTPUT.PUT_LINE('Messages enabled');
END;
```

Messages enabled

The following anonymous block enables messages, but setting SERVEROUTPUT(FALSE) directs messages to the message buffer.

```
BEGIN
   DBMS_OUTPUT.ENABLE;
   DBMS_OUTPUT.SERVEROUTPUT(FALSE);
   DBMS_OUTPUT.PUT_LINE('Message sent to buffer');
END;
```

GET_LINE

The GET_LINE procedure provides the capability to retrieve a line of text from the message buffer. Only text that has been terminated by an end-of-line character sequence is retrieved – that is complete lines generated using PUT_LINE, or by a series of PUT calls followed by a NEW_LINE call.

```
GET_LINE(<line> OUT VARCHAR2, <status> OUT INTEGER)
```

Parameters

line>

Variable receiving the line of text from the message buffer.

<status>

0 if a line was returned from the message buffer, 1 if there was no line to return.

Examples

The following anonymous block writes the emp table out to the message buffer as a comma-delimited string for each row.

```
EXEC DBMS_OUTPUT.SERVEROUTPUT(FALSE);
```

The following anonymous block reads the message buffer and inserts the messages written by the prior example into a table named messages . The rows in messages are then displayed.

```
BFGTN
    DBMS_OUTPUT.GET_LINE(v_line,v_status);
    WHILE v_status = 0 LOOP
         INSERT INTO messages VALUES(v_status, v_line);
        DBMS_OUTPUT.GET_LINE(v_line,v_status);
    END LOOP;
END;
SELECT msg FROM messages;
                                 msg
 7369, SMITH, CLERK, 7902, 17-DEC-80 00:00:00, 800.00, 20
 7499, ALLEN, SALESMAN, 7698, 20-FEB-81 00:00:00, 1600.00, 300.00, 30
 7521, WARD, SALESMAN, 7698, 22-FEB-81 00:00:00, 1250.00, 500.00, 30
 7566, JONES, MANAGER, 7839, 02-APR-81 00:00:00, 2975.00, 20
 7654, MARTIN, SALESMAN, 7698, 28-SEP-81 00:00:00, 1250.00, 1400.00, 30
 7698, BLAKE, MANAGER, 7839, 01-MAY-81 00:00:00, 2850.00, 30
 7782, CLARK, MANAGER, 7839, 09-JUN-81 00:00:00, 2450.00, 10
 7788, SCOTT, ANALYST, 7566, 19-APR-87 00:00:00, 3000.00, 20
 7839, KING, PRESIDENT, 17-NOV-81 00:00:00,5000.00, 10
 7844, TURNER, SALESMAN, 7698, 08-SEP-81 00:00:00, 1500.00, 0.00, 30
 7876, ADAMS, CLERK, 7788, 23-MAY-87 00:00:00, 1100.00, ,20
 7900, JAMES, CLERK, 7698, 03-DEC-81 00:00:00, 950.00, 30
 7902, FORD, ANALYST, 7566, 03-DEC-81 00:00:00, 3000.00, 20
 7934, MILLER, CLERK, 7782, 23-JAN-82 00:00:00, 1300.00, 10
(14 rows)
```

GET_LINES

The GET_LINES procedure provides the capability to retrieve one or more lines of text from the message buffer into a collection. Only text that has been terminated by an end-of-line character sequence is retrieved – that is complete lines generated using PUT_LINE, or by a series of PUT calls followed by a NEW_LINE call.

```
GET_LINES(<lines> OUT CHARARR, <numlines> IN OUT INTEGER)
```

Parameters

lines>

Table receiving the lines of text from the message buffer. See CHARARR for a description of

<numlines> IN

Number of lines to be retrieved from the message buffer.

```
<numlines> OUT
```

Actual number of lines retrieved from the message buffer. If the output value of <numlines> is less than the input value, then there are no more lines left in the message buffer.

Examples

The following example uses the GET_LINES procedure to store all rows from the emp table that were placed on the message buffer, into an array.

```
FOR i IN emp_cur LOOP
        v_emprec := i.empno || ',' || i.ename || ',' || i.job || ',' ||
             NVL(LTRIM(TO_CHAR(i.mgr,'9999')),'') || ',' || i.hiredate ||
             ',' || i.sal || ',' ||
             NVL(LTRIM(TO_CHAR(i.comm, '9990.99')), '') || ',' || i.deptno;
        DBMS_OUTPUT.PUT_LINE(v_emprec);
    END LOOP;
END;
DECLARE
                     DBMS_OUTPUT.CHARARR;
    v_lines
    v_numlines
                     INTEGER := 14;
                     INTEGER := 0;
    v_status
BEGIN
    DBMS_OUTPUT.GET_LINES(v_lines,v_numlines);
    FOR i IN 1..v_numlines LOOP
        INSERT INTO messages VALUES(v_numlines, v_lines(i));
    END LOOP;
END;
SELECT msq FROM messages;
                                 msa
 7369, SMITH, CLERK, 7902, 17-DEC-80 00:00:00, 800.00, 20
 7499, ALLEN, SALESMAN, 7698, 20-FEB-81 00:00:00, 1600.00, 300.00, 30
 7521, WARD, SALESMAN, 7698, 22-FEB-81 00:00:00, 1250.00, 500.00, 30
 7566, JONES, MANAGER, 7839, 02-APR-81 00:00:00, 2975.00, 20
 7654, MARTIN, SALESMAN, 7698, 28-SEP-81 00:00:00, 1250.00, 1400.00, 30
 7698, BLAKE, MANAGER, 7839, 01-MAY-81 00:00:00, 2850.00, 30
 7782, CLARK, MANAGER, 7839, 09-JUN-81 00:00:00, 2450.00, 10
 7788, SCOTT, ANALYST, 7566, 19-APR-87 00:00:00, 3000.00, 20
 7839,KING,PRESIDENT,,17-NOV-81 00:00:00,5000.00,,10
 7844, TURNER, SALESMAN, 7698, 08-SEP-81 00:00:00, 1500.00, 0.00, 30
 7876, ADAMS, CLERK, 7788, 23-MAY-87 00:00:00, 1100.00, ,20
 7900, JAMES, CLERK, 7698, 03-DEC-81 00:00:00, 950.00, 30
 7902, FORD, ANALYST, 7566, 03-DEC-81 00:00:00, 3000.00, 20
 7934, MILLER, CLERK, 7782, 23-JAN-82 00:00:00, 1300.00, 10
(14 rows)
```

NEW LINE

The NEW_LINE procedure writes an end-of-line character sequence in the message buffer.

NEW_LINE

Parameter

The NEW_LINE procedure expects no parameters.

DBMS_OUTPUT_PUT

PUT

The PUT procedure writes a string to the message buffer. No end-of-line character sequence is written at the end of the string. Use the NEW_LINE procedure to add an end-of-line character sequence.

```
PUT(<item> VARCHAR2)
```

Parameter

<item>

Text written to the message buffer.

Examples

The following example uses the PUT procedure to display a comma-delimited list of employees from the emp table.

```
DECLARE
    CURSOR emp_cur IS SELECT * FROM emp ORDER BY empno;
BEGIN
    FOR i IN emp_cur LOOP
        DBMS_OUTPUT.PUT(i.empno);
        DBMS_OUTPUT.PUT(',');
        DBMS_OUTPUT.PUT(i.ename);
        DBMS_OUTPUT.PUT(',');
        DBMS_OUTPUT.PUT(i.job);
        DBMS_OUTPUT.PUT(',');
        DBMS_OUTPUT.PUT(i.mgr);
        DBMS_OUTPUT.PUT(',');
        DBMS_OUTPUT.PUT(i.hiredate);
        DBMS_OUTPUT.PUT(',');
        DBMS_OUTPUT.PUT(i.sal);
        DBMS_OUTPUT.PUT(',');
        DBMS_OUTPUT.PUT(i.comm);
        DBMS_OUTPUT.PUT(',');
        DBMS_OUTPUT.PUT(i.deptno);
        DBMS_OUTPUT.NEW_LINE;
    END LOOP;
END;
7369, SMITH, CLERK, 7902, 17-DEC-80 00:00:00, 800.00, 20
7499, ALLEN, SALESMAN, 7698, 20-FEB-81 00:00:00, 1600.00, 300.00, 30
7521, WARD, SALESMAN, 7698, 22-FEB-81 00:00:00, 1250.00, 500.00, 30
7566, JONES, MANAGER, 7839, 02-APR-81 00:00:00, 2975.00, 20
7654, MARTIN, SALESMAN, 7698, 28-SEP-81 00:00:00, 1250.00, 1400.00, 30
7698, BLAKE, MANAGER, 7839, 01-MAY-81 00:00:00, 2850.00, 30
7782, CLARK, MANAGER, 7839, 09-JUN-81 00:00:00, 2450.00, 10
7788, SCOTT, ANALYST, 7566, 19-APR-87 00:00:00, 3000.00, 20
7839,KING,PRESIDENT,,17-NOV-81 00:00:00,5000.00,,10
7844, TURNER, SALESMAN, 7698, 08-SEP-81 00:00:00, 1500.00, 0.00, 30
7876, ADAMS, CLERK, 7788, 23-MAY-87 00:00:00, 1100.00, 20
7900, JAMES, CLERK, 7698, 03-DEC-81 00:00:00, 950.00, 30
7902, FORD, ANALYST, 7566, 03-DEC-81 00:00:00, 3000.00, 20
7934, MILLER, CLERK, 7782, 23-JAN-82 00:00:00, 1300.00, 10
DBMS_OUTPUT_PUT_LINE
```

PUT LINE

The PUT_LINE procedure writes a single line to the message buffer including an end-of-line character sequence.

```
PUT_LINE(<item> VARCHAR2)
```

Parameter

<item>

Text to be written to the message buffer.

Examples

The following example uses the PUT_LINE procedure to display a comma-delimited list of employees from the emp table.

```
DECLARE

v_emprec VARCHAR2(120);
```

```
CURSOR emp_cur IS SELECT * FROM emp ORDER BY empno;
BEGIN
    FOR i IN emp_cur LOOP
        v_emprec := i.empno || ',' || i.ename || ',' || i.job || ',' ||
             NVL(LTRIM(TO_CHAR(i.mgr,'9999')),'') || ',' || i.hiredate ||
             ',' || i.sal || ',' ||
             NVL(LTRIM(TO_CHAR(i.comm, '9990.99')),'') || ',' || i.deptno;
        DBMS_OUTPUT.PUT_LINE(v_emprec);
    END LOOP;
END;
7369, SMITH, CLERK, 7902, 17-DEC-80 00:00:00, 800.00, 20
7499, ALLEN, SALESMAN, 7698, 20-FEB-81 00:00:00, 1600.00, 300.00, 30
7521, WARD, SALESMAN, 7698, 22-FEB-81 00:00:00, 1250.00, 500.00, 30
7566, JONES, MANAGER, 7839, 02-APR-81 00:00:00, 2975.00, ,20
7654, MARTIN, SALESMAN, 7698, 28-SEP-81 00:00:00, 1250.00, 1400.00, 30
7698, BLAKE, MANAGER, 7839, 01-MAY-81 00:00:00, 2850.00, 30
7782, CLARK, MANAGER, 7839, 09-JUN-81 00:00:00, 2450.00, 10
7788, SCOTT, ANALYST, 7566, 19-APR-87 00:00:00, 3000.00, 20
7839, KING, PRESIDENT, 17-NOV-81 00:00:00,5000.00, 10
7844, TURNER, SALESMAN, 7698, 08-SEP-81 00:00:00, 1500.00, 0.00, 30
7876, ADAMS, CLERK, 7788, 23-MAY-87 00:00:00, 1100.00, 20
7900, JAMES, CLERK, 7698, 03-DEC-81 00:00:00, 950.00, 30
7902, FORD, ANALYST, 7566, 03-DEC-81 00:00:00, 3000.00, 20
7934, MILLER, CLERK, 7782, 23-JAN-82 00:00:00, 1300.00, 10
```

SERVEROUTPUT

The SERVEROUTPUT procedure provides the capability to direct messages to standard output of the command line or to the message buffer. Setting SERVEROUTPUT(TRUE) also performs an implicit execution of ENABLE

The default setting of SERVEROUTPUT is implementation dependent. For example, in Oracle SQLPlus, SERVEROUTPUT(FALSE) is the default. In PSQL, SERVEROUTPUT(TRUE) is the default. Also note that in Oracle SQLPlus, this setting is controlled using the SQL*Plus SET command, not by a stored procedure as implemented in Advanced Server.

```
SERVEROUTPUT(<stdout> BOOLEAN)
```

Parameter

<stdout>

Set to TRUE if subsequent PUT, PUT_LINE, or NEW_LINE commands are to send text directly to standard output of the command line. Set to FALSE if text is to be sent to the message buffer.

Examples

The following anonymous block sends the first message to the command line and the second message to the message buffer.

```
BEGIN
```

```
DBMS_OUTPUT.SERVEROUTPUT(TRUE);
DBMS_OUTPUT.PUT_LINE('This message goes to the command line');
DBMS_OUTPUT.SERVEROUTPUT(FALSE);
DBMS_OUTPUT.PUT_LINE('This message goes to the message buffer');
END;
```

This message goes to the command line

If within the same session, the following anonymous block is executed, the message stored in the message buffer from the prior example is flushed and displayed on the command line as well as the new message.

BEGIN

```
DBMS_OUTPUT.SERVEROUTPUT(TRUE);
DBMS_OUTPUT.PUT_LINE('Flush messages from the buffer');
END;
This message goes to the message buffer
Flush messages from the buffer
```

5.3.10.0 DBMS_PIPE

The DBMS_PIPE package provides the capability to send messages through a pipe within or between sessions connected to the same database cluster.

The procedures and functions available in the DBMS_PIPE package are listed in the following table:

Function/Procedure	Return Type	Description
<pre>CREATE_PIPE(<pipename> [, <maxpipesize>] [, <private>])</private></maxpipesize></pipename></pre>	INTEGER	Explicitly create a private
NEXT_ITEM_TYPE	INTEGER	Determine the data type o
PACK_MESSAGE(<item>)</item>	n/a	Place <item> in the se</item>
<pre>PURGE(<pipename>)</pipename></pre>	n/a	Remove unreceived mess
<pre>RECEIVE_MESSAGE(<pipename> [, <timeout>])</timeout></pipename></pre>	INTEGER	Get a message from a spe
<pre>REMOVE_PIPE(<pipename>)</pipename></pre>	INTEGER	Delete an explicitly created
RESET_BUFFER	n/a	Reset the local message b
<pre>SEND_MESSAGE(<pipename> [, <timeout>] [, <maxpipesize>])</maxpipesize></timeout></pipename></pre>	INTEGER	Send a message on a pipe
UNIQUE_SESSION_NAME	VARCHAR2	Obtain a unique session n
<pre>UNPACK_MESSAGE(<item> OUT)</item></pre>	n/a	Retrieve the next data iten

Pipes are categorized as implicit or explicit. An *implicit pipe* is created if a reference is made to a pipe name that was not previously created by the CREATE_PIPE function. For example, if the SEND_MESSAGE function is executed using a non-existent pipe name, a new implicit pipe is created with that name. An *explicit pipe* is created using the CREATE_PIPE function whereby the first parameter specifies the pipe name for the new pipe.

Pipes are also categorized as private or public. A *private pipe* can only be accessed by the user who created the pipe. Even a superuser cannot access a private pipe that was created by another user. A *public pipe* can be accessed by any user who has access to the DBMS_PIPE package.

A public pipe can only be created by using the CREATE_PIPE function with the third parameter set to FALSE.

The CREATE_PIPE function can be used to create a private pipe by setting the third parameter to TRUE or by omitting the third parameter. All implicit pipes are private.

The individual data items or "lines" of a message are first built-in a *local message buffer*, unique to the current session. The PACK_MESSAGE procedure builds the message in the session's local message buffer. The SEND_MESSAGE function is then used to send the message through the pipe.

Receipt of a message involves the reverse operation. The RECEIVE_MESSAGE function is used to get a message from the specified pipe. The message is written to the session's local message buffer. The UNPACK_MESSAGE procedure is then used to transfer the message data items from the message buffer to program variables. If a pipe contains multiple messages, (first-in-first-out) order.

Each session maintains separate message buffers for messages created with the PACK_MESSAGE procedure and messages retrieved by the RECEIVE_MESSAGE function. Thus messages can be both built and received in the same session. However, if consecutive RECEIVE_MESSAGE calls are made, only the message from the last RECEIVE_MESSAGE call will be preserved in the local message buffer.

5.3.10.1 CREATE PIPE

The CREATE_PIPE function creates an explicit public pipe or an explicit private pipe with a specified name.

```
<status> INTEGER CREATE_PIPE(<pipename> VARCHAR2
   [, <maxpipesize> INTEGER ] [, <private> BOOLEAN ])
```

Parameters

```
<pipename>
```

Name of the pipe.

<maxpipesize>

Maximum capacity of the pipe in bytes. Default is 8192 bytes.

<private>

Create a public pipe if set to FALSE. Create a private pipe if set to TRUE. This is the default.

<status>

Status code returned by the operation. 0 indicates successful creation.

Examples

The following example creates a private pipe named messages:

```
DECLARE
                    INTEGER;
    v_status
BEGIN
    v_status := DBMS_PIPE.CREATE_PIPE('messages');
    DBMS_OUTPUT.PUT_LINE('CREATE_PIPE status: ' || v_status);
CREATE_PIPE status: 0
The following example creates a public pipe named mailbox:
DECLARE
    v status
                    INTEGER;
BEGIN
    v_status := DBMS_PIPE.CREATE_PIPE('mailbox',8192,FALSE);
    DBMS_OUTPUT.PUT_LINE('CREATE_PIPE status: ' || v_status);
END:
CREATE_PIPE status: 0
```

5.3.10.2 NEXT ITEM TYPE

The NEXT_ITEM_TYPE function returns an integer code identifying the data type of the next data item in a message that has been retrieved into the session's local message buffer. As each item is moved off of the local message buffer with the UNPACK_MESSAGE procedure, the NEXT_ITEM_TYPE function will return the data type code for the next available item. A code of 0 is returned when there are no more items left in the message.

```
<typecode> INTEGER NEXT_ITEM_TYPE
```

Parameters

<typecode>

Code identifying the data type of the next data item as shown in the following table.

Type Code	Data Type
0	No more data items
9	NUMBER
11	VARCHAR2

13	DATE	
10	DAIL	
23	RAW	
20	1 17 X V	

Note

The type codes list in the table are not compatible with Oracle databases. Oracle assigns a different numbering sequence to the data types.

Examples

The following example shows a pipe packed with a NUMBER item, a VARCHAR2 item, a DATE item, and a RAW item. A second anonymous block then uses the NEXT_ITEM_TYPE function to display the type code of each item.

```
DECLARE
   v_number
                  NUMBER := 123;
   v_varchar
                  VARCHAR2(20) := 'Character data';
                  DATE := SYSDATE;
   v_date
                  RAW(4) := '21222324';
   v_raw
                  INTEGER;
   v_status
BEGIN
   DBMS_PIPE.PACK_MESSAGE(v_number);
   DBMS_PIPE.PACK_MESSAGE(v_varchar);
   DBMS_PIPE.PACK_MESSAGE(v_date);
   DBMS_PIPE.PACK_MESSAGE(v_raw);
   v_status := DBMS_PIPE.SEND_MESSAGE('datatypes');
   DBMS_OUTPUT.PUT_LINE('SEND_MESSAGE status: ' || v_status);
EXCEPTION
   WHEN OTHERS THEN
       DBMS_OUTPUT.PUT_LINE('SQLERRM: ' || SQLERRM);
       DBMS_OUTPUT.PUT_LINE('SQLCODE: ' || SQLCODE);
END;
SEND_MESSAGE status: 0
DECLARE
   v_number
                  NUMBER;
   v_varchar
                  VARCHAR2(20);
   v_date
                  DATE;
                  TIMESTAMP;
   v_timestamp
                  RAW(4);
   v_raw
   v_status
                  INTEGER;
BEGIN
   v_status := DBMS_PIPE.RECEIVE_MESSAGE('datatypes');
   DBMS_OUTPUT.PUT_LINE('RECEIVE_MESSAGE status: ' || v_status);
   DBMS_OUTPUT.PUT_LINE('-----');
   v_status := DBMS_PIPE.NEXT_ITEM_TYPE;
   DBMS_OUTPUT.PUT_LINE('NEXT_ITEM_TYPE: ' || v_status);
   DBMS_PIPE.UNPACK_MESSAGE(v_number);
   DBMS_OUTPUT.PUT_LINE('NUMBER Item : ' || v_number);
   DBMS_OUTPUT.PUT_LINE('-----');
   v_status := DBMS_PIPE.NEXT_ITEM_TYPE;
   DBMS_OUTPUT.PUT_LINE('NEXT_ITEM_TYPE: ' || v_status);
   DBMS_PIPE.UNPACK_MESSAGE(v_varchar);
   DBMS_OUTPUT.PUT_LINE('VARCHAR2 Item : ' || v_varchar);
   DBMS_OUTPUT.PUT_LINE('-----');
   v_status := DBMS_PIPE.NEXT_ITEM_TYPE;
   DBMS_OUTPUT.PUT_LINE('NEXT_ITEM_TYPE: ' || v_status);
```

```
DBMS_PIPE.UNPACK_MESSAGE(v_date);
   DBMS_OUTPUT.PUT_LINE('DATE Item : ' || v_date);
   DBMS_OUTPUT.PUT_LINE('-----');
   v_status := DBMS_PIPE.NEXT_ITEM_TYPE;
   DBMS_OUTPUT.PUT_LINE('NEXT_ITEM_TYPE: ' || v_status);
   DBMS_PIPE.UNPACK_MESSAGE(v_raw);
   DBMS_OUTPUT.PUT_LINE('RAW Item : ' || v_raw);
   DBMS_OUTPUT.PUT_LINE('-----');
   v_status := DBMS_PIPE.NEXT_ITEM_TYPE;
   DBMS_OUTPUT.PUT_LINE('NEXT_ITEM_TYPE: ' || v_status);
   DBMS_OUTPUT.PUT_LINE('-----');
EXCEPTION
   WHEN OTHERS THEN
      DBMS_OUTPUT.PUT_LINE('SQLERRM: ' || SQLERRM);
      DBMS_OUTPUT.PUT_LINE('SQLCODE: ' || SQLCODE);
END;
RECEIVE_MESSAGE status: 0
_____
NEXT ITEM TYPE: 9
NUMBER Item : 123
NEXT_ITEM_TYPE: 11
VARCHAR2 Item : Character data
NEXT_ITEM_TYPE: 13
DATE Item : 02-0CT-07 11:11:43
NEXT_ITEM_TYPE: 23
RAW Item : 21222324
NEXT_ITEM_TYPE: 0
```

5.3.10.3 PACK MESSAGE

The PACK_MESSAGE procedure places an item of data in the session's local message buffer. PACK_MESSAGE must be executed at least once before issuing a SEND_MESSAGE call.

```
> PACK_MESSAGE(<item> { DATE | NUMBER | VARCHAR2 | RAW })
```

Use the UNPACK_MESSAGE procedure to obtain data items once the message is retrieved using a RECEIVE_MESSAGE call.

Parameters

<item>

An expression evaluating to any of the acceptable parameter data types. The value is added to the session's local message buffer.

5.3.10.4 PURGE

The PURGE procedure removes the unreceived messages from a specified implicit pipe.

PURGE(<pipename> VARCHAR2)

Use the REMOVE_PIPE function to delete an explicit pipe.

```
Parameter
```

<pipename>

```
Name of the pipe.
Examples
Two messages are sent on a pipe:
DECLARE
    v_status
                     INTEGER;
BEGIN
    DBMS_PIPE.PACK_MESSAGE('Message #1');
    v_status := DBMS_PIPE.SEND_MESSAGE('pipe');
    DBMS_OUTPUT.PUT_LINE('SEND_MESSAGE status: ' || v_status);
    DBMS_PIPE.PACK_MESSAGE('Message #2');
    v_status := DBMS_PIPE.SEND_MESSAGE('pipe');
    DBMS_OUTPUT.PUT_LINE('SEND_MESSAGE status: ' || v_status);
END;
SEND_MESSAGE status: 0
SEND_MESSAGE status: 0
Receive the first message and unpack it:
DECLARE
                     VARCHAR2(80);
    v_item
    v_status
                     INTEGER;
BEGIN
    v_status := DBMS_PIPE.RECEIVE_MESSAGE('pipe',1);
    DBMS_OUTPUT.PUT_LINE('RECEIVE_MESSAGE status: ' || v_status);
    DBMS_PIPE.UNPACK_MESSAGE(v_item);
    DBMS_OUTPUT.PUT_LINE('Item: ' || v_item);
END;
RECEIVE_MESSAGE status: 0
Item: Message #1
Purge the pipe:
EXEC DBMS_PIPE.PURGE('pipe');
Try to retrieve the next message. The RECEIVE_MESSAGE call returns status code 1 indicating it timed out
because no message was available.
DECLARE
    v_item
                     VARCHAR2(80);
    v_status
                     INTEGER;
BEGIN
    v_status := DBMS_PIPE.RECEIVE_MESSAGE('pipe',1);
    DBMS_OUTPUT.PUT_LINE('RECEIVE_MESSAGE status: ' || v_status);
END;
RECEIVE_MESSAGE status: 1
```

5.3.10.5 RECEIVE_MESSAGE

```
The RECEIVE_MESSAGE function obtains a message from a specified pipe.
```

```
<status> INTEGER RECEIVE_MESSAGE(cpipename> VARCHAR2
[, <timeout> INTEGER ])
```

Parameters

```
<pipename>
```

Name of the pipe.

<timeout>

Wait time (seconds). Default is 86400000 (1000 days).

<status>

Status code returned by the operation.

The possible status codes are:

Status Code	Description Success
1	Time out
2	Message too large .for the buffer

5.3.10.6 REMOVE PIPE

The REMOVE_PIPE function deletes an explicit private or explicit public pipe.

```
<status> INTEGER REMOVE_PIPE(<pipename> VARCHAR2)
```

Use the REMOVE_PIPE function to delete explicitly created pipes – i.e., pipes created with the CREATE_PIPE function.

Parameters

<pipename>

Name of the pipe.

<status>

Status code returned by the operation. A status code of 0 is returned even if the named pipe is non-existent.

Examples

Two messages are sent on a pipe:

Receive the first message and unpack it:

```
DECLARE
                     VARCHAR2(80);
    v_item
    v_status
                     INTEGER;
BEGIN
    v_status := DBMS_PIPE.RECEIVE_MESSAGE('pipe',1);
    DBMS_OUTPUT.PUT_LINE('RECEIVE_MESSAGE status: ' || v_status);
    DBMS_PIPE.UNPACK_MESSAGE(v_item);
    DBMS_OUTPUT.PUT_LINE('Item: ' || v_item);
END;
RECEIVE_MESSAGE status: 0
Item: Message #1
Remove the pipe:
SELECT DBMS_PIPE.REMOVE_PIPE('pipe') FROM DUAL;
remove_pipe
_____
          0
(1 row)
Try to retrieve the next message. The RECEIVE_MESSAGE call returns status code 1 indicating it timed out
because the pipe had been deleted.
DECLARE
    v_{item}
                     VARCHAR2(80);
                     INTEGER;
    v_status
    v_status := DBMS_PIPE.RECEIVE_MESSAGE('pipe',1);
    DBMS_OUTPUT.PUT_LINE('RECEIVE_MESSAGE status: ' || v_status);
END;
RECEIVE_MESSAGE status: 1
```

5.3.10.7 RESET BUFFER

The RESET_BUFFER procedure resets a "pointer" to the session's local message buffer back to the beginning of the buffer. This has the effect of causing subsequent PACK_MESSAGE calls to overwrite any data items that existed in the message buffer prior to the RESET_BUFFER call.

```
RESET_BUFFER
```

Examples

A message to John is written to the local message buffer. It is replaced by a message to Bob by calling RESET_BUFFER . The message is sent on the pipe.

```
DBMS_OUTPUT.PUT_LINE('SEND_MESSAGE status: ' || v_status);
END;
SEND_MESSAGE status: 0
The message to Bob is in the received message.
DECLARE
    v_item
                    VARCHAR2(80);
    v_status
                    INTEGER;
BEGIN
    v_status := DBMS_PIPE.RECEIVE_MESSAGE('pipe',1);
    DBMS_OUTPUT.PUT_LINE('RECEIVE_MESSAGE status: ' || v_status);
    DBMS_PIPE.UNPACK_MESSAGE(v_item);
    DBMS_OUTPUT.PUT_LINE('Item: ' || v_item);
    DBMS_PIPE.UNPACK_MESSAGE(v_item);
    DBMS_OUTPUT.PUT_LINE('Item: ' || v_item);
END;
RECEIVE_MESSAGE status: 0
Item: Hi, Bob
Item: Can you attend a meeting at 9:30, tomorrow?
```

5.3.10.8 SEND_MESSAGE

The SEND_MESSAGE function sends a message from the session's local message buffer to the specified pipe.

```
<status> SEND_MESSAGE(<pipename> VARCHAR2 [, <timeout> INTEGER ]
   [, <maxpipesize> INTEGER ])
```

Parameters

<pipename>

Name of the pipe.

<timeout>

Wait time (seconds). Default is 86400000 (1000 days).

<maxpipesize>

Maximum capacity of the pipe in bytes. Default is 8192 bytes.

<status>

Status code returned by the operation.

The possible status codes are:

Status Code	Description
0	Success
1	Time out
3	Function interrupted

5.3.10.9 UNIQUE_SESSION_NAME

The UNIQUE_SESSION_NAME function returns a name, unique to the current session.

<name> VARCHAR2 UNIQUE_SESSION_NAME

Parameters

<name>

Unique session name.

Examples

The following anonymous block retrieves and displays a unique session name.

```
DECLARE
    v_session    VARCHAR2(30);
BEGIN
    v_session := DBMS_PIPE.UNIQUE_SESSION_NAME;
    DBMS_OUTPUT.PUT_LINE('Session Name: ' || v_session);
END;
Session Name: PG$PIPE$5$2752
```

5.3.10.10 UNPACK_MESSAGE

The UNPACK_MESSAGE procedure copies the data items of a message from the local message buffer to a specified program variable. The message must be placed in the local message buffer with the RECEIVE_MESSAGE function before using UNPACK_MESSAGE.

```
> UNPACK_MESSAGE(<item> OUT { DATE | NUMBER | VARCHAR2 | RAW })
Parameter
<item>
```

Type-compatible variable that receives a data item from the local message buffer.

5.3.10.11 Comprehensive Example

The following example uses a pipe as a "mailbox". The procedures to create the mailbox, add a multi-item message to the mailbox (up to three items), and display the full contents of the mailbox are enclosed in a package named, mailbox.

```
CREATE OR REPLACE PACKAGE mailbox
IS
    PROCEDURE create_mailbox;
    PROCEDURE add_message (
        p_mailbox
                    VARCHAR2,
                    VARCHAR2,
        p_item_1
        p_item_2
                    VARCHAR2 DEFAULT 'END',
                    VARCHAR2 DEFAULT 'END'
        p_item_3
    PROCEDURE empty_mailbox (
        p_mailbox
                    VARCHAR2,
        p_waittime INTEGER DEFAULT 10
END mailbox;
CREATE OR REPLACE PACKAGE BODY mailbox
IS
    PROCEDURE create_mailbox
    IS
        v_mailbox
                    VARCHAR2(30);
                    INTEGER;
        v_status
    BEGIN
```

```
v_mailbox := DBMS_PIPE.UNIQUE_SESSION_NAME;
   v_status := DBMS_PIPE.CREATE_PIPE(v_mailbox,1000,FALSE);
   IF v_status = 0 THEN
        DBMS_OUTPUT.PUT_LINE('Created mailbox: ' || v_mailbox);
   ELSE
        DBMS_OUTPUT.PUT_LINE('CREATE_PIPE failed - status: ' ||
            v_status);
    END IF;
END create_mailbox;
PROCEDURE add_message (
   p_mailbox
                VARCHAR2,
                VARCHAR2,
VARCHAR2 DEFAULT 'END'
   p_item_1
   p_item_2
                VARCHAR2 DEFAULT 'END'
   p_item_3
IS
   v_item_cnt INTEGER := 0;
   v_status
                INTEGER;
BEGIN
   DBMS_PIPE.PACK_MESSAGE(p_item_1);
   v_item_cnt := 1;
   IF p_item_2 != 'END' THEN
        DBMS_PIPE.PACK_MESSAGE(p_item_2);
        v_item_cnt := v_item_cnt + 1;
    END IF;
    IF p_item_3 != 'END' THEN
        DBMS_PIPE.PACK_MESSAGE(p_item_3);
        v_item_cnt := v_item_cnt + 1;
   END IF;
   v_status := DBMS_PIPE.SEND_MESSAGE(p_mailbox);
   IF v_status = 0 THEN
        DBMS_OUTPUT.PUT_LINE('Added message with ' || v_item_cnt ||
            ' item(s) to mailbox ' || p_mailbox);
        DBMS_OUTPUT.PUT_LINE('SEND_MESSAGE in add_message failed - ' ||
            'status: ' || v_status);
    END IF;
END add_message;
PROCEDURE empty_mailbox (
   p_mailbox
                VARCHAR2,
   p_waittime INTEGER DEFAULT 10
IS
                INTEGER DEFAULT 0;
   v_msgno
                INTEGER DEFAULT 0;
   v_itemno
   v_item
                VARCHAR2(100);
   v_status
                INTEGER;
BEGIN
    v_status := DBMS_PIPE.RECEIVE_MESSAGE(p_mailbox,p_waittime);
   WHILE v_status = 0 LOOP
        v_msqno := v_msqno + 1;
        DBMS_OUTPUT.PUT_LINE('***** Start message #' || v_msgno ||
             ******');
        BEGIN
            L<sub>00</sub>P
                v_status := DBMS_PIPE.NEXT_ITEM_TYPE;
                EXIT WHEN v_status = 0;
                DBMS_PIPE.UNPACK_MESSAGE(v_item);
                v_itemno := v_itemno + 1;
```

```
DBMS_OUTPUT.PUT_LINE('Item #' || v_itemno || ': ' ||
                         v_item);
                 END LOOP:
                DBMS_OUTPUT.PUT_LINE('****** End message #' || v_msqno ||
                DBMS_OUTPUT.PUT_LINE('*');
                v_{itemno} := 0;
                v_status := DBMS_PIPE.RECEIVE_MESSAGE(p_mailbox,1);
            END;
        END LOOP;
        DBMS_OUTPUT.PUT_LINE('Number of messages received: ' || v_msgno);
        v_status := DBMS_PIPE.REMOVE_PIPE(p_mailbox);
        IF v_status = 0 THEN
            DBMS_OUTPUT.PUT_LINE('Deleted mailbox ' || p_mailbox);
        ELSE
            DBMS_OUTPUT.PUT_LINE('Could not delete mailbox - status: '
                 || v_status);
        END IF;
    END empty_mailbox;
END mailbox;
The following demonstrates the execution of the procedures in mailbox. The first procedure creates a public
pipe using a name generated by the UNIQUE_SESSION_NAME function.
EXEC mailbox.create_mailbox;
Created mailbox: PG$PIPE$13$3940
Using the mailbox name, any user in the same database with access to the mailbox package and
DBMS_PIPE package can add messages:
EXEC mailbox.add_message('PG$PIPE$13$3940','Hi, John','Can you attend a meeting at 3:00, today?',
- Mary');
Added message with 3 item(s) to mailbox PG$PIPE$13$3940
EXEC mailbox.add_message('PG$PIPE$13$3940','Don''t forget to submit your report','Thanks,','-
- Joe');
Added message with 3 item(s) to mailbox PG$PIPE$13$3940
Finally, the contents of the mailbox can be emptied:
EXEC mailbox.empty_mailbox('PG$PIPE$13$3940');
***** Start message #1 *****
Item #1: Hi, John
Item #2: Can you attend a meeting at 3:00, today?
Item #3: -- Marv
***** End message #1 ******
***** Start message #2 *****
Item #1: Don't forget to submit your report
Item #2: Thanks,
Item #3: Joe
***** End message #2 ******
Number of messages received: 2
Deleted mailbox PG$PIPE$13$3940
```

198

5.3.11 DBMS PROFILER

The DBMS_PROFILER package collects and stores performance information about the PL/pgSQL and SPL statements that are executed during a performance profiling session; use the functions and procedures listed below to control the profiling tool.

Function/Procedure	Return Type	D
FLUSH_DATA	Status Code or Exception	FI
<pre>GET_VERSION(<major> OUT, <minor> OUT)</minor></major></pre>	n/a	R
INTERNAL_VERSION_CHECK	Status Code	C
PAUSE_PROFILER	Status Code or Exception	Pa
RESUME_PROFILER	Status Code or Exception	R
<pre>START_PROFILER(<run_comment>, <run_comment1> [, <run_number> OUT])</run_number></run_comment1></run_comment></pre>	Status Code or Exception	St
STOP_PROFILER	Status Code or Exception	St

The functions within the DBMS_PROFILER package return a status code to indicate success or failure; the DBMS_PROFILER procedures raise an exception only if they encounter a failure. The status codes and messages returned by the functions, and the exceptions raised by the procedures are listed in the table below.

Status Code	Message	Exception	Description
-1	error version	version_mismatch	The profiler version and the database are incompatible.
0	success	n/a	The operation completed successfully.
1	error_param	<pre>profiler_error</pre>	The operation received an incorrect parameter.
2	error_io	<pre>profiler_error</pre>	The data flush operation has failed.

FLUSH_DATA

The FLUSH_DATA function/procedure flushes the data collected in the current session without terminating the profiler session. The data is flushed to the tables described in the Advanced Server Performance Features Guide. The function and procedure signatures are:

<status> INTEGER FLUSH_DATA

FLUSH_DATA

Parameter

<status>

Status code returned by the operation.

GET_VERSION

The GET_VERSION procedure returns the version of DBMS_PROFILER. The procedure signature is:

GET_VERSION(<major> OUT INTEGER, <minor> OUT INTEGER)

Parameters

<major>

The major version number of DBMS_PROFILER .

<minor>

The minor version number of DBMS_PROFILER .

INTERNAL VERSION CHECK

The INTERNAL_VERSION_CHECK function confirms that the current version of DBMS_PROFILER will work with the current database. The function signature is:

```
<status> INTEGER INTERNAL_VERSION_CHECK
```

Parameter

<status>

Status code returned by the operation.

PAUSE_PROFILER

The PAUSE_PROFILER function/procedure pauses a profiling session. The function and procedure signatures are:

```
<status> INTEGER PAUSE_PROFILER
PAUSE_PROFILER
```

Parameter

<status>

Status code returned by the operation.

RESUME PROFILER

The RESUME_PROFILER function/procedure pauses a profiling session. The function and procedure signatures are:

```
<status> INTEGER RESUME_PROFILER
RESUME_PROFILER
```

Parameter

<status>

Status code returned by the operation.

START_PROFILER

The START_PROFILER function/procedure starts a data collection session. The function and procedure signatures are:

Parameters

<run_comment>

A user-defined comment for the profiler session. The default value is SYSDATE .

```
<run_comment1>
```

An additional user-defined comment for the profiler session. The default value is ".

<run_number>

The session number of the profiler session.

<status>

Status code returned by the operation.

STOP_PROFILER

The STOP_PROFILER function/procedure stops a profiling session and flushes the performance information to the DBMS_PROFILER tables and view. The function and procedure signatures are:

```
<status> INTEGER STOP_PROFILER
STOP_PROFILER
```

Parameter

<status>

Status code returned by the operation.

Using DBMS_PROFILER

The DBMS_PROFILER package collects and stores performance information about the PL/pgSQL and SPL statements that are executed during a profiling session; you can review the performance information in the tables and views provided by the profiler.

DBMS_PROFILER works by recording a set of performance-related counters and timers for each line of PL/pgSQL or SPL statement that executes within a profiling session. The counters and timers are stored in a table named SYS.PLSQL_PROFILER_DATA. When you complete a profiling session, DBMS_PROFILER will write a row to the performance statistics table for each line of PL/pgSQL or SPL code that executed within the session. For example, if you execute the following function:

```
1 - CREATE OR REPLACE FUNCTION getBalance(acctNumber INTEGER)
2 - RETURNS NUMERIC AS $$
3 - DECLARE
4 - result NUMERIC;
5 - BEGIN
6 - SELECT INTO result balance FROM acct WHERE id = acctNumber;
7 -
8 - IF (result IS NULL) THEN
9 - RAISE INFO 'Balance is null';
10- END IF;
11-
12- RETURN result;
13- END;
14- $$ LANGUAGE 'plpgsql';
```

DBMS_PROFILER adds one PLSQL_PROFILER_DATA entry for each line of code within the <code>getBalance()</code> function (including blank lines and comments). The entry corresponding to the <code>SELECT</code> statement executed exactly one time; and required a very small amount of time to execute. On the other hand, the entry corresponding to the <code>RAISE INFO</code> statement executed once or not at all (depending on the value for the <code>balance column)</code>.

Some of the lines in this function contain no executable code so the performance statistics for those lines will always contain zero values.

To start a profiling session, invoke the DBMS_PROFILER.START_PROFILER function (or procedure). Once you've invoked START_PROFILER, Advanced Server will profile every PL/pgSQL or SPL function, procedure, trigger, or anonymous block that your session executes until you either stop or pause the profiler (by calling STOP_PROFILER or PAUSE_PROFILER).

It is important to note that when you start (or resume) the profiler, the profiler will only gather performance statistics for functions/procedures/triggers that start after the call to START_PROFILER (or RESUME_PROFILER).

While the profiler is active, Advanced Server records a large set of timers and counters in memory; when you invoke the STOP_PROFILER (or FLUSH_DATA) function/procedure, DBMS_PROFILER writes those timers and counters to a set of three tables:

SYS.PLSQL_PROFILER_RAWDATA

Contains the performance counters and timers for each statement executed within the session.

SYS.PLSQL_PROFILER_RUNS

Contains a summary of each run (aggregating the information found in PLSQL_PROFILER_RAWDATA).

SYS.PLSQL_PROFILER_UNITS

Contains a summary of each code unit (function, procedure, trigger, or anonymous block) executed within a session.

In addition, DBMS_PROFILER defines a view, SYS.PLSQL_PROFILER_DATA , which contains a subset of the PLSQL_PROFILER_RAWDATA table.

Please note that a non-superuser may gather profiling information, but may not view that profiling information unless a superuser grants specific privileges on the profiling tables (stored in the SYS schema). This permits a non-privileged user to gather performance statistics without exposing information that the administrator may want to keep secret.

Querying the DBMS PROFILER Tables and View

The following step-by-step example uses DBMS_PROFILER to retrieve performance information for procedures, functions, and triggers included in the sample data distributed with Advanced Server.

1. Open the EDB-PSQL command line, and establish a connection to the Advanced Server database. Use an EXEC statement to start the profiling session:

```
acctg=# EXEC dbms_profiler.start_profiler('profile list_emp');
```

EDB-SPL Procedure successfully completed

Note

(The call to start_profiler() includes a comment that DBMS_PROFILER associates with the profiler session).

2. Then call the list_emp function:

```
acctg=# SELECT list_emp();
INFO: EMPNO
                ENAME
INFO:
INFO:
       7369
                SMITH
INFO:
       7499
                ALLEN
INFO:
       7521
                WARD
INFO:
       7566
                JONES
INFO:
       7654
                MARTIN
INFO:
       7698
                BLAKE
INFO:
                CLARK
       7782
INFO:
       7788
                SCOTT
INFO: 7839
                KING
```

```
INFO: 7844
                TURNER
INFO: 7876
                ADAMS
INFO: 7900
                JAMES
INFO: 7902
                FORD
INFO: 7934
                MILLER
 list_emp
(1 row)
  3. Stop the profiling session with a call to dbms_profiler.stop_profiler:
acctg=# EXEC dbms_profiler.stop_profiler;
EDB-SPL Procedure successfully completed
  4. Start a new session with the dbms_profiler.start_profiler function (followed by a new com-
    ment):
acctg=# EXEC dbms_profiler.start_profiler('profile get_dept_name and
emp_sal_trig');
EDB-SPL Procedure successfully completed
  5. Invoke the get_dept_name function:
acctg=# SELECT get_dept_name(10);
 get_dept_name
 ACCOUNTING
(1 row)
  6. Execute an UPDATE statement that causes a trigger to execute:
acctg=# UPDATE memp SET sal = 500 WHERE empno = 7902;
INFO: Updating employee 7902
INFO: ..Old salary: 3000.00
INFO: ..New salary: 500.00
INFO: ..Raise: -2500.00
INFO: User enterprisedb updated employee(s) on 04-FEB-14
UPDATE 1
  7. Terminate the profiling session and flush the performance information to the profiling tables:
acctg=# EXEC dbms_profiler.stop_profiler;
EDB-SPL Procedure successfully completed
  8. Now, query the plsql_profiler_runs table to view a list of the profiling sessions, arranged by
     runid:
acctg=# SELECT * FROM plsql_profiler_runs;
runid | related_run | run_owner |
                                            run_date
                                                                           run_comment
Irun_total_time | run_system_info | run_comment1 | spare1
-----
               l enterprisedb | 04-FEB-14 09:32:48.874315 | profile list_emp
   2 |
               l enterprisedb | 04-FEB-14 09:41:30.546503 | profile get_dept_name and emp_sal_tri
(2 rows)
  9. Query the plsql_profiler_units table to view the amount of time consumed by each unit (each
    function, procedure, or trigger):
acctg=# SELECT * FROM plsql_profiler_units;
runid | unit_number | unit_type | unit_owner |
                                                                        | unit_timestamp | total
                                                     unit_name
```

```
-----
        16999 | FUNCTION | enterprisedb | list_emp() | 17002 | FUNCTION | enterprisedb | user_audit_trig() |
                                                                     1 |
  2 |
         17000 | FUNCTION | enterprisedb | get_dept_name(p_deptno numeric) |
  2 |
         17004 | FUNCTION | enterprisedb | emp_sal_trig() |
                                                                            1 |
(4 rows)
10. Query the plsql_profiler_rawdata table to view a list of the wait event counters and wait event
acctg=# SELECT runid, sourcecode, func_oid, line_number, exec_count, tuples_returned, time_total
runid | sourcecode | func_oid | line_number | exec_count | tu
                                      l 16999 l
  1 | DECLARE
                                                           1 |
                                                                              0 |
                  NUMERIC(4);
                                                          2 l
3 l
                                               l 16999 l
                                                                      0 |
  1 l v_empno
                                              v_ename VARCHAR(10);
     emp_cur CURSOR FOR
                                          SELECT empno, ename FROM memp ORDER BY empno; | 16999 |
  1 |
                                                                            0 I
  1 | BEGIN
       OPEN emp_cur;
  1 |
       RAISE INFO 'EMPNO ENAME';
       RAISE INFO '----';
  1 |
  1 |
         FETCH emp_cur INTO v_empno, v_ename;
                                                   l 16999 l
  1 |
                                                             11 l
        EXIT WHEN NOT FOUND;
                                              l 16999 l
                                                             12 l
                                                                      15 I
                                                      16999 | 13 |
                                                                         15 I
  1 |
         RAISE INFO '% %', v_empno, v_ename;
                                               l 16999 l
                                                          14 i
15 l v
1 l
                                                           14 I
                                                                   14 I
  1 |
       END LOOP;
                                                                   0 |
                                              l 16999 l
  1 |
       CLOSE emp_cur;
                                                         16 I
                                               16999 I
  1 |
       RETURN;
05
  1 | END;
                                           l 16999 l
                                                        17 l
                                                                  1 |
                                                                             0 |
                                            16999 | 18 |
| 17002 | 1 |
                                                                 0 I
                                                                            0 I
                                          l 16999 l
  1 |
  2 | DECLARE
                                                                              0 |
                                           | 17002 | 2 |
| 17002 | 3 | 0
| 17002 | 4 | 0 |
                 VARCHAR(24);
  2 |
       v_action
                                                                  0 |
  2 |
       v_text
                  TEXT;
  2 | BEGIN
                                                                              0 |
                                                l 17002 l
  2 |
       IF TG_OP = 'INSERT' THEN
                                                               5 I
  2 |
         v_action := ' added employee(s) on ';
                                                   l 17002 l
                                                               6 I
                                                                          1 |
                                                   17002 l
                                                                7 I
  2 |
       ELSIF TG_OP = 'UPDATE' THEN
                                                                        0 |
         v_action := ' updated employee(s) on ';
  2 |
                                                      17002 l
                                                                 8 I
                                                                           0 |
                                                               9 I
  2 |
       ELSIF TG_OP = 'DELETE' THEN
                                                  17002 l
                                                      11 | 0 |
  2 |
         v_action := ' deleted employee(s) on ';
                                                  l 17002 l
                                           l 17002 l
  2 |
                                                                              0 |
                                                          17002 l
       v_text := 'User ' || USER || v_action || CURRENT_DATE;
  2 |
       RAISE INFO ' %', v_text;
                                               l 17002 l 13 l
  2 |
                                                            14 l
       RETURN NULL;
                                               17002 l
  2 |
                                             17002 l
  2 | END;
                                                         15 l
                                                                   1 |
05
                                            17002 | 16
| 17000 |
                                                        16 I 0 1 I
                                                                 0 |
                                                                            0 |
  2 | DECLARE
                                                                              0 |
                                           | 17000 | 2 | 0 |
| 17000 | 3 | 0 |
  2 |
                  VARCHAR(14);
       v_dname
  2 | BEGIN
                                                                              0 I
       SELECT INTO v_dname dname FROM dept WHERE deptno = p_deptno; | 17000 |
  2 |
  2 |
                                             l 17000 l 5 l
                                                                    1 l
       RETURN v_dname;
```

```
05
   2 |
            RAISE INFO 'Invalid department number %', p_deptno;
                                                                          17000 I
                                                                                          7 I
                                                                                                    0 1
   2 |
                                                         l 17000 l
                                                                           8 I
                                                                                       0 1
                                                                                                    0
                                                            17000 l
                                                                           9 I
                                                                                                    0 1
   2 |
         END IF;
                                                                                      0 I
   2 | END;
                                                            17000 l
                                                                          10 I
                                                                                     0 |
                                                                                                   0 1
   2 |
                                                          17000 l
                                                                         11 |
                                                                                    0 |
                                                                                                  0 |
   2 | DECLARE
                                                            17004 I
                                                                            1 |
                                                                                      0 1
                                                                                                    0 1
                                                                17004 l
                       NUMERIC(7,2);
                                                                                 2 |
   2 |
         sal_diff
                                                             2 | BEGIN
                                                            17004 I
                                                                           3 I
                                                                                     0 1
                                                                                                   0 1
   2 |
         IF TG_OP = 'INSERT' THEN
                                                                 17004 I
                                                             1
   2 |
            RAISE INFO 'Inserting employee %', NEW.empno;
                                                                 17004 I
                                                                                        5 I
                                                                                                  1 |
05
   2 |
            RAISE INFO '... New salary: %', NEW.sal;
                                                                      17004 l
                                                                                     6 I
                                                                                                0 1
   2 |
            RETURN NEW;
                                                          Ι
                                                              17004 l
                                                                            7 I
                                                                                       0 |
                                                                                                     0
         END IF;
   2 |
                                                            17004 l
                                                                                      0 1
                                                                                                    0 |
                                                                           8 I
                                                                                           0 I
   2 |
         IF TG_OP = 'UPDATE' THEN
                                                                 17004 l
                                                                                 9 |
            sal_diff := NEW.sal - OLD.sal;
   2 |
                                                                   17004 l
            RAISE INFO 'Updating employee %', OLD.empno;
                                                                        17004 l
   2 |
                                                                                       11 I
                                                                                                  1 |
   2 |
            RAISE INFO '..Old salary: %', OLD.sal;
                                                                      17004 l
                                                                                     12 l
                                                                                                1 |
05
   2 |
            RAISE INFO '... New salary: %', NEW.sal;
                                                                      17004 l
                                                                                     13 I
                                                                                                1 |
05
            RAISE INFO '..Raise : %', sal_diff;
                                                                     17004 l
                                                                                    14 I
                                                                                               1 I
   2 |
                                                                 1
05
                                                                            15 I
   2 |
            RETURN NEW;
                                                              17004 I
                                                                                       1 |
05
   2 |
         END IF;
                                                            17004 l
                                                                           16 I
                                                                                      1 |
                                                                                                    0 I
06
   2 |
         IF TG_OP = 'DELETE' THEN
                                                                 17004 l
                                                                                17 I
            RAISE INFO 'Deleting employee %', OLD.empno;
                                                                    l 17004 l
   2 |
                                                                                       18 I
                                                                                                  0 |
            RAISE INFO '...Old salary: %', OLD.sal;
                                                                      17004 l
   2 |
                                                                                     19 I
                                                                                                0 I
   2 |
            RETURN OLD:
                                                             17004 l
                                                                           20 I
                                                                                       0 I
                                                                                                     0
   2 |
         END IF;
                                                           17004 l
                                                                           21 I
                                                                                      0 |
                                                                                                    0 1
   2 | END;
                                                           17004 l
                                                                          22 I
                                                                                     0 1
                                                                                                   0 |
   2 |
                                                          17004 l
                                                                         23 I
                                                                                    0 |
                                                                                                  0 I
 (68 rows)
 11. Query the plsql_profiler_data view to review a subset of the information found in plsql_profiler_rawdata
    table:
acctg=# SELECT * FROM plsql_profiler_data;
runid | unit_number | line# | total_occur | total_time | min_time | max_time | spare1 | spare2 | spa
    1 |
                        1 |
                                               0 I
            16999 I
                                    0 |
                                                         0 I
                                                                  0 |
                        2 |
    1 |
            16999 I
                                    0 I
                                               0 |
                                                         0 I
                                                                  0 |
                        3 I
                                    0 I
                                               0 |
                                                         0 |
    1 |
            16999 I
    1 |
            16999 I
                        4 |
                                    0 I
                                               0 |
                                                         0 1
                                                                  0 1
                                                                  0 |
    1 |
                        5 I
                                    0 I
                                               0 |
                                                         0 |
            16999 I
    1 |
            16999 I
                        6 I
                                    0 |
                                               0 |
                                                         0 |
                                                                  0 |
            16999 I
    1 |
                        7 1
                                   0 |
                                               0 |
                                                         0 |
                                                                  0 |
   1 |
           16999 I
                      8 |
                                 1 | 0.001621 | 0.001621 | 0.001621 |
                                                                              П
   1 |
           16999 I
                                 1 I
                                      0.000301 | 0.000301 | 0.000301 |
                      9 I
                                                                              Ι
                   16999 I
                                 10 I
                                                    1 |
                                                             4.6e-05 |
                                                                          4.6e-05 |
05 I
                      -
                                 16999 I
                                 1 I
                                       0.001114 | 0.001114 | 0.001114 |
   1 |
                      11 |
                                                                              16999 I
                                 12 l
                                                  15 l
                                                           0.000206
      1 |
                                                                            5e-06 l
                                                                                      7.8e-
05 I
             16999 I
                                13 I
                                                  15 I
                                                            8.3e-05 l
                                                                            2e-06 l
                                                                                      4.7e-
      1 |
05 I
                      - 1
                                 1
```

2 |

IF NOT FOUND THEN

17000 I

6 I

1 |

```
14 | 0.000773 | 4.7e-
                          1 | 1e-05 | 1e-05 | 1e-05 |
                         1 | 0 | 0 |
0 | 0 | 0 |
0 | 0 | 0 |
                                              0 |
   1 I
        16999 I 17 I
         16999 I 18 I
                                                  0 |
   1 |
                                                0 I
                1 l
   2 |
         17002 l
   2 |
         17002 | 2 |
                          0 |
0 |
                          0 I
                                   0 I
                                          0 |
                                                  0 1
         17002 I 3 I
                                   0 I
                                          0 I
                                                  0 |
   2 |
                                          0 I
   2 I
        17002 | 4 |
                                   0 |
                                                  0 |
                          0 | 0 |
        17002 I 5 I
   2 |
                                          0 |
                                                  0 I
   2 |
        17002 | 6 |
                         1 | 0.000143 | 0.000143 | 0.000143 |
                        0 | 0 | 0 | 0 |
0 | 0 | 0 | 0 |
9 | 1 | 3.2e-05 |
   2 | 17002 | 7 |
2 | 17002 | 8 |
                                                         -
  2 I
         17002 l
                                                       3.2e-05 |
05 l
                         1
                        10 l
  2 |
         17002 l
                                                        - 1
  2 |
         17002 | 11 |
                                                        - 1
  2 |
         17002 | 12 |
        17002 l 13 l
                        1 | 0.000383 | 0.000383 | 0.000383 |
                                                        - 1
   2 |
   2 l 17002 l
                         14 | 1 | 6.3e-05 | 6.3e-05 | 6.3e-
        17002 |
| 17002 |
| |
                         15 I
                                      1 | 3.6e-05 |
                                                       3.6e-05 | 3.6e-
05 I
                        I
                        17002 I 16 I
   2 I
                                               0 I
         17000 | 1 |
   2 |
                                                 0 I
   2 |
         17000 l 2 l
                                                 0 I
        17000 | 3 |
17000 | 4 |
17000 | 5 |
   2 |
                                                  0 |
   2 |
                                                  0 I
                        1 | 0.000647 | 0.000647 | 0.000647 |
   2 I
  2 | 17000 |
| | |
                        6 l 1 l 2.6e-05 l
                                                       2.6e-05 l
                        0 | 0 |
0 | 0 |
0 | 0 |
   2 |
         17000 I 7 I
                                         0 |
                                                 0 |
   2 |
         17000 | 8 |
                                         0 |
                                                 0 1
         17000 l 9 l
                                          0 1
                                                  0 1
   2 |
                          0 I
         17000 | 10 |
   2 |
                                  0 |
                                          0 1
                                                  0 1
         17000 l 11 l
                          0 |
   2 |
                                   0 I
                                          0 I
                                                  0 1
                1 I
   2 |
         17004 l
                          0 |
                                   0 |
                                          0 |
                                                  0 1
   2 |
         17004 | 2 |
                          0 I
                                   0 I
                                          0 1
                                                  0 1
                         0 |
         17004 | 3 |
17004 | 4 |
                                          0 |
   2 |
                                   0 I
                                                  0 |
                                   0 |
   2 |
                                          0 |
                                                  0 |
   2 I
        17004 |
| |
                        5 I
                                   1 l 8.4e-05 l
                                                       8.4e-05 |
05 I
                       0 | 0 |
0 | 0 |
0 | 0 |
0 | 0 |
         17004 | 6 |
17004 | 7 |
   2 |
                                         0 I
                                                 0 I
                                         0 |
   2 |
                                                0 I
         17004 | 8 |
17004 | 9 |
                                                 0 I
   2 |
                                          0 |
                                       0 |
   2 |
                                                 0 1
  2 |
                        1 | 0.000355 | 0.000355 | 0.000355 |
         17004 | 10 |
   2 |
         17004 | 11 |
                        1 | 0.000177 | 0.000177 | 0.000177 |
        17004 l
                         12 l
                                      1 I
                                             5.5e-05 l
                                                       5.5e-05 l
              - 1
05 I
                         1
                         13 I
     2 |
              17004 I
                                       1 I
                                             3.1e-05 l
                                                       3.1e-05 | 3.1e-
05 I
               17004 I
                         14 I
                                       1 |
                                            2.8e-05 l
                                                       2.8e-05 | 2.8e-
              1
                        1
               17004 I
                         15 I
                                      1 | 2.7e-05 |
   2 |
                                                       2.7e-05 | 2.7e-
               1
                        - 1
                       2 |
         17004 | 16 |
                                                               - 1
                                                       - 1
         17004 | 17 |
   2 |
                                                               17004 l
   2 |
                 18 I
                                                         - 1
   2 |
         17004 | 19 |
```

2 l	17004 l	20 I	0 l	0	0 I	0	1	1	- 1
2	17004 l	21 l	0 I	0 I	0 I	0 l	1	1	- 1
2	17004 l	22 I	0 I	0 I	0 I	0 l	1	1	- 1
2	17004 l	23 I	0 I	0 I	0 I	0 l	1	1	- 1
(68 rows)									

DBMS_PROFILER - Reference

The Advanced Server installer creates the following tables and views that you can query to review PL/SQL performance profile information:

Table Name	Description		
PLSQL_PROFILER_RUNS	Table containing information about all profiler runs, organized by runid.		
PLSQL_PROFILER_UNITS	Table containing information about all profiler runs, organized by unit.		
PLSQL_PROFILER_DATA	View containing performance statistics.		
PLSQL_PROFILER_RAWDATA	Table containing the performance statistics and the extended performance statistics fo		

PLSQL_PROFILER_RUNS The PLSQL_PROFILER_RUNS table contains the following columns:

Column	Data Type	Description
runid	INTEGER (NOT NULL)	Unique identifier (plsql_profiler_runnumber)
related_run	INTEGER	The runid of a related run.
run_owner	TEXT	The role that recorded the profiling session.
run_date	TIMESTAMP WITHOUT TIME ZONE	The profiling session start time.
run_comment	TEXT	User comments relevant to this run
<pre>run_total_time</pre>	BIGINT	Run time (in microseconds)
run_system_info	TEXT	Currently Unused
run_comment1	TEXT	Additional user comments
spare1	TEXT	Currently Unused

PLSQL_PROFILER_UNITS The PLSQL_PROFILER_UNITS table contains the following columns:

Column	Data Type	Description
runid	INTEGER	Unique identifier (plsql_profiler_runnumber)
unit_number	OID	Corresponds to the OID of the row in the pg_proc table that
unit_type	TEXT	PL/SQL function, procedure, trigger or anonymous block
unit_owner	TEXT	The identity of the role that owns the unit.
unit_name	TEXT	The complete signature of the unit.
unit_timestamp	TIMESTAMP WITHOUT TIME ZONE	Creation date of the unit (currently NULL).
total_time	BIGINT	Time spent within the unit (in milliseconds)
spare1	BIGINT	Currently Unused
spare2	BIGINT	Currently Unused

PLSQL_PROFILER_DATA The PLSQL_PROFILER_DATA view contains the following columns:

Column	Data Type	Description
runid	INTEGER	Unique identifier (plsql_profiler_runnumber)
unit_number	OID	Object ID of the unit that contains the current line.

Column Data Type		Description	
line# total_occur	INTEGER BIGINT	Current line number of the profiled workload. The number of times that the line was executed.	
<pre>total_time min_time</pre>	DOUBLE PRECISION DOUBLE PRECISION	The amount of time spent executing the line (in seconds) The minimum execution time for the line.	
max_time spare1	DOUBLE PRECISION NUMBER	The maximum execution time for the line. Currently Unused	
spare2	NUMBER	Currently Unused	
spare3 spare4	NUMBER NUMBER	Currently Unused Currently Unused	

PLSQL_PROFILER_RAWDATA The PLSQL_PROFILER_RAWDATA table contains the statistical and wait events information that is found in the PLSQL_PROFILER_DATA view, as well as the performance statistics returned by the DRITA counters and timers.

Column	Data Type	Description
runid	INTEGER	The run identifier (plsql_profiler_runnumbe
sourcecode	TEXT	The individual line of profiled code.
func_oid	OID	Object ID of the unit that contains the curre
line_number	INTEGER	Current line number of the profiled workloa
exec_count	BIGINT	The number of times that the line was exec
tuples_returned	BIGINT	Currently Unused
time_total	DOUBLE PRECISION	The amount of time spent executing the lin
time_shortest	DOUBLE PRECISION	The minimum execution time for the line.
time_longest	DOUBLE PRECISION	The maximum execution time for the line.
num_scans	BIGINT	Currently Unused
tuples_fetched	BIGINT	Currently Unused
tuples_inserted	BIGINT	Currently Unused
tuples_updated	BIGINT	Currently Unused
tuples_deleted	BIGINT	Currently Unused
blocks_fetched	BIGINT	Currently Unused
blocks_hit	BIGINT	Currently Unused
wal_write	BIGINT	A server has waited for a write to the write
wal_flush	BIGINT	A server has waited for the write-ahead log
wal_file_sync	BIGINT	A server has waited for the write-ahead log
db_file_read	BIGINT	A server has waited for the completion of a
db_file_write	BIGINT	A server has waited for the completion of a
db_file_sync	BIGINT	A server has waited for the operating syste
db_file_extend	BIGINT	A server has waited for the operating syste
sql_parse	BIGINT	Currently Unused.
query_plan	BIGINT	A server has generated a query plan.
other_lwlock_acquire	BIGINT	A server has waited for other light-weight le
shared_plan_cache_collision	BIGINT	A server has waited for the completion of t
shared_plan_cache_insert	BIGINT	A server has waited for the completion of t
shared_plan_cache_hit	BIGINT	A server has waited for the completion of t
shared_plan_cache_miss	BIGINT	A server has waited for the completion of t
shared_plan_cache_lock	BIGINT	A server has waited for the completion of t
onal captan_cache_tock	5 - 5 - 5 - 5	7. Co. To. Tido Wallod for the completion of t

BIGINT

A server has waited for the completion of t

shared_plan_cache_busy

Column	Data Type	Description
shmemindexlock	BIGINT	A server has waited to find or allocate space
oidgenlock	BIGINT	A server has waited to allocate or assign a
xidgenlock	BIGINT	A server has waited to allocate or assign a
procarraylock	BIGINT	A server has waited to get a snapshot or cl
sinvalreadlock	BIGINT	A server has waited to retrieve or remove r
sinvalwritelock	BIGINT	A server has waited to add a message to t
walbufmappinglock	BIGINT	A server has waited to replace a page in W
walwritelock	BIGINT	A server has waited for WAL buffers to be
controlfilelock	BIGINT	A server has waited to read or update the
checkpointlock	BIGINT	A server has waited to perform a checkpoin
clogcontrollock	BIGINT	A server has waited to read or update the t
subtranscontrollock	BIGINT	A server has waited to read or update the s
multixactgenlock	BIGINT	A server has waited to read or update the
multixactoffsetcontrollock	BIGINT	A server has waited to read or update mult
multixactmembercontrollock	BIGINT	A server has waited to read or update mult
relcacheinitlock	BIGINT	A server has waited to read or write the rel
checkpointercommlock	BIGINT	A server has waited to manage the fsync re
twophasestatelock	BIGINT	A server has waited to read or update the
tablespacecreatelock	BIGINT	A server has waited to create or drop the ta
btreevacuumlock	BIGINT	A server has waited to read or update the
addinshmeminitlock	BIGINT	A server has waited to manage space alloc
autovacuumlock	BIGINT	The autovacuum launcher waiting to read o
autovacuumschedulelock syncscanlock	BIGINT BIGINT	A server has waited to ensure that the table
-	BIGINT	A server has waited to get the start location
relationmappinglock		A server has waited to update the relation
asyncctllock	BIGINT	A server has waited to read or update shar
asyncqueuelock	BIGINT	A server has waited to read or update the r
serializablexacthashlock	BIGINT	A server has waited to retrieve or store info
serializablefinishedlistlock	BIGINT BIGINT	A server has waited to access the list of fin
serializablepredicatelocklistlock oldserxidlock		A server has waited to perform an operatio
syncreplock	BIGINT BIGINT	A server has waited to read or record the c A server has waited to read or update infor
backgroundworkerlock	BIGINT	
dynamicsharedmemorycontrollock	BIGINT	A server has waited to read or update the to A server has waited to read or update the description.
, and the second		·
autofilelock	BIGINT	A server has waited to update the postg
replicationslotallocationlock	BIGINT	A server has waited to allocate or free a re
replicationslotcontrollock	BIGINT	A server has waited to read or update repli
committscontrollock	BIGINT	A server has waited to read or update trans
committslock	BIGINT	A server has waited to read or update the l
replicationoriginlock	BIGINT	A server has waited to set up, drop, or use
multixacttruncationlock	BIGINT	A server has waited to read or undate old of
oldsnapshottimemaplock	BIGINT	A server has waited to read or update old s
backendrandomlock	BIGINT BIGINT	A server has waited to generate a random
logicalrepworkerlock		A server has waited to trupeate the write of
clogtruncationlock	BIGINT	A server has waited to truncate the write-al
bulkloadlock edhresourcemanagerlock	BIGINT	A server has waited for the bulkloadlog
edbresourcemanagerlock	BIGINT	The edbresourcemanagerlock provid

Column	Data Type	Description
wal_write_time	BIGINT	The amount of time that the server has wa
wal_flush_time	BIGINT	The amount of time that the server has wa
wal_file_sync_time	BIGINT	The amount of time that the server has wa
<pre>db_file_read_time</pre>	BIGINT	The amount of time that the server has wa
db_file_write_time	BIGINT	The amount of time that the server has wa
db_file_sync_time	BIGINT	The amount of time that the server has wa
db_file_extend_time	BIGINT	The amount of time that the server has wa
sql_parse_time	BIGINT	The amount of time that the server has wa
query_plan_time	BIGINT	The amount of time that the server has wa
other_lwlock_acquire_time	BIGINT	The amount of time that the server has wa
<pre>shared_plan_cache_collision_time</pre>	BIGINT	The amount of time that the server has wa
<pre>shared_plan_cache_insert_time</pre>	BIGINT	The amount of time that the server has wa
<pre>shared_plan_cache_hit_time</pre>	BIGINT	The amount of time that the server has wa
shared_plan_cache_miss_time	BIGINT	The amount of time that the server has wa
<pre>shared_plan_cache_lock_time</pre>	BIGINT	The amount of time that the server has wa
shared_plan_cache_busy_time	BIGINT	The amount of time that the server has wa
shmemindexlock_time	BIGINT	The amount of time that the server has wa
oidgenlock_time	BIGINT	The amount of time that the server has wa
xidgenlock_time	BIGINT	The amount of time that the server has wa
procarraylock_time	BIGINT	The amount of time that the server has wa
sinvalreadlock_time	BIGINT	The amount of time that the server has wa
sinvalwritelock_time	BIGINT	The amount of time that the server has wa
walbufmappinglock_time	BIGINT	The amount of time that the server has wa
walwritelock_time	BIGINT	The amount of time that the server has wa
controlfilelock_time	BIGINT	The amount of time that the server has wa
<pre>checkpointlock_time</pre>	BIGINT	The amount of time that the server has wa
clogcontrollock_time	BIGINT	The amount of time that the server has wa
subtranscontrollock_time	BIGINT	The amount of time that the server has wa
multixactgenlock_time	BIGINT	The amount of time that the server has wa
multixactoffsetcontrollock_time	BIGINT	The amount of time that the server has wa
multixactmembercontrollock_time	BIGINT	The amount of time that the server has wa
relcacheinitlock_time	BIGINT	The amount of time that the server has wa
checkpointercommlock_time	BIGINT	The amount of time that the server has wa
twophasestatelock_time	BIGINT	The amount of time that the server has wa
tablespacecreatelock_time	BIGINT	The amount of time that the server has wa
btreevacuumlock_time	BIGINT	The amount of time that the server has wa
addinshmeminitlock_time	BIGINT	The amount of time that the server has wa
autovacuumlock_time	BIGINT	The amount of time that the server has wa
autovacuumschedulelock_time	BIGINT	The amount of time that the server has wa
syncscanlock_time	BIGINT	The amount of time that the server has wa
relationmappinglock_time	BIGINT	The amount of time that the server has wa
asyncctllock_time	BIGINT	The amount of time that the server has wa
asyncqueuelock_time	BIGINT	The amount of time that the server has wa
serializablexacthashlock_time	BIGINT	The amount of time that the server has wa
serializablefinishedlistlock_time	BIGINT	The amount of time that the server has wa
serializablepredicatelocklistlock_time	BIGINT	The amount of time that the server has wa

Column	Data Type	Description
oldserxidlock_time	BIGINT	The amount of time that the server has wa
syncreplock_time	BIGINT	The amount of time that the server has wa
backgroundworkerlock_time	BIGINT	The amount of time that the server has wa
<pre>dynamicsharedmemorycontrollock_time</pre>	BIGINT	The amount of time that the server has wa
<pre>autofilelock_time</pre>	BIGINT	The amount of time that the server has wa
replicationslotallocationlock_time	BIGINT	The amount of time that the server has wa
replicationslotcontrollock_time	BIGINT	The amount of time that the server has wa
committscontrollock_time	BIGINT	The amount of time that the server has wa
committslock_time	BIGINT	The amount of time that the server has wa
replicationoriginlock_time	BIGINT	The amount of time that the server has wa
multixacttruncationlock_time	BIGINT	The amount of time that the server has wa
oldsnapshottimemaplock_time	BIGINT	The amount of time that the server has wa
backendrandomlock_time	BIGINT	The amount of time that the server has wa
logicalrepworkerlock_time	BIGINT	The amount of time that the server has wa
clogtruncationlock_time	BIGINT	The amount of time that the server has wa
bulkloadlock_time	BIGINT	The amount of time that the server has wa
edbresourcemanagerlock_time	BIGINT	The amount of time that the server has wa
totalwaits	BIGINT	The total number of event waits.
totalwaittime	BIGINT	The total time spent waiting for an event.

5.3.12 DBMS_RANDOM

The DBMS_RANDOM package provides a number of methods to generate random values. The procedures and functions available in the DBMS_RANDOM package are listed in the following table.

Function/Procedure	Return Type	Description
<pre>INITIALIZE(<val>)</val></pre>	n/a	Initializes the DBMS_RANDOM package with the specified seed <value></value>
NORMAL()	NUMBER	Returns a random NUMBER .
RANDOM	INTEGER	Returns a random INTEGER with a value greater than or equal to -2^31 at
SEED(<val>)</val>	n/a	Resets the seed with the specified <value> .</value>
SEED(<val>)</val>	n/a	Resets the seed with the specified <value> .</value>
<pre>STRING(<opt>, <len>)</len></opt></pre>	VARCHAR2	Returns a random string.
TERMINATE	n/a	TERMINATE has no effect. Deprecated, but supported for backward compa
VALUE	NUMBER	Returns a random number with a value greater than or equal to 0 and les
<pre>VALUE(<low>, <high>)</high></low></pre>	NUMBER	Returns a random number with a value greater than or equal to <low> ar</low>

INITIALIZE

The INITIALIZE procedure initializes the DBMS_RANDOM package with a seed value. The signature is:

INITIALIZE(<val> IN INTEGER)

This procedure should be considered deprecated; it is included for backward compatibility only.

Parameter

<val>

<val> is the seed value used by the DBMS_RANDOM package algorithm.

Example

The following code snippet demonstrates a call to the INITIALIZE procedure that initializes the DBMS_RANDOM package with the seed value, 6475 .

DBMS_RANDOM.INITIALIZE(6475);

NORMAL

The NORMAL function returns a random number of type NUMBER . The signature is:

```
<result> NUMBER NORMAL()
```

Parameter

<result>

<result> is a random value of type NUMBER .

Example

The following code snippet demonstrates a call to the NORMAL function:

```
x:= DBMS_RANDOM.NORMAL();
```

RANDOM

The RANDOM function returns a random INTEGER value that is greater than or equal to -2 ^31 and less than 2 ^31. The signature is:

```
<result> INTEGER RANDOM()
```

This function should be considered deprecated; it is included for backward compatibility only.

Parameter

<result>

<result> is a random value of type INTEGER.

Example

The following code snippet demonstrates a call to the RANDOM function. The call returns a random number:

```
x := DBMS_RANDOM.RANDOM();
```

SEED

The first form of the SEED procedure resets the seed value for the DBMS_RANDOM package with an INTEGER value. The SEED procedure is available in two forms; the signature of the first form is:

```
SEED(<val> IN INTEGER)
```

Parameter

<val>

<val> is the seed value used by the DBMS_RANDOM package algorithm.

Example

The following code snippet demonstrates a call to the SEED procedure; the call sets the seed value at 8495

```
DBMS_RANDOM.SEED(8495);
```

SEED

The second form of the SEED procedure resets the seed value for the DBMS_RANDOM package with a string value. The SEED procedure is available in two forms; the signature of the second form is:

SEED(<val> IN VARCHAR2)

Parameter

<val>

<val> is the seed value used by the DBMS_RANDOM package algorithm.

Example

The following code snippet demonstrates a call to the SEED procedure; the call sets the seed value to abc123.

DBMS_RANDOM.SEED('abc123');

STRING

The STRING function returns a random VARCHAR2 string in a user-specified format. The signature of the STRING function is:

<result> VARCHAR2 STRING(<opt> IN CHAR, <len> IN NUMBER)

Parameters

<opt>

Formatting option for the returned string. <option> may be:

Y{0.6}I

Option		1	Specifies Formatting Option	
u	or	U	Uppercase alpha string	
1	or	L	Lowercase alpha string	
а	or	Α	Mixed case string	
Χ	or	Χ	Uppercase alpha-numeric string	
p	or	P	Any printable characters	

<len>

The length of the returned string.

<result>

<result> is a random value of type VARCHAR2 .

Example

The following code snippet demonstrates a call to the STRING function; the call returns a random alphanumeric character string that is 10 characters long.

x := DBMS_RANDOM.STRING('X', 10);

TERMINATE

The TERMINATE procedure has no effect. The signature is:

TERMINATE

The TERMINATE procedure should be considered deprecated; the procedure is supported for compatibility only.

VALUE

The VALUE function returns a random NUMBER that is greater than or equal to 0, and less than 1, with 38 digit precision. The VALUE function has two forms; the signature of the first form is:

```
<result> NUMBER VALUE()
```

Parameter

<result>

<result> is a random value of type NUMBER .

Example

The following code snippet demonstrates a call to the VALUE function. The call returns a random NUMBER :

```
x := DBMS_RANDOM.VALUE();
```

DBMS_RANDOM_VALUE_SECOND_FORM

VALUE

The VALUE function returns a random NUMBER with a value that is between user-specified boundaries. The VALUE function has two forms; the signature of the second form is:

```
<result> NUMBER VALUE(<low> IN NUMBER, <high> IN NUMBER)
```

Parameters

<low>

<low> specifies the lower boundary for the random value. The random value may be equal to <low> .

<high>

<high> specifies the upper boundary for the random value; the random value will be less than
<high> .

<result>

<result> is a random value of type NUMBER .

Example

The following code snippet demonstrates a call to the VALUE function. The call returns a random NUMBER with a value that is greater than or equal to 1 and less than 100:

```
x := DBMS_RANDOM.VALUE(1, 100);
```

5.3.13 DBMS REDACT

The DBMS_REDACT package enables the redacting or masking of data returned by a query. The DBMS_REDACT package provides a procedure to create policies, alter policies, enable policies, disable policies, and drop policies. The procedures available in the DBMS_REDACT package are listed in the following table.

Function/Procedure

ADD_POLICY(<object_schema>, <object_name>, <policy_name>, <policy_description>, <column_name> ALTER_POLICY(<object_schema>, <object_name>, <policy_name>, <action>, <column_name>, <function</p>

```
DISABLE_POLICY(<object_schema>, <object_name>, <policy_name>)
ENABLE_POLICY(<object_schema,> <object_name>, <policy_name>)
DROP_POLICY(<object_schema>, <object_name>, <policy_name>)
UPDATE_FULL_REDACTION_VALUES(<number_val>, <binfloat_val>, <bindouble_val>, <char_val>, <varchema</pre>
```

The data redaction feature uses the DBMS_REDACT package to define policies or conditions to redact data in a column based on the table column type and redaction type.

Note that you must be the owner of the table to create or change the data redaction policies. The users are exempted from all the column redaction policies, which the table owner or super-user is by default.

Using DBMS_REDACT Constants and Function Parameters

The DBMS_REDACT package uses the constants and redacts the column data by using any one of the data redaction types. The redaction type can be decided based on the function_type parameter of dbms_redact.add_policy and dbms_redact.alter_policy procedure. The below table highlights the values for function_type parameters of dbms_redact.add_policy and dbms_redact.alter_policy.

Constant	Туре	Value	Description
NONE	INTEGER	0	No redaction, zero effect on the result of a query against table.
FULL	INTEGER	1	Full redaction, redacts full values of the column data.
PARTIAL	INTEGER	2	Partial redaction, redacts a portion of the column data.
RANDOM	INTEGER	4	Random redaction, each query results in a different random value depending on the da
REGEXP	INTEGER	5	Regular Expression based redaction, searches for the pattern of data to redact.
CUSTOM	INTEGER	99	Custom redaction type.

The following table shows the values for the action parameter of dbms_redact.alter_policy .

Constant	Type	Value	Description
ADD_COLUMN	INTEGER	1	Adds a column to the redaction policy.
DROP_COLUMN	INTEGER	2	Drops a column from the redaction policy.
MODIFY_EXPRESSION	INTEGER	3	Modifies the expression of a redaction policy. The redaction is app
MODIFY_COLUMN	INTEGER	4	Modifies a column in the redaction policy to change the redaction f
SET_POLICY_DESCRIPTION	INTEGER	5	Sets the redaction policy description.
SET_COLUMN_DESCRIPTION	INTEGER	6	Sets a description for the redaction performed on the column.

The partial data redaction enables you to redact only a portion of the column data. To use partial redaction, you must set the <code>dbms_redact.add_policy</code> procedure function_type parameter to dbms_redact.partial and use the function_parameters parameter to specify the partial redaction behavior.

The data redaction feature provides a predefined format to configure policies that use the following datatype:

- Character
- Number
- Datetime

The following table highlights the format descriptor for partial redaction with respect to datatype. The example described below shows how to perform a redaction for a string datatype (in this scenario, a Social Security Number (SSN)), a Number datatype, and a DATE datatype.

Datatype	Format Descriptor	Desc	ription
Character	REDACT_PARTIAL_INPUT_FORMAT	Spec	ifies the input format. Enter ${ m V}$ for each character from the inp
	REDACT_PARTIAL_OUTPUT_FORMAT	Spec	ifies the output format. Enter $oldsymbol{V}$ for each character from the in
	REDACT_PARTIAL_MASKCHAR	Spec	ifies the character to be used for redaction.
	REDACT_PARTIAL_MASKFROM	Spec	ifies which $oldsymbol{V}$ within the input format from which to start the re
	REDACT_PARTIAL_MASKTO	Spec	ifies which $oldsymbol{V}$ within the input format at which to end the redac
Number	REDACT_PARTIAL_MASKCHAR	Spec	ifies the character to be displayed in the range between 0 and 9
	REDACT_PARTIAL_MASKFROM	Spec	ifies the start digit position for redaction.
	REDACT_PARTIAL_MASKTO	Spec	ifies the end digit position for redaction.
Datetime	REDACT_PARTIAL_DATE_MONTH	'm'	redacts the month. To mask a specific month, specify 'm#'
	REDACT_PARTIAL_DATE_DAY	'd'	redacts the day of the month. To mask with a day of the month
	REDACT_PARTIAL_DATE_YEAR	' y'	redacts the year. To mask with a year, append 1-9999 to a
	REDACT_PARTIAL_DATE_HOUR	'h'	redacts the hour. To mask with an hour, append 0-23 to a l
	REDACT_PARTIAL_DATE_MINUTE	'm'	redacts the minute. To mask with a minute, append 0-59 to
	REDACT_PARTIAL_DATE_SECOND	's'	redacts the second. To mask with a second, append 0-59 t

The following table represents function_parameters values that can be used in partial redaction.

A regular expression-based redaction searches for patterns of data to redact. The regexp_pattern search the values in order for the regexp_replace_string to change the value. The following table illustrates the regexp_pattern values that you can use during REGEXP based redaction.

Function Parameter and Description	Data Type
	RE_PATTERN_CC_L6_T4: Searches for the middle digits of a credit card number
	RE_PATTERN_ANY_DIGITs: Searches for any digit and replaces the identified
	RE_PATTERN_US_PHONE: Searches for the U.S phone number and replaces
	RE_PATTERN_EMAIL_ADDRESS: Searches for the email address and replace
	RE_PATTERN_IP_ADDRESS: Searches for an IP address and replaces the idea
	RE_PATTERN_AMEX_CCN: Searches for the American Express credit card nur
	RE_PATTERN_CCN: Searches for the credit card number other than American I
	RE_PATTERN_US_SSN: Searches the SSN number and replaces the identified
	RE_REDACT_CC_MIDDLE_DIGITS: Redacts the middle digits of a credit card r
	RE_REDACT_WITH_SINGLE_X: Replaces the data with a single X character for

The below table illustrates the regexp_replace_string values that you can use during REGEXP based redaction.

The following tables show the regexp_position value and regexp_occurence values that you can use during REGEXP based redaction.

Function Parameter RE_BEGINNING	Data Type INTEGER	Value 1	Description Specifies the position of a character where search must begin. By default, the
Function Parameter	Data Type	Value	Description

Function Parameter Data Type Value Description
RE_ALL INTEGER 0 Specifies the replacement occurrence of a substring. If the value is 0, then the
RE_FIRST INTEGER 1 Specifies the replacement occurrence of a substring. If the value is 1, then the

The following table shows the regexp_match_parameter values that you can use during REGEXP based redaction which lets you change the default matching behavior of a function.

Function Parameter	Data Type	Value	Description
RE_CASE_SENSITIVE	VARCHAR2	'c'	Specifies the case-sensitive matching.
RE_CASE_INSENSITIVE	VARCHAR2	Ϊ'	Specifies the case-insensitive matching.
RE_MULTIPLE_LINES	VARCHAR2	'n'	Treats the source string as multiple lines but if you omit this parame
RE_NEWLINE_WILDCARD	VARCHAR2	'n'	Specifies the period (.), but if you omit this parameter, then the period
RE_IGNORE_WHITESPACE	VARCHAR2	'x'	Ignores the whitespace characters.

Note

If you create a redaction policy based on a numeric type column, then make sure that the result after redaction is a number and accordingly set the replacement string to avoid runtime errors.

Note

If you create a redaction policy based on a character type column, then make sure that a length of the result after redaction is compatible with the column type and accordingly set the replacement string to avoid runtime errors.

DBMS_REDACT_ADD_POLICY

ADD POLICY

The add_policy procedure creates a new data redaction policy for a table.

```
PROCEDURE add_policy (
object_schema
                      IN VARCHAR2 DEFAULT NULL,
object_name
                     IN VARCHAR2,
                     IN VARCHAR2,
policy_name
                         IN VARCHAR2 DEFAULT NULL,
policy_description
                     IN VARCHAR2 DEFAULT NULL,
column_name
column_description
                         IN VARCHAR2 DEFAULT NULL.
function_type IN INTEGER DEFAULT DBMS_REDACT.FULL,
                         IN VARCHAR2 DEFAULT NULL,
function_parameters
expression
                     IN VARCHAR2,
enable
                     IN BOOLEAN DEFAULT TRUE,
                         IN VARCHAR2 DEFAULT NULL,
regexp_pattern
                         IN VARCHAR2 DEFAULT NULL,
regexp_replace_string
regexp_position
                  IN INTEGER DEFAULT DBMS_REDACT.RE_BEGINNING,
                                      DBMS_REDACT.RE_ALL,
regexp_occurrence IN INTEGER DEFAULT
                        IN VARCHAR2 DEFAULT NULL,
regexp_match_parameter
custom_function_expression IN VARCHAR2 DEFAULT NULL
)
```

Parameters

```
<object_schema>
```

Specifies the name of the schema in which the object resides and on which the data redaction policy will be applied. If you specify NULL then the given object is searched by the order specified by search_path setting.

```
<object_name>
```

Name of the table on which the data redaction policy is created.

```
<policy_name>
```

Name of the policy to be added. Ensure that the policy_name is unique for the table on which the policy is created.

```
<policy_description>
```

Specify the description of a redaction policy.

<column_name>

Name of the column to which the redaction policy applies. To redact more than one column, use the alter_policy procedure to add additional columns.

<column_description>

Description of the column to be redacted. The column_description is not supported, but if you specify the description for a column then, you will get a warning message.

<function_type>

The type of redaction function to be used. The possible values are NONE, FULL, PARTIAL, RANDOM, REGEXP, and CUSTOM.

<function_parameters>

Specifies the function parameters for the partition redaction and is applicable only for partial redaction.

<expression>

Specifies the Boolean expression for the table and determines how the policy is to be applied. The redaction occurs if this policy expression is evaluated to TRUE.

<enable>

When set to TRUE, the policy is enabled upon creation. The default is set as TRUE. When set to FALSE, the policy is disabled but the policy can be enabled by calling the procedure.

<regexp_pattern>

Specifies the regular expression pattern to redact data. If the regexp_pattern does not match, then the NULL value is returned.

<regexp_replace_string>

Specifies the replacement string value.

<regexp_position>

Specifies the position of a character where search must begin. By default, the function parameter is RE_BEGINNING .

<regexp_occurrence>

Specifies the replacement occurrence of a substring. If the constant is RE_ALL , then the replacement of each matching substring occurs. If the constant is RE_FIRST , then the replacement of the first matching substring occurs.

<regexp_match_parameter>

Changes the default matching behavior of a function. The possible regexp_match_parameter constants can be 'RE_CASE_SENSITIVE', 'RE_CASE_INSENSITIVE', 'RE_MULTIPLE_LINES', 'RE_NEWLINE_WI

Note

For more information on constants, function_parameters, or regexp (regular expressions) see, Using DBMS_REDACT Constants and Function Parameters.

<custom_function_expression>

The custom_function_expression is applicable only for the CUSTOM redaction type. The custom_function_expression is a function expression that is, schema-qualified function with

a parameter such as schema_name.function_name (argument1, ...)that allows a user to use their redaction logic to redact the column data.

Example

The following example illustrates how to create a policy and use full redaction for values in the payment_details_tab table customer id column.

```
edb=# CREATE TABLE payment_details_tab (
customer_id NUMBER
                         NOT NULL,
card_string VARCHAR2(19) NOT NULL);
CREATE TABLE
edb=# BEGIN
  INSERT INTO payment_details_tab VALUES (4000, '1234-1234-1234-1234');
  INSERT INTO payment_details_tab VALUES (4001, '2345-2345-2345-2345');
END;
EDB-SPL Procedure successfully completed
edb=# CREATE USER redact_user;
CREATE ROLE
edb=# GRANT SELECT ON payment_details_tab TO redact_user;
GRANT
\c edb base_user
BEGIN
  DBMS_REDACT.add_policy(
    object_schema
                               => 'public',
    object_name
                              => 'payment_details_tab',
                               => 'redactPolicy_001',
    policy_name
                              => 'redactPolicy_001 for payment_details_tab table',
    policy_description
                               => 'customer_id',
    column_name
                         => DBMS_REDACT.full,
    function_type
    expression
                              => '1=1',
    enable
                               => TRUE);
END;
Redacted Result:
edb=# \c edb redact_user
You are now connected to database "edb" as user "redact_user".
edb=> select customer_id from payment_details_tab order by 1;
 customer_id
           0
           0
(2 rows)
```

ALTER POLICY

The alter_policy procedure alters or modifies an existing data redaction policy for a table.

```
expression
                               IN VARCHAR2 DEFAULT NULL,
                           IN VARCHAR2 DEFAULT NULL,
regexp_pattern
                               IN VARCHAR2 DEFAULT NULL,
regexp_replace_string
regexp_position IN INTEGER DEFAULT DBMS_REDACT.RE_BEGINNING,
regexp_occurrence IN INTEGER DEFAULT DBMS_REDACT.RE_ALL,
regexp_match_parameter
                           IN VARCHAR2 DEFAULT NULL,
policy_description
                              IN VARCHAR2 DEFAULT NULL,
column_description
                              IN VARCHAR2 DEFAULT NULL,
custom_function_expression IN VARCHAR2 DEFAULT NULL
)
```

Parameters

<object_schema>

Specifies the name of the schema in which the object resides and on which the data redaction policy will be altered. If you specify NULL then the given object is searched by the order specified by search_path setting.

<object_name>

Name of the table to which to alter a data redaction policy.

<policy_name>

Name of the policy to be altered.

<action>

The action to perform. For more information about action parameters see, DBMS_REDACT Constants and Function

<column_name>

Name of the column to which the redaction policy applies.

<function_type>

The type of redaction function to be used. The possible values are NONE, FULL, PARTIAL, RANDOM, REGEXP, and CUSTOM.

<function_parameters>

Specifies the function parameters for the redaction function.

<expression>

Specifies the Boolean expression for the table and determines how the policy is to be applied. The redaction occurs if this policy expression is evaluated to TRUE.

<regexp_pattern>

Enables the use of regular expressions to redact data. If the regexp_pattern does not match the data, then the NULL value is returned.

<regexp_replace_string>

Specifies the replacement string value.

<regexp_position>

Specifies the position of a character where search must begin. By default, the function parameter is RE_BEGINNING .

<regexp_occurence>

Specifies the replacement occurrence of a substring. If the constant is RE_ALL , then the replacement of each matching substring occurs. If the constant is RE_FIRST , then the replacement of the first matching substring occurs.

```
<regexp_match_parameter>
```

Note

For more information on constants, function_parameters, or regexp (regular expressions) see, Using DBMS_REDACT Constants and Function Parameters.

```
<policy_description>
```

Specify the description of a redaction policy.

```
<column_description>
```

Description of the column to be redacted. The column_description is not supported, but if you specify the description for a column then, you will get a warning message.

```
<custom_function_expression>
```

The custom_function_expression is applicable only for the CUSTOM redaction type. The custom_function_expression is a function expression that is, schema-qualified function with a parameter such as schema_name.function_name (argument1, ...)that allows a user to use their redaction logic to redact the column data.

Example

The following example illustrates to alter a policy partial redaction for values in the payment_details_tab table card_string (usually a credit card number) column.

```
\c edb base _user
   BEGIN
     DBMS_REDACT.alter_policy (
      object_schema
                              => 'public',
      object_name
                             => 'payment_details_tab',
                             => 'redactPolicy_001',
      policy_name
                             => DBMS_REDACT.ADD_COLUMN,
      action
                            => 'card_string',
      column_name
      END;
Redacted Result:
edb=# \c - redact_user
You are now connected to database "edb" as user "redact_user".
edb=> SELECT * FROM payment_details_tab;
customer_id | card_string
         0 | ****-****-1234
         0 | ****-****-2345
(2 rows)
```

DISABLE_POLICY

The disable_policy procedure disables an existing data redaction policy.

<object_name>

Name of the table for which to disable a data redaction policy.

```
<policy_name>
```

Name of the policy to be disabled.

Example

The following example illustrates how to disable a policy.

```
\c edb base_user

BEGIN
   DBMS_REDACT.disable_policy(
    object_schema => 'public',
    object_name => 'payment_details_tab',
    policy_name => 'redactPolicy_001');
END;
```

Redacted Result: Data is no longer redacted after disabling a policy.

```
DBMS_REDACT_ENABLE_POLICY
```

ENABLE_POLICY

The enable_policy procedure enables the previously disabled data redaction policy.

Parameters

```
<object_schema>
```

Specifies the name of the schema in which the object resides and on which the data redaction policy will be applied. If you specify NULL then the given object is searched by the order specified by search_path setting.

```
<object_name>
```

Name of the table to which to enable a data redaction policy.

```
<policy_name>
```

Name of the policy to be enabled.

Example

```
The following example illustrates how to enable a policy.
```

```
\c edb base_user

BEGIN
   DBMS_REDACT.enable_policy(
    object_schema => 'public',
    object_name => 'payment_details_tab',
    policy_name => 'redactPolicy_001');
END;

Redacted Result: Data is redacted after enabling a policy.
```

DROP_POLICY

DBMS_REDACT_DROP_POLICY

The drop_policy procedure drops a data redaction policy by removing the masking policy from a table.

Parameters

```
<object_schema>
```

Specifies the name of the schema in which the object resides and on which the data redaction policy will be applied. If you specify NULL then the given object is searched by the order specified by search_path setting.

```
<object_name>
```

Name of the table from which to drop a data redaction policy.

```
<policy_name>
```

Name of the policy to be dropped.

Example

The following example illustrates how to drop a policy.

```
\c edb base_user

BEGIN
   DBMS_REDACT.drop_policy(
    object_schema => 'public',
    object_name => 'payment_details_tab',
    policy_name => 'redactPolicy_001');
```

Redacted Result: The server drops the specified policy.

UPDATE FULL REDACTION VALUES

The update_full_redaction_values procedure updates the default displayed values for a data redaction policy and these default values can be viewed using the redaction_values_for_type_full view that use the full redaction type.

```
PROCEDURE update_full_redaction_values (
number_val
                 IN NUMBER
                                    DEFAULT NULL,
binfloat val
                 IN FLOAT4
                                    DEFAULT NULL,
bindouble_val IN FLOAT8
                                    DEFAULT NULL,
char_val
                 IN CHAR
                                         DEFAULT NULL.
varchar_val
                      IN VARCHAR2
                                             DEFAULT NULL,
                                    DEFAULT NULL,
nchar_val
                 IN NCHAR
                 IN NVARCHAR2
                                             DEFAULT NULL,
nvarchar_val
                 IN DATE
                                         DEFAULT NULL,
datecol_val
            IN TIMESTAMP
                                         DEFAULT NULL,
ts val
tswtz_val
                 IN TIMESTAMPTZ
                                             DEFAULT NULL,
                 IN BLOB
                                         DEFAULT NULL,
blob_val
                                         DEFAULT NULL,
clob_val
                 IN CLOB
nclob_val
                 IN CLOB
                                         DEFAULT NULL
)
Parameters
<number_val>
    Updates the default value for columns of the NUMBER datatype.
<br/><br/>binfloat_val>
    The FLOAT4 datatype is a random value. The binary float datatype is not supported.
<br/><br/>bindouble_val>
    The FLOAT8 datatype is a random value. The binary double datatype is not supported.
<char_val>
    Updates the default value for columns of the CHAR datatype.
<varchar_val>
    Updates the default value for columns of the VARCHAR2 datatype.
<nchar_val>
    The nchar_val is mapped to CHAR datatype and returns the CHAR value.
<nvarchar_val>
    The nvarchar_val is mapped to VARCHAR2 datatype and returns the VARCHAR value.
<datecol_val>
    Updates the default value for columns of the DATE datatype.
<ts_val>
    Updates the default value for columns of the TIMESTAMP datatype.
<tswtz_val>
    Updates the default value for columns of the TIMESTAMPTZ datatype.
<blob_val>
```

Updates the default value for columns of the BLOB datatype.

```
<clob_val>
```

Updates the default value for columns of the CLOB datatype.

```
<nclob_val>
```

The nclob_val is mapped to CLOB datatype and returns the CLOB value.

Example

The following example illustrates how to update the full redaction values but before updating the values, you can:

```
1. View the default values using redaction_values_for_type_full view as shown below:
edb=# \x
Expanded display is on.
edb=# SELECT number_value, char_value, varchar_value, date_value,
       timestamp_value, timestamp_with_time_zone_value, blob_value, clob_value
FROM redaction_values_for_type_full;
-Γ RECORD 1 ]----+
number_value
char_value
                               Т
varchar_value
date_value
                               | 01-JAN-01 00:00:00
timestamp_value
                               | 01-JAN-01 01:00:00
timestamp_with_time_zone_value | 31-DEC-00 20:00:00 -05:00
blob_value
                               | \x5b72656461637465645d
clob value
                               | [redacted]
(1 row)
2. Now, update the default values for full redaction type. The NULL values will be ignored. c edb base_user
edb=# BEGIN
    DBMS_REDACT.update_full_redaction_values (
    number_val => 9999999,
    char_val => 'Z',
    varchar_val => 'V'.
    datecol_val => to_date('17/10/2018', 'DD/MM/YYYY'),
    ts_val => to_timestamp('17/10/2018 11:12:13', 'DD/MM/YYYY HH24:MI:SS'),
    tswtz_val => NULL,
    blob_val => 'NEW REDACTED VALUE'.
    clob_val => 'NEW REDACTED VALUE');
END:
  3. You can now see the updated values using redaction values for type full view.
EDB-SPL Procedure successfully completed
edb=# SELECT number_value, char_value, varchar_value, date_value,
       timestamp_value, timestamp_with_time_zone_value, blob_value, clob_value
FROM redaction_values_for_type_full;
-[ RECORD 1 ]-----
number_value
                               1 9999999
char value
                               ΙZ
varchar_value
                               ΙV
                               | 17-0CT-18 00:00:00
date_value
timestamp_value
                               | 17-0CT-18 11:12:13
timestamp_with_time_zone_value | 31-DEC-00 20:00:00 -05:00
blob_value
                           | \x4e45572052454441435445442056414c5545
clob_value
                               I NEW REDACTED VALUE
(1 row)
Redacted Result:
```

```
edb=# \c edb redact_user
```

You are now connected to database "edb" as user "redact_user".

5.3.14 DBMS RLS

The DBMS_RLS package enables the implementation of Virtual Private Database on certain Advanced Server database objects.

Function/Procedure

ADD_POLICY(<object_schema>, <object_name>, <function_schema>, <policy_function> [, <statement_type="color: blue;">statement_type="color: blue;">statement_type="color: blue;">tope="color:
ENABLE_POLICY(<object_schema>, <object_name>, <policy_name>, <enable>)

Advanced Server's implementation of DBMS_RLS is a partial implementation when compared to Oracle's version. Only those functions and procedures listed in the table above are supported.

Virtual Private Database is a type of fine-grained access control using security policies. *Fine-grained access control* in Virtual Private Database means that access to data can be controlled down to specific rows as defined by the security policy.

The rules that encode a security policy are defined in a *policy function*, which is an SPL function with certain input parameters and return value. The *security policy* is the named association of the policy function to a particular database object, typically a table.

Note

In Advanced Server, the policy function can be written in any language supported by Advanced Server such as SQL, PL/pgSQL and SPL.

Note

The database objects currently supported by Advanced Server Virtual Private Database are tables. Policies cannot be applied to views or synonyms.

The advantages of using Virtual Private Database are the following:

- Provides a fine-grained level of security. Database object level privileges given by the GRANT command determine access privileges to the entire instance of a database object, while Virtual Private Database provides access control for the individual rows of a database object instance.
- A different security policy can be applied depending upon the type of SQL command (INSERT, UPDATE, DELETE, o
).
- The security policy can vary dynamically for each applicable SQL command affecting the database object depending upon factors such as the session user of the application accessing the database object.
- Invocation of the security policy is transparent to all applications that access the database object and thus, individual applications do not have to be modified to apply the security policy.
- Once a security policy is enabled, it is not possible for any application (including new applications) to circumvent the security policy except by the system privilege noted by the following.
- Even superusers cannot circumvent the security policy except by the system privilege noted by the following.

Note

The only way security policies can be circumvented is if the EXEMPT ACCESS POLICY system privilege has been granted to a user. The EXEMPT ACCESS POLICY privilege should be granted with extreme care as a user with this privilege is exempted from all policies in the database.

The DBMS_RLS package provides procedures to create policies, remove policies, enable policies, and disable policies.

The process for implementing Virtual Private Database is as follows:

- Create a policy function. The function must have two input parameters of type VARCHAR2. The first input parameter is for the schema containing the database object to which the policy is to apply and the second input parameter is for the name of that database object. The function must have a VARCHAR2 return type. The function must return a string in the form of a WHERE clause predicate. This predicate is dynamically appended as an AND condition to the SQL command that acts upon the database object. Thus, rows that do not satisfy the policy function predicate are filtered out from the SQL command result set.
- Use the ADD_POLICY procedure to define a new policy, which is the association of a policy function with
 a database object. With the ADD_POLICY procedure, you can also specify the types of SQL commands
 (INSERT, UPDATE, DELETE, or SELECT) to which the policy is to apply, whether or not to enable
 the policy at the time of its creation, and if the policy should apply to newly inserted rows or the modified
 image of updated rows.
- Use the ENABLE_POLICY procedure to disable or enable an existing policy.
- Use the DROP_POLICY procedure to remove an existing policy. The DROP_POLICY procedure does not drop the policy function or the associated database object.

Once policies are created, they can be viewed in the catalog views, compatible with Oracle databases: ALL_POLICIES, DBA_POLICIES, or USER_POLICIES. The supported compatible views are listed in the Database Compatibility for Oracle Developers Reference Guide, available at the EnterpriseDB website at:

https://www.enterprisedb.com/edb-docs/

The SYS_CONTEXT function is often used with DBMS_RLS . The signature is:

SYS_CONTEXT(<namespace>, <attribute>)

Where:

<namespace> is a VARCHAR2 ; the only accepted value is USERENV . Any other value will
return NULL .

<attribute> is a VARCHAR2 . <attribute> may be:

attribute Value	Equivalent Value
SESSION_USER CURRENT_USER CURRENT_SCHEMA HOST IP_ADDRESS SERVER_HOST	pg_catalog.session_user pg_catalog.current_user pg_catalog.current_schema pg_catalog.inet_host pg_catalog.inet_client_addr pg_catalog.inet_server_addr

Note

The examples used to illustrate the DBMS_RLS package are based on a modified copy of the sample emp table provided with Advanced Server along with a role named salesmgr that is granted all privileges on the table. You can create the modified copy of the emp table named vpemp and the salesmgr role as shown by the following:

```
CREATE TABLE public.vpemp AS SELECT empno, ename, job, sal, comm, deptno FROM emp; ALTER TABLE vpemp ADD authid VARCHAR2(12); UPDATE vpemp SET authid = 'researchmgr' WHERE deptno = 20; UPDATE vpemp SET authid = 'salesmgr' WHERE deptno = 30; SELECT * FROM vpemp;
```

•		job l			•	authid +
7782 İ (CLARK I N	MANAGER I PRESIDENT I	2450.00	İ	•	İ

```
7934 | MILLER | CLERK
                           | 1300.00 |
                                                    10 I
                          l 800.00 l
                                                    20 | researchmgr
 7369 | SMITH | CLERK
 7566 | JONES | MANAGER | 2975.00 |
                                              1
                                                    20 | researchmar
 7788 | SCOTT | ANALYST | 3000.00 |
                                                    20 | researchmgr
                                              П
 7876 | ADAMS
              l CLERK
                           | 1100.00 |
                                                    20 | researchmgr
                                              20 | researchmgr
 7902 | FORD
               I ANALYST
                           3000.00 l
  7499 | ALLEN | SALESMAN
                          | 1600.00 |
                                        300.00 I
                                                    30 | salesmgr
 7521 | WARD
               I SALESMAN
                          | 1250.00 | 500.00 |
                                                    30 | salesmgr
 7654 | MARTIN | SALESMAN
                          | 1250.00 | 1400.00 |
                                                    30 | salesmgr
 7698 | BLAKE | MANAGER
                          | 2850.00 |
                                                    30 | salesmar
                                                    30 | salesmar
 7844 | TURNER | SALESMAN | 1500.00 |
                                          0.00 |
 7900 | JAMES | CLERK
                           1 950.00 1
                                              30 | salesmgr
(14 rows)
```

CREATE ROLE salesmgr WITH LOGIN PASSWORD 'password'; GRANT ALL ON vpemp TO salesmgr;
DBMS RLSADD POLICY:

ADD_POLICY

The ADD_POLICY procedure creates a new policy by associating a policy function with a database object. You must be a superuser to execute this procedure.

```
ADD_POLICY(<object_schema> VARCHAR2, <object_name> VARCHAR2,
<policy_name> VARCHAR2, <function_schema> VARCHAR2,
<policy_function> VARCHAR2
[, <statement_types> VARCHAR2
[, <update_check> BOOLEAN
[, <enable> BOOLEAN
[, <static_policy> BOOLEAN
[, <policy_type> INTEGER
[, <long_predicate> BOOLEAN
[, <sec_relevant_cols> VARCHAR2
[, <sec_relevant_cols_opt> INTEGER ]]]]]]]]))
```

Parameters

<object_schema>

Name of the schema containing the database object to which the policy is to be applied.

<object_name>

Name of the database object to which the policy is to be applied. A given database object may have more than one policy applied to it.

<policy_name>

Name assigned to the policy. The combination of database object (identified by <object_schema> and <object_name>) and policy name must be unique within the database.

<function_schema>

Name of the schema containing the policy function.

Note

The policy function may belong to a package in which case <function_schema> must contain the name of the schema in which the package is defined.

<policy_function>

Name of the SPL function that defines the rules of the security policy. The same function may be specified in more than one policy.

Note

The policy function may belong to a package in which case <policy_function> must also contain the package name in dot notation (that is, <package_name>.<function_name>).

<statement_types>

Comma-separated list of SQL commands to which the policy applies. Valid SQL commands are INSERT, UPDATE, DELETE, and SELECT. The default is INSERT, UPDATE, DELETE, SELECT

Note

Advanced Server accepts INDEX as a statement type, but it is ignored. Policies are not applied to index operations in Advanced Server.

<update_check>

Applies to INSERT and UPDATE SQL commands only.

When set to TRUE, the policy is applied to newly inserted rows and to the modified image of updated rows. If any of the new or modified rows do not qualify according to the policy function predicate, then the INSERT or UPDATE command throws an exception and no rows are inserted or modified by the INSERT or UPDATE command.

When set to FALSE, the policy is not applied to newly inserted rows or the modified image of updated rows. Thus, a newly inserted row may not appear in the result set of a subsequent SQL command that invokes the same policy. Similarly, rows which qualified according to the policy prior to an UPDATE command may not appear in the result set of a subsequent SQL command that invokes the same policy.

The default is FALSE .

<enable>

When set to TRUE , the policy is enabled and applied to the SQL commands given by the <statement_types> parameter. When set to FALSE the policy is disabled and not applied to any SQL commands. The policy can be enabled using the ENABLE_POLICY procedure. The default is TRUE .

<static_policy>

In Oracle, when set to TRUE, the policy is *static*, which means the policy function is evaluated once per database object the first time it is invoked by a policy on that database object. The resulting policy function predicate string is saved in memory and reused for all invocations of that policy on that database object while the database server instance is running.

When set to FALSE, the policy is *dynamic*, which means the policy function is re-evaluated and the policy function predicate string regenerated for all invocations of the policy.

The default is FALSE .

Note

In Oracle 10g, the <policy_type> parameter was introduced, which is intended to replace the <static_policy> parameter. In Oracle, if the <policy_type> parameter is not set to its de-

fault value of NULL , the <policy_type> parameter setting overrides the <static_policy> setting.

Note

The setting of <static_policy> is ignored by Advanced Server. Advanced Server implements only the dynamic policy, regardless of the setting of the <static_policy> parameter.

<policy_type>

In Oracle, determines when the policy function is re-evaluated, and hence, if and when the predicate string returned by the policy function changes. The default is NULL .

Note

The setting of this parameter is ignored by Advanced Server. Advanced Server always assumes a dynamic policy.

<long_predicate>

In Oracle, allows predicates up to 32K bytes if set to TRUE, otherwise predicates are limited to 4000 bytes. The default is FALSE.

Note

The setting of this parameter is ignored by Advanced Server. An Advanced Server policy function can return a predicate of unlimited length for all practical purposes.

```
<sec_relevant_cols>
```

Comma-separated list of columns of <object_name> . Provides column-level Virtual Private Database for the listed columns. The policy is enforced if any of the listed columns are referenced in a SQL command of a type listed in <statement_types> . The policy is not enforced if no such columns are referenced.

```
<sec_relevant_cols_opt>
```

In Oracle, if <code><sec_relevant_cols_opt></code> is set to <code>DBMS_RLS.ALL_ROWS</code> (INTEGER constant of value 1), then the columns listed in <code><sec_relevant_cols></code> return <code>NULL</code> on all rows where the applied policy predicate is false. (If <code><sec_relevant_cols_opt></code> is not set to <code>DBMS_RLS.ALL_ROWS</code>, these rows would not be returned at all in the result set.) The default is <code>NULL</code>.

Note

Advanced Server does not support the DBMS_RLS.ALL_ROWS functionality. Advanced Server throws an error if sec_relevant_cols_opt is set to DBMS_RLS.ALL_ROWS (INTEGER value of 1).

Examples

This example uses the following policy function:

This function generates the predicate $authid = SYS_CONTEXT('USERENV', 'SESSION_USER')$, which is added to the WHERE clause of any SQL command of the type specified in the ADD_POLICY procedure.

This limits the effect of the SQL command to those rows where the content of the authid column is the same as the session user.

Note

This example uses the SYS_CONTEXT function to return the login user name. In Oracle the SYS_CONTEXT function is used to return attributes of an *application context*. The first parameter of the SYS_CONTEXT function is the name of an application context while the second parameter is the name of an attribute set within the application context. USERENV is a special built-in namespace that describes the current session. Advanced Server does not support application contexts, but only this specific usage of the SYS_CONTEXT function.

The following anonymous block calls the ADD_POLICY procedure to create a policy named secure_update to be applied to the vpemp table using function verify_session_user whenever an INSERT, UPDATE, or DELETE SQL command is given referencing the vpemp table.

```
DECLARE
    v_object_schema
                             VARCHAR2(30) := 'public';
                             VARCHAR2(30) := 'vpemp';
    v_object_name
                             VARCHAR2(30) := 'secure_update';
    v_policy_name
                             VARCHAR2(30) := 'enterprisedb';
    v_function_schema
                             VARCHAR2(30) := 'verify_session_user';
    v_policy_function
                             VARCHAR2(30) := 'INSERT, UPDATE, DELETE';
    v_statement_types
    v_update_check
                             BOOLEAN
                                          := TRUE;
    v_enable
                             BOOLEAN
                                          := TRUE;
BEGIN
    DBMS_RLS.ADD_POLICY(
        v_object_schema,
        v_object_name,
        v_policy_name,
        v_function_schema,
        v_policy_function,
        v_statement_types,
        v_update_check,
        v_enable
    );
END;
```

After successful creation of the policy, a terminal session is started by user salesmgr. The following query shows the content of the vpemp table:

```
edb=# \c edb salesmgr
Password for user salesmgr:
You are now connected to database "edb" as user "salesmgr".
edb=> SELECT * FROM vpemp;
 empno I ename I
                                sal
                                         comm
                                                l deptno l
                                                             authid
 7782 | CLARK | MANAGER
                          | 2450.00 |
                                                Ι
                                                      10 I
                | PRESIDENT |
 7839 | KING
                              5000.00 l
                                                10 I
 7934 | MILLER | CLERK
                                                      10 I
                            -
                              1300.00 l
                                                7369 | SMITH
               I CLERK
                            Ι
                               800.00
                                                      20 | researchmar
                                                1
 7566 | JONES
               I MANAGER
                            | 2975.00 |
                                                1
                                                      20 | researchmar
 7788 | SCOTT
               I ANALYST
                            1 3000.00 I
                                                П
                                                      20 | researchmgr
 7876 | ADAMS
               l CLERK
                            | 1100.00 |
                                                П
                                                      20 | researchmar
 7902 | FORD
                I ANALYST
                            1 3000.00 I
                                                      20 | researchmar
 7499 | ALLEN | SALESMAN | 1600.00 |
                                         300.00 I
                                                      30 | salesmgr
 7521 | WARD
                I SALESMAN
                           l 1250.00 l
                                         500.00 I
                                                      30 | salesmgr
                           7654 | MARTIN | SALESMAN
                              1250.00 | 1400.00 |
                                                      30 | salesmar
 7698 | BLAKE
               I MANAGER
                           | 2850.00 |
                                                1
                                                      30 | salesmgr
```

```
7844 | TURNER | SALESMAN | 1500.00 | 0.00 | 30 | salesmgr
7900 | JAMES | CLERK | 950.00 | 30 | salesmgr
(14 rows)
```

An unqualified UPDATE command (no WHERE clause) is issued by the salesmgr user:

```
edb=> UPDATE vpemp SET comm = sal * .75;
UPDATE 6
```

Instead of updating all rows in the table, the policy restricts the effect of the update to only those rows where the authid column contains the value salesmgr as specified by the policy function predicate authid = SYS_CONTEXT('USERENV', 'SESSION_USER').

The following query shows that the comm column has been changed only for those rows where authid contains salesmgr. All other rows are unchanged.

```
edb=> SELECT * FROM vpemp;
 empno I ename I
                      job
                             sal | comm | deptno |
7782 | CLARK | MANAGER | 2450.00 |
                                               10 l
                 | PRESIDENT | 5000.00 |
                                                  - 1
  7839 | KING
                                                           10 I
  7934 | MILLER | CLERK | 1300.00 |
                                                    10 I
                                                  I 20 | researchmgrI 20 | researchmgrI 20 | researchmgr
  7369 | SMITH | CLERK
                             l 800.00 l
  7566 | JONES | MANAGER | 2975.00 |
  7788 | SCOTT | ANALYST | 3000.00 |
  7876 | ADAMS | CLERK
                             | 1100.00 |
                                                   20 I researchmar
  7902 | FORD | ANALYST | 3000.00 |
                                                   20 | researchmgr
 7499 | ALLEN | SALESMAN | 1600.00 | 1200.00 | 7521 | WARD | SALESMAN | 1250.00 | 937.50 | 7654 | MARTIN | SALESMAN | 1250.00 | 937.50 | 7698 | BLAKE | MANAGER | 2850.00 | 2137.50 | 7844 | TURNER | SALESMAN | 1500.00 | 1100.00 |
                                                          30 | salesmgr
                                                           30 | salesmar
                                                           30 | salesmgr
                                                           30 | salesmgr
  7844 | TURNER | SALESMAN
                             | 1500.00 | 1125.00 |
                                                           30 | salesmar
  7900 | JAMES | CLERK
                             | 950.00 | 712.50 |
                                                           30 | salesmar
(14 rows)
```

Furthermore, since the <update_check> parameter was set to TRUE in the ADD_POLICY procedure, the following INSERT command throws an exception since the value given for the authid column, researchmgr, does not match the session user, which is salesmgr, and hence, fails the policy.

```
edb=> INSERT INTO vpemp VALUES (9001, 'SMITH', 'ANALYST', 3200.00, NULL, 20, 'researchmgr'); ERROR: policy with check option violation

DETAIL: Policy predicate was evaluated to FALSE with the updated values
```

If <update_check> was set to FALSE , the preceding INSERT command would have succeeded.

The following example illustrates the use of the <sec_relevant_cols> parameter to apply a policy only when certain columns are referenced in the SQL command. The following policy function is used for this example, which selects rows where the employee salary is less than 2000.

```
v_object_name
                            VARCHAR2(30) := 'vpemp';
                            VARCHAR2(30) := 'secure_salary';
    v_policy_name
                           VARCHAR2(30) := 'enterprisedb';
    v_function_schema
   v_policy_function
                           VARCHAR2(30) := 'sal_lt_2000';
                            VARCHAR2(30) := 'SELECT';
    v_statement_types
                            VARCHAR2(30) := 'sal,comm';
    v_sec_relevant_cols
BEGIN
   DBMS_RLS.ADD_POLICY(
       v_object_schema,
       v_object_name,
       v_policy_name,
       v_function_schema,
       v_policy_function,
       v_statement_types,
       sec_relevant_cols => v_sec_relevant_cols
END;
```

If a query does not reference columns sal or comm, then the policy is not applied. The following query returns all 14 rows of table vpemp:

edb=# SELECT empno, ename, job, deptno, authid FROM vpemp;

```
        empno | ename | job | deptno | authid

        7782 | CLARK | MANAGER | 10 |

        7839 | KING | PRESIDENT | 10 |

        7934 | MILLER | CLERK | 10 |

        7369 | SMITH | CLERK | 20 | researchmgr

        7566 | JONES | MANAGER | 20 | researchmgr

        7788 | SCOTT | ANALYST | 20 | researchmgr

        7876 | ADAMS | CLERK | 20 | researchmgr

        7902 | FORD | ANALYST | 20 | researchmgr

        7499 | ALLEN | SALESMAN | 30 | salesmgr

        7521 | WARD | SALESMAN | 30 | salesmgr

        7698 | BLAKE | MANAGER | 30 | salesmgr

        7844 | TURNER | SALESMAN | 30 | salesmgr

        7900 | JAMES | CLERK | 30 | salesmgr

        (14 rows)
```

If the query references the sal or comm columns, then the policy is applied to the query eliminating any rows where sal is greater than or equal to 2000 as shown by the following:

```
edb=# SELECT empno, ename, job, sal, comm, deptno, authid FROM vpemp; empno | ename | job | sal | comm | deptno | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid | authid
```

DROP_POLICY

DBMS RLS DROP POLICY

The DROP_POLICY procedure deletes an existing policy. The policy function and database object associated with the policy are not deleted by the DROP_POLICY procedure.

You must be a superuser to execute this procedure.

```
DROP_POLICY(<object_schema> VARCHAR2, <object_name> VARCHAR2 ,
<policy_name> VARCHAR2)
```

Parameters

```
<object_schema>
```

Name of the schema containing the database object to which the policy applies.

```
<object_name>
```

Name of the database object to which the policy applies.

```
<policy_name>
```

Name of the policy to be deleted.

Examples

The following example deletes policy secure_update on table public.vpemp:

ENABLE_POLICY

The ENABLE_POLICY procedure enables or disables an existing policy on the specified database object.

You must be a superuser to execute this procedure.

```
ENABLE_POLICY(<object_schema> VARCHAR2, <object_name> VARCHAR2 ,
<policy_name> VARCHAR2, <enable> BOOLEAN)
```

Parameters

```
<object_schema>
```

Name of the schema containing the database object to which the policy applies.

```
<object_name>
```

Name of the database object to which the policy applies.

```
<policy_name>
```

Name of the policy to be enabled or disabled.

<enable>

When set to TRUE, the policy is enabled. When set to FALSE, the policy is disabled.

Examples

The following example disables policy secure_update on table public.vpemp:

```
DECLARE
                             VARCHAR2(30) := 'public';
    v_object_schema
                             VARCHAR2(30) := 'vpemp';
    v_object_name
                             VARCHAR2(30) := 'secure_update';
    v_policy_name
                             BOOLEAN := FALSE;
    v_enable
BEGIN
    DBMS_RLS.ENABLE_POLICY(
        v_object_schema,
        v_object_name,
        v_policy_name,
        v_enable
END;
```

5.3.15.0 DBMS_SCHEDULER

The DBMS_SCHEDULER package provides a way to create and manage Oracle-styled jobs, programs and job schedules. The DBMS_SCHEDULER package implements the following functions and procedures:

```
Function/Procedure
CREATE_JOB(<job_name>, <job_type>, <job_action>, <number_of_arguments>, <start_date>, <repeat_interval>, <end_
CREATE_JOB(<job_name>, comments>)
CREATE_PROGRAM(crogram_name, crogram_action, <number_of_arguments</pre>, <coi
CREATE_SCHEDULE( <schedule_name>, <start_date>, <repeat_interval>, <end_date>, <comments>)
DEFINE PROGRAM ARGUMENT( rogram name>, <argument position>, <argument name>, <argument type>, <def
DEFINE PROGRAM ARGUMENT( rogram name>, <argument position>, <argument name>, <argument type>, <out
DISABLE(<name>, <force>, <commit semantics>)
DROP JOB(<job name>, <force>, <defer>, <commit semantics>)
DROP PROGRAM(cpream name>, <force>)
DROP PROGRAM ARGUMENT( cprogram name>, <argument position>)
DROP_SCHEDULE(<schedule_name>, <force>)
ENABLE(<name>, <commit semantics>)
EVALUATE_CALENDAR_STRING( <calendar_string>, <start_date>, <return_date_after>, <next_run_date>)
RUN_JOB(<job_name>, <use_current_session>, <manually>)
SET_JOB_ARGUMENT_VALUE( < job_name>, < argument_position>, < argument_value>)
SET JOB _ARGUMENT_VALUE( < job_name>, < argument_name>, < argument_value>)
```

Advanced Server's implementation of DBMS_SCHEDULER is a partial implementation when compared to Oracle's version. Only those functions and procedures listed in the table above are supported.

The DBMS_SCHEDULER package is dependent on the pgAgent service; you must have a pgAgent service installed and running on your server before using DBMS_SCHEDULER.

Before using DBMS_SCHEDULER, a database superuser must create the catalog tables in which the DBMS_SCHEDULER programs, schedules and jobs are stored. Use the psql client to connect to the database, and invoke the command:

```
CREATE EXTENSION dbms_scheduler ;
```

By default, the dbms_scheduler extension resides in the contrib/dbms_scheduler_ext subdirectory (under the Advanced Server installation).

Note that after creating the DBMS_SCHEDULER tables, only a superuser will be able to perform a dump or reload of the database.

5.3.15.1 'Using Calendar Syntax to Specify a Repeating Interval'

The CREATE_JOB and CREATE_SCHEDULE procedures use Oracle-styled calendar syntax to define the interval with which a job or schedule is repeated. You should provide the scheduling information in the <repeat_interval> parameter of each procedure.

<repeat_interval> is a value (or series of values) that define the interval between the executions of the
scheduled job. Each value is composed of a token, followed by an equal sign, followed by the unit (or units) on
which the schedule will execute. Multiple token values must be separated by a semi-colon (;).

For example, the following value:

```
FREQ=DAILY; BYDAY=MON, TUE, WED, THU, FRI; BYHOUR=17; BYMINUTE=45
```

Defines a schedule that is executed each weeknight at 5:45.

The token types and syntax described in the table below are supported by Advanced Server:

5.3.15.2 CREATE JOB

Use the CREATE_JOB procedure to create a job. The procedure comes in two forms; the first form of the procedure specifies a schedule within the job definition, as well as a job action that will be invoked when the job executes:

The second form uses a job schedule to specify the schedule on which the job will execute, and specifies the name of a program that will execute when the job runs:

Parameters

```
<job_ame>
     <job_name> specifies the optionally schema-qualified name of the job being created.
<job_type>
```

<job_type> specifies the type of job. The current implementation of CREATE_JOB supports a
job type of PLSQL_BLOCK or STORED_PROCEDURE .

<job_action>

If <job_type> is PLSQL_BLOCK, <job_action> specifies the content of the PL/SQL block that will be invoked when the job executes. The block must be terminated with a semi-colon (;).

If <job_type> is STORED_PROCEDURE , <job_action> specifies the optionally schema-qualified name of the procedure.

<number_of_arguments>

<number_of_arguments> is an INTEGER value that specifies the number of arguments expected by the job. The default is 0 .

<start_date>

<start_date> is a TIMESTAMP WITH TIME ZONE value that specifies the first time that the
job is scheduled to execute. The default value is NULL , indicating that the job should be scheduled
to execute when the job is enabled.

<repeat_interval>

<repeat_interval> is a VARCHAR2 value that specifies how often the job will repeat. If a
<repeat_interval> is not specified, the job will execute only once. The default value is NULL

<end_date>

<end_date> is a TIMESTAMP WITH TIME ZONE value that specifies a time after which the job
will no longer execute. If a date is specified, the <end_date> must be after <start_date> .
The default value is NULL .

Please note that if an <end_date> is not specified and a <repeat_interval> is specified, the job will repeat indefinitely until it is disabled.

ogram_name>

am_name> is the name of a program that will be executed by the job.

<schedule_name>

<schedule_name> is the name of the schedule associated with the job.

<job_class>

<job_class> is accepted for compatibility and ignored.

<enabled>

<enabled> is a BOOLEAN value that specifies if the job is enabled when created. By default,
a job is created in a disabled state, with <enabled> set to FALSE . To enable a job, specify
a value of TRUE when creating the job, or enable the job with the DBMS_SCHEDULER.ENABLE
procedure.

<auto_drop>

The <auto_drop> parameter is accepted for compatibility and is ignored. By default, a job's status will be changed to DISABLED after the time specified in <end_date> .

<comments>

Use the <comments> parameter to specify a comment about the job.

Example

The following example demonstrates a call to the CREATE_JOB procedure:

The code fragment creates a job named $\mbox{update_log}$ that executes each weeknight at 5:00. The job executes a PL/SQL block that inserts the current timestamp into a logfile ($\mbox{my_log}$). Since no $\mbox{end_date}$ is specified, the job will execute until it is disabled by the DBMS_SCHEDULER.DISABLE procedure.

5.3.15.3 CREATE_PROGRAM

Use the CREATE_PROGRAM procedure to create a DBMS_SCHEDULER program. The signature is:

Parameters

```
action>
```

```
<number_of_arguments>
```

<enabled>

<enabled> specifies if the program is created enabled or disabled:

- If <enabled> is TRUE, the program is created enabled.
- If <enabled> is FALSE, the program is created disabled; use the DBMS_SCHEDULER.ENABLE program to enable a disabled program.

The default value is FALSE .

<comments>

Use the <comments> parameter to specify a comment about the program; by default, this parameter is NULL .

Example

The following call to the CREATE_PROGRAM procedure creates a program named update_log:

EXEC

update_log is a PL/SQL block that adds a row containing the current date and time to the my_log table. The program will be enabled when the CREATE_PROGRAM procedure executes.

5.3.15.4 CREATE_SCHEDULE

Use the CREATE_SCHEDULE procedure to create a job schedule. The signature of the CREATE_SCHEDULE procedure is:

```
create_schedule(
<schedule_name> IN VARCHAR2 ,
<start_date> IN TIMESTAMP WITH TIME ZONE DEFAULT NULL ,
<repeat_interval> IN VARCHAR2 ,
<end_date> IN TIMESTAMP WITH TIME ZONE DEFAULT NULL ,
<comments> IN VARCHAR2 DEFAULT NULL)
```

Parameters

```
<schedule_name>
```

<schedule_name> specifies the name of the schedule.

<start_date>

<start_date> is a TIMESTAMP WITH TIME ZONE value that specifies the date and time that
the schedule is eligible to execute. If a <start_date> is not specified, the date that the job is
enabled is used as the <start_date> . By default, <start_date> is NULL .

```
<repeat_interval>
```

```
<repeat_interval> is a VARCHAR2 value that specifies how often the job will repeat. If a
<repeat_interval> is not specified, the job will execute only once, on the date specified by
<start_date> .
```

Note

You must provide a value for either <start_date> or <repeat_interval> ; if both <start_date> and <repeat_interval> are NULL , the server will return an error.

```
<end_date> IN TIMESTAMP WITH TIME ZONE DEFAULT NULL
```

Please note that if a <repeat_interval> is specified and an <end_date> is not specified, the schedule will repeat indefinitely until it is disabled.

```
<comments> IN VARCHAR2 DEFAULT NULL)
```

Use the <comments> parameter to specify a comment about the schedule; by default, this parameter is NULL .

Example

The following code fragment calls
CREATE_SCHEDULE to create a schedule named weeknights_at_5:
EXEC

The schedule executes each weeknight, at 5:00 pm, effective after June 1, 2013. Since no end_date is specified, the schedule will execute indefinitely until it is disabled with DBMS_SCHEDULER.DISABLE.

5.3.15.5 DEFINE_PROGRAM_ARGUMENT

Use the DEFINE_PROGRAM_ARGUMENT procedure to define a program argument. The DEFINE_PROGRAM_ARGUMENT procedure comes in two forms; the first form defines an argument with a default value:

The second form defines an argument without a default value:

Parameters

```
oprogram_name>
```

am_name> is the name of the program to which the arguments belong.

Example

The following code fragment uses the DEFINE_PROGRAM_ARGUMENT procedure to define the first and second arguments in a program named add_emp :

<out_argument> is not currently used; if specified, the value must be FALSE .

The first argument is an INTEGER value named dept_no that has a default value of 20. The second argument is a VARCHAR2 value named emp_name; the second argument does not have a default value.

5.3.15.6 DISABLE

Use the DISABLE procedure to disable a program or a job. The signature of the DISABLE procedure is:

```
DISABLE(
<name> IN VARCHAR2 ,
    <force> IN BOOLEAN DEFAULT FALSE ,
    <commit_semantics> IN VARCHAR2 DEFAULT 'STOP_ON_FIRST_ERROR')
```

Parameters

```
<name>
<name>
<name> specifies the name of the program or job that is being disabled.
<force>
<force> is accepted for compatibility, and ignored.
```

<commit_semantics>

<commit_semantics> instructs the server how to handle an error encountered while disabling a
program or job. By default, <commit_semantics> is set to STOP_ON_FIRST_ERROR , instructing the server to stop when it encounters an error. Any programs or jobs that were successfully
disabled prior to the error will be committed to disk.

The TRANSACTIONAL and ABSORB_ERRORS keywords are accepted for compatibility, and ignored.

Example

The following call to the DISABLE procedure disables a program named update_emp : DBMS_SCHEDULER.DISABLE('update_emp');

5.3.15.7 DROP JOB

Use the DROP_JOB procedure to DROP a job, DROP any arguments that belong to the job, and eliminate any future job executions. The signature of the procedure is:

Parameters

<job_name>

<job_name> specifies the name of the job that is being dropped.

<force>

<force> is accepted for compatibility, and ignored.

<defer>

<defer> is accepted for compatibility, and ignored.

<commit_semantics>

<commit_semantics> instructs the server how to handle an error encountered while dropping a
program or job. By default, <commit_semantics> is set to STOP_ON_FIRST_ERROR , instructing the server to stop when it encounters an error.

The TRANSACTIONAL and ABSORB_ERRORS keywords are accepted for compatibility, and ignored.

Example

The following call to DROP_JOB drops a job named update_log:

DBMS_SCHEDULER.DROP_JOB('update_log');

5.3.15.8 DROP_PROGRAM

The DROP_PROGRAM procedure

The signature of the DROP_PROGRAM procedure is:

Parameters

```
oprogram_name>
```

am_name> specifies the name of the program that is being dropped.

<force>

<force> is a BOOLEAN value that instructs the server how to handle programs with dependent jobs.

Specify FALSE to instruct the server to return an error if the program is referenced by a job.

Specify TRUE to instruct the server to disable any jobs that reference the program before dropping the program.

The default value is FALSE.

Example

```
The following call to DROP_PROGRAM drops a job named update_emp : DBMS_SCHEDULER.DROP_PROGRAM('update_emp');
```

5.3.15.9 DROP_PROGRAM_ARGUMENT

Use the DROP_PROGRAM_ARGUMENT procedure to drop a program argument. The DROP_PROGRAM_ARGUMENT procedure comes in two forms; the first form uses an argument position to specify which argument to drop:

The second form takes the argument name:

```
drop_program_argument(
  argument_name> IN VARCHAR2 ,
```

Parameters

Examples

The following call to DROP_PROGRAM_ARGUMENT drops the first argument in the update_emp program:

DBMS_SCHEDULER.DROP_PROGRAM_ARGUMENT('update_emp', 1);

```
The following call to DROP_PROGRAM_ARGUMENT drops an argument named emp_name : DBMS_SCHEDULER.DROP_PROGRAM_ARGUMENT(update_emp', 'emp_name');
```

5.3.15.10 DROP_SCHEDULE

Use the DROP_SCHEDULE procedure to drop a schedule. The signature is:

```
DROP_SCHEDULE(
<schedule_name IN VARCHAR2 ,
<force> IN BOOLEAN DEFAULT FALSE)
```

Parameters

<schedule_name>

<schedule_name> specifies the name of the schedule that is being dropped.

<force>

<force> specifies the behavior of the server if the specified schedule is referenced by any job:

- Specify FALSE to instruct the server to return an error if the specified schedule is referenced by a job. This is the default behavior.
- Specify TRUE to instruct the server to disable to any jobs that use the specified schedule before dropping the schedule. Any running jobs will be allowed to complete before the schedule is dropped.

Example

The following call to DROP_SCHEDULE drops a schedule named weeknights_at_5:

DBMS_SCHEDULER.DROP_SCHEDULE('weeknights_at_5', TRUE);

The server will disable any jobs that use the schedule before dropping the schedule.

5.3.15.11 ENABLE

Use the ENABLE procedure to enable a disabled program or job.

The signature of the ENABLE procedure is:

```
ENABLE(
<name> IN VARCHAR2 ,
<commit_semantics> IN VARCHAR2 DEFAULT 'STOP_ON_FIRST_ERROR')
```

Parameters

<name>

<name> specifies the name of the program or job that is being enabled.

```
<commit_semantics>
```

<commit_semantics> instructs the server how to handle an error encountered while enabling a
program or job. By default, <commit_semantics> is set to STOP_ON_FIRST_ERROR , instructing the server to stop when it encounters an error.

The TRANSACTIONAL and ABSORB_ERRORS keywords are accepted for compatibility, and ignored.

Example

The following call to DBMS_SCHEDULER.ENABLE enables the update_emp program:

5.3.15.12 EVALUATE CALENDAR STRING

Use the EVALUATE_CALENDAR_STRING procedure to evaluate the <repeat_interval> value specified when creating a schedule with the CREATE_SCHEDULE procedure. The EVALUATE_CALENDAR_STRING procedure will return the date and time that a specified schedule will execute without actually scheduling the job.

The signature of the EVALUATE_CALENDAR_STRING procedure is:

```
evaluate_calendar_string(
  <calendar_string> IN VARCHAR2 ,
  <start_date> IN TIMESTAMP WITH TIME ZONE ,
  <return_date_after> IN TIMESTAMP WITH TIME ZONE ,
  <next_run_date> OUT TIMESTAMP WITH TIME ZONE)
```

Parameters

```
<calendar_string>
```

<calendar_string> is the calendar string that describes a <repeat_interval> that is being
evaluated.

```
<start_date> IN TIMESTAMP WITH TIME ZONE
```

<start_date> is the date and time after which the <repeat_interval> will become valid.

```
<return_date_after>
```

Use the <return_date_after parameter> to specify the date and time that EVALUATE_CALENDAR_STRING should use as a starting date when evaluating the <repeat_interval> .

For example, if you specify a <return_date_after> value of 01-APR-13 09.00.00.000000, EVALUATE_CALE will return the date and time of the first iteration of the schedule after April 1st, 2013.

```
<next_run_date OUT TIMESTAMP WITH TIME ZONE</pre>
```

<next_run_date> is an OUT parameter that will contain the first occurrence of the schedule
after the date specified by the <return_date_after> parameter.

Example

The following example evaluates a calendar string and returns the first date and time that the schedule will be executed after June 15, 2013:

June 15, 2013 is a Saturday; the schedule will not execute until Monday, June 17, 2013 at 5:00 pm.

5.3.15.13 RUN JOB

Use the RUN_JOB procedure to execute a job immediately. The signature of the RUN_JOB procedure is:

```
run_job(
<job_name> IN VARCHAR2 ,
<use_current_session> IN BOOLEAN DEFAULT TRUE
```

Parameters

```
<job_name>
```

<job_name> specifies the name of the job that will execute.

```
<use_current_session>
```

By default, the job will execute in the current session. If specified, <use_current_session> must be set to TRUE ; if <use_current_session> is set to FALSE , Advanced Server will return an error.

Example

```
The following call to RUN_JOB executes a job named update_log:
```

DBMS_SCHEDULER.RUN_JOB('update_log', TRUE);

Passing a value of TRUE as the second argument instructs the server to invoke the job in the current session.

5.3.15.14 SET_JOB_ARGUMENT_VALUE

Use the SET_JOB_ARGUMENT_VALUE procedure to specify a value for an argument. The SET_JOB_ARGUMENT_VALUE procedure comes in two forms; the first form specifies which argument should be modified by position:

```
set_job_argument_value(
<job_name> IN VARCHAR2 ,
<argument_position> IN PLS_INTEGER ,
<argument_value> IN VARCHAR2)
```

The second form uses an argument name to specify which argument to modify:

```
set_job_argument_value(
<job_name> IN VARCHAR2 ,
<argument_name> IN VARCHAR2 ,
<argument_value> IN VARCHAR2)
```

Argument values set by the SET_JOB_ARGUMENT_VALUE procedure override any values set by default.

Parameters

```
<job_name>
```

<job_name> specifies the name of the job to which the modified argument belongs.

```
<argument_position>
```

Use <argument_position> to specify the argument position for which the value will be set.

```
<argument_name>
```

Use <argument_name> to specify the argument by name for which the value will be set.

```
<argument_value>
```

<argument_value> specifies the new value of the argument.

Examples

The following example assigns a value of 30 to the first argument in the update_emp job:

```
DBMS_SCHEDULER.SET_JOB_ARGUMENT_VALUE('update_emp', 1, '30');
```

The following example sets the emp_name argument to SMITH:

```
DBMS_SCHEDULER.SET_JOB_ARGUMENT_VALUE('update_emp', 'emp_name',
'SMITH');
```

5.3.16 DBMS_SESSION

Advanced Server provides support for the following DBMS_SESSION.SET_ROLE procedure:

Function/Procedure	Return Type	Description
SET_ROLE(<role_cmd>)</role_cmd>	n/a	Executes a SET ROLE statement followed by the string value specified in <role< td=""></role<>

Advanced Server's implementation of DBMS_SESSION is a partial implementation when compared to Oracle's version. Only DBMS_SESSION.SET_ROLE is supported.

SET_ROLE

The SET_ROLE procedure sets the current session user to the role specified in <role_cmd> . After invoking the SET_ROLE procedure, the current session will use the permissions assigned to the specified role. The signature of the procedure is:

```
SET_ROLE(<role_cmd>)
```

The SET_ROLE procedure appends the value specified for <role_cmd> to the SET_ROLE statement, and then invokes the statement.

Parameters

<role_cmd>

<role_cmd> specifies a role name in the form of a string value.

Example

The following call to the SET_ROLE procedure invokes the SET_ROLE command to set the identity of the current session user to manager:

```
edb=# exec DBMS_SESSION.SET_ROLE('manager');
```

5.3.17.0 DBMS_SQL

The DBMS_SQL package provides an application interface compatible with Oracle databases to the Enter-priseDB dynamic SQL functionality. With DBMS_SQL you can construct queries and other commands at run time (rather than when you write the application). EnterpriseDB Advanced Server offers native support for dynamic SQL; DBMS_SQL provides a way to use dynamic SQL in a fashion compatible with Oracle databases without modifying your application.

DBMS_SQL assumes the privileges of the current user when executing dynamic SQL statements.

Function/Procedure	Function or Procedure
BIND_VARIABLE(c, name, value [, out_value_size])	Procedure
BIND_VARIABLE_CHAR(c, name, value [, out_value_size])	Procedure
BIND_VARIABLE_RAW(c, name, value [, out_value_size])	Procedure
CLOSE_CURSOR(c IN OUT)	Procedure
COLUMN_VALUE(c, position, value OUT [, column_error OUT [, actual_length OUT]])	Procedure
COLUMN_VALUE_CHAR(c, position, value OUT [, column_error OUT [, actual_length OUT]])	Procedure
COLUMN_VALUE_RAW(c, position, value OUT [, column_error OUT [, actual_length OUT]])	Procedure
DEFINE_COLUMN(c, position, column [, column_size])	Procedure
DEFINE_COLUMN_CHAR(c, position, column, column_size)	Procedure
DEFINE_COLUMN_RAW(c, position, column, column_size)	Procedure
DESCRIBE_COLUMNS	Procedure
EXECUTE(c)	Function
EXECUTE_AND_FETCH(c [, exact])	Function
FETCH_ROWS(c)	Function
IS_OPEN(c)	Function
LAST_ROW_COUNT	Function
OPEN_CURSOR	Function
PARSE(c, statement, language_flag)	Procedure

Advanced Server's implementation of DBMS_SQL is a partial implementation when compared to Oracle's version. Only those functions and procedures listed in the table above are supported.

The following table lists the public variable available in the DBMS_SQL package.

Public Variables	Data Type	Value	Description
native	INTEGER	1	Provided for compatibility with Oracle syntax. See DBMS_SQL.PARSE for more in
V6	INTEGER	2	Provided for compatibility with Oracle syntax. See DBMS_SQL.PARSE for more in
V7	INTEGER	3	Provided for compatibility with Oracle syntax. See DBMS_SQL.PARSE for more in

5.3.17.1 BIND_VARIABLE

The BIND_VARIABLE procedure provides the capability to associate a value with an IN or IN OUT bind variable in a SQL command.

```
BIND_VARIABLE(c INTEGER, <name> VARCHAR2 ,

> <value> { BLOB | CLOB | DATE | FLOAT | INTEGER | NUMBER |

> TIMESTAMP | VARCHAR2 }

[, <out_value_size> INTEGER ])
```

Parameters

<C>

Cursor ID of the cursor for the SQL command with bind variables.

<name>

Name of the bind variable in the SQL command.

<value>

Value to be assigned.

<out_value_size>

If <name> is an IN OUT variable, defines the maximum length of the output value. If not specified, the length of <value> is assumed.

Examples

The following anonymous block uses bind variables to insert a row into the emp table.

```
DECLARE
    curid
                      INTEGER;
                      VARCHAR2(150) := 'INSERT INTO emp VALUES ' ||
    v_sql
                           '(:p_empno, :p_ename, :p_job, :p_mgr, ' ||
                           ':p_hiredate, :p_sal, :p_comm, :p_deptno)';
                      emp.empno%TYPE;
    v_empno
    v_ename
                      emp.ename%TYPE;
                      emp.job%TYPE;
    v_job
                      emp.mgr%TYPE;
    v_mgr
    v_hiredate
                      emp.hiredate%TYPE;
    v_sal
                      emp.sal%TYPE;
    V_COMM
                      emp.comm%TYPE;
                      emp.deptno%TYPE;
    v_deptno
                      INTEGER;
    v_status
BEGIN
    curid := DBMS_SOL.OPEN_CURSOR;
    DBMS_SQL.PARSE(curid,v_sql,DBMS_SQL.native);
             := 9001;
    v_empno
                := 'JONES';
    v_ename
                := 'SALESMAN';
    v_job
                := 7369;
    v_mgr
    v_hiredate := TO_DATE('13-DEC-07','DD-MON-YY');
                := 8500.00;
    v_sal
    v_comm
                := 1500.00;
                := 40:
    v_deptno
    DBMS_SQL.BIND_VARIABLE(curid,':p_empno',v_empno);
    DBMS_SQL.BIND_VARIABLE(curid,':p_ename',v_ename);
    DBMS_SQL.BIND_VARIABLE(curid,':p_job',v_job);
    DBMS_SQL.BIND_VARIABLE(curid,':p_mgr',v_mgr);
    DBMS_SQL.BIND_VARIABLE(curid,':p_hiredate',v_hiredate);
DBMS_SQL.BIND_VARIABLE(curid,':p_sal',v_sal);
DBMS_SQL.BIND_VARIABLE(curid,':p_comm',v_comm);
    DBMS_SQL.BIND_VARIABLE(curid,':p_deptno',v_deptno);
    v_status := DBMS_SQL.EXECUTE(curid);
    DBMS_OUTPUT.PUT_LINE('Number of rows processed: ' || v_status);
    DBMS_SQL.CLOSE_CURSOR(curid);
END;
Number of rows processed: 1
```

5.3.17.2 BIND_VARIABLE_CHAR

The BIND_VARIABLE_CHAR procedure provides the capability to associate a CHAR value with an IN or IN OUT bind variable in a SQL command.

```
BIND_VARIABLE_CHAR(<c> INTEGER, <name> VARCHAR2, <value> CHAR
[, <out_value_size> INTEGER ])
```

Parameters

<C>

Cursor ID of the cursor for the SQL command with bind variables.

<name>

Name of the bind variable in the SQL command.

<value>

Value of type CHAR to be assigned.

<out_value_size>

If <name> is an IN OUT variable, defines the maximum length of the output value. If not specified, the length of <value> is assumed.

5.3.17.3 BIND VARIABLE RAW

The BIND_VARIABLE_RAW procedure provides the capability to associate a RAW value with an IN or IN OUT bind variable in a SQL command.

```
BIND_VARIABLE_RAW(<c> INTEGER, <name> VARCHAR2, <value> RAW
[, <out_value_size> INTEGER])
```

Parameters

<C>

Cursor ID of the cursor for the SQL command with bind variables.

<name>

Name of the bind variable in the SQL command.

<value>

Value of type RAW to be assigned.

<out_value_size>

If <name> is an IN OUT variable, defines the maximum length of the output value. If not specified, the length of <value> is assumed.

5.3.17.4 CLOSE CURSOR

The CLOSE_CURSOR procedure closes an open cursor. The resources allocated to the cursor are released and it can no longer be used.

CLOSE_CURSOR(<c> IN OUT INTEGER)

Parameters

<C>

Cursor ID of the cursor to be closed.

Examples

The following example closes a previously opened cursor:

END;

5.3.17.5 COLUMN VALUE

```
The COLUMN_VALUE procedure defines a variable to receive a value from a cursor.
```

```
COLUMN_VALUE(<c> INTEGER, <position> INTEGER, <value> OUT { BLOB | > CLOB | DATE | FLOAT | INTEGER | NUMBER | TIMESTAMP | VARCHAR2 }
```

```
[, <column_error> OUT NUMBER [, <actual_length> OUT INTEGER ]])
```

Parameters

<C>

Cursor id of the cursor returning data to the variable being defined.

```
<position>
```

Position within the cursor of the returned data. The first value in the cursor is position 1.

<value>

Variable receiving the data returned in the cursor by a prior fetch call.

```
<column_error>
```

Error number associated with the column, if any.

```
<actual_length>
```

Actual length of the data prior to any truncation.

Examples

The following example shows the portion of an anonymous block that receives the values from a cursor using the COLUMN_VALUE procedure.

```
DECLARE
```

```
INTEGER;
   curid
                  NUMBER(4);
   v_empno
                  VARCHAR2(10);
   v_ename
   v_hiredate
                  DATE;
                  NUMBER(7,2);
   v_sal
                  NUMBER(7,2);
   V_COMM
   v_sql
                  VARCHAR2(50) := 'SELECT empno, ename, hiredate, sal, ' ||
                                 'comm FROM emp';
                  INTEGER;
   v_status
BEGIN
   L00P
       v_status := DBMS_SQL.FETCH_ROWS(curid);
       EXIT WHEN v_{status} = 0;
       DBMS_SQL.COLUMN_VALUE(curid,1,v_empno);
       DBMS_SQL.COLUMN_VALUE(curid,2,v_ename);
       DBMS_SQL.COLUMN_VALUE(curid,3,v_hiredate);
       DBMS_SQL.COLUMN_VALUE(curid,4,v_sal);
       TO_CHAR(v_hiredate,'yyyy-mm-dd') || ' ' ||
           TO_CHAR(v_sal,'9,999.99') | | ' ' | |
```

```
TO_CHAR(NVL(v_comm,0),'9,999.99'));
END LOOP;
DBMS_SQL.CLOSE_CURSOR(curid);
END;
```

5.3.17.6 COLUMN_VALUE_CHAR

The COLUMN_VALUE_CHAR procedure defines a variable to receive a CHAR value from a cursor.

COLUMN_VALUE_CHAR(<c> INTEGER, <position> INTEGER, <value> OUT CHAR

[, <column_error> OUT NUMBER [, <actual_length> OUT INTEGER]])

Parameters

<C>

Cursor id of the cursor returning data to the variable being defined.

<position>

Position within the cursor of the returned data. The first value in the cursor is position 1.

<value>

Variable of data type CHAR receiving the data returned in the cursor by a prior fetch call.

<column_error>

Error number associated with the column, if any.

<actual_length>

Actual length of the data prior to any truncation.

5.3.17.7 COLUMN_VALUE_RAW

The COLUMN_VALUE_RAW procedure defines a variable to receive a RAW value from a cursor.

COLUMN_VALUE_RAW(<c> INTEGER, <position> INTEGER, <value> OUT RAW

[, <column_error> OUT NUMBER [, <actual_length> OUT INTEGER]])

Parameters

<C>

Cursor id of the cursor returning data to the variable being defined.

<position>

Position within the cursor of the returned data. The first value in the cursor is position 1.

<value>

Variable of data type RAW receiving the data returned in the cursor by a prior fetch call.

<column_error>

Error number associated with the column, if any.

<actual_length>

Actual length of the data prior to any truncation.

252

5.3.17.8 DEFINE_COLUMN

The DEFINE_COLUMN procedure defines a column or expression in the SELECT list that is to be returned and retrieved in a cursor.

```
DEFINE_COLUMN(<c> INTEGER, <position> INTEGER, <column> { BLOB |
> CLOB | DATE | FLOAT | INTEGER | NUMBER | TIMESTAMP | VARCHAR2 }
   [, <column_size> INTEGER ])
```

Parameters

<C>

Cursor id of the cursor associated with the SELECT command.

<position>

Position of the column or expression in the SELECT list that is being defined.

<column>

A variable that is of the same data type as the column or expression in position <position> of the SELECT list .

```
<column_size>
```

The maximum length of the returned data. <column_size> must be specified only if <column> is VARCHAR2 . Returned data exceeding <column_size> is truncated to <column_size> characters.

Examples

The following shows how the empno, ename, hiredate, sal, and comm columns of the emp table are defined with the DEFINE_COLUMN procedure.

```
DECLARE
```

```
curid
                    INTEGER;
    v_empno
                    NUMBER(4);
    v_ename
                    VARCHAR2(10);
    v_hiredate
                    DATE;
    v_sal
                    NUMBER(7,2);
                    NUMBER(7,2);
    V_COMM
                    VARCHAR2(50) := 'SELECT empno, ename, hiredate, sal, ' ||
    v_sql
                                     'comm FROM emp';
                    INTEGER;
    v_status
BEGIN
    curid := DBMS_SQL.OPEN_CURSOR;
    DBMS_SQL.PARSE(curid,v_sql,DBMS_SQL.native);
    DBMS_SQL.DEFINE_COLUMN(curid,1,v_empno);
    DBMS_SQL.DEFINE_COLUMN(curid,2,v_ename,10);
    DBMS_SQL.DEFINE_COLUMN(curid,3,v_hiredate);
    DBMS_SQL.DEFINE_COLUMN(curid,4,v_sal);
    DBMS_SQL.DEFINE_COLUMN(curid,5,v_comm);
```

END;

The following shows an alternative to the prior example that produces the exact same results. Note that the lengths of the data types are irrelevant – the empno, sal, and comm columns will still return data equivalent to NUMBER(4) and NUMBER(7,2), respectively, even though v_num is defined as NUMBER(1) (assuming the declarations in the COLUMN_VALUE procedure are of the appropriate maximum sizes). The

ename column will return data up to ten characters in length as defined by the <length> parameter in the DEFINE_COLUMN call, not by the data type declaration, VARCHAR2(1) declared for v_varchar. The actual size of the returned data is dictated by the COLUMN_VALUE procedure.

```
DECLARE
    curid
                    INTEGER;
                    NUMBER(1);
    v_num
                    VARCHAR2(1);
    v_varchar
    v_date
                    DATE;
                    VARCHAR2(50) := 'SELECT empno, ename, hiredate, sal, ' ||
    v_sql
                                      'comm FROM emp';
    v_status
                    INTEGER;
BEGIN
    curid := DBMS_SQL.OPEN_CURSOR;
    DBMS_SQL.PARSE(curid,v_sql,DBMS_SQL.native);
    DBMS_SQL.DEFINE_COLUMN(curid,1,v_num);
    DBMS_SQL.DEFINE_COLUMN(curid,2,v_varchar,10);
    DBMS_SQL.DEFINE_COLUMN(curid,3,v_date);
    DBMS_SQL.DEFINE_COLUMN(curid,4,v_num);
    DBMS_SQL.DEFINE_COLUMN(curid,5,v_num);
END;
```

5.3.17.9 DEFINE_COLUMN_CHAR

The DEFINE_COLUMN_CHAR procedure defines a CHAR column or expression in the SELECT list that is to be returned and retrieved in a cursor.

DEFINE_COLUMN_CHAR(<c> INTEGER, <position> INTEGER, <column> CHAR, <column_size> INTEGER

Parameters

<C>

Cursor id of the cursor associated with the SELECT command.

<position>

Position of the column or expression in the SELECT list that is being defined.

<column>

A CHAR variable.

<column_size>

The maximum length of the returned data. Returned data exceeding <column_size> is truncated to <column_size> characters.

5.3.17.10 DEFINE COLUMN RAW

The DEFINE_COLUMN_RAW procedure defines a RAW column or expression in the SELECT list that is to be returned and retrieved in a cursor.

Parameters

<C>

Cursor id of the cursor associated with the SELECT command.

<position>

Position of the column or expression in the SELECT list that is being defined.

<column>

A RAW variable.

<column_size>

The maximum length of the returned data. Returned data exceeding <column_size> is truncated to <column_size> characters.

5.3.17.11 DESCRIBE COLUMNS

The DESCRIBE_COLUMNS procedure describes the columns returned by a cursor.

DESCRIBE_COLUMNS(c INTEGER, col_cnt OUT INTEGER, desc_t OUT
DESC_TAB);

Parameters

<C>

The cursor ID of the cursor.

<col_cnt>

The number of columns in cursor result set.

<desc_tab>

The table that contains a description of each column returned by the cursor. The descriptions are of type <code>DESC_REC</code> , and contain the following values:

Column Name	Туре
col_type	INTEGER
col_max_len	INTEGER
col_name	VARCHAR2(128)
col_name_len	INTEGER
col_schema_name	VARCHAR2(128)
col_schema_name_len	INTEGER
col_precision	INTEGER
col_scale	INTEGER
col_charsetid	INTEGER
col_charsetform	INTEGER
col_null_ok	BOOLEAN
·	

5.3.17.12 EXECUTE

The EXECUTE function executes a parsed SQL command or SPL block.

<status> INTEGER EXECUTE(<c> INTEGER)

Parameters

<C>

Cursor ID of the parsed SQL command or SPL block to be executed.

```
<status>
```

Number of rows processed if the SQL command was DELETE, INSERT , or UPDATE . <status> is meaningless for all other commands.

Examples

The following anonymous block inserts a row into the dept table.

5.3.17.13 EXECUTE AND FETCH

Function EXECUTE_AND_FETCH executes a parsed SELECT command and fetches one row.

```
<status> INTEGER EXECUTE_AND_FETCH(<c> INTEGER
[, <exact> BOOLEAN ])
```

Parameters

<C>

Cursor id of the cursor for the SELECT command to be executed.

<exact>

If set to TRUE, an exception is thrown if the number of rows in the result set is not exactly equal to 1. If set to FALSE, no exception is thrown. The default is FALSE. A NO_DATA_FOUND exception is thrown if $\langle exact \rangle$ is TRUE and there are no rows in the result set. A TOO_MANY_ROWS exception is thrown if $\langle exact \rangle$ is TRUE and there is more than one row in the result set.

<status>

Returns 1 if a row was successfully fetched, 0 if no rows to fetch. If an exception is thrown, no value is returned.

Examples

The following stored procedure uses the EXECUTE_AND_FETCH function to retrieve one employee using the employee's name. An exception will be thrown if the employee is not found, or there is more than one employee with the same name.

```
v_sal
                    emp.sal%TYPE;
    V_COMM
                    emp.comm%TYPE;
    v dname
                    dept.dname%TYPE;
                    VARCHAR2(10);
    v_disp_date
                    VARCHAR2(120) := 'SELECT empno, hiredate, sal, ' ||
    v_sql
                                      'NVL(comm, 0), dname ' ||
                                      'FROM emp e, dept d ' ||
                                      'WHERE ename = :p_ename ' ||
                                      'AND e.deptno = d.deptno';
    v_status
                    INTEGER;
BEGIN
    curid := DBMS_SQL.OPEN_CURSOR;
    DBMS_SQL.PARSE(curid,v_sql,DBMS_SQL.native);
    DBMS_SQL.BIND_VARIABLE(curid,':p_ename',UPPER(p_ename));
    DBMS_SQL.DEFINE_COLUMN(curid,1,v_empno);
    DBMS_SQL.DEFINE_COLUMN(curid,2,v_hiredate);
    DBMS_SQL.DEFINE_COLUMN(curid,3,v_sal);
    DBMS_SQL.DEFINE_COLUMN(curid,4,v_comm);
    DBMS_SQL.DEFINE_COLUMN(curid,5,v_dname,14);
    v_status := DBMS_SQL.EXECUTE_AND_FETCH(curid,TRUE);
    DBMS_SQL.COLUMN_VALUE(curid,1,v_empno);
    DBMS_SQL.COLUMN_VALUE(curid,2,v_hiredate);
    DBMS_SQL.COLUMN_VALUE(curid,3,v_sal);
    DBMS_SQL.COLUMN_VALUE(curid,4,v_comm);
    DBMS_SQL.COLUMN_VALUE(curid,5,v_dname);
    v_disp_date := TO_CHAR(v_hiredate, 'MM/DD/YYYY');
                                    : ' || v_empno);
    DBMS_OUTPUT.PUT_LINE('Number
                                     : ' || UPPER(p_ename));
    DBMS_OUTPUT.PUT_LINE('Name
    DBMS_OUTPUT.PUT_LINE('Hire Date : ' || v_disp_date);
    DBMS_OUTPUT.PUT_LINE('Salary
                                    : ' || v_sal);
    DBMS_OUTPUT.PUT_LINE('Commission: ' || v_comm);
    DBMS_OUTPUT.PUT_LINE('Department: ' || v_dname);
    DBMS_SQL.CLOSE_CURSOR(curid);
EXCEPTION
    WHEN NO_DATA_FOUND THEN
        DBMS_OUTPUT.PUT_LINE('Employee ' || p_ename || ' not found');
        DBMS_SQL.CLOSE_CURSOR(curid);
    WHEN TOO_MANY_ROWS THEN
        DBMS_OUTPUT.PUT_LINE('Too many employees named, ' ||
            p_ename || ', found');
        DBMS_SQL.CLOSE_CURSOR(curid);
    WHEN OTHERS THEN
        DBMS_OUTPUT.PUT_LINE('The following is SQLERRM:');
        DBMS_OUTPUT.PUT_LINE(SQLERRM);
        DBMS_OUTPUT.PUT_LINE('The following is SQLCODE:');
        DBMS_OUTPUT.PUT_LINE(SQLCODE);
        DBMS_SQL.CLOSE_CURSOR(curid);
END;
EXEC select_by_name('MARTIN')
          : 7654
Number
Name
          : MARTIN
Hire Date: 09/28/1981
Salary
         : 1250
Commission: 1400
Department: SALES
```

5.3.17.14 FETCH ROWS

The FETCH_ROWS function retrieves a row from a cursor.

```
<status> INTEGER FETCH_ROWS(<c> INTEGER)
```

Parameters

<C>

Cursor ID of the cursor from which to fetch a row.

<status>

Returns 1 if a row was successfully fetched, 0 if no more rows to fetch.

Examples

The following examples fetches the rows from the emp table and displays the results.

```
DECLARE
    curid
                      INTEGER;
    v_empno
                      NUMBER(4):
    v_ename
                      VARCHAR2(10);
    v_hiredate
                      DATE;
                      NUMBER(7,2);
    v_sal
                      NUMBER(7,2);
    v_comm
                      VARCHAR2(50) := 'SELECT empno, ename, hiredate, sal, ' ||
    v_sql
                                        'comm FROM emp';
    v status
                      INTEGER;
BEGIN
    curid := DBMS_SQL.OPEN_CURSOR;
    DBMS_SQL.PARSE(curid,v_sql,DBMS_SQL.native);
    DBMS_SQL.DEFINE_COLUMN(curid,1,v_empno);
    DBMS_SQL.DEFINE_COLUMN(curid,2,v_ename,10);
    DBMS_SQL.DEFINE_COLUMN(curid,3,v_hiredate);
    DBMS_SQL.DEFINE_COLUMN(curid,4,v_sal);
    DBMS_SQL.DEFINE_COLUMN(curid,5,v_comm);
    v_status := DBMS_SQL.EXECUTE(curid);
    DBMS_OUTPUT.PUT_LINE('EMPNO ENAME
                                                 HIREDATE
                                                              SAL
                                                                          COMM');
    DBMS_OUTPUT.PUT_LINE('----
                                                                          ' 11
         '----');
    L00P
        v_status := DBMS_SQL.FETCH_ROWS(curid);
        EXIT WHEN v_{status} = 0;
        DBMS_SQL.COLUMN_VALUE(curid,1,v_empno);
        DBMS_SQL.COLUMN_VALUE(curid,2,v_ename);
        DBMS_SQL.COLUMN_VALUE(curid,3,v_hiredate);
        DBMS_SQL.COLUMN_VALUE(curid,4,v_sal);
        DBMS_SQL.COLUMN_VALUE(curid,4,v_sal);
        DBMS_SQL.COLUMN_VALUE(curid,5,v_comm);
DBMS_OUTPUT.PUT_LINE(v_empno || ' ' || RPAD(v_ename,10) || ' ' ||
             TO_CHAR(v_hiredate,'yyyy-mm-dd') || TO_CHAR(v_sal,'9,999.99') || ' ' ||
             TO_{CHAR(NVL(v_{comm}, 0), '9, 999.99'));
    END LOOP;
    DBMS_SQL.CLOSE_CURSOR(curid);
END;
```

EMPN0	ENAME	HIREDATE	SAL	COMM
7369	SMITH	1980-12-17	800.00	.00
7499	ALLEN	1981-02-20	1,600.00	300.00
7521	WARD	1981-02-22	1.250.00	500.00

```
7566
       JONES
                   1981-04-02 2,975.00
                                                .00
                   1981-09-28 1,250.00
                                         1,400.00
7654
       MARTIN
7698
       BLAKE
                   1981-05-01 2,850.00
                                               .00
7782
       CLARK
                   1981-06-09 2,450.00
                                               .00
       SCOTT
                   1987-04-19 3,000.00
                                               .00
7788
7839
       KING
                   1981-11-17
                               5,000.00
                                                .00
7844
       TURNER
                   1981-09-08
                               1,500.00
                                                .00
7876
       ADAMS
                   1987-05-23 1,100.00
                                                .00
7900
       JAMES
                                                .00
                   1981-12-03
                                 950.00
7902
       FORD
                   1981-12-03 3,000.00
                                                .00
7934
                   1982-01-23 1,300.00
                                                .00
       MILLER
```

5.3.17.15 IS_OPEN

The IS_OPEN function provides the capability to test if the given cursor is open.

```
<status> BOOLEAN IS_OPEN(<c> INTEGER)
```

Parameters

<C>

Cursor ID of the cursor to be tested.

<status>

Set to TRUE if the cursor is open, set to FALSE if the cursor is not open.

5.3.17.16 LAST_ROW_COUNT

The LAST_ROW_COUNT function returns the number of rows that have been currently fetched.

```
<rowcnt> INTEGER LAST_ROW_COUNT
```

Parameters

<rowcnt>

Number of row fetched thus far.

Examples

The following example uses the LAST_ROW_COUNT function to display the total number of rows fetched in the query.

```
DECLARE
```

```
curid
                    INTEGER;
                    NUMBER(4);
    v_empno
                    VARCHAR2(10);
    v_ename
    v_hiredate
                    DATE;
                    NUMBER(7,2);
    v_sal
    V_COMM
                    NUMBER(7,2);
                    VARCHAR2(50) := 'SELECT empno, ename, hiredate, sal, ' ||
    v_sql
                                     'comm FROM emp';
                    INTEGER;
    v_status
BEGIN
    curid := DBMS_SQL.OPEN_CURSOR;
    DBMS_SQL.PARSE(curid,v_sql,DBMS_SQL.native);
    DBMS_SQL.DEFINE_COLUMN(curid,1,v_empno);
    DBMS_SQL.DEFINE_COLUMN(curid,2,v_ename,10);
    DBMS_SQL.DEFINE_COLUMN(curid,3,v_hiredate);
    DBMS_SQL.DEFINE_COLUMN(curid,4,v_sal);
    DBMS_SQL.DEFINE_COLUMN(curid,5,v_comm);
```

```
v_status := DBMS_SQL.EXECUTE(curid);
                                                                      COMM');
    DBMS_OUTPUT.PUT_LINE('EMPNO ENAME
                                               HIREDATE
                                                            SAL
    DBMS_OUTPUT.PUT_LINE('----
                                                                       ' ||
                                 -----
                                               -----
        '----');
    L00P
        v_status := DBMS_SQL.FETCH_ROWS(curid);
        EXIT WHEN v_status = 0;
        DBMS_SQL.COLUMN_VALUE(curid,1,v_empno);
        DBMS_SQL.COLUMN_VALUE(curid,2,v_ename);
        DBMS_SQL.COLUMN_VALUE(curid,3,v_hiredate);
        DBMS_SQL.COLUMN_VALUE(curid,4,v_sal);
        DBMS_SQL.COLUMN_VALUE(curid,4,v_sal);
        DBMS_SQL.COLUMN_VALUE(curid,5,v_comm);
        DBMS_OUTPUT.PUT_LINE(v_empno | | ' ' | | RPAD(v_ename, 10) | | ' ' | |
            TO_CHAR(v_hiredate,'yyyy-mm-dd') || ' ' || TO_CHAR(v_sal,'9,999.99') || ' ' ||
            TO_CHAR(NVL(v_comm, 0), '9,999.99'));
    END LOOP;
    DBMS_OUTPUT.PUT_LINE('Number of rows: ' || DBMS_SQL.LAST_ROW_COUNT);
    DBMS_SQL.CLOSE_CURSOR(curid);
END;
EMPNO
                                           COMM
      ENAME
                   HIREDATE
                                SAL
7369
                                  800.00
                                                .00
       SMITH
                   1980-12-17
       ALLEN
7499
                   1981-02-20
                                1,600.00
                                             300.00
7521
                                             500.00
       WARD
                   1981-02-22
                                1,250.00
7566
       JONES
                   1981-04-02
                                2,975.00
                                                .00
7654
                                          1,400.00
       MARTIN
                   1981-09-28
                                1,250.00
7698
                   1981-05-01 2,850.00
                                                .00
       BLAKE
                                                .00
7782
       CLARK
                   1981-06-09 2,450.00
7788
       SC0TT
                   1987-04-19
                                3,000.00
                                                .00
7839
                                5,000.00
                                                .00
       KING
                   1981-11-17
7844
       TURNER
                   1981-09-08 1,500.00
                                                .00
7876
                   1987-05-23
                                1,100.00
                                                .00
       ADAMS
7900
       JAMES
                   1981-12-03
                                  950.00
                                                .00
7902
       FORD
                   1981-12-03 3,000.00
                                                .00
7934
       MILLER
                   1982-01-23 1,300.00
                                                .00
Number of rows: 14
```

5.3.17.17 OPEN_CURSOR

The OPEN_CURSOR function creates a new cursor. A cursor must be used to parse and execute any dynamic SQL statement. Once a cursor has been opened, it can be re-used with the same or different SQL statements. The cursor does not have to be closed and re-opened in order to be re-used.

```
<c> INTEGER OPEN_CURSOR
```

Parameters

<C>

Cursor ID number associated with the newly created cursor.

Examples

The following example creates a new cursor:

```
DECLARE
curid INTEGER;
BEGIN
```

```
curid := DBMS_SQL.OPEN_CURSOR;
.
.
.
END;
```

5.3.17.18 PARSE

The PARSE procedure parses a SQL command or SPL block. If the SQL command is a DDL command, it is immediately executed and does not require running the EXECUTE function.

```
PARSE(<c> INTEGER, <statement> VARCHAR2, <language_flag> INTEGER)
```

Parameters

<C>

Cursor ID of an open cursor.

<statement>

SQL command or SPL block to be parsed. A SQL command must not end with the semi-colon terminator, however an SPL block does require the semi-colon terminator.

```
<language_flag>
```

Language flag provided for compatibility with Oracle syntax. Use DBMS_SQL.V6, DBMS_SQL.V7 or DBMS_SQL.native . This flag is ignored, and all syntax is assumed to be in EnterpriseDB Advanced Server form.

Examples

The following anonymous block creates a table named, job . Note that DDL statements are executed immediately by the PARSE procedure and do not require a separate EXECUTE step.

```
DECLARE
    curid
                    INTEGER;
BEGIN
    curid := DBMS_SQL.OPEN_CURSOR;
    DBMS_SQL.PARSE(curid, 'CREATE TABLE job (jobno NUMBER(3), ' ||
         jname VARCHAR2(9))',DBMS_SQL.native);
    DBMS_SQL.CLOSE_CURSOR(curid);
END;
The following inserts two rows into the job table.
DECLARE
    curid
                    INTEGER;
                    VARCHAR2(50);
    v_sql
    v_status
                    INTEGER;
BEGIN
    curid := DBMS_SQL.OPEN_CURSOR;
    v_sql := 'INSERT INTO job VALUES (100, ''ANALYST'')';
    DBMS_SQL.PARSE(curid, v_sql, DBMS_SQL.native);
    v_status := DBMS_SQL.EXECUTE(curid);
    DBMS_OUTPUT.PUT_LINE('Number of rows processed: ' || v_status);
    v_sql := 'INSERT INTO job VALUES (200, ''CLERK'')';
    DBMS_SQL.PARSE(curid, v_sql, DBMS_SQL.native);
    v_status := DBMS_SQL.EXECUTE(curid);
    DBMS_OUTPUT.PUT_LINE('Number of rows processed: ' || v_status);
    DBMS_SQL.CLOSE_CURSOR(curid);
END:
```

```
Number of rows processed: 1
Number of rows processed: 1
```

The following anonymous block uses the DBMS_SQL package to execute a block containing two INSERT statements. Note that the end of the block contains a terminating semi-colon, while in the prior example, each individual INSERT statement does not have a terminating semi-colon.

```
DECLARE
    curid
                    INTEGER;
                    VARCHAR2(100);
    v_sql
    v_status
                    INTEGER;
BEGIN
    curid := DBMS_SQL.OPEN_CURSOR;
    v_sql := 'BEGIN ' ||
               'INSERT INTO job VALUES (300, ''MANAGER''); ' ||
               'INSERT INTO job VALUES (400, ''SALESMAN''); ' ||
             'END;';
    DBMS_SQL.PARSE(curid, v_sql, DBMS_SQL.native);
    v_status := DBMS_SQL.EXECUTE(curid);
    DBMS_SQL.CLOSE_CURSOR(curid);
END;
```

5.3.18 DBMS UTILITY

The DBMS_UTILITY package provides support for the following various utility programs:

```
Function/Procedure
ANALYZE DATABASE(method [, estimate rows [, estimate percent [, method opt ]]])
ANALYZE PART OBJECT(schema, object name [, object type [, command type [, command opt [, sample clause ]]]])
ANALYZE_SCHEMA(schema, method [, estimate_rows [, estimate_percent [, method_opt ]]])
CANONICALIZE(name, canon_name OUT, canon_len)
COMMA_TO_TABLE(list, tablen OUT, tab OUT)
DB_VERSION(version OUT, compatibility OUT)
EXEC_DDL_STATEMENT(parse_string)
FORMAT_CALL_STACK
GET CPU TIME
GET_DEPENDENCY(type, schema, name)
GET_HASH_VALUE(name, base, hash_size)
GET_PARAMETER_VALUE(parnam, intval OUT, strval OUT)
GET TIME
NAME TOKENIZE(name, a OUT, b OUT, c OUT, dblink OUT, nextpos OUT)
TABLE_TO_COMMA(tab, tablen OUT, list OUT)
```

Advanced Server's implementation of DBMS_UTILITY is a partial implementation when compared to Oracle's version. Only those functions and procedures listed in the table above are supported.

The following table lists the public variables available in the DBMS_UTILITY package.

Public Variables inv error on restrictions	Data Type PLS INTEGER	Value	Description Used by the INVALIDATE procedure.
Iname_array	TABLE	1	For lists of long names.
uncl_array	TABLE		For lists of users and names.

LNAME ARRAY

The LNAME_ARRAY is for storing lists of long names including fully-qualified names.

TYPE lname_array IS `TABLE OF VARCHAR2(4000) INDEX BY BINARY_INTEGER;

UNCL ARRAY

The UNCL_ARRAY is for storing lists of users and names.

TYPE uncl_array IS TABLE OF VARCHAR2(227) INDEX BY BINARY_INTEGER;

ANALYZE_DATABASE, ANALYZE SCHEMA and ANALYZE PART_OBJECT

The ANALYZE_DATABASE(), ANALYZE_SCHEMA() and ANALYZE_PART_OBJECT() procedures provide the capability to gather statistics on tables in the database. When you execute the ANALYZE statement, Postgres samples the data in a table and records distribution statistics in the pg_statistics system table.

ANALYZE_DATABASE, ANALYZE_SCHEMA, and ANALYZE_PART_OBJECT differ primarily in the number of tables that are processed:

- ANALYZE_DATABASE analyzes all tables in all schemas within the current database.
- ANALYZE_SCHEMA analyzes all tables in a given schema (within the current database).
- ANALYZE_PART_OBJECT analyzes a single table.

The syntax for the ANALYZE commands are:

Parameters - ANALYZE_DATABASE and ANALYZE_SCHEMA

<method>

method determines whether the ANALYZE procedure populates the pg_statistics table or removes entries from the pg_statistics table. If you specify a method of DELETE , the ANALYZE procedure removes the relevant rows from pg_statistics . If you specify a method of COMPUTE or ESTIMATE , the ANALYZE procedure analyzes a table (or multiple tables) and records the distribution information in pg_statistics. There is no difference between COMPUTE and ESTIMATE ; both methods execute the Postgres ANALYZE statement. All other parameters are validated and then ignored.

<estimate_rows>

Number of rows upon which to base estimated statistics. One of <estimate_rows> or <estimate_percent> must be specified if method is ESTIMATE .

This argument is ignored, but is included for compatibility.

<estimate_percent>

Percentage of rows upon which to base estimated statistics. One of <estimate_rows> or <estimate_percent> must be specified if method is ESTIMATE .

This argument is ignored, but is included for compatibility.

```
<method_opt>
```

Object types to be analyzed. Any combination of the following:

```
[ FOR TABLE ]
[ FOR ALL [ INDEXED ] COLUMNS ] [ SIZE n ]
[ FOR ALL INDEXES ]
```

This argument is ignored, but is included for compatibility.

Parameters - ANALYZE_PART_OBJECT

```
<schema>
```

Name of the schema whose objects are to be analyzed.

```
<object_name>
```

Name of the partitioned object to be analyzed.

```
<object_type>
```

Type of object to be analyzed. Valid values are: T - table, I - index.

This argument is ignored, but is included for compatibility.

```
<command_type>
```

Type of analyze functionality to perform. Valid values are: E - gather estimated statistics based upon on a specified number of rows or a percentage of rows in the <sample_clause> clause;

C - compute exact statistics; or V - validate the structure and integrity of the partitions.

This argument is ignored, but is included for compatibility.

<command_opt>

```
For <command_type> C or E , can be any combination of:

[ FOR TABLE ]

[ FOR ALL COLUMNS ]

[ FOR ALL LOCAL INDEXES ]

For <command_type> V , can be CASCADE if <object_type> is T .
```

This argument is ignored, but is included for compatibility.

```
<sample_clause>
```

If <command_type> is E , contains the following clause to specify the number of rows or percentage or rows on which to base the estimate.

```
SAMPLE <n> { ROWS | PERCENT }
```

This argument is ignored, but is included for compatibility.

CANONICALIZE

The CANONICALIZE procedure performs the following operations on an input string:

- If the string is not double-quoted, verifies that it uses the characters of a legal identifier. If not, an exception is thrown. If the string is double-quoted, all characters are allowed.
- If the string is not double-quoted and does not contain periods, uppercases all alphabetic characters and eliminates leading and trailing spaces.

- If the string is double-quoted and does not contain periods, strips off the double quotes.
- If the string contains periods and no portion of the string is double-quoted, uppercases each portion of the string and encloses each portion in double quotes.
- If the string contains periods and portions of the string are double-quoted, returns the double-quoted portions unchanged including the double quotes and returns the non-double-quoted portions uppercased and enclosed in double quotes.

Parameters

```
<name>
String to be canonicalized.
<canon_name>
```

The canonicalized string.

<canon_len>

Number of bytes in <name> to canonicalize starting from the first character.

Examples

The following procedure applies the CANONICALIZE procedure on its input parameter and displays the results.

```
CREATE OR REPLACE PROCEDURE canonicalize (
    p_name
               VARCHAR2,
    p_length
                BINARY_INTEGER DEFAULT 30
IS
                VARCHAR2(100);
    v_canon
BEGIN
    DBMS_UTILITY.CANONICALIZE(p_name,v_canon,p_length);
    DBMS_OUTPUT.PUT_LINE('Canonicalized name ==>' || v_canon || '<==');
    DBMS_OUTPUT.PUT_LINE('Length: ' || LENGTH(v_canon));
EXCEPTION
   WHEN OTHERS THEN
        DBMS_OUTPUT.PUT_LINE('SQLERRM: ' || SQLERRM);
        DBMS_OUTPUT.PUT_LINE('SQLCODE: ' || SQLCODE);
END;
EXEC canonicalize('Identifier')
Canonicalized name ==>IDENTIFIER<==
Length: 10
EXEC canonicalize('"Identifier"')
Canonicalized name ==>Identifier<==
Length: 10
EXEC canonicalize('"_+142%"')
Canonicalized name ==>_+142%<==
Length: 6
EXEC canonicalize('abc.def.ghi')
Canonicalized name ==>"ABC"."DEF"."GHI"<==
Length: 17
EXEC canonicalize('"abc.def.ghi"')
Canonicalized name ==>abc.def.ghi<==
Length: 11
```

```
EXEC canonicalize('"abc".def."ghi"')
Canonicalized name ==>"abc"."DEF"."ghi"<==
Length: 17

EXEC canonicalize('"abc.def".ghi')
Canonicalized name ==>"abc.def"."GHI"<==
Length: 15</pre>
```

COMMA_TO_TABLE

The COMMA_TO_TABLE procedure converts a comma-delimited list of names into a table of names. Each entry in the list becomes a table entry. The names must be formatted as valid identifiers.

```
COMMA_TO_TABLE(<list> VARCHAR2, <tablen> OUT BINARY_INTEGER ,
> <tab> OUT { LNAME_ARRAY | UNCL_ARRAY })
```

Parameters

```
st>
```

Comma-delimited list of names.

<tablen>

Number of entries in <tab> .

<tab>

Table containing the individual names in t> .

LNAME_ARRAY

A DBMS_UTILITY LNAME_ARRAY (as described in the LNAME_ARRAY <\ld>LNAME_ARRAY <\ld>lname_array> section).

<UNCL_ARRAY>

A DBMS_UTILITY UNCL_ARRAY (as described in the UNCL_ARRAY <uncl_array> section).

Examples

The following procedure uses the COMMA_TO_TABLE procedure to convert a list of names to a table. The table entries are then displayed.

```
CREATE OR REPLACE PROCEDURE comma_to_table (
                VARCHAR2
    p_list
IS
    r_lname
                DBMS_UTILITY.LNAME_ARRAY;
    v_length
                BINARY_INTEGER;
BEGIN
    DBMS_UTILITY.COMMA_TO_TABLE(p_list,v_length,r_lname);
    FOR i IN 1..v_length LOOP
        DBMS_OUTPUT.PUT_LINE(r_lname(i));
    END LOOP;
END;
EXEC comma_to_table('edb.dept, edb.emp, edb.jobhist')
edb.dept
edb.emp
edb.jobhist
```

DB VERSION

The DB_VERSION procedure returns the version number of the database.

```
DB_VERSION(<version> OUT VARCHAR2, <compatibility> OUT VARCHAR2)
```

Parameters

```
<version>
```

Database version number.

```
<compatibility>
```

Compatibility setting of the database. (To be implementation-defined as to its meaning.)

Examples

The following anonymous block displays the database version information.

Version: EnterpriseDB 10.0.0 on i686-pc-linux-gnu, compiled by GCC gcc (GCC) 4.1.2 20080704 (Red Ho 48), 32-bit Compatibility: EnterpriseDB 10.0.0 on i686-pc-linux-gnu, compiled by GCC gcc (GCC) 4.1.220080704 (48), 32-bit

EXEC DDL STATEMENT

The EXEC_DDL_STATEMENT provides the capability to execute a DDL command.

```
EXEC_DDL_STATEMENT(<parse_string> VARCHAR2)
```

Parameters

```
<parse_string>
```

The DDL command to be executed.

Examples

The following anonymous block creates the job table.

```
REGTN
```

```
edb=# exec dbms_utility.exec_ddl_statement('select rownum from dual');
ERROR: EDB-20001: 'parse_string' must be a valid DDL statement
```

FORMAT CALL STACK

The FORMAT_CALL_STACK function returns the formatted contents of the current call stack.

```
DBMS_UTILITY.FORMAT_CALL_STACK return VARCHAR2
```

This function can be used in a stored procedure, function or package to return the current call stack in a readable format. This function is useful for debugging purposes.

GET_CPU_TIME

The GET_CPU_TIME function returns the CPU time in hundredths of a second from some arbitrary point in time.

```
<cputime> NUMBER GET_CPU_TIME
```

Parameters

<cputime>

Number of hundredths of a second of CPU time.

Examples

The following SELECT command retrieves the current CPU time, which is 603 hundredths of a second or .0603 seconds.

```
SELECT DBMS_UTILITY.GET_CPU_TIME FROM DUAL;
```

```
get_cpu_time
------
603
```

GET_DEPENDENCY

The GET_DEPENDENCY procedure provides the capability to list the objects that are dependent upon the specified object. GET_DEPENDENCY does not show dependencies for functions or procedures.

Parameters

<type>

The object type of <name> . Valid values are INDEX, PACKAGE, PACKAGE BODY, SEQUENCE, TABLE, TRIGGER and VIEW .

<schema>

Name of the schema in which <name> exists.

<name>

Name of the object for which dependencies are to be obtained.

Examples

The following anonymous block finds dependencies on the EMP table .

```
BEGIN
```

```
DBMS_UTILITY.GET_DEPENDENCY('TABLE','public','EMP');
END;
```

```
DEPENDENCIES ON public.EMP
```

```
*TABLE public.EMP()

* CONSTRAINT c public.emp()

* CONSTRAINT f public.emp()

* CONSTRAINT p public.emp()

* TYPE public.emp()

* CONSTRAINT c public.emp()

* CONSTRAINT f public.jobhist()

* VIEW .empname_view()
```

GET_HASH_VALUE

The GET_HASH_VALUE function provides the capability to compute a hash value for a given string.

Parameters

<name>

The string for which a hash value is to be computed.

<base>

Starting value at which hash values are to be generated.

<hash_size>

The number of hash values for the desired hash table.

<hash>

The generated hash value.

Examples

The following anonymous block creates a table of hash values using the ename column of the emp table and then displays the key along with the hash value. The hash values start at 100 with a maximum of 1024 distinct values.

```
DECLARE
    v_hash
                    NUMBER;
    TYPE hash_tab IS TABLE OF NUMBER INDEX BY VARCHAR2(10);
                    HASH_TAB;
    r_hash
    CURSOR emp_cur IS SELECT ename FROM emp;
BEGIN
    FOR r_emp IN emp_cur LOOP
        r_hash(r_emp.ename.. code-block:: text) :=
            DBMS_UTILITY.GET_HASH_VALUE(r_emp.ename, 100, 1024);
    END LOOP:
    FOR r_emp IN emp_cur LOOP
        DBMS_OUTPUT.PUT_LINE(RPAD(r_emp.ename, 10) | | ' ' | |
            r_hash(r_emp.ename));
    END LOOP;
END;
SMITH
           377
ALLEN
           740
WARD
           718.. code-block:: text
JONES
           131
MARTIN
           176
BLAKE
           568
           621
CLARK
```

```
SCOTT 1097
KING 235
TURNER 850
ADAMS 156
JAMES 942
FORD 775
MILLER 148
```

GET_PARAMETER_VALUE

The GET_PARAMETER_VALUE procedure provides the capability to retrieve database initialization parameter settings.

Parameters

<parnam>

Name of the parameter whose value is to be returned. The parameters are listed in the pg_settings system view.

<intval>

Value of an integer parameter or the length of <strval> .

<strval>

Value of a string parameter.

<status>

Returns 0 if the parameter value is INTEGER or BOOLEAN . Returns 1 if the parameter value is a string.

Examples

The following anonymous block shows the values of two initialization parameters.

```
DECLARE
```

```
v_intval INTEGER;
v_strval VARCHAR2(80);
BEGIN
   DBMS_UTILITY.GET_PARAMETER_VALUE('max_fsm_pages', v_intval, v_strval);
   DBMS_OUTPUT.PUT_LINE('max_fsm_pages' || ': ' || v_intval);
   DBMS_UTILITY.GET_PARAMETER_VALUE('client_encoding', v_intval, v_strval);
   DBMS_OUTPUT.PUT_LINE('client_encoding' || ': ' || v_strval);
END;

max_fsm_pages: 72625
client_encoding: SQL_ASCII
```

GET TIME

The GET_TIME function provides the capability to return the current time in hundredths of a second.

```
<time> NUMBER GET_TIME
```

Parameters

<time>

Number of hundredths of a second from the time in which the program is started.

Examples

```
The following example shows calls to the GET_TIME function.

SELECT DBMS_UTILITY.GET_TIME FROM DUAL;

get_time
-------
1555860

SELECT DBMS_UTILITY.GET_TIME FROM DUAL;

get_time
-------
1556037
```

NAME TOKENIZE

The NAME_TOKENIZE procedure parses a name into its component parts. Names without double quotes are uppercased. The double quotes are stripped from names with double quotes.

Parameters

```
<name>
```

String containing a name in the following format:

```
<a> [.<b> [.<c>]][@<dblink> ]
```

<a>>

Returns the leftmost component.

Returns the second component, if any.

<C>

Returns the third component, if any.

<dblink>

Returns the database link name.

<nextpos>

Position of the last character parsed in name.

Examples

The following stored procedure is used to display the returned parameter values of the procedure for various names.

NAME_TOKENIZE

```
CREATE OR REPLACE PROCEDURE name_tokenize (
    p_name
                    VARCHAR2
IS
                    VARCHAR2(30);
    v_a
    v_b
                    VARCHAR2(30);
                    VARCHAR2(30);
    V_C
    v_dblink
                    VARCHAR2(30);
                    BINARY_INTEGER;
    v_nextpos
BEGIN
    DBMS_UTILITY.NAME_TOKENIZE(p_name,v_a,v_b,v_c,v_dblink,v_nextpos);
```

```
DBMS_OUTPUT.PUT_LINE('name
                                   : ' || p_name);
                                     : ' || v_a);
    DBMS_OUTPUT.PUT_LINE('a
    DBMS_OUTPUT.PUT_LINE('b
                                     : ' || v_b);
                                     : ' || v_c);
    DBMS_OUTPUT.PUT_LINE('c
    DBMS_OUTPUT.PUT_LINE('dblink : ' || v_dblink);
DBMS_OUTPUT.PUT_LINE('nextpos: ' || v_nextpos);
END;
Tokenize the name, emp:
BEGIN
name_tokenize('emp');
END;
name
: emp
а
: EMP
b
C
dblink:
nextpos: 3
Tokenize the name, edb.list_emp :
BEGIN
name_tokenize('edb.list_emp');
END;
name
а
b
C
dblink:
nextpos:
edb.list_emp
EDB
LIST_EMP
12
Tokenize the name, "edb"."Emp_Admin".update_emp_sal:
name_tokenize('"edb"."Emp_Admin".update_emp_sal');
END;
name
а
b
C
dblink:
nextpos:
"edb"."Emp_Admin".update_emp_sal
Emp_Admin
UPDATE_EMP_SAL
```

```
32
```

```
Tokenize the name edb.emp@edb_dblink :
BEGIN
Copyright © 2007 - 2019 EnterpriseDB Corporation. All rights reserved.
255Database Compatibility for Oracle Developers
Built-in Package Guide
name_tokenize('edb.emp@edb_dblink');
END;
name
а
h
C
dblink:
nextpos:
edb.emp@edb_dblink
FDB
FMP
EDB_DBLINK
18
```

TABLE TO COMMA

The TABLE_TO_COMMA procedure converts table of names into a comma-delimited list of names. Each table entry becomes a list entry. The names must be formatted as valid identifiers.

Parameters

<tab>

Table containing names.

LNAME_ARRAY

A DBMS_UTILITY LNAME_ARRAY (as described in the [LNAME ARRAY](#Iname_array) section.

UNCL_ARRAY

A DBMS_UTILITY UNCL_ARRAY (as described the UNCL_ARRAY <uncl_array> section).

<tablen>

Number of entries in st> .

st>

Comma-delimited list of names from <tab> .

Examples

The following example first uses the COMMA_TO_TABLE procedure to convert a comma-delimited list to a table. The TABLE_TO_COMMA procedure then converts the table back to a comma-delimited list that is displayed.

```
CREATE OR REPLACE PROCEDURE table_to_comma (
    p_list VARCHAR2
)
IS
```

```
DBMS_UTILITY.LNAME_ARRAY;
    r_lname
    v_length
                BINARY_INTEGER;
    v_listlen
                BINARY_INTEGER;
    v_list
                VARCHAR2(80);
BEGIN
    DBMS_UTILITY.COMMA_TO_TABLE(p_list,v_length,r_lname);
    DBMS_OUTPUT.PUT_LINE('Table Entries');
DBMS_OUTPUT.PUT_LINE('----');
    FOR i IN 1..v_length LOOP
        DBMS_OUTPUT.PUT_LINE(r_lname(i));
    END LOOP;
    DBMS_OUTPUT.PUT_LINE('----');
    DBMS_UTILITY.TABLE_TO_COMMA(r_lname,v_listlen,v_list);
    DBMS_OUTPUT.PUT_LINE('Comma-Delimited List: ' || v_list);
END;
EXEC table_to_comma('edb.dept, edb.emp, edb.jobhist')
Table Entries
_____
edb.dept
edb.emp
edb.jobhist
Comma-Delimited List: edb.dept, edb.emp, edb.jobhist
```

5.3.19.0 UTL_ENCODE

The UTL_ENCODE package provides a way to encode and decode data. Advanced Serve supports the following functions and procedures:

Function/Procedure	Return Type	Description
BASE64_DECODE(r)	RAW	Use the BASE64_DECODE function to transla
BASE64_ENCODE(r)	RAW	Use the BASE64_ENCODE function to transla
BASE64_ENCODE(loid)	TEXT	Use the BASE64_ENCODE function to transla
MIMEHEADER_DECODE(buf)	VARCHAR2	Use the MIMEHEADER_DECODE function to
MIMEHEADER_ENCODE(buf, encode_charset, encoding)	VARCHAR2	Use the MIMEHEADER_ENCODE function to
QUOTED_PRINTABLE_DECODE(r)	RAW	Use the QUOTED_PRINTABLE_DECODE fur
QUOTED_PRINTABLE_ENCODE(r)	RAW	Use the QUOTED_PRINTABLE_ENCODE fur
TEXT_DECODE(buf, encode_charset, encoding)	VARCHAR2	Use the TEXT_DECODE function to decode a
TEXT_ENCODE(buf, encode_charset, encoding)	VARCHAR2	Use the TEXT_ENCODE function to translate
UUDECODE(r)	RAW	Use the UUDECODE function to translate a u
UUENCODE(r, type, filename, permission)	RAW	Use the UUENCODE function to translate a R

5.3.19.1 BASE64_DECODE

Use the BASE64_DECODE function to translate a Base64 encoded string to the original value originally encoded by BASE64_ENCODE. The signature is:

```
BASE64_DECODE (<r> IN RAW)
```

This function returns a RAW value.

Parameters

<r>

<r> is the string that contains the Base64 encoded data that will be translated to RAW form.

Examples

Before executing the following example, invoke the command:

```
SET bytea_output = escape ;
```

This command instructs the server to escape any non-printable characters, and to display BYTEA or RAW values onscreen in readable form. For more information, please refer to the Postgres Core Documentation available at:

https://www.postgresql.org/docs/12/static/datatype-binary.html

The following example first encodes (using BASE64_ENCODE), and then decodes (using BASE64_DECODE) a string that contains the text abc:

```
edb=# SELECT UTL_ENCODE.BASE64_ENCODE(CAST ('abc' AS RAW));
base64_encode
-----
YWJj
(1 row)

edb=# SELECT UTL_ENCODE.BASE64_DECODE(CAST ('YWJj' AS RAW));
base64_decode
------
abc
(1 row)
```

5.3.19.2 BASE64_ENCODE

Use the BASE64_ENCODE function to translate and encode a string in Base64 format (as described in RFC 4648). This function can be useful when composing MIME email that you intend to send using the UTL_SMTP package. The BASE64_ENCODE function has two signatures:

```
BASE64_ENCODE(<r> IN RAW)

BASE64_ENCODE(<loid> IN OID)
```

This function returns a RAW value or an OID .

Parameters

```
<r>
```

and

<r> specifies the RAW string that will be translated to Base64.

<loid>

<loid> specifies the object ID of a large object that will be translated to Base64.

Examples

Before executing the following example, invoke the command:

```
SET bytea_output = escape;
```

This command instructs the server to escape any non-printable characters, and to display BYTEA or RAW values onscreen in readable form. For more information, please refer to the Postgres Core Documentation available at:

https://www.postgresql.org/docs/12/static/datatype-binary.html

The following example first encodes (using BASE64_ENCODE), and then decodes (using BASE64_DECODE) a string that contains the text | abc :

```
edb=# SELECT UTL_ENCODE.BASE64_ENCODE(CAST ('abc' AS RAW));
base64_encode
-----
YWJj
(1 row)

edb=# SELECT UTL_ENCODE.BASE64_DECODE(CAST ('YWJj' AS RAW));
base64_decode
------
abc
(1 row)
```

5.3.19.3 MIMEHEADER_DECODE

Use the MIMEHEADER_DECODE function to decode values that are encoded by the MIMEHEADER_ENCODE function. The signature is:

```
MIMEHEADER_DECODE(<buf> IN VARCHAR2)
```

This function returns a VARCHAR2 value.

Parameters

<buf>

<buf> contains the value (encoded by MIMEHEADER_ENCODE) that will be decoded.

Examples

The following examples use the MIMEHEADER_ENCODE and MIMEHEADER_DECODE functions to first encode, and then decode a string:

5.3.19.4 MIMEHEADER_ENCODE

Use the MIMEHEADER_ENCODE function to convert a string into mime header format, and then encode the string. The signature is:

MIMEHEADER_ENCODE(<buf> IN VARCHAR2, <encode_charset> IN VARCHAR2 DEFAULT NULL, <encodin

This function returns a VARCHAR2 value.

Parameters

<buf>

<bush string that will be formatted and encoded. The string is a VARCHAR2 value.

<encode_charset>

<encode_charset> specifies the character set to which the string will be converted before being
formatted and encoded. The default value is NULL .

<encoding>

<encoding> specifies the encoding type used when encoding the string. You can specify:

- Q to enable quoted-printable encoding. If you do not specify a value, MIMEHEADER_ENCODE will use quoted-printable encoding.
- · B to enable base-64 encoding.

Examples

The following examples use the MIMEHEADER_ENCODE and MIMEHEADER_DECODE functions to first encode, and then decode a string:

5.3.19.5 QUOTED_PRINTABLE_DECODE

Use the QUOTED_PRINTABLE_DECODE function to translate an encoded quoted-printable string into a decoded RAW string.

The signature is:

```
QUOTED_PRINTABLE_DECODE(<r> IN RAW)
```

This function returns a RAW value.

Parameters

<r>

<r> contains the encoded string that will be decoded. The string is a RAW value, encoded by QUOTED_PRINTABLE_ENCODE .

Examples

Before executing the following example, invoke the command:

```
SET bytea_output = escape;
```

This command instructs the server to escape any non-printable characters, and to display BYTEA or RAW values onscreen in readable form. For more information, please refer to the Postgres Core Documentation available at:

https://www.postgresql.org/docs/12/static/datatype-binary.html

The following example first encodes and then decodes a string:

```
edb=# SELECT UTL_ENCODE.QUOTED_PRINTABLE_ENCODE('E=mc2') FROM DUAL; quoted_printable_encode
------
E=3Dmc2
(1 row)
```

```
edb=# SELECT UTL_ENCODE.QUOTED_PRINTABLE_DECODE('E=3Dmc2') FROM DUAL;
quoted_printable_decode
------
E=mc2
(1 row)
```

5.3.19.6 QUOTED PRINTABLE ENCODE

Use the QUOTED_PRINTABLE_ENCODE function to translate and encode a string in quoted-printable format. The signature is:

```
QUOTED_PRINTABLE_ENCODE(<r> IN RAW)
```

This function returns a RAW value.

Parameters

<r>

<r> contains the string (a RAW value) that will be encoded in a quoted-printable format.

Examples

Before executing the following example, invoke the command:

```
SET bytea_output = escape;
```

This command instructs the server to escape any non-printable characters, and to display BYTEA or RAW values onscreen in readable form. For more information, please refer to the Postgres Core Documentation available at:

https://www.postgresql.org/docs/12/static/datatype-binary.html

The following example first encodes and then decodes a string:

5.3.19.7 TEXT DECODE

Use the TEXT_DECODE function to translate and decode an encoded string to the VARCHAR2 value that was originally encoded by the TEXT_ENCODE function. The signature is:

TEXT_DECODE(<buf> IN VARCHAR2, <encode_charset> IN VARCHAR2 DEFAULT NULL, <encoding> IN

This function returns a VARCHAR2 value.

Parameters

<buf>

<buf> contains the encoded string that will be translated to the original value encoded by TEXT_ENCODE .

<encode_charset>

<encode_charset> specifies the character set to which the string will be translated before encoding. The default value is NULL .

<encoding>

<encoding> specifies the encoding type used by TEXT_DECODE . Specify:

- UTL_ENCODE.BASE64 to specify base-64 encoding.
- UTL_ENCODE.QUOTED_PRINTABLE to specify quoted printable encoding. This is the default.

Examples

The following example uses the TEXT_ENCODE and TEXT_DECODE functions to first encode, and then decode a string:

5.3.19.8 TEXT_ENCODE

Use the TEXT_ENCODE function to translate a string to a user-specified character set, and then encode the string. The signature is:

TEXT_DECODE(<buf> IN VARCHAR2, <encode_charset> IN VARCHAR2 DEFAULT NULL, <encoding> IN

This function returns a VARCHAR2 value.

Parameters

<buf>

<buf> contains the encoded string that will be translated to the specified character set and encoded by TEXT_ENCODE .

<encode_charset>

<encode_charset> specifies the character set to which the value will be translated before encoding. The default value is NULL .

<encoding>

<encoding> specifies the encoding type used by TEXT_ENCODE . Specify:

- UTL_ENCODE.BASE64 to specify base-64 encoding.
- UTL_ENCODE.QUOTED_PRINTABLE to specify quoted printable encoding. This is the default.

Examples

The following example uses the TEXT_ENCODE and TEXT_DECODE functions to first encode, and then decode a string:

```
edb=# SELECT UTL_ENCODE.TEXT_ENCODE('What is the date?', 'BIG5',
UTL_ENCODE.BASE64) FROM DUAL;
```

5.3.19.9 UUDECODE

Use the UUDECODE function to translate and decode a uuencode encoded string to the RAW value that was originally encoded by the UUENCODE function. The signature is:

```
UUDECODE(<r> IN RAW)
```

This function returns a RAW value.

If you are using the Advanced Server UUDECODE function to decode uuencoded data that was created by the Oracle implementation of the UTL_ENCODE.UUENCODE function, then you must first set the Advanced Server configuration parameter utl_encode.uudecode_redwood to TRUE before invoking the Advanced Server UUDECODE function on the Oracle-created data. (For example, this situation may occur if you migrated Oracle tables containing uuencoded data to an Advanced Server database.)

The uuencoded data created by the Oracle version of the UUENCODE function results in a format that differs from the uuencoded data created by the Advanced Server UUENCODE function. As a result, attempting to use the Advanced Server UUDECODE function on the Oracle uuencoded data results in an error unless the configuration parameter utl_encode.uudecode_redwood is set to TRUE.

However, if you are using the Advanced Server UUDECODE function on uuencoded data created by the Advanced Server UUENCODE function, then $utl_encode.uudecode_redwood$ must be set to FALSE, which is the default setting.

Parameters

<r>

<r> contains the uuencoded string that will be translated to RAW .

Examples

Before executing the following example, invoke the command:

```
SET bytea_output = escape;
```

This command instructs the server to escape any non-printable characters, and to display BYTEA or RAW values onscreen in readable form. For more information, please refer to the Postgres Core Documentation available at:

https://www.postgresql.org/docs/12/static/datatype-binary.html

The following example uses UUENCODE and UUDECODE to first encode and then decode a string:

edb=# SET bytea_output = escape;

SET

edb=# SELECT UTL_ENCODE.UUENCODE('What is the date?') FROM DUAL;

uuencode

begin 0 uuencode.txt\01215VAA="!I<R!T:&4@9&%T93\\`\012`\012end\012

(1 row)

5.3.19.10 UUENCODE

Use the UUENCODE function to translate RAW data into a uuencode formatted encoded string. The signature is:

UUENCODE(<r> IN RAW, <type> IN INTEGER DEFAULT 1, <filename> IN VARCHAR2 DEFAULT NULL, <

This function returns a RAW value.

Parameters

<r>

<r> contains the RAW string that will be translated to uuencode format.

<type>

<type> is an INTEGER value or constant that specifies the type of uuencoded string that will be returned; the default value is 1 . The possible values are:

Value	Constant
1	complete
2	header_piece
3	middle_piece
4	end_piece

<filename>

<filename> is a VARCHAR2 value that specifies the file name that you want to embed in the encoded form; if you do not specify a file name, UUENCODE will include a filename of uuencode.txt
in the encoded form.

<permission>

<permission> is a VARCHAR2 that specifies the permission mode; the default value is NULL

Examples

Before executing the following example, invoke the command:

```
SET bytea_output = escape;
```

This command instructs the server to escape any non-printable characters, and to display BYTEA or RAW values onscreen in readable form. For more information, please refer to the Postgres Core Documentation available at:

https://www.postgresql.org/docs/12/static/datatype-binary.html

```
The following example uses UUENCODE and UUDECODE to first encode and then decode a string:

edb=# SET bytea_output = escape;

SET

edb=# SELECT UTL_ENCODE.UUENCODE('What is the date?') FROM DUAL;

uuencode
```

5.3.20 UTL_FILE

The UTL_FILE package provides the capability to read from, and write to files on the operating system's file system. Non-superusers must be granted EXECUTE privilege on the UTL_FILE package by a superuser before using any of the functions or procedures in the package. For example the following command grants the privilege to user mary:

GRANT EXECUTE ON PACKAGE SYS.UTL_FILE TO mary;

Also, the operating system username, enterprisedb , must have the appropriate read and/or write permissions on the directories and files to be accessed using the UTL_FILE functions and procedures. If the required file permissions are not in place, an exception is thrown in the UTL_FILE function or procedure.

A handle to the file to be written to, or read from is used to reference the file. The *file handle* is defined by a public variable in the <code>UTL_FILE</code> package named, <code>UTL_FILE.FILE_TYPE</code> . A variable of type <code>FILE_TYPE</code> must be declared to receive the file handle returned by calling the <code>FOPEN</code> function. The file handle is then used for all subsequent operations on the file.

References to directories on the file system are done using the directory name or alias that is assigned to the directory using the CREATE DIRECTORY command. The procedures and functions available in the UTL_FILE package are listed in the following table:

Function/Procedure	Return Type	Description
FCLOSE(file IN OUT)	n/a	Closes the specified file identified
FCLOSE_ALL	n/a	Closes all open files.
FCOPY(location, filename, dest_dir, dest_file [, start_line [, end_line]])	n/a	Copies filename in the directory id
FFLUSH(file)	n/a	Forces data in the buffer to be wri
FOPEN(location, filename, open_mode [, max_linesize])	FILE_TYPE	Opens file, filename, in the directo
FREMOVE(location, filename)	n/a	Removes the specified file from the
FRENAME(location, filename, dest_dir, dest_file [, overwrite])	n/a	Renames the specified file.
GET_LINE(file, buffer OUT)	n/a	Reads a line of text into variable,
IS_OPEN(file)	BOOLEAN	Determines whether or not the given
NEW_LINE(file [, lines])	n/a	Writes an end-of-line character se
PUT(file, buffer)	n/a	Writes buffer to the given file. PU
PUT_LINE(file, buffer)	n/a	Writes buffer to the given file. An
PUTF(file, format [, arg1] [,])	n/a	Writes a formatted string to the given

Advanced Server's implementation of UTL_FILE is a partial implementation when compared to Oracle's version. Only those functions and procedures listed in the table above are supported.

UTL FILE Exception Codes

If a call to a UTL_FILE procedure or function raises an exception, you can use the condition name to catch the exception. The UTL_FILE package reports the following exception codes compatible with Oracle databases:

Exception Code	Condition name
-29283	invalid_operation
-29285	write_error
-29284	read_error
-29282	invalid_filehandle
-29287	invalid_maxlinesize
-29281	invalid_mode
-29280	invalid_path

Setting File Permissions with utl_file.umask

When a UTL_FILE function or procedure creates a file, there are default file permissions as shown by the following.

```
-rw----- 1 enterprisedb enterprisedb 21 Jul 24 16:08 utlfile
```

Note that all permissions are denied on users belonging to the enterprisedb group as well as all other users. Only the enterprisedb user has read and write permissions on the created file.

If you wish to have a different set of file permissions on files created by the UTL_FILE functions and procedures, you can accomplish this by setting the utl_file.umask configuration parameter.

The utl_file.umask parameter sets the *file mode creation mask* or simply, the *mask*, in a manner similar to the Linux umask command. This is for usage only within the Advanced Server UTL_FILE package.

Note

The utl_file.umask parameter is not supported on Windows systems.

The value specified for utl_file.umask is a 3 or 4-character octal string that would be valid for the Linux umask command. The setting determines the permissions on files created by the UTL_FILE functions and procedures. (Refer to any information source regarding Linux or Unix systems for information on file permissions and the usage of the umask command.)

The following is an example of setting the file permissions with utl_file.umask .

First, set up the directory in the file system to be used by the UTL_FILE package. Be sure the operating system account, enterprisedb or postgres, whichever is applicable, can read and write in the directory.

```
mkdir /tmp/utldir
chmod 777 /tmp/utldir
```

The CREATE DIRECTORY command is issued in psql to create the directory database object using the file system directory created in the preceding step.

```
CREATE DIRECTORY utldir AS '/tmp/utldir';
```

Set the utl_file.umask configuration parameter. The following setting allows the file owner any permission. Group users and other users are permitted any permission except for the execute permission.

```
SET utl_file.umask TO '0011';
```

In the same session during which the utl_file.umask parameter is set to the desired value, run the UTL_FILE functions and procedures.

```
DECLARE
```

```
v_utlfile UTL_FILE.FILE_TYPE;
v_directory VARCHAR2(50) := 'utldir';
v_filename VARCHAR2(20) := 'utlfile';
BEGIN
v_utlfile := UTL_FILE.FOPEN(v_directory, v_filename, 'w');
UTL_FILE.PUT_LINE(v_utlfile, 'Simple one-line file');
DBMS_OUTPUT.PUT_LINE('Created file: ' || v_filename);
```

```
UTL_FILE.FCLOSE(v_utlfile);
END;
```

The permission settings on the resulting file show that group users and other users have read and write permissions on the file as well as the file owner.

```
$ pwd
/tmp/utldir
$ ls -l
total 4
-rw-rw-rw- 1 enterprisedb enterprisedb 21 Jul 24 16:04 utlfile
```

This parameter can also be set on a per role basis with the ALTER ROLE command, on a per database basis with the ALTER DATABASE command, or for the entire database server instance by setting it in the postgresql.conf file.

FCLOSE

The FCLOSE procedure closes an open file.

```
FCLOSE(<file> IN OUT FILE_TYPE)
```

Parameters

<file>

Variable of type FILE_TYPE containing a file handle of the file to be closed.

FCLOSE ALL

The FLCLOSE_ALL procedures closes all open files. The procedure executes successfully even if there are no open files to close.

FCLOSE_ALL

FCOPY

The FCOPY procedure copies text from one file to another.

Parameters

<location>

Directory name, as stored in pg_catalog.edb_dir.dirname, of the directory containing the file to be copied.

<filename>

Name of the source file to be copied.

```
<dest_dir>
```

Directory name, as stored in pg_catalog.edb_dir.dirname, of the directory to which the file is to be copied.

```
<dest_file>
```

Name of the destination file.

```
<start_line>
```

Line number in the source file from which copying will begin. The default is 1.

<end_line>

Line number of the last line in the source file to be copied. If omitted or null, copying will go to the last line of the file.

Examples

CREATE DIRECTORY empdir AS 'C:/TEMP/EMPDIR';

The following makes a copy of a file, C:\TEMP\EMPDIR\empfile.csv , containing a comma-delimited list of employees from the emp table. The copy, empcopy.csv , is then listed.

```
DECLARE
    v_empfile
                     UTL_FILE.FILE_TYPE;
    v_src_dir
                     VARCHAR2(50) := 'empdir';
    v_src_file
                     VARCHAR2(20) := 'empfile.csv';
                     VARCHAR2(50) := 'empdir';
    v_dest_dir
                     VARCHAR2(20) := 'empcopy.csv';
    v_dest_file
    v_emprec
                     VARCHAR2(120);
    v_count
                     INTEGER := 0;
BEGIN
    UTL_FILE.FCOPY(v_src_dir,v_src_file,v_dest_dir,v_dest_file);
    v_empfile := UTL_FILE.FOPEN(v_dest_dir,v_dest_file,'r');
    DBMS_OUTPUT.PUT_LINE('The following is the destination file, ''' ||
        v_dest_file || '''');
    L00P
        UTL_FILE.GET_LINE(v_empfile,v_emprec);
        DBMS_OUTPUT.PUT_LINE(v_emprec);
        v_{count} := v_{count} + 1;
    END LOOP;
    EXCEPTION
        WHEN NO_DATA_FOUND THEN
             UTL_FILE.FCLOSE(v_empfile);
             DBMS_OUTPUT.PUT_LINE(v_count || ' records retrieved');
        WHEN OTHERS THEN
             DBMS_OUTPUT.PUT_LINE('SQLERRM: ' || SQLERRM);
             DBMS_OUTPUT.PUT_LINE('SQLCODE: ' || SQLCODE);
END;
The following is the destination file, 'empcopy.csv'
7369, SMITH, CLERK, 7902, 17-DEC-80, 800, ,20
7499, ALLEN, SALESMAN, 7698, 20-FEB-81, 1600, 300, 30
7521, WARD, SALESMAN, 7698, 22-FEB-81, 1250, 500, 30
7566, JONES, MANAGER, 7839, 02-APR-81, 2975, , 20
7654, MARTIN, SALESMAN, 7698, 28-SEP-81, 1250, 1400, 30
7698, BLAKE, MANAGER, 7839, 01-MAY-81, 2850, ,30
7782, CLARK, MANAGER, 7839, 09-JUN-81, 2450, ,10
7788, SCOTT, ANALYST, 7566, 19-APR-87, 3000, , 20
7839, KING, PRESIDENT, ,17-NOV-81,5000, ,10
7844, TURNER, SALESMAN, 7698, 08-SEP-81, 1500, 0, 30
7876, ADAMS, CLERK, 7788, 23-MAY-87, 1100, , 20
7900, JAMES, CLERK, 7698, 03-DEC-81, 950, ,30
7902, FORD, ANALYST, 7566, 03-DEC-81, 3000, ,20
7934, MILLER, CLERK, 7782, 23-JAN-82, 1300, ,10
14 records retrieved
```

FFLUSH

The FFLUSH procedure flushes unwritten data from the write buffer to the file.

```
FFLUSH(<file> FILE_TYPE)
```

Parameters

```
<file>
```

Variable of type FILE_TYPE containing a file handle.

Examples

```
Each line is flushed after the NEW_LINE procedure is called.
DECLARE
    v_empfile
                      UTL_FILE.FILE_TYPE;
    v_directory
                      VARCHAR2(50) := 'empdir';
                      VARCHAR2(20) := 'empfile.csv';
    v_filename
    CURSOR emp_cur IS SELECT * FROM emp ORDER BY empno;
    v_empfile := UTL_FILE.FOPEN(v_directory,v_filename,'w');
    FOR i IN emp_cur LOOP
        UTL_FILE.PUT(v_empfile,i.empno);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.ename);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.job);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.mgr);
        UTL_FILE.PUT(v_empfile,',');
UTL_FILE.PUT(v_empfile,i.hiredate);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.sal);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.comm);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.deptno);
        UTL_FILE.NEW_LINE(v_empfile);
        UTL_FILE.FFLUSH(v_empfile);
    END LOOP;
    DBMS_OUTPUT.PUT_LINE('Created file: ' || v_filename);
    UTL_FILE.FCLOSE(v_empfile);
END;
FOPEN
The FOPEN function opens a file for I/O.
     <filetype> FILE_TYPE FOPEN(<location> VARCHAR2 ,
     <filename> VARCHAR2,<open_mode> VARCHAR2
    [, <max_linesize> BINARY_INTEGER ])
Parameters
<location>
    Directory name, as stored in pg_catalog.edb_dir.dirname, of the directory containing the
    file to be opened.
<filename>
    Name of the file to be opened.
<open_mode>
    Mode in which the file will be opened. Modes are: a - append to file; r - read from file; w -
    write to file.
<max_linesize>
```

Maximum size of a line in characters. In read mode, an exception is thrown if an attempt is made to read a line exceeding <max_linesize> . In write and append modes, an exception is thrown if an attempt is made to write a line exceeding <max_linesize> . The end-of-line character(s) are not included in determining if the maximum line size is exceeded. This behavior is not compatible with Oracle databases; Oracle does count the end-of-line character(s).

```
<filetype>
```

Variable of type FILE_TYPE containing the file handle of the opened file.

FREMOVE

The FREMOVE procedure removes a file from the system.

```
FREMOVE(<location> VARCHAR2, <filename> VARCHAR2)
```

An exception is thrown if the file to be removed does not exist.

Parameters

```
<location>
```

Directory name, as stored in pg_catalog.edb_dir.dirname, of the directory containing the file to be removed.

<filename>

Name of the file to be removed.

Examples

```
The following removes file empfile.csv .
```

FRENAME

Removed file: empfile.csv

The FRENAME procedure renames a given file. This effectively moves a file from one location to another.

Parameters

```
<location>
```

Directory name, as stored in pg_catalog.edb_dir.dirname, of the directory containing the file to be renamed.

```
<filename>
```

Name of the source file to be renamed.

```
<dest_dir>
```

Directory name, as stored in pg_catalog.edb_dir.dirname, of the directory to which the renamed file is to exist.

```
<dest_file>
```

New name of the original file.

```
<overwrite>
```

Replaces any existing file named <dest_file> in <dest_dir> if set to TRUE, otherwise an exception is thrown if set to FALSE. This is the default.

Examples

The following renames a file, C:\TEMP\EMPDIR\empfile.csv , containing a comma-delimited list of employees from the emp table. The renamed file, C:\TEMP\NEWDIR\newemp.csv , is then listed.

CREATE DIRECTORY "newdir" AS 'C:/TEMP/NEWDIR';

```
DECLARE
    v_empfile
                     UTL_FILE.FILE_TYPE;
                     VARCHAR2(50) := 'empdir';
    v_src_dir
                     VARCHAR2(20) := 'empfile.csv';
    v_src_file
                     VARCHAR2(50) := 'newdir';
    v_dest_dir
                     VARCHAR2(50) := 'newemp.csv';
    v_dest_file
    v_replace
                     BOOLEAN := FALSE;
                     VARCHAR2(120);
    v_emprec
    v_count
                     INTEGER := 0;
BEGIN
    UTL_FILE.FRENAME(v_src_dir,v_src_file,v_dest_dir,
        v_dest_file,v_replace);
    v_empfile := UTL_FILE.FOPEN(v_dest_dir,v_dest_file,'r');
    DBMS_OUTPUT.PUT_LINE('The following is the renamed file, ''' ||
        v_dest_file || '''');
    I 00P
        UTL_FILE.GET_LINE(v_empfile,v_emprec);
        DBMS_OUTPUT.PUT_LINE(v_emprec);
        v_count := v_count + 1;
    END LOOP;
    EXCEPTION
        WHEN NO_DATA_FOUND THEN
            UTL_FILE.FCLOSE(v_empfile);
            DBMS_OUTPUT.PUT_LINE(v_count || ' records retrieved');
        WHEN OTHERS THEN
            DBMS_OUTPUT.PUT_LINE('SOLERRM: ' | SOLERRM);
            DBMS_OUTPUT.PUT_LINE('SQLCODE: ' || SQLCODE);
END;
The following is the renamed file, 'newemp.csv'
7369, SMITH, CLERK, 7902, 17-DEC-80 00:00:00, 800.00, 20
7499, ALLEN, SALESMAN, 7698, 20-FEB-81 00:00:00, 1600.00, 300.00, 30
7521, WARD, SALESMAN, 7698, 22-FEB-81 00:00:00, 1250.00, 500.00, 30
7566, JONES, MANAGER, 7839, 02-APR-81 00:00:00, 2975.00, ,20
7654, MARTIN, SALESMAN, 7698, 28-SEP-81 00:00:00, 1250.00, 1400.00, 30
7698, BLAKE, MANAGER, 7839, 01-MAY-81 00:00:00, 2850.00, 30
7782, CLARK, MANAGER, 7839, 09-JUN-81 00:00:00, 2450.00, 10
7788, SCOTT, ANALYST, 7566, 19-APR-87 00:00:00, 3000.00, 20
7839,KING,PRESIDENT,,17-NOV-81 00:00:00,5000.00,,10
7844, TURNER, SALESMAN, 7698, 08-SEP-81 00:00:00, 1500.00, 0.00, 30
7876, ADAMS, CLERK, 7788, 23-MAY-87 00:00:00, 1100.00, 20
7900, JAMES, CLERK, 7698, 03-DEC-81 00:00:00, 950.00, 30
```

```
7902, FORD, ANALYST, 7566, 03-DEC-81 00:00:00, 3000.00, 20 7934, MILLER, CLERK, 7782, 23-JAN-82 00:00:00, 1300.00, 10 14 records retrieved
```

GET_LINE

The GET_LINE procedure reads a line of text from a given file up to, but not including the end-of-line terminator.

A NO_DATA_FOUND exception is thrown when there are no more lines to read.

```
GET_LINE(<file> FILE_TYPE, <buffer> OUT VARCHAR2)
```

Parameters

<file>

Variable of type FILE_TYPE containing the file handle of the opened file.

<buffer>

Variable to receive a line from the file.

Examples

The following anonymous block reads through and displays the records in file empfile.csv.

```
DECLARE
    v_empfile
                     UTL_FILE.FILE_TYPE;
                     VARCHAR2(50) := 'empdir';
    v_directory
                     VARCHAR2(20) := 'empfile.csv';
    v_filename
    v_emprec
                     VARCHAR2(120);
                     INTEGER := 0;
    v_count
BEGIN
    v_empfile := UTL_FILE.FOPEN(v_directory,v_filename,'r');
    L<sub>00</sub>P
        UTL_FILE.GET_LINE(v_empfile,v_emprec);
        DBMS_OUTPUT.PUT_LINE(v_emprec);
        v_{count} := v_{count} + 1;
    END LOOP:
    EXCEPTION
        WHEN NO_DATA_FOUND THEN
             UTL_FILE.FCLOSE(v_empfile);
             DBMS_OUTPUT.PUT_LINE('End of file ' || v_filename || ' - ' ||
                 v_count || ' records retrieved');
        WHEN OTHERS THEN
             DBMS_OUTPUT.PUT_LINE('SOLERRM: ' | SOLERRM);
             DBMS_OUTPUT.PUT_LINE('SQLCODE: ' || SQLCODE);
END;
7369, SMITH, CLERK, 7902, 17-DEC-80 00:00:00, 800.00, 20
7499, ALLEN, SALESMAN, 7698, 20-FEB-81 00:00:00, 1600.00, 300.00, 30
7521, WARD, SALESMAN, 7698, 22-FEB-81 00:00:00, 1250.00, 500.00, 30
7566, JONES, MANAGER, 7839, 02-APR-81 00:00:00, 2975.00, 20
7654, MARTIN, SALESMAN, 7698, 28-SEP-81 00:00:00, 1250.00, 1400.00, 30
7698, BLAKE, MANAGER, 7839, 01-MAY-81 00:00:00, 2850.00, 30
7782, CLARK, MANAGER, 7839, 09-JUN-81 00:00:00, 2450.00, 10
7788, SCOTT, ANALYST, 7566, 19-APR-87 00:00:00, 3000.00, 20
7839, KING, PRESIDENT, ,17-NOV-81 00:00:00,5000.00,,10
7844, TURNER, SALESMAN, 7698, 08-SEP-81 00:00:00, 1500.00, 0.00, 30
7876, ADAMS, CLERK, 7788, 23-MAY-87 00:00:00, 1100.00, 20
7900, JAMES, CLERK, 7698, 03-DEC-81 00:00:00, 950.00, 30
7902, FORD, ANALYST, 7566, 03-DEC-81 00:00:00, 3000.00, 20
7934, MILLER, CLERK, 7782, 23-JAN-82 00:00:00, 1300.00, 10
End of file empfile.csv - 14 records retrieved
```

IS OPEN

The IS_OPEN function determines whether or not the given file is open.

```
<status> BOOLEAN IS_OPEN(<file> FILE_TYPE)
```

Parameters

```
<file>
```

Variable of type FILE_TYPE containing the file handle of the file to be tested.

<status>

TRUE if the given file is open, FALSE otherwise.

NEW_LINE

The NEW_LINE procedure writes an end-of-line character sequence in the file.

```
NEW_LINE(<file> FILE_TYPE [, <lines> INTEGER ])
```

Parameters

<file>

Variable of type FILE_TYPE containing the file handle of the file to which end-of-line character sequences are to be written.

lines>

Number of end-of-line character sequences to be written. The default is one.

Examples

Created file: empfile.csv

A file containing a double-spaced list of employee records is written.

```
DECLARE
    v_empfile
                    UTL_FILE.FILE_TYPE;
                    VARCHAR2(50) := 'empdir';
    v_directory
    v filename
                    VARCHAR2(20) := 'empfile.csv';
    CURSOR emp_cur IS SELECT * FROM emp ORDER BY empno;
BEGIN
    v_empfile := UTL_FILE.FOPEN(v_directory,v_filename,'w');
    FOR i IN emp_cur LOOP
        UTL_FILE.PUT(v_empfile,i.empno);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.ename);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.job);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.mgr);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.hiredate);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.sal);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.comm);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.deptno);
        UTL_FILE.NEW_LINE(v_empfile,2);
    END LOOP:
    DBMS_OUTPUT.PUT_LINE('Created file: ' || v_filename);
    UTL_FILE.FCLOSE(v_empfile);
END;
```

```
This file is then displayed:
```

```
C:\TEMP\EMPDIR>TYPE empfile.csv
```

```
7369, SMITH, CLERK, 7902, 17-DEC-80 00:00:00, 800.00, 20
```

7499, ALLEN, SALESMAN, 7698, 20-FEB-81 00:00:00, 1600.00, 300.00, 30

7521, WARD, SALESMAN, 7698, 22-FEB-81 00:00:00, 1250.00, 500.00, 30

7566, JONES, MANAGER, 7839, 02-APR-81 00:00:00, 2975.00, 20

7654, MARTIN, SALESMAN, 7698, 28-SEP-81 00:00:00, 1250.00, 1400.00, 30

7698, BLAKE, MANAGER, 7839, 01-MAY-81 00:00:00, 2850.00, 30

7782, CLARK, MANAGER, 7839, 09-JUN-81 00:00:00, 2450.00, 10

7788, SCOTT, ANALYST, 7566, 19-APR-87 00:00:00, 3000.00, 20

7839, KING, PRESIDENT, ,17-NOV-81 00:00:00,5000.00, ,10

7844, TURNER, SALESMAN, 7698, 08-SEP-81 00:00:00, 1500.00, 0.00, 30

7876, ADAMS, CLERK, 7788, 23-MAY-87 00:00:00, 1100.00, ,20

7900, JAMES, CLERK, 7698, 03-DEC-81 00:00:00, 950.00, 30

7902, FORD, ANALYST, 7566, 03-DEC-81 00:00:00, 3000.00, 20

7934, MILLER, CLERK, 7782, 23-JAN-82 00:00:00, 1300.00, ,10

UTL_FILE_PUT

PUT

The PUT procedure writes a string to the given file. No end-of-line character sequence is written at the end of the string. Use the NEW_LINE procedure to add an end-of-line character sequence.

Parameters

<file>

Variable of type FILE_TYPE containing the file handle of the file to which the given string is to be written.

<buffer>

Text to be written to the specified file.

Examples

The following example uses the PUT procedure to create a comma-delimited file of employees from the emptable.

```
DECLARE
```

```
v_empfile    UTL_FILE.FILE_TYPE;
v_directory    VARCHAR2(50) := 'empdir';
v_filename    VARCHAR2(20) := 'empfile.csv';
CURSOR emp_cur IS SELECT * FROM emp ORDER BY empno;
BEGIN
```

```
v_empfile := UTL_FILE.FOPEN(v_directory,v_filename,'w');
    FOR i IN emp_cur LOOP
        UTL_FILE.PUT(v_empfile,i.empno);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.ename);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.job);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.mgr);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.hiredate);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.sal);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.comm);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.deptno);
        UTL_FILE.NEW_LINE(v_empfile);
    END LOOP;
    DBMS_OUTPUT.PUT_LINE('Created file: ' || v_filename);
    UTL_FILE.FCLOSE(v_empfile);
END:
Created file: empfile.csv
The following is the contents of empfile.csv created above:
C:\TEMP\EMPDIR>TYPE empfile.csv
7369, SMITH, CLERK, 7902, 17-DEC-80 00:00:00, 800.00, 20
7499, ALLEN, SALESMAN, 7698, 20-FEB-81 00:00:00, 1600.00, 300.00, 30
7521, WARD, SALESMAN, 7698, 22-FEB-81 00:00:00, 1250.00, 500.00, 30
7566, JONES, MANAGER, 7839, 02-APR-81 00:00:00, 2975.00, 20
7654, MARTIN, SALESMAN, 7698, 28-SEP-81 00:00:00, 1250.00, 1400.00, 30
7698, BLAKE, MANAGER, 7839, 01-MAY-81 00:00:00, 2850.00, 30
7782, CLARK, MANAGER, 7839, 09-JUN-81 00:00:00, 2450.00, 10
7788, SCOTT, ANALYST, 7566, 19-APR-87 00:00:00, 3000.00, 20
7839,KING,PRESIDENT,,17-NOV-81 00:00:00,5000.00,,10
7844, TURNER, SALESMAN, 7698, 08-SEP-81 00:00:00, 1500.00, 0.00, 30
7876, ADAMS, CLERK, 7788, 23-MAY-87 00:00:00, 1100.00, 20
7900, JAMES, CLERK, 7698, 03-DEC-81 00:00:00, 950.00, 30
7902, FORD, ANALYST, 7566, 03-DEC-81 00:00:00, 3000.00, ,20
7934, MILLER, CLERK, 7782, 23-JAN-82 00:00:00, 1300.00, 10
UTL FILE PUT LINE
PUT_LINE
The PUT_LINE procedure writes a single line to the given file including an end-of-line character sequence.
     PUT_LINE(<file> FILE_TYPE ,
     <buffer> {DATE|NUMBER|TIMESTAMP|VARCHAR2})
Parameters
<file>
```

Text to be written to the specified file.

<buffer>

Variable of type FILE_TYPE containing the file handle of the file to which the given line is to be

Examples

DECLARE

The following example uses the PUT_LINE procedure to create a comma-delimited file of employees from the emp table.

```
v_empfile
                     UTL_FILE.FILE_TYPE;
                     VARCHAR2(50) := 'empdir';
    v_directory
                     VARCHAR2(20) := 'empfile.csv';
    v_filename
    v emprec
                     VARCHAR2(120);
    CURSOR emp_cur IS SELECT * FROM emp ORDER BY empno;
BEGIN
    v_empfile := UTL_FILE.FOPEN(v_directory,v_filename,'w');
    FOR i IN emp_cur LOOP
        v_emprec := i.empno || ',' || i.ename || ',' || i.job || ',' ||
             NVL(LTRIM(TO_CHAR(i.mgr,'9999')),'') || ',' || i.hiredate ||
             ',' || i.sal || ',' ||
            NVL(LTRIM(TO_CHAR(i.comm, '9990.99')),'') || ',' || i.deptno;
        UTL_FILE.PUT_LINE(v_empfile,v_emprec);
    END LOOP:
    DBMS_OUTPUT.PUT_LINE('Created file: ' || v_filename);
    UTL_FILE.FCLOSE(v_empfile);
END;
The following is the contents of empfile.csv created above:
C:\TEMP\EMPDIR>TYPE empfile.csv
7369, SMITH, CLERK, 7902, 17-DEC-80 00:00:00, 800.00, 20
7499, ALLEN, SALESMAN, 7698, 20-FEB-81 00:00:00, 1600.00, 300.00, 30
7521, WARD, SALESMAN, 7698, 22-FEB-81 00:00:00, 1250.00, 500.00, 30
7566, JONES, MANAGER, 7839, 02-APR-81 00:00:00, 2975.00, 20
7654, MARTIN, SALESMAN, 7698, 28-SEP-81 00:00:00, 1250.00, 1400.00, 30
7698, BLAKE, MANAGER, 7839, 01-MAY-81 00:00:00, 2850.00, 30
7782, CLARK, MANAGER, 7839, 09-JUN-81 00:00:00, 2450.00, 10
7788, SCOTT, ANALYST, 7566, 19-APR-87 00:00:00, 3000.00, 20
7839,KING,PRESIDENT,,17-NOV-81 00:00:00,5000.00,,10
7844, TURNER, SALESMAN, 7698, 08-SEP-81 00:00:00, 1500.00, 0.00, 30
7876, ADAMS, CLERK, 7788, 23-MAY-87 00:00:00, 1100.00, 20
7900, JAMES, CLERK, 7698, 03-DEC-81 00:00:00, 950.00, 30
7902, FORD, ANALYST, 7566, 03-DEC-81 00:00:00, 3000.00, 20
7934, MILLER, CLERK, 7782, 23-JAN-82 00:00:00, 1300.00, ,10
PUTF
```

The PUTF procedure writes a formatted string to the given file.

```
PUTF(<file> FILE_TYPE, <format> VARCHAR2 [, <arg1> VARCHAR2]
[, ...])
```

Parameters

<file>

Variable of type FILE_TYPE containing the file handle of the file to which the formatted line is to be written.

<format>

String to format the text written to the file. The special character sequence, \(\%s \), is substituted by the value of arg. The special character sequence, \n, indicates a new line. Note, however, in Advanced Server, a new line character must be specified with two consecutive backslashes instead of one - \\n . This characteristic is not compatible with Oracle databases.

```
<arg1>
```

Up to five arguments, $\langle arg1 \rangle$,... $\langle arg5 \rangle$, to be substituted in the format string for each occurrence of %s. The first arg is substituted for the first occurrence of %s, the second arg is substituted for the second occurrence of %s, etc.

Examples

The following anonymous block produces formatted output containing data from the emp table. Note the use of the E literal syntax and double backslashes for the new line character sequence in the format string which are not compatible with Oracle databases.

```
DECLARE
                    UTL_FILE.FILE_TYPE;
    v_empfile
    v_directory
                    VARCHAR2(50) := 'empdir';
    v_filename
                    VARCHAR2(20) := 'empfile.csv';
    v_format
                    VARCHAR2(200);
    CURSOR emp_cur IS SELECT * FROM emp ORDER BY empno;
BEGIN
    v_format := E'%s %s, %s\\nSalary: $%s Commission: $%s\\n\\n';
    v_empfile := UTL_FILE.FOPEN(v_directory,v_filename,'w');
    FOR i IN emp_cur LOOP
        UTL_FILE.PUTF(v_empfile,v_format,i.empno,i.ename,i.job,i.sal,
            NVL(i.comm, 0));
    END LOOP;
    DBMS_OUTPUT.PUT_LINE('Created file: ' || v_filename);
    UTL_FILE.FCLOSE(v_empfile);
EXCEPTION
    WHEN OTHERS THEN
        DBMS_OUTPUT.PUT_LINE('SQLERRM: ' || SQLERRM);
        DBMS_OUTPUT.PUT_LINE('SQLCODE: ' || SQLCODE);
END;
Created file: empfile.csv
The following is the contents of empfile.csv created above:
C:\TEMP\EMPDIR>TYPE empfile.csv
7369 SMITH, CLERK
Salary: $800.00 Commission: $0
7499 ALLEN, SALESMAN
Salary: $1600.00 Commission: $300.00
7521 WARD, SALESMAN
Salary: $1250.00 Commission: $500.00
7566 JONES, MANAGER
Salary: $2975.00 Commission: $0
7654 MARTIN, SALESMAN
Salary: $1250.00 Commission: $1400.00
7698 BLAKE, MANAGER
Salary: $2850.00 Commission: $0
7782 CLARK, MANAGER
Salary: $2450.00 Commission: $0
7788 SCOTT, ANALYST
Salary: $3000.00 Commission: $0
7839 KING, PRESIDENT
Salary: $5000.00 Commission: $0
7844 TURNER, SALESMAN
Salary: $1500.00 Commission: $0.00
7876 ADAMS, CLERK
Salary: $1100.00 Commission: $0
7900 JAMES, CLERK
Salary: $950.00 Commission: $0
```

7902 FORD, ANALYST

Salary: \$3000.00 Commission: \$0

7934 MILLER, CLERK

Salary: \$1300.00 Commission: \$0

5.3.21 UTL HTTP

The UTL_HTTP package provides a way to use the HTTP or HTTPS protocol to retrieve information found at an URL. Advanced Server supports the following functions and procedures:

Function/Procedure	Return Type	Description
BEGIN_REQUEST(url, method, http_version)	UTL_HTTP.REQ	Initiates a new HTTP request.
END_REQUEST(r IN OUT)	n/a	Ends an HTTP request before
END_RESPONSE(r IN OUT)	n/a	Ends the HTTP response.
GET_BODY_CHARSET	VARCHAR2	Returns the default character
GET_BODY_CHARSET(charset OUT)	n/a	Returns the default character
GET_FOLLOW_REDIRECT(max_redirects OUT)	n/a	Current setting for the maximu
GET_HEADER(r IN OUT, n, name OUT, value OUT)	n/a	Returns the nth header of the
GET_HEADER_BY_NAME(r IN OUT, name, value OUT, n)	n/a	Returns the HTTP response h
GET_HEADER_COUNT(r IN OUT)	INTEGER	Returns the number of HTTP
GET_RESPONSE(r IN OUT)	UTL_HTTP.RESP	Returns the HTTP response.
GET_RESPONSE_ERROR_CHECK(enable OUT)	n/a	Returns whether or not respor
GET_TRANSFER_TIMEOUT(timeout OUT)	n/a	Returns the transfer timeout s
(r IN OUT, data OUT, remove_crlf)	n/a	Returns the HTTP response b
READ_RAW(r IN OUT, data OUT, len)	n/a	Returns the HTTP response b
READ_TEXT(r IN OUT, data OUT, len)	n/a	Returns the HTTP response b
REQUEST(url)	VARCHAR2	Returns the content of a web
REQUEST_PIECES(url, max_pieces)	UTL_HTTP. HTML_PIECES	Returns a table of 2000-byte s
SET_BODY_CHARSET(charset)	n/a	Sets the default character set
SET_FOLLOW_REDIRECT(max_redirects)	n/a	Sets the maximum number of
SET_FOLLOW_REDIRECT(r IN OUT, max_redirects)	n/a	Sets the maximum number of
SET_HEADER(r IN OUT, name, value)	n/a	Sets the HTTP request heade
SET_RESPONSE_ERROR_CHECK(enable)	n/a	Determines whether or not HT
SET_TRANSFER_TIMEOUT(timeout)	n/a	Sets the default, transfer time
SET_TRANSFER_TIMEOUT(r IN OUT, timeout)	n/a	Sets the transfer timeout value
WRITE_LINE(r IN OUT, data)	n/a	Writes CRLF terminated data
WRITE_RAW(r IN OUT, data)	n/a	Writes data to the HTTP reque
WRITE_TEXT(r IN OUT, data)	n/a	Writes data to the HTTP reque

Advanced Server's implementation of UTL_HTTP is a partial implementation when compared to Oracle's version. Only those functions and procedures listed in the table above are supported.

Note

In Advanced Server, an HTTP 4xx or HTTP 5xx response produces a database error; in Oracle, this is configurable but FALSE by default.

In Advanced Server, the UTL_HTTP text interfaces expect the downloaded data to be in the database encoding. All currently-available interfaces are text interfaces. In Oracle, the encoding is detected from HTTP headers; in the absence of the header, the default is configurable and defaults to ISO-8859-1.

Advanced Server ignores all cookies it receives.

The UTL_HTTP exceptions that can be raised in Oracle are not recognized by Advanced Server. In addition, the error codes returned by Advanced Server are not the same as those returned by Oracle.

There are various public constants available with UTL_HTTP . These are listed in the following tables.

The following table contains UTL_HTTP public constants defining HTTP versions and port assignments.

HTTP VERSIONS HTTP_VERSION_1_0 CONSTANT VARCHAR2(64) := 'HTTP/1.0'; HTTP_VERSION_1_1 CONSTANT VARCHAR2(64) := 'HTTP/1.1'; STANDARD PORT ASSIGNMENTS DEFAULT_HTTP_PORT CONSTANT INTEGER := 80; DEFAULT_HTTPS_PORT CONSTANT INTEGER := 443;

The following table contains UTL_HTTP public status code constants.

1XX INFORMATIONAL	
HTTP_CONTINUE	CONSTANT INTEGER := 100;
HTTP_SWITCHING_PROTOCOLS	CONSTANT INTEGER := 101;
HTTP_PROCESSING	CONSTANT INTEGER := 102;
2XX SUCCESS	
HTTP_OK	CONSTANT INTEGER := 200;
HTTP_CREATED	CONSTANT INTEGER := 201;
HTTP_ACCEPTED	CONSTANT INTEGER := 202;
HTTP_NON_AUTHORITATIVE_INFO	CONSTANT INTEGER := 203;
HTTP_NO_CONTENT	CONSTANT INTEGER := 204;
HTTP_RESET_CONTENT	CONSTANT INTEGER := 205;
HTTP_PARTIAL_CONTENT	CONSTANT INTEGER := 206;
HTTP_MULTI_STATUS	CONSTANT INTEGER := 207;
HTTP_ALREADY_REPORTED	CONSTANT INTEGER := 208;
HTTP_IM_USED	CONSTANT INTEGER := 226;
3XX REDIRECTION	
HTTP_MULTIPLE_CHOICES	CONSTANT INTEGER := 300;
HTTP_MOVED_PERMANENTLY	CONSTANT INTEGER := 301;
HTTP_FOUND	CONSTANT INTEGER := 302;
HTTP_SEE_OTHER	CONSTANT INTEGER := 303;
HTTP_NOT_MODIFIED	CONSTANT INTEGER := 304;
HTTP_USE_PROXY	CONSTANT INTEGER := 305;
HTTP_SWITCH_PROXY	CONSTANT INTEGER := 306;
HTTP_TEMPORARY_REDIRECT	CONSTANT INTEGER := 307;
HTTP_PERMANENT_REDIRECT	CONSTANT INTEGER := 308;

4XX CLIENT ERROR

HTTP_BAD_REQUEST	CONSTANT INTEGER := 400;
HTTP_UNAUTHORIZED	CONSTANT INTEGER := 401;
HTTP_PAYMENT_REQUIRED	CONSTANT INTEGER := 402;
HTTP_FORBIDDEN	CONSTANT INTEGER := 403;
HTTP_NOT_FOUND	CONSTANT INTEGER := 404;
HTTP_METHOD_NOT_ALLOWED	CONSTANT INTEGER := 405;
HTTP_NOT_ACCEPTABLE	CONSTANT INTEGER := 406;
HTTP_PROXY_AUTH_REQUIRED	CONSTANT INTEGER := 407;
HTTP_REQUEST_TIME_OUT	CONSTANT INTEGER := 408;
HTTP_CONFLICT	CONSTANT INTEGER := 409;
HTTP_GONE	CONSTANT INTEGER := 410;
HTTP_LENGTH_REQUIRED	CONSTANT INTEGER := 411;
HTTP_PRECONDITION_FAILED	CONSTANT INTEGER := 412;
HTTP_REQUEST_ENTITY_TOO_LARGE	CONSTANT INTEGER := 413;
HTTP_REQUEST_URI_TOO_LARGE	CONSTANT INTEGER := 414;
HTTP_UNSUPPORTED_MEDIA_TYPE	CONSTANT INTEGER := 415;
HTTP_REQ_RANGE_NOT_SATISFIABLE	CONSTANT INTEGER := 416;
HTTP_EXPECTATION_FAILED	CONSTANT INTEGER := 417;
HTTP_I_AM_A_TEAPOT	CONSTANT INTEGER := 418;
HTTP_AUTHENTICATION_TIME_OUT	CONSTANT INTEGER := 419;

4XX CLIENT ERROR HTTP ENHANCE YOUR CALM CONSTANT INTEGER := 420: HTTP_UNPROCESSABLE_ENTITY CONSTANT INTEGER := 422: HTTP LOCKED CONSTANT INTEGER := 423; HTTP FAILED DEPENDENCY CONSTANT INTEGER := 424; HTTP UNORDERED COLLECTION CONSTANT INTEGER := 425; HTTP_UPGRADE_REQUIRED CONSTANT INTEGER := 426; HTTP_PRECONDITION_REQUIRED CONSTANT INTEGER := 428; HTTP_TOO_MANY_REQUESTS CONSTANT INTEGER := 429; HTTP_REQUEST_HEADER_FIELDS_TOO_LARGE CONSTANT INTEGER := 431; HTTP_NO_RESPONSE CONSTANT INTEGER := 444; CONSTANT INTEGER := 449; HTTP_RETRY_WITH HTTP_BLOCKED_BY_WINDOWS_PARENTAL_CONTROLS CONSTANT INTEGER := 450: HTTP REDIRECT CONSTANT INTEGER := 451; HTTP_REQUEST_HEADER_TOO_LARGE CONSTANT INTEGER := 494; HTTP_CERT_ERROR CONSTANT INTEGER := 495; HTTP_NO_CERT CONSTANT INTEGER := 496; HTTP_HTTP_TO_HTTPS CONSTANT INTEGER := 497; HTTP_CLIENT_CLOSED_REQUEST CONSTANT INTEGER := 499;

5XX SERVER ERROR	
HTTP_INTERNAL_SERVER_ERROR	CONSTANT INTEGER := 500;
HTTP_NOT_IMPLEMENTED	CONSTANT INTEGER := 501;
HTTP_BAD_GATEWAY	CONSTANT INTEGER := 502;
HTTP_SERVICE_UNAVAILABLE	CONSTANT INTEGER := 503;
HTTP_GATEWAY_TIME_OUT	CONSTANT INTEGER := 504;
HTTP_VERSION_NOT_SUPPORTED	CONSTANT INTEGER := 505;
HTTP_VARIANT_ALSO_NEGOTIATES	CONSTANT INTEGER := 506;
HTTP_INSUFFICIENT_STORAGE	CONSTANT INTEGER := 507;
HTTP_LOOP_DETECTED	CONSTANT INTEGER := 508;
HTTP_BANDWIDTH_LIMIT_EXCEEDED	CONSTANT INTEGER := 509;
HTTP_NOT_EXTENDED	CONSTANT INTEGER := 510;
HTTP_NETWORK_AUTHENTICATION_REQUIRED	CONSTANT INTEGER := 511;
HTTP_NETWORK_READ_TIME_OUT_ERROR	CONSTANT INTEGER := 598;
HTTP NETWORK CONNECT TIME OUT ERROR	CONSTANT INTEGER := 599:

HTML_PIECES

The UTL_HTTP package declares a type named HTML_PIECES, which is a table of type VARCHAR2 (2000) indexed by BINARY INTEGER. A value of this type is returned by the REQUEST_PIECES function.

TYPE html_pieces IS TABLE OF VARCHAR2(2000) INDEX BY BINARY_INTEGER;

REQ

The REQ record type holds information about each HTTP request.

```
TYPE req IS RECORD (
url VARCHAR2(32767), -- URL to be accessed
method VARCHAR2(64), -- HTTP method
http_version VARCHAR2(64), -- HTTP version
private_hndl INTEGER -- Holds handle for this request
);
```

RESP

The RESP record type holds information about the response from each HTTP request.

```
TYPE resp IS RECORD (
status_code INTEGER, -- HTTP status code
reason_phrase VARCHAR2(256), -- HTTP response reason phrase
http_version VARCHAR2(64), -- HTTP version
private_hndl INTEGER -- Holds handle for this response
);
```

BEGIN REQUEST

The BEGIN_REQUEST function initiates a new HTTP request. A network connection is established to the web server with the specified URL. The signature is:

```
BEGIN_REQUEST(<url> IN VARCHAR2, <method> IN VARCHAR2 DEFAULT
'GET ', <http_version> IN VARCHAR2 DEFAULT NULL) RETURN
UTL_HTTP.REQ
```

The BEGIN_REQUEST function returns a record of type UTL_HTTP.REQ .

Parameters

```
<url>
```

<url> is the Uniform Resource Locator from which UTL_HTTP will return content.

<method>

<method> is the HTTP method to be used. The default is GET .

<http_version>

<a a href="http-version">>a>a>a>a>a>a>a>a>a>a>a>a>a>a>a>a>a>a>a>a>a>a>a>a>a>a>a>a>a>a>a>a>a>a>a>a<a href="http-ver

END_REQUEST

The END_REQUEST procedure terminates an HTTP request. Use the END_REQUEST procedure to terminate an HTTP request without completing it and waiting for the response. The normal process is to begin the request, get the response, then close the response. The signature is:

```
END_REQUEST(<r> IN OUT UTL_HTTP.REQ)
```

Parameters

<r>

<r> is the HTTP request record.

END RESPONSE

The END_RESPONSE procedure terminates the HTTP response. The END_RESPONSE procedure completes the HTTP request and response. This is the normal method to end the request and response process. The signature is:

```
END_RESPONSE(<r> IN OUT UTL_HTTP.RESP)
```

Parameters

<r>

<r> is the HTTP response record.

GET BODY CHARSET

The GET_BODY_CHARSET program is available in the form of both a procedure and a function. A call to GET_BODY_CHARSET returns the default character set of the body of future HTTP requests.

The procedure signature is:

```
GET_BODY_CHARSET(<charset> OUT VARCHAR2)
```

The function signature is:

```
GET_BODY_CHARSET() RETURN VARCHAR2
```

This function returns a VARCHAR2 value.

Parameters

```
<charset>
```

<charset> is the character set of the body.

Examples

```
The following is an example of the GET_BODY_CHARSET function.
```

```
edb=# SELECT UTL_HTTP.GET_BODY_CHARSET() FROM DUAL;
  get_body_charset
------
  ISO-8859-1
(1 row)
```

GET_FOLLOW_REDIRECT

The GET_FOLLOW_REDIRECT procedure returns the current setting for the maximum number of redirections allowed. The signature is:

```
GET_FOLLOW_REDIRECT(<max_redirects> OUT INTEGER)
```

Parameters

```
<max_redirects>
```

<max_redirects> is maximum number of redirections allowed.

GET_HEADER

The GET_HEADER procedure returns the nth header of the HTTP response. The signature is:

```
GET_HEADER(<r> IN OUT UTL_HTTP.RESP, <n> INTEGER, <name> OUT
VARCHAR2, <value> OUT VARCHAR2)
```

Parameters

<r>

<r> is the HTTP response record.

<n>

<n> is the nth header of the HTTP response record to retrieve.

<name>

<name> is the name of the response header.

<value>

<value> is the value of the response header.

Examples

The following example retrieves the header count, then the headers.

```
DECLARE
                    UTL_HTTP.REQ;
    v_req
    v_resp
                    UTL_HTTP.RESP;
                    VARCHAR2(30);
    v_name
                    VARCHAR2(200);
    v_value
                    INTEGER;
    v_header_cnt
BEGIN
 -- Initiate request and get response
    v_req := UTL_HTTP.BEGIN_REQUEST('www.enterprisedb.com');
    v_resp := UTL_HTTP.GET_RESPONSE(v_req);
 -- Get header count
    v_header_cnt := UTL_HTTP.GET_HEADER_COUNT(v_resp);
    DBMS_OUTPUT.PUT_LINE('Header Count: ' || v_header_cnt);
 -- Get all headers
    FOR i IN 1 .. v_header_cnt LOOP
        UTL_HTTP.GET_HEADER(v_resp, i, v_name, v_value);
        DBMS_OUTPUT.PUT_LINE(v_name | | ': ' | | v_value);
    END LOOP;
 -- Terminate request
    UTL_HTTP.END_RESPONSE(v_resp);
END;
The following is the output from the example.
Header Count: 23
Age: 570
Cache-Control: must-revalidate
Content-Type: text/html; charset=utf-8
Date: Wed, 30 Apr 2015 14:57:52 GMT
ETaq: "aab02f2bd2d696eed817ca89ef411dda"
Expires: Sun, 19 Nov 1978 05:00:00 GMT
Last-Modified: Wed, 30 Apr 2015 14:15:49 GMT
RTSS: 1-1307-3
Server: Apache/2.2.3 (Red Hat)
Set-Cookie: SESS2771d0952de2a1a84d322a262e0c173c=jn1u1j1etmdi5gg4lh8hakvs01; expires=Fri, 23-
May-2015 18:21:43 GMT; path=/; domain=.enterprisedb.com
Vary: Accept-Encoding
Via: 1.1 varnish
X-EDB-Backend: ec
X-EDB-Cache: HIT
X-EDB-Cache-Address: 10.31.162.212
X-EDB-Cache-Server: ip-10-31-162-212
X-EDB-Cache-TTL: 600.000
X-EDB-Cacheable: MAYBE: The user has a cookie of some sort. Maybe it's double choc-chip!
X-EDB-Do-GZIP: false
X-Powered-By: PHP/5.2.17
X-Varnish: 484508634 484506789
transfer-encoding: chunked
Connection: keep-alive
```

GET_HEADER_BY_NAME

The GET_HEADER_BY_NAME procedure returns the header of the HTTP response according to the specified name. The signature is:

```
GET_HEADER_BY_NAME(<r> IN OUT UTL_HTTP.RESP, <name> VARCHAR2 ,
```

```
<value> OUT VARCHAR2, <n> INTEGER DEFAULT 1)
```

Parameters

Examples

The following example retrieves the header for Content-Type.

Content-Type: text/html; charset=utf-8

GET_HEADER_COUNT

The GET_HEADER_COUNT function returns the number of HTTP response headers. The signature is:

```
GET_HEADER_COUNT(<r> IN OUT UTL_HTTP.RESP) RETURN INTEGER
```

This function returns an INTEGER value.

Parameters

<r>

<r> is the HTTP response record.

GET_RESPONSE

The GET_RESPONSE function sends the network request and returns any HTTP response. The signature is:

```
GET_RESPONSE(<r> IN OUT UTL_HTTP.REQ) RETURN UTL_HTTP.RESP
```

This function returns a UTL_HTTP.RESP record.

Parameters

<r>

<r> is the HTTP request record.

GET RESPONSE ERROR CHECK

The GET_RESPONSE_ERROR_CHECK procedure returns whether or not response error check is set. The signature is:

```
GET_RESPONSE_ERROR_CHECK(<enable> OUT BOOLEAN)
```

Parameters

<enable>

<enable> returns TRUE if response error check is set, otherwise it returns FALSE .

GET_TRANSFER_TIMEOUT

The GET_TRANSFER_TIMEOUT procedure returns the current, default transfer timeout setting for HTTP requests. The signature is:

```
GET_TRANSFER_TIMEOUT(<timeout> OUT INTEGER)
```

Parameters

<timeout>

<timeout> is the transfer timeout setting in seconds.

READ LINE

The READ_LINE procedure returns the data from the HTTP response body in text form until the end of line is reached. A CR character, a LF character, a CR LF sequence, or the end of the response body constitutes the end of line. The signature is:

READ_LINE(<r> IN OUT UTL_HTTP.RESP, <data> OUT VARCHAR2, <remove_crlf> BOOLEAN DEFAULT FA

Parameters

Examples

The following example retrieves and displays the body of the specified website.

```
DECLARE
                    UTL_HTTP.REQ;
    v_req
                    UTL_HTTP.RESP;
    v_resp
    v_value
                    VARCHAR2(1024);
BEGIN
    v_req := UTL_HTTP.BEGIN_REQUEST('http://www.enterprisedb.com');
    v_resp := UTL_HTTP.GET_RESPONSE(v_req);
    L00P
        UTL_HTTP.READ_LINE(v_resp, v_value, TRUE);
        DBMS_OUTPUT.PUT_LINE(v_value);
    END LOOP;
    EXCEPTION
        WHEN OTHERS THEN
            UTL_HTTP.END_RESPONSE(v_resp);
END;
```

```
The following is the output.
```

```
<!DOCTYPE html PUBLIC "-//W3C//DTD XHTML 1.0 Strict//EN"</pre>
     "http://www.w3.org/TR/xhtml1/DTD/xhtml1-strict.dtd">
<html xmlns="http://www.w3.org/1999/xhtml" xml:lang="en" lang="en" dir="ltr">
    <!-- _____ HEAD _____ -->
    <head>
<meta http-equiv="Content-Type" content="text/html; charset=utf-8" />
         <title>EnterpriseDB | The Postgres Database Company</title>
         <meta http-equiv="Content-Type" content="text/html; charset=utf-8" />
<meta name="keywords" content="postgres, postgresql, postgresql installer, mysql migration, open</pre>
<meta name="description" content="The leader in open source database products, services, support,</pre>
<meta name="abstract" content="The Enterprise PostgreSQL Company" />
<link rel="EditURI" type="application/rsd+xml" title="RSD" href="http://www.enterprisedb.com/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloom/bloo
<link rel="alternate" type="application/rss+xml" title="EnterpriseDB RSS" href="http://www.enter</pre>
<link rel="shortcut icon" href="/sites/all/themes/edb_pixelcrayons/favicon.ico" type="image/x-</pre>
icon" />
      <link type="text/css" rel="stylesheet" media="all" href="/sites/default/files/css/css_db11ada</pre>
<!--[if IE 6]>
<link type="text/css" rel="stylesheet" media="all" href="/sites/all/themes/oho_basic/css/ie6.cs</pre>
<![endif]-->
<!--[if IE 7]>
<link type="text/css" rel="stylesheet" media="all" href="/sites/all/themes/oho_basic/css/ie7.cs</pre>
<![endif]-->
      <script type="text/javascript" src="/sites/default/files/js/js_74d97b1176812e2fd6e43d62503a5</pre>
<script type="text/javascript">
<!--//--><![CDATA[//><!--
```

READ_RAW

The READ_RAW procedure returns the data from the HTTP response body in binary form. The number of bytes returned is specified by the <len> parameter. The signature is:

```
READ_RAW(<r> IN OUT UTL_HTTP.RESP, <data> OUT RAW, <len> INTEGER)
```

Parameters

Examples

The following example retrieves and displays the first 150 bytes in binary form.

```
UTL_HTTP.READ_RAW(v_resp, v_data, 150);
DBMS_OUTPUT.PUT_LINE(v_data);
UTL_HTTP.END_RESPONSE(v_resp);
END;
```

The following is the output from the example.

\x3c21444f43545950452068746d6c205055424c494320222d2f2f5733432f2f4454442058485 44d4c20312e30205374726963742f2f454e220d0a202022687474703a2f2f7777772e77332e6f 72672f54522f7868746d6c312f4454442f7868746d6c312d7374726963742e647464223e0d0a3 c68746d6c20786d6c6e733d22687474703a2f2f7777772e77332e6f72672f313939392f

READ TEXT

The READ_TEXT procedure returns the data from the HTTP response body in text form. The maximum number of characters returned is specified by the <le>> parameter. The signature is:

```
READ_TEXT(<r> IN OUT UTL_HTTP.RESP, <data> OUT VARCHAR2, <len> INTEGER)
```

Parameters

Set <len> to the maximum number of characters to be returned.

Examples

The following example retrieves the first 150 characters.

```
DECLARE
                     UTL_HTTP.REQ;
    v_req
                     UTL_HTTP.RESP;
    v_resp
    v_data
                     VARCHAR2(150);
BEGIN
    v_req := UTL_HTTP.BEGIN_REQUEST('http://www.enterprisedb.com');
    v_resp := UTL_HTTP.GET_RESPONSE(v_req);
    UTL_HTTP.READ_TEXT(v_resp, v_data, 150);
    DBMS_OUTPUT.PUT_LINE(v_data);
    UTL_HTTP.END_RESPONSE(v_resp);
END;
The following is the output.
<!DOCTYPE html PUBLIC "-//W3C//DTD XHTML 1.0 Strict//EN"</pre>
  "http://www.w3.org/TR/xhtml1/DTD/xhtml1-strict.dtd">
<html xmlns="http://www.w3.org/1999/</pre>
```

REQUEST

The REQUEST function returns the first 2000 bytes retrieved from a user-specified URL. The signature is:

```
REQUEST(<url> IN VARCHAR2) RETURN VARCHAR2
```

If the data found at the given URL is longer than 2000 bytes, the remainder will be discarded. If the data found at the given URL is shorter than 2000 bytes, the result will be shorter than 2000 bytes.

Parameters

<url>

<url> is the Uniform Resource Locator from which UTL_HTTP will return content.

Example

The following command returns the first 2000 bytes retrieved from the EnterpriseDB website:

SELECT UTL_HTTP.REQUEST('http://www.enterprisedb.com/') FROM DUAL;

REQUEST_PIECES

The REQUEST_PIECES function returns a table of 2000-byte segments retrieved from an URL. The signature is:

```
REQUEST_PIECES(<url> IN VARCHAR2, <max_pieces> NUMBER IN DEFAULT 32767) RETURN UTL_HTTP.HTML_PIECES
```

Parameters

<url>

<url> is the Uniform Resource Locator from which UTL_HTTP will return content.

<max_pieces>

<max_pieces> specifies the maximum number of 2000-byte segments that the REQUEST_PIECES
function will return. If <max_pieces> specifies more units than are available at the specified
<url> , the final unit will contain fewer bytes.

Example

The following example returns the first four 2000 byte segments retrieved from the EnterpriseDB website:

DECLARE

```
result UTL_HTTP.HTML_PIECES;
BEGIN
result := UTL_HTTP.REQUEST_PIECES('http://www.enterprisedb.com/', 4);
END
```

SET BODY CHARSET

The SET_BODY_CHARSET procedure sets the default character set of the body of future HTTP requests. The signature is:

```
SET_BODY_CHARSET(<charset> VARCHAR2 DEFAULT NULL)
```

Parameters

<charset>

<charset> is the character set of the body of future requests. The default is null in which case the database character set is assumed.

SET_FOLLOW_REDIRECT

The SET_FOLLOW_REDIRECT procedure sets the maximum number of times the HTTP redirect instruction is to be followed in the response to this request or future requests. This procedures has two signatures:

```
SET_FOLLOW_REDIRECT(<max_redirects> IN INTEGER DEFAULT 3)
```

and

```
SET_FOLLOW_REDIRECT(<r> IN OUT UTL_HTTP.REQ, <max_redirects> IN INTEGER DEFAULT 3)
```

Use the second form to change the maximum number of redirections for an individual request that a request inherits from the session default settings.

Parameters

<r>

<r> is the HTTP request record.

<max_redirects>

<max_redirects> is maximum number of redirections allowed. Set to 0 to disable redirections.
The default is 3.

SET_HEADER

The SET_HEADER procedure sets the HTTP request header. The signature is:

SET_HEADER(<r> IN OUT UTL_HTTP.REQ, <name> IN VARCHAR2, <value>
IN VARCHAR2 DEFAULT NULL)

Parameters

<r>

<r> is the HTTP request record.

<name>

<name> is the name of the request header.

<value>

<value> is the value of the request header. The default is null.

SET_RESPONSE_ERROR_CHECK

The SET_RESPONSE_ERROR_CHECK procedure determines whether or not HTTP 4xx and 5xx status codes returned by the GET_RESPONSE function should be interpreted as errors. The signature is:

SET_RESPONSE_ERROR_CHECK(<enable> IN BOOLEAN DEFAULT FALSE)

Parameters

<enable>

Set <enable> to TRUE if HTTP 4xx and 5xx status codes are to be treated as errors, otherwise set to FALSE . The default is FALSE .

SET_TRANSFER_TIMEOUT

The SET_TRANSFER_TIMEOUT procedure sets the default, transfer timeout setting for waiting for a response from an HTTP request. This procedure has two signatures:

SET_TRANSFER_TIMEOUT(<timeout> IN INTEGER DEFAULT 60)

and

SET_TRANSFER_TIMEOUT(<r> IN OUT UTL_HTTP.REQ, <timeout> IN INTEGER DEFAULT 60)

Use the second form to change the transfer timeout setting for an individual request that a request inherits from the session default settings.

Parameters

<r>

<r> is the HTTP request record.

<timeout>

<timeout> is the transfer timeout setting in seconds for HTTP requests. The default is 60 seconds.

WRITE LINE

The WRITE_LINE procedure writes data to the HTTP request body in text form; the text is terminated with a CRLF character pair. The signature is:

```
WRITE_LINE(<r> IN OUT UTL_HTTP.REQ, <data> IN VARCHAR2)
```

Parameters

Example

The following example writes data (Account balance \$500.00) in text form to the request body to be sent using the HTTP POST method. The data is sent to a hypothetical web application (post.php) that accepts and processes data.

Assuming the web application successfully processed the POST method, the following output would be displayed:

```
Status Code: 200
Reason Phrase: OK
```

WRITE_RAW

The WRITE_RAW procedure writes data to the HTTP request body in binary form. The signature is:

```
WRITE_RAW(<r> IN OUT UTL_HTTP.REQ, <data> IN RAW)
```

Parameters

Example

The following example writes data in binary form to the request body to be sent using the HTTP POST method to a hypothetical web application that accepts and processes such data.

```
'POST');
UTL_HTTP.SET_HEADER(v_req, 'Content-Length', '23');
UTL_HTTP.WRITE_RAW(v_req, HEXTORAW)

('54657374696e6720504f5354206d6574686f6420696e20485454502072657175657374'));
v_resp := UTL_HTTP.GET_RESPONSE(v_req);
DBMS_OUTPUT.PUT_LINE('Status Code: ' || v_resp.status_code);
DBMS_OUTPUT.PUT_LINE('Reason Phrase: ' || v_resp.reason_phrase);
UTL_HTTP.END_RESPONSE(v_resp);
END;
```

The text string shown in the HEXTORAW function is the hexadecimal translation of the text Testing POST method in HTT

Assuming the web application successfully processed the POST method, the following output would be displayed:

Status Code: 200 Reason Phrase: OK

WRITE TEXT

The WRITE_TEXT procedure writes data to the HTTP request body in text form. The signature is:

```
WRITE_TEXT(<r> IN OUT UTL_HTTP.REQ, <data> IN VARCHAR2)
```

Parameters

```
<r> <r> <r> is the HTTP request record.
<data> 
<data> is the request body in text form.
```

Example

The following example writes data (Account balance \$500.00) in text form to the request body to be sent using the HTTP POST method. The data is sent to a hypothetical web application (post.php) that accepts and processes data.

Assuming the web application successfully processed the POST method, the following output would be displayed:

Status Code: 200 Reason Phrase: OK

308

5.3.22 UTL MAIL

The UTL_MAIL package provides the capability to manage e-mail. Advanced Server supports the following procedures:

```
Function/Procedure
```

```
SEND(<sender>, <recipients>, <cc>, <bcc>, <subject>, <message>[, <mime_type>[, <priority>]])
```

Note

An administrator must grant execute privileges to each user or group before they can use this package.

SEND

The SEND procedure provides the capability to send an e-mail to an SMTP server.

```
SEND(<sender> VARCHAR2, <recipients> VARCHAR2, <cc> VARCHAR2, <bc> VARCHAR2, <subject> VARCHAR2
```

Parameters

```
<sender>
```

E-mail address of the sender.

```
<recipients>
```

Comma-separated e-mail addresses of the recipients.

<CC>

Comma-separated e-mail addresses of copy recipients.

<bcc>

Comma-separated e-mail addresses of blind copy recipients.

```
<subject>
```

Subject line of the e-mail.

<message>

Body of the e-mail.

```
<mime_type>
```

Mime type of the message. The default is text/plain; charset=us-ascii.

```
<priority>
```

Priority of the e-mail The default is 3.

Examples

The following anonymous block sends a simple e-mail message.

```
DECLARE
```

```
'6:00 PM. Please RSVP by Dec. 15th.';
UTL_MAIL.SEND(v_sender,v_recipients,NULL,NULL,v_subj,v_msg);
END;
```

SEND_ATTACH_RAW

The SEND_ATTACH_RAW procedure provides the capability to send an e-mail to an SMTP server with an attachment containing either BYTEA data or a large object (identified by the large object's OID). The call to SEND_ATTACH_RAW can be written in two ways:

SEND_ATTACH_RAW(<sender> VARCHAR2, <recipients> VARCHAR2, <cc> VARCHAR2, <bcc> VARCHAR2, <sub

or

SEND_ATTACH_RAW(<sender> VARCHAR2, <recipients> VARCHAR2, <cc> VARCHAR2, <bcc> VARCHAR2, <sub

Parameters

```
<sender>
```

E-mail address of the sender.

<recipients>

Comma-separated e-mail addresses of the recipients.

<CC>

Comma-separated e-mail addresses of copy recipients.

<bcc>

Comma-separated e-mail addresses of blind copy recipients.

<subject>

Subject line of the e-mail.

<message>

Body of the e-mail.

<mime_type>

Mime type of the message. The default is text/plain; charset=us-ascii .

<priority>

Priority of the e-mail. The default is 3.

<attachment>

The attachment.

<att_inline>

If set to TRUE, then the attachment is viewable inline, FALSE otherwise. The default is TRUE.

<att_mime_type>

Mime type of the attachment. The default is application/octet.

<att_filename>

The file name containing the attachment. The default is null.

SEND ATTACH VARCHAR2

The SEND_ATTACH_VARCHAR2 procedure provides the capability to send an e-mail to an SMTP server with a text attachment.

SEND_ATTACH_VARCHAR2(<sender> VARCHAR2, <recipients> VARCHAR2, <cc> VARCHAR2, <bc> VARCHAR2,

Parameters

<sender>

E-mail address of the sender.

<recipients>

Comma-separated e-mail addresses of the recipients.

<CC>

Comma-separated e-mail addresses of copy recipients.

<bcc>

Comma-separated e-mail addresses of blind copy recipients.

<subject>

Subject line of the e-mail.

<message>

Body of the e-mail.

<mime_type>

Mime type of the message. The default is text/plain; charset=us-ascii .

<priority>

Priority of the e-mail The default is 3.

<attachment>

The VARCHAR2 attachment.

<att_inline>

If set to TRUE, then the attachment is viewable inline, FALSE otherwise. The default is TRUE.

<att_mime_type>

Mime type of the attachment. The default is text/plain; charset=us-ascii .

<att_filename>

The file name containing the attachment. The default is null.

5.3.23 UTL_RAW

The UTL_RAW package allows you to manipulate or retrieve the length of raw data types.

Note

An administrator must grant execute privileges to each user or group before they can use this package.

Function/Procedure
CAST_TO_RAW(c IN VARCHAR2)
CAST_TO_VARCHAR2(r IN RAW)

Function or Procedure Function

Function

Return Type RAW VARCHAR2

CONCAT(r1 IN RAW, r2 IN RAW, r3 IN RAW,)	Function	RAW	-
CONVERT(r IN RAW, to_charset IN VARCHAR2, from_charset IN VARCHAR2	Function	RAW	(
LENGTH(r IN RAW)	Function	NUMBER	-
SUBSTR(r IN RAW, pos IN INTEGER, len IN INTEGER)	Function	RAW	-

Advanced Server's implementation of UTL_RAW is a partial implementation when compared to Oracle's version. Only those functions and procedures listed in the table above are supported.

CAST_TO_RAW

The CAST_TO_RAW function converts a VARCHAR2 string to a RAW value. The signature is:

```
CAST_TO_RAW(<c> VARCHAR2)
```

The function returns a RAW value if you pass a non- NULL value; if you pass a NULL value, the function will return NULL .

Parameters

<C>

The VARCHAR2 value that will be converted to RAW.

Example

The following example uses the CAST_TO_RAW function to convert a VARCHAR2 string to a RAW value:

```
DECLARE
  v VARCHAR2;
  r RAW;
BEGIN
  v := 'Accounts';
  dbms_output.put_line(v);
  r := UTL_RAW.CAST_TO_RAW(v);
  dbms_output.put_line(r);
END:
```

The result set includes the content of the original string and the converted RAW value:

Accounts

\x4163636f756e7473

CAST TO VARCHAR2

The CAST_TO_VARCHAR2 function converts RAW data to VARCHAR2 data. The signature is:

```
CAST_TO_VARCHAR2(<r> RAW)
```

The function returns a VARCHAR2 value if you pass a non- NULL value; if you pass a NULL value, the function will return NULL .

Parameters

<r>

The RAW value that will be converted to a VARCHAR2 value.

Example

The following example uses the CAST_TO_VARCHAR2 function to convert a RAW value to a VARCHAR2 string:

```
DECLARE
r RAW;
v VARCHAR2;
BEGIN
```

```
r := '\x4163636f756e7473'
dbms_output.put_line(v);
v := UTL_RAW.CAST_TO_VARCHAR2(r);
dbms_output.put_line(r);
END;
```

The result set includes the content of the original string and the converted RAW value:

```
\x4163636f756e7473
Accounts
```

CONCAT

The CONCAT function concatenates multiple RAW values into a single RAW value. The signature is:

```
CONCAT(<r1> RAW, <r2> RAW, <r3> RAW,...)
```

The function returns a RAW value. Unlike the Oracle implementation, the Advanced Server implementation is a variadic function, and does not place a restriction on the number of values that can be concatenated.

Parameters

```
<r1, r2, r3,...>
```

The RAW values that CONCAT will concatenate.

Example

The following example uses the CONCAT function to concatenate multiple RAW values into a single RAW value:

```
| SELECT UTL_RAW.CAST_TO_VARCHAR2(UTL_RAW.CONCAT('\x61', '\x62', | '\x63')) FROM DUAL; | concat | ------ | abc | (1 row)
```

The result (the concatenated values) is then converted to VARCHAR2 format by the CAST_TO_VARCHAR2 function.

CONVERT

The CONVERT function converts a string from one encoding to another encoding and returns the result as a RAW value. The signature is:

```
CONVERT(<r> RAW, <to_charset> VARCHAR2, <from_charset> VARCHAR2)
```

The function returns a RAW value.

Parameters

<r>

The RAW value that will be converted.

<to_charset>

The name of the encoding to which <r> will be converted.

```
<from_charset>
```

The name of the encoding from which <r> will be converted.

Example

```
The following example uses the UTL_RAW.CAST_TO_RAW function to convert a VARCHAR2
Accounts ) to a raw value, and then convert the value from UTF8 to LATIN7 , and then from LATIN7
to UTF8:
DECLARE
  r RAW;
  v VARCHAR2;
BEGIN
  v:= 'Accounts';
  dbms_output.put_line(v);
  r:= UTL_RAW.CAST_TO_RAW(v);
  dbms_output.put_line(r);
r:= UTL_RAW.CONVERT(r, 'UTF8', 'LATIN7');
  dbms_output.put_line(r);
r:= UTL_RAW.CONVERT(r, 'LATIN7', 'UTF8');
  dbms_output.put_line(r);
The example returns the VARCHAR2 value, the RAW value, and the converted values:
Accounts
\x4163636f756e7473
\x4163636f756e7473
\x4163636f756e7473
LENGTH
The LENGTH function returns the length of a RAW value. The signature is:
     LENGTH(<r> RAW)
The function returns a RAW value.
Parameters
<r>
The RAW value that LENGTH will evaluate.
Example
The following example uses the LENGTH function to return the length of a RAW value:
SELECT UTL_RAW.LENGTH(UTL_RAW.CAST_TO_RAW('Accounts')) FROM DUAL;
length
-----
(1 row)
The following example uses the LENGTH function to return the length of a RAW value that includes multi-byte
characters:
SELECT UTL_RAW.LENGTH(UTL_RAW.CAST_TO_RAW('hello'));
length
     5
(1 row)
UTL_RAW_SUBSTR
SUBSTR
```

The SUBSTR function returns a substring of a RAW value. The signature is:

SUBSTR (<r> RAW, <pos> INTEGER, <len> INTEGER)

This function returns a RAW value.

Parameters

<r>

The RAW value from which the substring will be returned.

<pos>

The position within the RAW value of the first byte of the returned substring.

- If <pos> is 0 or 1, the substring begins at the first byte of the RAW value.
- If <pos> is greater than one, the substring begins at the first byte specified by <pos> . For example,
 if <pos> is 3 , the substring begins at the third byte of the value.
- If <pos> is negative, the substring begins at <pos> bytes from the end of the source value. For example, if <pos> is -3 , the substring begins at the third byte from the end of the value.

<len>

The maximum number of bytes that will be returned.

Example

The following example uses the SUBSTR function to select a substring that begins 3 bytes from the start of a RAW value:

```
SELECT UTL_RAW.SUBSTR(UTL_RAW.CAST_TO_RAW('Accounts'), 3, 5) FROM DUAL;
substr
-----
count
(1 row)
```

The following example uses the SUBSTR function to select a substring that starts 5 bytes from the end of a RAW value:

```
SELECT UTL_RAW.SUBSTR(UTL_RAW.CAST_TO_RAW('Accounts'), -5 , 3) FROM DUAL; substr ------oun (1 row)
```

5.3.24 UTL_SMTP

The UTL_SMTP package provides the capability to send e-mails over the Simple Mail Transfer Protocol (SMTP).

Note

An administrator must grant execute privileges to each user or group before they can use this package.

Function/Procedure	Function or Procedure	Return Type	Description
CLOSE_DATA(c IN OUT)	Procedure	n/a	Ends an e-mail message.
COMMAND(c IN OUT, cmd [, arg])	Both	REPLY	Execute an SMTP commar
COMMAND_REPLIES(c IN OUT, cmd [, arg])	Function	REPLIES	Execute an SMTP comma
DATA(c IN OUT, body VARCHAR2)	Procedure	n/a	Specify the body of an e-m
EHLO(c IN OUT, domain)	Procedure	n/a	Perform initial handshaking
HELO(c IN OUT, domain)	Procedure	n/a	Perform initial handshaking
HELP(c IN OUT [, command])	Function	REPLIES	Send the HELP command.
MAIL(c IN OUT, sender [, parameters])	Procedure	n/a	Start a mail transaction.
NOOP(c IN OUT)	Both	REPLY	Send the null command.
OPEN CONNECTION(host [, port [, tx timeout]])	Function	CONNECTION	Open a connection.

OPEN_DATA(c IN OUT)	Both	REPLY	Send the DATA command.
QUIT(c IN OUT)	Procedure	n/a	Terminate the SMTP session
RCPT(c IN OUT, recipient [, parameters])	Procedure	n/a	Specify the recipient of an
RSET(c IN OUT)	Procedure	n/a	Terminate the current mail
VRFY(c IN OUT, recipient)	Function	REPLY	Validate an e-mail address
WRITE_DATA(c IN OUT, data)	Procedure	n/a	Write a portion of the e-ma

Advanced Server's implementation of UTL_SMTP is a partial implementation when compared to Oracle's version. Only those functions and procedures listed in the table above are supported.

The following table lists the public variables available in the UTL_SMTP package.

Public Variables	Data Type	Value	Description
connection	RECORD		Description of an SMTP connection.
reply	RECORD		SMTP reply line.

CONNECTION

The CONNECTION record type provides a description of an SMTP connection.

REPLY/REPLIES

The REPLY record type provides a description of an SMTP reply line. REPLIES is a table of multiple SMTP reply lines.

CLOSE_DATA

The CLOSE_DATA procedure terminates an e-mail message by sending the following sequence:

```
<CR><LF>.<CR><LF>
```

This is a single period at the beginning of a line.

```
CLOSE_DATA(<c> IN OUT CONNECTION)
```

Parameters

<C>

The SMTP connection to be closed.

COMMAND

The COMMAND procedure provides the capability to execute an SMTP command. If you are expecting multiple reply lines, use COMMAND_REPLIES.

```
<reply> REPLY COMMAND(<c> IN OUT CONNECTION, <cmd> VARCHAR2
[, <arg> VARCHAR2 ])
COMMAND(<c> IN OUT CONNECTION, <cmd> VARCHAR2 [, <arg> VARCHAR2 ])
```

Parameters

<C>

The SMTP connection to which the command is to be sent.

<cmd>

The SMTP command to be processed.

<arg>

An argument to the SMTP command. The default is null.

<reply>

SMTP reply to the command. If SMTP returns multiple replies, only the last one is returned in <reply> .

See Reply/Replies <reply/replies> for a description of REPLY and REPLIES .

COMMAND_REPLIES

The COMMAND_REPLIES function processes an SMTP command that returns multiple reply lines. Use COMMAND if only a single reply line is expected.

```
<replies> REPLIES COMMAND(<c> IN OUT CONNECTION, <cmd> VARCHAR2
[, <arg> VARCHAR2 ])
```

Parameters

<C>

The SMTP connection to which the command is to be sent.

<cmd>

The SMTP command to be processed.

<arg>

An argument to the SMTP command. The default is null.

<replies>

SMTP reply lines to the command. See Reply/Replies <reply/replies> for a description of REPLY and REPLIES .

DATA

The DATA procedure provides the capability to specify the body of the e-mail message. The message is terminated with a <CR><LF>.<CR><LF> sequence.

```
DATA(<c> IN OUT CONNECTION, <body> VARCHAR2)
```

Parameters

<C>

The SMTP connection to which the command is to be sent.

<body>

Body of the e-mail message to be sent.

EHLO

The EHLO procedure performs initial handshaking with the SMTP server after establishing the connection. The EHLO procedure allows the client to identify itself to the SMTP server according to RFC 821. RFC 1869 specifies the format of the information returned in the server's reply. The *HELO* procedure performs the equivalent functionality, but returns less information about the server.

EHLO(<c> IN OUT CONNECTION, <domain> VARCHAR2)

Parameters

<C>

The connection to the SMTP server over which to perform handshaking.

<domain>

Domain name of the sending host.

HELO

The HELO procedure performs initial handshaking with the SMTP server after establishing the connection. The HELO procedure allows the client to identify itself to the SMTP server according to RFC 821. The *EHLO* procedure performs the equivalent functionality, but returns more information about the server.

```
HELO(<c> IN OUT, <domain*> VARCHAR2)
```

Parameters

<C>

The connection to the SMTP server over which to perform handshaking.

<domain>

Domain name of the sending host.

HELP

The HELP function provides the capability to send the HELP command to the SMTP server.

```
<replies> REPLIES HELP(<c> IN OUT CONNECTION [, <command> VARCHAR2 ])
```

Parameters

<C>

The SMTP connection to which the command is to be sent.

<command>

Command on which help is requested.

<replies>

SMTP reply lines to the command. See Reply/Replies <reply/replies> for a description of REPLY and REPLIES .

MAIL

The MAIL procedure initiates a mail transaction.

```
MAIL(<c> IN OUT CONNECTION, <sender> VARCHAR2
[, <parameters> VARCHAR2 ])
```

Parameters

<C>

Connection to SMTP server on which to start a mail transaction.

<sender>

The sender's e-mail address.

<parameters>

Mail command parameters in the format, key=value as defined in RFC 1869.

NOOP

The NOOP function/procedure sends the null command to the SMTP server. The NOOP has no effect upon the server except to obtain a successful response.

```
<reply> REPLY NOOP(<c> IN OUT CONNECTION)
NOOP(<c> IN OUT CONNECTION)
```

Parameters

<C>

The SMTP connection on which to send the command.

<reply>

SMTP reply to the command. If SMTP returns multiple replies, only the last one is returned in <reply> . See Reply/Replies <reply/replies> for a description of REPLY and REPLIES .

OPEN CONNECTION

The OPEN_CONNECTION functions open a connection to an SMTP server.

```
<c> CONNECTION OPEN_CONNECTION(<host> VARCHAR2 [, <port>
PLS_INTEGER [, <tx_timeout> PLS_INTEGER DEFAULT NULL]])
```

Parameters

<host>

Name of the SMTP server.

<port>

Port number on which the SMTP server is listening. The default is 25.

<tx_timeout>

Time out value in seconds. Do not wait is indicated by specifying 0. Wait indefinitely is indicated by setting timeout to null. The default is null.

<C>

Connection handle returned by the SMTP server.

OPEN_DATA

The OPEN_DATA procedure sends the DATA command to the SMTP server.

```
OPEN_DATA(<c> IN OUT CONNECTION)
```

Parameters

<C>

SMTP connection on which to send the command.

QUIT

The QUIT procedure closes the session with an SMTP server.

```
QUIT(<c> IN OUT CONNECTION)
```

Parameters

<C>

SMTP connection to be terminated.

RCPT

The RCPT procedure provides the e-mail address of the recipient. To schedule multiple recipients, invoke RCPT multiple times.

```
RCPT(<c> IN OUT CONNECTION, <recipient> VARCHAR2
[, <parameters> VARCHAR2 ])
```

Parameters

<C>

Connection to SMTP server on which to add a recipient.

<recipient>

The recipient's e-mail address.

<parameters>

Mail command parameters in the format, key=value as defined in RFC 1869.

RSET

The RSET procedure provides the capability to terminate the current mail transaction.

```
RSET(<c> IN OUT CONNECTION)
```

Parameters

<C>

SMTP connection on which to cancel the mail transaction.

VRFY

The VRFY function provides the capability to validate and verify the recipient's e-mail address. If valid, the recipient's full name and fully qualified mailbox is returned.

```
<reply> REPLY VRFY(<c> IN OUT CONNECTION, <recipient> VARCHAR2)
```

Parameters

<C>

The SMTP connection on which to verify the e-mail address.

<recipient>

The recipient's e-mail address to be verified.

<reply>

SMTP reply to the command. If SMTP returns multiple replies, only the last one is returned in *reply*. See Reply/Replies <reply/replies> for a description of REPLY and REPLIES.

WRITE DATA

The WRITE_DATA procedure provides the capability to add VARCHAR2 data to an e-mail message. The WRITE_DATA procedure may be repetitively called to add data.

```
WRITE_DATA(<c> IN OUT CONNECTION, <data> VARCHAR2)
```

Parameters

<C>

The SMTP connection on which to add data.

<data>

Data to be added to the e-mail message. The data must conform to the RFC 822 specification.

UTL SMTP Comprehensive example

Comprehensive Example

The following procedure constructs and sends a text e-mail message using the UTL_SMTP package.

```
CREATE OR REPLACE PROCEDURE send_mail (
    p_sender
                    VARCHAR2,
                    VARCHAR2,
    p_recipient
                    VARCHAR2,
    p_subj
    p_msg
                    VARCHAR2,
    p_mailhost
                    VARCHAR2
TS
                    UTL_SMTP.CONNECTION;
    v_conn
                    CONSTANT VARCHAR2(2) := CHR(13) \mid I \mid CHR(10);
    v_crlf
    v_port
                    CONSTANT PLS_INTEGER := 25;
BEGIN
    v_conn := UTL_SMTP.OPEN_CONNECTION(p_mailhost,v_port);
    UTL_SMTP.HELO(v_conn,p_mailhost);
    UTL_SMTP.MAIL(v_conn,p_sender);
    UTL_SMTP.RCPT(v_conn,p_recipient);
    UTL_SMTP.DATA(v_conn, SUBSTR(
        'Date: ' || TO_CHAR(SYSDATE,
        'Dy, DD Mon YYYY HH24:MI:SS') || v_crlf
        | 'From: ' | p_sender | v_crlf
        || 'To: ' || p_recipient || v_crlf
        II 'Subject: ' || p_subj || v_crlf
        II p_msg
         1, 32767));
    UTL_SMTP.QUIT(v_conn);
END;
```

EXEC send_mail('asmith@enterprisedb.com','pjones@enterprisedb.com','Holiday Party','Are you planterprisedb.com'

The following example uses the OPEN_DATA, WRITE_DATA, and CLOSE_DATA procedures instead of the DATA procedure.

```
CREATE OR REPLACE PROCEDURE send_mail_2 (
                    VARCHAR2,
    p_sender
    p_recipient
                    VARCHAR2,
                    VARCHAR2,
    p_subj
                    VARCHAR2,
    p_msg
    p_mailhost
                    VARCHAR2
IS
                    UTL_SMTP.CONNECTION;
    v_conn
    v_crlf
                    CONSTANT VARCHAR2(2) := CHR(13) | | CHR(10);
```

EXEC send_mail_2('asmith@enterprisedb.com','pjones@enterprisedb.com','Holiday Party','Are you p

5.3.25 UTL_URL

The UTL_URL package provides a way to escape illegal and reserved characters within an URL.

Function/Procedure	Return Type	Description
ESCAPE(url, escape_reserved_chars, url_charset)	VARCHAR2	Use the ESCAPE function to escape any illegal and re
UNESCAPE(url, url_charset)	VARCHAR2	The UNESCAPE function to convert an URL to it's ori

The UTL_URL package will return the BAD_URL exception if the call to a function includes an incorrectly-formed URL.

ESCAPE

Use the ESCAPE function to escape illegal and reserved characters within an URL. The signature is:

Reserved characters are replaced with a percent sign, followed by the two-digit hex code of the ascii value for the escaped character.

Parameters

<url>

<url> specifies the Uniform Resource Locator that UTL_URL will escape.

<escape_reserved_chars>

<escape_reserved_chars> is a BOOLEAN value that instructs the ESCAPE function to
escape reserved characters as well as illegal characters:

- If <escaped_reserved_chars> is FALSE , ESCAPE will escape only the illegal characters in the specified URL.
- If <escape_reserved_chars> is TRUE, ESCAPE will escape both the illegal characters and the reserved characters in the specified URL.

By default, $\langle escape_reserved_chars \rangle$ is FALSE .

Within an URL, legal characters are:

Uppercase A through Z	Lowercase a through z	0 through 9
asterisk (*)	exclamation point (!)	hyphen (-)
left parenthesis (()	period (.)	right parenthesis ())
single-quote (')	tilde (~)	underscore (_)

Some characters are legal in some parts of an URL, while illegal in others; to review comprehensive rules about illegal characters, please refer to RFC 2396. Some *examples* of characters that are considered illegal in any part of an URL are:

Illegal Character	Escape Sequence
a blank space () curly braces ({ or }) hash mark (#)	%20 %7b and %7d %23

The ESCAPE function considers the following characters to be reserved, and will escape them if <escape_reserved_chars> is set to TRUE:

Reserved Character	Escape Sequence
ampersand (&)	%5C
at sign (@)	%25
colon (:)	%3a
comma (,)	%2c
dollar sign (\$)	%24
equal sign (=)	%3d
plus sign (+)	%2b
question mark (?)	%3f
semi-colon (;)	%3b
slash (/)	%2f

<url_charset>

<url_charset> specifies a character set to which a given character will be converted before it
is escaped. If <url_charset> is NULL , the character will not be converted. The default value
of <url_charset> is ISO-8859-1 .

Examples

The following anonymous block uses the ESCAPE function to escape the blank spaces in the URL:

The ESCAPE function escapes the reserved characters as well as the illegal characters in the URL:

http%3A%2F%2Fwww.example.com%2FUsing%20the%20ESCAPE%20function.html

UNESCAPE

The UNESCAPE function removes escape characters added to an URL by the ESCAPE function, converting the URL to it's original form.

The signature is:

```
UNESCAPE(<url> VARCHAR2, <url_charset> VARCHAR2)
```

Parameters

<url>

<url> specifies the Uniform Resource Locator that UTL_URL will unescape.

<url charset>

After unescaping a character, the character is assumed to be in <url_charset> encoding, and will be converted from that encoding to database encoding before being returned. If <url_charset> is NULL , the character will not be converted. The default value of <url_charset> is ISO-8859-1 .

Examples

The following anonymous block uses the ESCAPE function to escape the blank spaces in the URL:

DECLARE

result varchar2(400);

BEGIN result := UTL_URL.UNESCAPE('http://www.example.com/Using%20the%20UNESCAPE%20function.html
DBMS_OUTPUT.PUT_LINE(result);
END;

The resulting (unescaped) URL is:

http://www.example.com/Using the UNESCAPE function.htm

5.4 Acknowledgements

The PostgreSQL 8.3, 8.4, 9.0, 9.1, 9.2, 9.3, 9.4, 9.5, 9.6, 10, 11, and 12 Documentation provided the baseline for the portions of this guide that are common to PostgreSQL, and is hereby acknowledged:

Portions of this EnterpriseDB Software and Documentation may utilize the following copyrighted material, the use of which is hereby acknowledged.

PostgreSQL Documentation, Database Management System

PostgreSQL is Copyright © 1996-2020 by the PostgreSQL Global Development Group and is distributed under the terms of the license of the University of California below.

Postgres95 is Copyright © 1994-5 by the Regents of the University of California.

Permission to use, copy, modify, and distribute this software and its documentation for any purpose, without fee, and without a written agreement is hereby granted, provided that the above copyright notice and this paragraph and the following two paragraphs appear in all copies.

IN NO EVENT SHALL THE UNIVERSITY OF CALIFORNIA BE LIABLE TO ANY PARTY FOR DIRECT, INDIRECT, SPECIAL, INCIDENTAL, OR CONSEQUENTIAL DAMAGES, INCLUDING LOST PROFITS, ARISING OUT OF THE USE OF THIS SOFTWARE AND ITS DOCUMENTATION, EVEN IF THE UNIVERSITY OF CALIFORNIA HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

THE UNIVERSITY OF CALIFORNIA SPECIFICALLY DISCLAIMS ANY WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTIC-ULAR PURPOSE. THE SOFTWARE PROVIDED HEREUNDER IS ON AN "AS-IS" BASIS, AND THE UNIVERSITY OF CALIFORNIA HAS NO OBLIGATIONS TO PROVIDE MAINTENANCE, SUPPORT, UPDATES, ENHANCEMENTS, OR MODIFICATIONS.

5.5 Conclusion

Database Compatibility for Oracle Developers Built-in Packages Guide

Copyright © 2007 - 2020 EnterpriseDB Corporation. All rights reserved.

EnterpriseDB Corporation 34 Crosby Drive, Suite 201, Bedford, MA 01730, USA

T +1 781 357 3390 F +1 978 467 1307 E info@enterprisedb.com www.enterprisedb.com

- EnterpriseDB and Postgres Enterprise Manager are registered trademarks of EnterpriseDB Corporation. EDB and EDB Postgres are trademarks of EnterpriseDB Corporation. Oracle is a registered trademark of Oracle, Inc. Other trademarks may be trademarks of their respective owners.
- EDB designs, establishes coding best practices, reviews, and verifies input validation for the logon UI for EDB Postgres products where present. EDB follows the same approach for additional input components, however the nature of the product may require that it accepts freeform SQL, WMI or other strings to be entered and submitted by trusted users for which limited validation is possible. In such cases it is not possible to prevent users from entering incorrect or otherwise dangerous inputs.
- EDB reserves the right to add features to products that accept freeform SQL, WMI or other potentially dangerous inputs from authenticated, trusted users in the future, but will ensure all such features are designed and tested to ensure they provide the minimum possible risk, and where possible, require superuser or equivalent privileges.
- EDB does not warrant that we can or will anticipate all potential threats and therefore our process cannot fully guarantee that all potential vulnerabilities have been addressed or considered.

6.0 Database Compatibility for Oracle Developers

6.1.0 Introduction

Database Compatibility for Oracle means that an application runs in an Oracle environment as well as in the EDB Postgres Advanced Server (Advanced Server) environment with minimal or no changes to the application code. Developing an application that is compatible with Oracle databases in the Advanced Server requires special attention to which features are used in the construction of the application. For example, developing a compatible application means choosing compatible:

- System and built-in functions for use in SQL statements and procedural logic.
- Stored Procedure Language (SPL) when creating database server-side application logic for stored procedures, functions, triggers, and packages.
- Data types that are compatible with Oracle databases
- · SQL statements that are compatible with Oracle SQL
- · System catalog views that are compatible with Oracle's data dictionary

For detailed information about the compatible SQL syntax, data types, and views, see the *Database Compatibility for Oracle Developers Reference Guide*.

The compatibility offered by the procedures and functions that are part of the Built-in packages is documented in the *Database Compatibility for Oracle Developers Built-in Packages Guide*.

For information about using the compatible tools and utilities (EDB*Plus, EDB*Loader, DRITA, and EDB*Wrap) that are included with an Advanced Server installation, see the *Database Compatibility for Oracle Developers Tools and Utilities Guide.*

For applications written using the Oracle Call Interface (OCI), EnterpriseDB's Open Client Library (OCL) provides interoperability with these applications. For detailed information about using the Open Client Library, see the EDB Postgres Advanced Server OCL Connector Guide.

Advanced Server contains a rich set of features that enables development of database applications for either PostgreSQL or Oracle. For more information about all of the features of Advanced Server, see the user documentation available at the EnterpriseDB website.

Advanced Server documentation is available at:

https://www.enterprisedb.com/edb-docs	

6.1.1 What's New

The following database compatibility for Oracle features have been added to Advanced Server 11 to create Advanced Server 12:

- Advanced Server introduces COMPOUND TRIGGERS, which are stored as a PL block that executes in response to a specified triggering event. For information, see the *Database Compatibility for Oracle Developer's Guide*.
- Advanced Server now supports new DATA DICTIONARY VIEWS that provide information compatible
 with the Oracle data dictionary views. For information, see the Database Compatibility for Oracle Developer's Reference Guide.
- Advanced Server has added the LISTAGG function to support string aggregation that concatenates data from multiple rows into a single row in an ordered manner. For information, see the *Database Compatibility for Oracle Developer's Reference Guide*.
- Advanced Server now supports CAST(MULTISET) function, allowing subquery output to be CAST to a nested table type. For information, see the *Database Compatibility for Oracle Developer's Reference Guide*.
- Advanced Server has added the MEDIAN function to calculate a median value from the set of provided values. For information, see the *Database Compatibility for Oracle Developer's Reference Guide*.
- Advanced Server has added the SYS_GUID function to generate and return a globally unique identifier
 in the form of 16-bytes of RAW data. For information, see the *Database Compatibility for Oracle Developer's Reference Guide*.
- Advanced Server now supports an Oracle-compatible SELECT UNIQUE clause in addition to an existing SELECT DISTINCT clause. For information, see the *Database Compatibility for Oracle Developer's Reference Guide*.
- Advanced Server has re-implemented default_with_rowids, which is used to create a table that
 includes a ROWID column in the newly created table. For information, see the EDB Postgres Advanced
 Server Guide.
- Advanced Server now supports logical decoding on the standby server, which allows creating a logical replication slot on a standby, independently of a primary server. For information, see the EDB Postgres Advanced Server Guide.
- Advanced Server introduces INTERVAL PARTITIONING, which allows a database to automatically create partitions of a specified interval as new data is inserted into a table. For information, see the EDB Postgres Table Partitioning Guide.

6.1.2.0 Configuration Parameters Compatible with Oracle Databases

EDB Postgres Advanced Server supports the development and execution of applications compatible with PostgreSQL and Oracle. Some system behaviors can be altered to act in a more PostgreSQL or in a more Oracle compliant manner; these behaviors are controlled by configuration parameters. Modifying the parameters in the postgresql.conf file changes the behavior for all databases in the cluster, while a user or group can SET the parameter value on the command line, effecting only their session. These parameters are:

edb_redwood_date - Controls whether or not a time component is stored in DATE columns.
 For behavior compatible with Oracle databases, set edb_redwood_date to TRUE . See

edb_redwood_date <edb_redwood_date> .

- edb_redwood_raw_names Controls whether database object names appear in uppercase or lower-case letters when viewed from Oracle system catalogs. For behavior compatible with Oracle databases, edb_redwood_raw_names is set to its default value of FALSE. To view database object names as they are actually stored in the PostgreSQL system catalogs, set edb_redwood_raw_names to TRUE.
 See edb_redwood_raw_names <edb_redwood_raw_names>.
- edb_redwood_strings Equates NULL to an empty string for purposes of string concatenation operations. For behavior compatible with Oracle databases, set edb_redwood_strings to TRUE.
 See edb_redwood_strings <edb_redwood_strings .
- edb_stmt_level_tx Isolates automatic rollback of an aborted SQL command to statement level rollback only the entire, current transaction is not automatically rolled back as is the case for default PostgreSQL behavior. For behavior compatible with Oracle databases, set edb_stmt_level_tx to TRUE; however, use only when absolutely necessary. See edb_stmt_level_tx <edb_stmt_level_tx>
- oracle_home Point Advanced Server to the correct Oracle installation directory. See oracle_home <oracle_hom

6.1.2.1 edb_redwood_date

When DATE appears as the data type of a column in the commands, it is translated to TIMESTAMP at the time the table definition is stored in the data base if the configuration parameter edb_redwood_date is set to TRUE. Thus, a time component will also be stored in the column along with the date. This is consistent with Oracle's DATE data type.

If edb_redwood_date is set to FALSE the column's data type in a CREATE TABLE or ALTER TABLE command remains as a native PostgreSQL DATE data type and is stored as such in the database. The PostgreSQL DATE data type stores only the date without a time component in the column.

Regardless of the setting of edb_redwood_date , when DATE appears as a data type in any other context such as the data type of a variable in an SPL declaration section, or the data type of a formal parameter in an SPL procedure or SPL function, or the return type of an SPL function, it is always internally translated to a TIMESTAMP and thus, can handle a time component if present.

See the *Database Compatibility for Oracle Developers Reference Guide* for more information about date/time data types.

6.1.2.2 edb redwood raw names

When edb_redwood_raw_names is set to its default value of FALSE, database object names such as table names, column names, trigger names, program names, user names, etc. appear in uppercase letters when viewed from Oracle catalogs (for a complete list of supported catalog views, see the *Database Compatibility for Oracle Developers Reference Guide*). In addition, quotation marks enclose names that were created with enclosing quotation marks.

When edb_redwood_raw_names is set to TRUE, the database object names are displayed exactly as they are stored in the PostgreSQL system catalogs when viewed from the Oracle catalogs. Thus, names created without enclosing quotation marks appear in lowercase as expected in PostgreSQL. Names created with enclosing quotation marks appear exactly as they were created, but without the quotation marks.

For example, the following user name is created, and then a session is started with that user.

CREATE USER reduser IDENTIFIED BY password; edb=# \c - reduser

Password for user reduser:

You are now connected to database "edb" as user "reduser".

When connected to the database as reduser, the following tables are created.

```
CREATE TABLE all_lower (col INTEGER);
CREATE TABLE ALL_UPPER (COL INTEGER);
CREATE TABLE "Mixed_Case" ("Col" INTEGER);
```

When viewed from the Oracle catalog, USER_TABLES, with edb_redwood_raw_names set to the default value FALSE, the names appear in uppercase except for the Mixed_Case name, which appears as created and also with enclosing quotation marks.

When viewed with edb_redwood_raw_names set to TRUE, the names appear in lowercase except for the Mixed_Case name, which appears as created, but now without the enclosing quotation marks.

These names now match the case when viewed from the PostgreSQL pg_tables catalog.

6.1.2.3 edb_redwood_strings

In Oracle, when a string is concatenated with a null variable or null column, the result is the original string; however, in PostgreSQL concatenation of a string with a null variable or null column gives a null result. If the edb_redwood_strings parameter is set to TRUE, the aforementioned concatenation operation results in the original string as done by Oracle. If edb_redwood_strings is set to FALSE, the native PostgreSQL behavior is maintained.

The following example illustrates the difference.

The sample application introduced in the next section contains a table of employees. This table has a column named comm that is null for most employees. The following query is run with edb_redwood_string set to FALSE. The concatenation of a null column with non-empty strings produces a final result of null, so only employees that have a commission appear in the query result. The output line for all other employees is null.

```
SET edb_redwood_strings TO off;
```

```
SELECT RPAD(ename,10) || ' ' || TO_CHAR(sal,'99,999.99') || ' ' || TO_CHAR(comm,'99,999.99') "EMPLOYEE COMPENSATION" FROM emp;
```

EMPLOYEE COMPENSATION

ALLEN	1,600.00	300.00
WARD	1,250.00	500.00
MARTIN	1,250.00	1,400.00

TURNER 1,500.00 .00

(14 rows)

The following is the same query executed when edb_redwood_strings is set to TRUE . Here, the value of a null column is treated as an empty string. The concatenation of an empty string with a non-empty string produces the non-empty string. This result is consistent with the results produced by Oracle for the same query.

SET edb_redwood_strings TO on;

SELECT RPAD(ename,10) || ' ' || TO_CHAR(sal,'99,999.99') || ' ' || TO_CHAR(comm,'99,999.99') "EMPLOYEE COMPENSATION" FROM emp;

EMPLOYEE COMPENSATION

SMITH	800.00	
ALLEN	1,600.00	300.00
WARD	1,250.00	500.00
JONES	2,975.00	
MARTIN	1,250.00	1,400.00
BLAKE	2,850.00	
CLARK	2,450.00	
SCOTT	3,000.00	
KING	5,000.00	
TURNER	1,500.00	.00
ADAMS	1,100.00	
JAMES	950.00	
FORD	3,000.00	
MILLER	1,300.00	
(14 rows)		

6.1.2.4 edb_stmt_level_tx

In Oracle, when a runtime error occurs in a SQL command, all the updates on the database caused by that single command are rolled back. This is called *statement level transaction isolation*. For example, if a single UPDATE command successfully updates five rows, but an attempt to update a sixth row results in an exception, the updates to all six rows made by this UPDATE command are rolled back. The effects of prior SQL commands that have not yet been committed or rolled back are pending until a COMMIT or ROLLBACK command is executed.

In PostgreSQL, if an exception occurs while executing a SQL command, all the updates on the database since the start of the transaction are rolled back. In addition, the transaction is left in an aborted state and either a COMMIT or ROLLBACK command must be issued before another transaction can be started.

If $edb_stmt_level_tx$ is set to TRUE, then an exception will not automatically roll back prior uncommitted database updates, emulating the Oracle behavior. If $edb_stmt_level_tx$ is set to FALSE, then an exception will roll back uncommitted database updates.

Note

Use edb_stmt_level_tx set to TRUE only when absolutely necessary, as this may cause a negative performance impact.

The following example run in PSQL shows that when edb_stmt_level_tx is FALSE, the abort of the second INSERT command also rolls back the first INSERT command. Note that in PSQL, the command \set AUTOCOMMIT off must be issued, otherwise every statement commits automatically defeating the purpose of this demonstration of the effect of edb_stmt_level_tx.

In the following example, with edb_stmt_level_tx set to TRUE, the first INSERT command has not been rolled back after the error on the second INSERT command. At this point, the first INSERT command can either be committed or rolled back.

.

A ROLLBACK command could have been issued instead of the COMMIT command in which case the insert of employee number 9001 would have been rolled back as well.

6.1.2.5 oracle home

Before creating a link to an Oracle server, you must direct Advanced Server to the correct Oracle home directory. Set the LD_LIBRARY_PATH environment variable on Linux (or PATH on Windows) to the lib directory of the Oracle client installation directory.

For Windows only, you can instead set the value of the oracle_home configuration parameter in the postgresql.conf file. The value specified in the oracle_home configuration parameter will override the Windows PATH environment variable.

The LD_LIBRARY_PATH environment variable on Linux (PATH environment variable or oracle_home configuration parameter on Windows) must be set properly each time you start Advanced Server.

When using a Linux service script to start Advanced Server, be sure LD_LIBRARY_PATH has been set within the service script so it is in effect when the script invokes the pg_ctl utility to start Advanced Server.

For Windows only: To set the oracle_home configuration parameter in the postgresql.conf file, edit the file, adding the following line:

```
oracle_home = 'lib_directory'
```

Substitute the name of the Windows directory that contains oci.dll for lib_directory.

After setting the oracle_home configuration parameter, you must restart the server for the changes to take effect. Restart the server from the Windows Services console.

6.1.3 About the Examples Used in this Guide

The examples shown in this guide are illustrated using the PSQL program. The prompt that normally appears when using PSQL is omitted in these examples to provide extra clarity for the point being demonstrated.

Examples and output from examples are shown in fixed-width, grey font on a light background.


Also note the following points:

 During installation of the EDB Postgres Advanced Server the selection for configuration and defaults compatible with Oracle databases must be chosen in order to reproduce the same results as the examples shown in this guide. A default compatible configuration can be verified by issuing the following commands in PSQL and obtaining the same results as shown below.

• The examples use the sample tables, dept, emp, and jobhist, created and loaded when Advanced Server is installed. The emp table is installed with triggers that must be disabled in order to reproduce the same results as shown in this guide. Log onto Advanced Server as the enterprisedb superuser and disable the triggers by issuing the following command.

```
ALTER TABLE emp DISABLE TRIGGER USER;
```

The triggers on the emp table can later be re-activated with the following command.



6.2.0 SQL Tutorial

Advanced Server is a *relational database management system* (RDBMS). That means it is a system for managing data stored in *relations*. A relation is essentially a mathematical term for a *table*. The notion of storing data in tables is so commonplace today that it might seem inherently obvious, but there are a number of other ways of organizing databases. Files and directories on Unix-like operating systems form an example of a hierarchical database. A more modern development is the object-oriented database.

Each table is a named collection of *rows*. Each row of a given table has the same set of named *columns*, and each column is of a specific *data type*. Whereas columns have a fixed order in each row, it is important to remember that SQL does not guarantee the order of the rows within the table in any way (although they can be explicitly sorted for display).

Tables are grouped into *databases*, and a collection of databases managed by a single Advanced Server instance constitutes a database *cluster*.

6.2.1.0 Sample Database

Throughout this documentation we will be working with a sample database to help explain some basic to advanced level database concepts.

6.2.1.1 Sample Database Installation

When Advanced Server is installed a sample database named, edb , is automatically created. This sample database contains the tables and programs used throughout this document by executing the script, edb-sample.sql , located in the /usr/edb/as12/share directory.

This script does the following:

- · Creates the sample tables and programs in the currently connected database
- Grants all permissions on the tables to the PUBLIC group

The tables and programs will be created in the first schema of the search path in which the current user has permission to create tables and procedures. You can display the search path by issuing the command:

SHOW SEARCH_PATH;

Altering the search path can be done using commands in PSQL.

6.2.1.2 Sample Database Description

The sample database represents employees in an organization.

It contains three types of records: employees, departments, and historical records of employees.

Each employee has an identification number, name, hire date, salary, and manager. Some employees earn a commission in addition to their salary. All employee-related information is stored in the emp table.

The sample company is regionally diverse, so the database keeps track of the location of the departments. Each company employee is assigned to a department. Each department is identified by a unique department number and a short name. Each department is associated with one location. All department-related information is stored in the dept table.

The company also tracks information about jobs held by the employees. Some employees have been with the company for a long time and have held different positions, received raises, switched departments, etc. When a change in employee status occurs, the company records the end date of the former position. A new job record

is added with the start date and the new job title, department, salary, and the reason for the status change. All employee history is maintained in the jobhist table.

The following is an entity relationship diagram of the sample database tables.

Sample Database Tables

```
The following is the edb-sample.sql script.
    Script that creates the 'sample' tables, views, procedures,
   functions, triggers, etc.
--
   Start new transaction - commit all or nothing
BEGIN;
/
   Create and load tables used in the documentation examples.
   Create the 'dept' table
CREATE TABLE dept (
                    NUMBER(2) NOT NULL CONSTRAINT dept_pk PRIMARY KEY,
   deptno
   dname
                    VARCHAR2(14) CONSTRAINT dept_dname_uq UNIQUE,
   loc
                    VARCHAR2(13)
);
-- Create the 'emp' table
CREATE TABLE emp (
                   NUMBER(4) NOT NULL CONSTRAINT emp_pk PRIMARY KEY,
   empno
   ename
                   VARCHAR2(10),
   job
                   VARCHAR2(9),
                   NUMBER(4),
   mgr
   hiredate
                   DATE,
   sal
                   NUMBER(7,2) CONSTRAINT emp_sal_ck CHECK (sal > 0),
   comm
                   NUMBER(7,2),
                   NUMBER(2) CONSTRAINT emp_ref_dept_fk
   deptno
                        REFERENCES dept(deptno)
);
-- Create the 'jobhist' table
CREATE TABLE jobhist (
                   NUMBER(4) NOT NULL,
   empno
   startdate
                   DATE NOT NULL,
                   DATE,
   enddate
                   VARCHAR2(9),
   job
                   NUMBER(7,2),
   sal
   comm
                   NUMBER(7,2),
   deptno
                   NUMBER(2),
                   VARCHAR2(80),
   chadesc
   CONSTRAINT jobhist_pk PRIMARY KEY (empno, startdate),
   CONSTRAINT jobhist_ref_emp_fk FOREIGN KEY (empno)
       REFERENCES emp(empno) ON DELETE CASCADE,
   CONSTRAINT jobhist_ref_dept_fk FOREIGN KEY (deptno)
       REFERENCES dept (deptno) ON DELETE SET NULL,
   CONSTRAINT jobhist_date_chk CHECK (startdate <= enddate)</pre>
);
   Create the 'salesemp' view
```

```
CREATE OR REPLACE VIEW salesemp AS
    SELECT empno, ename, hiredate, sal, comm FROM emp WHERE job = 'SALESMAN';
    Sequence to generate values for function 'new_empno'.
CREATE SEQUENCE next_empno START WITH 8000 INCREMENT BY 1;
    Issue PUBLIC grants
GRANT ALL ON emp TO PUBLIC;
GRANT ALL ON dept TO PUBLIC;
GRANT ALL ON jobhist TO PUBLIC:
GRANT ALL ON salesemp TO PUBLIC
GRANT ALL ON next_empno TO PUBLIC;
-- Load the 'dept' table
INSERT INTO dept VALUES (10, 'ACCOUNTING', 'NEW YORK');
INSERT INTO dept VALUES (20, 'RESEARCH', 'DALLAS');
INSERT INTO dept VALUES (30, 'SALES', 'CHICAGO');
INSERT INTO dept VALUES (40, 'OPERATIONS', 'BOSTON');
-- Load the 'emp' table
INSERT INTO emp VALUES (7369, 'SMITH', 'CLERK', 7902, '17-DEC-80', 800, NULL, 20);
INSERT INTO emp VALUES (7499, 'ALLEN', 'SALESMAN', 7698, '20-FEB-
81',1600,300,30);
INSERT INTO emp VALUES (7521, 'WARD', 'SALESMAN', 7698, '22-FEB-81', 1250, 500, 30);
INSERT INTO emp VALUES (7566, 'JONES', 'MANAGER', 7839, '02-APR-
81',2975,NULL,20);
INSERT INTO emp VALUES (7654, 'MARTIN', 'SALESMAN', 7698, '28-SEP-
81',1250,1400,30);
INSERT INTO emp VALUES (7698, 'BLAKE', 'MANAGER', 7839, '01-MAY-
81',2850,NULL,30);
INSERT INTO emp VALUES (7782, 'CLARK', 'MANAGER', 7839, '09-JUN-
81',2450,NULL,10);
INSERT INTO emp VALUES (7788, 'SCOTT', 'ANALYST', 7566, '19-APR-
87',3000,NULL,20);
INSERT INTO emp VALUES (7839, 'KING', 'PRESIDENT', NULL, '17-NOV-
81',5000, NULL,10);
INSERT INTO emp VALUES (7844, 'TURNER', 'SALESMAN', 7698, '08-SEP-81', 1500, 0, 30); INSERT INTO emp VALUES (7876, 'ADAMS', 'CLERK', 7788, '23-MAY-87', 1100, NULL, 20); INSERT INTO emp VALUES (7900, 'JAMES', 'CLERK', 7698, '03-DEC-81', 950, NULL, 30); INSERT INTO emp VALUES (7902, 'FORD', 'ANALYST', 7566, '03-DEC-81', 3000, NULL, 20); INSERT INTO emp VALUES (7934, 'MILLER', 'CLERK', 7782, '23-JAN-82', 1300, NULL, 10);
-- Load the 'jobhist' table
INSERT INTO jobhist VALUES (7369, '17-DEC-80', NULL, 'CLERK', 800, NULL, 20, 'New
INSERT INTO jobhist VALUES (7499,'20-FEB-
81', NULL, 'SALESMAN', 1600, 300, 30, 'New Hire');
INSERT INTO jobhist VALUES (7521, '22-FEB-
81', NULL, 'SALESMAN', 1250, 500, 30, 'New Hire');
INSERT INTO jobhist VALUES (7566, '02-APR-
81', NULL, 'MANAGER', 2975, NULL, 20, 'New Hire');
INSERT INTO jobhist VALUES (7654, '28-SEP-
81',NULL,'SALESMAN',1250,1400,30,'New Hire');
INSERT INTO jobhist VALUES (7698, '01-MAY-
81', NULL, 'MANAGER', 2850, NULL, 30, 'New Hire');
```

```
INSERT INTO jobhist VALUES (7782, '09-JUN-
81', NULL, 'MANAGER', 2450, NULL, 10, 'New Hire');
INSERT INTO jobhist VALUES (7788, '19-APR-87', '12-APR-
88', 'CLERK', 1000, NULL, 20, 'New Hire');
INSERT INTO jobhist VALUES (7788, '13-APR-88', '04-MAY-
89','CLERK',1040,NULL,20,'Raise');
INSERT INTO jobhist VALUES (7788, '05-MAY-
90', NULL, 'ANALYST', 3000, NULL, 20, 'Promoted to Analyst');
INSERT INTO jobhist VALUES (7839, '17-NOV-
81', NULL, 'PRESIDENT', 5000, NULL, 10, 'New Hire');
INSERT INTO jobhist VALUES (7844, '08-SEP-81', NULL, 'SALESMAN', 1500, 0, 30, 'New
INSERT INTO jobhist VALUES (7876, '23-MAY-87', NULL, 'CLERK', 1100, NULL, 20, 'New
Hire');
INSERT INTO jobhist VALUES (7900, '03-DEC-81', '14-JAN-
83', 'CLERK', 950, NULL, 10, 'New Hire');
INSERT INTO jobhist VALUES (7900, '15-JAN-
83', NULL, 'CLERK', 950, NULL, 30, 'Changed to Dept 30');
INSERT INTO jobhist VALUES (7902, '03-DEC-
81', NULL, 'ANALYST', 3000, NULL, 20, 'New Hire');
INSERT INTO jobhist VALUES (7934, '23-JAN-82', NULL, 'CLERK', 1300, NULL, 10, 'New
Hire');
   Populate statistics table and view (pg_statistic/pg_stats)
ANALYZE dept;
ANALYZE emp;
ANALYZE jobhist;
-- Procedure that lists all employees' numbers and names
-- from the 'emp' table using a cursor.
CREATE OR REPLACE PROCEDURE list_emp
                   NUMBER(4);
   v_empno
                   VARCHAR2(10);
   v_ename
   CURSOR emp_cur IS
       SELECT empno, ename FROM emp ORDER BY empno;
BEGIN
   OPEN emp_cur;
   DBMS_OUTPUT.PUT_LINE('EMPNO
                                   ENAME');
   DBMS_OUTPUT.PUT_LINE('----
   L<sub>00</sub>P
       FETCH emp_cur INTO v_empno, v_ename;
       EXIT WHEN emp_cur%NOTFOUND;
       END LOOP;
   CLOSE emp_cur;
END;
    Procedure that selects an employee row given the employee
   number and displays certain columns.
CREATE OR REPLACE PROCEDURE select_emp (
   p_empno
                  IN NUMBER
IS
   v_ename
                   emp.ename%TYPE;
   v_hiredate
                   emp.hiredate%TYPE;
   v_sal
                   emp.sal%TYPE;
```

```
V_COMM
                    emp.comm%TYPE;
   v_dname
                    dept.dname%TYPE;
                    VARCHAR2(10);
   v_disp_date
BEGIN
   SELECT ename, hiredate, sal, NVL(comm, 0), dname
       INTO v_ename, v_hiredate, v_sal, v_comm, v_dname
       FROM emp e, dept d
       WHERE empno = p_{empno}
       AND e.deptno = d.deptno;
   v_disp_date := TO_CHAR(v_hiredate, 'MM/DD/YYYY');
                                   : ' || p_empno);
   DBMS_OUTPUT.PUT_LINE('Number
                                   : ' || v_ename);
   DBMS_OUTPUT.PUT_LINE('Name
   DBMS_OUTPUT.PUT_LINE('Hire Date : ' || v_disp_date);
DBMS_OUTPUT.PUT_LINE('Salary : ' || v_sal);
DBMS_OUTPUT.PUT_LINE('Commission: ' || v_comm);
   DBMS_OUTPUT.PUT_LINE('Department: ' || v_dname);
EXCEPTION
   WHEN NO_DATA_FOUND THEN
       DBMS_OUTPUT.PUT_LINE('Employee ' || p_empno || ' not found');
   WHEN OTHERS THEN
       DBMS_OUTPUT.PUT_LINE('The following is SQLERRM:');
       DBMS_OUTPUT.PUT_LINE(SQLERRM);
       DBMS_OUTPUT.PUT_LINE('The following is SQLCODE:');
       DBMS_OUTPUT.PUT_LINE(SQLCODE);
END;
/
-- Procedure that queries the 'emp' table based on
   department number and employee number or name. Returns
   employee number and name as IN OUT parameters and job,
-- hire date, and salary as OUT parameters.
CREATE OR REPLACE PROCEDURE emp_query (
                           NUMBER.
   p_deptno
                    ΙN
                    IN OUT NUMBER,
   p_empno
                    IN OUT VARCHAR2.
   p_ename
   p_job
                    OUT
                           VARCHAR2,
                           DATE,
   p_hiredate
                    OUT
                    OUT
                           NUMBER
   p_sal
)
IS
BEGIN
   SELECT empno, ename, job, hiredate, sal
       INTO p_empno, p_ename, p_job, p_hiredate, p_sal
       FROM emp
       WHERE deptno = p_deptno
         AND (empno = p_empno)
          OR ename = UPPER(p_ename));
END;
/
-- Procedure to call 'emp_query_caller' with IN and IN OUT
    parameters. Displays the results received from IN OUT and
    OUT parameters.
CREATE OR REPLACE PROCEDURE emp_query_caller
                    NUMBER(2);
   v_deptno
                    NUMBER(4);
   v_empno
   v_ename
                    VARCHAR2(10);
   v_job
                    VARCHAR2(9);
```

```
v_hiredate
                   DATE:
                   NUMBER;
   v_sal
BEGIN
   v_{deptno} := 30;
   v_{empno} := 0;
   v_ename := 'Martin';
   emp_query(v_deptno, v_empno, v_ename, v_job, v_hiredate, v_sal);
   DBMS_OUTPUT.PUT_LINE('Department : ' || v_deptno);
   DBMS_OUTPUT.PUT_LINE('Employee No: ' || v_empno);
                                  : ' | | v_ename);
   DBMS_OUTPUT.PUT_LINE('Name
                                    : ' || v_iob);
   DBMS_OUTPUT.PUT_LINE('Job
   DBMS_OUTPUT.PUT_LINE('Hire Date : ' || v_hiredate);
   DBMS_OUTPUT.PUT_LINE('Salary
                                    : ' || v_sal);
EXCEPTION
   WHEN TOO_MANY_ROWS THEN
       DBMS_OUTPUT.PUT_LINE('More than one employee was selected');
   WHEN NO_DATA_FOUND THEN
       DBMS_OUTPUT.PUT_LINE('No employees were selected');
END;
/
-- Function to compute yearly compensation based on semimonthly
-- salary.
CREATE OR REPLACE FUNCTION emp_comp (
                   NUMBER,
   p_sal
   p_comm
                   NUMBER
) RETURN NUMBER
IS
BEGIN
   RETURN (p_sal + NVL(p_comm, 0)) * 24;
END;
-- Function that gets the next number from sequence, 'next_empno',
-- and ensures it is not already in use as an employee number.
CREATE OR REPLACE FUNCTION new_empno RETURN NUMBER
IS
   v_cnt
                   INTEGER := 1;
                   NUMBER;
   v_new_empno
BEGIN
   WHILE v_{cnt} > 0 LOOP
       SELECT next_empno.nextval INTO v_new_empno FROM dual;
       SELECT COUNT(*) INTO v_cnt FROM emp WHERE empno = v_new_empno;
   END LOOP;
   RETURN v_new_empno;
END;
/
-- EDB-SPL function that adds a new clerk to table 'emp'. This function
   uses package 'emp_admin'.
CREATE OR REPLACE FUNCTION hire_clerk (
                  VARCHAR2,
   p_ename
                   NUMBER
   p_deptno
) RETURN NUMBER
TS
                   NUMBER(4);
   v_empno
   v_ename
                   VARCHAR2(10);
                   VARCHAR2(9);
   v_job
```

```
NUMBER(4);
   v_mgr
   v_hiredate
                    DATE;
                    NUMBER(7,2);
   v_sal
                    NUMBER(7,2);
   V_COMM
   v_deptno
                    NUMBER(2);
BEGIN
   v_empno := new_empno;
   INSERT INTO emp VALUES (v_empno, p_ename, 'CLERK', 7782,
       TRUNC(SYSDATE), 950.00, NULL, p_deptno);
   SELECT empno, ename, job, mgr, hiredate, sal, comm, deptno INTO
       v_empno, v_ename, v_job, v_mgr, v_hiredate, v_sal, v_comm, v_deptno
       FROM emp WHERE empno = v_{empno};
   DBMS_OUTPUT.PUT_LINE('Department : ' || v_deptno);
   DBMS_OUTPUT.PUT_LINE('Employee No: ' | | v_empno);
   DBMS_OUTPUT.PUT_LINE('Name : ' | | v_ename);
                                      : ' || v_job);
   DBMS_OUTPUT.PUT_LINE('Job
                                    : ' || v_mgr);
   DBMS_OUTPUT.PUT_LINE('Manager
   DBMS_OUTPUT.PUT_LINE('Hire Date : ' || v_hiredate);
   DBMS_OUTPUT.PUT_LINE('Salary
                                  : ' || v_sal);
   DBMS_OUTPUT.PUT_LINE('Commission : ' || v_comm);
   RETURN v_empno;
EXCEPTION
   WHEN OTHERS THEN
       DBMS_OUTPUT.PUT_LINE('The following is SQLERRM:');
       DBMS_OUTPUT.PUT_LINE(SQLERRM);
       DBMS_OUTPUT.PUT_LINE('The following is SQLCODE:');
       DBMS_OUTPUT.PUT_LINE(SQLCODE);
       RETURN -1;
END;
/
   PostgreSQL PL/pgSQL function that adds a new salesman
-- to table 'emp'.
CREATE OR REPLACE FUNCTION hire_salesman (
   p_ename
                    VARCHAR,
   p_sal
                    NUMERIC,
                    NUMERIC
   p_comm
) RETURNS NUMERIC
AS $$
DECLARE
   v_empno
                    NUMERIC(4);
   v_ename
                    VARCHAR(10);
                    VARCHAR(9);
   v_job
                    NUMERIC(4);
   v_mgr
   v_hiredate
                    DATE;
                    NUMERIC(7,2);
   v_sal
   V_COMM
                    NUMERIC(7,2);
   v_deptno
                    NUMERIC(2);
BEGIN
   v_empno := new_empno();
   INSERT INTO emp VALUES (v_empno, p_ename, 'SALESMAN', 7698,
       CURRENT_DATE, p_sal, p_comm, 30);
   SELECT INTO
       v_empno, v_ename, v_job, v_mgr, v_hiredate, v_sal, v_comm, v_deptno
       empno, ename, job, mgr, hiredate, sal, comm, deptno
       FROM emp WHERE empno = v_{empno};
   RAISE INFO 'Department : %', v_deptno;
RAISE INFO 'Employee No: %', v_empno;
RAISE INFO 'Name : %', v_ename;
                           : %', v_job;
   RAISE INFO 'Job
```

```
RAISE INFO 'Manager : %', v_mgr;
  RAISE INFO 'Hire Date : %', v_hiredate; RAISE INFO 'Salary : %', v_sal;
   RAISE INFO 'Commission: %', v_comm;
   RETURN v_empno;
EXCEPTION
   WHEN OTHERS THEN
       RAISE INFO 'The following is SQLERRM:';
       RAISE INFO '%', SQLERRM;
       RAISE INFO 'The following is SOLSTATE:';
       RAISE INFO '%', SQLSTATE;
       RETURN -1;
END;
$$ LANGUAGE 'plpgsql';
-- Rule to INSERT into view 'salesemp'
CREATE OR REPLACE RULE salesemp_i AS ON INSERT TO salesemp
DO INSTEAD
   INSERT INTO emp VALUES (NEW.empno, NEW.ename, 'SALESMAN', 7698,
       NEW.hiredate, NEW.sal, NEW.comm, 30);
-- Rule to UPDATE view 'salesemp'
CREATE OR REPLACE RULE salesemp_u AS ON UPDATE TO salesemp
DO INSTEAD
   UPDATE emp SET empno
                            = NEW.empno,
                  ename
                          = NEW.ename,
                  hiredate = NEW.hiredate,
                          = NEW.sal,
                  sal
                            = NEW.comm
                  comm
       WHERE empno = OLD.empno;
-- Rule to DELETE from view 'salesemp'
CREATE OR REPLACE RULE salesemp_d AS ON DELETE TO salesemp
DO INSTEAD
   DELETE FROM emp WHERE empno = OLD.empno;

    After statement-level trigger that displays a message after

-- an insert, update, or deletion to the 'emp' table. One message
-- per SQL command is displayed.
CREATE OR REPLACE TRIGGER user_audit_trig
   AFTER INSERT OR UPDATE OR DELETE ON emp
DECLARE
   v_action
                   VARCHAR2(24);
BEGIN
   IF INSERTING THEN
       v_action := ' added employee(s) on ';
   ELSIF UPDATING THEN
       v_action := ' updated employee(s) on ';
   ELSIF DELETING THEN
       v_action := ' deleted employee(s) on ';
   DBMS_OUTPUT.PUT_LINE('User ' || USER || v_action ||
TO_CHAR(SYSDATE, 'YYYY-MM-DD'));
END;
/
```

```
-- Before row-level trigger that displays employee number and
   salary of an employee that is about to be added, updated,
    or deleted in the 'emp' table.
CREATE OR REPLACE TRIGGER emp_sal_trig
   BEFORE DELETE OR INSERT OR UPDATE ON emp
   FOR EACH ROW
DECLARE
   sal_diff
                  NUMBER;
BEGIN
   IF INSERTING THEN
       DBMS_OUTPUT.PUT_LINE('Inserting employee ' | :NEW.empno);
       DBMS_OUTPUT.PUT_LINE('..New salary: ' || :NEW.sal);
   END IF;
   IF UPDATING THEN
       sal_diff := :NEW.sal - :OLD.sal;
       DBMS_OUTPUT.PUT_LINE('Updating employee ' || :OLD.empno);
       DBMS_OUTPUT.PUT_LINE('..Old salary: ' || :OLD.sal);
       DBMS_OUTPUT.PUT_LINE('..New salary: ' || :NEW.sal);
       DBMS_OUTPUT.PUT_LINE('..Raise
                                         : ' || sal_diff);
    END IF;
    IF DELETING THEN
       DBMS_OUTPUT.PUT_LINE('Deleting employee ' | OLD.empno);
       DBMS_OUTPUT.PUT_LINE('..Old salary: ' || :OLD.sal);
    END IF;
END;
  Package specification for the 'emp_admin' package.
CREATE OR REPLACE PACKAGE emp_admin
IS
   FUNCTION get_dept_name (
       p_deptno
                       NUMBER
   ) RETURN VARCHAR2;
   FUNCTION update_emp_sal (
       p_empno
                       NUMBER,
       p_raise
                       NUMBER
   ) RETURN NUMBER;
   PROCEDURE hire_emp (
                       NUMBER,
       p_empno
       p_ename
                       VARCHAR2,
       p_job
                       VARCHAR2,
       p_sal
                       NUMBER,
                       DATE,
       p_hiredate
       p_comm
                       NUMBER,
                       NUMBER,
       p_mgr
       p_deptno
                       NUMBER
   );
   PROCEDURE fire_emp (
                       NUMBER
       p_empno
END emp_admin;
    Package body for the 'emp_admin' package.
CREATE OR REPLACE PACKAGE BODY emp_admin
IS
   -- Function that queries the 'dept' table based on the department
```

```
-- number and returns the corresponding department name.
FUNCTION get_dept_name (
    p_deptno
                    IN NUMBER
) RETURN VARCHAR2
IS
   v_dname
                    VARCHAR2(14);
BEGIN
    SELECT dname INTO v_dname FROM dept WHERE deptno = p_deptno;
    RETURN v_dname;
EXCEPTION
   WHEN NO_DATA_FOUND THEN
        DBMS_OUTPUT.PUT_LINE('Invalid department number ' || p_deptno);
        RETURN '';
END;
   Function that updates an employee's salary based on the
-- employee number and salary increment/decrement passed
-- as IN parameters. Upon successful completion the function
-- returns the new updated salary.
FUNCTION update_emp_sal (
                    IN NUMBER,
    p_empno
                    IN NUMBER
    p_raise
) RETURN NUMBER
   v_sal
                    NUMBER := 0;
BEGIN
    SELECT sal INTO v_{sal} FROM emp WHERE empno = p_{empno};
    v_sal := v_sal + p_raise;
    UPDATE emp SET sal = v_sal WHERE empno = p_empno;
    RETURN v_sal;
EXCEPTION
    WHEN NO DATA FOUND THEN
        DBMS_OUTPUT.PUT_LINE('Employee ' || p_empno || ' not found');
        RETURN -1;
   WHEN OTHERS THEN
        DBMS_OUTPUT.PUT_LINE('The following is SQLERRM:');
        DBMS_OUTPUT.PUT_LINE(SQLERRM);
        DBMS_OUTPUT.PUT_LINE('The following is SQLCODE:');
        DBMS_OUTPUT.PUT_LINE(SQLCODE);
        RETURN -1;
END;
   Procedure that inserts a new employee record into the 'emp' table.
PROCEDURE hire_emp (
    p_empno
                    NUMBER,
    p_ename
                    VARCHAR2,
    p_job
                    VARCHAR2,
                    NUMBER,
    p_sal
    p_hiredate
                    DATE,
                    NUMBER.
    p_comm
    p_mgr
                    NUMBER,
                    NUMBER
    p_deptno
)
AS
BEGIN
    INSERT INTO emp(empno, ename, job, sal, hiredate, comm, mgr, deptno)
        VALUES(p_empno, p_ename, p_job, p_sal,
               p_hiredate, p_comm, p_mgr, p_deptno);
```

6.2.2 Creating a New Table

A new table is created by specifying the table name, along with all column names and their types. The following is a simplified version of the emp sample table with just the minimal information needed to define a table.

```
CREATE TABLE emp (
                     NUMBER(4),
    empno
                     VARCHAR2(10),
    ename
    job
                     VARCHAR2(9),
                     NUMBER(4),
    mar
    hiredate
                     DATE,
                     NUMBER(7,2),
    sal
                     NUMBER(7,2),
    comm
    deptno
                     NUMBER(2)
);
```

You can enter this into PSQL with line breaks. PSQL will recognize that the command is not terminated until the semicolon.

White space (i.e., spaces, tabs, and newlines) may be used freely in SQL commands. That means you can type the command aligned differently than the above, or even all on one line. Two dashes ("--") introduce comments. Whatever follows them is ignored up to the end of the line. SQL is case insensitive about key words and identifiers, except when identifiers are double-guoted to preserve the case (not done above).

VARCHAR2(10) specifies a data type that can store arbitrary character strings up to 10 characters in length. NUMBER(7,2) is a fixed point number with precision 7 and scale 2. NUMBER(4) is an integer number with precision 4 and scale 0.

Advanced Server supports the usual SQL data types $\,$ INTEGER , $\,$ SMALLINT , $\,$ NUMBER , $\,$ REAL , $\,$ DOUBLE PRECISION , $\,$ CHAR , $\,$ VARCHAR2 , $\,$ DATE , and $\,$ TIMESTAMP as well as various synonyms for these types.

If you don't need a table any longer or want to recreate it differently you can remove it using the following command:

```
DROP TABLE tablename;
```

6.2.3 Populating a Table With Rows

The INSERT statement is used to populate a table with rows:

INSERT INTO emp VALUES (7369, 'SMITH', 'CLERK', 7902, '17-DEC-80', 800, NULL, 20);

Note that all data types use rather obvious input formats. Constants that are not simple numeric values usually must be surrounded by single quotes ('), as in the example. The DATE type is actually quite flexible in what it accepts, but for this tutorial we will stick to the unambiguous format shown here.

The syntax used so far requires you to remember the order of the columns. An alternative syntax allows you to list the columns explicitly:

```
INSERT INTO emp(empno,ename,job,mgr,hiredate,sal,comm,deptno)
   VALUES (7499,'ALLEN','SALESMAN',7698,'20-FEB-81',1600,300,30);
```

You can list the columns in a different order if you wish or even omit some columns, e.g., if the commission is unknown:

```
INSERT INTO emp(empno,ename,job,mgr,hiredate,sal,deptno)
VALUES (7369,'SMITH','CLERK',7902,'17-DEC-80',800,20);
```

Many developers consider explicitly listing the columns better style than relying on the order implicitly.

6.2.4 Querying a Table

To retrieve data from a table, the table is *queried*. An SQL_SELECT statement is used to do this. The statement is divided into a select list (the part that lists the columns to be returned), a table list (the part that lists the tables from which to retrieve the data), and an optional qualification (the part that specifies any restrictions). The following query lists all columns of all employees in the table in no particular order.

SELECT * FROM emp;

Here, "*" in the select list means all columns. The following is the output from this query.

						hired				l comm		deptno
7369 I		CLERK				17-DEC-80		+-	800.00		+ 	20
7499 l	ALLEN I	SALESMAN	1	7698		20-FEB-81	00:00:00	-	1600.00	1 300.0	00 l	30
7521 l	WARD	SALESMAN	1	7698	-	22-FEB-81	00:00:00	-	1250.00	500.0	00 l	30
7566 l	JONES	MANAGER	1	7839	-	02-APR-81	00:00:00	-	2975.00		- 1	20
7654 l	MARTINI	SALESMAN	1	7698		28-SEP-81	00:00:00	1	1250.00	1400.0	00 l	30
7698 I	BLAKE I	MANAGER	1	7839	1	01-MAY-81	00:00:00	1	2850.00		- 1	30
7782 l	CLARK I	MANAGER	1	7839	1	09-JUN-81	00:00:00	1	2450.00		- 1	10
7788 I	SCOTT I	ANALYST	1	7566		19-APR-87	00:00:00	-	3000.00	1	-	20
7839 l	KING	PRESIDENT	1			17-NOV-81	00:00:00	-	5000.00	1		10
7844 l	TURNERI	SALESMAN	1	7698		08-SEP-81	00:00:00	-	1500.00	0.00		30
7876 l	ADAMS I	CLERK	1	7788		23-MAY-87	00:00:00	-	1100.00	1	-	20
7900 l	JAMES I	CLERK	1	7698		03-DEC-81	00:00:00	-	950.00	1	-	30
7902 l	FORD	ANALYST	1	7566		03-DEC-81	00:00:00	-	3000.00	1	-	20
7934 l	MILLERI	CLERK	1	7782		23-JAN-82	00:00:00	-	1300.00	1	-	10
(14 ro	NS)											

You may specify any arbitrary expression in the select list. For example, you can do:

SELECT ename, sal, sal * 24 AS yearly_salary, deptno FROM emp;

ename	l sal	l yearly_salary	l deptno
SMITH	800.00	19200.00	l 20
ALLEN	1600.00	l 38400.00	l 30
WARD	1250.00	30000.00	l 30
JONES	1 2975.00	71400.00	l 20
MARTIN	1250.00	30000.00	l 30
BLAKE	1 2850.00	l 68400.00	l 30
CLARK	1 2450.00	l 58800.00	l 10
SC0TT	1 3000.00	72000.00	l 20
KING	1 5000.00	120000.00	l 10
TURNER	1 1500.00	l 36000.00	l 30
ADAMS	1100.00	1 26400.00	l 20

```
JAMES | 950.00 | 22800.00 | 30

FORD | 3000.00 | 72000.00 | 20

MILLER | 1300.00 | 31200.00 | 10

(14 rows)
```

Notice how the AS clause is used to re-label the output column. (The AS clause is optional.)

A query can be qualified by adding a WHERE clause that specifies which rows are wanted. The WHERE clause contains a Boolean (truth value) expression, and only rows for which the Boolean expression is true are returned. The usual Boolean operators (AND , OR , and NOT) are allowed in the qualification. For example, the following retrieves the employees in department 20 with salaries over \$1000.00:

SELECT ename, sal, deptno FROM emp WHERE deptno = 20 AND sal > 1000;

ename				deptno
	+-		٠+٠	
JONES	1	2975.00	I	20
SC0TT	1	3000.00	1	20
ADAMS	1	1100.00	1	20
FORD	1	3000.00	1	20
(4 rows	(

You can request that the results of a query be returned in sorted order:

SELECT ename, sal, deptno FROM emp ORDER BY ename;

ename		sal	1	deptno
ADAMS	† 	1100.00		20
ALLEN	I	1600.00	I	30
BLAKE	I	2850.00	1	30
CLARK	I	2450.00	1	10
FORD	I	3000.00	1	20
JAMES	I	950.00	1	30
JONES	I	2975.00	1	20
KING	I	5000.00	1	10
MARTIN	I	1250.00	1	30
MILLER	I	1300.00	1	10
SC0TT	I	3000.00	1	20
SMITH	I	800.00	1	20
TURNER	I	1500.00	1	30
WARD	I	1250.00	1	30
(14 rows)			

You can request that duplicate rows be removed from the result of a query:

SELECT DISTINCT job FROM emp;

```
job
-----ANALYST
CLERK
MANAGER
PRESIDENT
SALESMAN
(5 rows)
```

The following section shows how to obtain rows from more than one table in a single query.

6.2.5 Joins Between Tables

Thus far, our queries have only accessed one table at a time. Queries can access multiple tables at once, or access the same table in such a way that multiple rows of the table are being processed at the same time. A

query that accesses multiple rows of the same or different tables at one time is called a *join* query. For example, say you wish to list all the employee records together with the name and location of the associated department. To do that, we need to compare the deptno column of each row of the emp table with the deptno column of all rows in the dept table, and select the pairs of rows where these values match. This would be accomplished by the following query:

SELECT emp.ename, emp.sal, dept.deptno, dept.dname, dept.loc FROM emp, dept WHERE emp.deptno = dept.deptno;

ename	1	sal	1	deptno	1	dname	1	loc
MILLER	·+·	1300.00	·+·	10	-+· 	ACCOUNTING		NEW YORK
CLARK	I	2450.00	I	10	1	ACCOUNTING	I	NEW YORK
KING	1	5000.00	1	10	1	ACCOUNTING	1	NEW YORK
SC0TT	1	3000.00	I	20	1	RESEARCH	1	DALLAS
JONES	1	2975.00	1	20	1	RESEARCH	1	DALLAS
SMITH	1	800.00	1	20	1	RESEARCH	1	DALLAS
ADAMS	1	1100.00		20	-	RESEARCH		DALLAS
FORD	1	3000.00		20	-	RESEARCH		DALLAS
WARD	1	1250.00		30	-	SALES		CHICAGO
TURNER	1	1500.00	1	30	1	SALES	1	CHICAGO
ALLEN	1	1600.00	1	30	1	SALES	1	CHICAGO
BLAKE	1	2850.00	1	30	1	SALES	1	CHICAGO
MARTIN	1	1250.00	1	30	1	SALES	1	CHICAGO
JAMES	I	950.00	I	30	1	SALES	I	CHICAGO
(14 rows	5)							

Observe two things about the result set:

- There is no result row for department 40. This is because there is no matching entry in the emp table for department 40, so the join ignores the unmatched rows in the dept table. Shortly we will see how this can be fixed.
- It is more desirable to list the output columns qualified by table name rather than using * or leaving out the qualification as follows:

SELECT ename, sal, dept.deptno, dname, loc FROM emp, dept WHERE emp.deptno = dept.deptno;

Since all the columns had different names (except for deptno which therefore must be qualified), the parser automatically found out which table they belong to, but it is good style to fully qualify column names in join queries:

Join queries of the kind seen thus far can also be written in this alternative form:

SELECT emp.ename, emp.sal, dept.deptno, dept.dname, dept.loc FROM emp INNER JOIN dept ON emp.deptno = dept.deptno;

This syntax is not as commonly used as the one above, but we show it here to help you understand the following topics.

You will notice that in all the above results for joins no employees were returned that belonged to department 40 and as a consequence, the record for department 40 never appears. Now we will figure out how we can get the department 40 record in the results despite the fact that there are no matching employees. What we want the query to do is to scan the dept table and for each row to find the matching emp row. If no matching row is found we want some "empty" values to be substituted for the emp table's columns. This kind of query is called an *outer join*. (The joins we have seen so far are *inner joins*.) The command looks like this:

SELECT emp.ename, emp.sal, dept.deptno, dept.dname, dept.loc FROM dept LEFT OUTER JOIN emp ON emp.deptno = dept.deptno;

						dname 		
	•	1300.00	•		•	ACCOUNTING	•	
CLARK		2450.00		10		ACCOUNTING	1	NEW YORK

```
10 | ACCOUNTING | NEW YORK
KING
        | 5000.00 |
                        20 | RESEARCH
                                         I DALLAS
SC0TT
        1 3000.00 I
JONES
       | 2975.00 |
                        20 | RESEARCH
                                         I DALLAS
           800.00 |
                        20 | RESEARCH
                                         I DALLAS
SMITH
       -
ADAMS
                        20 I
                                         I DALLAS
         1100.00 I
                             RESEARCH
        1
FORD
        3000.00 l
                        20 I
                             RESEARCH
                                         I DALLAS
          1250.00 l
                        30 I
                                         | CHICAGO
WARD
        SALES
TURNER | 1500.00 |
                        30 | SALES
                                         I CHICAGO
      | 1600.00 |
                        30 | SALES
ALLEN
                                         | CHICAGO
BLAKE
       | 2850.00 |
                        30 | SALES
                                         | CHICAGO
MARTIN | 1250.00 |
                        30 | SALES
                                         | CHICAGO
JAMES
          950.00 I
                        30 | SALES
                                         | CHICAGO
                  Ι
                        40 | OPERATIONS | BOSTON
(15 rows)
```

This query is called a *left outer join* because the table mentioned on the left of the join operator will have each of its rows in the output at least once, whereas the table on the right will only have those rows output that match some row of the left table. When a left-table row is selected for which there is no right-table match, empty (NULL) values are substituted for the right-table columns.

An alternative syntax for an outer join is to use the outer join operator, "(+)", in the join condition within the WHERE clause. The outer join operator is placed after the column name of the table for which null values should be substituted for unmatched rows. So for all the rows in the dept table that have no matching rows in the emp table, Advanced Server returns null for any select list expressions containing columns of emp. Hence the above example could be rewritten as:

SELECT emp.ename, emp.sal, dept.deptno, dept.dname, dept.loc FROM dept, emp
WHERE emp.deptno(+) = dept.deptno;

ename	I	sal	I	deptno		dname	I	loc
MILLER	-+·	1300.00	-+- 	 10	·+·	ACCOUNTING	·+·	NEW YORK
CLARK	İ	2450.00	İ	10	i	ACCOUNTING	İ	NEW YORK
KING	I	5000.00	I	10	I	ACCOUNTING	I	NEW YORK
SC0TT	I	3000.00	1	20	1	RESEARCH	I	DALLAS
JONES	1	2975.00	1	20	1	RESEARCH	1	DALLAS
SMITH	1	800.00	1	20	1	RESEARCH	1	DALLAS
ADAMS	1	1100.00	1	20	1	RESEARCH	1	DALLAS
FORD	1	3000.00	1	20	1	RESEARCH	1	DALLAS
WARD	1	1250.00	1	30	1	SALES	1	CHICAGO
TURNER	1	1500.00	1	30	1	SALES	1	CHICAGO
ALLEN	1	1600.00	1	30	1	SALES	1	CHICAGO
BLAKE	1	2850.00	1	30	1	SALES	1	CHICAGO
MARTIN	1	1250.00	1	30	1	SALES	1	CHICAGO
JAMES	-	950.00		30		SALES		CHICAGO
	I		1	40	1	OPERATIONS	I	BOSTON
(15 rows	;)							

We can also join a table against itself. This is called a *self join*. As an example, suppose we wish to find the name of each employee along with the name of that employee's manager. So we need to compare the mgr column of each emp row to the empno column of all other emp rows.

```
SELECT e1.ename | | ' works for ' | | e2.ename AS "Employees and their Managers" FROM emp e1, emp e2 WHERE e1.mgr = e2.empno;
```

```
Employees and their Managers
```

FORD works for JONES SCOTT works for JONES WARD works for BLAKE TURNER works for BLAKE

MARTIN works for BLAKE

```
JAMES works for BLAKE
ALLEN works for BLAKE
MILLER works for CLARK
ADAMS works for SCOTT
CLARK works for KING
BLAKE works for KING
JONES works for KING
SMITH works for FORD
(13 rows)
```

Here, the emp table has been re-labeled as e1 to represent the employee row in the select list and in the join condition, and also as e2 to represent the matching employee row acting as manager in the select list and in the join condition. These kinds of aliases can be used in other queries to save some typing, for example:

SELECT e.ename, e.mgr, d.deptno, d.dname, d.loc FROM emp e, dept d WHERE e.deptno = d.deptno;

ename	1	mgr	1	deptno	1	dname	1	loc
MILLER CLARK	 	7782 7839		10 10	-+· 	ACCOUNTING ACCOUNTING	-+· 	NEW YORK NEW YORK
KING	I		ı	10	1	ACCOUNTING	1	NEW YORK
SC0TT	ı	7566	1	20	-	RESEARCH	-	DALLAS
JONES	ı	7839	1	20	1	RESEARCH	1	DALLAS
SMITH	ı	7902	1	20	1	RESEARCH	1	DALLAS
ADAMS	ı	7788	1	20	1	RESEARCH	1	DALLAS
FORD		7566	1	20	-	RESEARCH	-	DALLAS
WARD		7698	I	30	-	SALES	1	CHICAGO
TURNER		7698	I	30	-	SALES	1	CHICAGO
ALLEN		7698	I	30	-	SALES	1	CHICAGO
BLAKE	ı	7839	1	30	1	SALES	1	CHICAGO
MARTIN	ı	7698	1	30	1	SALES	1	CHICAGO
JAMES	ı	7698	1	30	-	SALES	-	CHICAGO
(14 rows	(

This style of abbreviating will be encountered quite frequently.

6.2.6 Aggregate Functions

Like most other relational database products, Advanced Server supports aggregate functions. An aggregate function computes a single result from multiple input rows. For example, there are aggregates to compute the COUNT, SUM, AVG (average), MAX (maximum), and MIN (minimum) over a set of rows.

As an example, the highest and lowest salaries can be found with the following query:

SELECT MAX(sal) highest_salary, MIN(sal) lowest_salary FROM emp;

If we wanted to find the employee with the largest salary, we may be tempted to try:

SELECT ename FROM emp WHERE sal = MAX(sal);

ERROR: aggregates not allowed in WHERE clause

This does not work because the aggregate function, MAX, cannot be used in the WHERE clause. This restriction exists because the WHERE clause determines the rows that will go into the aggregation stage so it has to be evaluated before aggregate functions are computed. However, the query can be restated to accomplish the intended result by using a *subquery*:

```
SELECT ename FROM emp WHERE sal = (SELECT MAX(sal) FROM emp);
ename
-----
KING
(1 row)
```

The subquery is an independent computation that obtains its own result separately from the outer query.

Aggregates are also very useful in combination with the GROUP BY clause. For example, the following query gets the highest salary in each department.

SELECT deptno, MAX(sal) FROM emp GROUP BY deptno;

This query produces one output row per department. Each aggregate result is computed over the rows matching that department. These grouped rows can be filtered using the HAVING clause.

SELECT deptno, MAX(sal) FROM emp GROUP BY deptno HAVING AVG(sal) > 2000;

This query gives the same results for only those departments that have an average salary greater than 2000.

Finally, the following query takes into account only the highest paid employees who are analysts in each department.

There is a subtle distinction between the WHERE and HAVING clauses. The WHERE clause filters out rows before grouping occurs and aggregate functions are applied. The HAVING clause applies filters on the results after rows have been grouped and aggregate functions have been computed for each group.

So in the previous example, only employees who are analysts are considered. From this subset, the employees are grouped by department and only those groups where the average salary of analysts in the group is greater than 2000 are in the final result. This is true of only the group for department 20 and the maximum analyst salary in department 20 is 3000.00.

6.2.7 Updates

The column values of existing rows can be changed using the UPDATE command. For example, the following sequence of commands shows the before and after results of giving everyone who is a manager a 10% raise:

```
SELECT ename, sal FROM emp WHERE job = 'MANAGER';
```

```
ename | sal
-----JONES | 2975.00
```

6.2.8 Deletions

Rows can be removed from a table using the DELETE command. For example, the following sequence of commands shows the before and after results of deleting all employees in department 20.

SELECT ename, deptno FROM emp;

ename l	deptno
+	
SMITH	20
ALLEN I	30
WARD I	30
JONES I	20
MARTIN	30
BLAKE I	30
CLARK I	10
SCOTT I	20
KING	10
TURNER I	30
ADAMS I	20
JAMES I	30
FORD I	20
MILLER	10
(14 rows)	

DELETE FROM emp WHERE deptno = 20;

SELECT ename, deptno FROM emp;

ename l	deptno
+	
ALLEN I	30
WARD I	30
MARTIN I	30
BLAKE I	30
CLARK I	10
KING	10
TURNER I	30
JAMES I	30
MILLER I	10
(9 rows)	

Be extremely careful of giving a DELETE command without a WHERE clause such as the following:

DELETE FROM tablename;

This statement will remove all rows from the given table, leaving it completely empty. The system will not request confirmation before doing this.

6.2.9 The SQL Language

Advanced Server supports SQL language that is compatible with Oracle syntax as well as syntax and commands for extended functionality (functionality that does not provide database compatibility for Oracle or support Oracle-styled applications).

The Database Compatibility for Oracle Developer's SQL Reference Guide provides detailed information about:

- · Compatible SQL syntax and language elements
- Data types
- Supported SQL command syntax

To review a copy of the guide, visit the Advanced Server website at:

https://www.enterprisedb.com/edb-docs

6.3.0 Advanced Concepts

The previous section discussed the basics of using SQL to store and access your data in Advanced Server. This section discusses more advanced SQL features that may simplify management and prevent loss or corruption of your data.

6.3.1 Views

Consider the following SELECT command.

SELECT ename, sal, sal * 24 AS yearly_salary, deptno FROM emp;

ename	1	sal	1	yearly_salary	1	deptno
SMITH	+-	800.00		19200.00	+	20
ALLEN	I	1600.00	I	38400.00	1	30
WARD	I	1250.00	1	30000.00		30
JONES	I	2975.00	I	71400.00	1	20
MARTIN	I	1250.00	1	30000.00		30
BLAKE	1	2850.00	1	68400.00	1	30
CLARK	I	2450.00	I	58800.00		10
SC0TT	1	3000.00	1	72000.00	1	20
KING	1	5000.00	1	120000.00	1	10
TURNER	1	1500.00	1	36000.00	1	30
ADAMS	1	1100.00	1	26400.00	1	20
JAMES	1	950.00	1	22800.00	1	30
FORD	1	3000.00	1	72000.00	1	20
MILLER	1	1300.00	1	31200.00	1	10
(14 rows	(

If this is a query that is used repeatedly, a shorthand method of reusing this query without re-typing the entire SELECT command each time is to create a *view* as shown below.

```
CREATE VIEW employee_pay AS SELECT ename, sal, sal * 24 AS yearly_salary,
deptno FROM emp;
```

The view name, employee_pay, can now be used like an ordinary table name to perform the query.

```
SELECT * FROM employee_pay;
```

```
ename | sal | yearly_salary | deptno
```

```
SMITH |
           800.00
                          19200.00 I
                                          20
       | 1600.00 |
ALLEN
                          38400.00 l
                                          30
WARD
        | 1250.00 |
                          30000.00 I
                                          30
JONES
       l 2975.00 l
                          71400.00 I
                                          20
MARTIN | 1250.00
                          30000.00
                                          30
       1 2850.00
                          68400.00
                                          30
BLAKE
CLARK
       | 2450.00 |
                          58800.00 I
                                          10
       | 3000.00 |
                          72000.00 I
SC0TT
                                          20
KING
        | 5000.00 |
                         120000.00 I
                                          10
TURNER | 1500.00 |
                          36000.00 I
                                          30
ADAMS
       | 1100.00 |
                          26400.00 I
                                          20
JAMES
          950.00 l
                          22800.00 I
                                          30
       - 1
FORD
        1 3000.00 I
                          72000.00 I
                                          20
MILLER | 1300.00 |
                          31200.00 I
                                          10
(14 rows)
```

Making liberal use of views is a key aspect of good SQL database design. Views provide a consistent interface that encapsulate details of the structure of your tables which may change as your application evolves.

Views can be used in almost any place a real table can be used. Building views upon other views is not uncommon.

6.3.2 Foreign Keys

Suppose you want to make sure all employees belong to a valid department. This is called maintaining the referential integrity of your data. In simplistic database systems this would be implemented (if at all) by first looking at the dept table to check if a matching record exists, and then inserting or rejecting the new employee record. This approach has a number of problems and is very inconvenient. Advanced Server can make it easier for you.

A modified version of the emp table presented in [Creating a New Table](../02_sql_tutorial/02_creating_a_new_table#creating is shown in this section with the addition of a foreign key constraint. The modified emp table looks like the following:

```
CREATE TABLE emp (
                     NUMBER(4) NOT NULL CONSTRAINT emp_pk PRIMARY KEY,
    empno
    ename
                     VARCHAR2(10),
                     VARCHAR2(9),
    job
                     NUMBER(4),
    mar
                     DATE,
    hiredate
                     NUMBER(7,2),
    sal
    comm
                     NUMBER(7,2),
    deptno
                     NUMBER(2) CONSTRAINT emp_ref_dept_fk
                         REFERENCES dept(deptno)
);
```

If an attempt is made to issue the following INSERT command in the sample emp table, the foreign key constraint, emp_ref_dept_fk , ensures that department 50 exists in the dept table. Since it does not, the command is rejected.

```
INSERT INTO emp VALUES (8000, 'JONES', 'CLERK', 7902, '17-AUG-07', 1200, NULL, 50); ERROR: insert or update on table "emp" violates foreign key constraint "emp_ref_dept_fk" DETAIL: Key (deptno)=(50) is not present in table "dept".
```

The behavior of foreign keys can be finely tuned to your application. Making correct use of foreign keys will definitely improve the quality of your database applications, so you are strongly encouraged to learn more about them.

6.3.3 The ROWNUM Pseudo-Column

ROWNUM is a pseudo-column that is assigned an incremental, unique integer value for each row based on the order the rows were retrieved from a query. Therefore, the first row retrieved will have ROWNUM of 1; the second row will have ROWNUM of 2 and so on.

This feature can be used to limit the number of rows retrieved by a query. This is demonstrated in the following example:

SELECT empno, ename, job FROM emp WHERE ROWNUM < 5;

The ROWNUM value is assigned to each row before any sorting of the result set takes place. Thus, the result set is returned in the order given by the ORDER BY clause, but the ROWNUM values may not necessarily be in ascending order as shown in the following example:

SELECT ROWNUM, empno, ename, job FROM emp WHERE ROWNUM < 5 ORDER BY ename;

The following example shows how a sequence number can be added to every row in the jobhist table. First a new column named, seqno, is added to the table and then seqno is set to ROWNUM in the UPDATE command.

```
ALTER TABLE jobhist ADD seqno NUMBER(3); UPDATE jobhist SET seqno = ROWNUM;
```

The following SELECT command shows the new segno values.

SELECT seqno, empno, TO_CHAR(startdate,'DD-MON-YY') AS start, job FROM jobhist;

seqno	I	empno	I	start	I	job
	+-		+-		+-	
1	ı	7369	ı	17-DEC-80	I	CLERK
2	1	7499		20-FEB-81		SALESMAN
3	1	7521	I	22-FEB-81		SALESMAN
4	1	7566	I	02-APR-81	1	MANAGER
5	-	7654		28-SEP-81	1	SALESMAN
6		7698		01-MAY-81	1	MANAGER
7		7782		09-JUN-81	1	MANAGER
8		7788		19-APR-87	1	CLERK
9		7788		13-APR-88	1	CLERK
10		7788		05-MAY-90		ANALYST
11		7839		17-NOV-81	1	PRESIDENT
12		7844		08-SEP-81	1	SALESMAN
13	1	7876	1	23-MAY-87	1	CLERK
14	1	7900		03-DEC-81	1	CLERK
15	1	7900	1	15-JAN-83	1	CLERK
16	1	7902	1	03-DEC-81	1	ANALYST

```
17 | 7934 | 23-JAN-82 | CLERK
(17 rows)
```

6.3.4 Synonyms

A *synonym* is an identifier that can be used to reference another database object in a SQL statement. A synonym is useful in cases where a database object would normally require full qualification by schema name to be properly referenced in a SQL statement. A synonym defined for that object simplifies the reference to a single, unqualified name.

Advanced Server supports synonyms for:

- · tables
- views
- · materialized views
- · sequences
- procedures
- functions
- types
- · objects that are accessible through a database link
- · other synonyms

Neither the referenced schema or referenced object must exist at the time that you create the synonym; a synonym may refer to a non-existent object or schema. A synonym will become invalid if you drop the referenced object or schema. You must explicitly drop a synonym to remove it.

As with any other schema object, Advanced Server uses the search path to resolve unqualified synonym names. If you have two synonyms with the same name, an unqualified reference to a synonym will resolve to the first synonym with the given name in the search path. If public is in your search path, you can refer to a synonym in that schema without qualifying that name.

When Advanced Server executes an SQL command, the privileges of the current user are checked against the synonym's underlying database object; if the user does not have the proper permissions for that object, the SQL command will fail.

Creating a Synonym

```
Use the CREATE SYNONYM command to create a synonym. The syntax is:
```

Parameters:

syn_name

syn_name is the name of the synonym. A synonym name must be unique within a schema.

schema

schema specifies the name of the schema that the synonym resides in. If you do not specify a schema name, the synonym is created in the first existing schema in your search path.

object_name

object_name specifies the name of the object.

object_schema

object_schema specifies the name of the schema that the object resides in.

dblink name

dblink_name specifies the name of the database link through which a target object may be accessed.

Include the REPLACE clause to replace an existing synonym definition with a new synonym definition.

Include the PUBLIC clause to create the synonym in the public schema. Compatible with Oracle databases, the CREATE PUBLIC SYNONYM command creates a synonym that resides in the public schema:

CREATE [OR REPLACE] PUBLIC SYNONYM <syn_name> FOR <object_schema>.<object_name>;
This just a shorthand way to write:

The following example creates a synonym named personnel that refers to the enterprised b.emp table.

CREATE SYNONYM personnel FOR enterprisedb.emp;

Unless the synonym is schema qualified in the CREATE SYNONYM command, it will be created in the first existing schema in your search path. You can view your search path by executing the following command:

SHOW SEARCH_PATH;

```
search_path
-----
development,accounting
(1 row)
```

In our example, if a schema named development does not exist, the synonym will be created in the schema named accounting .

Now, the emp table in the enterprisedb schema can be referenced in any SQL statement (DDL or DML), by using the synonym, personnel:

INSERT INTO personnel VALUES (8142, 'ANDERSON', 'CLERK', 7902, '17-DEC-06', 1300, NULL, 20);

SELECT * FROM personnel;

•				_	_	l hiredo					eptno
7369	-+ 		-	CLERK	•	+ 17-DEC-80	· ·	800.00		+ 	20
7499		ALLEN	I	SALESMAN	17698	120-FEB-81	00:00:001	1600.00	300.00		30
7521	-	WARD	l	SALESMAN	17698	122-FEB-81	00:00:001	1250.00	500.00		30
7566	-	JONES	l	MANAGER	17839	102-APR-81	00:00:001	2975.00			20
7654	-	MARTIN	l	SALESMAN	17698	128-SEP-81	00:00:001	1250.00	1400.00		30
7698	-	BLAKE	l	MANAGER	17839	101-MAY-81	00:00:001	2850.00			30
7782	-	CLARK	l	MANAGER	17839	109-JUN-81	00:00:001	2450.00			10
7788		SCOTT	l	ANALYST	17566	119-APR-87	00:00:001	3000.00			20
7839		KING	l	PRESIDENT	Ī	117-NOV-81	00:00:001	5000.00			10
7844		TURNER	l	SALESMAN	17698	108-SEP-81	00:00:001	1500.00	0.00		30
7876		ADAMS	l	CLERK	17788	123-MAY-87	00:00:001	1100.00			20
7900		JAMES	l	CLERK	17698	103-DEC-81	00:00:001	950.00			30
7902		FORD	l	ANALYST	17566	103-DEC-81	00:00:001	3000.00			20
7934		MILLER	l	CLERK	17782	123-JAN-82	00:00:001	1300.00			10
8142		ANDERSON	l	CLERK	17902	117-DEC-06	00:00:001	1300.00			20
(15 ro	ws)									

Deleting a Synonym

To delete a synonym, use the command, DROP SYNONYM. The syntax is:

```
DROP [PUBLIC] SYNONYM [<schema>.] <syn_name>
```

Parameters:

syn_name

syn_name is the name of the synonym. A synonym name must be unique within a schema.

schema

schema specifies the name of the schema in which the synonym resides.

Like any other object that can be schema-qualified, you may have two synonyms with the same name in your search path. To disambiguate the name of the synonym that you are dropping, include a schema name. Unless a synonym is schema qualified in the DROP SYNONYM command. Advanced Server deletes the first instance of the synonym it finds in your search path.

You can optionally include the PUBLIC clause to drop a synonym that resides in the public schema. Compatible with Oracle databases, the DROP PUBLIC SYNONYM command drops a synonym that resides in the public schema:

```
DROP PUBLIC SYNONYM <syn_name>;
The following example drops the synonym, personnel:
DROP SYNONYM personnel;
```

6.3.5.0 Hierarchical Queries

A hierarchical query is a type of query that returns the rows of the result set in a hierarchical order based upon data forming a parent-child relationship. A hierarchy is typically represented by an inverted tree structure. The tree is comprised of interconnected *nodes*. Each node may be connected to none, one, or multiple *child* nodes. Each node is connected to one parent node except for the top node which has no parent. This node is the root node. Each tree has exactly one root node. Nodes that don't have any children are called leaf nodes. A tree always has at least one leaf node - e.g., the trivial case where the tree is comprised of a single node. In this case it is both the root and the leaf.

In a hierarchical query the rows of the result set represent the nodes of one or more trees.

Note

It is possible that a single, given row may appear in more than one tree and thus appear more than once in the result set.

The hierarchical relationship in a query is described by the CONNECT BY clause which forms the basis of the order in which rows are returned in the result set. The context of where the CONNECT BY clause and its associated optional clauses appear in the SELECT command is shown below.

```
SELECT <select_list> FROM <table_expression> [ WHERE ...]
  [ START WITH <start_expression> ]
    CONNECT BY { PRIOR <parent_expr> = <child_expr> |
      <child_expr> = PRIOR <parent_expr> }
  [ ORDER SIBLINGS BY <column1> [ ASC | DESC ]
      [, <column2> [ ASC | DESC ] ] ...
  [ GROUP BY ...]
  [ HAVING ...]
  [ <other> ...]
```

select_list is one or more expressions that comprise the fields of the result set. table_expression is one or more tables or views from which the rows of the result set originate. other is any additional legal SELECT command clauses. The clauses pertinent to hierarchical queries, START WITH, CONNECT BY, and ORDER SIBLINGS BY are described in the following sections.

Note

At this time, Advanced Server does not support the use of AND (or other operators) in the CONNECT BY clause.

355

6.3.5.1 Defining the Parent/Child Relationship

For any given row, its parent and its children are determined by the CONNECT BY clause. The CONNECT BY clause must consist of two expressions compared with the equals (=) operator. In addition, one of these two expressions must be preceded by the keyword, PRIOR.

For any given row, to determine its children:

- 1. Evaluate *parent_expr* on the given row
- 2. Evaluate child_expr on any other row resulting from the evaluation of table_expression
- 3. If parent_expr = child_expr, then this row is a child node of the given parent row
- 4. Repeat the process for all remaining rows in *table_expression*. All rows that satisfy the equation in step 3 are the children nodes of the given parent row.

Note

The evaluation process to determine if a row is a child node occurs on every row returned by *table_expression* before the WHERE clause is applied to *table_expression*.

By iteratively repeating this process treating each child node found in the prior steps as a parent, an inverted tree of nodes is constructed. The process is complete when the final set of child nodes has no children of their own - these are the leaf nodes.

A SELECT command that includes a CONNECT BY clause typically includes the START WITH clause. The START WITH clause determines the rows that are to be the root nodes - i.e., the rows that are the initial parent nodes upon which the algorithm described previously is to be applied. This is further explained in the following section.

6.3.5.2 Selecting the Root Nodes

The START WITH clause is used to determine the row(s) selected by *table_expression* that are to be used as the root nodes. All rows selected by *table_expression* where *start_expression* evaluates to true become a root node of a tree. Thus, the number of potential trees in the result set is equal to the number of root nodes. As a consequence, if the START WITH clause is omitted, then every row returned by *table_expression* is a root of its own tree.

6.3.5.3 Organization Tree in the Sample Application

Consider the emp table of the sample application. The rows of the emp table form a hierarchy based upon the mgr column which contains the employee number of the employee's manager. Each employee has at most, one manager. KING is the president of the company so he has no manager, therefore KING's mgr column is null. Also, it is possible for an employee to act as a manager for more than one employee. This relationship forms a typical, tree-structured, hierarchical organization chart as illustrated below.

Employee Organization Hierarchy

To form a hierarchical query based upon this relationship, the SELECT command includes the clause, CONNECT BY PRIOR empno = mgr . For example, given the company president, KING , with employee number 7839 , any employee whose mgr column is 7839 reports directly to KING which is true for JONES, BLAKE , and CLARK (these are the child nodes of KING). Similarly, for employee, JONES , any other employee with mgr column equal to 7566 is a child node of JONES - these are SCOTT and FORD in this example.

The top of the organization chart is KING so there is one root node in this tree. The START WITH mgr IS NULL clause selects only KING as the initial root node.

The complete SELECT command is shown below.

```
SELECT ename, empno, mgr
FROM emp
START WITH mgr IS NULL
CONNECT BY PRIOR empno = mgr;
```

The rows in the query output traverse each branch from the root to leaf moving in a top-to-bottom, left-to-right order. Below is the output from this query.

KING 7839 JONES 7566 7839 SCOTT 7788 7566 7788 7566 ADAMS 7876 7788 FORD 7902 7566 SMITH 7369 7902 BLAKE 7698 7839 ALLEN 7499 7698 WARD 7521 7698 MARTIN 7654 7698 TURNER 7844 7698 JAMES 7900 7698 CLARK 7782 7839 MILLER 7934 7782	ename I	empno I mgr		
SMITH 7369 7902 BLAKE 7698 7839 ALLEN 7499 7698 WARD 7521 7698 MARTIN 7654 7698 TURNER 7844 7698 JAMES 7900 7698 CLARK 7782 7839	KING JONES SCOTT ADAMS	7839 7566 7839 7788 7566 7876 7788		
TURNER 7844 7698 JAMES 7900 7698 CLARK 7782 7839	SMITH BLAKE ALLEN WARD	7369 7902 7698 7839 7499 7698 7521 7698		
(14 rows)	TURNER I JAMES I CLARK I MILLER I	7844 7698 7900 7698 7782 7839		

6.3.5.4 Node Level

LEVEL is a pseudo-column that can be used wherever a column can appear in the SELECT command. For each row in the result set, LEVEL returns a non-zero integer value designating the depth in the hierarchy of the node represented by this row. The LEVEL for root nodes is 1. The LEVEL for direct children of root nodes is 2, and so on.

The following query is a modification of the previous query with the addition of the LEVEL pseudo-column. In addition, using the LEVEL value, the employee names are indented to further emphasize the depth in the hierarchy of each row.

```
SELECT LEVEL, LPAD (' ', 2 * (LEVEL - 1)) || ename "employee", empno, mgr
FROM emp START WITH mgr IS NULL
CONNECT BY PRIOR empno = mgr;
```

The output from this query follows.

level	I	employee		empno	I	mgr
	+-		+-		+-	
1		KING		7839	1	
2		JONES		7566	1	7839
3		SCOTT		7788	1	7566
4		ADAMS		7876	1	7788
3		FORD		7902		7566
4	1	SMITH	1	7369	1	7902
2	1	BLAKE	1	7698	1	7839
3	1	ALLEN	1	7499	1	7698
3	1	WARD	1	7521	1	7698
3	1	MARTIN	1	7654	1	7698
3	1	TURNER	1	7844	1	7698
3	1	JAMES	1	7900	1	7698
2	1	CLARK	1	7782	1	7839
3	1	MILLER	1	7934	I	7782
(14 rd	ws	s)				

Nodes that share a common parent and are at the same level are called *siblings*. For example in the above output, employees ALLEN, WARD, MARTIN, TURNER, and JAMES are siblings since they are all at level three with parent, BLAKE. JONES, BLAKE, and CLARK are siblings since they are at level two and KING is their common parent.

6.3.5.5 Ordering the Siblings

The result set can be ordered so the siblings appear in ascending or descending order by selected column value(s) using the ORDER SIBLINGS BY clause. This is a special case of the ORDER BY clause that can be used only with hierarchical queries.

The previous query is further modified with the addition of ORDER SIBLINGS BY ename ASC.

```
SELECT LEVEL, LPAD (' ', 2 * (LEVEL - 1)) || ename "employee", empno, mgr
FROM emp START WITH mgr IS NULL
CONNECT BY PRIOR empno = mgr
ORDER SIBLINGS BY ename ASC;
```

The output from the prior query is now modified so the siblings appear in ascending order by name. Siblings BLAKE, CLARK, and JONES are now alphabetically arranged under KING. Siblings ALLEN, JAMES, MARTIN, TURNER, and WARD are alphabetically arranged under BLAKE, and so on.

leve	11.	employee	I	empno	I	mgr
1	+ 	 KTNG	 	7839	. – - I	+
2	i	BLAKE	i	7698	i	7839
3	- 1	ALLEN	I	7499	I	7698
3	- 1	JAMES	1	7900	1	7698
3	- 1	MARTIN	I	7654	I	7698
3	- 1	TURNER	1	7844	I	7698
3		WARD	1	7521		7698
2		CLARK	1	7782		7839
3		MILLER	1	7934		7782
2		JONES	1	7566		7839
3		FORD	1	7902		7566
4		SMITH	1	7369		7902
3		SC0TT	1	7788		7566
4		ADAMS	1	7876		7788
(14	rows)				

This final example adds the WHERE clause and starts with three root nodes. After the node tree is constructed, the WHERE clause filters out rows in the tree to form the result set.

```
SELECT LEVEL, LPAD (' ', 2 * (LEVEL - 1)) || ename "employee", empno, mgr
FROM emp WHERE mgr IN (7839, 7782, 7902, 7788)
START WITH ename IN ('BLAKE','CLARK','JONES')
CONNECT BY PRIOR empno = mgr
ORDER SIBLINGS BY ename ASC;
```

The output from the query shows three root nodes (level one) - BLAKE, CLARK, and JONES. In addition, rows that do not satisfy the WHERE clause have been eliminated from the output.

```
level | employee | empno | mgr
------
               -
                  7698 | 7839
 1
   I BLAKE
 1
     I CLARK
                  7782 | 7839
     - 1
        MILLER
                  7934 | 7782
     I JONES
 1
                  7566 | 7839
                ı
                  7369 | 7902
 3
     SMITH |
 3
     ADAMS | 7876 | 7788
(6 rows)
```

6.3.5.6 Retrieving the Root Node with CONNECT BY ROOT

CONNECT_BY_ROOT is a unary operator that can be used to qualify a column in order to return the column's value of the row considered to be the root node in relation to the current row.

Note

A *unary operator* operates on a single operand, which in the case of CONNECT_BY_ROOT , is the column name following the CONNECT_BY_ROOT keyword.

In the context of the SELECT list, the CONNECT_BY_ROOT operator is shown by the following.

```
SELECT [...,] CONNECT_BY_ROOT <column> [, ...]
FROM <table_expression> ...
```

The following are some points to note about the CONNECT_BY_ROOT operator.

- The CONNECT_BY_ROOT operator can be used in the SELECT list, the WHERE clause, the GROUP BY clause, the HAVING clause, the ORDER BY clause, and the ORDER SIBLINGS BY clause as long as the SELECT command is for a hierarchical query.
- The CONNECT_BY_ROOT operator cannot be used in the CONNECT BY clause or the START WITH clause of the hierarchical query.
- It is possible to apply CONNECT_BY_ROOT to an expression involving a column, but to do so, the expression must be enclosed within parentheses.

The following query shows the use of the CONNECT_BY_ROOT operator to return the employee number and employee name of the root node for each employee listed in the result set based on trees starting with employees BLAKE, CLARK, and JONES.

```
SELECT LEVEL, LPAD (' ', 2 * (LEVEL - 1)) || ename "employee", empno, mgr, CONNECT_BY_ROOT empno "mgr empno", CONNECT_BY_ROOT ename "mgr ename" FROM emp START WITH ename IN ('BLAKE','CLARK','JONES') CONNECT BY PRIOR empno = mgr ORDER SIBLINGS BY ename ASC;
```

Note that the output from the query shows that all of the root nodes in columns mgr empno and mgr ename are one of the employees, BLAKE, CLARK, or JONES, listed in the START WITH clause.

```
level | employee | empno | mgr | mgr empno | mgr ename
-----+----+-----+-----
 1
      I BLAKE
                     7698 | 7839 |
                                        7698 | BLAKE
 2
      Ι
          ALLEN
                  Ι
                     7499 | 7698 |
                                        7698 | BLAKE
 2
                  Т
                     7900 | 7698 |
                                        7698 | BLAKE
      Ι
          JAMES
 2
      1
          MARTIN
                 7654 | 7698 |
                                        7698 | BLAKE
 2
          TURNER
                     7844 | 7698 |
                                        7698 | BLAKE
      1
 2
         WARD
                     7521 | 7698 |
                                        7698 | BLAKE
     1
                     7782 | 7839 |
                                        7782 | CLARK
     I CLARK
 2
     MILLER
                     7934 | 7782 |
                                        7782 | CLARK
 1
                     7566 | 7839
                                        7566 I
     I JONES
                                               JONES
 2
     1
          FORD
                  ı
                     7902 | 7566 |
                                        7566 | JONES
                                        7566 | JONES
 3
      1
                     7369 | 7902 |
            SMITH I
 2
                     7788 | 7566 |
      1
          SCOTT
                                        7566 | JONES
 3
      ADAMS I
                     7876 | 7788 |
                                        7566 | JONES
(13 rows)
```

The following is a similar query, but producing only one tree starting with the single, top-level, employee where the mgr column is null.

```
SELECT LEVEL, LPAD (' ', 2 * (LEVEL - 1)) || ename "employee", empno, mgr,
```

```
CONNECT_BY_ROOT empno "mgr empno",
CONNECT_BY_ROOT ename "mgr ename"
FROM emp START WITH mgr IS NULL
CONNECT BY PRIOR empno = mgr
ORDER SIBLINGS BY ename ASC;
```

In the following output, all of the root nodes in columns mgr empno and mgr ename indicate KING as the root for this particular query.

					-		_			mgr ename
· ·	 ING	 	 7839		+	 	+			+ KING
2 I	BLAKE		7698		7839	-		7839	1	KING
3 l	ALLEN	1	7499		7698	-		7839	1	KING
3 l	JAMES	1	7900		7698	-		7839	1	KING
3 l	MARTIN	1	7654		7698	-		7839	1	KING
3 l	TURNER	1	7844		7698	-		7839	1	KING
3 l	WARD	1	7521		7698	-		7839	1	KING
2 l	CLARK	1	7782		7839	-		7839	1	KING
3 l	MILLER	1	7934		7782	-		7839	1	KING
2 l	JONES	1	7566		7839	-		7839	1	KING
3 l	FORD	1	7902		7566	-		7839	1	KING
4	SMITH		7369		7902	-		7839	1	KING
3 l	SC0TT		7788		7566	-		7839	1	KING
4	ADAMS		7876	1	7788			7839		KING
(14 rows)										

By contrast, the following example omits the START WITH clause thereby resulting in fourteen trees.

```
SELECT LEVEL, LPAD (' ', 2 * (LEVEL - 1)) || ename "employee", empno, mgr,
CONNECT_BY_ROOT empno "mgr empno",
CONNECT_BY_ROOT ename "mgr ename"
FROM emp
CONNECT BY PRIOR empno = mgr
ORDER SIBLINGS BY ename ASC;
```

The following is the output from the query. Each node appears at least once as a root node under the mgr empno and mgr ename columns since even the leaf nodes form the top of their own trees.

level	employee I	empno	l mgr	l mgr	empno	Ι.	mgr ename
1 I	ADAMS I		-+ 7788		7876		ADAMS
1	ALLEN I	7499	7698	I	7499	ı	ALLEN
1	BLAKE I	7698	l 7839	1	7698		BLAKE
2	ALLEN I	7499	7698	1	7698		BLAKE
2	JAMES I	7900	7698	1	7698		BLAKE
2	MARTIN I	7654	7698	1	7698		BLAKE
2	TURNER I	7844	l 7698	1	7698	1	BLAKE
2	WARD I	7521	7698	1	7698		BLAKE
1 I	CLARK I	7782	l 7839	1	7782		CLARK
2	MILLER	7934	7782	1	7782		CLARK
1	FORD I	7902	7566	1	7902		FORD
2	SMITH I	7369	7902	1	7902	1	FORD
1	JAMES I	7900	l 7698	1	7900	1	JAMES
1	JONES I	7566	l 7839	1	7566		JONES
2	FORD I	7902	7566	1	7566	1	JONES
3 l	SMITH I	7369	7902	1	7566		JONES
2	SCOTT I	7788	7566	1	7566		JONES
3 l	adams i	7876	7788	1	7566	1	JONES
1 I	KING I	7839		1	7839		KING
2	BLAKE I	7698	l 7839	1	7839		KING
3 l	ALLEN I	7499	7698	1	7839	1	KING
3 l	JAMES I	7900	7698	I	7839	I	KING

```
7654 | 7698 |
    3 I
            MARTIN |
                                           7839 | KING
    3 I
                       7844 | 7698 |
                                           7839 | KING
            TURNER I
    3 I
            WARD
                       7521 | 7698 |
                                           7839 | KING
                    2 |
          CLARK
                       7782 | 7839 |
                                           7839 | KING
                    7839 | KING
    3 |
            MILLER
                       7934 | 7782 |
                    2 |
          JONES
                    7566 | 7839 |
                                           7839 | KING
    3 I
            FORD
                       7902 | 7566 |
                                           7839 | KING
                    |
    4 |
              SMITH I
                       7369 | 7902 |
                                           7839 | KING
    3 I
                       7788 | 7566 |
                                           7839 | KING
            SC0TT
                    - 1
                       7876 | 7788 |
                                           7839 | KING
    4 |
              ADAMS I
                       7654 | 7698 |
                                           7654 | MARTIN
    1 | MARTIN
                    -
    1 | MILLER
                    Т
                       7934 | 7782 |
                                           7934 | MILLER
                       7788 | 7566 |
                                           7788 | SCOTT
    1 | SCOTT
                    7788 | SCOTT
                       7876 | 7788 |
    2 |
          ADAMS
                    7369 | SMITH
    1 | SMITH
                    Т
                       7369 | 7902 |
    1 | TURNER
                    Т
                       7844 | 7698 |
                                           7844 | TURNER
    1 | WARD
                    7521 | 7698 |
                                           7521 | WARD
(39 rows)
```

The following illustrates the unary operator effect of CONNECT_BY_ROOT. As shown in this example, when applied to an expression that is not enclosed in parentheses, the CONNECT_BY_ROOT operator affects only the term, ename, immediately following it. The subsequent concatenation of II 'manages' II ename is not part of the CONNECT_BY_ROOT operation, hence the second occurrence of ename results in the value of the currently processed row while the first occurrence of ename results in the value from the root node.

```
SELECT LEVEL, LPAD (' ', 2 * (LEVEL - 1)) || ename "employee", empno, mgr, CONNECT_BY_ROOT ename || ' manages ' || ename "top mgr/employee" FROM emp START WITH ename IN ('BLAKE','CLARK','JONES') CONNECT BY PRIOR empno = mgr ORDER SIBLINGS BY ename ASC;
```

The following is the output from the query. Note the values produced under the top mgr/employee column.

```
level | employee | empno | mgr |
                                  top mgr/employee
1 | BLAKE |
                   7698 | 7839 | BLAKE manages BLAKE
   2 |
         ALLEN |
                   7499 | 7698 | BLAKE manages ALLEN
   2 |
         JAMES
                7900 | 7698 | BLAKE manages JAMES
   2 |
         MARTIN |
                   7654 | 7698 | BLAKE manages MARTIN
   2 |
         TURNER
               - 1
                   7844 | 7698 | BLAKE manages TURNER
   2 |
         WARD
                - 1
                   7521 | 7698 | BLAKE manages WARD
   1 | CLARK
                -
                  7782 | 7839 | CLARK manages CLARK
         MILLER |
                   7934 | 7782 | CLARK manages MILLER
   2 |
   1 | JONES
                   7566 | 7839 | JONES manages JONES
                1
                   7902 | 7566 | JONES manages FORD
   2 I
         FORD
                1
   3 I
           SMITH |
                   7369 | 7902 | JONES manages SMITH
   2 |
         SC0TT
               7788 | 7566 | JONES manages SCOTT
   3 I
           ADAMS | 7876 | 7788 | JONES manages ADAMS
(13 rows)
```

The following example uses the CONNECT_BY_ROOT operator on an expression enclosed in parentheses.

```
SELECT LEVEL, LPAD (' ', 2 * (LEVEL - 1)) || ename "employee", empno, mgr,
CONNECT_BY_ROOT ('Manager ' || ename || ' is emp # ' || empno)
"top mgr/empno"
FROM emp
START WITH ename IN ('BLAKE','CLARK','JONES')
CONNECT BY PRIOR empno = mgr
ORDER SIBLINGS BY ename ASC;
```

The following is the output of the query. Note that the values of both ename and empno are affected by

the CONNECT_BY_ROOT operator and as a result, return the values from the root node as shown under the top mgr/empno column.

level employee		•		•		top mgr/empno
•		7698 7499 7900 7654 7844	 	7839 7698 7698 7698 7698 7698	 	Hanager BLAKE is emp # 7698 Manager BLAKE is emp # 7698 Manager BLAKE is emp # 7698 Manager BLAKE is emp # 7698 Manager BLAKE is emp # 7698 Manager BLAKE is emp # 7698 Manager BLAKE is emp # 7698
1 CLARK 2 MILLER 1 JONES 2 FORD 3 SMITH 2 SCOTT 3 ADAMS	 	7934 7566 7902 7369 7788	 	7782 7839 7566 7902 7566	 	Manager CLARK is emp # 7782 Manager CLARK is emp # 7782 Manager JONES is emp # 7566 Manager JONES is emp # 7566 Manager JONES is emp # 7566 Manager JONES is emp # 7566 Manager JONES is emp # 7566
(13 rows)						

6.3.5.7 Retrieving a Path with SYS_CONNECT_BY_PATH

SYS_CONNECT_BY_PATH is a function that works within a hierarchical query to retrieve the column values of a specified column that occur between the current node and the root node. The signature of the function is:

```
SYS_CONNECT_BY_PATH (<column>, <delimiter>)
```

The function takes two arguments:

column is the name of a column that resides within a table specified in the hierarchical query that is calling the function.

delimiter is the varchar value that separates each entry in the specified column.

The following example returns a list of employee names, and their managers; if the manager has a manager, that name is appended to the result:

```
edb=# SELECT level, ename , SYS_CONNECT_BY_PATH(ename, '/') managers
    FROM emp
    CONNECT BY PRIOR empno = mgr
    START WITH mgr IS NULL
    ORDER BY level, ename, managers;
```

lev	el	I	ename	I	managers
		+-		-+-	
	1	ı	KING	ı	/KING
	2		BLAKE		/KING/BLAKE
	2	1	CLARK		/KING/CLARK
	2	1	JONES	1	/KING/JONES
	3	1	ALLEN	1	/KING/BLAKE/ALLEN
	3	1	FORD		/KING/JONES/FORD
	3	1	JAMES	1	/KING/BLAKE/JAMES
	3	1	MARTIN	1	/KING/BLAKE/MARTIN
	3	1	MILLER	1	/KING/CLARK/MILLER
	3	1	SCOTT	1	/KING/JONES/SCOTT
	3	1	TURNER	1	/KING/BLAKE/TURNER
	3	1	WARD	1	/KING/BLAKE/WARD
	4	1	ADAMS		/KING/JONES/SCOTT/ADAMS
	4	1	SMITH	1	/KING/JONES/FORD/SMITH
(14	row	ıs))		

Within the result set:

- The level column displays the number of levels that the query returned.
- The ename column displays the employee name.
- The managers column contains the hierarchical list of managers.

The Advanced Server implementation of SYS_CONNECT_BY_PATH does not support use of:

- SYS_CONNECT_BY_PATH inside CONNECT_BY_PATH
- SYS_CONNECT_BY_PATH inside SYS_CONNECT_BY_PATH

6.3.6.0 Multidimensional Analysis

Multidimensional analysis refers to the process commonly used in data warehousing applications of examining data using various combinations of dimensions. *Dimensions* are categories used to classify data such as time, geography, a company's departments, product lines, and so forth. The results associated with a particular set of dimensions are called *facts*. Facts are typically figures associated with product sales, profits, volumes, counts, etc.

In order to obtain these facts according to a set of dimensions in a relational database system, SQL aggregation is typically used. *SQL aggregation* basically means data is grouped according to certain criteria (dimensions) and the result set consists of aggregates of facts such as counts, sums, and averages of the data in each group.

The GROUP BY clause of the SQL SELECT command supports the following extensions that simplify the process of producing aggregate results.

- ROLLUP extension
- CUBE extension
- GROUPING SETS extension

In addition, the GROUPING function and the GROUPING_ID function can be used in the SELECT list or the HAVING clause to aid with the interpretation of the results when these extensions are used.

Note

The sample dept and emp tables are used extensively in this discussion to provide usage examples. The following changes were applied to these tables to provide more informative results.

```
UPDATE dept SET loc = 'BOSTON' WHERE deptno = 20;
INSERT INTO emp (empno,ename,job,deptno) VALUES (9001,'SMITH','CLERK',40);
INSERT INTO emp (empno,ename,job,deptno) VALUES (9002,'JONES','ANALYST',40);
INSERT INTO emp (empno,ename,job,deptno) VALUES (9003,'ROGERS','MANAGER',40);
```

The following rows from a join of the emp and dept tables are used:

```
SELECT loc, dname, job, empno FROM emp e, dept d
WHERE e.deptno = d.deptno
ORDER BY 1, 2, 3, 4;
```

loc	1	dname	I	job	1	empno
BOSTON	-+- 	OPERATIONS	-+· 	ANALYST	-+-	9002
BOSTON	- [OPERATIONS	1	CLERK	-	9001
BOSTON	- [OPERATIONS	1	MANAGER		9003
BOSTON	-	RESEARCH	-	ANALYST		7788
BOSTON	-	RESEARCH	-	ANALYST		7902
BOSTON	-	RESEARCH	-	CLERK		7369
BOSTON	- 1	RESEARCH	-	CLERK		7876
BOSTON	- 1	RESEARCH	-	MANAGER		7566
CHICAGO	- 1	SALES	-	CLERK		7900
CHICAGO	- 1	SALES	-	MANAGER		7698
CHICAGO	- 1	SALES	-	SALESMAN		7499
CHICAGO	- [SALES	1	SALESMAN		7521
CHICAGO	-	SALES	1	SALESMAN		7654

```
CHICAGO | SALES | SALESMAN | 7844

NEW YORK | ACCOUNTING | CLERK | 7934

NEW YORK | ACCOUNTING | MANAGER | 7782

NEW YORK | ACCOUNTING | PRESIDENT | 7839

(17 rows)
```

The loc, dname, and job columns are used for the dimensions of the SQL aggregations used in the examples. The resulting facts of the aggregations are the number of employees obtained by using the COUNT(*) function.

A basic query grouping the loc, dname, and job columns is given by the following.

```
SELECT loc, dname, job, COUNT(*) AS "employees" FROM emp e, dept d
WHERE e.deptno = d.deptno
GROUP BY loc, dname, job
ORDER BY 1, 2, 3;
```

The rows of this result set using the basic GROUP BY clause without extensions are referred to as the base aggregate rows.

loc	Ι.	dname I		job	I	employees	
BOSTON	 	OPERATIONS	 	ANALYST		+	1
BOSTON	I	OPERATIONS	1	CLERK		1	1
BOSTON	- 1	OPERATIONS		MANAGER		1	1
BOSTON	- 1	RESEARCH	I	ANALYST		1	2
BOSTON	- 1	RESEARCH	ı	CLERK		1	2
BOSTON	- 1	RESEARCH	1	MANAGER		1	1
CHICAGO	- 1	SALES	1	CLERK		1	1
CHICAGO	- 1	SALES	1	MANAGER		1	1
CHICAGO	-	SALES		SALESMAN		1	4
NEW YORK	ΚI	ACCOUNTING		CLERK		1	1
NEW YORK	ΚI	ACCOUNTING	1	MANAGER		1	1
NEW YORK	ΚI	ACCOUNTING	1	PRESIDEN	Τ	1	1
(12 rows	s)						

The ROLLUP and CUBE extensions add to the base aggregate rows by providing additional levels of subtotals to the result set.

The GROUPING SETS extension provides the ability to combine different types of groupings into a single result set.

The GROUPING and GROUPING_ID functions aid in the interpretation of the result set.

The additions provided by these extensions are discussed in more detail in the subsequent sections.

6.3.6.1 ROLLUP Extension

The ROLLUP extension produces a hierarchical set of groups with subtotals for each hierarchical group as well as a grand total. The order of the hierarchy is determined by the order of the expressions given in the ROLLUP expression list. The top of the hierarchy is the leftmost item in the list. Each successive item proceeding to the right moves down the hierarchy with the rightmost item being the lowest level.

The syntax for a single ROLLUP is as follows:

```
ROLLUP ( { <expr_1> | ( <expr_1a> [, <expr_1b> ] ...) }
  [, <expr_2> | ( <expr_2a> [, <expr_2b> ] ...) ] ...)
```

Each expr is an expression that determines the grouping of the result set. If enclosed within parenthesis as (expr_1a, expr_1b, ...) then the combination of values returned by expr_1a and expr_1b defines a single grouping level of the hierarchy.

The base level of aggregates returned in the result set is for each unique combination of values returned by the expression list.

In addition, a subtotal is returned for the first item in the list ($expr_1$ or the combination of ($expr_1$, ...), whichever is specified) for each unique value. A subtotal is returned for the second item in the list ($expr_2$ or the combination of ($expr_2$, $expr_2$, ...), whichever is specified) for each unique value, within each grouping of the first item and so on. Finally a grand total is returned for the entire result set.

For the subtotal rows, null is returned for the items across which the subtotal is taken.

The ROLLUP extension specified within the context of the GROUP BY clause is shown by the following:

```
SELECT <select_list> FROM ...
GROUP BY [...,] ROLLUP ( <expression_list> ) [, ...]
```

The items specified in select_list must also appear in the ROLLUP expression_list; or they must be aggregate functions such as COUNT, SUM, AVG, MIN, or MAX; or they must be constants or functions whose return values are independent of the individual rows in the group (for example, the SYSDATE function).

The GROUP BY clause may specify multiple ROLLUP extensions as well as multiple occurrences of other GROUP BY extensions and individual expressions.

The ORDER BY clause should be used if you want the output to display in a hierarchical or other meaningful structure. There is no guarantee on the order of the result set if no ORDER BY clause is specified.

The number of grouping levels or totals is n + 1 where n represents the number of items in the expression list. A parenthesized list counts as one item.

The following query produces a rollup based on a hierarchy of columns loc, dname, then job.

```
SELECT loc, dname, job, COUNT(*) AS "employees" FROM emp e, dept d WHERE e.deptno = d.deptno GROUP BY ROLLUP (loc, dname, job) ORDER BY 1, 2, 3;
```

The following is the result of the query. There is a count of the number of employees for each unique combination of loc, dname, and job, as well as subtotals for each unique combination of loc and dname, for each unique value of loc, and a grand total displayed on the last line.

loc	1	dname		job	1	employees
LOC BOSTON BOSTON BOSTON BOSTON BOSTON BOSTON BOSTON BOSTON CHICAGO CH		dname OPERATIONS OPERATIONS OPERATIONS OPERATIONS RESEARCH RESEARCH RESEARCH SALES SALES SALES SALES ACCOUNTING ACCOUNTING ACCOUNTING		job ANALYST CLERK MANAGER ANALYST CLERK MANAGER CLERK MANAGER SALESMAN CLERK MANAGER PRESIDENT		employees +
(20 rows)	i)		İ		i	17

The following query shows the effect of combining items in the ROLLUP list within parenthesis.

SELECT loc, dname, job, COUNT(*) AS "employees" FROM emp e, dept d

```
WHERE e.deptno = d.deptno
GROUP BY ROLLUP (loc, (dname, job))
ORDER BY 1, 2, 3;
```

In the output, note that there are no subtotals for loc and dname combinations as in the prior example.

loc	١	dname	I	job	I	employees
BOSTON	- – - I	OPERATIONS		+ ANALYST	 I	+ 1
BOSTON	i	OPERATIONS	i	CLERK	i	1
BOSTON	İ	OPERATIONS	İ	MANAGER	İ	1
BOSTON	1	RESEARCH	I	ANALYST	I	2
BOSTON	1	RESEARCH	I	CLERK	1	2
BOSTON	1	RESEARCH	I	MANAGER	1	1
BOSTON	1		I		1	8
CHICAGO	1	SALES	ı	CLERK	1	1
CHICAGO	1	SALES	ı	MANAGER	1	1
CHICAGO	1	SALES	ı	SALESMAN	1	4
CHICAGO	1				1	6
NEW YORK	1	ACCOUNTING		CLERK	1	1
NEW YORK		ACCOUNTING		MANAGER		1
NEW YORK	1	ACCOUNTING	1	PRESIDENT	1	1
NEW YORK	1		1		1	3
	1		1		1	17
(16 rows))					

If the first two columns in the ROLLUP list are enclosed in parenthesis, the subtotal levels differ as well.

```
SELECT loc, dname, job, COUNT(*) AS "employees" FROM emp e, dept d WHERE e.deptno = d.deptno GROUP BY ROLLUP ((loc, dname), job) ORDER BY 1, 2, 3;
```

Now there is a subtotal for each unique loc and dname combination, but none for unique values of loc

loc	I	dname	I	job	I	employees
BOSTON BOSTON BOSTON BOSTON BOSTON	 	OPERATIONS OPERATIONS OPERATIONS OPERATIONS RESEARCH		ANALYST CLERK MANAGER ANALYST	 	1 1 1 3 2
BOSTON BOSTON BOSTON		RESEARCH RESEARCH RESEARCH	-	CLERK MANAGER		2 1 5
CHICAGO CHICAGO CHICAGO		SALES SALES SALES		CLERK MANAGER SALESMAN		1 1 4
CHICAGO NEW YORK NEW YORK	 	SALES ACCOUNTING		CLERK MANAGER	 	6 1 1
NEW YORK NEW YORK	 	ACCOUNTING ACCOUNTING	 	PRESIDENT	 	1 3 17

6.3.6.2 CUBE Extension

The CUBE extension is similar to the ROLLUP extension. However, unlike ROLLUP, which produces groupings and results in a hierarchy based on a left to right listing of items in the ROLLUP expression list, a

CUBE produces groupings and subtotals based on every permutation of all items in the CUBE expression list. Thus, the result set contains more rows than a ROLLUP performed on the same expression list.

The syntax for a single CUBE is as follows:

```
CUBE ( { <expr_1> | ( <expr_1a> [, <expr_1b> ] ...) }
  [, <expr_2> | ( <expr_2a> [, <expr_2b> ] ...) ] ...)
```

Each expr is an expression that determines the grouping of the result set. If enclosed within parenthesis as (expr_1a, expr_1b, ...) then the combination of values returned by expr_1a and expr_1b defines a single group.

The base level of aggregates returned in the result set is for each unique combination of values returned by the expression list.

In addition, a subtotal is returned for the first item in the list ($expr_1$ or the combination of ($expr_1a$, $expr_1b$, ...), whichever is specified) for each unique value. A subtotal is returned for the second item in the list ($expr_2$ or the combination of ($expr_2a$, $expr_2b$, ...), whichever is specified) for each unique value. A subtotal is also returned for each unique combination of the first item and the second item. Similarly, if there is a third item, a subtotal is returned for each unique value of the third item, each unique value of the third item and first item combination, each unique value of the third item and second item combination, and each unique value of the third item, second item, and first item combination. Finally a grand total is returned for the entire result set.

For the subtotal rows, null is returned for the items across which the subtotal is taken.

The CUBE extension specified within the context of the GROUP BY clause is shown by the following:

```
SELECT <select_list> FROM ...
GROUP BY [...,] CUBE ( <expression_list> ) [, ...]
```

The items specified in select_list must also appear in the CUBE expression_list; or they must be aggregate functions such as COUNT, SUM, AVG, MIN, or MAX; or they must be constants or functions whose return values are independent of the individual rows in the group (for example, the SYSDATE function).

The GROUP BY clause may specify multiple CUBE extensions as well as multiple occurrences of other GROUP BY extensions and individual expressions.

The ORDER BY clause should be used if you want the output to display in a meaningful structure. There is no guarantee on the order of the result set if no ORDER BY clause is specified.

The number of grouping levels or totals is 2 raised to the power of *n* where *n* represents the number of items in the CUBE expression list. A parenthesized list counts as one item.

The following query produces a cube based on permutations of columns loc, dname, and job.

```
SELECT loc, dname, job, COUNT(*) AS "employees" FROM emp e, dept d WHERE e.deptno = d.deptno GROUP BY CUBE (loc, dname, job) ORDER BY 1, 2, 3;
```

The following is the result of the query. There is a count of the number of employees for each combination of loc, dname, and job, as well as subtotals for each combination of loc and dname, for each combination of loc and job, for each combination of dname and job, for each unique value of loc, for each unique value of dname, for each unique value of job, and a grand total displayed on the last line.

loc	l dname l job	employees
BOSTON	OPERATIONS ANALYS	•
BOSTON	OPERATIONS CLERK	1
BOSTON	I OPERATIONS I MANAGER	R I 1
BOSTON	OPERATIONS	l 3

BOSTON I BOSTON I BOSTON I BOSTON I	RESEARCH RESEARCH RESEARCH	I ANALYST I CLERK I MANAGER I	2 2 1 5
BOSTON I BOSTON I BOSTON I		ANALYST CLERK MANAGER 	5 3 3 2
CHICAGO CHICAGO CHICAGO CHICAGO	SALES SALES SALES	CLERK MANAGER SALESMAN 	1 1 4 6
CHICAGO CHICAGO CHICAGO		CLERK MANAGER SALESMAN 	1 1 4 6
NEW YORK I NEW YORK I NEW YORK I	ACCOUNTING ACCOUNTING ACCOUNTING	CLERK MANAGER PRESIDENT 	1 1 1 3
NEW YORK I NEW YORK I NEW YORK I		CLERK MANAGER PRESIDENT 	1 1 1 3 1
 	ACCOUNTING ACCOUNTING ACCOUNTING	CLERK MANAGER PRESIDENT 	1 1 3
 	OPERATIONS OPERATIONS OPERATIONS	ANALYST CLERK MANAGER 	1 1 1 3 2
 	RESEARCH RESEARCH RESEARCH	I ANALYST I CLERK I MANAGER	2 2 1 5
 	SALES SALES SALES SALES	CLERK MANAGER SALESMAN 	1 4 6
 		ANALYST CLERK MANAGER PRESIDENT SALESMAN	3 5 4 1
(50 rows)		I	l 17

The following query shows the effect of combining items in the CUBE list within parenthesis.

```
SELECT loc, dname, job, COUNT(*) AS "employees" FROM emp e, dept d WHERE e.deptno = d.deptno GROUP BY CUBE (loc, (dname, job)) ORDER BY 1, 2, 3;
```

In the output note that there are no subtotals for permutations involving loc and dname combinations, loc and job combinations, or for dname by itself, or for job by itself.

loc	1	difame	1	_		employees
BOSTON BOSTON	I	OPERATIONS OPERATIONS	I	ANALYST	 	1 1

```
| OPERATIONS | MANAGER
BOSTON
                                             1
         | RESEARCH | ANALYST
                                             2
BOSTON
                                             2
BOSTON
         | RESEARCH
                      I CLERK
BOSTON
         I RESEARCH
                      I MANAGER
                                             1
                                             8
BOSTON
CHICAGO
        l SALES
                        CLERK
                                             1
CHICAGO
        l SALES
                        MANAGER
                                             1
CHICAGO
        I SALES
                        SALESMAN
                                             4
                                             6
CHICAGO
NEW YORK | ACCOUNTING | CLERK
                                             1
NEW YORK | ACCOUNTING | MANAGER
                                             1
NEW YORK | ACCOUNTING | PRESIDENT |
                                             1
NEW YORK I
                                             3
                                             1
         | ACCOUNTING | CLERK
         | ACCOUNTING | MANAGER
                                             1
         | ACCOUNTING | PRESIDENT |
                                             1
         | OPERATIONS | ANALYST
                                             1
         | OPERATIONS | CLERK
                                             1
         | OPERATIONS | MANAGER
                                             1
                                             2
         I RESEARCH
                      I ANALYST
                                             2
         I RESEARCH
                      I CLERK
         I RESEARCH
                      I MANAGER
                                             1
         I SALES
                      I CLERK
                                             1
         I SALES
                                             1
                      I MANAGER
         I SALES
                      I SALESMAN
                                             4
                                            17
```

(28 rows)

The following query shows another variation whereby the first expression is specified outside of the extension.

```
SELECT loc, dname, job, COUNT(*) AS "employees" FROM emp e, dept d WHERE e.deptno = d.deptno GROUP BY loc, CUBE (dname, job) ORDER BY 1, 2, 3;
```

In this output, the permutations are performed for dname and job within each grouping of loc .

loc		dname		job	 	employees
BOSTON		OPERATIONS		ANALYST		1
BOSTON	1	OPERATIONS	1	CLERK	-	1
BOSTON		OPERATIONS		MANAGER	- 1	1
BOSTON		OPERATIONS			- 1	3
BOSTON		RESEARCH		ANALYST	- 1	2
BOSTON	1	RESEARCH	ı	CLERK	1	2
BOSTON	1	RESEARCH	ı	MANAGER	1	1
BOSTON	1	RESEARCH	ı		1	5
BOSTON	1		ı	ANALYST	1	3
BOSTON	1		ı	CLERK	1	3
BOSTON	I		ı	MANAGER	I	2
BOSTON	I		ı		I	8
CHICAGO		SALES		CLERK	I	1
CHICAGO		SALES		MANAGER	I	1
CHICAGO		SALES		SALESMAN	I	4
CHICAGO	I	SALES	ı		I	6
CHICAGO	I		ı	CLERK	I	1
CHICAGO	I		ı	MANAGER	I	1
CHICAGO	I		ı	SALESMAN	I	4
CHICAGO	I		ı		I	6
NEW YORK		ACCOUNTING		CLERK	I	1
NEW YORK	I	ACCOUNTING	I	MANAGER	I	1

NEW YORK	ACCOUNTING	PRESIDENT	I	1
NEW YORK	<pre>ACCOUNTING</pre>	1	1	3
NEW YORK		l CLERK	1	1
NEW YORK		l manager	1	1
NEW YORK		PRESIDENT	1	1
NEW YORK		1	1	3
(28 rows	(;			
•				

6.3.6.3 GROUPING SETS Extension

The use of the GROUPING SETS extension within the GROUP BY clause provides a means to produce one result set that is actually the concatenation of multiple results sets based upon different groupings. In other words, a UNION ALL operation is performed combining the result sets of multiple groupings into one result set.

Note that a UNION ALL operation, and therefore the GROUPING SETS extension, do not eliminate duplicate rows from the result sets that are being combined together.

The syntax for a single GROUPING SETS extension is as follows:

```
GROUPING SETS (
     { <expr_1> | ( <expr_1a> [, <expr_1b> ] ...) |
          ROLLUP ( <expr_list> ) | CUBE ( <expr_list> )
     } [, ...] )
```

A GROUPING SETS extension can contain any combination of one or more comma-separated expressions, lists of expressions enclosed within parenthesis, ROLLUP extensions, and CUBE extensions.

The GROUPING SETS extension is specified within the context of the GROUP BY clause as shown by the following:

```
SELECT <select_list> FROM ...
GROUP BY [...,] GROUPING SETS ( <expression_list> ) [, ...]
```

The items specified in select_list must also appear in the GROUPING SETS expression_list; or they must be aggregate functions such as COUNT, SUM, AVG, MIN, or MAX; or they must be constants or functions whose return values are independent of the individual rows in the group (for example, the SYSDATE function).

The GROUP BY clause may specify multiple GROUPING SETS extensions as well as multiple occurrences of other GROUP BY extensions and individual expressions.

The ORDER BY clause should be used if you want the output to display in a meaningful structure. There is no guarantee on the order of the result set if no ORDER BY clause is specified.

The following query produces a union of groups given by columns loc, dname, and job.

```
SELECT loc, dname, job, COUNT(*) AS "employees" FROM emp e, dept d WHERE e.deptno = d.deptno GROUP BY GROUPING SETS (loc, dname, job) ORDER BY 1, 2, 3;
```

The result is as follows:

loc	I	dname	Ι.	job I	employees
BOSTON CHICAGO	 		 	 	8 6
NEW YORK			1		3
		ACCOUNTING	1	1	3
		OPERATIONS	1	1	3
		RESEARCH	1	1	5

This is equivalent to the following query, which employs the use of the UNION ALL operator.

SELECT loc AS "loc", NULL AS "dname", NULL AS "job", COUNT(*) AS "employees" FROM emp e, dept d

WHERE e.deptno = d.deptno

GROUP BY loc

UNION ALL

SELECT NULL, dname, NULL, COUNT(*) AS "employees" FROM emp e, dept d

WHERE e.deptno = d.deptno

GROUP BY dname

UNION ALL

SELECT NULL, NULL, job, COUNT(*) AS "employees" FROM emp e, dept d

WHERE e.deptno = d.deptno

GROUP BY job

ORDER BY 1, 2, 3;

The output from the UNION ALL query is the same as the GROUPING SETS output.

loc	I	dname	I	job	I	employees
BOSTON CHICAGO NEW YORK		ACCOUNTING OPERATIONS RESEARCH SALES		ANALYST CLERK MANAGER PRESIDENT SALESMAN		+
(12 rows))					

The following example shows how various types of GROUP BY extensions can be used together within a GROUPING SETS expression list.

SELECT loc, dname, job, COUNT(*) AS "employees" FROM emp e, dept d WHERE e.deptno = d.deptno GROUP BY GROUPING SETS (loc, ROLLUP (dname, job), CUBE (job, loc)) ORDER BY 1, 2, 3;

The following is the output from this query.

loc	1	dname	I	job	I	employees
BOSTON BOSTON	+- 		 	ANALYST CLERK	 	3 3
BOSTON			I	MANAGER	-	2
BOSTON			I		-	8
BOSTON	1		- 1		- 1	8
CHICAGO	1		- 1	CLERK	- 1	1
CHICAGO	1		- 1	MANAGER	- 1	1
CHICAGO	1		- 1	SALESMAN	- 1	4
CHICAGO	1		- 1		- 1	6
CHICAGO	I		I		I	6

```
NEW YORK I
                       I CLERK
                                               1
NEW YORK I
                       I MANAGER
                                               1
NEW YORK I
                       | PRESIDENT |
                                               1
NEW YORK I
                                               3
NEW YORK I
                                               3
          | ACCOUNTING | CLERK
                                               1
          | ACCOUNTING | MANAGER
                                               1
          | ACCOUNTING | PRESIDENT |
                                               1
                                               3
          | ACCOUNTING |
          | OPERATIONS | ANALYST
                                               1
          | OPERATIONS | CLERK
                                               1
          | OPERATIONS | MANAGER
                                               1
                                               3
          | OPERATIONS |
                                               2
          I RESEARCH
                       I ANALYST
                                               2
          I RESEARCH
                       I CLERK
                       I MANAGER
                                               1
          I RESEARCH
                                               5
          I RESEARCH
                                               1
          I SALES
                       I CLERK
                       I MANAGER
          I SALES
                                               1
                       I SALESMAN
                                               4
          I SALES
                                               6
          I SALES
                                               3
                       I ANALYST
                                               5
                       I CLERK
                                               4
                       I MANAGER
                                               1
                       | PRESIDENT |
                       I SALESMAN
                                               4
                                              17
                                              17
                       |
```

(38 rows)

The output is basically a concatenation of the result sets that would be produced individually from GROUP BY loc, GROUP BY ROLLUP (dname, job), and GROUP BY CUBE (job, loc). These individual queries are shown by the following.

```
SELECT loc, NULL AS "dname", NULL AS "job", COUNT(*) AS "employees" FROM emp e, dept d
WHERE e.deptno = d.deptno
GROUP BY loc
ORDER BY 1;
```

The following is the result set from the GROUP BY loc clause.

loc	I	dname	I	job	I	employees
BOSTON CHICAGO	 		 		 	8 6
NEW YORK (3 rows)	İ		İ		İ	3

The following query uses the GROUP BY ROLLUP (dname, job) clause.

```
SELECT NULL AS "loc", dname, job, COUNT(*) AS "employees" FROM emp e, dept d WHERE e.deptno = d.deptno GROUP BY ROLLUP (dname, job) ORDER BY 2, 3;
```

The following is the result set from the GROUP BY ROLLUP (dname, job) clause.

loc			I	job		employee	
		+ ACCOUNTING		•	- - -	+	1
	I	ACCOUNTING	I	MANAGER	I		1
	1	ACCOUNTING	1	PRESIDENT	1		1
		ACCOUNTING	1		1		3

```
| OPERATIONS | ANALYST
                                         1
    | OPERATIONS | CLERK
                                         1
                               1
    | OPERATIONS | MANAGER
                                         1
    | OPERATIONS |
                                         3
                                         2
    I RESEARCH
                 | ANALYST
                                         2
    I RESEARCH
                 l CLERK
    I RESEARCH
                 I MANAGER
                                         1
    I RESEARCH
                                         5
                 - [
                                         1
    I SALES
                  I CLERK
                                         1
    I SALES
                  I MANAGER
    I SALES
                  I SALESMAN
                                         4
                               Ι
    I SALES
                  Ι
                                         6
                               Т
                  1
                               17
(17 rows)
```

The following query uses the GROUP BY CUBE (job, loc) clause.

```
SELECT loc, NULL AS "dname", job, COUNT(*) AS "employees" FROM emp e, dept d
WHERE e.deptno = d.deptno
GROUP BY CUBE (job, loc)
ORDER BY 1, 3;
```

The following is the result set from the GROUP BY CUBE (job, loc) clause.

loc	1	dname	I	job	I	employees
BOSTON BOSTON BOSTON CHICAGO CHICAGO CHICAGO CHICAGO NEW YORK NEW YORK NEW YORK NEW YORK	 	dname		job + ANALYST CLERK MANAGER CLERK MANAGER SALESMAN CLERK MANAGER PRESIDENT ANALYST CLERK MANAGER PRESIDENT ANALYST CLERK MANAGER PRESIDENT SALESMAN		employees +
(18 rows)			I		I	17

(18 rows)

If the previous three queries are combined with the UNION ALL operator, a concatenation of the three results sets is produced.

```
SELECT loc AS "loc", NULL AS "dname", NULL AS "job", COUNT(*) AS "employees"
FROM emp e, dept d
WHERE e.deptno = d.deptno
GROUP BY loc
UNION ALL
SELECT NULL, dname, job, count(*) AS "employees" FROM emp e, dept d
WHERE e.deptno = d.deptno
GROUP BY ROLLUP (dname, job)
UNION ALL
SELECT loc, NULL, job, count(*) AS "employees" FROM emp e, dept d
WHERE e.deptno = d.deptno
GROUP BY CUBE (job, loc)
ORDER BY 1, 2, 3;
```

The following is the output, which is the same as when the GROUP BY GROUPING SETS (loc, ROLLUP (dname, job), clause is used.

loc	l dname	l job	l employees
BOSTON BOSTON BOSTON	l	I ANALYST I CLERK I MANAGER	1 3 1 3 1 2
BOSTON BOSTON	 	 	l 8 l 8
CHICAGO CHICAGO		l CLERK I MANAGER	l 1 l 1
CHICAGO CHICAGO		l SALESMAN	l 4 l 6
CHICAGO	! 	 	l 6
NEW YORK	l	I CLERK I MANAGER	1 1
NEW YORK	 	l PRESIDENT I	l 1 l 3
	l I ACCOUNTING		3 1
	ACCOUNTING ACCOUNTING		1 I 1
		l I ANALYST	3 1
	OPERATIONS	l CLERK I MANAGER	l 1 l 1
	OPERATIONS	I ANALYST	I 3 I 2
	l RESEARCH	l CLERK	1 2
	l RESEARCH	MANAGER 	l 1 l 5
	l SALES	I CLERK I MANAGER	1 1
	. 5.1.	l SALESMAN I	l 4 l 6
	<u>-</u>	I ANALYST I CLERK	l 3 l 5
		l MANAGER l PRESIDENT	l 4 l 1
	 		4 17
(38 rows)	l	l	17
(30 10113)			

6.3.6.4 GROUPING Function

When using the ROLLUP, CUBE, or GROUPING SETS extensions to the GROUP BY clause, it may sometimes be difficult to differentiate between the various levels of subtotals generated by the extensions as well as the base aggregate rows in the result set. The GROUPING function provides a means of making this distinction.

The general syntax for use of the GROUPING function is shown by the following.

```
SELECT [ <expr> ...,] GROUPING( <col_expr> ) [, <expr> ] ...
FROM ...
GROUP BY [...,]
{ ROLLUP | CUBE | GROUPING SETS }( [...,] <col_expr>
   [, ...] ) [, ...]
```

The GROUPING function takes a single parameter that must be an expression of a dimension column specified in the expression list of a ROLLUP, CUBE, or GROUPING SETS extension of the GROUP BY clause.

The return value of the GROUPING function is either a 0 or 1. In the result set of a query, if the column expression specified in the GROUPING function is null because the row represents a subtotal over multiple values of that column then the GROUPING function returns a value of 1. If the row returns results based on a particular value of the column specified in the GROUPING function, then the GROUPING function returns a value of 0. In the latter case, the column can be null as well as non-null, but in any case, it is for a particular value of that column, not a subtotal across multiple values.

The following query shows how the return values of the GROUPING function correspond to the subtotal lines.

```
SELECT loc, dname, job, COUNT(*) AS "employees",
   GROUPING(loc) AS "gf_loc",
   GROUPING(dname) AS "gf_dname",
   GROUPING(job) AS "gf_job"
FROM emp e, dept d
WHERE e.deptno = d.deptno
GROUP BY ROLLUP (loc, dname, job)
ORDER BY 1, 2, 3;
```

In the three right-most columns displaying the output of the GROUPING functions, a value of 1 appears on a subtotal line wherever a subtotal is taken across values of the corresponding columns.

loc	I	dname	l job	l empl	oyees	I	gf_loc	١٠	gf_dname	Ι.	gf_job
BOSTON		OPERATIONS	-+ ANALYST		1		0		0		0
BOSTON	-	OPERATIONS	l CLERK	1	1		0		0		0
BOSTON	- 1	OPERATIONS	l manager	1	1		0		0	I	0
BOSTON	- 1	OPERATIONS		1	3		0		0	I	1
BOSTON	-	RESEARCH	l analyst	1	2		0		0		0
BOSTON	-	RESEARCH	l CLERK	1	2		0		0		0
BOSTON	-	RESEARCH	l manager	1	1		0		0	I	0
BOSTON	-	RESEARCH		1	5		0		0	I	1
BOSTON	-			1	8		0		1	I	1
CHICAGO	-	SALES	l CLERK	1	1		0		0	I	0
CHICAGO	-	SALES	l manager	1	1		0		0	I	0
CHICAGO	- 1	SALES	l SALESMAN	1	4		0		0	I	0
CHICAGO	- 1	SALES		1	6		0		0	I	1
CHICAGO	- 1			1	6		0		1	I	1
NEW YORK	-	ACCOUNTING	l CLERK	1	1		0		0	I	0
NEW YORK	1	ACCOUNTING	l manager	1	1		0		0		0
NEW YORK	1	ACCOUNTING	PRESIDENT	1	1		0		0		0
NEW YORK	1	ACCOUNTING		1	3		0		0		1
NEW YORK	1			1	3		0		1	I	1
	- [17		1	1	1	I	1
(20 rows)										

These indicators can be used as screening criteria for particular subtotals. For example, using the previous query, you can display only those subtotals for loc and dname combinations by using the GROUPING function in a HAVING clause.

```
SELECT loc, dname, job, COUNT(*) AS "employees",
   GROUPING(loc) AS "gf_loc",
   GROUPING(dname) AS "gf_dname",
   GROUPING(job) AS "gf_job"
FROM emp e, dept d
WHERE e.deptno = d.deptno
GROUP BY ROLLUP (loc, dname, job)
HAVING GROUPING(loc) = 0
   AND GROUPING(dname) = 0
   AND GROUPING(job) = 1
```

ORDER BY 1, 2;

This query produces the following result:

loc	1	dname +		_	employees		•		•		
BOSTON BOSTON	 	OPERATIONS RESEARCH	 	 	3 5	1	0	 	0	 	1 1
CHICAGO NEW YORK	•	SALES ACCOUNTING		I 	6 3	•	0 0	•	0 0	:	1
(4 rows)											

The GROUPING function can be used to distinguish a subtotal row from a base aggregate row or from certain subtotal rows where one of the items in the expression list returns null as a result of the column on which the expression is based being null for one or more rows in the table, as opposed to representing a subtotal over the column.

To illustrate this point, the following row is added to the emp table. This provides a row with a null value for the job column.

```
INSERT INTO emp (empno, ename, deptno) VALUES (9004, 'PETERS', 40);
```

The following query is issued using a reduced number of rows for clarity.

```
SELECT loc, job, COUNT(*) AS "employees",
   GROUPING(loc) AS "gf_loc",
   GROUPING(job) AS "gf_job"
FROM emp e, dept d
WHERE e.deptno = d.deptno AND loc = 'BOSTON'
GROUP BY CUBE (loc, job)
ORDER BY 1, 2;
```

Note that the output contains two rows containing BOSTON in the loc column and spaces in the job column (fourth and fifth entries in the table).

loc	I	job	I	employees			I	gf_job
BOSTON	 	+ ANALYST		3	 	+ 0	 	+0
BOSTON	1	CLERK	I	3	1	0	1	0
BOSTON	1	MANAGER	I	2	1	0	1	0
BOSTON	1		1	1	I	0	1	0
BOSTON	1		1	9	I	0	1	1
	1	ANALYST	1	3	I	1	1	0
	-	CLERK	1	3	1	1	1	0
	-	MANAGER	1	2	1	1	1	0
	-		1	1	1	1	1	0
	-		1	9	1	1	1	1
(10 rov	vs])						

The fifth row where the GROUPING function on the job column (gf_{job}) returns 1 indicates this is a subtotal over all jobs. Note that the row contains a subtotal value of 9 in the employees column.

The fourth row where the GROUPING function on the job column as well as on the loc column returns 0 indicates this is a base aggregate of all rows where loc is BOSTON and job is null, which is the row inserted for this example. The employees column contains 1, which is the count of the single such row inserted.

Also note that in the ninth row (next to last) the GROUPING function on the job column returns 0 while the GROUPING function on the loc column returns 1 indicating this is a subtotal over all locations where the job column is null, which again, is a count of the single row inserted for this example.

6.3.6.5 'GROUPING ID Function'

The GROUPING_ID function provides a simplification of the GROUPING function in order to determine the subtotal level of a row in the result set from a ROLLBACK, CUBE, or GROUPING SETS extension.

The GROUPING function takes only one column expression and returns an indication of whether or not a row is a subtotal over all values of the given column. Thus, multiple GROUPING functions may be required to interpret the level of subtotals for queries with multiple grouping columns.

The GROUPING_ID function accepts one or more column expressions that have been used in the ROLLBACK, CUBE, or GROUPING SETS extensions and returns a single integer that can be used to determine over which of these columns a subtotal has been aggregated.

The general syntax for use of the GROUPING_ID function is shown by the following.

```
SELECT [ <expr> ...,]
   GROUPING_ID( <col_expr_1> [, <col_expr_2> ] ... )
   [, <expr> ] ...
FROM ...
GROUP BY [...,]
   { ROLLUP | CUBE | GROUPING SETS }( [...,] <col_expr_1>
   [, <col_expr_2> ] [, ...] ) [, ...]
```

The GROUPING_ID function takes one or more parameters that must be expressions of dimension columns specified in the expression list of a ROLLUP, CUBE, or GROUPING SETS extension of the GROUP BY clause.

The GROUPING_ID function returns an integer value. This value corresponds to the base-10 interpretation of a bit vector consisting of the concatenated 1's and 0's that would be returned by a series of GROUPING functions specified in the same left-to-right order as the ordering of the parameters specified in the GROUPING_ID function.

The following query shows how the returned values of the GROUPING_ID function represented in column gid correspond to the values returned by two GROUPING functions on columns loc and dname.

```
SELECT loc, dname, COUNT(*) AS "employees",
   GROUPING(loc) AS "gf_loc", GROUPING(dname) AS "gf_dname",
   GROUPING_ID(loc, dname) AS "gid"
FROM emp e, dept d
WHERE e.deptno = d.deptno
GROUP BY CUBE (loc, dname)
ORDER BY 6, 1, 2;
```

In the following output, note the relationship between a bit vector consisting of the gf_{loc} value and gf_{loc} value compared to the integer given in gid.

loc	I	dname	I	employees	I	gf_loc	I	gf_dname	I	gio	t
BOSTON	 	OPERATIONS		3		0		0	1	+))
BOSTON	ı	RESEARCH	ı	5	ı	0	ı	0	ı	6)
CHICAGO		SALES		6		0		0	-	0)
NEW YORK		ACCOUNTING	-	3		0		0	1	6)
BOSTON	-		1	8	1	0	1	1		1	L
CHICAGO			-	6		0		1	1	1	L
NEW YORK	-		1	3	1	0	1	1	1	1	L
		ACCOUNTING	1	3	-	1		0	I	2	2
		OPERATIONS	-	3		1	-	0	-	2	2
		RESEARCH	1	5	-	1		0	I	2	2
		SALES	-	6		1	-	0	-	2	2
	-		1	17	1	1	-	1	1	3	3
(12 rows))										

The following table provides specific examples of the GROUPING_ID function calculations based on the GROUPING function return values for four rows of the output.

The following table summarizes how the GROUPING_ID function return values correspond to the grouping columns over which aggregation occurs.

So to display only those subtotals by dname , the following simplified query can be used with a HAVING clause based on the GROUPING_ID function.

```
SELECT loc, dname, COUNT(*) AS "employees",
   GROUPING(loc) AS "gf_loc", GROUPING(dname) AS "gf_dname",
   GROUPING_ID(loc, dname) AS "gid"
FROM emp e, dept d
WHERE e.deptno = d.deptno
GROUP BY CUBE (loc, dname)
HAVING GROUPING_ID(loc, dname) = 2
ORDER BY 6, 1, 2;
```

The following is the result of the query.

loc I	dname	I	employees	I	gf_loc	I	gf_dname gid
1	ACCOUNTING OPERATIONS RESEARCH SALES	 	3 3 5 6	į	1 1 1 1	i	0 2 0 2 0 2 0 2 0 2

6.4.0 Profile Management

Advanced Server allows a database superuser to create named *profiles*. Each profile defines rules for password management that augment password and md5 authentication. The rules in a profile can:

- · count failed login attempts
- · lock an account due to excessive failed login attempts
- · mark a password for expiration
- · define a grace period after a password expiration
- · define rules for password complexity
- · define rules that limit password re-use

A profile is a named set of password attributes that allow you to easily manage a group of roles that share comparable authentication requirements. If the password requirements change, you can modify the profile to have the new requirements applied to each user that is associated with that profile.

After creating the profile, you can associate the profile with one or more users. When a user connects to the server, the server enforces the profile that is associated with their login role. Profiles are shared by all databases within a cluster, but each cluster may have multiple profiles. A single user with access to multiple databases will use the same profile when connecting to each database within the cluster.

Advanced Server creates a profile named default that is associated with a new role when the role is created unless an alternate profile is specified. If you upgrade to Advanced Server from a previous server version, existing roles will automatically be assigned to the default profile. You cannot delete the default profile.

The default profile specifies the following attributes:

FAILED_LOGIN_ATTEMPTS	UNLIMITED
PASSWORD_LOCK_TIME	UNLIMITED
PASSWORD_LIFE_TIME	UNLIMITED
PASSWORD_GRACE_TIME	UNLIMITED
PASSWORD_REUSE_TIME	UNLIMITED

PASSWORD_REUSE_MAX	UNLIMITED		
PASSWORD_VERIFY_FUNCTION	NULL		
PASSWORD_ALLOW_HASHED	TRUE		

A database superuser can use the ALTER PROFILE command to modify the values specified by the default profile. For more information about modifying a profile, see Altering a Profile<altering_a_profile>

6.4.1.0 Creating a New Profile

Use the CREATE PROFILE command to create a new profile. The syntax is:

Include the LIMIT clause and one or more space-delimited parameter / value pairs to specify the rules enforced by Advanced Server.

Parameters:

profile_name specifies the name of the profile.

parameter specifies the attribute limited by the profile.

value specifies the parameter limit.

Advanced Server supports the value shown below for each parameter:

FAILED_LOGIN_ATTEMPTS specifies the number of failed login attempts that a user may make before the server locks the user out of their account for the length of time specified by PASSWORD_LOCK_TIME. Supported values are:

- An INTEGER value greater than 0.
- DEFAULT the value of FAILED_LOGIN_ATTEMPTS specified in the DEFAULT profile.
- UNLIMITED the connecting user may make an unlimited number of failed login attempts.

PASSWORD_LOCK_TIME specifies the length of time that must pass before the server unlocks an account that has been locked because of FAILED_LOGIN_ATTEMPTS. Supported values are:

- A NUMERIC value greater than or equal to 0. To specify a fractional portion of a day, specify a decimal value. For example, use the value 4.5 to specify 4 days, 12 hours.
- DEFAULT the value of PASSWORD_LOCK_TIME specified in the DEFAULT profile.
- UNLIMITED the account is locked until it is manually unlocked by a database superuser.

PASSWORD_LIFE_TIME specifies the number of days that the current password may be used before the user is prompted to provide a new password. Include the PASSWORD_GRACE_TIME clause when using the PASSWORD_LIFE_TIME clause to specify the number of days that will pass after the password expires before connections by the role are rejected. If PASSWORD_GRACE_TIME is not specified, the password will expire on the day specified by the default value of PASSWORD_GRACE_TIME, and the user will not be allowed to execute any command until a new password is provided. Supported values are:

- A NUMERIC value greater than or equal to 0. To specify a fractional portion of a day, specify a decimal value. For example, use the value 4.5 to specify 4 days, 12 hours.
- DEFAULT the value of PASSWORD_LIFE_TIME specified in the DEFAULT profile.
- UNLIMITED The password does not have an expiration date.

PASSWORD_GRACE_TIME specifies the length of the grace period after a password expires until the user is forced to change their password. When the grace period expires, a user will be allowed to connect, but will not be allowed to execute any command until they update their expired password. Supported values are:

- A NUMERIC value greater than or equal to 0. To specify a fractional portion of a day, specify a decimal value. For example, use the value 4.5 to specify 4 days, 12 hours.
- DEFAULT the value of PASSWORD_GRACE_TIME specified in the DEFAULT profile.
- UNLIMITED The grace period is infinite.

PASSWORD_REUSE_TIME specifies the number of days a user must wait before re-using a password. The PASSWORD_REUSE_TIME and PASSWORD_REUSE_MAX parameters are intended to be used together. If you specify a finite value for one of these parameters while the other is UNLIMITED, old passwords can never be reused. If both parameters are set to UNLIMITED there are no restrictions on password reuse. Supported values are:

- A NUMERIC value greater than or equal to 0. To specify a fractional portion of a day, specify a decimal value. For example, use the value 4.5 to specify 4 days, 12 hours.
- DEFAULT the value of PASSWORD_REUSE_TIME specified in the DEFAULT profile.
- UNLIMITED The password can be re-used without restrictions.

PASSWORD_REUSE_MAX specifies the number of password changes that must occur before a password can be reused. The PASSWORD_REUSE_TIME and PASSWORD_REUSE_MAX parameters are intended to be used together. If you specify a finite value for one of these parameters while the other is UNLIMITED, old passwords can never be reused. If both parameters are set to UNLIMITED there are no restrictions on password reuse. Supported values are:

- An INTEGER value greater than or equal to 0.
- DEFAULT the value of PASSWORD_REUSE_MAX specified in the DEFAULT profile.
- UNLIMITED The password can be re-used without restrictions.

PASSWORD_VERIFY_FUNCTION specifies password complexity. Supported values are:

- The name of a PL/SQL function.
- DEFAULT the value of PASSWORD_VERIFY_FUNCTION specified in the DEFAULT profile.
- NULL

PASSWORD_ALLOW_HASHED specifies whether an encrypted password to be allowed for use or not. If you specify the value as TRUE, the system allows a user to change the password by specifying a hash computed encrypted password on the client side. However, if you specify the value as FALSE, then a password must be specified in a plain-text form in order to be validated effectively, else an error will be thrown if a server receives an encrypted password. Supported values are:

- A BOOLEAN value TRUE/ON/YES/1 or FALSE/OFF/NO/0.
- DEFAULT the value of PASSWORD_ALLOW_HASHED specified in the DEFAULT profile.

Note

The PASSWORD_ALLOW_HASHED is not an Oracle-compatible parameter.

Notes

Use DROP PROFILE command to remove the profile.

Examples

The following command creates a profile named acctg. The profile specifies that if a user has not authenticated with the correct password in five attempts, the account will be locked for one day:

```
CREATE PROFILE acctg LIMIT FAILED_LOGIN_ATTEMPTS 5 PASSWORD_LOCK_TIME 1;
```

The following command creates a profile named sales. The profile specifies that a user must change their password every 90 days:

```
CREATE PROFILE sales LIMIT
PASSWORD_LIFE_TIME 90
PASSWORD_GRACE_TIME 3;
```

If the user has not changed their password before the 90 days specified in the profile has passed, they will be issued a warning at login. After a grace period of 3 days, their account will not be allowed to invoke any commands until they change their password.

The following command creates a profile named accts. The profile specifies that a user cannot re-use a password within 180 days of the last use of the password, and must change their password at least 5 times before re-using the password:

```
CREATE PROFILE accts LIMIT
PASSWORD_REUSE_TIME 180
PASSWORD_REUSE_MAX 5;
```

The following command creates a profile named resources; the profile calls a user-defined function named password_rules that will verify that the password provided meets their standards for complexity:

```
CREATE PROFILE resources LIMIT PASSWORD_VERIFY_FUNCTION password_rules;
```

6.4.1.1 Creating a Password Function

When specifying PASSWORD_VERIFY_FUNCTION, you can provide a customized function that specifies the security rules that will be applied when your users change their password. For example, you can specify rules that stipulate that the new password must be at least *n* characters long, and may not contain a specific value.

The password function has the following signature:

Where:

user_name is the name of the user.

new_password is the new password.

old_password is the user's previous password. If you reference this parameter within your function:

When a database superuser changes their password, the third parameter will always be NULL .

When a user with the CREATEROLE attribute changes their password, the parameter will pass the previous password if the statement includes the REPLACE clause. Note that the REPLACE clause is optional syntax for a user with the CREATEROLE privilege.

When a user that is not a database superuser and does not have the CREATEROLE attribute changes their password, the third parameter will contain the previous password for the role.

The function returns a Boolean value. If the function returns true and does not raise an exception, the password is accepted; if the function returns false or raises an exception, the password is rejected. If the function raises an exception, the specified error message is displayed to the user. If the function does not raise an exception, but returns false, the following error message is displayed:

ERROR: password verification for the specified password failed

The function must be owned by a database superuser, and reside in the sys schema.

Example:

The following example creates a profile and a custom function; then, the function is associated with the profile. The following CREATE PROFILE command creates a profile named acctq_pwd_profile:

```
CREATE PROFILE acctg_pwd_profile;
```

The following commands create a (schema-qualified) function named verify_password:

```
CREATE OR REPLACE FUNCTION sys.verify_password(user_name varchar2,
new_password varchar2, old_password varchar2)
RETURN boolean IMMUTABLE
IS
BEGIN
   IF (length(new_password) < 5)
   THEN
     raise_application_error(-20001, 'too short');
   END IF;

IF substring(new_password FROM old_password) IS NOT NULL
   THEN
     raise_application_error(-20002, 'includes old password');
   END IF;

RETURN true;
END;</pre>
```

The function first ensures that the password is at least 5 characters long, and then compares the new password to the old password. If the new password contains fewer than 5 characters, or contains the old password, the function raises an error.

The following statement sets the ownership of the verify_password function to the enterprisedb database superuser:

```
ALTER FUNCTION verify_password(varchar2, varchar2, varchar2) OWNER TO enterprisedb;
```

Then, the verify_password function is associated with the profile:

```
ALTER PROFILE acctg_pwd_profile LIMIT PASSWORD_VERIFY_FUNCTION verify_password;
```

The following statements confirm that the function is working by first creating a test user (alice), and then attempting to associate invalid and valid passwords with her role:

```
CREATE ROLE alice WITH LOGIN PASSWORD 'temp_password' PROFILE acctg_pwd_profile;
```

Then, when alice connects to the database and attempts to change her password, she must adhere to the rules established by the profile function. A non-superuser without CREATEROLE must include the REPLACE clause when changing a password:

```
edb=> ALTER ROLE alice PASSWORD 'hey';
ERROR: missing REPLACE clause
The new password must be at least 5 characters long:
edb=> ALTER USER alice PASSWORD 'hey' REPLACE 'temp_password';
ERROR: EDB-20001: too short
CONTEXT:
          edb-spl function verify_password(character varying,character
varying, character varying) line 5 at procedure/function invocation statement
If the new password is acceptable, the command completes without error:
edb=> ALTER USER alice PASSWORD 'hello' REPLACE 'temp_password';
ALTER ROLE
If alice decides to change her password, the new password must not contain the old password:
edb=> ALTER USER alice PASSWORD 'helloworld' REPLACE 'hello';
ERROR: EDB-20002: includes old password
CONTEXT: edb-spl function verify_password(character varying,character
varying, character varying) line 10 at procedure/function invocation statement
To remove the verify function, set password_verify_function to NULL:
ALTER PROFILE acctg_pwd_profile LIMIT password_verify_function NULL;
Then, all password constraints will be lifted:
edb=# ALTER ROLE alice PASSWORD 'hey';
ALTER ROLE
```

6.4.2 'Altering a Profile'

Use the ALTER PROFILE command to modify a user-defined profile; Advanced Server supports two forms of the command:

Include the LIMIT clause and one or more space-delimited parameter/value pairs to specify the rules enforced by Advanced Server, or use ALTER PROFILE...RENAME TO to change the name of a profile.

Parameters:

```
profile_name specifies the name of the profile.

new_name specifies the new name of the profile.

parameter specifies the attribute limited by the profile.

value specifies the parameter limit.
```

See the table in [Creating a New Profile](../04_profile_management/01_creating_a_new_profile/#creating_a_new_profile), for a complete list of accepted parameter/value pairs.

Examples

The following example modifies a profile named <code>acctg_profile</code>:

```
ALTER PROFILE acctg_profile
LIMIT FAILED_LOGIN_ATTEMPTS 3 PASSWORD_LOCK_TIME 1;
```

acctg_profile will count failed connection attempts when a login role attempts to connect to the server. The profile specifies that if a user has not authenticated with the correct password in three attempts, the account will be locked for one day.

The following example changes the name of <code>acctg_profile</code> to <code>payables_profile</code>:

ALTER PROFILE acctg_profile RENAME TO payables_profile;

6.4.3 Dropping a Profile

Use the DROP PROFILE command to drop a profile. The syntax is:

Include the IF EXISTS clause to instruct the server to not throw an error if the specified profile does not exist. The server will issue a notice if the profile does not exist.

Include the optional CASCADE clause to reassign any users that are currently associated with the profile to the default profile, and then drop the profile. Include the optional RESTRICT clause to instruct the server to not drop any profile that is associated with a role. This is the default behavior.

Parameters

profile_name

The name of the profile being dropped.

Examples

The following example drops a profile named <code>acctg_profile</code> :

DROP PROFILE acctg_profile CASCADE;

The command first re-associates any roles associated with the <code>acctg_profile</code> profile with the <code>default</code> profile, and then drops the <code>acctg_profile</code> profile.

The following example drops a profile named <code>acctg_profile</code>:

DROP PROFILE acctg_profile RESTRICT;

The RESTRICT clause in the command instructs the server to not drop acctg_profile if there are any roles associated with the profile.

6.4.4 Associating a Profile with an Existing Role

After creating a profile, you can use the ALTER USER... PROFILE or ALTER ROLE... PROFILE command to associate the profile with a role. The command syntax related to profile management functionality is:

> ALTER USERIROLE <name> [[WITH] option[...]

where option can be the following compatible clauses:

```
PROFILE 
PROFILE 
PROFILE 
Profile_name>
| ACCOUNT {LOCK|UNLOCK}
| PASSWORD EXPIRE [AT '<timestamp>']

or option can be the following non-compatible clauses:

| PASSWORD SET AT '<timestamp>'
| LOCK TIME '<timestamp>'
| STORE PRIOR PASSWORD {'<password>' '<timestamp>} [, ...]
| ...]
| PASSWORD SET AT '<timestamp>' | ...]
| STORE PRIOR PASSWORD {'<password>' '<timestamp>} [, ...]
| PASSWORD SET AT '<timestamp> | ...]
| PASSWORD PASSWORD {'<password>' '<timestamp> } [, ...]
| PASSWORD PASSWORD {'<password>' '<timestamp> } [, ...]
| PASSWORD PASSWORD {'<password>' '<timestamp> } [, ...]
| PASSWORD PASSWORD {'<password>' '<timestamp> } [, ...]
| PASSWORD PASSWORD PASSWORD {'<password>' '<timestamp> } [, ...]
| PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PASSWORD PA
```

For information about the administrative clauses of the ALTER USER or ALTER ROLE command that are supported by Advanced Server, please see the PostgreSQL core documentation available at:

https://www.postgresql.org/docs/12/static/sql-commands.html

Only a database superuser can use the Clauses enforce the following behaviors:

ALTER USER | ROLE | clauses that enforce profile management. The

Include the PROFILE clause and a profile_name to associate a pre-defined profile with a role, or to change which pre-defined profile is associated with a user.

Include the ACCOUNT clause and the LOCK or UNLOCK keyword to specify that the user account should be placed in a locked or unlocked state.

Include the LOCK TIME 'timestamp' clause and a date/time value to lock the role at the specified time, and unlock the role at the time indicated by the PASSWORD_LOCK_TIME parameter of the profile assigned to this role. If LOCK TIME is used with the ACCOUNT LOCK clause, the role can only be unlocked by a database superuser with the ACCOUNT UNLOCK clause.

Include the PASSWORD EXPIRE clause with the AT 'timestamp' keywords to specify a date/time when the password associated with the role will expire. If you omit the AT 'timestamp' keywords, the password will expire immediately.

Include the PASSWORD SET AT 'timestamp' keywords to set the password modification date to the time specified.

Include the STORE PRIOR PASSWORD {'password' 'timestamp} [, ...] clause to modify the password history, adding the new password and the time the password was set.

Each login role may only have one profile. To discover the profile that is currently associated with a login role, query the profile column of the DBA_USERS view.

Parameters

name

The name of the role with which the specified profile will be associated.

password

The password associated with the role.

profile_name

The name of the profile that will be associated with the role.

timestamp

The date and time at which the clause will be enforced. When specifying a value for timestamp, enclose the value in single-quotes.

Examples

The following command uses the ALTER USER... PROFILE command to associate a profile named acctg with a user named john:

ALTER USER john PROFILE acctg_profile;

The following command uses the ALTER ROLE... PROFILE command to associate a profile named acctg with a user named john:

ALTER ROLE john PROFILE acctg_profile;

6.4.5 Unlocking a Locked Account

A database superuser can use clauses of the ALTER USER I ROLE... command to lock or unlock a role. The syntax is:

Include the ACCOUNT LOCK clause to lock a role immediately; when locked, a role's LOGIN functionality is disabled. When you specify the ACCOUNT LOCK clause without the LOCK TIME clause, the state of the role will not change until a superuser uses the ACCOUNT UNLOCK clause to unlock the role.

Use the ACCOUNT UNLOCK clause to unlock a role.

Use the LOCK TIME 'timestamp' clause to instruct the server to lock the account at the time specified by the given timestamp for the length of time specified by the PASSWORD_LOCK_TIME parameter of the profile associated with this role.

Combine the LOCK TIME 'timestamp' clause and the ACCOUNT LOCK clause to lock an account at a specified time until the account is unlocked by a superuser invoking the ACCOUNT UNLOCK clause.

Parameters

name

The name of the role that is being locked or unlocked.

timestamp

The date and time at which the role will be locked. When specifying a value for timestamp, enclose the value in single-quotes.

Note

This command (available only in Advanced Server) is implemented to support Oracle-styled profile management.

Examples

The following example uses the ACCOUNT LOCK clause to lock the role named john. The account will remain locked until the account is unlocked with the ACCOUNT UNLOCK clause:

ALTER ROLE john ACCOUNT LOCK;

The following example uses the ACCOUNT UNLOCK clause to unlock the role named john:

ALTER USER john ACCOUNT UNLOCK;

The following example uses the LOCK TIME 'timestamp' clause to lock the role named john on September 4, 2015:

ALTER ROLE john LOCK TIME 'September 4 12:00:00 2015';

The role will remain locked for the length of time specified by the PASSWORD_LOCK_TIME parameter.

The following example combines the LOCK TIME 'timestamp' clause and the ACCOUNT LOCK clause to lock the role named john on September 4, 2015:

ALTER ROLE john LOCK TIME 'September 4 12:00:00 2015' ACCOUNT LOCK;

The role will remain locked until a database superuser uses the ACCOUNT UNLOCK command to unlock the role.

6.4.6 Creating a New Role Associated with a Profile

A database superuser can use clauses of the CREATE USER I ROLE command to assign a named profile to a role when creating the role, or to specify profile management details for a role. The command syntax related to profile management functionality is:

> CREATE USERIROLE <name> [[WITH] <option> [...]]

where option can be the following compatible clauses:

or option can be the following non-compatible clauses:

LOCK TIME '<timestamp>'

For information about the administrative clauses of the CREATE USER or CREATE ROLE command that are supported by Advanced Server, see the PostgreSQL core documentation available at:

https://www.postgresql.org/docs/12/static/sql-commands.html

CREATE ROLE | USER... PROFILE | adds a new role with an associated profile to an Advanced Server database cluster.

Roles created with the CREATE USER command are (by default) login roles. Roles created with the CREATE ROLE command are (by default) not login roles. To create a login account with the CREATE ROLE command, you must include the LOGIN keyword.

Only a database superuser can use the CREATE USER I ROLE clauses that enforce profile management; these clauses enforce the following behaviors:

Include the PROFILE clause and a profile_name to associate a pre-defined profile with a role, or to change which pre-defined profile is associated with a user.

Include the ACCOUNT clause and the LOCK or UNLOCK keyword to specify that the user account should be placed in a locked or unlocked state.

Include the LOCK TIME 'timestamp' clause and a date/time value to lock the role at the specified time, and unlock the role at the time indicated by the PASSWORD_LOCK_TIME parameter of the profile assigned to this role. If LOCK TIME is used with the ACCOUNT LOCK clause, the role can only be unlocked by a database superuser with the ACCOUNT UNLOCK clause.

Include the PASSWORD EXPIRE clause with the optional AT 'timestamp' keywords to specify a date/time when the password associated with the role will expire. If you omit the AT 'timestamp' keywords, the password will expire immediately.

Each login role may only have one profile. To discover the profile that is currently associated with a login role, query the profile column of the DBA_USERS view.

Parameters

name

The name of the role.

profile_name

The name of the profile associated with the role.

timestamp

The date and time at which the clause will be enforced. When specifying a value for timestamp, enclose the value in single-quotes.

Examples

The following example uses CREATE USER to create a login role named john who is associated with the acctq_profile profile:

CREATE USER john PROFILE acctg_profile IDENTIFIED BY "1safepwd";

john can log in to the server, using the password 1safepwd.

The following example uses CREATE ROLE to create a login role named john who is associated with the acctg_profile profile:

CREATE ROLE john PROFILE acctg_profile LOGIN PASSWORD "1safepwd";

john can log in to the server, using the password 1safepwd.

6.4.7 Backing up Profile Management Functions

A profile may include a PASSWORD_VERIFY_FUNCTION clause that refers to a user-defined function that specifies the behavior enforced by Advanced Server. Profiles are global objects; they are shared by all of the databases within a cluster. While profiles are global objects, user-defined functions are database objects.

Invoking $pg_dumpall$ with the -g or -r option will create a script that recreates the definition of any existing profiles, but that does not recreate the user-defined functions that are referred to by the PASSWORD_VERIFY_FUNCTION clause. You should use the pg_dump utility to explicitly dump (and later restore) the database in which those functions reside.

The script created by pg_dump will contain a command that includes the clause and function name:

ALTER PROFILE... LIMIT PASSWORD_VERIFY_FUNCTION <function_name>

to associate the restored function with the profile with which it was previously associated.

If the PASSWORD_VERIFY_FUNCTION clause is set to DEFAULT or NULL, the behavior will be replicated by the script generated by the pg_dumpall -q or pg_dumpall -r command.

6.5.0 Optimizer Hints

When you invoke a DELETE, INSERT, SELECT or UPDATE command, the server generates a set of execution plans; after analyzing those execution plans, the server selects a plan that will (generally) return the result set in the least amount of time. The server's choice of plan is dependent upon several factors:

- The estimated execution cost of data handling operations.
- Parameter values assigned to parameters in the Query Tuning section of the postgresql.conf file.
- · Column statistics that have been gathered by the ANALYZE command.

As a rule, the query planner will select the least expensive plan. You can use an *optimizer hint* to influence the server as it selects a query plan. An optimizer hint is a directive (or multiple directives) embedded in a comment-like syntax that immediately follows a DELETE, INSERT, SELECT or UPDATE command. Keywords in the comment instruct the server to employ or avoid a specific plan when producing the result set.

Synopsis

Optimizer hints may be included in either of the forms shown above. Note that in both forms, a plus sign (+) must immediately follow the /* or -- opening comment symbols, with no intervening space, or the server will not interpret the following tokens as hints.

If you are using the first form, the hint and optional comment may span multiple lines. The second form requires all hints and comments to occupy a single line; the remainder of the statement must start on a new line.

Description

Please Note:

- The database server will always try to use the specified hints if at all possible.
- If a planner method parameter is set so as to disable a certain plan type, then this plan will not be used even if it is specified in a hint, unless there are no other possible options for the planner. Examples of planner method parameters are enable_indexscan, enable_seqscan, enable_hashjoin, enable_mergejoin, and enable_nestloop. These are all Boolean parameters.
- Remember that the hint is embedded within a comment. As a consequence, if the hint is misspelled or
 if any parameter to a hint such as view, table, or column name is misspelled, or non-existent in the SQL
 command, there will be no indication that any sort of error has occurred. No syntax error will be given
 and the entire hint is simply ignored.
- If an alias is used for a table or view name in the SQL command, then the alias name, not the original object name, must be used in the hint. For example, in the command, SELECT /*+ FULL(acct) */ * FROM accounts of the alias for accounts, must be specified in the FULL hint, not the table name, accounts.

Use the EXPLAIN command to ensure that the hint is correctly formed and the planner is using the hint. See the Advanced Server documentation set for information on the EXPLAIN command.

In general, optimizer hints should not be used in production applications (where table data changes throughout the life of the application). By ensuring that dynamic columns are ANALYZED frequently, the column statistics will be updated to reflect value changes, and the planner will use such information to produce the least cost plan for any given command execution. Use of optimizer hints defeats the purpose of this process and will result in the same plan regardless of how the table data changes.

Parameters

hint

An optimizer hint directive.

comment

A string with additional information. Note that there are restrictions as to what characters may be included in the comment. Generally, comment may only consist of alphabetic, numeric, the underscore, dollar sign, number sign and space characters. These must also conform to the syntax of an identifier. Any subsequent hint will be ignored if the comment is not in this form.

statement_body

The remainder of the DELETE, INSERT, SELECT, or UPDATE command.

The following sections describe the optimizer hint directives in more detail.

6.5.1 'Default Optimization Modes'

There are a number of optimization modes that can be chosen as the default setting for an Advanced Server database cluster. This setting can also be changed on a per session basis by using the ALTER SESSION command as well as in individual DELETE, SELECT, and UPDATE commands within an optimizer hint. The configuration parameter that controls these default modes is named OPTIMIZER_MODE.

The following table shows the possible values.

These optimization modes are based upon the assumption that the client submitting the SQL command is interested in viewing only the first "n" rows of the result set and will then abandon the remainder of the result set. Resources allocated to the query are adjusted as such.

Examples

Alter the current session to optimize for retrieval of the first 10 rows of the result set.

```
ALTER SESSION SET OPTIMIZER_MODE = FIRST_ROWS_10;
```

The current value of the OPTIMIZER_MODE parameter can be shown by using the SHOW command. Note that this command is a utility dependent command. In PSQL, the SHOW command is used as follows:

```
SHOW OPTIMIZER_MODE;
```

```
optimizer_mode
-----
first_rows_10
(1 row)
```

The SHOW command, compatible with Oracle databases, has the following syntax:

SHOW PARAMETER OPTIMIZER_MODE;

```
NAME
------
VALUE
------
optimizer_mode
first_rows_10
```

The following example shows an optimization mode used in a SELECT command as a hint:

SELECT /*+ FIRST_ROWS(7) */ * FROM emp;

•	ename I	_		mgr	1		date		sal	l comm l	deptno
7369 I	+ SMITH	CLERK		7902		17-DEC-80		-	800.00	·++ 	20
7499 l	ALLEN I	SALESMAN	I	7698		20-FEB-81	00:00:00	1	1600.00	1 300.001	30
7521 l	WARD I	SALESMAN	1	7698		22-FEB-81	00:00:00	-	1250.00	1 500.001	30
7566 l	JONES	MANAGER	1	7839		02-APR-81	00:00:00	1	2975.00	1 1	20
7654 l	MARTINI	SALESMAN	1	7698		28-SEP-81	00:00:00	1	1250.00	1400.001	30
7698 I	BLAKE	MANAGER	1	7839		01-MAY-81	00:00:00	1	2850.00	1 1	30
7782 l	CLARK I	MANAGER	1	7839		09-JUN-81	00:00:00	1	2450.00	1 1	10
7788 I	SCOTT I	ANALYST	1	7566		19-APR-87	00:00:00	1	3000.00	1 1	20
7839 I	KING	PRESIDENT	1		1	17-NOV-81	00:00:00	1	5000.00	1 1	10
7844 l	TURNERI	SALESMAN	I	7698	1	08-SEP-81	00:00:00	1	1500.00	I 0.00 I	30
7876 l	ADAMS I	CLERK	I	7788	-	23-MAY-87	00:00:00	1	1100.00	1 1	20
7900 l	JAMES I	CLERK	I	7698	1	03-DEC-81	00:00:00	1	950.00	1 1	30
7902 l	FORD I	ANALYST	I	7566	1	03-DEC-81	00:00:00	1	3000.00	1 1	20
7934 I	MILLERI	CLERK	I	7782	1	23-JAN-82	00:00:00	1	1300.00	1 1	10
(14 ro	ws)										

6.5.2 Access Method Hints

The following hints influence how the optimizer accesses relations to create the result set.

```
Hint Description

FULL(table) Perform a full sequential scan on table .

INDEX(table [ index ] [...]) Use index on table to access the relation.

NO_INDEX(table [ index ] [...]) Do not use index on table to access the relation.
```

In addition, the ALL_ROWS, FIRST_ROWS, and FIRST_ROWS(n) hints can be used.

Examples

The sample application does not have sufficient data to illustrate the effects of optimizer hints so the remainder of the examples in this section will use a banking database created by the pgbench application located in the Advanced Server bin subdirectory.

The following steps create a database named, bank, populated by the tables, pgbench_accounts, pgbench_branches, and pgbench_history. The -s 20 option specifies a scaling factor of twenty, which results in the creation of twenty branches, each with 100,000 accounts, resulting in a total of 2,000,000 rows in the pgbench_accounts table and twenty rows in the pgbench_branches table. Ten tellers are assigned to each branch resulting in a total of 200 rows in the pgbench_tellers table.

```
The following initializes the pgbench application in the bank database.
createdb -U enterprisedb bank
CREATE DATABASE
pgbench -i -s 20 -U enterprisedb bank
NOTICE: table "pgbench_history" does not exist, skipping
NOTICE: table "pabench_tellers" does not exist, skipping
NOTICE: table "pgbench_accounts" does not exist, skipping
NOTICE: table "pgbench_branches" does not exist, skipping
creating tables...
100000 of 2000000 tuples (5%) done (elapsed 0.11 s, remaining 2.10 s)
200000 of 2000000 tuples (10%) done (elapsed 0.22 s, remaining 1.98 s)
300000 of 2000000 tuples (15%) done (elapsed 0.33 s, remaining 1.84 s)
400000 of 2000000 tuples (20%) done (elapsed 0.42 s, remaining 1.67 s)
500000 of 2000000 tuples (25%) done (elapsed 0.52 s, remaining 1.57 s)
600000 of 2000000 tuples (30%) done (elapsed 0.62 s, remaining 1.45 s)
700000 of 2000000 tuples (35%) done (elapsed 0.73 s, remaining 1.35 s)
800000 of 2000000 tuples (40%) done (elapsed 0.87 s, remaining 1.31 s)
900000 of 2000000 tuples (45%) done (elapsed 0.98 s, remaining 1.19 s)
1000000 of 2000000 tuples (50%) done (elapsed 1.09 s, remaining 1.09 s)
1100000 of 2000000 tuples (55%) done (elapsed 1.22 s, remaining 1.00 s)
1200000 of 2000000 tuples (60%) done (elapsed 1.36 s, remaining 0.91 s)
1300000 of 2000000 tuples (65%) done (elapsed 1.51 s, remaining 0.82 s)
1400000 of 2000000 tuples (70%) done (elapsed 1.65 s, remaining 0.71 s)
1500000 of 2000000 tuples (75%) done (elapsed 1.78 s, remaining 0.59 s)
1600000 of 2000000 tuples (80%) done (elapsed 1.93 s, remaining 0.48 s)
1700000 of 2000000 tuples (85%) done (elapsed 2.10 s, remaining 0.37 s)
1800000 of 2000000 tuples (90%) done (elapsed 2.23 s, remaining 0.25 s)
1900000 of 2000000 tuples (95%) done (elapsed 2.37 s, remaining 0.12 s)
2000000 of 2000000 tuples (100%) done (elapsed 2.48 s, remaining 0.00 s)
vacuum...
set primary keys...
done.
A total of 500,00 transactions are then processed. This will populate the pgbench_history table with
500.000 rows.
pgbench -U enterprisedb -t 500000 bank
starting vacuum...end.
transaction type: <builtin: TPC-B (sort of)>
scaling factor: 20
query mode: simple
number of clients: 1
number of threads: 1
number of transactions per client: 500000
number of transactions actually processed: 500000/500000
latency average: 0.000 ms
```

tps = 1464.338375 (including connections establishing)

```
The table definitions are shown below:
\d pgbench_accounts
  Table "public.pgbench_accounts"
 Column | Type | Modifiers
             -----
aid | integer | not null
bid | integer |
abalance | integer | |
filler | character(84) |
Indexes:
    "pgbench_accounts_pkey" PRIMARY KEY, btree (aid)
\d pgbench_branches
  Table "public.pgbench_branches"
 Column | Type | Modifiers
-----
bid | integer | not null
bbalance | integer
filler | character(88) |
Indexes:
   "pgbench_branches_pkey" PRIMARY KEY, btree (bid)
\d pgbench_tellers
  Table "public.pgbench_tellers"
 Column | Type | Modifiers
-----
tid | integer | not null
bid | integer |
tbalance | integer |
filler | character(84) |
Indexes:
    "pgbench_tellers_pkey" PRIMARY KEY, btree (tid)
\d pgbench_history
         Table "public.pgbench_history"
Column | Type | Modifiers
tid | integer
bid | integer
aid | integer
delta | integer
mtime | timestamp without time zone |
filler | character(22)
The EXPLAIN command shows the plan selected by the query planner. In the following example, aid is
the primary key column, so an indexed search is used on index, pgbench_accounts_pkey .
EXPLAIN SELECT * FROM pgbench_accounts WHERE aid = 100;
                                     QUERY PLAN
Index Scan using pgbench_accounts_pkey on pgbench_accounts (cost=0.43..8.45
```

tps = 1464.350357 (excluding connections establishing)

rows=1 width=97)

Index Cond: (aid = 100)

```
(2 rows)
```

The FULL hint is used to force a full sequential scan instead of using the index as shown below:

EXPLAIN SELECT /*+ FULL(pgbench_accounts) */ * FROM pgbench_accounts WHERE aid = 100;

```
QUERY PLAN
```

```
Seq Scan on pgbench_accounts (cost=0.00..58781.69 rows=1 width=97)
Filter: (aid = 100)
```

(2 rows)

The NO_INDEX hint forces a parallel sequential scan instead of use of the index as shown below:

EXPLAIN SELECT /*+ NO_INDEX(pgbench_accounts pgbench_accounts_pkey) */ * FROM pgbench_accounts WHERE aid = 100;

QUERY PLAN

```
Gather (cost=1000.00..45094.80 rows=1 width=97)
```

Workers Planned: 2

-> Parallel Seq Scan on pgbench_accounts (cost=0.00..44094.70 rows=1 width=97)

Filter: (aid = 100)

(4 rows)

In addition to using the EXPLAIN command as shown in the prior examples, more detailed information regarding whether or not a hint was used by the planner can be obtained by setting the trace_hints configuration parameter as follows:

SET trace_hints TO on;

The SELECT command with the NO_INDEX hint is repeated below to illustrate the additional information produced when the trace_hints configuration parameters is set.

EXPLAIN SELECT /*+ NO_INDEX(pgbench_accounts pgbench_accounts_pkey) */ * FROM pgbench_accounts WHERE aid = 100;

INFO: [HINTS] Index Scan of [pgbench_accounts].[pgbench_accounts_pkey]
rejected due to NO_INDEX hint.

QUERY PLAN

· -----

```
Gather (cost=1000.00..45094.80 rows=1 width=97)
```

Workers Planned: 2

-> Parallel Seq Scan on pgbench_accounts (cost=0.00..44094.70 rows=1
width=97)

Filter: (aid = 100)

(4 rows)

Note that if a hint is ignored, the INFO: [HINTS] line will not appear. This may be an indication that there was a syntax error or some other misspelling in the hint as shown in the following example where the index name is misspelled.

EXPLAIN SELECT /*+ NO_INDEX(pgbench_accounts pgbench_accounts_xxx) */ * FROM pgbench_accounts WHERE aid = 100;

QUERY PLAN

Index Scan using pgbench_accounts_pkey on pgbench_accounts (cost=0.43..8.45
rows=1 width=97)

```
Index Cond: (aid = 100)
(2 rows)
```

6.5.3 Specifying a Join Order

Include the ORDERED directive to instruct the query optimizer to join tables in the order in which they are listed in the FROM clause. If you do not include the ORDERED keyword, the query optimizer will choose the order in which to join the tables.

For example, the following command allows the optimizer to choose the order in which to join the tables listed in the FROM clause:

```
SELECT e.ename, d.dname, h.startdate
FROM emp e, dept d, jobhist h
WHERE d.deptno = e.deptno
AND h.empno = e.empno;
```

The following command instructs the optimizer to join the tables in the ordered specified:

```
SELECT /*+ ORDERED */ e.ename, d.dname, h.startdate
FROM emp e, dept d, jobhist h
WHERE d.deptno = e.deptno
AND h.empno = e.empno;
```

In the ORDERED version of the command, Advanced Server will first join emp e with dept d before joining the results with jobhist h . Without the ORDERED directive, the join order is selected by the query optimizer.

Note

The ORDERED directive does not work for Oracle-style outer joins (those joins that contain a '+' sign).

6.5.4 'Joining Relations Hints'

When two tables are to be joined, there are three possible plans that may be used to perform the join.

- Nested Loop Join A table is scanned once for every row in the other joined table.
- *Merge Sort Join* Each table is sorted on the join attributes before the join starts. The two tables are then scanned in parallel and the matching rows are combined to form the join rows.
- Hash Join A table is scanned and its join attributes are loaded into a hash table using its join attributes as hash keys. The other joined table is then scanned and its join attributes are used as hash keys to locate the matching rows from the first table.

The following table lists the optimizer hints that can be used to influence the planner to use one type of join plan over another.

Examples

In the following example, the USE_HASH hint is used for a join on the pgbench_branches and pgbench_accounts tables. The query plan shows that a hash join is used by creating a hash table from the join attribute of the pgbench_branches table.

EXPLAIN SELECT /*+ USE_HASH(b) */ b.bid, a.aid, abalance FROM pgbench_branches b, pgbench_accounts a WHERE b.bid = a.bid;

```
QUERY PLAN
-----
Hash Join (cost=21.45..81463.06 rows=2014215 width=12)
Hash Cond: (a.bid = b.bid)
-> Seq Scan on pgbench_accounts a (cost=0.00..53746.15 rows=2014215
```

```
width=12)
    -> Hash (cost=21.20..21.20 rows=20 width=4)
         -> Seq Scan on pgbench_branches b (cost=0.00..21.20 rows=20
width=4)
(5 rows)
Next, the NO_USE_HASH(a b) hint forces the planner to use an approach other than hash tables. The result
is a merge join.
EXPLAIN SELECT /*+ NO_USE_HASH(a b) */ b.bid, a.aid, abalance FROM
pgbench_branches b, pgbench_accounts a WHERE b.bid = a.bid;
                                        QUERY PLAN
  Merge Join (cost=333526.08..368774.94 rows=2014215 width=12)
    Merge Cond: (b.bid = a.bid)
    -> Sort (cost=21.63..21.68 rows=20 width=4)
          Sort Key: b.bid
          -> Seq Scan on pgbench_branches b (cost=0.00..21.20 rows=20
width=4)
    -> Materialize (cost=333504.45..343575.53 rows=2014215 width=12)
          -> Sort (cost=333504.45..338539.99 rows=2014215 width=12)
                Sort Key: a.bid
                -> Seq Scan on pgbench_accounts a (cost=0.00..53746.15
rows=2014215 width=12)
(9 rows)
Finally, the USE_MERGE hint forces the planner to use a merge join.
EXPLAIN SELECT /*+ USE_MERGE(a) */ b.bid, a.aid, abalance FROM
pgbench_branches b, pgbench_accounts a WHERE b.bid = a.bid;
                                        QUERY PLAN
  Merge Join (cost=333526.08..368774.94 rows=2014215 width=12)
    Merge Cond: (b.bid = a.bid)
    -> Sort (cost=21.63..21.68 rows=20 width=4)
          Sort Key: b.bid
          -> Seq Scan on pgbench_branches b (cost=0.00..21.20 rows=20
width=4)
    -> Materialize (cost=333504.45..343575.53 rows=2014215 width=12)
          -> Sort (cost=333504.45..338539.99 rows=2014215 width=12)
                Sort Key: a.bid
                -> Seq Scan on pgbench_accounts a (cost=0.00..53746.15
rows=2014215 width=12)
(9 rows)
In this three-table join example, the planner first performs a hash join on the pgbench_branches and
pgbench_history tables, then finally performs a hash join of the result with the pgbench_accounts
table.
EXPLAIN SELECT h.mtime, h.delta, b.bid, a.aid FROM pgbench_history h,
pgbench_branches b, pgbench_accounts a WHERE h.bid = b.bid AND h.aid = a.aid;
                                    QUERY PLAN
 Hash Join (cost=86814.29..123103.29 rows=500000 width=20)
  Hash Cond: (h.aid = a.aid)
  -> Hash Join (cost=21.45..15081.45 rows=500000 width=20)
```

Hash Cond: (h.bid = b.bid)

```
-> Seq Scan on pgbench_history h (cost=0.00..8185.00
rows=500000 width=20)
        -> Hash (cost=21.20..21.20 rows=20 width=4)
            -> Seq Scan on pgbench_branches b (cost=0.00..21.20 rows=20
width=4)
  -> Hash (cost=53746.15..53746.15 rows=2014215 width=4)
           Seq Scan on pgbench_accounts a (cost=0.00..53746.15 rows=2014215
width=4)
(9 rows)
This plan is altered by using hints to force a combination of a merge sort join and a hash join.
EXPLAIN SELECT /*+ USE_MERGE(h b) USE_HASH(a) */ h.mtime, h.delta, b.bid,
a.aid FROM pgbench_history h, pgbench_branches b, pgbench_accounts a WHERE
h.bid = b.bid AND h.aid = a.aid;
                                        QUERY PLAN
-----
 Hash Join (cost=152583.39..182562.49 rows=500000 width=20)
  Hash Cond: (h.aid = a.aid)
   -> Merge Join (cost=65790.55..74540.65 rows=500000 width=20)
        Merge Cond: (b.bid = h.bid)
        -> Sort (cost=21.63..21.68 rows=20 width=4)
              Sort Key: b.bid
              -> Seq Scan on pgbench_branches b (cost=0.00..21.20 rows=20
width=4)
```

6.5.5 Global Hints

rows=500000 width=20)

rows=2014215 width=4)

Thus far, hints have been applied directly to tables that are referenced in the SQL command. It is also possible to apply hints to tables that appear in a view when the view is referenced in the SQL command. The hint does not appear in the view, itself, but rather in the SQL command that references the view.

Materialize (cost=65768.92..68268.92 rows=500000 width=20)
-> Sort (cost=65768.92..67018.92 rows=500000 width=20)

Sea Scan on paperich_accounts a (cost=0.00..53746.15

-> Seq Scan on pgbench_history h (cost=0.00..8185.00

Sort Key: h.bid

-> Hash (cost=53746.15..53746.15 rows=2014215 width=4)

When specifying a hint that is to apply to a table within a view, the view and table names are given in dot notation within the hint argument list.

Synopsis

(13 rows)

<hint(view.table)>

Parameters

hint

Any of the hints in table Access Method Hints<access_method_hints> , Joining Relations Hints<joini

view

The name of the view containing table.

table

The table on which the hint is to be applied.

Examples

(9 rows)

A view named, tx , is created from the three-table join of pgbench_history, pgbench_branches , and pgbench_accounts shown in the final example of Joining Relations Hints<joining_relations_hints>

CREATE VIEW tx AS SELECT h.mtime, h.delta, b.bid, a.aid FROM pgbench_history h, pgbench_branches b, pgbench_accounts a WHERE h.bid = b.bid AND h.aid = a.aid;

The query plan produced by selecting from this view is shown below:

EXPLAIN SELECT * FROM tx;

```
QUERY PLAN
```

```
Hash Join (cost=86814.29..123103.29 rows=500000 width=20)
Hash Cond: (h.aid = a.aid)
-> Hash Join (cost=21.45..15081.45 rows=500000 width=20)
Hash Cond: (h.bid = b.bid)
-> Seq Scan on pgbench_history h (cost=0.00..8185.00 rows=500000 width=20)
-> Hash (cost=21.20..21.20 rows=20 width=4)
-> Seq Scan on pgbench_branches b (cost=0.00..21.20 rows=20 width=4)
-> Hash (cost=53746.15..53746.15 rows=2014215 width=4)
-> Seq Scan on pgbench_accounts a (cost=0.00..53746.15 rows=2014215 width=4)
```

The same hints that were applied to this join at the end of can be applied to the view as follows:

EXPLAIN SELECT /*+ USE_MERGE(tx.h tx.b) USE_HASH(tx.a) */ * FROM tx;

```
QUERY PLAN
```

```
______
Hash Join (cost=152583.39..182562.49 rows=500000 width=20)
  Hash Cond: (h.aid = a.aid)
  -> Merge Join (cost=65790.55..74540.65 rows=500000 width=20)
       Merge Cond: (b.bid = h.bid)
        -> Sort (cost=21.63..21.68 rows=20 width=4)
             Sort Key: b.bid
             -> Seq Scan on pgbench_branches b (cost=0.00..21.20 rows=20
width=4)
        -> Materialize (cost=65768.92..68268.92 rows=500000 width=20)
             -> Sort (cost=65768.92..67018.92 rows=500000 width=20)
                  Sort Key: h.bid
                  -> Seq Scan on pgbench_history h (cost=0.00..8185.00
rows=500000 width=20)
  -> Hash (cost=53746.15..53746.15 rows=2014215 width=4)
        -> Seq Scan on pgbench_accounts a (cost=0.00..53746.15
rows=2014215 width=4)
(13 rows)
```

In addition to applying hints to tables within stored views, hints can be applied to tables within subqueries as illustrated by the following example. In this query on the sample application emp table, employees and their managers are listed by joining the emp table with a subquery of the emp table identified by the alias, b.

```
SELECT a.empno, a.ename, b.empno "mgr empno", b.ename "mgr ename" FROM emp a, (SELECT * FROM emp) b WHERE a.mgr = b.empno;
```

```
empno I ename I mgr empno I mgr ename
-----+-----
  7369 | SMITH |
                        7902 | FORD
  7499 | ALLEN |
                        7698 | BLAKE
                        7698 | BLAKE
  7521 | WARD
  7566 | JONES |
                        7839 | KING
  7654 | MARTIN |
                        7698 | BLAKE
 765-
7698 | BLAKE
7782 | CLARK |
7788 | SCOTT |
7844 | TURNER |
7076 | ADAMS |
                       7839 | KING
                       7839 | KING
                       7566 | JONES
                       7698 | BLAKE
                        7788 | SCOTT
                        7698 | BLAKE
  7902 | FORD |
                        7566 | JONES
  7934 | MILLER |
                        7782 | CLARK
(13 rows)
```

The plan chosen by the guery planner is shown below:

EXPLAIN SELECT a.empno, a.ename, b.empno "mgr empno", b.ename "mgr ename" FROM emp a, (SELECT * FROM emp) b WHERE a.mgr = b.empno;

```
QUERY PLAN
```

```
.-----
```

```
Hash Join (cost=1.32..2.64 rows=13 width=22)
Hash Cond: (a.mgr = emp.empno)
-> Seq Scan on emp a (cost=0.00..1.14 rows=14 width=16)
-> Hash (cost=1.14..1.14 rows=14 width=11)
-> Seq Scan on emp (cost=0.00..1.14 rows=14 width=11)
(5 rows)
```

A hint can be applied to the emp table within the subquery to perform an index scan on index, emp_pk , instead of a table scan. Note the difference in the query plans.

EXPLAIN SELECT /*+ INDEX(b.emp emp_pk) */ a.empno, a.ename, b.empno "mgr empno", b.ename "mgr ename" FROM emp a, (SELECT * FROM emp) b WHERE a.mgr = b.empno;

```
QUERY PLAN
```

6.5.6 Using the APPEND Optimizer Hint

By default, Advanced Server will add new data into the first available free-space in a table (vacated by vacuumed records). Include the APPEND directive after an INSERT or SELECT command to instruct the server to bypass mid-table free space, and affix new rows to the end of the table. This optimizer hint can be particularly useful when bulk loading data.

The syntax is:

```
/*+APPEND*/
```

For example, the following command, compatible with Oracle databases, instructs the server to append the data in the INSERT statement to the end of the sales table:

```
INSERT /*+APPEND*/ INTO sales VALUES
(10, 10, '01-Mar-2011', 10, 'OR');
```

Note that Advanced Server supports the APPEND hint when adding multiple rows in a single INSERT statement:

```
INSERT /*+APPEND*/ INTO sales VALUES (20, 20, '01-Aug-2011', 20, 'NY'), (30, 30, '01-Feb-2011', 30, 'FL'), (40, 40, '01-Nov-2011', 40, 'TX');
```

The APPEND hint can also be included in the SELECT clause of an INSERT INTO statement:

INSERT INTO sales_history SELECT /*+APPEND*/ FROM sales;

6.5.7 Parallelism Hints

The PARALLEL optimizer hint is used to force parallel scanning.

The NO_PARALLEL optimizer hint prevents usage of a parallel scan.

Synopsis

```
PARALLEL ( [ <parallel_degree> | DEFAULT ])
NO_PARALLEL ()
```

Description

Parallel scanning is the usage of multiple background workers to simultaneously perform a scan of a table (that is, in parallel) for a given query. This process provides performance improvement over other methods such as the sequential scan.

Parameters

table

The table to which the parallel hint is to be applied.

```
parallel_degree | DEFAULT
```

parallel_degree is a positive integer that specifies the desired number of workers to use for a parallel scan. If specified, the lesser of parallel_degree and configuration parameter max_parallel_workers_per_gather is used as the planned number of workers. For information on the max_parallel_workers_per_gather parameter, see Asynchronous Behavior located under Resource Consumption in the PostgreSQL core documentation available at:

https://www.postgresql.org/docs/12/static/runtime-config-resource.html

If DEFAULT is specified, then the maximum possible parallel degree is used.

If both <code>parallel_degree</code> and <code>DEFAULT</code> are omitted, then the query optimizer determines the parallel degree. In this case, if <code>table</code> has been set with the <code>parallel_workers</code> storage parameter, then this value is used as the parallel degree, otherwise the optimizer uses the maximum possible parallel degree as if <code>DEFAULT</code> was specified. For information on the <code>parallel_workers</code> storage parameter, see the <code>Storage Parameters</code> located under <code>CREATE TABLE</code> in the PostgreSQL core documentation available at:

https://www.postgresql.org/docs/12/static/sql-createtable.html

Regardless of the circumstance, the parallel degree never exceeds the setting of configuration parameter $max_parallel_workers_per_gather$.

Examples

```
The following configuration parameter settings are in effect:
SHOW max_worker_processes;
 max_worker_processes
 8
(1 row)
SHOW max_parallel_workers_per_gather;
 max_parallel_workers_per_gather
 2
(1 row)
The following example shows the default scan on table pgbench_accounts. Note that a sequential scan is
shown in the query plan.
SET trace_hints TO on;
EXPLAIN SELECT * FROM pgbench_accounts;
                               QUERY PLAN
 Seq Scan on pgbench_accounts (cost=0.00..53746.15 rows=2014215 width=97)
(1 row)
The following example uses the PARALLEL hint. In the query plan, the Gather node, which launches the
background workers, indicates that two workers are planned to be used.
Note
If trace_hints is set to on , the INFO: [HINTS] lines appear stating that PARALLEL has been
accepted for pgbench_accounts as well as other hint information. For the remaining examples, these lines
will not be displayed as they generally show the same output (that is, trace_hints has been reset to off
).
EXPLAIN SELECT /*+ PARALLEL(pgbench_accounts) */ * FROM pgbench_accounts;
       [HINTS] SeqScan of [pgbench_accounts] rejected due to PARALLEL hint.
INFO: [HINTS] PARALLEL on [pgbench_accounts] accepted.
INFO: [HINTS] Index Scan of [pgbench_accounts].[pgbench_accounts_pkey]
rejected due to PARALLEL hint.
                                       OUERY PLAN
 Gather (cost=1000.00..244418.06 rows=2014215 width=97)
   Workers Planned: 2
   -> Parallel Seq Scan on pgbench_accounts (cost=0.00..41996.56
rows=839256 width=97)
(3 rows)
Now, the max_parallel_workers_per_gather setting is increased:
SET max_parallel_workers_per_gather TO 6;
SHOW max_parallel_workers_per_gather;
 max_parallel_workers_per_gather
 6
```

(1 row)

The same query on pgbench_accounts is issued again with no parallel degree specification in the PARALLEL hint. Note that the number of planned workers has increased to 4 as determined by the optimizer.

EXPLAIN SELECT /*+ PARALLEL(pgbench_accounts) */ * FROM pgbench_accounts;

```
QUERY PLAN
```

Gather (cost=1000.00..241061.04 rows=2014215 width=97)

Workers Planned: 4

-> Parallel Seq Scan on pgbench_accounts (cost=0.00..38639.54
rows=503554 width=97)

(3 rows)

Now, a value of 6 is specified for the parallel degree parameter of the PARALLEL hint. The planned number of workers is now returned as this specified value:

EXPLAIN SELECT /*+ PARALLEL(pgbench_accounts 6) */ * FROM pgbench_accounts;

QUERY PLAN

Gather (cost=1000.00..239382.52 rows=2014215 width=97)

Workers Planned: 6

-> Parallel Seq Scan on pgbench_accounts (cost=0.00..36961.03

rows=335702 width=97)

(3 rows)

The same query is now issued with the DEFAULT setting for the parallel degree. The results indicate that the maximum allowable number of workers is planned.

EXPLAIN SELECT /*+ PARALLEL(pgbench_accounts DEFAULT) */ * FROM pgbench_accounts;

QUERY PLAN

Gather (cost=1000.00..239382.52 rows=2014215 width=97)

Workers Planned: 6

-> Parallel Seq Scan on pgbench_accounts (cost=0.00..36961.03

rows=335702 width=97)

(3 rows)

Table pgbench_accounts is now altered so that the parallel_workers storage parameter is set to 3

Note

This format of the ALTER TABLE command to set the parallel_workers parameter is not compatible with Oracle databases.

The parallel_workers setting is shown by the PSQL \d+ command.

ALTER TABLE pgbench_accounts SET (parallel_workers=3);

\d+ pgbench_accounts

```
abalancel integer
                                      l plain
 filler | character(84) |
                                     l extended l
Indexes:
    "pgbench_accounts_pkey" PRIMARY KEY, btree (aid)
Options: fillfactor=100, parallel_workers=3
Now, when the PARALLEL hint is given with no parallel degree, the resulting number of planned workers is
the value from the parallel_workers parameter:
EXPLAIN SELECT /*+ PARALLEL(pgbench_accounts) */ * FROM pgbench_accounts;
                                     QUERY PLAN
 Gather (cost=1000.00..242522.97 rows=2014215 width=97)
   Workers Planned: 3
   -> Parallel Seq Scan on pgbench_accounts (cost=0.00..40101.47
rows=649747 width=97)
(3 rows)
Specifying a parallel degree value or DEFAULT in the PARALLEL hint overrides the parallel_workers
The following example shows the NO_PARALLEL hint. Note that with trace_hints set to on , the
INFO: [HINTS] message states that the parallel scan was rejected due to the NO_PARALLEL hint.
EXPLAIN SELECT /*+ NO_PARALLEL(pgbench_accounts) */ * FROM pgbench_accounts;
INFO: [HINTS] Parallel SeqScan of [pgbench_accounts] rejected due to
NO_PARALLEL hint.
                             QUERY PLAN
_____
 Seq Scan on pgbench_accounts (cost=0.00..53746.15 rows=2014215 width=97)
(1 row)
```

6.5.8 'Conflicting Hints'

If a command includes two or more conflicting hints, the server will ignore the contradictory hints. The following table lists hints that are contradictory to each other.

6.6.0 dblink_ora

dblink_ora provides an OCI-based database link that allows you to SELECT, INSERT, UPDATE or DELETE data stored on an Oracle system from within Advanced Server.

Connecting to an Oracle Database

To enable Oracle connectivity, download Oracle's freely available OCI drivers from their website, presently at:

http://www.oracle.com/technetwork/database/database-technologies/instant-client/overview/index.html

For Linux, if the Oracle instant client that you've downloaded does not include the libclntsh.so library, you must create a symbolic link named libclntsh.so that points to the downloaded version. Navigate to the instant client directory and execute the following command:

```
ln -s libclntsh.so.<version> libclntsh.so
```

Where version is the version number of the libclntsh.so library. For example:

ln -s libclntsh.so.12.1 libclntsh.so

Before creating a link to an Oracle server, you must tell Advanced Server where to find the OCI driver.

Set the LD_LIBRARY_PATH environment variable on Linux (or PATH on Windows) to the lib directory of the Oracle client installation directory.

For Windows only, you can instead set the value of the oracle_home configuration parameter in the postgresql.conf file. The value specified in the oracle_home configuration parameter will override the Windows PATH environment variable.

The LD_LIBRARY_PATH environment variable on Linux (PATH environment variable or oracle_home configuration parameter on Windows) must be set properly each time you start Advanced Server.

When using a Linux service script to start Advanced Server, be sure LD_LIBRARY_PATH has been set within the service script so it is in effect when the script invokes the pq_ctl utility to start Advanced Server.

For Windows only: To set the oracle_home configuration parameter in the postgresql.conf file, edit the file, adding the following line:

```
oracle_home = 'lib_directory'
```

Substitute the name of the Windows directory that contains oci.dll for lib_directory .

After setting the oracle_home configuration parameter, you must restart the server for the changes to take effect. Restart the server from the Windows Services console.

6.6.1.0 dblink_ora Functions and Procedures

dblink_ora supports the following functions and procedures.

6.6.1.1 dblink_ora_connect()

The dblink_ora_connect() function establishes a connection to an Oracle database with user-specified connection information. The function comes in two forms; the signature of the first form is:

dblink_ora_connect(<conn_name>, <server_name>, <service_name>, <user_name>, <password>, <</pre>

Where:

conn_name specifies the name of the link.

server_name specifies the name of the host.

service_name specifies the name of the service.

user_name specifies the name used to connect to the server.

password specifies the password associated with the user name.

port specifies the port number.

asDBA is True if you wish to request SYSDBA privileges on the Oracle server. This parameter is optional; if omitted, the default value is FALSE.

The first form of dblink_ora_connect() returns a TEXT value.

The signature of the second form of the dblink_ora_connect() function is:

dblink_ora_connect(<foreign_server_name>, <asDBA>)

Where:

foreign_server_name specifies the name of a foreign server.

asDBA is True if you wish to request SYSDBA privileges on the Oracle server. This parameter is optional; if omitted, the default value is FALSE.

The second form of the dblink_ora_connect() function allows you to use the connection properties of a pre-defined foreign server when establishing a connection to the server.

Before invoking the second form of the dblink_ora_connect() function, use the CREATE SERVER command to store the connection properties for the link to a system table. When you call the dblink_ora_connect() function, substitute the server name specified in the CREATE SERVER command for the name of the link.

The second form of dblink_ora_connect() returns a TEXT value.

6.6.1.2 dblink_ora_status()

The dblink_ora_status() function returns the database connection status. The signature is:

dblink_ora_status(<conn_name>)

Where:

conn_name specifies the name of the link.

If the specified connection is active, the function returns a TEXT value of OK .

6.6.1.3 dblink_ora_disconnect()

The dblink_ora_disconnect() function closes a database connection. The signature is:

dblink_ora_disconnect(<conn_name>)

Where:

conn_name specifies the name of the link.

The function returns a TEXT value.

6.6.1.4 dblink_ora_record()

The dblink_ora_record() function retrieves information from a database. The signature is:

dblink_ora_record(<conn_name>, <query_text>)

Where:

conn_name specifies the name of the link.

query_text specifies the text of the SQL SELECT statement that will be invoked on the Oracle server.

The function returns a SETOF record.

6.6.1.5 dblink_ora_call()

The dblink_ora_call() function executes a non- SELECT statement on an Oracle database and returns a result set. The signature is:

dblink_ora_call(<conn_name>, <command>, <iterations>)

Where:

conn_name specifies the name of the link.

command specifies the text of the SQL statement that will be invoked on the Oracle server.

iterations specifies the number of times the statement is executed.

The function returns a SETOF record.

6.6.1.6 dblink_ora_exec()

The dblink_ora_exec() procedure executes a DML or DDL statement in the remote database. The signature is:

dblink_ora_exec(<conn_name>, <command>)

Where:

conn_name specifies the name of the link.

command specifies the text of the INSERT, UPDATE, or DELETE SQL statement that will be invoked on the Oracle server.

The function returns a VOID .

6.6.1.7 dblink_ora_copy()

The dblink_ora_copy() function copies an Oracle table to an EnterpriseDB table. The dblink_ora_copy() function returns a BIGINT value that represents the number of rows copied. The signature is:

dblink_ora_copy(<conn_name>, <command>, <schema_name>, <table_name>, <truncate>, <count>)

Where:

conn_name specifies the name of the link.

command specifies the text of the SQL SELECT statement that will be invoked on the Oracle server.

schema_name specifies the name of the target schema.

table_name specifies the name of the target table.

truncate specifies if the server should TRUNCATE the table prior to copying; specify TRUE to indicate that the server should TRUNCATE the table. truncate is optional; if omitted, the value is FALSE.

count instructs the server to report status information every n record, where n is the number specified. During the execution of the function, Advanced Server raises a notice of severity INFO with each iteration of the count. For example, if FeedbackCount is 10, dblink_ora_copy() raises a notice every 10 records. count is optional; if omitted, the value is 0.

6.6.2 Calling dblink_ora Functions

The following command establishes a connection using the dblink_ora_connect() function:

```
SELECT dblink_ora_connect('acctg', 'localhost', 'xe', 'hr', 'pwd', 1521);
```

The example connects to a service named xe running on port 1521 (on the localhost) with a user name of hr and a password of pwd. You can use the connection name acctg to refer to this connection when calling other dblink_ora functions.

The following command uses the dblink_ora_copy() function over a connection named edb_conn to copy the empid and deptno columns from a table (on an Oracle server) named ora_acctg to a table located in the public schema on an instance of Advanced Server named as_acctg. The TRUNCATE option is enforced, and a feedback count of 3 is specified:

```
edb=# SELECT dblink_ora_copy('edb_conn','select empid, deptno FROM
ora_acctg', 'public', 'as_acctg', true, 3);
```

The following SELECT statement uses dblink_ora_record() function and the acctg connection to retrieve information from the Oracle server:

```
SELECT * FROM dblink_ora_record( 'acctg', 'SELECT first_name from employees') AS t1(id VA
```

The command retrieves a list that includes all of the entries in the first_name column of the employees table.

6.7 Open Client Library

The Open Client Library provides application interoperability with the Oracle Call Interface – an application that was formerly "locked in" can now work with either an EDB Postgres Advanced Server or an Oracle database with minimal to no changes to the application code. The EnterpriseDB implementation of the Open Client Library is written in C.

The following diagram compares the Open Client Library and Oracle Call Interface application stacks.

For detailed usage information about the Open Client Library and the supported functions, see the EDB Postgres Advanced Server OCL Connector Guide, available at:

https://www.enterprisedb.com/edb-docs

Note

EnterpriseDB does not support use of the Open Client Library with Oracle Real Application Clusters (RAC) and Oracle Exadata; the aforementioned Oracle products have not been evaluated nor certified with this EnterpriseDB product.

6.8 Oracle Catalog Views

The Oracle Catalog Views provide information about database objects in a manner compatible with the Oracle data dictionary views. Information about the supported views is now available in the *Database Compatibility for Oracle Developer's Catalog Views Guide*, available at:

https://www.enterprisedb.com/edb-docs

6.9 Tools and Utilities

Compatible tools and utility programs can allow a developer to work with Advanced Server in a familiar environment. The tools supported by Advanced Server include:

- EDB*Plus
- · EDB*Loader
- EDB*Wrap
- The Dynamic Runtime Instrumentation Tools Architecture (DRITA)

For detailed information about the functionality supported by Advanced Server, see the *Database Compatibility* for Oracle Developer's Tools and Utilities Guide, available at:

https://www.enterprisedb.com/edb-docs

6.10 ECPGPlus

EnterpriseDB has enhanced ECPG (the PostgreSQL pre-compiler) to create ECPGPlus. ECPGPlus allows you to include embedded SQL commands in C applications; when you use ECPGPlus to compile an application that contains embedded SQL commands, the SQL code is syntax-checked and translated into C.

ECPGPlus supports Pro*C compatible syntax in C programs when connected to an Advanced Server database. ECPGPlus supports:

- Oracle Dynamic SQL Method 4 (ODS-M4).
- Pro*C compatible anonymous blocks.
- A CALL statement compatible with Oracle databases.

As part of ECPGPlus' Pro*C compatibility, you do not need to include the BEGIN DECLARE SECTION and END DECLARE SECTION directives.

For more information about using ECPGPlus, see the EDB Postgres Advanced Server ECPG Connector Guide available from the EnterpriseDB website at:

https://www.enterprisedb.com/edb-docs

6.11 System Catalog Tables

The system catalog tables contain definitions of database objects that are available to Advanced Server; the layout of the system tables is subject to change. If you are writing an application that depends on information stored in the system tables, it would be prudent to use an existing catalog view, or create a catalog view to isolate the application from changes to the system table.

For detailed information about the system catalog tables, see the Database Compatibility for Oracle Developer's Reference Guide, available at:

https://www.enterprisedb.com/edb-docs

6.12 Conclusion

Database Compatibility for Oracle Developers Guide

Copyright © 2007 - 2020 EnterpriseDB Corporation. All rights reserved.

EnterpriseDB Corporation 34 Crosby Drive, Suite 201, Bedford, MA 01730, USA

T +1 781 357 3390 F +1 978 467 1307 E info@enterprisedb.com www.enterprisedb.com

- EnterpriseDB and Postgres Enterprise Manager are registered trademarks of EnterpriseDB Corporation. EDB and EDB Postgres are trademarks of EnterpriseDB Corporation. Oracle is a registered trademark of Oracle, Inc. Other trademarks may be trademarks of their respective owners.
- EDB designs, establishes coding best practices, reviews, and verifies input validation for the logon UI for EDB Postgres products where present. EDB follows the same approach for additional input components, however the nature of the product may require that it accepts freeform SQL, WMI or other strings to be entered and submitted by trusted users for which limited validation is possible. In such cases it is not possible to prevent users from entering incorrect or otherwise dangerous inputs.
- EDB reserves the right to add features to products that accept freeform SQL, WMI or other potentially dangerous inputs from authenticated, trusted users in the future, but will ensure all such features are designed and tested to ensure they provide the minimum possible risk, and where possible, require superuser or equivalent privileges.
- EDB does not that warrant that we can or will anticipate all potential threats and therefore our process cannot fully guarantee that all potential vulnerabilities have been addressed or considered.

7.0 Database Compatibility for Oracle Developers Tools and Utilities Guide

The tools and utilities documented in this guide allow a developer that is accustomed to working with Oracle utilities to work with Advanced Server in a familiar environment.

The sections in this guide describe compatible tools and utilities that are supported by Advanced Server. These include:

- EDB*Loader
- EDB*Wrap
- · Dynamic Runtime Instrumentation

The EDB*Plus command line client provides a user interface to Advanced Server that supports SQL*Plus commands; EDB*Plus allows you to:

- · Query database objects
- · Execute stored procedures
- · Format output from SQL commands
- · Execute batch scripts
- Execute OS commands
- · Record output

For detailed installation and usage information about EDB*Plus, please see the* EDB*Plus User's Guide*, available from the EnterpriseDB website at:

https://www.enterprisedb.com/edb-docs/p/edbplus

For detailed information about the features supported by Advanced Server, please consult the complete library of Advanced Server guides available at:

https://www	v.enterprisedb	.com/edb-do	CS	

7.1 EDB*Loader

EDBLoader is a high-performance bulk data loader that provides an interface compatible with Oracle databases for Advanced Server. The EDBLoader command line utility loads data from an input source, typically a file, into one or more tables using a subset of the parameters offered by Oracle SQL*Loader.

EDB*Loader features include:

- Support for the Oracle SQL*Loader data loading methods conventional path load, direct path load, and parallel direct path load
- Syntax for control file directives compatible with Oracle SQL*Loader
- · Input data with delimiter-separated or fixed-width fields
- · Bad file for collecting rejected records
- · Loading of multiple target tables
- · Discard file for collecting records that do not meet the selection criteria of any target table
- Log file for recording the EDB*Loader session and any error messages
- Data loading from standard input and remote loading, particularly useful for large data sources on remote hosts

These features are explained in detail in the following sections.

Note

The following are important version compatibility restrictions between the EDB*Loader client and the database server.

- When you invoke the EDBLoader program (called edbldr), you pass in parameters and directive information to the database server. **We strongly recommend that the version 12 EDBLoader client (the edbldr program supplied with Advanced Server 12) be used to load data only into version 12 of the database server. In general, the EDB*Loader client and database server should be the same version.**
- Use of a version 12, 11, 10, 9.6, 9.5, 9.4 or 9.3 EDB*Loader client is not supported for database servers version 9.2 or earlier.

Data Loading Methods

As with Oracle SQLLoader, EDBLoader supports three data loading methods:

- · Conventional path load
- · Direct path load
- · Parallel direct path load

Conventional path load is the default method used by EDB*Loader. Basic insert processing is used to add rows to the table.

The advantage of a conventional path load over the other methods is that table constraints and database objects defined on the table such as primary keys, not null constraints, check constraints, unique indexes, foreign key constraints, and triggers are enforced during a conventional path load.

One exception is that the Advanced Server *rules* defined on the table are not enforced. EDB*Loader can load* tables on which rules are defined, but the rules are not executed. As a consequence, partitioned tables implemented using rules cannot be loaded using EDBLoader.

Note

Advanced Server rules are created by the CREATE RULE command. Advanced Server rules are not the same database objects as rules and rule sets used in Oracle.

EDB*Loader also supports direct path loads. A direct path load is faster than a conventional path load, but requires the removal of most types of constraints and triggers from the table. For more information see, [Direct Path Load](01_edb_loader#direct_path_load).

Finally, EDB*Loader supports parallel direct path loads. A parallel direct path load provides even greater performance improvement by permitting multiple EDB*Loader sessions to run simultaneously to load a single table. For more information, see [Parallel Direct Path Load](01_edb_loader#parallel_direct_path_load).

General Usage

EDB*Loader can load data files with either delimiter-separated or fixed-width fields, in single-byte or multi-byte character sets. The delimiter can be a string consisting of one or more single-byte or multi-byte characters. Data file encoding and the database encoding may be different. Character set conversion of the data file to the database encoding is supported.

Each EDBLoader session runs as a single, independent transaction. If an error should occur during the EDBLoader session that aborts the transaction, all changes made during the session are rolled back.

Generally, formatting errors in the data file do not result in an aborted transaction. Instead, the badly formatted records are written to a text file called the *bad file*. The reason for the error is recorded in the *log file*.

Records causing database integrity errors do result in an aborted transaction and rollback. As with formatting errors, the record causing the error is written to the bad file and the reason is recorded in the log file.

Note

EDBLoader differs from Oracle SQLLoader in that a database integrity error results in a rollback in EDBLoader. In OracleSQLLoader, only the record causing the error is rejected. Records that were previously inserted into the table are retained and loading continues after the rejected record.

The following are examples of types of formatting errors that do not abort the transaction:

- Attempt to load non-numeric value into a numeric column
- · Numeric value is too large for a numeric column
- · Character value is too long for the maximum length of a character column
- · Attempt to load improperly formatted date value into a date column

The following are examples of types of database errors that abort the transaction and result in the rollback of all changes made in the EDB*Loader session:

- · Violation of a unique constraint such as a primary key or unique index
- · Violation of a referential integrity constraint
- Violation of a check constraint
- · Error thrown by a trigger fired as a result of inserting rows

Building the EDB*Loader Control File

When you invoke EDBLoader, the list of arguments provided must include the name of a control file. The control file includes the instructions that EDBLoader uses to load the table (or tables) from the input data file. The control file includes information such as:

- The name of the input data file containing the data to be loaded.
- The name of the table or tables to be loaded from the data file.
- Names of the columns within the table or tables and their corresponding field placement in the data file.
- Specification of whether the data file uses a delimiter string to separate the fields, or if the fields occupy fixed column positions.
- Optional selection criteria to choose which records from the data file to load into a given table.
- The name of the file that will collect illegally formatted records.
- The name of the discard file that will collect records that do not meet the selection criteria of any table.

The syntax for the EDB*Loader control file is as follows:

```
[ OPTIONS (param =value* [, param=value ] ...) ]
LOAD DATA
  [ CHARACTERSET charset ]
   INFILE '{ data_file | stdin }' ]
   BADFILE 'bad_file' ]
  [ DISCARDFILE 'discard_file' ]
[ { DISCARDMAX | DISCARDS } max_discard_recs ]
[ INSERT | APPEND | REPLACE | TRUNCATE ]
[ PRESERVE BLANKS ]
{ INTO TABLE target_table
  [ WHEN field_condition [ AND field_condition ] ...]
  FIELDS TERMINATED BY 'termstring'
    [ OPTIONALLY ENCLOSED BY 'enclstring' ] ]
[ RECORDS DELIMITED BY 'delimstring' ]

    □ TRAILING NULLCOLS □

  (field_def [, field_def ] ...)
} ...
```

where field_def defines a field in the specified data_file that describes the location, data format, or value of the data to be inserted into column_name of the target_table. The syntax of field_def is the following:

```
column_name {
CONSTANT val |
FILLER [ POSITION (start:end) ] [ fieldtype ] |
BOUNDFILLER [ POSITION (start:end) ] [ fieldtype ] |
[ POSITION (start:end) ] [ fieldtype ]
[ NULLIF field_condition [ AND field_condition ] ...]
[ PRESERVE BLANKS ] [ "expr" ]
}
where fieldtype is one of:
CHAR [(length)] | DATE [(length)] [ "datemask" ] |
| INTEGER EXTERNAL [(length)] |
| FLOAT EXTERNAL [(length)] | DECIMAL EXTERNAL [(length)] |
ZONED EXTERNAL [(length)] | ZONED [(precision [,scale])]
```

Description

The specification of data_file , bad_file , and discard_file may include the full directory path or a relative directory path to the file name. If the file name is specified alone or with a relative directory path, the file is then assumed to exist (in the case of data_file), or is created (in the case of bad_file or discard_file), relative to the current working directory from which edbldr is invoked.

You can include references to environment variables within the EDB*Loader control file when referring to a directory path and/or file name. Environment variable references are formatted differently on Windows systems than on Linux systems:

- On Linux, the format is \$ENV_VARIABLE or \${ENV_VARIABLE}
- On Windows, the format is %ENV_VARIABLE%

Where ENV_VARIABLE is the environment variable that is set to the directory path and/or file name.

The EDBLDR_ENV_STYLE environment variable instructs Advanced Server to interpret environment variable references as Windows-styled references or Linux-styled references irregardless of the operating system on which EDBLoader resides. You can use this environment variable to create portable control files for EDBLoader.

- On a Windows system, set EDBLDR_ENV_STYLE to linux or unix to instruct Advanced Server to recognize Linux-style references within the control file.
- On a Linux system, set EDBLDR_ENV_STYLE to windows to instruct Advanced Server to recognize Windows-style references within the control file.

The operating system account enterprisedb must have read permission on the directory and file specified by data_file .

The operating system account enterprised must have write permission on the directories where bad_file and discard_file are to be written.

Note

The file names for $data_file$, bad_file , and $discard_file$ should include extensions of .dat, .bad, and .dsc, respectively. If the provided file name does not contain an extension, EDB*Loader assumes the actual file name includes the appropriate aforementioned extension.

If an EDB*Loader session results in data format errors and the BADFILE clause is not specified, nor is the BAD parameter given on the command line when edbldr is invoked, a bad file is created with the name control_file_base .bad in the current working directory from which edbldr is invoked. control_file_base is the base name of the control file (that is, the file name without any extension) used in the edbldr session.

If all of the following conditions are true, the discard file is not created even if the EDB*Loader session results in discarded records:

- The DISCARDFILE clause for specifying the discard file is not included in the control file.
- The DISCARD parameter for specifying the discard file is not included on the command line.

- The DISCARDMAX clause for specifying the maximum number of discarded records is not included in the control file.
- The DISCARDS clause for specifying the maximum number of discarded records is not included in the control file.
- The DISCARDMAX parameter for specifying the maximum number of discarded records is not included on the command line.

If neither the DISCARDFILE clause nor the DISCARD parameter for explicitly specifying the discard file name are specified, but DISCARDMAX or DISCARDS is specified, then the EDB*Loader session creates a discard file using the data file name with an extension of .dsc.

Note

There is a distinction between keywords DISCARD and DISCARDS. DISCARD is an EDBLoader command line parameter used to specify the discard file name (see [General Usage](#general_usage)). DISCARDS is a clause of the LOAD DATA directive that may only appear in the control file. Keywords DISCARDS and DISCARDMAX provide the same functionality of specifying the maximum number of discarded records allowed before terminating the EDBLoader session. Records loaded into the database before termination of the EDB*Loader session due to exceeding the DISCARDS or DISCARDMAX settings are kept in the database and are not rolled back.

If one of INSERT, APPEND, REPLACE, or TRUNCATE is specified, it establishes the default action of how rows are to be added to target tables. If omitted, the default action is as if INSERT had been specified.

If the FIELDS TERMINATED BY clause is specified, then the POSITION (start:end) clause may not be specified for any field_def . Alternatively if the FIELDS TERMINATED BY clause is not specified, then every field_def must contain either the POSITION (start:end) clause, the fieldtype(length) clause, or the CONSTANT clause.

Parameters

OPTIONS param=value

Use the OPTIONS clause to specify param=value pairs that represent an EDB*Loader directive. If a parameter is specified in both the OPTIONS clause and on the command line when edbldr is invoked, the command line setting is used.

Specify one or more of the following parameter/value pairs:

DIRECT= { FALSE | TRUE }

If DIRECT is set to TRUE EDB*Loader performs a direct path load instead of a conventional path load. The default value of DIRECT is FALSE.

For information on direct path loads see, [Direct Path Load](01_edb_loader#direct_path_load).

ERRORS=error_count

error_count specifies the number of errors permitted before aborting the EDB*Loader session.

The default is 50.

FREEZE= { FALSE | TRUE }

Set FREEZE to TRUE to indicate that the data should be copied with the rows frozen. A tuple guaranteed to be visible to all current and future transactions is marked as frozen to prevent transaction ID wrap-around. For more information about frozen tuples, see the PostgreSQL core documentation at:

https://www.postgresql.org/docs/12/static/routine-vacuuming.html

You must specify a data-loading type of TRUNCATE in the control file when using the FREEZE option. FREEZE is not supported for direct loading.

By default, FREEZE is FALSE.

PARALLEL= { FALSE | TRUE }

Set PARALLEL to TRUE to indicate that this EDB*Loader session is one of a number of concurrent EDB*Loader sessions participating in a parallel direct path load. The default value of PARALLEL is FALSE.

When PARALLEL is TRUE, the DIRECT parameter must also be set to TRUE. For more information about parallel direct path loads, see [Parallel Direct Path Load](01_edb_loader#parallel_direct_path_load).

ROWS=n

n specifies the number of rows that EDB*Loader will commit before loading the next set of n rows.

If EDB*Loader encounters an invalid row during a load (in which the ROWS parameter is specified), those rows committed prior to encountering the error will remain in the destination table.

SKIP=skip_count

skip_count specifies the number of records at the beginning of the input data file that should be skipped before loading begins. The default is 0.

SKIP_INDEX_MAINTENANCE={ FALSE | TRUE }

If SKIP_INDEX_MAINTENANCE is TRUE, index maintenance is not performed as part of a direct path load, and indexes on the loaded table are marked as invalid. The default value of SKIP_INDEX_MAINTENANCE is FALSE.

Note

During a parallel direct path load, target table indexes are not updated, and are marked as invalid after the load is complete.

You can use the REINDEX command to rebuild an index. For more information about the REINDEX command, see the PostgreSQL core documentation.

charset

Use the CHARACTERSET clause to identify the character set encoding of data_file where charset is the character set name. This clause is required if the data file encoding differs from the control file encoding. (The control file encoding must always be in the encoding of the client where edbldr is invoked.)

Examples of charset settings are UTF8, SQL_ASCII, and SJIS.

For more information about client to database character set conversion, see the PostgreSQL core documentation.

data_file

File containing the data to be loaded into target_table. Each record in the data file corresponds to a row to be inserted into target_table.

If an extension is not provided in the file name, EDB*Loader assumes the file has an extension of .dat , for example, mydatafile.dat .

Note

If the DATA parameter is specified on the command line when edbldr is invoked, the file given by the command line DATA parameter is used instead.

If the INFILE clause is omitted as well as the command line DATA parameter, then the data file name is assumed to be identical to the control file name, but with an extension of .dat .

stdin

Specify stdin (all lowercase letters) if you want to use standard input to pipe the data to be loaded directly to EDB*Loader. This is useful for data sources generating a large number of records to be loaded.

bad_file

A file that receives data_file records that cannot be loaded due to errors. The bad file is generated for collecting rejected or bad records.

From Advanced Server version 12 and onwards, a bad file will be generated only if there are any bad or rejected records. However, if there is an existing bad file with identical name and location, and no bad records are generated after invoking a new version of ebdldr, the existing bad file remains untouched.

If an extension is not provided in the file name, EDB*Loader assumes the file has an extension of .bad , for example, mybadfile.bad .

Note

If the BAD parameter is specified on the command line when edbldr is invoked, the file given by the command line BAD parameter is used instead.

discard_file

File that receives input data records that are not loaded into any table because none of the selection criteria are met for tables with the WHEN clause, and there are no tables without a WHEN clause. (All records meet the selection criteria of a table without a WHEN clause.)

If an extension is not provided in the file name, EDB*Loader assumes the file has an extension of .dsc , for example, mydiscardfile.dsc .

Note

If the DISCARD parameter is specified on the command line when edbldr is invoked, the file given by the command line DISCARD parameter is used instead.

{ DISCARDMAX | DISCARDS } max_discard_recs

Maximum number of discarded records that may be encountered from the input data records before terminating the EDB*Loader session. (A discarded record is described in the preceding description of the discard_file parameter.) Either keyword DISCARDMAX or DISCARDS may be used preceding the integer value specified by max_discard_recs.

For example, if <code>max_discard_recs</code> is <code>0</code> , then the EDBLoader session is terminated if and when a first discarded record is encountered. If <code>max_discard_recs</code> is 1, then the EDBLoader session is terminated if and when a second discarded record is encountered.

When the EDB*Loader session is terminated due to exceeding max_discard_recs, prior input data records that have been loaded into the database are retained. They are not rolled back.

INSERT | APPEND | REPLACE | TRUNCATE

Specifies how data is to be loaded into the target tables. If one of INSERT, APPEND, REPLACE, or TRUNCATE is specified, it establishes the default action for all tables, overriding the default of INSERT.

TNSFRT

Data is to be loaded into an empty table. EDB*Loader throws an exception and does not load any data if the table is not initially empty.

Note

If the table contains rows, the TRUNCATE command must be used to empty the table prior to invoking EDB*Loader*. *EDB*Loader throws an exception if the DELETE command is used to empty the table instead of the TRUNCATE command. Oracle SQL*Loader allows the table to be emptied by using either the DELETE or TRUNCATE command.

APPEND

Data is to be added to any existing rows in the table. The table may be initially empty as well.

REPLACE

The REPLACE keyword and TRUNCATE keywords are functionally identical. The table is truncated by EDB*Loader prior to loading the new data.

Note

Delete triggers on the table are not fired as a result of the REPLACE operation.

TRUNCATE

The table is truncated by EDB*Loader prior to loading the new data. Delete triggers on the table are not fired as a result of the truncate operation.

PRESERVE BLANKS

For all target tables, retains leading white space when the optional enclosure delimiters are not present and leaves trailing white space intact when fields are specified with a predetermined size. When omitted, the default behavior is to trim leading and trailing white space.

target_table

Name of the table into which data is to be loaded. The table name may be schema-qualified (for example, enterprisedb.emp). The specified target must not be a view.

field_condition

Conditional clause taking the following form:

```
[(] { (start:end) | column_name } { = | != | <> } 'val'[)]
```

This conditional clause is used for the WHEN clause, which is part of the INTO TABLE target_table clause, and the NULLIF clause, which is part of the field definition denoted as field_def in the syntax diagram.

start and end are positive integers specifying the column positions in $data_file$ that mark the beginning and end of a field that is to be compared with the constant val. The first character in each record begins with a start value of 1.

column_name specifies the name assigned to a field definition of the data file as defined by field_def in the syntax diagram.

Use of either (start : end) or column_name defines the portion of the record in data_file that is to be compared with the value specified by 'val' to evaluate as either true or false.

All characters used in the field_condition text (particularly in the val string) must be valid in the database encoding. (For performing data conversion, EDB*Loader first converts the characters in val string to the database encoding and then to the data file encoding.)

In the WHEN field_condition[AND field_condition] clause, if all such conditions evaluate to TRUE for a given record, then EDB*Loader attempts to insert that record into target_table. If the insert operation fails, the record is written to bad_file. If for a given record, none of the WHEN clauses evaluate to TRUE for all INTO TABLE clauses, the record is written to discard_file, if a discard file was spe NULLIF clause in this Parameters" list for the effect of field_condition on this clause.

termstring

String of one or more characters that separates each field in <code>data_file</code> . The characters may be single-byte or multi-byte as long as they are valid in the database encoding. Two consecutive

appearances of termstring with no intervening character results in the corresponding column set to null.

enclstring

String of one or more characters used to enclose a field value in *data_file*. The characters may be single-byte or multi-byte as long as they are valid in the database encoding. Use enclstring on fields where termstring appears as part of the data.

delimstring

String of one or more characters that separates each record in <code>data_file</code>. The characters may be single-byte or multi-byte as long as they are valid in the database encoding. Two consecutive appearances of <code>delimstring</code> with no intervening character results in no corresponding row loaded into the table. The last record (in other words, the end of the data file) must also be terminated by the <code>delimstring</code> characters, otherwise the final record is not loaded into the table.

Note

The RECORDS DELIMITED BY 'delimstring' clause is not compatible with Oracle databases.

TRAILING NULLCOLS

If TRAILING NULLCOLS is specified, then the columns in the column list for which there is no data in *data_file* for a given record, are set to null when the row is inserted. This applies only to one or more consecutive columns at the end of the column list.

If fields are omitted at the end of a record and TRAILING NULLCOLS is not specified, EDB*Loader assumes the record contains formatting errors and writes it to the bad file.

column_name

Name of a column in target_table into which a field value defined by field_def is to be inserted. If the field definition includes the FILLER or BOUNDFILLER clause, then column_name is not required t be the name of a column in the table. It can be any identifier name since the FILLER and BOUNDFILLER clauses prevent the loading of the field data into a table column.

CONSTANT val

Specifies a constant that is type-compatible with the column data type to which it is assigned in a field definition. Single or double quotes may enclose *val*. If *val* contains white space, then enclosing quotation marks must be used.

The use of the CONSTANT clause completely determines the value to be assigned to a column in each inserted row. No other clause may appear in the same field definition.

If the TERMINATED BY clause is used to delimit the fields in data_file, there must be no delimited field in data_file corresponding to any field definition with a CONSTANT clause. In other words, EDB*Loader assumes there is no field in data_file for any field definition with a CONSTANT clause.

FTIIFR

Specifies that the data in the field defined by the field definition is not to be loaded into the associated column if the identifier of the field definition is an actual column name in the table. In such case, the column is set to null. Use of the FILLER or BOUNDFILLER clause is the only circumstance in which the field definition does not have to be identified by an actual column name.

Unlike the BOUNDFILLER clause, an identifier defined with the FILLER clause must not be referenced in a SQL expression. See the discussion of the *expr* parameter.

BOUNDFILLER

Specifies that the data in the field defined by the field definition is not to be loaded into the associated column if the identifier of the field definition is an actual column name in the table. In such case, the column is set to null. Use of the FILLER or BOUNDFILLER clause is the only circumstance in which the field definition does not have to be identified by an actual column name.

Unlike the FILLER clause, an identifier defined with the BOUNDFILLER clause may be referenced in a SQL expression. See the discussion of the *expr* parameter.

POSITION (start:end)

Defines the location of the field in a record in a fixed-width field data file. *start* and *end* are positive integers. The first character in the record has a start value of 1.

CHAR [(length)] | DATE [(length)] ["datemask"] | INTEGER EXTERNAL [(length)] | FLOAT EXTERNA

Field type that describes the format of the data field in data_file .

Note

Specification of a field type is optional (for descriptive purposes only) and has no effect on whether or not $EDB^*Loader$ successfully inserts the data in the field into the table column. Successful loading depends upon the compatibility of the column data type and the field value. For example, a column with data type NUM-BER(7,2) successfully accepts a field containing 2600, but if the field contains a value such as 26XX, the insertion fails and the record is written to bad_file .

Please note that ZONED data is not human-readable; ZONED data is stored in an internal format where each digit is encoded in a separate nibble/nybble/4-bit field. In each ZONED value, the last byte contains a single digit (in the high-order 4 bits) and the sign (in the low-order 4 bits).

length

Specifies the length of the value to be loaded into the associated column.

If the POSITION (start: end) clause is specified along with a fieldtype(length) clause, then the ending position of the field is overridden by the specified length value. That is, the length of the value to be loaded into the column is determined by the length value beginning at the start position, and not by the end position of the POSITION (start: end) clause. Thus, the value to be loaded into the column may be shorter than the field defined by POSITION (start: end), or it may go beyond the end position depending upon the specified length size.

If the FIELDS TERMINATED BY 'termstring' clause is specified as part of the INTO TABLE clause, and a field definition contains the fieldtype(length) clause, then a record is accepted as long as the specified *length* values are greater than or equal to the field lengths as determined by the termstring characters enclosing all such fields of the record. If the specified length value is less than a field length as determined by the enclosing termstring characters for any such field, then the record is rejected.

If the FIELDS TERMINATED BY 'termstring' clause is not specified, and the POSITION (start: end) clause is not included with a field containing the fieldtype(length) clause, then the starting position of this field begins with the next character following the ending position of the preceding field. The ending position of the preceding field is either the end of its length value if the preceding field contains the fieldtype(length) clause, or by its end parameter if the field contains the POSITION (start: end) clause without the fieldtype(length) clause.

precision

Use precision to specify the length of the ZONED value.

If the precision value specified for ZONED conflicts with the length calculated by the server based on information provided with the POSITION clause, EDB*Loader will use the value specified for precision .

scale

scale specifies the number of digits to the right of the decimal point in a ZONED value.

datemask

Specifies the ordering and abbreviation of the day, month, and year components of a date field.

Note

If the DATE field type is specified along with a SQL expression for the column, then datemask must be specified after DATE and before the SQL expression. See the following discussion of the expr parameter.

```
NULLIF field_condition [ AND field_condition ] ...
```

See the description of *field_condition* previously listed in this Parameters section for the syntax of *field_condition*.

If all field conditions evaluate to TRUE, then the column identified by column_name in the field definition is set to null. If any field condition evaluates to FALSE, then the column is set to the appropriate value as would normally occur according to the field definition.

PRESERVE BLANKS

For the column on which this option appears, retains leading white space when the optional enclosure delimiters are not present and leaves trailing white space intact when fields are specified with a predetermined size. When omitted, the default behavior is to trim leading and trailing white space.

expr

A SQL expression returning a scalar value that is type-compatible with the column data type to which it is assigned in a field definition. Double quotes must enclose expr . expr may contain a reference to any column in the field list (except for fields with the FILLER clause) by prefixing the column name by a colon character (:).

expr may also consist of a SQL SELECT statement. If a SELECT statement is used then the following rules must apply:

- The SELECT statement must be enclosed within parentheses (SELECT ...)
- The select list must consist of exactly one expression following the SELECT keyword.
- The result set must not return more than one row. If no rows are returned, then the returned value of the resulting expression is null.

The following is the syntax for use of the SELECT statement:

```
"(SELECT expr [ FROM table_list [ WHERE condition ] ])"
```

Note

Omitting the FROM table_list clause is not compatible with Oracle databases. If no tables need to be specified, use of the FROM DUAL clause is compatible with Oracle databases.

EDB Loader Control File Examples

The following are some examples of control files and their corresponding data files.

Delimiter-Separated Field Data File

The following control file uses a delimiter-separated data file that appends rows to the emp table:

```
LOAD DATA
INFILE 'emp.dat'
BADFILE 'emp.bad'
```

```
APPEND
INTO TABLE emp
FIELDS TERMINATED BY ',' OPTIONALLY ENCLOSED BY '"'
TRAILING NULLCOLS
(
empno,
ename,
job,
mgr,
hiredate,
sal,
deptno,
comm
)
```

In the preceding control file, the APPEND clause is used to allow the insertion of additional rows into the emp table.

The following is the corresponding delimiter-separated data file:

```
9101,ROGERS,CLERK,7902,17-DEC-10,1980.00,20
9102,PETERSON,SALESMAN,7698,20-DEC-10,2600.00,30,2300.00
9103,WARREN,SALESMAN,7698,22-DEC-10,5250.00,30,2500.00
9104,"JONES, JR.",MANAGER,7839,02-APR-09,7975.00,20
```

The use of the TRAILING NULLCOLS clause allows the last field supplying the comm column to be omitted from the first and last records. The comm column is set to null for the rows inserted from these records.

The double quotation mark enclosure character surrounds the value JONES, JR. in the last record since the comma delimiter character is part of the field value.

The following query displays the rows added to the table after the EDB*Loader session:

SELECT * FROM emp WHERE empno > 9100;

		ename		3		_									•
	-+		-+		+		+					•	+	-+-	
9101		ROGERS		CLERK	-	7902	-	17-DEC-10	00:00:00	0	1980.00		1	-	20
9102	1	PETERSON	-	SALESMAN	1	7698	1	20-DEC-10	00:00:00	0	2600.00		12300.00	1	30
9103	1	WARREN		SALESMAN	-	7698	-	22-DEC-10	00:00:00	0	5250.00		12500.00	ı	30
9104	1	JONES, JR.	-	MANAGER	1	7839	1	02-APR-09	00:00:00	0	7975.00		1	-	20
(4 rov	vs [°]) ´													

Fixed-Width Field Data File

The following example is a control file that loads the same rows into the emp table, but uses a data file containing fixed-width fields:

```
LOAD DATA
INFILE 'emp_fixed.dat'
BADFILE 'emp_fixed.bad'
APPEND
INTO TABLE emp
TRAILING NULLCOLS
(
empno POSITION (1:4),
ename POSITION (5:14),
job POSITION (15:23),
mgr POSITION (24:27),
hiredate POSITION (28:38),
sal POSITION (39:46),
deptno POSITION (47:48),
comm POSITION (49:56)
)
```

In the preceding control file, the FIELDS TERMINATED BY and OPTIONALLY ENCLOSED BY clauses are absent. Instead, each field now includes the POSITION clause.

The following is the corresponding data file containing fixed-width fields:

```
9101ROGERS CLERK 790217-DEC-10 1980.0020
9102PETERSON SALESMAN 769820-DEC-10 2600.0030 2300.00
9103WARREN SALESMAN 769822-DEC-10 5250.0030 2500.00
9104JONES, JR.MANAGER 783902-APR-09 7975.0020
```

Single Physical Record Data File – RECORDS DELIMITED BY Clause

The following example is a control file that loads the same rows into the emp table, but uses a data file with one physical record. Each individual record that is to be loaded as a row in the table is terminated by the semicolon character (;) specified by the RECORDS DELIMITED BY clause.

```
LOAD DATA
  INFILE 'emp_recdelim.dat'
    BADFILE 'emp_recdelim.bad'
APPEND
INTO TABLE emp
  FIELDS TERMINATED BY ',' OPTIONALLY ENCLOSED BY '"'
  RECORDS DELIMITED BY ';'
  TRAILING NULLCOLS
(
  empno,
  ename,
  job,
  mgr,
  hiredate,
  sal,
  deptno,
  comm
)
```

The following is the corresponding data file. The content is a single, physical record in the data file. The record delimiter character is included following the last record (that is, at the end of the file).

```
9101,ROGERS,CLERK,7902,17-DEC-10,1980.00,20,;9102,PETERSON,SALESMAN,7698,20-DEC-10,2600.00,30,2300.00;9103,WARREN,SALESMAN,7698,22-DEC-10,5250.00,30,2500.00;9104,"JONES, JR.",MANAGER,7839,02-APR-09,7975.00,20,;
```

FILLER Clause

The following control file illustrates the use of the FILLER clause in the data fields for the sal and comm columns. EDB*Loader ignores the values in these fields and sets the corresponding columns to null.

```
LOAD DATA
  INFILE
                'emp_fixed.dat'
                'emp_fixed.bad'
    BADFILE
APPEND
INTO TABLE emp
  TRAILING NULLCOLS
(
               POSITION (1:4),
  empno
               POSITION (5:14)
  ename
               POSITION (15:23),
  job
               POSITION (24:27),
  mar
              POSITION (28:38),
  hiredate
               FILLER POSITION (39:46),
  sal
  deptno
               POSITION (47:48),
               FILLER POSITION (49:56)
  comm
)
```

Using the same fixed-width data file as in the prior fixed-width field example, the resulting rows in the table appear as follows:

SELECT * FROM emp WHERE empno > 9100;

							hiredate 				•
	•	•		•		•	17-DEC-10 00:00:00	•			 20
9102	I PETERSON	I S	ALESMAN	1	7698	1	20-DEC-10 00:00:00	1	I		30
9103	I WARREN	I S	ALESMAN	1	7698	1	22-DEC-10 00:00:00	1	I		30
9104	I JONES, JR.	I M	IANAGER	1	7839	1	02-APR-09 00:00:00	1	I		20
(4 row	vs)										

BOUNDFILLER Clause

The following control file illustrates the use of the BOUNDFILLER clause in the data fields for the job and mgr columns. EDB*Loader ignores the values in these fields and sets the corresponding columns to null in the same manner as the FILLER clause. However, unlike columns with the FILLER clause, columns with the BOUNDFILLER clause are permitted to be used in an expression as shown for column jobdesc.

```
LOAD DATA
  INFILE
            'emp.dat'
    BADFILE 'emp.bad'
APPEND
INTO TABLE empjob
   FIELDS TERMINATED BY ',' OPTIONALLY ENCLOSED BY '"'
   TRAILING NULLCOLS
(
   empno,
   ename,
   job
                BOUNDFILLER,
                 BOUNDFILLER,
   mar
   hiredate
                FILLER,
   sal
                 FILLER,
   deptno
                FILLER,
                 FILLER,
   comm
                 ":job | | ' for manager ' | | :mgr"
   iobdesc
)
The following is the delimiter-separated data file used in this example.
9101, ROGERS, CLERK, 7902, 17-DEC-10, 1980.00, 20
9102, PETERSON, SALESMAN, 7698, 20-DEC-10, 2600.00, 30, 2300.00
9103, WARREN, SALESMAN, 7698, 22-DEC-10, 5250.00, 30, 2500.00
9104, "JONES, JR.", MANAGER, 7839, 02-APR-09, 7975.00, 20
The following table is loaded using the preceding control file and data file.
CREATE TABLE empjob (
                     NUMBER(4) NOT NULL CONSTRAINT empjob_pk PRIMARY KEY,
empno
ename
                     VARCHAR2(10),
job
                     VARCHAR2(9),
                     NUMBER(4)
mgr
jobdesc
                     VARCHAR2(25)
);
The resulting rows in the table appear as follows:
SELECT * FROM empjob;
                   l job l mgr l
                                           jobdesc
empno l
           ename
9101 | ROGERS
                   I CLERK for manager 7902
                                I SALESMAN for manager 7698
9102 | PETERSON
9103 | WARREN
                                I SALESMAN for manager 7698
9104 | JONES, JR. |
                                I MANAGER for manager 7839
                          1
```

Field Types with Length Specification

The following example is a control file that contains the field type clauses with the length specification:

```
LOAD DATA
  INFILE 'emp_fixed.dat'
    BADFILE 'emp_fixed.bad'
APPEND
INTO TABLE emp
  TRAILING NULLCOLS
  empno
               CHAR(4),
               CHAR(10),
  ename
  job
               POSITION (15:23) CHAR(9),
               INTEGER EXTERNAL(4),
  mgr
               DATE(11) "DD-MON-YY"
  hiredate
  sal
               DECIMAL EXTERNAL(8),
               POSITION (47:48),
  deptno
               POSITION (49:56) DECIMAL EXTERNAL(8)
  COMM
)
```

Note

The POSITION clause and the *fieldtype*(*length*) clause can be used individually or in combination as long as each field definition contains at least one of the two clauses.

The following is the corresponding data file containing fixed-width fields:

```
9101ROGERS
               CLERK
                           790217-DEC-10
                                           1980.0020
9102PETERSON
               SALESMAN
                           769820-DEC-10
                                          2600.0030
                                                      2300.00
9103WARREN
               SALESMAN
                           769822-DEC-10
                                           5250,0030
                                                      2500.00
                                          7975.0020
                           783902-APR-09
9104JONES, JR. MANAGER
```

The resulting rows in the table appear as follows:

```
SELECT * FROM emp WHERE empno > 9100;
empno l
                        job
                              hiredate
                                                           1
                                                                      l comm
                                                                               Ideptno
          ename
                                 mgr l
                                                               sal
9101 | ROGERS
                   I CLERK
                               | 7902 | 17-DEC-10 00:00:00 | 1980.00 |
                                                                                  20
9102 | PETERSON
                   | SALESMAN | 7698 | 20-DEC-10 00:00:00 | 2600.00 |2300.00 |
                                                                                  30
9103
      I WARREN
                   | SALESMAN | 7698 | 22-DEC-10 00:00:00 | 5250.00 |2500.00 |
                                                                                  30
9104 | JONES, JR. | MANAGER | 7839 | 02-APR-09 00:00:00 | 7975.00 |
                                                                                  20
(4 rows)
```

NULLIF Clause

The following example uses the NULLIF clause on the sal column to set it to null for employees of job MANAGER as well as on the comm column to set it to null if the employee is not a SALESMAN and is not in department 30. In other words, a comm value is accepted if the employee is a SALESMAN or is a member of department 30.

The following is the control file:

```
LOAD DATA
             'emp_fixed_2.dat'
  INFILE
    BADFILE 'emp_fixed_2.bad'
APPEND
INTO TABLE emp
  TRAILING NULLCOLS
(
              POSITION (1:4),
  empno
              POSITION (5:14)
  ename
              POSITION (15:23),
  job
              POSITION (24:27),
  mgr
              POSITION (28:38),
  hiredate
              POSITION (39:46) NULLIF job = 'MANAGER',
  sal
              POSITION (47:48),
  deptno
```

```
POSITION (49:56) NULLIF job <> 'SALESMAN' AND deptno <> '30'
  comm
)
The following is the corresponding data file:
9101ROGERS
                  CLERK
                                 790217-DEC-10
                                                     1980.0020
9102PETERSON
                   SALESMAN
                                 769820-DEC-10
                                                     2600.0030
                                                                    2300.00
                                                                    2500.00
9103WARREN
                  SALESMAN
                                 769822-DEC-10
                                                     5250.0030
                                 783902-APR-09
                                                     7975.0020
9104JONES, JR.
                  MANAGER
9105ARNOLDS
                                 778213-SEP-10
                                                     3750.0030
                                                                    800.00
                  CLERK
9106JACKSON
                  ANALYST
                                 756603-JAN-11
                                                     4500.0040
                                                                    2000.00
9107MAXWELL
                  SALESMAN
                                 769820-DEC-10
                                                     2600.0010
                                                                    1600.00
The resulting rows in the table appear as follows:
```

```
SELECT empno, ename, job, NVL(TO_CHAR(sal),'--null--') "sal"
NVL(TO_CHAR(comm),'--null--') "comm", deptno FROM emp WHERE empno > 9100;
```

empno I ename		_					•
9104 JONES, JR. 9105 ARNOLDS	1 1 1 1 1	CLERK SALESMAN SALESMAN MANAGER CLERK ANALYST	1 1 1 1 1	1980.00 2600.00 5250.00 null 3750.00 4500.00	null 2300.00 2500.00	 	20

Note

The sal column for employee JONES, JR. is null since the job is MANAGER.

The comm values from the data file for employees PETERSON, WARREN, ARNOLDS, and MAXWELL are all loaded into the comm column of the emp table since these employees are either SALESMAN or members of department 30.

The comm value of 2000.00 in the data file for employee JACKSON is ignored and the comm column of the emp table set to null since this employee is neither a SALESMAN nor is a member of department 30.

SELECT Statement in a Field Expression

The following example uses a SELECT statement in the expression of the field definition to return the value to be loaded into the column.

```
LOAD DATA
  INFILE
             'emp_fixed.dat'
    BADFILE 'emp_fixed.bad'
APPEND
INTO TABLE emp
  TRAILING NULLCOLS
              POSITION (1:4),
  empno
  ename
              POSITION (5:14),
              POSITION (15:23) "(SELECT dname FROM dept WHERE deptno = :deptno)",
  job
              POSITION (24:27),
  mgr
              POSITION (28:38),
  hiredate
  sal
              POSITION (39:46),
              POSITION (47:48),
  deptno
  comm
              POSITION (49:56)
)
```

The content of the dept table used in the SELECT statement is the following:

```
SELECT * FROM dept;
```

The following is the corresponding data file:

```
9101ROGERS
               CLERK
                         790217-DEC-10
                                           1980.0020
9102PETERSON
               SALESMAN
                                           2600.0030
                                                       2300.00
                         769820-DEC-10
9103WARREN
               SALESMAN
                         769822-DEC-10
                                           5250.0030
                                                       2500.00
9104JONES, JR. MANAGER
                         783902-APR-09
                                           7975.0020
```

The resulting rows in the table appear as follows:

SELECT * FROM emp WHERE empno > 9100;

•	l ename		_		_									•
9101 9102 9103	PETERSON WARREN JONES, JR.		RESEARCH SALES SALES	 	7902 7698 7698		17-DEC-10 20-DEC-10 22-DEC-10	00:00:00 00:00:00 00:00:00) 	1980.00 2600.00 5250.00	 	2300.00 2500.00	1	20 30 30 30 20

Note

The job column contains the value from the dname column of the dept table returned by the SELECT statement instead of the job name from the data file.

Multiple INTO TABLE Clauses

The following example illustrates the use of multiple INTO TABLE clauses. For this example, two empty tables are created with the same data definition as the emp table. The following CREATE TABLE commands create these two empty tables, while inserting no rows from the original emp table:

```
CREATE TABLE emp_research AS SELECT * FROM emp WHERE deptno = 99; CREATE TABLE emp_sales AS SELECT * FROM emp WHERE deptno = 99;
```

The following control file contains two INTO TABLE clauses. Also note that there is no APPEND clause so the default operation of INSERT is used, which requires that tables emp_research and emp_sales be empty.

```
LOAD DATA
                 'emp_multitbl.dat'
  INFILE
                 'emp_multitbl.bad'
    BADFILE
    DISCARDFILE 'emp_multitbl.dsc'
INTO TABLE emp_research
    WHEN (47:48) = '20'
    TRAILING NULLCOLS
(
                POSITION (1:4),
    empno
                POSITION (5:14),
    ename
                POSITION (15:23),
    job
               POSITION (24:27),
    mgr
    hiredate
                POSITION (28:38),
    sal
                POSITION (39:46),
    deptno
                CONSTANT '20'.
                POSITION (49:56)
    comm
)
    INTO TABLE emp_sales
    WHEN (47:48) = '30'
```

```
TRAILING NULLCOLS
(
               POSITION (1:4),
    empno
               POSITION (5:14),
    ename
               POSITION (15:23),
    job
               POSITION (24:27),
    mgr
              POSITION (28:38),
    hiredate
               POSITION (39:46),
    sal
               CONSTANT '30'.
    deptno
               POSITION (49:56) "ROUND(:comm + (:sal * .25), 0)"
    comm
)
```

The WHEN clauses specify that when the field designated by columns 47 thru 48 contains 20 , the record is inserted into the emp_research table and when that same field contains 30, the record is inserted into the emp_sales table. If neither condition is true, the record is written to the discard file named emp_multitbl.dsc .

The CONSTANT clause is given for column deptno so the specified constant value is inserted into deptno for each record. When the CONSTANT clause is used, it must be the only clause in the field definition other than the column name to which the constant value is assigned.

Finally, column of the emp_sales table is assigned a SQL expression. Column names may be referenced in the expression by prefixing the column name with a colon character (:).

The following is the corresponding data file:

```
9101ROGERS
               CLERK
                          790217-DEC-10
                                          1980.0020
9102PETERSON
               SALESMAN
                          769820-DEC-10
                                          2600.0030
                                                      2300.00
9103WARREN
               SALESMAN
                          769822-DEC-10
                                          5250.0030
                                                      2500.00
9104JONES, JR. MANAGER
                          783902-APR-09
                                          7975.0020
9105ARNOLDS
               CLERK
                          778213-SEP-10
                                          3750.0010
9106JACKSON
               ANALYST
                          756603-JAN-11
                                          4500.0040
```

Since the records for employees ARNOLDS and JACKSON contain 10 and 40 in columns 47 thru 48, which do not satisfy any of the WHEN clauses, EDB*Loader writes these two records to the discard file, emp_multitbl.dsc , whose content is shown by the following:

```
9105ARNOLDS CLERK 778213-SEP-10 3750.0010
9106JACKSON ANALYST 756603-JAN-11 4500.0040
```

The following are the rows loaded into the emp_research and emp_sales tables:

SELECT * FROM emp_research;

empno l ename	-	l mgr l	hiredate		l comm deptno
9101 ROGERS	l CLERK	i 7902 i	17-DEC-10 00:00:00	1980.00 7975.00	20.00
SELECT * FROM emp_s	sales;				
empno ename	job	mgr	hiredate I		comm deptno
-	5.1. = 51.1.1.1.1.1.1.1.1.1.1.1.1.1.1.1.1.1.1.	7000 1	20 25 40 00 00 00 1		
9102 PETERSON 9103 WARREN (2 rows)	SALESMAN SALESMAN		20-DEC-10 00:00:00 22-DEC-10 00:00:00		2950.00 30.00 3813.00 30.00

Invoking EDB*Loader

You must have superuser privileges to run EDB*Loader. Use the following command to invoke EDB*Loader from the command line:

```
edbldr [ -d dbname ] [ -p port ] [ -h host ]
[ USERID={ username/password | username/ | username | / } ]
CONTROL=control_file
[ DATA=data_file ]
[ BAD=bad_file]
[ DISCARD=discard_file ]
[ DISCARDMAX=max_discard_recs ]
[ LOG=log_file ]
[ PARFILE=param_file ]
□ DIRECT={ FALSE | TRUE } □
FREEZE={ FALSE | TRUE } ]
[ ERRORS=error_count ]
[ PARALLEL={ FALSE | TRUE } ]
 ROWS=n ]
[ SKIP=skip_count ]
[ SKIP_INDEX_MAINTENANCE={ FALSE | TRUE } ]
[ edb_resource_group=group_name ]
```

Description

If the _-d option, the _-p option, or the _-h option are omitted, the defaults for the database, port, and host are determined according to the same rules as other Advanced Server utility programs such as _edb-psql , for example.

Any parameter listed in the preceding syntax diagram except for the -d option, -p option, -h option, and the PARFILE parameter may be specified in a parameter file. The parameter file is specified on the command line when edbldr is invoked using PARFILE=param_file. Some parameters may be specified in the OPTIONS clause in the control file. For more information on the control file, see Building the EDB*Loader Control File

-building_the_edb_loader_control_file>.

The specification of control_file , data_file , bad_file , discard_file , log_file , and param_file may include the full directory path or a relative directory path to the file name. If the file name is specified alone or with a relative directory path, the file is assumed to exist (in the case of control_file , data_file , or param_file), or to be created (in the case of bad_file , discard_file , or log_file) relative to the current working directory from which edbldr is invoked.

Note

The control file must exist in the character set encoding of the client where <code>edbldr</code> is invoked. If the client is in a different encoding than the database encoding, then the <code>PGCLIENTENCODING</code> environment variable must be set on the client to the client's encoding prior to invoking <code>edbldr</code>. This must be done to ensure character set conversion is properly done between the client and the database server.

The operating system account used to invoke edbldr must have read permission on the directories and files specified by *control_file*, *data_file*, and *param_file*.

The operating system account enterprised must have write permission on the directories where *bad_file*, *discard_file*, and *log_file* are to be written.

Note

The file names for *control_file*, *data_file*, *bad_file*, *discard_file*, and *log_file* should include extensions of .ctl , .dat , .bad , .dsc , and .log , respectively. If the provided file name does not contain an extension, EDB*Loader assumes the actual file name includes the appropriate aforementioned extension.

Parameters

dbname

Name of the database containing the tables to be loaded.

port

Port number on which the database server is accepting connections.

host

IP address of the host on which the database server is running.

USERID={ username/password | username/ | username | / }

EDB*Loader connects to the database with username . username must be a superuser. password is the password for username .

If the USERID parameter is omitted, EDBLoader prompts for username and password. If USERID= <username>/ is specified, then EDBLoader 1) uses the password file specified by environment variable PGPASSFILE if PGPASSFILE is set, or 2) uses the .pgpass password file (pgpass.conf on Windows systems) if PGPASSFILE is not set. If USERID=<username> is specified, then EDB*Loader prompts for password. If USERID=/ is specified, the connection is attempted using the operating system account as the user name.

Note

The Advanced Server connection environment variables PGUSER and PGPASSWORD are ignored by EDB*Loader. See the PostgreSQL core documentation for information on the PGPASSFILE environment variable and the password file.

CONTROL=control_file

control_file specifies the name of the control file containing EDB*Loader directives. If a file extension is not specified, an extension of .ctl is assumed.

For more information on the control file, see Building the EDB*Loader Control File <building_the_edb_l

DATA=data_file

data_file specifies the name of the file containing the data to be loaded into the target table. If a file extension is not specified, an extension of .dat is assumed. Specifying a data_file on the command line overrides the INFILE clause specified in the control file.

For more information about <code>data_file</code>, see <code>Building the EDB*Loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader Control File <building_the_edb_loader C</code>

BAD=bad_file

bad_file specifies the name of a file that receives input data records that cannot be loaded due to errors. Specifying a bad_file on the command line overrides any BADFILE clause specified in the control file.

 $\hbox{For more information about } \textit{bad_file}, \hbox{see} \quad \hbox{Building the EDB*Loader Control File $$<$$building_the_edb_loader. } \\$

DISCARD=discard_file

discard_file is the name of the file that receives input data records that do not meet any table's selection criteria. Specifying a *discard_file* on the command line overrides the DISCARDFILE clause in the control file.

For more information about discard_file, see Building the EDB*Loader Control File <building_the_o

DISCARDMAX=max_discard_recs

max_discard_recs is the maximum number of discarded records that may be encountered from the input data records before terminating the EDB*Loader session. Specifying max_discard_recs on the command line overrides the DISCARDMAX or DISCARDS clause in the control file.

For more information about max_discard_recs, see Building the EDB*Loader Control File <building_the

LOG=log_file

log_file specifies the name of the file in which EDB*Loader records the results of the EDB*Loader session.

If the LOG parameter is omitted, EDBLoader creates a log file with the name control_file_base .log in the directory from which edbldr is invoked. control_file_base is the base name of the control file used in the EDBLoader session. The operating system account enterprised must have write permission on the directory where the log file is to be written.

PARFILE=param_file

param_file specifies the name of the file that contains command line parameters for the EDB*Loader session. Any command line parameter listed in this section except for the -d , -p , and -h options, and the PARFILE parameter itself, can be specified in param_file instead of on the command line.

Any parameter given in *param_file* overrides the same parameter supplied on the command line before the PARFILE option. Any parameter given on the command line that appears after the PARFILE option overrides the same parameter given in *param_file*.

Note

Unlike other EDB*Loader files, there is no default file name or extension assumed for* param_file, though by Oracle SQLLoader convention, .par is typically used, but not required, as an extension.

DIRECT= { FALSE | TRUE }

If DIRECT is set to TRUE EDB*Loader performs a direct path load instead of a conventional path load. The default value of DIRECT is FALSE.

For information about direct path loads, see [Direct Path Load](01_edb_loader#direct_path_load).

FREEZE= { FALSE | TRUE }

Set FREEZE to TRUE to indicate that the data should be copied with the rows *frozen*. A tuple guaranteed to be visible to all current and future transactions is marked as frozen to prevent transaction ID wrap-around. For more information about frozen tuples, see the PostgreSQL core documentation at:

https://www.postgresgl.org/docs/12/static/routine-vacuuming.html

You must specify a data-loading type of TRUNCATE in the control file when using the FREEZE option. FREEZE is not supported for direct loading.

By default, FREEZE is FALSE .

ERRORS=error_count

error_count specifies the number of errors permitted before aborting the EDB*Loader session. The default is 50 .

PARALLEL= { FALSE | TRUE }

Set PARALLEL to TRUE to indicate that this EDB*Loader session is one of a number of concurrent EDB*Loader sessions participating in a parallel direct path load. The default value of PARALLEL is FALSE.

When PARALLEL is TRUE, the DIRECT parameter must also be set to TRUE. For more information about parallel direct path loads, see [Parallel Direct Path Load](01_edb_loader#parallel_direct_path_load).

ROWS=n

n specifies the number of rows that EDB*Loader will commit before loading the next set of n rows.

SKIP=skip_count

Number of records at the beginning of the input data file that should be skipped before loading begins. The default is 0.

```
SKIP_INDEX_MAINTENANCE= { FALSE | TRUE }
```

If set to TRUE, index maintenance is not performed as part of a direct path load, and indexes on the loaded table are marked as invalid. The default value of SKIP_INDEX_MAINTENANCE is FALSE.

During a parallel direct path load, target table indexes are not updated, and are marked as invalid after the load is complete.

You can use the REINDEX command to rebuild an index. For more information about the REINDEX command, see the PostgreSQL core documentation.

```
edb_resource_group=group_name
```

group_name specifies the name of an EDB Resource Manager resource group to which the EDB*Loader session is to be assigned.

Any default resource group that may have been assigned to the session (for example, a database user running the EDB*Loader session who had been assigned a default resource group with the ALTER ROLE ... SET edb_resource_group command) is overridden by the resource group given by the edb_resource_group parameter specified on the edbldr command line.

Examples

In the following example EDB*Loader is invoked using a control file named emp.ctl located in the current working directory to load a table in database edb:

```
$ /usr/edb/as12/bin/edbldr -d edb USERID=enterprisedb/password
CONTROL=emp.ctl
EDB*Loader: Copyright (c) 2007-2018, EnterpriseDB Corporation.
```

Successfully loaded (4) records

In the following example, EDB*Loader prompts for the user name and password since they are omitted from the command line. In addition, the files for the bad file and log file are specified with the BAD and LOG command line parameters.

```
$ /usr/edb/as12/bin/edbldr -d edb CONTROL=emp.ctl BAD=/tmp/emp.bad
LOG=/tmp/emp.log
Enter the user name : enterprisedb
Enter the password :
EDB*Loader: Copyright (c) 2007-2018, EnterpriseDB Corporation.
```

```
Successfully loaded (4) records
```

The following example runs EDB*Loader with the same parameters as shown in the preceding example, but using a parameter file located in the current working directory. The SKIP and ERRORS parameters are altered from their defaults in the parameter file as well. The parameter file, emp.par, contains the following:

```
CONTROL=emp.ctl
BAD=/tmp/emp.bad
LOG=/tmp/emp.log
SKIP=1
ERRORS=10
```

EDB*Loader is invoked with the parameter file as shown by the following:

\$ /usr/edb/as12/bin/edbldr -d edb PARFILE=emp.par

Enter the user name : enterprisedb

Enter the password:

EDB*Loader: Copyright (c) 2007-2018, EnterpriseDB Corporation.

Successfully loaded (3) records

Exit Codes

When EDB*Loader exits, it will return one of the following codes:

Exit Code	Description
0	Indicates that all rows loaded successfully.
1	Indicates that EDB*Loader encountered command line or syntax errors, or aborted the load operation due to a
2	Indicates that the load completed, but some (or all) rows were rejected or discarded.
3	Indicates that EDB*Loader encountered fatal errors (such as OS errors). This class of errors is equivalent to the

Direct Path Load

During a direct path load, EDB*Loader writes the data directly to the database pages, which is then synchronized to disk. The insert processing associated with a conventional path load is bypassed, thereby resulting in a performance improvement.

Bypassing insert processing reduces the types of constraints that may exist on the target table. The following types of constraints are permitted on the target table of a direct path load:

- · Primary key
- · Not null constraints
- Indexes (unique or non-unique)

The restrictions on the target table of a direct path load are the following:

- Triggers are not permitted
- · Check constraints are not permitted
- · Foreign key constraints on the target table referencing another table are not permitted
- Foreign key constraints on other tables referencing the target table are not permitted
- The table must not be partitioned
- · Rules may exist on the target table, but they are not executed

Note

Currently, a direct path load in EDB*Loader is more restrictive than in Oracle SQL*Loader. The preceding restrictions do not apply to Oracle SQL*Loader in most cases. The following restrictions apply to a control file used in a direct path load:

- Multiple table loads are not supported. That is, only one INTO TABLE clause may be specified in the control file.
- SQL expressions may not be used in the data field definitions of the INTO TABLE clause.
- The FREEZE option is not supported for direct path loading.

To run a direct path load, add the DIRECT=TRUE option as shown by the following example:

 $\$ /usr/edb/as12/bin/edbldr -d edb USERID=enterprisedb/password CONTROL=emp.ctl DIRECT=TRUE

EDB*Loader: Copyright (c) 2007-2018, EnterpriseDB Corporation.

Successfully loaded (4) records

Parallel Direct Path Load

The performance of a direct path load can be further improved by distributing the loading process over two or more sessions running concurrently. Each session runs a direct path load into the same table.

Since the same table is loaded from multiple sessions, the input records to be loaded into the table must be divided amongst several data files so that each EDB*Loader session uses its own data file and the same record is not loaded more than once into the table.

The target table of a parallel direct path load is under the same restrictions as a direct path load run in a single session.

The restrictions on the target table of a direct path load are the following:

- · Triggers are not permitted
- · Check constraints are not permitted
- Foreign key constraints on the target table referencing another table are not permitted
- · Foreign key constraints on other tables referencing the target table are not permitted
- The table must not be partitioned
- · Rules may exist on the target table, but they are not executed

In addition, the APPEND clause must be specified in the control file used by each EDB*Loader session.

To run a parallel direct path load, run EDBLoader in a separate session for each participant of the parallel direct path load. Invocation of each such EDBLoader session must include the DIRECT=TRUE and PARALLEL=TRUE parameters.

Each EDB*Loader session runs as an independent transaction so if one of the parallel sessions aborts and rolls back its changes, the loading done by the other parallel sessions are not affected.

Note: In a parallel direct path load, each EDB*Loader session reserves a fixed number of blocks in the target table in a round-robin fashion. Some of the blocks in the last allocated chunk may not be used, and those blocks remain uninitialized. A subsequent use of the VACUUM command on the target table may show warnings regarding these uninitialized blocks such as the following:

```
WARNING: relation "emp" page 98264 is uninitialized --- fixing WARNING: relation "emp" page 98265 is uninitialized --- fixing WARNING: relation "emp" page 98266 is uninitialized --- fixing This is an expected behavior and does not indicate data corruption.
```

Indexes on the target table are not updated during a parallel direct path load and are therefore marked as invalid after the load is complete. You must use the REINDEX command to rebuild the indexes.

The following example shows the use of a parallel direct path load on the emp table.

Note

If you attempt a parallel direct path load on the sample emp table provided with Advanced Server, you must first remove the triggers and constraints referencing the emp table. In addition the primary key column, empno , was expanded from NUMBER(4) to NUMBER in this example to allow for the insertion of a larger number of rows.

The following is the control file used in the first session:

```
LOAD DATA
             '/home/user/loader/emp_parallel_1.dat'
  INFILE
  APPEND
  INTO TABLE emp
    FIELDS TERMINATED BY ',' OPTIONALLY ENCLOSED BY '"'
    TRAILING NULLCOLS
(
  empno,
  ename,
  job,
  mgr,
  hiredate,
  sal,
  deptno.
  comm
```

```
)
The APPEND clause must be specified in the control file for a parallel direct path load.
The following shows the invocation of EDB*Loader in the first session. The DIRECT=TRUE
                                                                                           and
PARALLEL=TRUE parameters must be specified.
$ /usr/edb/as12/bin/edbldr -d edb USERID=enterprisedb/password
CONTROL=emp_parallel_1.ctl DIRECT=TRUE PARALLEL=TRUE
WARNING: index maintenance will be skipped with PARALLEL load
EDB*Loader: Copyright (c) 2007-2018, EnterpriseDB Corporation.
The control file used for the second session appears as follows. Note that it is the same as the one used in the
first session, but uses a different data file.
LOAD DATA
  INFILE '/home/user/loader/emp_parallel_2.dat'
  APPEND
  INTO TABLE emp
    FIELDS TERMINATED BY ',' OPTIONALLY ENCLOSED BY '"'
    TRAILING NULLCOLS
(
    empno,
    ename.
    job,
    mgr,
    hiredate,
    sal,
    deptno,
    comm
)
The preceding control file is used in a second session as shown by the following:
$ /usr/edb/as12/bin/edbldr -d edb USERID=enterprisedb/password
CONTROL=emp_parallel_2.ctl DIRECT=TRUE PARALLEL=TRUE
WARNING: index maintenance will be skipped with PARALLEL load
EDB*Loader: Copyright (c) 2007-2018, EnterpriseDB Corporation.
EDB*Loader displays the following message in each session when its respective load operation completes:
Successfully loaded (10000) records
The following guery shows that the index on the emp table has been marked as INVALID:
SELECT index_name, status FROM user_indexes WHERE table_name = 'EMP';
  index_name | status
   EMP_PK
              | INVALID
 (1 row)
Note
user_indexes is the view of indexes compatible with Oracle databases owned by the current user.
Queries on the emp table will not utilize the index unless it is rebuilt using the REINDEX command as shown
by the following:
REINDEX INDEX emp_pk;
A subsequent query on user indexes shows that the index is now marked as VALID:
SELECT index_name, status FROM user_indexes WHERE table_name = 'EMP';
  index_name | status
```

EMP_PK | VALID

(1 row)

Remote Loading

EDBLoader supports a feature called remote loading. In remote loading, the database containing the table to be loaded is running on a database server on a different host than from where EDBLoader is invoked with the input data source.

This feature is useful if you have a large amount of data to be loaded, and you do not want to create a large data file on the host running the database server.

In addition, you can use the standard input feature to pipe the data from the data source such as another program or script, directly to EDBLoader, which then loads the table in the remote database. This bypasses the process of having to create a data file on disk for EDBLoader.

Performing remote loading along with using standard input requires the following:

- The edbldr program must be installed on the client host on which it is to be invoked with the data source for the EDB*Loader session.
- The control file must contain the clause INFILE 'stdin' so you can pipe the data directly into EDBLoader's standard input. For more information, see Building the EDB*Loader Control File
building for information on the INFILE clause and the EDBLoader control file.
- All files used by EDB*Loader such as the control file, bad file, discard file, and log file must reside on, or are created on, the client host on which edbldr is invoked.
- When invoking EDBLoader, use the -h option to specify the IP address of the remote database server. For more information, see Invoking EDB*Loader <invoking_edb_loader> for information on invoking EDBLoader.
- Use the operating system pipe operator (I) or input redirection operator (<) to supply the input data to EDB*Loader.

The following example loads a database running on a database server at 192.168.1.14 using data piped from a source named datasource.

```
datasource | ./edbldr -d edb -h 192.168.1.14
USERID=enterprisedb/password CONTROL=remote.ctl
```

The following is another example of how standard input can be used:

```
./edbldr -d edb -h 192.168.1.14 USERID=enterprisedb/password
CONTROL=remote.ctl < datasource</pre>
```

Updating a Table with a Conventional Path Load

You can use EDB*Loader with a conventional path load to update the rows within a table, merging new data with the existing data. When you invoke EDB*Loader to perform an update, the server searches the table for an existing row with a matching primary key:

- If the server locates a row with a matching key, it replaces the existing row with the new row.
- If the server does not locate a row with a matching key, it adds the new row to the table.

To use EDBLoader to update a table, the table must have a primary key. Please note that you cannot use EDBLoader to UPDATE a partitioned table.

To perform an UPDATE, use the same steps as when performing a conventional path load:

- 1. Create a data file that contains the rows you wish to UPDATE or INSERT .
- 2. Define a control file that uses the INFILE keyword to specify the name of the data file. For information about building the EDB*Loader control file, see Building the EDB*Loader Control File <building_the_edl
- 3. Invoke EDBLoader, specifying the database name, connection information, and the name of the control file. For information about invoking EDBLoader, see Invoking EDB*Loader <invoking_edb_loader>

433

The following example uses the emp table that is distributed with the Advanced Server sample data. By default, the table contains:

```
edb=# select * from emp;
empnolename I job I mgr I
                                hiredate |
                                               sal
                                                      I comm | deptno
----+----
7369 | SMITH | CLERK | 7902 | 17-DEC-80 00:00:00 | 800.00
                                                                20
7499 | ALLEN | SALESMAN | 7698 | 20-FEB-81 00:00:00 | 1600.00
                                                     1300.00 l
                                                                 30
1500.00 I
                                                                30
7566 | JONES | MANAGER | 7839 | 02-APR-81 00:00:00 | 2975.00
                                                                20
                                                      7654 | MARTIN| SALESMAN | 7698 | 28-SEP-81 00:00:00 | 1250.00
                                                      1400.001
                                                                30
7698 | BLAKE | MANAGER | 7839 | 01-MAY-81 00:00:00 | 2850.00
                                                        - 1
                                                                30
7782 | CLARK | MANAGER | 7839 | 09-JUN-81 00:00:00 | 2450.00
                                                      10
7788 | SCOTT | ANALYST | 7566 | 19-APR-87 00:00:00 | 3000.00
                                                            20
7839 | KING | PRESIDENT| | 17-NOV-81 00:00:00 | 5000.00
                                                                10
7844 | TURNER | SALESMAN | 7698 | 08-SEP-81 00:00:00 | 1500.00
                                                     1 0.00 1
7876 | ADAMS | CLERK | 7788 | 23-MAY-87 00:00:00 | 1100.00 |
                                                            - 1
                                                                20
7900 | JAMES | CLERK | 7698 | 03-DEC-81 00:00:00 | 950.00
                                                      30
                                                             1
7902 | FORD | ANALYST | 7566 | 03-DEC-81 00:00:00 | 3000.00
                                                                20
                                                     7934 |MILLER|CLERK
                   | 7782 | 23-JAN-82 00:00:00 | 1300.00
                                                     10
(14 rows)
```

The following control file (emp_update.ctl) specifies the fields in the table in a comma-delimited list. The control file performs an UPDATE on the emp table:

```
LOAD DATA
INFILE 'emp_update.dat'
BADFILE 'emp_update.bad'
DISCARDFILE 'emp_update.dsc'
UPDATE INTO TABLE emp
FIELDS TERMINATED BY ","
(empno, ename, job, mgr, hiredate, sal, comm, deptno)
```

The data that is being updated or inserted is saved in the emp_update.dat file. emp_update.dat contains:

```
7521, WARD, MANAGER, 7839, 22-FEB-81 00:00:00, 3000.00, 0.00, 30 7566, JONES, MANAGER, 7839, 02-APR-81 00:00:00, 3500.00, 0.00, 20 7903, BAKER, SALESMAN, 7521, 10-JUN-13 00:00:00, 1800.00, 500.00, 20 7904, MILLS, SALESMAN, 7839, 13-JUN-13 00:00:00, 1800.00, 500.00, 20 7654, MARTIN, SALESMAN, 7698, 28-SEP-81 00:00:00, 1500.00, 400.00, 30
```

Invoke EDB*Loader, specifying the name of the database (edb), the name of a database superuser (and their associated password) and the name of the control file (emp_update.ctl):

```
edbldr -d edb userid=user_name/password control=emp_update.ctl
```

After performing the update, the emp table contains:

```
edb=# select * from emp;
                                hiredate |
empnolename | job | mgr |
                                                 sal | comm | deptno
7369 | SMITH | CLERK | 7902 | 17-DEC-80 00:00:00 | 800.00 |
                                                                 20
7499 | ALLEN | SALESMAN | 7698 | 20-FEB-81 00:00:00 | 1600.00 | 300.00 |
                                                                 30
7521 | WARD | MANAGER | 7839 | 22-FEB-81 00:00:00 | 3000.00 | 0.00
                                                                 30
7566 | JONES | MANAGER | 7839 | 02-APR-81 00:00:00 | 3500.00 | 0.00
                                                               1
                                                                 20
7654 | MARTIN| SALESMAN | 7698 | 28-SEP-81 00:00:00 | 1500.00 | 400.00 |
                                                                 30
                                                             - 1
7698 | BLAKE | MANAGER | 7839 | 01-MAY-81 00:00:00 | 2850.00 |
                                                                 30
7782 | CLARK | MANAGER | 7839 | 09-JUN-81 00:00:00 | 2450.00 |
                                                                 10
7788 | SCOTT | ANALYST | 7566 | 19-APR-87 00:00:00 | 3000.00 |
                                                                 20
7839 | KING | PRESIDENT | | 17-NOV-81 00:00:00 | 5000.00 |
                                                                 10
                                                              7844 | TURNER| | SALESMAN | 7698 | 08-SEP-81 00:00:00 | 1500.00 | 0.00 |
                                                                 30
```

```
7876 IADAMS ICLERK
                      | 7788 | 23-MAY-87 00:00:00 | 1100.00 |
                                                                          20
7900 IJAMES ICLERK
                      | 7698 | 03-DEC-81 00:00:00 | 950.00 |
                                                                          30
7902 | FORD | ANALYST
                      | 7566 | 03-DEC-81 00:00:00 | 3000.00 |
                                                                          20
7903 | BAKER | SALESMAN | 7521 | 10-JUN-13 00:00:00 | 1800.00 | 500.00 |
                                                                          20
7904 | MILLS | SALESMAN | 7839 | 13-JUN-13 00:00:00 | 1800.00 |
                                                                500.00 l
                                                                          20
7934 | MILLER | CLERK
                      | 7782 | 23-JAN-82 00:00:00 | 1300.00 |
                                                                          10
(16 rows)
```

The rows containing information for the three employees that are currently in the emp table are updated, while rows are added for the new employees (BAKER and MILLS)

7.2 EDB*Wrap

The EDB*Wrap utility protects proprietary source code and programs (functions, stored procedures, triggers, and packages) from unauthorized scrutiny. The EDBWrap program translates a file that contains SPL or PL/pgSQL source code (the plaintext) into a file that contains the same code in a form that is nearly impossible to read. Once you have the obfuscated form of the code, you can send that code to the PostgreSQL server and the server will store those programs in obfuscated form. While EDB*Wrap does obscure code, table definitions are still exposed.*

Everything you wrap is stored in obfuscated form. If you wrap an entire package, the package body source, as well as the prototypes contained in the package header and the functions and procedures contained in the package body are stored in obfuscated form.

If you wrap a CREATE PACKAGE statement, you hide the package API from other developers. You may want to wrap the package body, but not the package header so users can see the package prototypes and other public variables that are defined in the package body. To allow users to see what prototypes the package contains, use EDBWrap to obfuscate only the CREATE PACKAGE BODY statement in the edbwrap input file, omitting the CREATE PACKAGE statement. The package header source will be stored plaintext, while the package body source and package functions and procedures will be stored obfuscated.

Once wrapped, source code and programs cannot be unwrapped or debugged. Reverse engineering is possible, but would be very difficult.

The entire source file is wrapped into one unit. Any psql meta-commands included in the wrapped file will not be recognized when the file is executed; executing an obfuscated file that contains a psql meta-command will cause a syntax error. edbwrap does not validate SQL source code -if the plaintext form contains a syntax error, edbwrap will not complain. Instead, the server will report an error and abort the entire file when you try to execute the obfuscated form.

Using EDB*Wrap to Obfuscate Source Code

EDB*Wrap is a command line utility; it accepts a single input source file, obfuscates the contents and returns a single output file. When you invoke the edbwrap utility, you must provide the name of the file that contains the source code to obfuscate. You may also specify the name of the file where edbwrap will write the obfuscated form of the code. edbwrap offers three different command-line styles. The first style is compatible with Oracle's wrap utility:

edbwrap iname=input_file [oname= output_file]

The iname=input_file argument specifies the name of the input file; if input_file does not contain an extension, edbwrap will search for a file named *input_file*.sql

The oname=output_file argument (which is optional) specifies the name of the output file; if output_file does not contain an extension, edbwrap will append .plb to the name.

If you do not specify an output file name, edbwrap writes to a file whose name is derived from the input file name: edbwrap strips the suffix (typically .sql) from the input file name and adds .plb.

edbwrap offers two other command-line styles that may feel more familiar:

```
edbwrap --iname input_file [--oname <output_file>]
```

```
edbwrap -i input_file [-o <output_file>]
```

You may mix command-line styles; the rules for deriving input and output file names are identical regardless of which style you use.

Once edbwrap has produced a file that contains obfuscated code, you typically feed that file into the Post-greSQL server using a client application such as edb-psql . The server executes the obfuscated code line by line and stores the source code for SPL and PL/pgSQL programs in wrapped form.

In summary, to obfuscate code with EDB*Wrap, you:

- 1. Create the source code file.
- 2. Invoke EDB*Wrap to obfuscate the code.
- 3. Import the file as if it were in plaintext form.

The following sequence demonstrates edbwrap functionality.

```
First, create the source code for the list_emp procedure (in plaintext form):
[bash] cat listemp.sql
CREATE OR REPLACE PROCEDURE list_emp
IS
     v_empno
                     NUMBER(4);
     v_ename
                     VARCHAR2(10);
     CURSOR emp_cur IS
         SELECT empno, ename FROM emp ORDER BY empno;
BEGIN
     OPEN emp_cur;
     DBMS_OUTPUT.PUT_LINE('EMPNO ENAME');
     DBMS_OUTPUT.PUT_LINE('----
     L00P
         FETCH emp_cur INTO v_empno, v_ename;
         EXIT WHEN emp_cur%NOTFOUND;
         DBMS_OUTPUT.PUT_LINE(v_empno \| \| ' \| \| v_ename);
     END LOOP;
     CLOSE emp_cur;
END;
/
You can import the list_emp procedure with a client application such as edb-psql:
[bash] edb-psql edb
Welcome to edb-psql 8.4.3.2, the EnterpriseDB interactive terminal.
Type: \copyright for distribution terms
        \\h for help with SQL commands
        \\? for help with edb-psql commands
        \\q or terminate with semicolon to execute guery
        \\q to quit
edb=# \\i listemp.sql
CREATE PROCEDURE
You can view the plaintext source code (stored in the server) by examining the pg_proc system table:
edb=# SELECT prosrc FROM pg_proc WHERE proname = 'list_emp';
                              prosrc
                      NUMBER(4);
      v_empno
      v_ename
                      VARCHAR2(10);
      CURSOR emp_cur IS
```

SELECT empno, ename FROM emp ORDER BY empno;

```
BEGIN
      OPEN emp_cur;
      DBMS_OUTPUT.PUT_LINE('EMPNO ENAME');
      DBMS_OUTPUT.PUT_LINE('----
      L00P
          FETCH emp_cur INTO v_empno, v_ename;
          EXIT WHEN emp_cur%NOTFOUND;
          DBMS_OUTPUT.PUT_LINE(v_empno \| \| ' \| \| v_ename);
      END LOOP;
      CLOSE emp_cur;
  END
(1 row)
edb=# quit
Next. obfuscate the plaintext file with EDB*Wrap:
[bash] edbwrap -i listemp.sql
EDB*Wrap Utility: Release 8.4.3.2
Copyright (c) 2004-2013 EnterpriseDB Corporation. All Rights Reserved.
Usina encodina UTF8 for input
Processing listemp.sql to listemp.plb
Examining the contents of the output file (listemp.plb) file reveals
that the code is obfuscated:
[bash] cat listemp.plb
$__EDBwrapped__$
UTF8
d+6DL30RVaGjYMIzkuoSzAOqtBw7MhYFuAFkBsfYfhdJ0rjwBv+bHr1FCyH6j9SaH
movU+bYI+jR+hR2jbzq3sovHKEyZIp9y3/GckbQgualRhIlGpyWfE0dltDUpkYRLN
/OUXmk0/P4H6EI98sAHevGDhOWI+58DjJ44qhZ+l5NNEVxbWDztpb/s5sdx4660qQ
Ozx3/qh8VkqS2JbcxYMpjmrwVr6fAXfb68Ml9mW2Hl7fNtxcb5kjSzXvfWR2XYzJf
KFNrEhbL1DTVlSEC5wE6lGlwhYvX0f22m1R2IFns0MtF9fwcnBWAs1YqjR00j6+fc
er/f/efAFh4=
$__EDBwrapped__$
```

You may notice that the second line of the wrapped file contains an encoding name (in this case, the encoding is UTF8). When you obfuscate a file, edbwrap infers the encoding of the input file by examining the locale. For example, if you are running edbwrap while your locale is set to en_US.utf8, edbwrap assumes that the input file is encoded in UTF8. Be sure to examine the output file after running edbwrap; if the locale contained in the wrapped file does not match the encoding of the input file, you should change your locale and rewrap the input file

You can import the obfuscated code into the PostgreSQL server using the same tools that work with plaintext code:

```
UTF8
dw4B9Tz69J3W0sy0GgYJQa+G2sLZ3I0yxS8pDyu0TFuiYe/EXiEatwwG3h3tdJk
ea+AIp35dS/4idbN8wpegM3s994dQ3R97NgNHfvTQn02vtd4wQtsQ/Zc4v4Lhfj
nlV+A4UpHI5oQEnXeAch2LcRD87hkU0uo1ESeQV8IrXaj9BsZr+ueR0nwhGs/Ec
pva/tRV4m9RusFn0wyr38u4Z8w4dfnPW184Y3o6It4b3aH07WxTkWrMLmOZW1jJ
Nu6u4o+ez064G9QKPazgehslv4JB9NQnuocActfDSPMY7R7anmgw
$__EDBwrapped__$
(1 row)
```

Invoke the obfuscated code in the same way that you would invoke the plaintext form:

edb=# exec list_emp;

EMPN0	ENAME
7369	SMITH
7499	ALLEN
7521	WARD
7566	JONES
7654	MARTIN
7698	BLAKE
7782	CLARK
7788	SC0TT
7839	KING
7844	TURNER
7876	ADAMS
7900	JAMES
7902	FORD
7934	MILLER

EDB-SPL Procedure successfully completed edb=# quit

When you use pg_dump to back up a database, wrapped programs remain obfuscated in the archive file.

Be aware that audit logs produced by the Postgres server will show wrapped programs in plaintext form. Source code is also displayed in plaintext in SQL error messages generated during the execution of a program.

Note

At this time, the bodies of the objects created by the following statements will not be stored in obfuscated form:

```
CREATE [OR REPLACE] TYPE <type_name> AS OBJECT
CREATE [OR REPLACE] TYPE <type_name> UNDER <type_name>
CREATE [OR REPLACE] TYPE BODY <type_name>
```

7.3 Dynamic Runtime Instrumentation Tools Architecture (DRITA)

The Dynamic Runtime Instrumentation Tools Architecture (DRITA) allows a DBA to query catalog views to determine the *wait events* that affect the performance of individual sessions or the system as a whole. DRITA records the number of times each event occurs as well as the time spent waiting; you can use this information to diagnose performance problems. DRITA offers this functionality, while consuming minimal system resources.

DRITA compares *snapshots* to evaluate the performance of a system. A snapshot is a saved set of system performance data at a given point in time. Each snapshot is identified by a unique ID number; you can use snapshot ID numbers with DRITA reporting functions to return system performance statistics.

Configuring and Using DRITA

Advanced Server's postgresql.conf file includes a configuration parameter named $timed_statistics$ that controls the collection of timing data. The valid parameter values are TRUE or FALSE; the default value is FALSE.

This is a dynamic parameter which can be modified in the postgresql.conf file, or while a session is in progress. To enable DRITA, you must either:

```
Modify the postgresql.conf file, setting the timed\_statistics parameter to TRUE .
```

Connect to the server with the EDB-PSQL client, and invoke the command:

```
SET timed_statistics = TRUE
```

After modifying the timed_statistics parameter, take a starting snapshot. A snapshot captures the current state of each timer and event counter. The server will compare the starting snapshot to a later snapshot to gauge system performance.

Use the edbsnap() function to take the beginning snapshot:

Then, run the workload that you would like to evaluate; when the workload has completed (or at a strategic point during the workload), take another snapshot:

```
edb=# SELECT * FROM edbsnap();
edbsnap
-----
Statement processed.
(1 row)
```

You can capture multiple snapshots during a session. Then, use the DRITA functions and reports to manage and compare the snapshots to evaluate performance information.

DRITA Functions

You can use DRITA functions to gather wait information and manage snapshots. DRITA functions are fully supported by Advanced Server 10 whether your installation is made compatible with Oracle databases or is made in PostgreSQL-compatible mode.

get_snaps()

```
The get_snaps() function returns a list of the current snapshots. The signature is:

get_snaps()
```

The following example demonstrates using the get_snaps() function to display a list of snapshots:

The first column in the result list displays the snapshot identifier; the second column displays the date and time that the snapshot was captured.

sys_rpt()

The sys_rpt() function returns system wait information. The signature is:

sys_rpt(\ *beginning_id*, *ending_id*, *top_n*)

Parameters

beginning_id

beginning_id is an integer value that represents the beginning session identifier.

ending_id

ending_id is an integer value that represents the ending session identifier.

top_n

top_n represents the number of rows to return

This example demonstrates a call to the sys_rpt() function:

SELECT * FROM sys_rpt(9, 10, 10);

sys_rpt

WAIT NAME	COUNT	WAIT TIME	% WAIT
wal flush wal write wal file sync query plan db file extend db file read other lwlock acquire ProcArrayLock CLogControlLock (11 rows)	8359 8358 8358 33439 54 31 0 0	1.357593 1.349153 1.286437 0.439324 0.000585 0.000307 0.000000 0.000000	30.62 30.43 29.02 9.91 0.01 0.01 0.00 0.00 0.00

The information displayed in the result set includes:

Column Name	Description
WAIT NAME	The name of the wait.
COUNT	The number of times that the wait event occurred.
WAIT TIME	The time of the wait event in seconds.
% WAIT	The percentage of the total wait time used by this wait for this session.

sess_rpt()

The sess_rpt() function returns session wait information. The signature is:

sess_rpt(beginning_id, ending_id, top_n)

Parameters

beginning_id

beginning_id is an integer value that represents the beginning session identifier.

ending_id

ending_id is an integer value that represents the ending session identifier.

top_n

top_n represents the number of rows to return

The following example demonstrates a call to the sess_rpt() function:

SELECT * FROM sess_rpt(8, 9, 10);

sess_rpt

- ID	USER	WAIT NAME	COUNT	TIME	% WAIT SES	% WAIT ALL
3501	enterprise	wal flush	8354	1.354958	30.61	30.61
	enterprise		8354	1.348192	30.46	30.46
3501	enterprise	wal file sync	8354	1.285607	29.04	29.04
3501	enterprise	query plan	33413	0.436901	9.87	9.87
3501	enterprise	db file extend	54	0.000578	0.01	0.01
3501	enterprise	db file read	56	0.000541	0.01	0.01
3501	enterprise	ProcArrayLock	0	0.000000	0.00	0.00
3501 (10 r	enterprise ows)	CLogControlLock	0	0.000000	0.00	0.00

The information displayed in the result set includes:

Column Name	Description
ID	The processID of the session.
USER	The name of the user incurring the wait.
WAIT NAME	The name of the wait event.
COUNT	The number of times that the wait event occurred.
TIME	The length of the wait event in seconds.
% WAIT SES	The percentage of the total wait time used by this wait for this session.
% WAIT ALL	The percentage of the total wait time used by this wait (for all sessions).

sessid_rpt()

The sessid_rpt() function returns session ID information for a specified backend. The signature is:

sessid_rpt(beginning_id, ending_id, backend_id)

Parameters

beginning_id

beginning_id is an integer value that represents the beginning session identifier.

ending_id

ending_id is an integer value that represents the ending session identifier.

backend_id

backend_id is an integer value that represents the backend identifier.

The following code sample demonstrates a call to sessid_rpt():

SELECT * FROM sessid_rpt(8, 9, 3501);

sessid_rpt

- ID	USER	WAIT NAME	COUNT	TIME	% WAIT SES	% WAIT ALL
-						
3501	enterprise	CLogControlLock	0	0.000000	0.00	0.00
3501	enterprise	ProcArrayLock	0	0.000000	0.00	0.00
3501	enterprise	db file read	56	0.000541	0.01	0.01
3501	enterprise	db file extend	54	0.000578	0.01	0.01
3501	enterprise	query plan	33413	0.436901	9.87	9.87
3501	enterprise	wal file sync	8354	1.285607	29.04	29.04
3501	enterprise	wal write	8354	1.348192	30.46	30.46
3501 (10 r	enterprise ows)	wal flush	8354	1.354958	30.61	30.61

The information displayed in the result set includes:

Column Name	Description
ID	The process ID of the wait.
USER	The name of the user that owns the session.
WAIT NAME	The name of the wait event.
COUNT	The number of times that the wait event occurred.
TIME	The length of the wait in seconds.
% WAIT SES	The percentage of the total wait time used by this wait for this session.
% WAIT ALL	The percentage of the total wait time used by this wait (for all sessions).

sesshist_rpt()

The sesshist_rpt() function returns session wait information for a specified backend. The signature is:

sesshist_rpt(snapshot_id, session_id)

Parameters

snapshot_id

snapshot_id is an integer value that identifies the snapshot.

session_id

session_id is an integer value that represents the session.

The following example demonstrates a call to the sesshist_rpt() function:

Note

The following example has been shortened; over 1300 rows were actually generated.

SELECT * FROM sesshist_rpt (9, 3501);

sesshist_rpt

- ID Sum of	USER Blks	SEQ	WAIT NAME	ELAPSED	File	Name	# of	Blk
_								
3501 e 0	nterpris	e 1	query plan	13	0	N/A	0	
3501 e	nterpris	e 1	query plan	13	0	edb_password_histor	'y 0	
•	nterpris	e 1	query plan	13	0	edb_profile_passwor	d 0	

0								
_	enterprise	1	quer	y plan	13	0	edb_resource_group	0
-	enterprise	1	quer	y plan	13	0	edb_resource_group_n	0
-	enterprise	1	quer	y plan	13	0	edb_resource_group_o	0
-	enterprise	1	quer	y plan	13	0	pg_attribute	0
-	enterprise	1	quer	y plan	13	0	pg_attribute_relid_a	0
-	enterprise	1	quer	y plan	13	0	pg_auth_members	0
-	enterprise	1	quer	y plan	13	0	pg_auth_members_memb	0
-	enterprise	1	quer	y plan	13	0	pg_auth_members_role	0
Ü					•			
					•			
3501 0	enterprise	3	wal	write	148	0	N/A	0
-	enterprise	3	wal	write	148	0	edb_password_history	0
•	enterprise	3	wal	write	148	0	edb_password_history	0
•	enterprise	3	wal	write	148	0	edb_password_history	0
•	enterprise	3	wal	write	148	0	edb_profile	0
3501 0	enterprise	3	wal	write	148	0	edb_profile_name_ind	0
3501 0	enterprise	3	wal	write	148	0	edb_resource_group_n	0
3501 0	enterprise	3	wal	write	148	0	edb_resource_group_o	0
3501 0	enterprise	3	wal	write	148	0	pg_attribute	0
3501 0	enterprise	3	wal	write	148	0	pg_attribute_relid_a	0
_	enterprise	3	wal	write	148	0	pg_auth_members_memb	0
-	enterprise	24	wal	write	130	0	pg_type_oid_index	0
-	1 rows)							

The information displayed in the result set includes:

Column Name	Description
ID	The system-assigned identifier of the wait.
USER	The name of the user that incurred the wait.
SEQ	The sequence number of the wait event.
WAIT NAME	The name of the wait event.
ELAPSED	The length of the wait event in microseconds.
File	The relfilenode number of the file.
Name	If available, the name of the file name related to the wait event.
# of Blk	The block number read or written for a specific instance of the event .
Sum of Blks	The number of blocks read.

```
purgesnap()
```

```
The purgesnap() function purges a range of snapshots from the snapshot tables. The signature is:
     purgesnap(beginning_id, ending_id)
Parameters
beginning_id
     beginning_id is an integer value that represents the beginning session identifier.
ending_id
     ending_id is an integer value that represents the ending session identifier.
purgesnap() removes all snapshots between beginning_id and ending_id (inclusive):
SELECT * FROM purgesnap(6, 9);
             purgesnap
Snapshots in range 6 to 9 deleted.
(1 row)
A call to the get_snaps() function after executing the example shows that snapshots 6 through 9 have
been purged from the snapshot tables:
SELECT * FROM get_snaps();
        get_snaps
1 25-JUL-18 09:49:04.224597
2 25-JUL-18 09:49:09.310395
3 25-JUL-18 09:49:14.378728
4 25-JUL-18 09:49:19.448875
5 25-JUL-18 09:49:24.52103
10 25-JUL-18 09:49:49.855821
11 25-JUL-18 09:49:54.919954
12 25-JUL-18 09:49:59.987707
(8 rows)
truncsnap()
Use the truncsnap() function to delete all records from the snapshot table. The signature is:
     truncsnap()
For example:
SELECT * FROM truncsnap();
     truncsnap
______
Snapshots truncated.
(1 row)
A call to the get_snaps() function after calling the truncsnap() function shows that all records have
been removed from the snapshot tables:
SELECT * FROM get_snaps();
 get_snaps
(0 rows)
```

Simulating Statspack AWR Reports

The functions described in this section return information comparable to the information contained in an Oracle Statspack/AWR (Automatic Workload Repository) report. When taking a snapshot, performance data from system catalog tables is saved into history tables. The reporting functions listed below report on the differences between two given snapshots.

- stat_db_rpt()
- stat_tables_rpt()
- statio_tables_rpt()
- stat_indexes_rpt()
- statio_indexes_rpt()

The reporting functions can be executed individually or you can execute all five functions by calling the edbreport() function.

edbreport()

The edbreport() function includes data from the other reporting functions, plus additional system information. The signature is:

```
edbreport(beginning_id, ending_id)
```

Parameters

beginning_id

beginning_id is an integer value that represents the beginning session identifier.

ending_id

ending_id is an integer value that represents the ending session identifier.

The call to the edbreport() function returns a composite report that contains system information and the reports returned by the other statspack functions.

```
SELECT * FROM edbreport(9, 10);
```

edbreport

EnterpriseDB Report for database acctg 25-JUL-18 Version: PostgreSQL 12.0 (EnterpriseDB Advanced Server 12.0.2)on x86_64-pc-linux-gnu, compiled by gcc (GCC) 4.4.7 20120313 (Red Hat 4.4.7-18), 64-bit

Begin snapshot: 9 at 25-JUL-18 09:49:44.788392

End snapshot: 10 at 25-JUL-18 09:49:49.855821

Size of database acctg is 173 MB

Tablespace: pg_default Size: 231 MB Owner: enterprisedb Tablespace: pg_global Size: 719 kB Owner: enterprisedb

Schema: pg_toast_temp_1 Size: 0 bytes Owner: enterprisedb

Schema: public Size: 158 MB Owner: enterprisedb

The information displayed in the report introduction includes the database name and version, the current date, the beginning and ending snapshot date and times, database and tablespace details and schema information.

Top 10 Relations by pages

```
TABLE RELPAGES -----pgbench_accounts 16394
```

pgbench_history	391
pg_proc	145
pg_attribute	92
pg_depend	81
pg_collation	60
edb\$stat_all_indexes	46
edb\$statio_all_indexes	46
pg_description	44
edb\$stat_all_tables	29

The information displayed in the Top 10 Relations by pages section includes:

Column Name	Description
TABLE	The name of the table.
RELPAGES	The number of pages in the table.

Top 10 Indexes by pages

INDEX	RELPAGES
pgbench_accounts_pkey	2745
pg_depend_reference_index	68
pg_depend_depender_index	63
pg_proc_proname_args_nsp_index	53
pg_attribute_relid_attnam_index	25
pg_description_o_c_o_index	24
pg_attribute_relid_attnum_index	17
pg_proc_oid_index	14
pg_collation_name_enc_nsp_index	12
edb\$stat_idx_pk	
10	

The information displayed in the Top 10 Indexes by pages section includes:

Column Name	Description
INDEX	The name of the index.
RELPAGES	The number of pages in the index.

Top 10 Relations by DML

SCHEMA	RELATION	UPDATES	DELETES	INSERTS
public public public public	pgbench_accounts pgbench_tellers pgbench_branches pgbench_history	117209 117209 117209 0	0 0 0 0	1000000 100 10 10 117209

The information displayed in the Top 10 Relations by DML section includes:

Column Name	Description
SCHEMA	The name of the schema in which the table resides.
RELATION	The name of the table.
UPDATES	The number of UPDATES performed on the table.
DELETES	The number of DELETES performed on the table.
INSERTS	The number of INSERTS performed on the table.

DATA from pg_stat_database

DATABASE	NUMBACKENDS	XACT COMMIT	XACT ROLLBACK	BLKS READ	BLKS HIT	HIT RATIO
- acctg	0	8261	0	117	127985	99.91

The information displayed in the DATA from pg_stat_database section of the report includes:

Column Name	Description
DATABASE	The name of the database.
NUMBACKENDS	Number of backends currently connected to this database. This is the only column in this view that re
XACT COMMIT	Number of transactions in this database that have been committed.
XACT ROLLBACK	Number of transactions in this database that have been rolled back.
BLKS READ	Number of disk blocks read in this database.
BLKS HIT	Number of times disk blocks were found already in the buffer cache (when a read was not necessary
HIT RATIO	The percentage of times that a block was found in the shared buffer cache.

DATA from pg_buffercache

RELATION	BUFFERS
pgbench_accounts_pkey pgbench_history edb\$statio_all_indexes edb\$stat_all_indexes edb\$stat_all_tables edb\$statio_all_tables edb\$session_wait_history edb\$statio_idx_pk	16665 2745 751 94 94 96 96 86 81 17

The information displayed in the DATA from pg_buffercache section of the report includes:

Column Name	Description
RELATION	The name of the table.
BUFFERS	The number of shared buffers used by the relation.

Note

In order to obtain the report for DATA from pg_buffercache , the pg_buffercache module must have been installed in the database. Perform the installation with the CREATE EXTENSION command.

For more information on the CREATE EXTENSION command, see the PostgreSQL Core documentation. DATA from pg_stat_all_tables ordered by seq scan

SCHEMA IDX TUP READ :	INS UF	RELATION PD DEL	SEQ SCAN	REL TUP READ 1	EDX SCAN
-					
public		pgbench_branches	8258	82580	0
0 public	0 8	3258 0 pgbench_tellers	8258	825800	0
0	0 8	3258 0	_		
pg_catalog 80	0 0	pg_class 0 0	7	3969	92
pg_catalog	0	pg_index	5	950	31

38	0	0	0			
pg_catalog		p	og_namespace	4	144	5
4	0	0	0			
pg_catalog		p	og_database	2	12	7
7	0	0	0			
pg_catalog		p	og_am	1	1	0
0	0	0	0			
pg_catalog		p	og_authid	1	10	2
2	0	0	0			
sys		C	callback_queue_table	0	0	0
0	0	0	0			
sys		e	edb\$session_wait_history	0	0	0
0	125	0	0			

The information displayed in the DATA from $pg_stat_all_tables$ ordered by seq scan section includes:

Column Name	Description
SCHEMA	The name of the schema in which the table resides.
RELATION	The name of the table.
SEQ SCAN	The number of sequential scans initiated on this table.
REL TUP READ	The number of tuples read in the table.
IDX SCAN	The number of index scans initiated on the table.
IDX TUP READ	The number of index tuples read.
INS	The number of rows inserted.
UPD	The number of rows updated.
DEL	The number of rows deleted.

DATA from pg_stat_all_tables ordered by rel tup read

SCHEMA IDX TUP READ	INS		SEQ SCAN	REL TUP READ	IDX SCAN
public		pgbench_tellers	8258	825800	0
0	0	8258 0			
public		1.5	8258	82580	0
0	0	8258 0			
pg_catalog	_	pg_class	7	3969	92
80	0	0 0	_	050	24
pg_catalog	0	pg_index	5	950	31
38	0	0 0	4	1 1 1	5
pg_catalog 4	0	pg_namespace 0 0	4	144	3
pg_catalog	V	pg_database	2	12	7
7	0	0 0	_	12	•
pg_catalog	Ū	pg_authid	1	10	2
2	0	0 0			
pg_catalog		pg_am	1	1	0
0	0	0 0			
sys		callback_queue_table	0	0	0
0	0	0 0			
sys		edb\$session_wait_history	0	0	0
0	125	0 0			

The information displayed in the DATA from $pg_stat_all_tables$ ordered by rel tup read section includes:

Column Name	Description	
••••••	_ 000p	

SCHEMA	The name of the schema in which the table resides.
RELATION	The name of the table.
SEQ SCAN	The number of sequential scans performed on the table.
REL TUP READ	The number of tuples read from the table.
IDX SCAN	The number of index scans performed on the table.
IDX TUP READ	The number of index tuples read.
INS	The number of rows inserted.
UPD	The number of rows updated.
DEL	The number of rows deleted.

DATA from pg_statio_all_tables

SCHEMA		RELAT	ION	HEAP	HEAP	IDX	IDX
TOAST	TOAST	TIDX	TIDX				
				READ	HIT	READ	HIT
READ	HIT	READ	HIT				
public		pgben	ch_accounts	32	25016	0	49913
0	0	0	0				
public		. •	ch_tellers	0	24774	0	0
0	0	0 .	. 0	_			
public		. •	ch_branches	0	16516	0	0
0	0	0	0	F2	0264	0	0
public	0		ch_history	53	8364	0	0
0	0	0	0	0	100	0	107
pg_catalo 0	og 0	pg_cl 0	uss 0	0	199	V	187
pg_catalo	J	•	tribute	0	198	0	395
pg_catati	0 0	ρ <u>υ</u> _ατ	0	V	190	V	393
pg_catalo	•	pg_pr	· ·	0	75	0	153
0 0	0	0 9	0	Ü	. 3	Ū	133
pg_catalo	oa	pg_in	dex	0	56	0	33
0	0	0	0				
pg_catalo	og	pg_am	ор	0	48	0	56
0	0	0	0				
pg_catalo	og	pg_na	mespace	0	28	0	7
0	0	0	0				

The information displayed in the DATA from pg_statio_all_tables section includes:

DATA from pg_stat_all_indexes

SCHEMA RELATION INDEX	
IDX SCAN IDX TUP READ IDX TUP FETCH	
public pgbench_accounts pgbench_accounts_	_pkey
16516 16679 16516	
pg_catalog pg_attribute	
pg_attribute_relid_attnum_index 196 402 402	
pg_catalog pg_proc pg_proc_oid_index	(
70 70 70	
pg_catalog pg_class pg_class_oid_inde	ex
61 61 61	
pg_catalog pg_class pg_class_relname_	nsp index
31 19 19	
pg_catalog pg_type pg_type_oid_index	(
27 27 27	•

pg_catalog		edb_policy	edb_policy_object_name_index
21	0	0	
pg_catalog		pg_amop	pg_amop_fam_strat_index
16	16	16	
pg_catalog		pg_index	pg_index_indexrelid_index
16	16	16	
pg_catalog		pg_index	pg_index_indrelid_index
15	22	22	

The information displayed in the DATA from pg_stat_all_indexes section includes:

DATA from pg_statio_all_indexes

SCHEMA RELATION INDEX
IDX BLKS READ IDX BLKS HIT

public pgbench_accounts pgbench_accounts_pkey 49913 pg_catalog pg_attribute pg_attribute_relid_attnum_index 395 edb\$stat_all_indexes edb\$stat_idx_pk sys 1 382 edb\$statio_all_indexes edb\$statio_idx_pk sys 1 382 edb\$statio_all_tables edb\$statio_tab_pk sys 2 262 edb\$stat_all_tables edb\$stat_tab_pk sys 259 0 edb\$session_wait_history session_waits_hist_pk sys 251 pg_proc_oid_index pg_catalog pg_proc 142 pg_class_oid_index pg_catalog pg_class 123 pg_catalog pg_class pg_class_relname_nsp_index 63

The information displayed in the DATA from pg_statio_all_indexes section includes:

Column Name	Description
SCHEMA	The name of the schema in which the index resides.
RELATION	The name of the table on which the index is defined.
INDEX	The name of the index.
IDX BLKS READ	The number of index blocks read.
IDX BLKS HIT	The number of index blocks hit.

System Wait Information

WAIT NAME	COUNT	WAIT TIME	% WAIT
wal flush	8359	1.357593	30.62
wal write	8358	1.349153	30.43
wal file sync	8358	1.286437	29.02
query plan	33439	0.439324	9.91
db file extend	54	0.000585	0.01
db file read	31	0.000307	0.01
other lwlock acquire	0	0.000000	0.00
ProcArrayLock	0	0.000000	0.00
CLogControlLock	0	0.000000	0.00

The information displayed in the System Wait Information section includes:

Column Name	Description
WAIT NAME	The name of the wait.
COUNT	The number of times that the wait event occurred.
WAIT TIME	The length of the wait time in seconds.
% WAIT	The percentage of the total wait time used by this wait for this session.

Database Parameters from postgresql.conf

```
PARAMETER
                                       SETTING
                              MAXVAL
CONTEXT
              MINVAL
allow_system_table_mods
                                       off
postmaster
application_name
                                       psql.bin
user
                                       (disabled)
archive_command
sighup
archive_mode
                                       off
postmaster
                                       0
archive_timeout
                            1073741823
sighup
array_nulls
                                       on
user
                                       60
authentication_timeout
                             600
sighup
             1
autovacuum
                                       on
sighup
autovacuum_analyze_scale_factor
                                       0.1
sighup
                             100
autovacuum_analyze_threshold
                                       50
                            2147483647
sighup
             0
                                       200000000
autovacuum_freeze_max_age
             100000
                            2000000000
postmaster
                                       3
autovacuum_max_workers
                            262143
postmaster
autovacuum_multixact_freeze_max_age
                                       400000000
             10000
postmaster
                            2000000000
autovacuum_naptime
                           60
                                        sighup
             2147483
1
                                        20
autovacuum_vacuum_cost_delay
                             100
sighup
```

The information displayed in the Database Parameters from postgresql.conf section includes:

Column Name	Description
PARAMETER	The name of the parameter.
SETTING	The current value assigned to the parameter.
CONTEXT	The context required to set the parameter value.
MINVAL	The minimum value allowed for the parameter.
MAXVAL	The maximum value allowed for the parameter.

stat_db_rpt()

The signature is:

stat_db_rpt(beginning_id, ending_id)

Parameters

beginning_id

beginning_id is an integer value that represents the beginning session identifier.

ending_id

ending_id is an integer value that represents the ending session identifier.

The following example demonstrates the stat_db_rpt() function:

SELECT * FROM stat_db_rpt(9, 10);

stat_db_rpt

DATA from pg_stat_database

The information displayed in the DATA from pg_stat_database section of the report includes:

Column Name	Description
DATABASE	The name of the database.
NUMBACKENDS	Number of backends currently connected to this database. This is the only column in this view that re
XACT COMMIT	The number of transactions in this database that have been committed.
XACT ROLLBACK	The number of transactions in this database that have been rolled back.
BLKS READ	The number of blocks read.
BLKS HIT	The number of blocks hit.
HIT RATIO	The percentage of times that a block was found in the shared buffer cache.

stat_tables_rpt()

The signature is:

function_name(beginning_id, ending_id, top_n, scope)

Parameters

beginning_id

beginning_id is an integer value that represents the beginning session identifier.

ending_id

ending_id is an integer value that represents the ending session identifier.

top_n

top_n represents the number of rows to return

scope

scope determines which tables the function returns statistics about. Specify SYS , USER or ALL :

- SYS indicates that the function should return information about system defined tables. A table is considered a system table if it is stored in one of the following schemas: pg_catalog , information_schema , or sys .
- USER indicates that the function should return information about user-defined tables.
- ALL specifies that the function should return information about all tables.

The stat_tables_rpt() function returns a two-part report. The first portion of the report contains:

SELECT * FROM stat_tables_rpt(8, 9, 10, 'ALL');

stat_tables_rpt -----

DATA from pg_stat_all_tables ordered by seq scan

SCHEMA IDX TUP READ	INS	U	RELATION JPD DEL	SEQ SCAN	REL TUP READ	IDX SCAN
-						
public			pgbench_branches	8249	82490	0
0	0	82	249 0			
public			pgbench_tellers	8249	824900	0
0	0	82	249 0			
pg_catalog			pg_class	7	3969	92
80	0	0	0			
pg_catalog			pg_index	5	950	31
38	0	0	0			
pg_catalog			pg_namespace	4	144	5
4	0	0	0			
pg_catalog			pg_am	1	1	0
0	0	0	0			
pg_catalog			pg_authid	1	10	2
2	0	0	0			
pg_catalog			pg_database	1	6	3
3	0	0	0			
sys			callback_queue_table	0	0	0
0	0	0	0			
sys			edb\$session_wait_history	0	0	0
0	125		0			

The information displayed in the DATA from pg_stat_all_tables ordered by seq scan section includes:

Column Name	Description
SCHEMA	The name of the schema in which the table resides.
RELATION	The name of the table.
SEQ SCAN	The number of sequential scans on the table.
REL TUP READ	The number of tuples read from the table.
IDX SCAN	The number of index scans performed on the table.
IDX TUP READ	The number of index tuples read from the table.
INS	The number of rows inserted.
UPD	The number of rows updated.
DEL	The number of rows deleted.

The second portion of the report contains:

DATA from pg_stat_all_tables ordered by rel tup read

SCHEMA IDX TUP READ	TNS	RELATION UPD DEL	SEQ SCAN REL	TUP READ	IDX SCAN
		nghangh tallang	9240	924000	0
public 0	0	pgbench_tellers 8249 0	8249	824900	V
public		pgbench_branches	8249	82490	0
0	0	8249 0	_		
pg_catalog	0	pg_class 0 0	7	3969	92
80 pg_catalog	0	pg_index	5	950	31
38	0	0 0			-
pg_catalog		pg_namespace	4	144	5
4	0	0 0 pg_authid	1	10	2
pg_catalog 2	0	0 0	1	10	۷
pg_catalog	-	pg_database	1	6	3
3	0	0 0		_	_
pg_catalog 0	0	pg_am 0 0	1	1	0
sys	V	callback_queue_table	0	0	0
0	0	0 0			-
sys		edb\$session_wait_history	<i>'</i> 0	0	0
(30 nows)	125	0 0			
(29 rows)					

The information displayed in the DATA from pg_stat_all_tables ordered by rel tup read section includes:

Column Name	Description
SCHEMA	The name of the schema in which the table resides.
RELATION	The name of the table.
SEQ SCAN	The number of sequential scans performed on the table.
REL TUP READ	The number of tuples read from the table.
IDX SCAN	The number of index scans performed on the table.
IDX TUP READ	The number of live rows fetched by index scans.
INS	The number of rows inserted.
UPD	The number of rows updated.
DEL	The number of rows deleted.

statio_tables_rpt()

The signature is:

statio_tables_rpt(beginning_id, ending_id, top_n, scope)

Parameters

beginning_id

beginning_id is an integer value that represents the beginning session identifier.

ending_id

ending_id is an integer value that represents the ending session identifier.

top_n

top_n represents the number of rows to return

scope

scope determines which tables the function returns statistics about. Specify SYS , USER or ALL :

- SYS indicates that the function should return information about system defined tables. A table is considered a system table if it is stored in one of the following schemas: pg_catalog , information_schema , or sys .
- USER indicates that the function should return information about user-defined tables.
- ALL specifies that the function should return information about all tables.

The statio_tables_rpt() function returns a report that contains:

SELECT * FROM statio_tables_rpt(9, 10, 10, 'SYS');

		statio_tables_rpt					
DATA f	DATA from pg_statio_all_tables						
SCHEMA TOAST	TIDX	RELATION TIDX	HEAP	HEAP	IDX	IDX	TOAST
HIT	READ	HIT	READ	HIT	READ	HIT	READ
-							
sys 0	0	edb\$stat_all_indexes	8	18	1	382	0
sys 0	0	edb\$statio_all_index	8	18	1	382	0
sys		edb\$statio_all_table	5	12	2	262	0
0 sys	0	0 edb\$stat_all_tables	4	10	0	259	0
0 sys	0	0 edb\$session_wait_his	2	6	0	251	0
0 sys	0	0 edb\$session_waits	1	4	0	12	0
0 sys	0	0 callback_queue_table	0	0	0	0	0
0 sys	0	0 dual	0	0	0	0	0
0 sys	0	0 edb\$snap	0	1	0	2	0
0 sys	0	0 edb\$stat_database	0	2	0	7	0
0 (15 rows)	0	0					

The information displayed in the DATA from pg_statio_all_tables section includes:

Column Name	Description
SCHEMA	The name of the schema in which the relation resides.
RELATION	The name of the relation.
HEAP READ	The number of heap blocks read.
HEAP HIT	The number of heap blocks hit.
IDX READ	The number of index blocks read.
IDX HIT	The number of index blocks hit.
TOAST READ	The number of toast blocks read.
TOAST HIT	The number of toast blocks hit.

TIDX READ	The number of toast index blocks read.
TIDX HIT	The number of toast index blocks hit.

stat_indexes_rpt()

The signature is:

stat_indexes_rpt(beginning_id, ending_id, top_n, scope)

Parameters

beginning_id

beginning_id is an integer value that represents the beginning session identifier.

ending_id

ending_id is an integer value that represents the ending session identifier.

top_n

top_n represents the number of rows to return

scope

scope determines which tables the function returns statistics about. Specify SYS , USER or ALL :

- SYS indicates that the function should return information about system defined tables. A table is considered a system table if it is stored in one of the following schemas: pg_catalog, information_schema, or sys.
- USER indicates that the function should return information about user-defined tables.
- ALL specifies that the function should return information about all tables.

The stat_indexes_rpt() function returns a report that contains:

edb=# SELECT * FROM stat_indexes_rpt(9, 10, 10, 'ALL');

stat_indexes_rpt

DATA from pg_stat_all_indexes

SCHEMA		RELATION		INDEX
IDX SCAN	IDX TUP	READ IDX TUP FETCH		
public		pgbench_accounts		pgbench_accounts_pkey
16516	16679	16516		
pg_catalog		pg_attribute		
pg_attribute_r	elid_attr	num_index 196	402	402
pg_catalog		pg_proc		pg_proc_oid_index
70	70	70		
pg_catalog		pg_class		pg_class_oid_index
61	61	61		
pg_catalog		pg_class		pg_class_relname_nsp_index
31	19	19		
pg_catalog		pg_type		pg_type_oid_index
22	22	22		
pg_catalog		edb_policy		<pre>edb_policy_object_name_index</pre>
21	0	0		
pg_catalog		pg_amop		pg_amop_fam_strat_index

16	16	16	
pg_catalog		pg_index	pg_index_indexrelid_index
16	16	16	
pg_catalog		pg_index	pg_index_indrelid_index
15	22	22	
(14 rows)			

The information displayed in the DATA from pg_stat_all_indexes section includes:

Column Name	Description
SCHEMA	The name of the schema in which the relation resides.
RELATION	The name of the relation.
INDEX	The name of the index.
IDX SCAN	The number of indexes scanned.
IDX TUP READ	The number of index tuples read.
IDX TUP FETCH	The number of index tuples fetched.

\statio indexes rpt():index

The signature is:

statio_indexes_rpt(beginning_id, ending_id, top_n, scope)

Parameters

beginning_id

beginning_id is an integer value that represents the beginning session identifier.

ending_id

ending_id is an integer value that represents the ending session identifier.

top_n

top_n represents the number of rows to return

scope

scope determines which tables the function returns statistics about. Specify SYS, USER or ALL:

- SYS indicates that the function should return information about system defined tables. A table is considered a system table if it is stored in one of the following schemas: pg_catalog , information_schema , or sys .
- USER indicates that the function should return information about user-defined tables.
- ALL specifies that the function should return information about all tables.

The statio_indexes_rpt() function returns a report that contains:

edb=# SELECT * FROM statio_indexes_rpt(9, 10, 10, 'SYS');

statio_indexes_rpt

DATA from pq_statio_all_indexes

SCHEMA RELATION INDEX

IDX BLKS READ IDX BLKS HIT

pg_catalog pg_attribute

pg_attribute_relid_attnum_index 0 395					
sys		edb\$stat_all_indexes	edb\$stat_idx_pk		
1	382				
sys		edb\$statio_all_indexes	edb\$statio_idx_pk		
1	382				
sys	2.50	edb\$statio_all_tables	edb\$statio_tab_pk		
2	262	W. d			
sys	250	edb\$stat_all_tables	edb\$stat_tab_pk		
0	259	adlata a sala a susal a la la susa			
sys	251	edb\$session_wait_history	session_waits_hist_pk		
0 na cataloa	251	ng nnoc	ng mas sid indov		
pg_catalog 0	142	pg_proc	pg_proc_oid_index		
pg_catalog	142	pg_class	pg_class_oid_index		
0	123	pg_c1033	pg_ctuss_otu_thucx		
pg_catalog	123	pg_class	pg_class_relname_nsp_index		
0	63	pg_01400	pg_crass_rername_nsp_rnaex		
pg_catalog		pg_type	pg_type_oid_index		
0	45	F 3 = 37 F 3	F3=-5/F-=		
(14 rows)					

The information displayed in the DATA from pg_statio_all_indexes report includes:

Column Name	Description
SCHEMA	The name of the schema in which the relation resides.
RELATION	The name of the table on which the index is defined.
INDEX	The name of the index.
IDX BLKS READ	The number of index blocks read.
IDX BLKS HIT	The number of index blocks hit.

Performance Tuning Recommendations

To use DRITA reports for performance tuning, review the top five events in a given report, looking for any event that takes a disproportionately large percentage of resources. In a streamlined system, user I/O will probably make up the largest number of waits. Waits should be evaluated in the context of CPU usage and total time; an event may not be significant if it takes 2 minutes out of a total measurement interval of 2 hours, if the rest of the time is consumed by CPU time. The component of response time (CPU "work" time or other "wait" time) that consumes the highest percentage of overall time should be evaluated.

When evaluating events, watch for:

Event type	Description
Checkpoint waits	Checkpoint waits may indicate that checkpoint parameters need to be adjusted, (checkpoint
WAL-related waits	WAL-related waits may indicate wal_buffers are under-sized.
SQL Parse waits	If the number of waits is high, try to use prepared statements.
db file random reads	If high, check that appropriate indexes and statistics exist.
db file random writes	If high, may need to decrease bgwriter_delay .
btree random lock acquires	May indicate indexes are being rebuilt. Schedule index builds during less active time.

Performance reviews should also include careful scrutiny of the hardware, the operating system, the network and the application SQL statements.

Event Descriptions

The following table lists the basic wait events that are displayed by DRITA.

Event Name	Description
add in shmem lock acquire	Obsolete/unused
bgwriter communication lock acquire	The bgwriter (background writer) process has waited for the short-term le
btree vacuum lock acquire	The server has waited for the short-term lock that synchronizes access t
buffer free list lock acquire	The server has waited for the short-term lock that synchronizes access t
checkpoint lock acquire	A server process has waited for the short-term lock that prevents simulta
checkpoint start lock acquire	The server has waited for the short-term lock that synchronizes access t
clog control lock acquire	The server has waited for the short-term lock that synchronizes access t
control file lock acquire	The server has waited for the short-term lock that synchronizes write acc
db file extend	A server process has waited for the operating system while adding a new
db file read	A server process has waited for the completion of a read (from disk).
db file write	A server process has waited for the completion of a write (to disk).
db file sync	A server process has waited for the operating system to flush all change
first buf mapping lock acquire	The server has waited for a short-term lock that synchronizes access to
freespace lock acquire	The server has waited for the short-term lock that synchronizes access t
lwlock acquire	The server has waited for a short-term lock that has not been described
multi xact gen lock acquire	The server has waited for the short-term lock that synchronizes access t
multi xact member lock acquire	The server has waited for the short-term lock that synchronizes access t
multi xact offset lock acquire	The server has waited for the short-term lock that synchronizes access t
oid gen lock acquire	The server has waited for the short-term lock that synchronizes access t
query plan	The server has computed the execution plan for a SQL statement.
rel cache init lock acquire	The server has waited for the short-term lock that prevents simultaneous
shmem index lock acquire	The server has waited for the short-term lock that synchronizes access t
sinval lock acquire	The server has waited for the short-term lock that synchronizes access t
sql parse	The server has parsed a SQL statement.
subtrans control lock acquire	The server has waited for the short-term lock that synchronizes access t
tablespace create lock acquire	The server has waited for the short-term lock that prevents simultaneous
two phase state lock acquire	The server has waited for the short-term lock that synchronizes access t
wal insert lock acquire	The server has waited for the short-term lock that synchronizes write acc
wal write lock acquire	The server has waited for the short-term lock that synchronizes write-ah
wal file sync	The server has waited for the write-ahead log to sync to disk (related to
wal flush	The server has waited for the write-ahead log to flush to disk.
wal write	The server has waited for a write to the write-ahead log buffer (expect the
xid gen lock acquire	The server has waited for the short-term lock that synchronizes access t

When wait events occur for lightweight locks, they are displayed by DRITA as well. A lightweight lock is used to protect a particular data structure in shared memory.

Certain wait events can be due to the server process waiting for one of a group of related lightweight locks, which is referred to as a lightweight lock tranche. Individual lightweight lock tranches are not displayed by DRITA, but their summation is displayed by a single event named other lwlock acquire.

For a list and description of lightweight locks displayed by DRITA, please see Section 28.2, The Statistics Collector in the PostgreSQL core documentation available at:

https://www.postgresql.org/docs/12/static/monitoring-stats.html

Under Section 28.2.2. Viewing Statistics, the lightweight locks are listed in Table 28-4 wait_event Description where the Wait Event Type column designates LWLock.

The following example displays lightweight locks ProcArrayLock, CLogControlLock, WALBufMappingLock

, and XidGenLock .

WAIT NAME	COUNT	WAIT TIME	% WAIT
wal flush	56107	44.456494	47.65
db file read	66123	19.543968	20.95
wal write	32886	12.780866	13.70
wal file sync	32933	11.792972	12.64
query plan	223576	4.539186	4.87
db file extend	2339	0.087038	0.09
other lwlock acquire	402	0.066591	0.07
ProcArrayLock	135	0.012942	0.01
CLogControlLock	212	0.010333	0.01
WALBufMappingLock	47	0.006068	0.01
XidGenLock	53	0.005296	0.01
(13 rows)			

DRITA also displays wait events that occur that are related to certain Advanced Server product features.

These Advanced Server feature specific wait events and the other lwlock acquire event are listed in the following table.

Event Name	Description
BulkLoadLock	The server has waited for access related to EDB*Loader.
EDBResoureManagerLock	The server has waited for access related to EDB Resource Manager.
other lwlock acquire	Summation of waits for lightweight lock tranches.

7.4 Acknowledgements

The PostgreSQL 8.3, 8.4, 9.0, 9.1, 9.2, 9.3, 9.4, 9.5, 9.6, 10, 11, and 12 Documentation provided the baseline for the portions of this guide that are common to PostgreSQL, and is hereby acknowledged:

Portions of this EnterpriseDB Software and Documentation may utilize the following copyrighted material, the use of which is hereby acknowledged.

PostgreSQL Documentation, Database Management System

PostgreSQL is Copyright © 1996-2018 by the PostgreSQL Global Development Group and is distributed under the terms of the license of the University of California below.

Postgres95 is Copyright © 1994-5 by the Regents of the University of California.

Permission to use, copy, modify, and distribute this software and its documentation for any purpose, without fee, and without a written agreement is hereby granted, provided that the above copyright notice and this paragraph and the following two paragraphs appear in all copies.

IN NO EVENT SHALL THE UNIVERSITY OF CALIFORNIA BE LIABLE TO ANY PARTY FOR DIRECT, INDIRECT, SPECIAL, INCIDENTAL, OR CONSEQUENTIAL DAMAGES, INCLUDING LOST PROFITS, ARISING OUT OF THE USE OF THIS SOFTWARE AND ITS DOCUMENTATION, EVEN IF THE UNIVERSITY OF CALIFORNIA HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

THE UNIVERSITY OF CALIFORNIA SPECIFICALLY DISCLAIMS ANY WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTIC-ULAR PURPOSE. THE SOFTWARE PROVIDED HEREUNDER IS ON AN "AS-IS" BASIS, AND THE UNIVERSITY OF CALIFORNIA HAS NO OBLIGATIONS TO PROVIDE MAINTENANCE, SUPPORT, UPDATES, ENHANCEMENTS, OR MODIFICATIONS.

7.5 Conclusion

Database Compatibility for Oracle Developers Tools and Utilities Guide

Copyright © 2007 - 2020 EnterpriseDB Corporation. All rights reserved.

EnterpriseDB Corporation 34 Crosby Drive, Suite 201, Bedford, MA 01730, USA

T +1 781 357 3390 F +1 978 467 1307 E info@enterprisedb.com www.enterprisedb.com

- EnterpriseDB and Postgres Enterprise Manager are registered trademarks of EnterpriseDB Corporation. EDB and EDB Postgres are trademarks of EnterpriseDB Corporation. Oracle is a registered trademark of Oracle, Inc. Other trademarks may be trademarks of their respective owners.
- EDB designs, establishes coding best practices, reviews, and verifies input validation for the logon UI for EDB Postgres products where present. EDB follows the same approach for additional input components, however the nature of the product may require that it accepts freeform SQL, WMI or other strings to be entered and submitted by trusted users for which limited validation is possible. In such cases it is not possible to prevent users from entering incorrect or otherwise dangerous inputs.
- EDB reserves the right to add features to products that accept freeform SQL, WMI or other potentially dangerous inputs from authenticated, trusted users in the future, but will ensure all such features are designed and tested to ensure they provide the minimum possible risk, and where possible, require superuser or equivalent privileges.
- EDB does not warrant that we can or will anticipate all potential threats and therefore our process cannot fully guarantee that all potential vulnerabilities have been addressed or considered.

8.0 EDB Postgres Advanced Server ECPGPlus Guide

EnterpriseDB has enhanced ECPG (the PostgreSQL pre-compiler) to create ECPGPlus. ECPGPlus allows you to include Pro*C compatible embedded SQL commands in C applications when connected to an EDB Postgres Advanced Server (Advanced Server) database. When you use ECPGPlus to compile an application, the SQL code is syntax-checked and translated into C.

ECPGPlus supports:

- Oracle Dynamic SQL Method 4 (ODS-M4).
- Pro*C compatible anonymous blocks.
- · A CALL statement compatible with Oracle databases.

As part of ECPGPlus's Pro*C compatibility, you do not need to include the BEGIN DECLARE SECTION and END DECLARE SECTION directives.

PostgreSQL Compatibility

While most ECPGPlus statements will work with community PostgreSQL, the CALL statement, and the EXECUTE...END EXEC1 statement work only when the client application is connected to EDB Postgres Advanced Server.

8.1 ECPGPlus - Overview

Overview

EnterpriseDB has enhanced ECPG (the PostgreSQL pre-compiler) to create ECPGPlus. ECPGPlus is a Pro*C-compatible version of the PostgreSQL C pre-compiler. ECPGPlus translates a program that combines C code and embedded SQL statements into an equivalent C program. As it performs the translation, ECPGPlus verifies that the syntax of each SQL construct is correct.

The following diagram charts the path of a program containing embedded SQL statements as it is compiled into an executable:

Compilation of a program containing embedded SQL statements

To produce an executable from a C program that contains embedded SQL statements, pass the program (my_program.pgc in the diagram above) to the ECPGPlus pre-compiler. ECPGPlus translates each SQL

statement in my_program.pgc into C code that calls the ecpglib API, and produces a C program (my_program.c). Then, pass the C program to a C compiler; the C compiler generates an object file (my_program.o), as well as the ecpglib library file, and any other required libraries to the linker, which in turn produces the executable (my_program).

While the ECPGPlus preprocessor validates the *syntax* of each SQL statement, it cannot validate the *semantics*. For example, the preprocessor will confirm that an INSERT statement is syntactically correct, but it cannot confirm that the table mentioned in the INSERT statement actually exists.

Behind the Scenes

A client application contains a mix of C code and SQL code comprised of the following elements:

- · C preprocessor directives
- C declarations (variables, types, functions, ...)
- · C definitions (variables, types, functions, ...)
- · SQL preprocessor directives
- · SQL statements

For example:

```
1 #include <stdio.h>
2 EXEC SQL INCLUDE sqlca;
4 extern void printInt(char *label, int val);
5 extern void printStr(char *label, char *val);
6 extern void printFloat(char *label, float val);
7
8 void displayCustomer(int custNumber)
9 {
10 EXEC SQL BEGIN DECLARE SECTION;
11 VARCHAR custName[50];
12 float custBalance;
13 int custID = custNumber;
14 EXEC SQL END DECLARE SECTION;
16 EXEC SQL SELECT name, balance
17 INTO :custName, :custBalance
18 FROM customer
19 WHERE id = :custID;
20
21 printInt("ID", custID);
22 printStr("Name", custName);
23 printFloat("Balance", custBalance);
24 }
```

In the above code fragment:

Line 1 specifies a directive to the C preprocessor.

C preprocessor directives may be interpreted or ignored; the option is controlled by a command line option (-C PROC) entered when you invoke ECPGPlus. In either case, ECPGPlus copies each C preprocessor directive to the output file (4) without change; any C preprocessor directive found in the source file will appear in the output file.

· Line 2 specifies a directive to the SQL preprocessor.

SQL preprocessor directives are interpreted by the ECPGPlus preprocessor, and are not copied to the output file.

· Lines 4 through 6 contain C declarations.

C declarations are copied to the output file without change, except that each VARCHAR declaration is translated into an equivalent struct declaration.

- Lines 10 through 14 contain an embedded-SQL declaration section.
 C variables that you refer to within SQL code are known as host variables. If you invoke the ECPG-Plus preprocessor in Pro*C mode (-C PROC), you may refer to any C variable within a SQL statement; otherwise you must declare each host variable within a BEGIN/END DECLARATION SECTION pair.
- Lines 16 through 19 contain a SQL statement.

SQL statements are translated into calls to the ECPGPlus run-time library.

· Lines 21 through 23 contain C code.

C code is copied to the output file without change.

Any SQL statement must be prefixed with EXEC SQL and extends to the next (unquoted) semicolon. For example:

```
printf("Updating employee salaries\n");
EXEC SQL UPDATE emp SET sal = sal * 1.25;
EXEC SQL COMMIT;
printf("Employee salaries updated\n");
```

When the preprocessor encounters the code fragment shown above, it passes the C code (the first line and the last line) to the output file without translation and converts each ecpqlib function. The result would appear similar to the following:

Installation and Configuration

Installation and Configuration

On Windows, ECPGPlus is installed by the Advanced Server installation wizard as part of the Database Server component. On Linux, install with the edb-as<xx>-server-devel RPM package where xx is the Advanced Server version number. By default, the executable is located in:

On Windows:

C:\Program Files\edb\as12\bin

On Linux:

/usr/edb/as12/bin

When invoking the ECPGPlus compiler, the executable must be in your search path (%PATH% on Windows, \$PATH on Linux). For example, the following commands set the search path to include the directory that holds the ECPGPlus executable file ecpg .

On Windows:

```
set EDB_PATH=C:\Program Files\edb\as12\bin set PATH=%EDB_PATH%;%PATH%
```

On Linux:

export EDB_PATH==/usr/edb/as12/bin export PATH=\$EDB_PATH:\$PATH

Constructing a Makefile

Constructing a Makefile

A makefile contains a set of instructions that tell the make utility how to transform a program written in C (that contains embedded SQL) into a C program. To try the examples in this guide, you will need:

- a C compiler (and linker)
- the make utility
- · ECPGPlus preprocessor and library
- a makefile that contains instructions for ECPGPlus

The following code is an example of a makefile for the samples included in this guide. To use the sample code, save it in a file named makefile in the directory that contains the source code file.

```
INCLUDES = -I$(shell pg_config --includedir)
LIBPATH = -L $(shell pg_config --libdir)
CFLAGS += $(INCLUDES) -q
LDFLAGS += -a
LDLIBS += $(LIBPATH) -lecpg -lpq
.SUFFIXES: .pgc,.pc
.pgc.c:
     ecpg -c $(INCLUDES) $?
.pc.c:
    ecpq -C PROC -c $(INCLUDES) $?
```

The first two lines use the pg_config program to locate the necessary header files and library directories:

```
INCLUDES = -I$(shell pg_config --includedir)
LIBPATH = -L $(shell pg_config --libdir)
```

The pg_config program is shipped with Advanced Server.

make knows that it should use the CFLAGS variable when running the C compiler and LDFLAGS and LDLIBS when invoking the linker. ECPG programs must be linked against the ECPG run-time library (-lecpg) and the libpg library (-lpg)

```
CFLAGS += $(INCLUDES) -g
LDFLAGS += -a
LDLIBS += $(LIBPATH) -lecpg -lpq
```

The sample makefile instructs make how to translate a .pgc or a .pc file into a C program. Two lines in the makefile specify the mode in which the source file will be compiled. The first compile option is:

```
.pgc.c:
      ecpg -c $(INCLUDES) $?
```

The first option tells make how to transform a file that ends in .pgc (presumably, an ECPG source file) into a file that ends in .c (a C program), using community ECPG (without the ECPGPlus enhancements). It invokes the ECPG pre-compiler with the -c flag (instructing the compiler to convert SQL code into C), using the value of the INCLUDES variable and the name of the .pgc file.

```
.pc.c:
ecpg -C PROC -c $(INCLUDES) $?
```

The second option tells make how to transform a file that ends in .pg (an ECPG source file) into a file that ends in .c (a C program), using the ECPGPlus extensions. It invokes the ECPG pre-compiler with the -c flag (instructing the compiler to convert SQL code into C), as well as the -C PROC flag (instructing the compiler to use ECPGPlus in Pro*C-compatibility mode), using the value of the INCLUDES variable and the name of the .pgc file.

When you run make , pass the name of the ECPG source code file you wish to compile. For example, to compile an ECPG source code file named customer_list.pgc , use the command:

```
make customer_list
```

The make utility consults the makefile (located in the current directory), discovers that the makefile contains a rule that will compile customer_list.pgc into a C program (customer_list.c), and then uses the rules built into make to compile customer_list.c into an executable program.

ECPGPlus Command Line Options

ECPGPlus Command Line Options

In the sample makefile shown above, make includes the -C option when invoking ECPGPlus to specify that ECPGPlus should be invoked in Pro*C compatible mode.

If you include the -C PROC keywords on the command line, in addition to the ECPG syntax, you may use Pro*C command line syntax; for example:

```
$ ecpg -C PROC INCLUDE=/usr/edb/as12/include acct_update.c
```

To display a complete list of the other ECPGPlus options available, navigate to the ECPGPlus installation directory, and enter:

```
./ecpg --help
```

The command line options are:

Note

If you do not specify an output file name when invoking ECPGPlus, the output file name is created by stripping off the <code>.pgc</code> filename extension, and appending <code>.c</code> to the file name.

8.2 Using Embedded SQL

Using Embedded SQL

Each of the following sections leads with a code sample, followed by an explanation of each section within the code sample.

Example - A Simple Query

The first code sample demonstrates how to execute a SELECT statement (which returns a single row), storing the results in a group of host variables. After declaring host variables, it connects to the edb sample database using a hard-coded role name and the associated password, and queries the emp table. The query returns the values into the declared host variables; after checking the value of the NULL indicator variable, it prints a simple result set onscreen and closes the connection.

```
/*******************
* print_emp.pgc
*

#/
#include <stdio.h>

int main(void)
{
    EXEC SQL BEGIN DECLARE SECTION;
    int v_empno;
    char v_ename[40];
    double v_sal;
    double v_comm;
    short v_comm_ind;
```

```
EXEC SQL END DECLARE SECTION;
  EXEC SQL WHENEVER SQLERROR sqlprint;
   EXEC SQL CONNECT TO edb
     USER 'alice' IDENTIFIED BY '1safepwd';
  EXEC SQL
      SELECT
        empno, ename, sal, comm
      INTO
        :v_empno, :v_ename, :v_sal, :v_comm INDICATOR:v_comm_ind
      FROM
        emp
      WHERE
        empno = 7369;
  if (v_comm_ind)
      printf("empno(%d), ename(%s), sal(%.2f) comm(NULL)\n",
      v_empno, v_ename, v_sal);
  else
      printf("empno(%d), ename(%s), sal(%.2f) comm(%.2f)\n",
      v_{empno}, v_{ename}, v_{sal}, v_{comm});
  EXEC SQL DISCONNECT;
The code sample begins by including the prototypes and type definitions for the C stdio library, and then
declares the main function:
#include <stdio.h>
int main(void)
Next, the application declares a set of host variables used to interact with the database server:
EXEC SQL BEGIN DECLARE SECTION;
int v_empno;
char v_ename[40];
double v_sal;
double v_comm;
short v_comm_ind;
EXEC SQL END DECLARE SECTION;
```

Please note that if you plan to pre-compile the code in PROC mode, you may omit the BEGIN DECLARE...END DECLARE section. For more information about declaring host variables, refer to the [Declaring Host Variables](02_us-ing_embedded_sql#declaring_host_variables) section.

The data type associated with each variable within the declaration section is a C data type. Data passed between the server and the client application must share a compatible data type; for more information about data types, see the [Supported C Data Types] (06_reference#supported_c_data_types) section.

The next statement instructs the server how to handle an error:

```
EXEC SQL WHENEVER SQLERROR sqlprint;
```

If the client application encounters an error in the SQL code, the server will print an error message to stderr (standard error), using the sqlprint() function supplied with ecpglib. The next EXEC SQL statement establishes a connection with Advanced Server:

```
EXEC SQL CONNECT TO edb USER 'alice' IDENTIFIED BY '1safepwd';
```

In our example, the client application connects to the edb database, using a role named alice with a password of 1safepwd.

The code then performs a query against the emp table:

```
EXEC SQL
    SELECT
    empno, ename, sal, comm
INTO
    :v_empno, :v_ename, :v_sal, :v_comm INDICATOR :v_comm_ind
FROM
    emp
WHERE
    empno = 7369;
```

The query returns information about employee number 7369.

The SELECT statement uses an INTO clause to assign the retrieved values (from the empno, ename, sal and comm columns) into the :v_empno, :v_ename, :v_sal and :v_comm host variables (and the :v_comm_ind null indicator). The first value retrieved is assigned to the first variable listed in the INTO clause, the second value is assigned to the second variable, and so on.

The comm column contains the commission values earned by an employee, and could potentially contain a NULL value. The statement includes the INDICATOR keyword, and a host variable to hold a null indicator.

The code checks the null indicator, and displays the appropriate on-screen results:

If the null indicator is 0 (that is, false), the comm column contains a meaningful value, and the printf function displays the commission. If the null indicator contains a non-zero value, comm is NULL, and printf displays a value of NULL. Please note that a host variable (other than a null indicator) contains no meaningful value if you fetch a NULL into that host variable; you must use null indicators to identify any value which may be NULL.

The final statement in the code sample closes the connection to the server:

```
EXEC SQL DISCONNECT;
}
```

Using Indicator Variables

Using Indicator Variables

The previous example included an *indicator variable* that identifies any row in which the value of the comm column (when returned by the server) was NULL . An indicator variable is an extra host variable that denotes if the content of the preceding variable is NULL or truncated. The indicator variable is populated when the contents of a row are stored. An indicator variable may contain the following values:

Indicator Value	Denotes
If an indicator variable is less than 0. If an indicator variable is equal to 0.	The value returned by the server was NULL. The value returned by the server was not NULL, and was not truncated.
If an indicator variable is greater than 0.	The value returned by the server was truncated when stored in the host variable

When including an indicator variable in an INTO clause, you are not required to include the optional INDICATOR keyword.

You may omit an indicator variable if you are certain that a query will never return a NULL value into the

corresponding host variable. If you omit an indicator variable and a query returns a NULL value, ecpglib will raise a run-time error.

Declaring Host Variables

Declaring Host Variables

You can use a *host variable* in a SQL statement at any point that a value may appear within that statement. A host variable is a C variable that you can use to pass data values from the client application to the server, and return data from the server to the client application. A host variable can be:

- an array
- a typedef
- · a pointer
- a struct
- · any scalar C data type

The code fragments that follow demonstrate using host variables in code compiled in PROC mode, and in non-PROC mode. The SQL statement adds a row to the dept table, inserting the values returned by the variables v_deptno, v_dname and v_loc into the deptno column, the dname column and the loc column, respectively.

If you are compiling in PROC mode, you may omit the EXEC SQL BEGIN DECLARE SECTION and EXEC SQL END DECLARE SECTION directives. PROC mode permits you to use C function parameters as host variables:

```
void addDept(int v_deptno, char v_dname, char v_loc)
{
   EXEC SQL INSERT INTO dept VALUES( :v_deptno, :v_dname, :v_loc);
}
```

If you are not compiling in PROC mode, you must wrap embedded variable declarations with the EXEC SQL BEGIN DECLARE SECTION and the EXEC SQL END DECLARE SECTION directives, as shown below:

```
void addDept(int v_deptno, char v_dname, char v_loc)
{
   EXEC SQL BEGIN DECLARE SECTION;
   int v_deptno_copy = v_deptno;
   char v_dname_copy[14+1] = v_dname;
   char v_loc_copy[13+1] = v_loc;
   EXEC SQL END DECLARE SECTION;

EXEC SQL INSERT INTO dept VALUES( :v_deptno, :v_dname, :v_loc);
}
```

You can also include the INTO clause in a SELECT statement to use the host variables to retrieve information:

```
EXEC SQL SELECT deptno, dname, loc
  INTO :v_deptno, :v_dname, v_loc FROM dept;
```

Each column returned by the SELECT statement must have a type-compatible target variable in the INTO clause. This is a simple example that retrieves a single row; to retrieve more than one row, you must define a cursor, as demonstrated in the next example.

Example - Using a Cursor to Process a Result Set

Using a Cursor to Process a Result Set

The code sample that follows demonstrates using a cursor to process a result set. There are four basic steps involved in creating and using a cursor:

1. Use the DECLARE CURSOR statement to define a cursor.

- 2. Use the OPEN CURSOR statement to open the cursor.
- 3. Use the FETCH statement to retrieve data from a cursor.
- 4. Use the CLOSE CURSOR statement to close the cursor.

After declaring host variables, our example connects to the edb database using a user-supplied role name and password, and queries the emp table. The query returns the values into a cursor named employees. The code sample then opens the cursor, and loops through the result set a row at a time, printing the result set. When the sample detects the end of the result set, it closes the connection.

```
/*******************
```

```
print_emps.pgc
*/
#include <stdio.h>
int main(int argc, char *argv[])
EXEC SQL BEGIN DECLARE SECTION;
  char *username = argv[1];
  char *password = arqv[2];
  int v_empno;
  char v_ename[40];
  double v_sal;
  double v_comm;
  short v_comm_ind;
EXEC SQL END DECLARE SECTION;
EXEC SQL WHENEVER SQLERROR sqlprint;
EXEC SQL CONNECT TO edb USER :username IDENTIFIED BY :password;
EXEC SQL DECLARE employees CURSOR FOR
SELECT
  empno, ename, sal, comm
FROM
EXEC SQL OPEN employees;
EXEC SQL WHENEVER NOT FOUND DO break;
for (;;)
EXEC SQL FETCH NEXT FROM employees
  INTO
  :v_empno, :v_ename, :v_sal, :v_comm INDICATOR :v_comm_ind;
if (v_comm_ind)
  printf("empno(%d), ename(%s), sal(%.2f) comm(NULL)\n",
  v_empno, v_ename, v_sal);
else
  printf("empno(%d), ename(%s), sal(%.2f) comm(%.2f)\n",
  v_empno, v_ename, v_sal, v_comm);
EXEC SQL CLOSE employees;
EXEC SQL DISCONNECT;
/************************
The code sample begins by including the prototypes and type definitions for the C stdio library, and then
declares the main function:
#include <stdio.h>
  int main(int argc, char *argv□)
```

Next, the application declares a set of host variables used to interact with the database server:

```
EXEC SQL BEGIN DECLARE SECTION;
    char *username = argv[1];
    char *password = argv[2];
    int v_empno;
    char v_ename[40];
    double v_sal;
    double v_comm;
    short v_comm_ind;
EXEC SQL END DECLARE SECTION;
```

argv[] is an array that contains the command line arguments entered when the user runs the client application. argv[1] contains the first command line argument (in this case, a username), and argv[2] contains the second command line argument (a password); please note that we have omitted the error-checking code you would normally include a real-world application. The declaration initializes the values of username and password, setting them to the values entered when the user invoked the client application.

You may be thinking that you could refer to <code>argv[1]</code> and <code>argv[2]</code> in a SQL statement (instead of creating a separate copy of each variable); that will not work. All host variables must be declared within a <code>BEGIN/END DECLARE SECTION</code> (unless you are compiling in <code>PROC mode</code>). Since <code>argv</code> is a function <code>parameter</code> (not an automatic variable), it cannot be declared within a <code>BEGIN/END DECLARE SECTION</code>. If you are compiling in <code>PROC mode</code>, you can refer to <code>any C</code> variable within a SQL statement.

The next statement instructs the server to respond to an SQL error by printing the text of the error message returned by ECPGPlus or the database server:

```
EXEC SQL WHENEVER SQLERROR sqlprint;
```

Then, the client application establishes a connection with Advanced Server:

```
EXEC SQL CONNECT TO edb USER :username IDENTIFIED BY :password;
```

The CONNECT statement creates a connection to the edb database, using the values found in the :username and :password host variables to authenticate the application to the server when connecting.

The next statement declares a cursor named employees:

```
EXEC SQL DECLARE employees CURSOR FOR SELECT empno, ename, sal, comm FROM emp;
```

employees will contain the result set of a SELECT statement on the emp table. The query returns employee information from the following columns: empno , ename , sal and comm . Notice that when you declare a cursor, you do not include an INTO clause - instead, you specify the target variables (or descriptors) when you FETCH from the cursor.

Before fetching rows from the cursor, the client application must OPEN the cursor:

```
EXEC SQL OPEN employees;
```

In the subsequent FETCH section, the client application will loop through the contents of the cursor; the client application includes a WHENEVER statement that instructs the server to break (that is, terminate the loop) when it reaches the end of the cursor:

```
EXEC SQL WHENEVER NOT FOUND DO break;
```

The client application then uses a FETCH statement to retrieve each row from the cursor INTO the previously declared host variables:

```
for (;;)
{
EXEC SQL FETCH NEXT FROM employees
   INTO
```

```
:v_empno, :v_ename, :v_sal, :v_comm INDICATOR :v_comm_ind;
```

The FETCH statement uses an INTO clause to assign the retrieved values into the $:v_{empno}$, $:v_{ename}$, $:v_{sal}$ and $:v_{comm}$ host variables (and the $:v_{emm}$ null indicator). The first value in the cursor is assigned to the first variable listed in the INTO clause, the second value is assigned to the second variable, and so on.

The FETCH statement also includes the INDICATOR keyword and a host variable to hold a null indicator. If the comm column for the retrieved record contains a NULL value, v_comm_ind is set to a non-zero value, indicating that the column is NULL.

The code then checks the null indicator, and displays the appropriate on-screen results:

```
if (v_comm_ind)
  printf("empno(%d), ename(%s), sal(%.2f) comm(NULL)\n",
  v_empno, v_ename, v_sal);
else
  printf("empno(%d), ename(%s), sal(%.2f) comm(%.2f)\n",
  v_empno, v_ename, v_sal, v_comm);
}
```

If the null indicator is 0 (that is, false), v_{comm} contains a meaningful value, and the printf function displays the commission. If the null indicator contains a non-zero value, comm is $\frac{NULL}{N}$, and $\frac{NULL}{N}$ printf displays the string 'NULL'. Please note that a host variable (other than a null indicator) contains no meaningful value if you fetch a $\frac{NULL}{N}$ into that host variable; you must use null indicators for any value which may be $\frac{NULL}{N}$.

The final statements in the code sample close the cursor (employees), and the connection to the server:

```
EXEC SQL CLOSE employees;
EXEC SQL DISCONNECT;
```

8.3 Using Descriptors

Using Descriptors

Dynamic SQL allows a client application to execute SQL statements that are composed at runtime. This is useful when you don't know the content or form a statement will take when you are writing a client application. ECPGPlus does *not* allow you to use a host variable in place of an identifier (such as a table name, column name or index name); instead, you should use dynamic SQL statements to build a string that includes the information, and then execute that string. The string is passed between the client and the server in the form of a *descriptor*. A descriptor is a data structure that contains both the data and the information about the shape of the data.

A client application must use a GET DESCRIPTOR statement to retrieve information from a descriptor. The following steps describe the basic flow of a client application using dynamic SQL:

- 1. Use an ALLOCATE DESCRIPTOR statement to allocate a descriptor for the result set (select list).
- 2. Use an ALLOCATE DESCRIPTOR statement to allocate a descriptor for the input parameters (bind variables).
- 3. Obtain, assemble or compute the text of an SQL statement.
- 4. Use a PREPARE statement to parse and syntax-check the SQL statement.
- 5. Use a DESCRIBE statement to describe the select list into the select-list descriptor.
- 6. Use a DESCRIBE statement to describe the input parameters into the bind-variables descriptor.
- 7. Prompt the user (if required) for a value for each input parameter. Use a SET DESCRIPTOR statement to assign the values into a descriptor.
- 8. Use a DECLARE CURSOR statement to define a cursor for the statement.
- 9. Use an OPEN CURSOR statement to open a cursor for the statement.
- 10. Use a FETCH statement to fetch each row from the cursor, storing each row in select-list descriptor.

- 11. Use a GET DESCRIPTOR command to interrogate the select-list descriptor to find the value of each column in the current row.
- 12. Use a CLOSE CURSOR statement to close the cursor and free any cursor resources.

A descriptor may contain the attributes listed in the table below:

Example - Using a Descriptor to Return Data

Using a Descriptor to Return Data

The following simple application executes an SQL statement entered by an end user. The code sample demonstrates:

- how to use a SQL descriptor to execute a SELECT statement.
- how to find the data and metadata returned by the statement.

The application accepts an SQL statement from an end user, tests the statement to see if it includes the SELECT keyword, and executes the statement.

When invoking the application, an end user must provide the name of the database on which the SQL statement will be performed, and a string that contains the text of the query.

For example, a user might invoke the sample with the following command:

```
./exec_stmt edb "SELECT * FROM emp"
/*********************
/* exec_stmt.pgc
*/
#include <stdio.h>
#include <stdlib.h>
#include <sql3types.h>
#include <sqlca.h>
EXEC SQL WHENEVER SQLERROR SQLPRINT;
static void print_meta_data( char * desc_name );
char *md1 = "col field data ret";
char *md2 = "num name type len";
char *md3 = "--- ----";
int main( int argc, char *argv[] )
EXEC SQL BEGIN DECLARE SECTION;
char *db = argv[1];
char *stmt = argv[2];
int col_count;
EXEC SQL END DECLARE SECTION;
EXEC SQL CONNECT TO :db;
EXEC SOL ALLOCATE DESCRIPTOR parse_desc;
EXEC SQL PREPARE query FROM :stmt;
EXEC SQL DESCRIBE query INTO SQL DESCRIPTOR parse_desc;
EXEC SQL GET DESCRIPTOR 'parse_desc' :col_count = COUNT;
if( col_count == 0 )
EXEC SQL EXECUTE IMMEDIATE :stmt;
if( sqlca.sqlcode >= 0 )
EXEC SQL COMMIT;
}
else
int row;
EXEC SQL ALLOCATE DESCRIPTOR row_desc;
EXEC SQL DECLARE my_cursor CURSOR FOR query;
EXEC SQL OPEN my_cursor;
for( row = 0; ; row++ )
```

```
EXEC SQL BEGIN DECLARE SECTION;
int col;
EXEC SQL END DECLARE SECTION;
EXEC SQL FETCH IN my_cursor
INTO SQL DESCRIPTOR row_desc;
if( sqlca.sqlcode != 0 )
break;
if(row == 0)
print_meta_data( "row_desc" );
printf("[RECORD %d]\n", row+1);
for( col = 1; col <= col_count; col++ )</pre>
EXEC SQL BEGIN DECLARE SECTION;
short ind;
varchar val[40+1];
varchar name[20+1];
EXEC SQL END DECLARE SECTION;
EXEC SQL GET DESCRIPTOR 'row_desc'
VALUE :col
:val = DATA, :ind = INDICATOR, :name = NAME;
if( ind == -1 )
printf( " %-20s : <null>\n", name.arr );
else if( ind > 0 )
printf( " %-20s : <truncated>\n", name.arr );
printf( " %-20s : %s\n", name.arr, val.arr );
printf( "\n" );
printf( "%d rows\n", row );
exit( 0 );
static void print_meta_data( char *desc_name )
EXEC SQL BEGIN DECLARE SECTION;
char *desc = desc_name;
int col_count;
int col;
EXEC SQL END DECLARE SECTION;
static char *types[] =
{
"unused "
"CHARACTER ",
"NUMERIC "
"DECIMAL "
"INTEGER ".
"SMALLINT ",
"FLOAT ", "REAL ",
"DOUBLE<sup>*</sup>"
"DATE_TIME ",
"INTERVAL ",
"unused "
"CHARACTER_VARYING",
"ENUMERATED ",
"BIT ",
"BIT_VARYING ",
"BOOLEAN "
"abstract "
```

```
EXEC SQL GET DESCRIPTOR :desc :col_count = count;
printf( "%s\n", md1 );
printf( "%s\n", md2 );
printf( "%s\n", md3 );
for( col = 1; col <= col_count; col++ )
EXEC SQL BEGIN DECLARE SECTION;
int type;
int ret_len:
varchar name[21];
EXEC SQL END DECLARE SECTION;
char *type_name;
EXEC SOL GET DESCRIPTOR :desc
VALUE :col
:name = NAME,
:type = TYPE,
:ret_len = RETURNED_OCTET_LENGTH;
if( type > 0 && type < SQL3_abstract )
type_name = types[type];
else
type_name = "unknown";
printf( "%02d: %-20s %-17s %04d\n";
col, name.arr, type_name, ret_len );
printf( "\n" );
   *********************
```

The code sample begins by including the prototypes and type definitions for the C stdio and stdlib libraries, SQL data type symbols, and the SQLCA (SQL communications area) structure:

```
#include <stdio.h>
#include <stdlib.h>
#include <sql3types.h>
#include <sqlca.h>
```

The sample provides minimal error handling; when the application encounters an SQL error, it prints the error message to screen:

```
EXEC SOL WHENEVER SOLERROR SOLPRINT;
```

The application includes a forward-declaration for a function named print_meta_data() that will print the meta-data found in a descriptor:

```
static void print_meta_data( char * desc_name );
```

The following code specifies the column header information that the application will use when printing the metadata:

```
char *md1 = "col field data ret";
char *md2 = "num name type len";
char *md3 = "--- -----;
int main( int argc, char *argv[] )
{
```

The following declaration section identifies the host variables that will contain the name of the database to which the application will connect, the content of the SQL Statement, and a host variable that will hold the number of columns in the result set (if any).

```
EXEC SQL BEGIN DECLARE SECTION;
char *db = argv[1];
char *stmt = argv[2];
int col_count;
EXEC SQL END DECLARE SECTION;
```

The application connects to the database (using the default credentials):

```
EXEC SQL CONNECT TO :db;
```

Next, the application allocates an SQL descriptor to hold the metadata for a statement:

```
EXEC SQL ALLOCATE DESCRIPTOR parse_desc;
```

The application uses a PREPARE statement to syntax check the string provided by the user:

```
EXEC SQL PREPARE query FROM :stmt;
```

and a DESCRIBE statement to move the metadata for the query into the SQL descriptor.

```
EXEC SQL DESCRIBE query INTO SQL DESCRIPTOR parse_desc;
```

Then, the application interrogates the descriptor to discover the number of columns in the result set, and stores that in the host variable collocult.

```
EXEC SQL GET DESCRIPTOR parse_desc :col_count = COUNT;
```

If the column count is zero, the end user did not enter a SELECT statement; the application uses an EXECUTE IMMEDIATE statement to process the contents of the statement:

```
if( col_count == 0 )
{
EXEC SQL EXECUTE IMMEDIATE :stmt;
```

If the statement executes successfully, the application performs a COMMIT:

```
if( sqlca.sqlcode >= 0 )
EXEC SQL COMMIT;
}
else
{
```

If the statement entered by the user is a SELECT statement (which we know because the column count is non-zero), the application declares a variable named row.

```
int row;
```

Then, the application allocates another descriptor that holds the description and the values of a specific row in the result set:

```
EXEC SQL ALLOCATE DESCRIPTOR row_desc;
```

The application declares and opens a cursor for the prepared statement:

```
EXEC SQL DECLARE my_cursor CURSOR FOR query;
EXEC SQL OPEN my_cursor;
Loops through the rows in result set:
for( row = 0; ; row++ )
{
EXEC SQL BEGIN DECLARE SECTION;
int col;
EXEC SQL END DECLARE SECTION;
```

Then, uses a FETCH to retrieve the next row from the cursor into the descriptor:

```
EXEC SQL FETCH IN my_cursor INTO SQL DESCRIPTOR row_desc;
```

The application confirms that the FETCH did not fail; if the FETCH fails, the application has reached the end of the result set, and breaks the loop:

```
if( sqlca.sqlcode != 0 )
break;
```

The application checks to see if this is the first row of the cursor; if it is, the application prints the metadata for the row.

```
if( row == 0 )
print_meta_data( "row_desc" );
```

```
Next, it prints a record header containing the row number:
```

```
printf("[RECORD %d]\n", row+1);
Then, it loops through each column in the row:
for( col = 1; col <= col_count; col++ )
{
EXEC SQL BEGIN DECLARE SECTION;
short ind;
varchar val[40+1];
varchar name[20+1];
EXEC SQL END DECLARE SECTION;</pre>
```

The application interrogates the row descriptor (row_desc) to copy the column value (:val), null indicator (:ind) and column name (:name) into the host variables declared above. Notice that you can retrieve multiple items from a descriptor using a comma-separated list.

```
EXEC SQL GET DESCRIPTOR row_desc
VALUE :col
:val = DATA, :ind = INDICATOR, :name = NAME;
```

If the null indicator (ind) is negative, the column value is NULL; if the null indicator is greater than 0, the column value is too long to fit into the val host variable (so we print <truncated>); otherwise, the null indicator is 0 (meaning NOT NULL) so we print the value. In each case, we prefix the value (or <null> or <truncated>) with the name of the column.

```
if( ind == -1 )
printf( " %-20s : <null>\n", name.arr );
else if( ind > 0 )
printf( " %-20s : <truncated>\n", name.arr );
else
printf( " %-20s : %s\n", name.arr, val.arr );
}
printf( "\n" );
}
```

When the loop terminates, the application prints the number of rows fetched, and exits:

```
printf( "%d rows\n", row );
}
exit( 0 );
}
```

The print_meta_data() function extracts the metadata from a descriptor and prints the name, data type, and length of each column:

```
static void print_meta_data( char *desc_name )
{
The application declares host variables:
EXEC SQL BEGIN DECLARE SECTION;
char *desc = desc_name;
int col_count;
int col;
EXEC SQL END DECLARE SECTION;
```

The application then defines an array of character strings that map data type values (numeric) into data type names. We use the numeric value found in the descriptor to index into this array. For example, if we find that a given column is of type 2, we can find the name of that type (NUMERIC) by writing types[2].

```
static char *types[] =
{
"unused ",
"CHARACTER ",
"NUMERIC ",
"DECIMAL ",
"INTEGER ",
```

```
"SMALLINT ",
"FLOAT ",
"REAL ".
"DOUBLE "
"DATE_TIME ",
"INTERVAL "
"unused "
"CHARACTER_VARYING",
"ENUMERATED ",
"BIT ",
"BIT_VARYING ",
"BOOLEAN ", "abstract "
};
The application retrieves the column count from the descriptor. Notice that the program refers to the descriptor
using a host variable (desc) that contains the name of the descriptor. In most scenarios, you would use an
identifier to refer to a descriptor, but in this case, the caller provided the descriptor name, so we can use a host
variable to refer to the descriptor.
EXEC SQL GET DESCRIPTOR :desc :col_count = count;
The application prints the column headers (defined at the beginning of this application):
printf( "%s\n", md1 );
printf( "%s\n", md2 );
printf( "%s\n", md3 );
Then, loops through each column found in the descriptor, and prints the name, type and length of each column.
for( col = 1; col <= col_count; col++ )</pre>
EXEC SQL BEGIN DECLARE SECTION;
int type;
int ret_len;
varchar name[21];
EXEC SQL END DECLARE SECTION;
char *type_name;
It retrieves the name, type code, and length of the current column:
EXEC SQL GET DESCRIPTOR :desc
VALUE :col
:name = NAME,
:type = TYPE,
:ret_len = RETURNED_OCTET_LENGTH;
If the numeric type code matches a 'known' type code (that is, a type code found in the types[] array), it sets
type_name to the name of the corresponding type; otherwise, it sets type_name to "unknown".
if( type > 0 && type < SQL3_abstract )
type_name = types[type];
else
type_name = "unknown";
and prints the column number, name, type name, and length:
printf( "%02d: %-20s %-17s %04d\n"
col, name.arr, type_name, ret_len );
printf( "\n" );
If you invoke the sample application with the following command:
./exec_stmt test "SELECT * FROM emp WHERE empno IN(7902, 7934)"
```

The application returns:

col field data ret num name type len --- -----01: empno NUMERIC 0004 02: ename CHARACTER_VARYING 0004 03: job CHARACTER_VARYING 0007 04: mar 0004 NUMERIC 05: hiredate DATE_TIME 0018 06: sal NUMERIC 0007 07: comm NUMERIC 0000 08: deptno NUMERIC 0002 [RECORD 1] 7902 empno ename FORD : ANALYST job mgr : 7566 : 03-DEC-81 00:00:00 hiredate sal : 3000.00 comm : <null> deptno : 20 [RECORD 2] empno : 7934 ename : MILLER job : CLERK : 7782 mar hiredate : 23-JAN-82 00:00:00 sal : 1300.00 : <null> comm deptno : 10 2 rows

8.4 Building and Executing Dynamic SQL Statements

Building and Executing Dynamic SQL Statements

The following examples demonstrate four techniques for building and executing dynamic SQL statements. Each example demonstrates processing a different combination of statement and input types:

- The first example demonstrates processing and executing a SQL statement that does not contain a SE-LECT statement and does not require input variables. This example corresponds to the techniques used by Oracle Dynamic SQL Method 1.
- The second example demonstrates processing and executing a SQL statement that does not contain a SELECT statement, and contains a known number of input variables. This example corresponds to the techniques used by Oracle Dynamic SQL Method 2.
- The third example demonstrates processing and executing a SQL statement that may contain a SELECT statement, and includes a known number of input variables. This example corresponds to the techniques used by Oracle Dynamic SQL Method 3.
- The fourth example demonstrates processing and executing a SQL statement that may contain a SE-LECT statement, and includes an unknown number of input variables. This example corresponds to the techniques used by Oracle Dynamic SQL Method 4.

Example - Executing a Non-query Statement Without Parameters

Executing a Non-query Statement Without Parameters

The following example demonstrates how to use the EXECUTE IMMEDIATE command to execute a SQL statement where the text of the statement is not known until you run the application. You cannot use EXECUTE IMMEDIATE to execute a statement that returns a result set. You cannot use EXECUTE IMMEDIATE to execute a statement that contains parameter placeholders.

The EXECUTE IMMEDIATE statement parses and plans the SQL statement each time it executes, which can have a negative impact on the performance of your application. If you plan to execute the same statement repeatedly, consider using the PREPARE/EXECUTE technique described in the next example.

```
/***********************
#include <stdio.h>
#include <string.h>
#include <stdlib.h>
static void handle_error(void);
int main(int argc, char *argv□)
char *insertStmt;
EXEC SQL WHENEVER SQLERROR DO handle_error();
EXEC SQL CONNECT :argv[1];
insertStmt = "INSERT INTO dept VALUES(50, 'ACCTG', 'SEATTLE')";
EXEC SQL EXECUTE IMMEDIATE :insertStmt;
fprintf(stderr, "ok\n");
EXEC SQL COMMIT RELEASE;
exit(EXIT_SUCCESS);
}
static void handle_error(void)
fprintf(stderr, "%s\n", sqlca.sqlerrm.sqlerrmc);
EXEC SQL WHENEVER SQLERROR CONTINUE;
EXEC SQL ROLLBACK RELEASE;
exit(EXIT_FAILURE);
/***********************
```

The code sample begins by including the prototypes and type definitions for the C stdio, string, and stdlib libraries, and providing basic infrastructure for the program:

```
#include <stdio.h>
#include <string.h>
#include <stdlib.h>
static void handle_error(void);
int main(int argc, char *argv[])
{
char *insertStmt;
```

The example then sets up an error handler; ECPGPlus calls the handle error() function whenever a SQL error occurs:

```
EXEC SQL WHENEVER SQLERROR DO handle_error();
```

Then, the example connects to the database using the credentials specified on the command line:

```
EXEC SOL CONNECT :arav[1];
```

Next, the program uses an EXECUTE IMMEDIATE statement to execute a SQL statement, adding a row to the dept table:

```
insertStmt = "INSERT INTO dept VALUES(50, 'ACCTG', 'SEATTLE')";
EXEC SQL EXECUTE IMMEDIATE :insertStmt;
```

If the EXECUTE IMMEDIATE command fails for any reason, ECPGPlus will invoke the handle error() function (which terminates the application after displaying an error message to the user). If the EXECUTE IMMEDIATE command succeeds, the application displays a message (ok) to the user, commits the changes, disconnects from the server, and terminates the application.

```
fprintf(stderr, "ok\n");
EXEC SQL COMMIT RELEASE;
exit(EXIT_SUCCESS);
```

```
}
```

ECPGPlus calls the handle_error() function whenever it encounters a SQL error. The handle_error() function prints the content of the error message, resets the error handler, rolls back any changes, disconnects from the database, and terminates the application.

```
static void handle_error(void)
{
fprintf(stderr, "%s\n", sqlca.sqlerrm.sqlerrmc);
EXEC SQL WHENEVER SQLERROR CONTINUE;
EXEC SQL ROLLBACK RELEASE;
exit(EXIT_FAILURE);
}
```

Example - Executing a Non-query Statement with a Specified Number of Placeholders

Executing a Non-query Statement with a Specified Number of Placeholders

/***********************

To execute a non-query command that includes a known number of parameter placeholders, you must first PREPARE the statement (providing a *statement handle*), and then EXECUTE the statement using the statement handle. When the application executes the statement, it must provide a *value* for each placeholder found in the statement.

When an application uses the PREPARE/EXECUTE mechanism, each SQL statement is parsed and planned once, but may execute many times (providing different *values* each time).

ECPGPlus will convert each parameter value to the type required by the SQL statement, if possible; if not possible, ECPGPlus will report an error.

```
#include <stdio.h>
#include <string.h>
#include <stdlib.h>
#include <salca.h>
static void handle_error(void);
int main(int argc, char *argv[])
char *stmtText;
EXEC SQL WHENEVER SQLERROR DO handle_error();
EXEC SQL CONNECT :argv[1];
stmtText = "INSERT INTO dept VALUES(?, ?, ?)";
EXEC SQL PREPARE stmtHandle FROM :stmtText;
EXEC SQL EXECUTE stmtHandle USING :argv[2], :argv[3], :argv[4];
fprintf(stderr, "ok\n");
EXEC SQL COMMIT RELEASÉ;
exit(EXIT_SUCCESS);
}
static void handle_error(void)
printf("%s\n", sqlca.sqlerrm.sqlerrmc);
EXEC SQL WHENEVER SQLERROR CONTINUE;
EXEC SQL ROLLBACK RELEASE;
exit(EXIT_FAILURE);
}
```

The code sample begins by including the prototypes and type definitions for the C stdio, string, stdlib, and sqlca libraries, and providing basic infrastructure for the program:

```
#include <stdio.h>
#include <string.h>
#include <stdlib.h>
#include <sqlca.h>
static void handle_error(void);
```

```
int main(int argc, char *argv[])
{
char *stmtText;
```

The example then sets up an error handler; ECPGPlus calls the handle_error() function whenever a SQL error occurs:

```
EXEC SQL WHENEVER SQLERROR DO handle_error();
```

Then, the example connects to the database using the credentials specified on the command line:

```
EXEC SQL CONNECT :argv[1];
```

Next, the program uses a PREPARE statement to parse and plan a statement that includes three parameter markers - if the PREPARE statement succeeds, it will create a statement handle that you can use to execute the statement (in this example, the statement handle is named stmtHandle). You can execute a given statement multiple times using the same statement handle.

```
stmtText = "INSERT INTO dept VALUES(?, ?, ?)";
EXEC SQL PREPARE stmtHandle FROM :stmtText;
```

After parsing and planning the statement, the application uses the EXECUTE statement to execute the statement associated with the statement handle, substituting user-provided values for the parameter markers:

```
EXEC SQL EXECUTE stmtHandle USING :argv[2], :argv[3], :argv[4];
```

If the EXECUTE command fails for any reason, ECPGPlus will invoke the handle_error() function (which terminates the application after displaying an error message to the user). If the EXECUTE command succeeds, the application displays a message (ok) to the user, commits the changes, disconnects from the server, and terminates the application.

```
fprintf(stderr, "ok\n");
EXEC SQL COMMIT RELEASE;
exit(EXIT_SUCCESS);
}
```

ECPGPlus calls the handle_error() function whenever it encounters a SQL error. The handle_error() function prints the content of the error message, resets the error handler, rolls back any changes, disconnects from the database, and terminates the application.

```
static void handle_error(void)
{
printf("%s\n", sqlca.sqlerrm.sqlerrmc);
EXEC SQL WHENEVER SQLERROR CONTINUE;
EXEC SQL ROLLBACK RELEASE;
exit(EXIT_FAILURE);
}
```

Example - Executing a Query With a Known Number of Placeholders

Executing a Query With a Known Number of Placeholders

This example demonstrates how to execute a *query* with a known number of input parameters, and with a known number of columns in the result set. This method uses the PREPARE statement to parse and plan a query, before opening a cursor and iterating through the result set.

/***********************

```
#include <stdio.h>
#include <string.h>
#include <stdlib.h>
#include <stdbool.h>
#include <sqlca.h>
static void handle_error(void);
int main(int argc, char *argv[])
{
VARCHAR empno[10];
VARCHAR ename[20];
```

```
EXEC SQL WHENEVER SQLERROR DO handle_error();
EXEC SQL CONNECT :arav[1];
EXEC SQL PREPARE queryHandle
FROM "SELECT empno, ename FROM emp WHERE deptno = ?";
EXEC SQL DECLARE empCursor CURSOR FOR queryHandle;
EXEC SQL OPEN empCursor USING :argv[2];
EXEC SQL WHENEVER NOT FOUND DO break;
while(true)
EXEC SOL FETCH empCursor INTO :empno, :ename;
printf("%-10s %s\n", empno.arr, ename.arr);
EXEC SQL CLOSE empCursor;
EXEC SQL COMMIT RELEASE;
exit(EXIT_SUCCESS);
static void handle_error(void)
printf("%s\n", sqlca.sqlerrm.sqlerrmc);
EXEC SQL WHENEVER SQLERROR CONTINUE;
EXEC SQL ROLLBACK RELEASE;
exit(EXIT_FAILURE);
/***********************
```

and sqlca libraries, and providing basic infrastructure for the program:

The code sample begins by including the prototypes and type definitions for the C stdio, string, stdlib, stdbool,

```
#include <stdio.h>
#include <string.h>
#include <stdlib.h>
#include <stdbool.h>
#include <sqlca.h>
static void handle_error(void);
int main(int argc, char *argv[])
{
VARCHAR empno[10];
VARCHAR ename[20];
```

The example then sets up an error handler; ECPGPlus calls the handle_error() function whenever a SQL error occurs:

```
EXEC SOL WHENEVER SOLERROR DO handle_error();
```

Then, the example connects to the database using the credentials specified on the command line:

```
EXEC SQL CONNECT :argv[1];
```

Next, the program uses a PREPARE statement to parse and plan a query that includes a single parameter marker - if the PREPARE statement succeeds, it will create a statement handle that you can use to execute the statement (in this example, the statement handle is named stmtHandle). You can execute a given statement multiple times using the same statement handle.

```
EXEC SQL PREPARE stmtHandle
FROM "SELECT empno, ename FROM emp WHERE deptno = ?";
```

The program then declares and opens the cursor, empCursor, substituting a user-provided value for the parameter marker in the prepared SELECT statement. Notice that the OPEN statement includes a USING clause: the USING clause must provide a *value* for each placeholder found in the query:

```
EXEC SQL DECLARE empCursor CURSOR FOR stmtHandle;
EXEC SQL OPEN empCursor USING :argv[2];
EXEC SQL WHENEVER NOT FOUND DO break;
while(true)
{
```

The program iterates through the cursor, and prints the employee number and name of each employee in the selected department:

```
EXEC SQL FETCH empCursor INTO :empno, :ename;
printf("%-10s %s\n", empno.arr, ename.arr);
}
```

The program then closes the cursor, commits any changes, disconnects from the server, and terminates the application.

```
EXEC SQL CLOSE empCursor;
EXEC SQL COMMIT RELEASE;
exit(EXIT_SUCCESS);
}
```

The application calls the handle_error() function whenever it encounters a SQL error. The handle_error() function prints the content of the error message, resets the error handler, rolls back any changes, disconnects from the database, and terminates the application.

```
static void handle_error(void)
{
printf("%s\n", sqlca.sqlerrm.sqlerrmc);
EXEC SQL WHENEVER SQLERROR CONTINUE;
EXEC SQL ROLLBACK RELEASE;
exit(EXIT_FAILURE);
}
```

Example - Executing a Query With an Unknown Number of Variables

Executing a Query With an Unknown Number of Variables

The next example demonstrates executing a query with an unknown number of input parameters and/or columns in the result set. This type of query may occur when you prompt the user for the text of the query, or when a query is assembled from a form on which the user chooses from a number of conditions (i.e., a filter).

```
/***********************************
```

```
#include <stdio.h>
#include <stdlib.h>
#include <sqlda.h>
#include <sqlcpr.h>
SQLDA *params;
SQLDA *results;
static void allocateDescriptors(int count,
                                 int varNameLength,
                                int indNameLenth);
static void bindParams(void);
static void displayResultSet(void);
int main(int argc, char *argv□)
EXEC SQL BEGIN DECLARE SECTION;
  char *username = arqv[1];
  char *password = argv[2];
  char *stmtText = argv[3];
EXEC SQL END DECLARE SECTION;
EXEC SQL WHENEVER SQLERROR sqlprint;
EXEC SQL CONNECT TO test
  USER :username
  IDENTIFIED BY :password;
```

```
params = sqlald(20, 64, 64);
results = sqlald(20, 64, 64);
EXEC SQL PREPARE stmt FROM :stmtText;
EXEC SQL DECLARE dynCursor CURSOR FOR stmt;
bindParams();
EXEC SQL OPEN dynCursor USING DESCRIPTOR params;
displayResultSet(20);
static void bindParams(void)
{
  EXEC SQL DESCRIBE BIND VARIABLES FOR stmt INTO params;
  if (params -> F < 0)
    fprintf(stderr, "Too many parameters required\n");
  else
    int i;
    params -> N = params -> F;
    for (i = 0; i < params -> F; i++)
      char *paramName = params->S[i];
      int nameLen = params->C[i];
      char paramValue[255];
      printf("Enter value for parameter %.*s: ",
      nameLen, paramName);
      fgets(paramValue, sizeof(paramValue), stdin);
      params->T[i] = 1; /* Data type = Character (1) */
      params->L[i] = strlen(paramValue) - 1;
      params->V[i] = strdup(paramValue);
    }
  }
}
static void displayResultSet(void)
  EXEC SOL DESCRIBE SELECT LIST FOR stmt INTO results;
  if (results->F < 0)
    fprintf(stderr, "Too many columns returned by query\n");
  else if (results->F == 0)
    return;
  else
  {
    int col;
    results->N = results->F;
    for (col = 0; col < results->F; col++)
      int null_permitted, length;
      sqlnul(&results->T[col],
      &results->T[col],
      &null_permitted);
      switch (results->T[col])
      case 2: /* NUMERIC */
      {
        int precision, scale;
```

```
sqlprc(&results->L[col], &precision, &scale);
        if (precision == 0)
        precision = 38;
        length = precision + 3;
        break;
      }
      case 12: /* DATE */
      {
        length = 30;
        break;
      default: /* Others */
      length = results->L[col] + 1;
      break;
    }
  }
  results->V[col] = realloc(results->V[col], length);
  results->L[col] = length;
  results -> T[col] = 1;
EXEC SQL WHENEVER NOT FOUND DO break;
while (1)
{
  const char *delimiter = "";
  EXEC SQL FETCH dynCursor USING DESCRIPTOR results;
  for (col = 0; col < results->F; col++)
    if (*results -> I[col] == -1)
      printf("%s%s", delimiter, "<null>");
    else
      printf("%s%s", delimiter, results->V[col]);
    delimiter = ", ";
  }
  printf("\n");
}
}
```

The code sample begins by including the prototypes and type definitions for the C stdio and stdlib libraries. In addition, the program includes the sqlda.h and sqlcpr.h header files. sqlda.h defines the SQLDA structure used throughout this example. sqlcpr.h defines a small set of functions used to interrogate the metadata found in an SQLDA structure.

```
#include <stdio.h>
#include <stdlib.h>
#include <sqlda.h>
#include <sqlcpr.h>
```

Next, the program declares pointers to two SQLDA structures. The first SQLDA structure (params) will be used to describe the metadata for any parameter markers found in the dynamic query text. The second SQLDA structure (results) will contain both the metadata and the result set obtained by executing the dynamic query.

```
SQLDA *params;
SQLDA *results;
```

The program then declares two helper functions (defined near the end of the code sample):

```
static void bindParams(void);
static void displayResultSet(void);
```

Next, the program declares three host variables; the first two (username and password) are used to connect

to the database server; the third host variable (stmtTxt) is a NULL-terminated C string containing the text of the query to execute. Notice that the values for these three host variables are derived from the command-line arguments. When the program begins execution, it sets up an error handler and then connects to the database server:

```
int main(int argc, char *argv[])
{
EXEC SQL BEGIN DECLARE SECTION;
char *username = argv[1];
char *password = argv[2];
char *stmtText = argv[3];
EXEC SQL END DECLARE SECTION;
EXEC SQL WHENEVER SQLERROR sqlprint;
EXEC SQL CONNECT TO test
USER :username
IDENTIFIED BY :password;
```

Next, the program calls the sqlald()function to allocate the memory required for each descriptor. Each descriptor contains (among other things):

- · a pointer to an array of column names
- · a pointer to an array of indicator names
- a pointer to an array of data types
- · a pointer to an array of lengths
- · a pointer to an array of data values.

When you allocate an SQLDA descriptor, you specify the maximum number of columns you expect to find in the result set (for SELECT-list descriptors) or the maximum number of parameters you expect to find the dynamic query text (for bind-variable descriptors) - in this case, we specify that we expect no more than 20 columns and 20 parameters. You must also specify a maximum length for each column (or parameter) name and each indicator variable name - in this case, we expect names to be no more than 64 bytes long.

See [SQLDA Structure] (06_reference#sqlda_structure) section for a complete description of the SQLDA structure.

```
params = sqlald(20, 64, 64);
results = sqlald(20, 64, 64);
```

After allocating the SELECT-list and bind descriptors, the program prepares the dynamic statement and declares a cursor over the result set.

```
EXEC SQL PREPARE stmt FROM :stmtText;
EXEC SQL DECLARE dynCursor CURSOR FOR stmt;
```

Next, the program calls the bindParams() function. The bindParams() function examines the bind descriptor (params) and prompt the user for a value to substitute in place of each parameter marker found in the dynamic query.

```
bindParams();
```

Finally, the program opens the cursor (using the parameter values supplied by the user, if any) and calls the displayResultSet() function to print the result set produced by the query.

```
EXEC SQL OPEN dynCursor USING DESCRIPTOR params;
displayResultSet();
}
```

The bindParams() function determines whether the dynamic query contains any parameter markers, and, if so, prompts the user for a value for each parameter and then binds that value to the corresponding marker. The DESCRIBE BIND VARIABLE statement populates the params SQLDA structure with information describing each parameter marker.

```
static void bindParams(void)
{
EXEC SQL DESCRIBE BIND VARIABLES FOR stmt INTO params;
```

If the statement contains no parameter markers, params->F will contain 0. If the statement contains more parameters than will fit into the descriptor, params->F will contain a negative number (in this case, the absolute value of params->F indicates the number of parameter markers found in the statement). If params->F contains a positive number, that number indicates how many parameter markers were found in the statement.

```
if (params->F < 0)
fprintf(stderr, "Too many parameters required\n");
else
{
int i;
params->N = params->F;
```

Next, the program executes a loop that prompts the user for a value, iterating once for each parameter marker found in the statement.

```
for (i = 0; i < params->F; i++)
{
  char *paramName = params->S[i];
  int nameLen = params->C[i];
  char paramValue[255];
  printf("Enter value for parameter %.*s: ",
  nameLen, paramName);
  fgets(paramValue, sizeof(paramValue), stdin);
```

After prompting the user for a value for a given parameter, the program *binds* that value to the parameter by setting params->T[i] to indicate the data type of the value (see Section 7.3 for a list of type codes), params->L[i] to the length of the value (we subtract one to trim off the trailing new-line character added by fgets()), and params->V[i] to point to a copy of the NULL-terminated string provided by the user.

```
params->T[i] = 1; /* Data type = Character (1) */
params->L[i] = strlen(paramValue) + 1;
params->V[i] = strdup(paramValue);
}
}
```

The displayResultSet() function loops through each row in the result set and prints the value found in each column. displayResultSet() starts by executing a DESCRIBE SELECT LIST statement - this statement populates an SQLDA descriptor (results) with a description of each column in the result set.

```
static void displayResultSet(void)
{
EXEC SQL DESCRIBE SELECT LIST FOR stmt INTO results;
```

If the dynamic statement returns no columns (that is, the dynamic statement is not a SELECT statement), results->F will contain 0. If the statement returns more columns than will fit into the descriptor, results->F will contain a negative number (in this case, the absolute value of results->F indicates the number of columns returned by the statement). If results->F contains a positive number, that number indicates how many columns where returned by the query.

```
if (results->F < 0)
fprintf(stderr, "Too many columns returned by query\n");
else if (results->F == 0)
return;
else
{
  int col;
  results->N = results->F;

Next, the program enters a loop, iterating once for each column in the result set:
  for (col = 0; col < results->F; col++)
{
  int null_permitted, length;
```

To decode the type code found in results->T, the program invokes the sqlnul() function (see the description of the T member of the SQLDA structure in Section). This call to sqlnul() modifies results->T[col] to contain only

the type code (the nullability flag is copied to null_permitted). This step is necessary because the DESCRIBE SELECT LIST statement encodes the type of each column and the nullability of each column into the T array.

```
sqlnul(&results->T[col
&results->T[col
&null_permitted);
```

After decoding the actual data type of the column, the program modifies the results descriptor to tell ECPGPlus to return each value in the form of a NULL-terminated string. Before modifying the descriptor, the program must compute the amount of space required to hold each value. To make this computation, the program examines the maximum length of each column (results->V[col]) and the data type of each column (results->T[col]).

For numeric values (where results->T[col] = 2), the program calls the sqlprc() function to extract the precision and scale from the column length. To compute the number of bytes required to hold a numeric value in string form, displayResultSet() starts with the precision (that is, the maximum number of digits) and adds three bytes for a sign character, a decimal point, and a NULL terminator.

```
switch (results->T[col

case 2: /* NUMERIC

int precision, scale
sqlprc(&results->L[col], &precision, &scale);
if (precision == 0)
precision = 38;
length = precision + 3;
break;
}
```

For date values, the program uses a somewhat arbitrary, hard-coded length of 30. In a real-world application, you may want to more carefully compute the amount of space required.

```
case 12: /* DATE */
{
length = 30;
break;
}
```

For a value of any type other than date or numeric, displayResultSet() starts with the maximum column width reported by DESCRIBE SELECT LIST and adds one extra byte for the NULL terminator. Again, in a real-world application you may want to include more careful calculations for other data types.

```
default: /* Others */
{
length = results->L[col] + 1;
break;
}
}
```

After computing the amount of space required to hold a given column, the program allocates enough memory to hold the value, sets results->L[col] to indicate the number of bytes found at results->V[col], and set the type code for the column (results->T[col]) to 1 to instruct the upcoming FETCH statement to return the value in the form of a NULL-terminated string.

```
results->V[col] = malloc(length);
results->L[col] = length;
results->T[col] = 1;
}
```

At this point, the results descriptor is configured such that a FETCH statement can copy each value into an appropriately sized buffer in the form of a NULL-terminated string.

Next, the program defines a new error handler to break out of the upcoming loop when the cursor is exhausted.

```
EXEC SQL WHENEVER NOT FOUND DO break;
while (1)
{
```

```
const char *delimiter = "";
```

The program executes a FETCH statement to fetch the next row in the cursor into the results descriptor. If the FETCH statement fails (because the cursor is exhausted), control transfers to the end of the loop because of the EXEC SQL WHENEVER directive found before the top of the loop.

```
EXEC SQL FETCH dynCursor USING DESCRIPTOR results;
```

The FETCH statement will populate the following members of the results descriptor:

- *results->I[col] will indicate whether the column contains a NULL value (-1) or a non-NULL value (0). If the value non-NULL but too large to fit into the space provided, the value is truncated and *results->I[col] will contain a positive value.
- results->V[col] will contain the value fetched for the given column (unless *results->I[col] indicates that the column value is NULL).
- results->L[col] will contain the length of the value fetched for the given column

Finally, displayResultSet() iterates through each column in the result set, examines the corresponding NULL indicator, and prints the value. The result set is not aligned - instead, each value is separated from the previous value by a comma.

8.5 Error Handling

Error Handling

ECPGPlus provides two methods to detect and handle errors in embedded SQL code:

- A client application can examine the sqlca data structure for error messages, and supply customized error handling for your client application.
- A client application can include EXEC SQL WHENEVER directives to instruct the ECPGPlus compiler to add error-handling code.

Error Handling with sqlca

Error Handling with sqlca

sqlca (SQL communications area) is a global variable used by ecpglib to communicate information from the server to the client application. After executing a SQL statement (for example, an INSERT or SELECT statement) you can inspect the contents of sqlca to determine if the statement has completed successfully or if the statement has failed.

sqlca has the following structure:

```
struct
{
char sqlcaid[8];
long sqlabc;
long sqlcode;
```

```
struct
{
int sqlerrml;
char sqlerrmc[SQLERRMC_LEN];
} sqlerrm;
char sqlerrp[8];
long sqlerrd[6];
char sqlwarn[8];
char sqlstate[5];
} sqlca;
```

Use the following directive to implement sqlca functionality:

```
EXEC SQL INCLUDE sqlca;
```

If you include the ecpg directive, you do not need to #include the sqlca.h file in the client application's header declaration.

The Advanced Server sqlca structure contains the following members:

sqlcaid

sqlcaid contains the string: "SQLCA".

sqlabc

sqlabc contains the size of the sqlca structure.

sqlcode

The sqlcode member has been deprecated with SQL 92; Advanced Server supports sqlcode for backward compatibility, but you should use the sqlstate member when writing new code.

sqlcode is an integer value; a positive sqlcode value indicates that the client application has encountered a harmless processing condition, while a negative value indicates a warning or error.

If a statement processes without error, sqlcode will contain a value of 0. If the client application encounters an error (or warning) during a statement's execution, sqlcode will contain the last code returned.

The SQL standard defines only a positive value of 100, which indicates that he most recent SQL statement processed returned/affected no rows. Since the SQL standard does not define other sqlcode values, please be aware that the values assigned to each condition may vary from database to database.

sqlerrm is a structure embedded within sqlca, composed of two members:

sqlerrml

sqlerrml contains the length of the error message currently stored in sqlerrmc .

sqlerrmc

sqlerrmc contains the null-terminated message text associated with the code stored in sqlstate . If a message exceeds 149 characters in length, ecpglib will truncate the error message.

sqlerrp

sqlerrp contains the string "NOT SET".

sqlerrd is an array that contains six elements:

sqlerrd[1] contains the OID of the processed row (if applicable).

sqlerrd[2] contains the number of processed or returned rows.

sqlerrd[0], sqlerrd[3], sqlerrd[4] and sqlerrd[5] are unused.

sqlwarn is an array that contains 8 characters:

sqlwarn[0] contains a value of 'W' if any other element within sqlwarn is set to 'W'.

sqlwarn[1] contains a value of 'W' if a data value was truncated when it was stored in a host variable.

sqlwarn[2] contains a value of 'W' if the client application encounters a non-fatal warning.

sqlwarn[3], sqlwarn[4], sqlwarn[5], sqlwarn[6], and sqlwarn[7] are unused.

qlstate

sqlstate is a 5 character array that contains a SQL-compliant status code after the execution of a statement from the client application. If a statement processes without error, sqlstate will contain a value of 00000. Please note that sqlstate is *not* a null-terminated string.

sqlstate codes are assigned in a hierarchical scheme:

- The first two characters of sqlstate indicate the general class of the condition.
- The last three characters of sqlstate indicate a specific status within the class.

If the client application encounters multiple errors (or warnings) during an SQL statement's execution sqlstate will contain the last code returned.

The following table lists the sqlstate and sqlcode values, as well as the symbolic name and error description for the related condition:

EXEC SQL WHENEVER

EXEC SQL WHENEVER

Use the EXEC SQL WHENEVER directive to implement simple error handling for client applications compiled with ECPGPlus. The syntax of the directive is:

EXEC SQL WHENEVER <condition> <action>;

This directive instructs the ECPG compiler to insert error-handling code into your program.

The code instructs the client application that it should perform a specified action if the client application detects a given condition. The *condition* may be one of the following:

SQLERROR

A SQLERROR condition exists when sqlca.sqlcode is less than zero.

SQLWARNING

A SQLWARNING condition exists when sqlca.sqlwarn[0] contains a 'W'.

NOT FOUND

A NOT FOUND condition exists when sqlca.sqlcode is ECPG_NOT_FOUND (when a query returns no data).

You can specify that the client application perform one of the following *actions* if it encounters one of the previous conditions:

CONTINUE

Specify CONTINUE to instruct the client application to continue processing, ignoring the current condition. CONTINUE is the default action.

DO CONTINUE

An action of DO CONTINUE will generate a CONTINUE statement in the emitted C code that if it encounters the condition, skips the rest of the code in the loop and continues with the next iteration. You can only use it within a loop.

```
GOTO <label>
or
GO TO <label>
```

Use a C goto statement to jump to the specified label.

SQLPRINT

Print an error message to stderr (standard error), using the sqlprint() function. The sqlprint() function prints sql error , followed by the contents of sqlca.sqlerrm.sqlerrmc .

ST0P

Call exit(1) to signal an error, and terminate the program.

DO BREAK

Execute the C break statement. Use this action in loops, or switch statements.

```
CALL <name> (<args>)
or
DO <name> (<args>)
```

Invoke the C function specified by the name *parameter*, using the parameters specified in the *args* parameter.

Example:

The following code fragment prints a message if the client application encounters a warning, and aborts the application if it encounters an error:

```
EXEC SQL WHENEVER SQLWARNING SQLPRINT; EXEC SQL WHENEVER SQLERROR STOP;
```

Please Note: The ECPGPlus compiler processes your program from top to bottom, even though the client application may not *execute* from top to bottom. The compiler directive is applied to each line in order, and remains in effect until the compiler encounters another directive.

If the control of the flow within your program is not top-to-bottom, you should consider adding error-handling directives to any parts of the program that may be inadvertently missed during compilation.

8.6 Reference

Reference

The sections that follow describe ecpgPlus language elements:

- · C-Preprocessor Directives
- · Supported C Data Types
- Type Codes
- · The SQLDA Structure
- · ECPGPlus Statements

C-preprocessor Directives

C-preprocessor Directives

C-preprocessor Directives

The ECPGPlus C-preprocessor enforces two behaviors that are dependent on the mode in which you invoke ECPGPlus:

- PROC mode
- · non- PROC mode

Compiling in PROC mode

Compiling in PROC Mode

In PROC mode, ECPGPlus allows you to:

- Declare host variables outside of an EXEC SQL BEGIN/END DECLARE SECTION.
- Use any C variable as a host variable as long as it is of a data type compatible with ECPG.

When you invoke ECPGPlus in PROC mode (by including the -C PROC keywords), the ECPG compiler honors the following C-preprocessor directives:

```
#include
#if *expression*
#ifdef *symbolName*
#ifndef *symbolName*
#else
#elif *expression*
#endif
#define *symbolName expansion
#define *symbolName* ([*macro arguments*]) *expansion*
#undef *symbolName*
#defined(*symbolName*)
```

Pre-processor directives are used to effect or direct the code that is received by the compiler. For example, using the following code sample:

```
#if HAVE_LONG_LONG == 1
#define BALANCE_TYPE long long
#else
#define BALANCE_TYPE double
#endif
...
BALANCE_TYPE customerBalance;
```

If you invoke ECPGPlus with the following command-line arguments:

```
ecpg -C PROC -DHAVE_LONG_LONG=1
```

ECPGPlus will copy the entire fragment (without change) to the output file, but will only send the following tokens to the ECPG parser:

```
long long customerBalance;
```

On the other hand, if you invoke ECPGPlus with the following command-line arguments:

```
ecpg -C PROC -DHAVE_LONG_LONG=0
```

The ECPG parser will receive the following tokens:

```
double customerBalance;
```

If your code uses preprocessor directives to filter the code that is sent to the compiler, the complete code is retained in the original code, while the ECPG parser sees only the processed token stream.

You can also use compatible syntax when executing the following preprocessor directives with an executing the following preprocessor directives with an executing the following preprocessor directives with an executing the following preprocessor directives with an executing the following preprocessor directives with an executing the following preprocessor directives with an executing the following preprocessor directives with an executing the following preprocessor directives with an executing the following preprocessor directives with an executing the following preprocessor directives with an executing the following preprocessor directives with an executing the following preprocessor directives with an executing the following preprocessor directives with an executing the following preprocessor directives with an executing the following preprocessor directives with an executing the following preprocessor directives with an executing the following preprocessor directives with a first preprocessor directive and the following preprocessor directives with a first preprocessor directive and the first preproces

EXEC ORACLE DEFINE

EXEC ORACLE UNDEF

EXEC ORACLE INCLUDE

EXEC ORACLE IFDEF

EXEC ORACLE IFNDEF

EXEC ORACLE ELIF

EXEC ORACLE ELSE

EXEC ORACLE ENDIF

EXEC ORACLE OPTION

For example, if your code includes the following:

```
EXEC ORACLE IFDEF HAVE_LONG_LONG;
```

#define BALANCE_TYPE long long

EXEC ORACLE ENDIF;

BALANCE_TYPE customerBalance;

If you invoke ECPGPlus with the following command-line arguments:

```
ecpg -C PROC DEFINE=HAVE_LONG_LONG=1
```

ECPGPlus will send the following tokens to the output file, and the ECPG parser:

```
long long customerBalance;
```

Note

the EXEC ORACLE pre-processor directives only work if you specify -C PROC on the ECPG command line.

Using the SELECT_ERROR Precompiler Option

Using the SELECT_ERROR Precompiler Option

When using ECPGPlus in compatible mode, you can use the SELECT_ERROR precompiler option to instruct your program how to handle result sets that contain more rows than the host variable can accommodate. The syntax is:

```
> SELECT_ERROR={YES | NO}
```

The default value is YES; a SELECT statement will return an error message if the result set exceeds the capacity of the host variable. Specify NO to instruct the program to suppress error messages when a SELECT statement returns more rows than a host variable can accommodate.

Use SELECT_ERROR with the EXEC ORACLE OPTION directive.

Compiling in non-PROC mode

Compiling in non-PROC Mode

If you do not include the -C PROC command-line option:

- C preprocessor directives are copied to the output file without change.
- You must declare the type and name of each C variable that you intend to use as a host variable within an EXEC SQL BEGIN/END DECLARE section.

When invoked in non- PROC mode, ECPG implements the behavior described in the PostgreSQL Core documentation.

Supported C Data Types

Supported C Data Types

An ECPGPlus application must deal with two sets of data types: SQL data types (such as SMALLINT, DOUBLE PRECISION and CHARACTER VARYING) and C data types (like short, double and varchar[n]). When an application fetches data from the server, ECPGPlus will map each SQL data type to the type of the C variable into which the data is returned.

In general, ECPGPlus can convert most SQL server types into similar C types, but not all combinations are valid. For example, ECPGPlus will try to convert a SQL character value into a C integer value, but the conversion may fail (at execution time) if the SQL character value contains non-numeric characters. The reverse is also true; when an application sends a value to the server, ECPGPlus will try to convert the C data type into the required SQL type. Again, the conversion may fail (at execution time) if the C value cannot be converted into the required SQL type.

ECPGPlus can convert any SQL type into C character values (char[n] or varchar[n]). Although it is safe to convert any SQL type to/from char[n] or varchar[n], it is often convenient to use more natural C types such as int, double, or float.

The supported C data types are:

- short
- int
- unsigned int
- long long int
- float
- double
- char[n+1]
- varchar[n+1]
- bool
- and any equivalent created by a typedef

In addition to the numeric and character types supported by C, the pgtypeslib run-time library offers custom data types (and functions to operate on those types) for dealing with date/time and exact numeric values:

- timestamp
- interval
- date
- decimal
- numeric

To use a data type supplied by pgtypeslib, you must #include the proper header file.

Type Codes

Type Codes

The following table contains the type codes for *external* data types. An external data type is used to indicate the type of a C host variable. When an application binds a value to a parameter or binds a buffer to a SELECT-list item, the type code in the corresponding SQLDA descriptor (descriptor->T[column]) should be set to one of the following values:

Type Code	Host Variable Type (C Data Type)
1, 2, 8, 11, 12, 15, 23, 24, 91, 94, 95, 96, 97 3 4, 7, 21 5, 6 9 22 68	char[] int float null-terminated string (char[length+1]) varchar double unsigned int

The following table contains the type codes for *internal* data types. An internal type code is used to indicate the type of a value as it resides in the database. The DESCRIBE SELECT LIST statement populates the data type array (descriptor->T[column]) using the following values.

Internal Type Code	Server Type
1	VARCHAR2
2	NUMBER
8	LONG
11	ROWID
12	DATE
23	RAW
24	LONG RAW
96	CHAR
100	BINARY FLOAT
101	BINARY DOUBLE
104	UROWID
187	TIMESTAMP
188	TIMESTAMP W/TIMEZONE
189	INTERVAL YEAR TO MONTH
190	INTERVAL DAY TO SECOND
232	TIMESTAMP LOCAL_TZ

The SQLDA Structure

SQLDA Structure

Oracle Dynamic SQL method 4 uses the SQLDA data structure to hold the data and metadata for a dynamic SQL statement. A SQLDA structure can describe a set of input parameters corresponding to the parameter markers found in the text of a dynamic statement or the result set of a dynamic statement. The layout of the SQLDA structure is:

```
*/
      **5:
                                  / * Variable names
char
                                  / * Variable name maximum lengths
short
                                  / * Variable name actual lengths
short
       *C:
                                  / * Indicator names
                                                                                  */
      **X;
char
      *Y;
                                                                                  */
                                  / * Indicator name maximum lengths
short
       *Z;
                                  / * Indicator name actual lengths
short
};
```

Parameters

N - maximum number of entries

The N structure member contains the maximum number of entries that the SQLDA may describe. This member is populated by the sqlald() function when you allocate the SQLDA structure. Before using a descriptor in an OPEN or FETCH statement, you must set N to the *actual* number of values described.

V - data values

The V structure member is a pointer to an array of data values.

For a SELECT -list descriptor, V points to an array of values returned by a FETCH statement (each member in the array corresponds to a column in the result set).

For a bind descriptor, V points to an array of parameter values (you must populate the values in this array before opening a cursor that uses the descriptor).

Your application must allocate the space required to hold each value. Refer to [displayResultSet](04_build-ing_executing_dynamic_sql_statements#executing_query_with_unknown_number_of_variables) function for an example of how to allocate space for SELECT -list values.

L - length of each data value

The L structure member is a pointer to an array of lengths. Each member of this array must indicate the amount of memory available in the corresponding member of the V array. For example, if V[5] points to a buffer large enough to hold a 20-byte NULL-terminated string, L[5] should contain the value 21 (20 bytes for the characters in the string plus 1 byte for the NULL-terminator). Your application must set each member of the L array.

T - data types

The T structure member points to an array of data types, one for each column (or parameter) described by the descriptor.

For a bind descriptor, you must set each member of the T array to tell ECPGPlus the data type of each parameter.

For a SELECT -list descriptor, the DESCRIBE SELECT LIST statement sets each member of the T array to reflect the type of data found in the corresponding column.

You may change any member of the T array before executing a FETCH statement to force ECPGPlus to convert the corresponding value to a specific data type. For example, if the DESCRIBE SELECT LIST statement indicates that a given column is of type DATE, you may change the corresponding T member to request that the next FETCH statement return that value in the form of a NULL-terminated string. Each member of the T array is a numeric type code (see Type Codes for a list of type codes). The type codes returned by a DESCRIBE SELECT LIST statement differ from those expected by a FETCH statement. After executing a DESCRIBE SELECT LIST statement, each member of T encodes a data type and a flag indicating whether the corresponding column is nullable. You can use the sqlnul() function to extract the type code and nullable flag from a member of the T array. The signature of the sqlnul() function is as follows:

For example, to find the type code and nullable flag for the third column of a descriptor named results, you would invoke sqlnul() as follows:

sqlnul(&results->T[2], &typeCode, &isNull);

I - indicator variables

The I structure member points to an array of indicator variables. This array is allocated for you when your application calls the sqlald() function to allocate the descriptor.

For a SELECT -list descriptor, each member of the I array indicates whether the corresponding column contains a NULL (non-zero) or non-NULL (zero) value.

For a bind parameter, your application must set each member of the I array to indicate whether the corresponding parameter value is NULL.

F - number of entries

The F structure member indicates how many values are described by the descriptor (the N structure member indicates the *maximum* number of values which may be described by the descriptor; F indicates the actual number of values). The value of the F member is set by ECPGPlus when you execute a DESCRIBE statement. F may be positive, negative, or zero.

For a SELECT -list descriptor, F will contain a positive value if the number of columns in the result set is equal to or less than the maximum number of values permitted by the descriptor (as determined by the N structure member); 0 if the statement is *not* a SELECT statement, or a negative value if the query returns more columns than allowed by the N structure member.

For a bind descriptor, F will contain a positive number if the number of parameters found in the statement is less than or equal to the maximum number of values permitted by the descriptor (as determined by the N structure member); 0 if the statement contains no parameters markers, or a negative value if the statement contains more parameter markers than allowed by the N structure member.

If F contains a positive number (after executing a DESCRIBE statement), that number reflects the count of columns in the result set (for a SELECT -list descriptor) or the number of parameter markers found in the statement (for a bind descriptor). If F contains a negative value, you may compute the absolute value of F to discover how many values (or parameter markers) are required. For example, if F contains -24 after describing a SELECT list, you know that the query returns 24 columns.

S - column/parameter names

The S structure member points to an array of NULL-terminated strings.

For a SELECT -list descriptor, the DESCRIBE SELECT LIST statement sets each member of this array to the name of the corresponding column in the result set.

For a bind descriptor, the DESCRIBE BIND VARIABLES statement sets each member of this array to the name of the corresponding bind variable.

In this release, the name of each bind variable is determined by the left-to-right order of the parameter marker within the query - for example, the name of the first parameter is always ?0 , the name of the second parameter is always ?1 , and so on.

M - maximum column/parameter name length

The M structure member points to an array of lengths. Each member in this array specifies the *maximum* length of the corresponding member of the S array (that is, M[0] specifies the maximum length of the column/parameter name found at S[0]). This array is populated by the sqlald() function.

C - actual column/parameter name length

The C structure member points to an array of lengths. Each member in this array specifies the *actual* length of the corresponding member of the S array (that is, $C[\emptyset]$ specifies the actual length of the column/parameter name found at $S[\emptyset]$).

This array is populated by the DESCRIBE statement.

X - indicator variable names

The X structure member points to an array of NULL-terminated strings -each string represents the name of a NULL indicator for the corresponding value.

This array is not used by ECPGPlus, but is provided for compatibility with Pro*C applications.

Y - maximum indicator name length

The Y structure member points to an array of lengths. Each member in this array specifies the *maximum* length of the corresponding member of the X array (that is, Y[0] specifies the maximum length of the indicator name found at X[0]).

This array is not used by ECPGPlus, but is provided for compatibility with Pro*C applications.

Z - actual indicator name length

The Z structure member points to an array of lengths. Each member in this array specifies the *actual* length of the corresponding member of the X array (that is, Z[0] specifies the actual length of the indicator name found at X[0]).

This array is not used by ECPGPlus, but is provided for compatibility with Pro*C applications.

ECPGPlus Statements

ECPGPlus Statements

An embedded SQL statement allows your client application to interact with the server, while an embedded directive is an instruction to the ECPGPlus compiler.

You can embed any Advanced Server SQL statement in a C program. Each statement should begin with the keywords EXEC SQL , and must be terminated with a semi-colon (;). Within the C program, a SQL statement takes the form:

EXEC SQL <sql_command_body>;

Where *sql_command_body* represents a standard SQL statement. You can use a host variable anywhere that the SQL statement expects a value expression. For more information about substituting host variables for value expressions, please refer to [Declaring Host Variables](02_using_embedded_sql#declaring_host_variables) section.

ECPGPlus extends the PostgreSQL server-side syntax for some statements; for those statements, syntax differences are outlined in the following reference sections. For a complete reference to the supported syntax of other SQL commands, please refer to the *PostgreSQL Core Documentation* available at:

https://www.postgresql.org/docs/12/static/sql-commands.html

ALLOCATE DESCRIPTOR

ALLOCATE DESCRIPTOR

Use the ALLOCATE DESCRIPTOR statement to allocate an SQL descriptor area:

``EXEC SQL [FOR <array_size>] ALLOCATE DESCRIPTOR <descriptor_name> [WITH MAX <variable_count>];`

Where:

array_size is a variable that specifies the number of array elements to allocate for the descriptor. array_size may be an INTEGER value or a host variable.

descriptor_name is the host variable that contains the name of the descriptor, or the name of the descriptor. This value may take the form of an identifier, a quoted string literal, or of a host variable.

variable_count specifies the maximum number of host variables in the descriptor. The default value of variable_count is 100.

The following code fragment allocates a descriptor named emp_query that may be processed as an array (emp_array):

EXEC SQL FOR :emp_array ALLOCATE DESCRIPTOR emp_query;

CALL

CALL

Use the CALL statement to invoke a procedure or function on the server. The CALL statement works only on Advanced Server. The CALL statement comes in two forms; the first form is used to call a *function*:

The second form is used to call a *procedure*:

Where:

program_name is the name of the stored procedure or function that the CALL statement invokes. The program name may be schema-qualified or package-qualified (or both); if you do not specify the schema or package in which the program resides, ECPGPlus will use the value of search_path to locate the program.

actual_arguments specifies a comma-separated list of arguments required by the program. Note that each actual_argument corresponds to a formal argument expected by the program. Each formal argument may be an IN parameter, an OUT parameter, or an INOUT parameter.

:ret_variable specifies a host variable that will receive the value returned if the program is a function.

:ret_indicator specifies a host variable that will receive the indicator value returned, if the program is a function.

For example, the following statement invokes the get_job_desc function with the value contained in the :ename host variable, and captures the value returned by that function in the :job host variable:

```
EXEC SQL CALL get_job_desc(:ename)
   INTO :job;
```

CLOSE

CLOSE

Use the CLOSE statement to close a cursor, and free any resources scurrently in use by the cursor. A client application cannot fetch rows from a closed cursor. The syntax of the CLOSE statement is:

```
EXEC SQL CLOSE [<cursor_name>];
```

Where:

cursor_name is the name of the cursor closed by the statement. The cursor name may take the form of an identifier or of a host variable.

The OPEN statement initializes a cursor. Once initialized, a cursor result set will remain unchanged unless the cursor is re-opened. You do not need to CLOSE a cursor before re-opening it.

To manually close a cursor named emp_cursor, use the command:

```
EXEC SQL CLOSE emp_cursor;
```

A cursor is automatically closed when an application terminates.

COMMIT

COMMIT

Use the COMMIT statement to complete the current transaction, making all changes permanent and visible to other users. The syntax is:

```
EXEC SQL [AT <database_name>] COMMIT [WORK]
[COMMENT <'text'>] [COMMENT <'text'> RELEASE];
```

Where:

database_name is the name of the database (or host variable that contains the name of the database) in which the work resides. This value may take the form of an unquoted string literal, or of a host variable.

For compatibility, ECPGPlus accepts the COMMENT clause without error but does *not* store any text included with the COMMENT clause.

Include the RELEASE clause to close the current connection after performing the commit.

For example, the following command commits all work performed on the dept database and closes the current connection:

```
EXEC SQL AT dept COMMIT RELEASE;
```

By default, statements are committed only when a client application performs a COMMIT statement. Include the -t option when invoking ECPGPlus to specify that a client application should invoke AUTOCOMMIT functionality. You can also control AUTOCOMMIT functionality in a client application with the following statements:

```
EXEC SQL SET AUTOCOMMIT TO ON
```

and

EXEC SQL SET AUTOCOMMIT TO OFF

CONNECT

CONNECT

Use the CONNECT statement to establish a connection to a database. The CONNECT statement is available in two forms - one form is compatible with Oracle databases, the other is not.

The first form is compatible with Oracle databases:

```
EXEC SQL CONNECT
{{:<user_name> IDENTIFIED BY :<password>} | :<connection_id>}
[AT <database_name>]
[USING :<database_string>]
[ALTER AUTHORIZATION :new_password];
```

Where:

user_name is a host variable that contains the role that the client application will use to connect to the server. *password* is a host variable that contains the password associated with that role.

connection_id is a host variable that contains a slash-delimited user name and password used to connect to the database.

Include the AT clause to specify the database to which the connection is established. *database_name* is the name of the database to which the client is connecting; specify the value in the form of a variable, or as a string literal.

Include the USING clause to specify a host variable that contains a null-terminated string identifying the database to which the connection will be established.

The ALTER AUTHORIZATION clause is supported for syntax compatibility only; ECPGPlus parses the ALTER AUTHORIZATION clause, and reports a warning.

Using the first form of the CONNECT statement, a client application might establish a connection with a host variable named user that contains the identity of the connecting role, and a host variable named password that contains the associated password using the following command:

```
EXEC SQL CONNECT :user IDENTIFIED BY :password;
```

A client application could also use the first form of the CONNECT statement to establish a connection using a single host variable named :connection_id . In the following example, connection_id contains the slash-delimited role name and associated password for the user:

```
EXEC SQL CONNECT :connection_id;
```

The syntax of the second form of the CONNECT statement is:

```
EXEC SQL CONNECT TO <database_name>
[AS <connection_name>] [<credentials>];
```

Where credentials is one of the following:

- USER user_name password
- USER user_name IDENTIFIED BY password
- USER user_name USING password

In the second form:

database_name is the name or identity of the database to which the client is connecting. Specify database_name as a variable, or as a string literal, in one of the following forms:

```
<database_name> [@<hostname>][: <port>]
```

tcp:postgresql:// <hostname>[:<port>][/ <database_name>][<options>]

unix:postgresql:// <hostname>[:<port>][/ <database_name>][<options>]

Where:

hostname is the name or IP address of the server on which the database resides.

port is the port on which the server listens.

You can also specify a value of DEFAULT to establish a connection with the default database, using the default role name. If you specify DEFAULT as the target database, do not include a connection_name or credentials.

connection_name is the name of the connection to the database. connection_name should take the form of an identifier (that is, not a string literal or a variable). You can open multiple connections, by providing a unique connection_name for each connection.

If you do not specify a name for a connection, ecpglib assigns a name of DEFAULT to the connection. You can refer to the connection by name (DEFAULT) in any EXEC SQL statement.

CURRENT is the most recently opened or the connection mentioned in the most-recent SET CONNECTION TO statement. If you do not refer to a connection by name in an EXEC SQL statement, ECPG assumes the name of the connection to be CURRENT.

user_name is the role used to establish the connection with the Advanced Server database. The privileges of the specified role will be applied to all commands performed through the connection.

password is the password associated with the specified user_name.

The following code fragment uses the second form of the CONNECT statement to establish a connection to a database named edb, using the role alice and the password associated with that role, 1safepwd:

```
EXEC SQL CONNECT TO edb AS acctg_conn
   USER 'alice' IDENTIFIED BY '1safepwd';
```

The name of the connection is acctg_conn; you can use the connection name when changing the connection name using the SET CONNECTION statement.

DEALLOCATE DESCRIPTOR

DEALLOCATE DESCRIPTOR

Use the DEALLOCATE DESCRIPTOR statement to free memory in use by an allocated descriptor. The syntax of the statement is:

```
EXEC SQL DEALLOCATE DESCRIPTOR *descriptor_name*
```

Where:

descriptor_name is the name of the descriptor. This value may take the form of a quoted string literal, or of a host variable.

The following example deallocates a descriptor named emp_query:

EXEC SQL DEALLOCATE DESCRIPTOR emp_query;

DECLARE CURSOR

DECLARE CURSOR

Use the DECLARE CURSOR statement to define a cursor. The syntax of the statement is:

```
EXEC SQL [AT <database_name>] DECLARE <cursor_name> CURSOR FOR
(<select_statement> | <statement_name>);
```

Where:

database_name is the name of the database on which the cursor operates. This value may take the form of an identifier or of a host variable. If you do not specify a database name, the default value of database_name is the default database.

cursor name is the name of the cursor.

select_statement is the text of the SELECT statement that defines the cursor result set; the SELECT statement cannot contain an INTO clause.

statement_name is the name of a SQL statement or block that defines the cursor result set.

The following example declares a cursor named employees:

```
EXEC SQL DECLARE employees CURSOR FOR SELECT empno, ename, sal, comm FROM emp;
```

The cursor generates a result set that contains the employee number, employee name, salary and commission for each employee record that is stored in the emp table.

DECLARE DATABASE

DECLARE DATABASE

Use the DECLARE DATABASE statement to declare a database identifier for use in subsequent SQL statements (for example, in a CONNECT statement). The syntax is:

```
EXEC SQL DECLARE <database_name> DATABASE;
```

Where:

database_name specifies the name of the database.

The following example demonstrates declaring an identifier for the acctg database:

```
EXEC SQL DECLARE acctg DATABASE;
```

After invoking the command declaring acctg as a database identifier, the acctg database can be referenced by name when establishing a connection or in AT clauses.

This statement has no effect and is provided for Pro*C compatibility only.

DECLARE STATEMENT

DECLARE STATEMENT

Use the DECLARE STATEMENT directive to declare an identifier for an SQL statement. Advanced Server supports two versions of the DECLARE STATEMENT directive:

```
EXEC SQL [<database_name>] DECLARE <statement_name>
STATEMENT;
```

and

EXEC SQL DECLARE STATEMENT <statement_name>;

Where

statement_name specifies the identifier associated with the statement.

database_name specifies the name of the database. This value may take the form of an identifier or of a host variable that contains the identifier.

A typical usage sequence that includes the DECLARE STATEMENT directive might be:

EXEC SQL DECLARE give_raise STATEMENT; // give_raise is now a statement handle (not prepared)

EXEC SQL PREPARE give_raise FROM :stmtText; // give_raise is now associated with a statement EXEC SQL EXECUTE give_raise;

This statement has no effect and is provided for Pro*C compatibility only.

DELETE

DELETE

Use the DELETE statement to delete one or more rows from a table. The syntax for the ECPGPlus DELETE statement is the same as the syntax for the SQL statement, but you can use parameter markers and host variables any place that an expression is allowed. The syntax is:

```
[FOR <exec_count>] DELETE FROM [ONLY]  [[AS] <alias>]
  [USING <using_list>]
  [WHERE <condition> | WHERE CURRENT OF <cursor_name>]
  [{RETURNING|RETURN} * | <output_expression> [[ AS] <output_name>]
[, ...] INTO <host_variable_list> ]
```

Where:

Include the FOR *exec_count* clause to specify the number of times the statement will execute; this clause is valid only if the VALUES clause references an array or a pointer to an array.

table is the name (optionally schema-qualified) of an existing table. Include the ONLY clause to limit processing to the specified table; if you do not include the ONLY clause, any tables inheriting from the named table are also processed.

alias is a substitute name for the target table.

using_list is a list of table expressions, allowing columns from other tables to appear in the WHERE condition.

Include the WHERE clause to specify which rows should be deleted. If you do not include a WHERE clause in the statement, DELETE will delete all rows from the table, leaving the table definition intact.

condition is an expression, host variable or parameter marker that returns a value of type BOOLEAN . Those rows for which condition returns true will be deleted.

cursor_name is the name of the cursor to use in the WHERE CURRENT OF clause; the row to be deleted will be the one most recently fetched from this cursor. The cursor must be a non-grouping query on the DELETE statements target table. You cannot specify WHERE CURRENT OF in a DELETE statement that includes a Boolean condition.

The RETURN/RETURNING clause specifies an *output_expression* or *host_variable_list* that is returned by the DELETE command after each row is deleted:

output_expression is an expression to be computed and returned by the DELETE command after each row is deleted. output_name is the name of the returned column; include * to return all columns.

host_variable_list is a comma-separated list of host variables and optional indicator variables. Each host variable receives a corresponding value from the RETURNING clause.

For example, the following statement deletes all rows from the emp table where the sal column contains a value greater than the value specified in the host variable, :max_sal:

```
DELETE FROM emp WHERE sal > :max_sal;
```

For more information about using the DELETE statement, please see the PostgreSQL Core documentation available at:

https://www.postgresql.org/docs/12/static/sql-delete.html

DESCRIBE

DESCRIBE

Use the DESCRIBE statement to find the number of input values required by a prepared statement or the number of output values returned by a prepared statement. The DESCRIBE statement is used to analyze a SQL statement whose shape is unknown at the time you write your application.

The DESCRIBE statement populates an SQLDA descriptor; to populate a SQL descriptor, use the ALLOCATE DESCRIPTOR and DESCRIBE...DESCRIPTOR statements.

```
EXEC SQL DESCRIBE BIND VARIABLES FOR <statement_name> INTO <descriptor>;
```

or

EXEC SQL DESCRIBE SELECT LIST FOR <statement_name> INTO <descriptor>;

Where:

statement_name is the identifier associated with a prepared SQL statement or PL/SQL block.

descriptor is the name of C variable of type SQLDA*. You must allocate the space for the descriptor by calling sqlald() (and initialize the descriptor) before executing the DESCRIBE statement.

When you execute the first form of the DESCRIBE statement, ECPG populates the given descriptor with a description of each input variable *required* by the statement. For example, given two descriptors:

```
SQLDA *query_values_in;
SQLDA *query_values_out;
```

You might prepare a query that returns information from the emp table:

```
EXEC SQL PREPARE get_emp FROM
"SELECT ename, empno, sal FROM emp WHERE empno = ?";
```

The command requires one input variable (for the parameter marker (?)).

```
EXEC SQL DESCRIBE BIND VARIABLES FOR get_emp INTO query_values_in;
```

After describing the bind variables for this statement, you can examine the descriptor to find the number of variables required and the type of each variable.

When you execute the second form, ECPG populates the given descriptor with a description of each value *returned* by the statement. For example, the following statement returns three values:

```
EXEC SQL DESCRIBE SELECT LIST
FOR get_emp INTO query_values_out;
```

After describing the select list for this statement, you can examine the descriptor to find the number of returned values and the name and type of each value.

Before *executing* the statement, you must bind a variable for each input value and a variable for each output value. The variables that you bind for the input values specify the actual values used by the statement. The variables that you bind for the output values tell ECPGPlus where to put the values when you execute the statement.

This is alternate Pro*C compatible syntax for the DESCRIBE DESCRIPTOR statement.

DESCRIBE DESCRIPTOR

DESCRIBE DESCRIPTOR

Use the DESCRIBE DESCRIPTOR statement to retrieve information about a SQL statement, and store that information in a SQL descriptor. Before using DESCRIBE DESCRIPTOR, you must allocate the descriptor with the ALLOCATE DESCRIPTOR statement. The syntax is:

```
EXEC SQL DESCRIBE [INPUT | OUTPUT] <statement_identifier>
USING [SQL] DESCRIPTOR <descriptor_name>;
```

Where:

statement_name is the name of a prepared SQL statement.

descriptor_name is the name of the descriptor. descriptor_name can be a quoted string value or a host variable that contains the name of the descriptor.

If you include the INPUT clause, ECPGPlus populates the given descriptor with a description of each input variable *required* by the statement.

For example, given two descriptors:

```
EXEC SQL ALLOCATE DESCRIPTOR query_values_in; EXEC SQL ALLOCATE DESCRIPTOR query_values_out;
```

You might prepare a query that returns information from the emptable:

```
EXEC SQL PREPARE get_emp FROM
"SELECT ename, empno, sal FROM emp WHERE empno = ?";
```

The command requires one input variable (for the parameter marker (?)).

```
EXEC SQL DESCRIBE INPUT get_emp USING 'query_values_in';
```

After describing the bind variables for this statement, you can examine the descriptor to find the number of variables required and the type of each variable.

If you do not specify the INPUT clause, DESCRIBE DESCRIPTOR populates the specified descriptor with the values returned by the statement.

If you include the OUTPUT clause, ECPGPlus populates the given descriptor with a description of each value *returned* by the statement.

For example, the following statement returns three values:

```
EXEC SQL DESCRIBE OUTPUT FOR get_emp USING 'query_values_out';
```

After describing the select list for this statement, you can examine the descriptor to find the number of returned values and the name and type of each value.

DISCONNECT

DISCONNECT

Use the DISCONNECT statement to close the connection to the server. The syntax is:

```
EXEC SQL DISCONNECT
[<connection_name>][CURRENT][DEFAULT][ALL];
```

Where:

connection_name is the connection name specified in the CONNECT statement used to establish the connection. If you do not specify a connection name, the current connection is closed.

Include the CURRENT keyword to specify that ECPGPlus should close the most-recently used connection.

Include the DEFAULT keyword to specify that ECPGPlus should close the connection named DEFAULT. If you do not specify a name when opening a connection, ECPGPlus assigns the name, DEFAULT, to the connection.

Include the ALL keyword to instruct ECPGPlus to close all active connections.

The following example creates a connection (named hr_connection) that connects to the hr database, and then disconnects from the connection:

```
/* client.pgc*/
int main()
{
EXEC SQL CONNECT TO hr AS connection_name;
EXEC SQL DISCONNECT connection_name;
return(0);
}
```

EXECUTE

EXECUTE

Use the EXECUTE statement to execute a statement previously prepared using an EXEC SQL PREPARE statement. The syntax is:

```
EXEC SQL [FOR <array_size>] EXECUTE <statement_name>
[USING {DESCRIPTOR <SQLDA_descriptor>
I: <host_variable> [[INDICATOR] :<indicator_variable>]}];
```

Where:

array_size is an integer value or a host variable that contains an integer value that specifies the number of rows to be processed. If you omit the FOR clause, the statement is executed once for each member of the array.

statement_name specifies the name assigned to the statement when the statement was created (using the EXEC SQL PREPARE statement).

Include the USING clause to supply values for parameters within the prepared statement:

Include the DESCRIPTOR SQLDA_descriptor clause to provide an SQLDA descriptor value for a parameter.

Use a *host_variable* (and an optional *indicator_variable*) to provide a user-specified value for a parameter.

The following example creates a prepared statement that inserts a record into the emp table:

```
EXEC SQL PREPARE add_emp (numeric, text, text, numeric) AS INSERT INTO emp VALUES($1, $2, $3, $4);
```

Each time you invoke the prepared statement, provide fresh parameter values for the statement:

```
EXEC SQL EXECUTE add_emp USING 8000, 'DAWSON', 'CLERK', 7788;
```

EXEC SQL EXECUTE add_emp USING 8001, 'EDWARDS', 'ANALYST', 7698;

EXECUTE DESCRIPTOR

EXECUTE DESCRIPTOR

Use the EXECUTE statement to execute a statement previously prepared by an EXEC SQL PREPARE statement, using an SQL descriptor. The syntax is:

EXEC SQL [FOR <array_size>] EXECUTE <statement_identifier> [USING [SQL] DESCRIPTOR <descriptor_name>];

Where:

array_size is an integer value or a host variable that contains an integer value that specifies the number of rows to be processed. If you omit the FOR clause, the statement is executed once for each member of the array.

statement_identifier specifies the identifier assigned to the statement with the EXEC SQL PREPARE statement.

Include the USING clause to specify values for any input parameters required by the prepared statement.

Include the INTO clause to specify a descriptor into which the EXECUTE statement will write the results returned by the prepared statement.

descriptor_name specifies the name of a descriptor (as a single-quoted string literal), or a host variable that contains the name of a descriptor.

The following example executes the prepared statement, give_raise, using the values contained in the descriptor stmtText:

```
EXEC SQL PREPARE give_raise FROM :stmtText; EXEC SQL EXECUTE give_raise USING DESCRIPTOR :stmtText;
```

EXECUTE...END EXEC

EXECUTE...END EXEC

Use the EXECUTE...END-EXEC statement to embed an anonymous block into a client application. The syntax is:

```
EXEC SQL [AT <database_name>] EXECUTE <anonymous_block> END-EXEC;
```

Where:

database_name is the database identifier or a host variable that contains the database identifier. If you omit the AT clause, the statement will be executed on the current default database.

anonymous_block is an inline sequence of PL/pgSQL or SPL statements and declarations. You may include host variables and optional indicator variables within the block; each such variable is treated as an IN/OUT value.

The following example executes an anonymous block:

```
EXEC SQL EXECUTE
BEGIN
IF (current_user = :admin_user_name) THEN
DBMS_OUTPUT.PUT_LINE('You are an administrator');
END IF;
END-EXEC;
```

Note

The EXECUTE...END EXEC statement is supported only by Advanced Server.

EXECUTE IMMEDIATE

EXECUTE IMMEDIATE

Use the EXECUTE IMMEDIATE statement to execute a string that contains a SQL command. The syntax is: EXEC SQL [AT <database_name>] EXECUTE IMMEDIATE <command_text>;

Where:

database_name is the database identifier or a host variable that contains the database identifier. If you omit the AT clause, the statement will be executed on the current default database.

command_text is the command executed by the EXECUTE IMMEDIATE statement.

This dynamic SQL statement is useful when you don't know the text of an SQL statement (ie., when writing a client application). For example, a client application may prompt a (trusted) user for a statement to execute. After the user provides the text of the statement as a string value, the statement is then executed with an EXECUTE IMMEDIATE command.

The statement text may not contain references to host variables. If the statement may contain parameter markers or returns one or more values, you must use the PREPARE and DESCRIBE statements.

The following example executes the command contained in the :command_text host variable:

```
EXEC SQL EXECUTE IMMEDIATE :command_text;
```

FETCH

FETCH

Use the FETCH statement to return rows from a cursor into an SQLDA descriptor or a target list of host variables. Before using a FETCH statement to retrieve information from a cursor, you must prepare the cursor using DECLARE and OPEN statements. The statement syntax is:

```
EXEC SQL [FOR <array_size>] FETCH <cursor>
     { USING DESCRIPTOR <SQLDA_descriptor> }|{ INTO <target_list> };
```

Where:

array_size is an integer value or a host variable that contains an integer value specifying the number of rows to fetch. If you omit the FOR clause, the statement is executed once for each member of the array.

cursor is the name of the cursor from which rows are being fetched, or a host variable that contains the name of the cursor.

If you include a USING clause, the FETCH statement will populate the specified SQLDA descriptor with the values returned by the server.

If you include an INTO clause, the FETCH statement will populate the host variables (and optional indicator variables) specified in the $target_list$.

The following code fragment declares a cursor named employees that retrieves the employee number, name and salary from the emp table:

```
EXEC SQL DECLARE employees CURSOR
SELECT empno, ename, esal FROM emp
EXEC SQL OPEN emp_cursor
EXEC SQL FETCH emp_cursor INTO :emp_no, :emp_name, :emp_sal;
```

FETCH DESCRIPTOR

FETCH DESCRIPTOR

Use the FETCH DESCRIPTOR statement to retrieve rows from a cursor into an SQL descriptor. The syntax is:

```
EXEC SQL [FOR <array_size>] FETCH <cursor>
INTO [SQL] DESCRIPTOR <descriptor_name>;
```

Where:

array_size is an integer value or a host variable that contains an integer value specifying the number of rows to fetch. If you omit the FOR clause, the statement is executed once for each member of the array.

cursor is the name of the cursor from which rows are fetched, or a host variable that contains the name of the cursor. The client must DECLARE and OPEN the cursor before calling the FETCH DESCRIPTOR statement.

Include the INTO clause to specify an SQL descriptor into which the EXECUTE statement will write the results returned by the prepared statement. *descriptor_name* specifies the name of a descriptor (as a single-quoted string literal), or a host variable that contains the name of a descriptor. Prior to use, the descriptor must be allocated using an ALLOCATE DESCRIPTOR statement.

The following example allocates a descriptor named row_desc that will hold the description and the values of a specific row in the result set. It then declares and opens a cursor for a prepared statement (my_cursor

), before looping through the rows in result set, using a FETCH to retrieve the next row from the cursor into the descriptor:

```
EXEC SQL ALLOCATE DESCRIPTOR 'row_desc';
EXEC SQL DECLARE my_cursor CURSOR FOR query;
EXEC SQL OPEN my_cursor;
for( row = 0; ; row++ )
{
EXEC SQL BEGIN DECLARE SECTION;
int col;
EXEC SQL END DECLARE SECTION;
EXEC SQL FETCH my_cursor INTO SQL DESCRIPTOR 'row_desc';
```

GET DESCRIPTOR

GET DESCRIPTOR

Use the GET DESCRIPTOR statement to retrieve information from a descriptor. The GET DESCRIPTOR statement comes in two forms. The first form returns the number of values (or columns) in the descriptor.

```
EXEC SQL GET DESCRIPTOR <descriptor_name>
:<host_variable> = COUNT;
```

The second form returns information about a specific value (specified by the VALUE column_number clause).

```
EXEC SQL [FOR <array_size>] GET DESCRIPTOR
  <descriptor_name>
VALUE <column_number> {:<host_variable> = <descriptor_item>
  {,...}};
```

Where:

array_size is an integer value or a host variable that contains an integer value that specifies the number of rows to be processed. If you specify an array_size, the host_variable must be an array of that size; for example, if array_size is 10, :host_variable must be a 10-member array of host_variables. If you omit the FOR clause, the statement is executed once for each member of the array.

descriptor_name specifies the name of a descriptor (as a single-quoted string literal), or a host variable that contains the name of a descriptor.

Include the VALUE clause to specify the information retrieved from the descriptor.

column_number identifies the position of the variable within the descriptor.

host_variable specifies the name of the host variable that will receive the value of the item.

descriptor_item specifies the type of the retrieved descriptor item.

ECPGPlus implements the following descriptor_item types:

- TYPE
- LENGTH
- · OCTET LENGTH
- RETURNED_LENGTH
- RETURNED_OCTET_LENGTH
- PRECISION
- SCALE
- NULLABLE
- INDICATOR
- DATA

NAME

The following code fragment demonstrates using a GET DESCRIPTOR statement to obtain the number of columns entered in a user-provided string:

```
EXEC SQL ALLOCATE DESCRIPTOR parse_desc;

EXEC SQL PREPARE query FROM :stmt;

EXEC SQL DESCRIBE query INTO SQL DESCRIPTOR parse_desc;

EXEC SQL GET DESCRIPTOR parse_desc :col_count = COUNT;
```

The example allocates an SQL descriptor (named parse_desc), before using a PREPARE statement to syntax check the string provided by the user (:stmt). A DESCRIBE statement moves the user-provided string into the descriptor, parse_desc. The call to EXEC SQL GET DESCRIPTOR interrogates the descriptor to discover the number of columns (:col_count) in the result set.

INSERT

INSERT

Use the INSERT statement to add one or more rows to a table. The syntax for the ECPGPlus INSERT statement is the same as the syntax for the SQL statement, but you can use parameter markers and host variables any place that a value is allowed. The syntax is:

```
[FOR <exec_count>] INSERT INTO  [(<column> [, ...])]
{DEFAULT VALUES |

VALUES ({<expression> | DEFAULT} [, ...])[, ...] \| <query>}
[RETURNING * | <output_expression> [[ AS ]
<output_name>] [, ...]]
```

Where:

Include the FOR exec_count clause to specify the number of times the statement will execute; this clause is valid only if the VALUES clause references an array or a pointer to an array.

table specifies the (optionally schema-qualified) name of an existing table.

column is the name of a column in the table. The column name may be qualified with a subfield name or array subscript. Specify the DEFAULT VALUES clause to use default values for all columns.

expression is the expression, value, host variable or parameter marker that will be assigned to the corresponding column. Specify DEFAULT to fill the corresponding column with its default value.

query specifies a SELECT statement that supplies the row(s) to be inserted.

output_expression is an expression that will be computed and returned by the INSERT command after each row is inserted. The expression can refer to any column within the table. Specify * to return all columns of the inserted row(s).

output_name specifies a name to use for a returned column.

The following example adds a row to the employees table:

```
INSERT INTO emp (empno, ename, job, hiredate)
VALUES ('8400', :ename, 'CLERK', '2011-10-31');
```

Note that the INSERT statement uses a host variable (:ename) to specify the value of the ename column.

For more information about using the INSERT statement, please see the PostgreSQL Core documentation available at:

https://www.postgresql.org/docs/12/static/sql-insert.html

OPEN

OPEN

```
Use the OPEN statement to open a cursor. The syntax is:
```

Where parameters is one of the following:

```
DESCRIPTOR <SQLDA_descriptor> or <host_variable> [ [ INDICATOR ] <indicator_variable>, ... ]
```

Where:

*array_size is an integer value or a host variable that contains an integer value specifying the number of rows to fetch. If you omit the FOR clause, the statement is executed once for each member of the array.

cursor is the name of the cursor being opened.

parameters is either DESCRIPTOR SQLDA_descriptor or a comma-separated list of host variables (and optional indicator variables) that initialize the cursor. If specifying an SQLDA_descriptor, the descriptor must be initialized with a DESCRIBE statement.

The OPEN statement initializes a cursor using the values provided in *parameters*. Once initialized, the cursor result set will remain unchanged unless the cursor is closed and re-opened. A cursor is automatically closed when an application terminates.

The following example declares a cursor named employees , that queries the emp table, returning the employee number , name , salary and commission of an employee whose name matches a user-supplied value (stored in the host variable, :emp_name).

```
EXEC SQL DECLARE employees CURSOR FOR
SELECT
  empno, ename, sal, comm
FROM
  emp
WHERE ename = :emp_name;
EXEC SQL OPEN employees;
```

After declaring the cursor, the example uses an OPEN statement to make the contents of the cursor available to a client application.

OPEN DESCRIPTOR

OPEN DESCRIPTOR

Use the OPEN DESCRIPTOR statement to open a cursor with a SQL descriptor. The syntax is:

```
EXEC SQL [FOR <array_size>] OPEN <cursor>
[USING [SQL] DESCRIPTOR <descriptor_name>]
[INTO [SQL] DESCRIPTOR <descriptor_name>];
```

Where:

array_size is an integer value or a host variable that contains an integer value specifying the number of rows to fetch. If you omit the FOR clause, the statement is executed once for each member of the array.

cursor is the name of the cursor being opened.

descriptor_name specifies the name of an SQL descriptor (in the form of a single-quoted string literal) or a host variable that contains the name of an SQL descriptor that contains the query that initializes the cursor.

For example, the following statement opens a cursor (named emp_cursor), using the host variable, :employees :

EXEC SQL OPEN emp_cursor USING DESCRIPTOR :employees;

PREPARE

PREPARE

Where:

Prepared statements are useful when a client application must perform a task multiple times; the statement is parsed, written and planned only once, rather than each time the statement is executed, saving repetitive processing time.

Use the PREPARE statement to prepare an SQL statement or PL/pgSQL block for execution. The statement is available in two forms; the first form is:

```
EXEC SQL [AT <database_name>] PREPARE
  <statement_name>
FROM <sql_statement>;
The second form is:

EXEC SQL [AT <database_name>] PREPARE
  <statement_name>
AS <sql_statement>;
```

database_name is the database identifier or a host variable that contains the database identifier against which the statement will execute. If you omit the AT clause, the statement will execute against the current default database.

statement_name is the identifier associated with a prepared SQL statement or PL/SQL block.

sql_statement may take the form of a SELECT statement, a single-quoted string literal or host variable that contains the text of an SQL statement.

To include variables within a prepared statement, substitute placeholders (\$1, \$2, \$3, etc.) for statement values that might change when you PREPARE the statement. When you EXECUTE the statement, provide a value for each parameter. The values must be provided in the order in which they will replace placeholders.

The following example creates a prepared statement (named add_emp) that inserts a record into the emp table:

```
EXEC SQL PREPARE add_emp (int, text, text, numeric) AS INSERT INTO emp VALUES($1, $2, $3, $4);
```

Each time you invoke the statement, provide fresh parameter values for the statement:

```
EXEC SQL EXECUTE add_emp(8003, 'Davis', 'CLERK', 2000.00); EXEC SQL EXECUTE add_emp(8004, 'Myer', 'CLERK', 2000.00);
```

Note

A client application must issue a PREPARE statement within each session in which a statement will be executed; prepared statements persist only for the duration of the current session.

ROLLBACK

ROLLBACK

Use the ROLLBACK statement to abort the current transaction, and discard any updates made by the transaction. The syntax is:

```
EXEC SQL [AT <database_name>] ROLLBACK [WORK]
[ { TO [SAVEPOINT] <savepoint> } | RELEASE ]
```

Where:

database_name is the database identifier or a host variable that contains the database identifier against which the statement will execute. If you omit the AT clause, the statement will execute against the current default database.

Include the T0 clause to abort any commands that were executed after the specified savepoint; use the SAVEPOINT statement to define the savepoint. If you omit the T0 clause, the ROLLBACK statement will abort the transaction, discarding all updates.

Include the RELEASE clause to cause the application to execute an EXEC SQL COMMIT RELEASE and close the connection.

Use the following statement to rollback a complete transaction:

```
EXEC SQL ROLLBACK;
```

Invoking this statement will abort the transaction, undoing all changes, erasing any savepoints, and releasing all transaction locks. If you include a savepoint (my_savepoint in the following example):

```
EXEC SQL ROLLBACK TO SAVEPOINT my_savepoint;
```

Only the portion of the transaction that occurred after the my_savepoint is rolled back; my_savepoint is retained, but any savepoints created after my_savepoint will be erased.

Rolling back to a specified savepoint releases all locks acquired after the savepoint.

SAVEPOINT

SAVEPOINT

Use the SAVEPOINT statement to define a savepoint; a savepoint is a marker within a transaction. You can use a ROLLBACK statement to abort the current transaction, returning the state of the server to its condition prior to the specified savepoint. The syntax of a SAVEPOINT statement is:

```
EXEC SQL [AT <database_name>] SAVEPOINT <savepoint_name>
```

Where:

database_name is the database identifier or a host variable that contains the database identifier against which the savepoint resides. If you omit the AT clause, the statement will execute against the current default database.

savepoint_name is the name of the savepoint. If you re-use a savepoint_name, the original savepoint is discarded.

Savepoints can only be established within a transaction block. A transaction block may contain multiple savepoints.

To create a savepoint named my_savepoint, include the statement:

```
EXEC SQL SAVEPOINT my_savepoint;
```

SELECT

SET CONNECTION

ECPGPlus extends support of the SQL SELECT statement by providing the INTO host_variables clause. The clause allows you to select specified information from an Advanced Server database into a host variable. The syntax for the SELECT statement is:

```
EXEC SQL [AT <database_name>]
SELECT
[ <hint> ]
[ ALL | DISTINCT [ ON( <expression>, ...) ]]
<select_list> INTO <host_variables>
[ FROM from_item [, <from_item>]...]
[ WHERE <condition> ]
[ <hierarchical_query_clause> ]
[ GROUP BY <expression> [, ...]]
[ HAVING <condition> ]
[ { UNION [ ALL ] | INTERSECT | MINUS } (<subquery>) ]
```

Where:

database_name is the name of the database (or host variable that contains the name of the database) in which the table resides. This value may take the form of an unquoted string literal, or of a host variable.

host_variables is a list of host variables that will be populated by the SELECT statement. If the SELECT statement returns more than a single row, host_variables must be an array.

ECPGPlus provides support for the additional clauses of the SQL SELECT statement as documented in the PostgreSQL Core documentation available at:

https://www.postgresql.org/docs/12/static/sql-select.html

To use the INTO host_variables clause, include the names of defined host variables when specifying the SELECT statement. For example, the following SELECT statement populates the :emp_name and :emp_sal host variables with a list of employee names and salaries :

```
EXEC SQL SELECT ename, sal
INTO :emp_name, :emp_sal
FROM emp
WHERE empno = 7988;
```

The enhanced SELECT statement also allows you to include parameter markers (question marks) in any clause where a value would be permitted. For example, the following query contains a parameter marker in the WHERE clause:

```
SELECT * FROM emp WHERE dept_no = ?;
```

This SELECT statement allows you to provide a value at run-time for the dept_no parameter marker.

SET CONNECTION

SET CONNECTION

There are (at least) three reasons you may need more than one connection in a given client application:

- · You may want different privileges for different statements;
- · You may need to interact with multiple databases within the same client.
- Multiple threads of execution (within a client application) cannot share a connection concurrently.

The syntax for the SET CONNECTION statement is:

```
EXEC SQL SET CONNECTION <connection_name>;
```

Where:

connection_name is the name of the connection to the database.

To use the SET CONNECTION statement, you should open the connection to the database using the second form of the CONNECT statement; include the AS clause to specify a connection_name .

By default, the current thread uses the current connection; use the SET CONNECTION statement to specify a default connection for the current thread to use. The default connection is only used when you execute an EXEC SQL statement that does not explicitly specify a connection name. For example, the following statement will use the default connection because it does not include an AT connection_name clause. :

```
EXEC SQL DELETE FROM emp;
```

This statement will not use the default connection because it specifies a connection name using the connection_name clause:

```
EXEC SQL AT acctg_conn DELETE FROM emp;
```

For example, a client application that creates and maintains multiple connections (such as):

```
EXEC SQL CONNECT TO edb AS acctg_conn USER 'alice' IDENTIFIED BY 'acctpwd'; and EXEC SQL CONNECT TO edb AS hr_conn USER 'bob' IDENTIFIED BY 'hrpwd';
```

Can change between the connections with the SET CONNECTION statement:

```
SET CONNECTION acctg_conn;
```

or

SET CONNECTION hr_conn;

The server will use the privileges associated with the connection when determining the privileges available to the connecting client. When using the $acctg_conn$ connection, the client will have the privileges associated with the role, alice; when connected using hr_conn , the client will have the privileges associated with bob.

SET DESCRIPTOR

SET DESCRIPTOR

Use the SET DESCRIPTOR statement to assign a value to a descriptor area using information provided by the client application in the form of a host variable or an integer value. The statement comes in two forms; the first form is:

```
EXEC SQL [FOR <array_size>] SET DESCRIPTOR
<descriptor_name>
VALUE <column_number> <descriptor_item> =
<host_variable>;
The second form is:

EXEC SQL [FOR <array_size>] SET DESCRIPTOR
<descriptor_name>
COUNT = integer;
```

Where:

array_size is an integer value or a host variable that contains an integer value specifying the number of rows to fetch. If you omit the FOR clause, the statement is executed once for each member of the array.

descriptor_name specifies the name of a descriptor (as a single-quoted string literal), or a host variable that contains the name of a descriptor.

Include the VALUE clause to describe the information stored in the descriptor.

column_number identifies the position of the variable within the descriptor.

descriptor_item specifies the type of the descriptor item.

host variable specifies the name of the host variable that contains the value of the item.

ECPGPlus implements the following descriptor_item types:

- TYPE
- LENGTH
- [REF] INDICATOR
- [REF] DATA
- [REF] RETURNED LENGTH

For example, a client application might prompt a user for a dynamically created query:

```
query text = promptUser("Enter a query");
```

To execute a dynamically created query, you must first prepare the query (parsing and validating the syntax of the query), and then describe the input parameters found in the query using the EXEC SQL DESCRIBE INPUT statement.

```
EXEC SQL ALLOCATE DESCRIPTOR query_params;

EXEC SQL PREPARE emp_query FROM :query_text;

EXEC SQL DESCRIBE INPUT emp_query

USING SQL DESCRIPTOR 'query_params';
```

After describing the query, the query_params descriptor contains information about each parameter required by the query.

For this example, we'll assume that the user has entered:

```
SELECT ename FROM emp WHERE sal > ? AND job = ?;,
```

In this case, the descriptor describes two parameters, one for sal > ? and one for job = ?.

To discover the number of parameter markers (question marks) in the query (and therefore, the number of values you must provide before executing the query), use:

```
EXEC SQL GET DESCRIPTOR ... :host_variable = COUNT;
```

Then, you can use EXEC SQL GET DESCRIPTOR to retrieve the name of each parameter. You can also use EXEC SQL GET DESCRIPTOR to retrieve the type of each parameter (along with the number of parameters) from the descriptor, or you can supply each value in the form of a character string and ECPG will convert that string into the required data type.

The data type of the first parameter is numeric; the type of the second parameter is varchar. The name of the first parameter is sal; the name of the second parameter is job.

Next, loop through each parameter, prompting the user for a value, and store those values in host variables. You can use GET DESCRIPTOR ... COUNT to find the number of parameters in the guery.

```
EXEC SQL GET DESCRIPTOR 'query_params'
:param_count = COUNT;
for(param_number = 1;
param_number <= param_count;
param_number++)
{</pre>
```

Use GET DESCRIPTOR to copy the name of the parameter into the param_name host variable:

```
EXEC SQL GET DESCRIPTOR 'query_params'
VALUE :param_number :param_name = NAME;
reply = promptUser(param_name);
if (reply == NULL)
reply_ind = 1; /* NULL */
else
reply_ind = 0; /* NOT NULL */
```

To associate a *value* with each parameter, you use the ple: EXEC SQL SET DESCRIPTOR statement. For example:

```
EXEC SQL SET DESCRIPTOR 'query_params'
VALUE :param_number DATA = :reply;
EXEC SQL SET DESCRIPTOR 'query_params'
VALUE :param_number INDICATOR = :reply_ind;
}
```

Now, you can use the EXEC SQL EXECUTE DESCRIPTOR statement to execute the prepared statement on the server.

UPDATE

UPDATE

Use an UPDATE statement to modify the data stored in a table. The syntax is:

```
EXEC SQL [AT <database_name>][FOR <exec_count>]
UPDATE [ ONLY ]  [ [ AS ] <alias> ]
SET {<column> = { <expression> | DEFAULT } |
(<column> [, ...]) = ({ <expression> | DEFAULT } [, ...])} [, ...]
[ FROM <from_list> ]
[ WHERE <condition> | WHERE CURRENT OF <cursor_name> ]
[ RETURNING * | <output_expression> [[ AS ] <output_name>] [, ...] ]
```

Where:

database_name is the name of the database (or host variable that contains the name of the database) in which the table resides. This value may take the form of an unquoted string literal, or of a host variable.

Include the FOR exec_count clause to specify the number of times the statement will execute; this clause is valid only if the SET or WHERE clause contains an array.

ECPGPlus provides support for the additional clauses of the SQL UPDATE statement as documented in the PostgreSQL Core documentation available at:

```
https://www.postgresql.org/docs/12/static/sql-update.html
```

A host variable can be used in any clause that specifies a value. To use a host variable, simply substitute a defined variable for any value associated with any of the documented UPDATE clauses.

The following UPDATE statement changes the job description of an employee (identified by the :ename host variable) to the value contained in the :new_job host variable, and increases the employees salary, by multiplying the current salary by the value in the :increase host variable:

```
EXEC SQL UPDATE emp
SET job = :new_job, sal = sal * :increase
WHERE ename = :ename;
```

The enhanced UPDATE statement also allows you to include parameter markers (question marks) in any clause where an input value would be permitted. For example, we can write the same update statement with a parameter marker in the WHERE clause:

```
EXEC SQL UPDATE emp
SET job = ?, sal = sal * ?
WHERE ename = :ename;
```

This UPDATE statement could allow you to prompt the user for a new value for the job column and provide the amount by which the sal column is incremented for the employee specified by :ename.

WHENEVER

WHENEVER

Use the WHENEVER statement to specify the action taken by a client application when it encounters an SQL error or warning. The syntax is:

```
EXEC SQL WHENEVER <condition> <action>;
```

The following table describes the different conditions that might trigger an action:

Condition	Description
NOT FOUND	The server returns a NOT FOUND condition when it encounters a SELECT that returns no rows, or wher
SQLERROR	The server returns an SQLERROR condition when it encounters a serious error returned by an SQL state
SQLWARNING	The server returns an SQLWARNING condition when it encounters a non-fatal warning returned by an S

The following table describes the actions that result from a client encountering a condition:

Action	Description
CALL function [([args])]	Instructs the client application to call the named function.
CONTINUE	Instructs the client application to proceed to the next statement.
DO BREAK	Instructs the client application to a C break statement. A break statement may appear in a l
DO CONTINUE	Instructs the client application to emit a C continue statement. A continue statement may or
DO function ([args])	Instructs the client application to call the named function.
GOTO label or GO TO label	Instructs the client application to proceed to the statement that contains the label.
SQLPRINT	Instructs the client application to print a message to standard error.
STOP	Instructs the client application to stop execution.

The following code fragment prints a message if the client application encounters a warning, and aborts the application if it encounters an error:

EXEC SQL WHENEVER SQLWARNING SQLPRINT;

EXEC SQL WHENEVER SQLERROR STOP;

Include the following code to specify that a client should continue processing after warning a user of a problem:

EXEC SQL WHENEVER SQLWARNING SQLPRINT;

Include the following code to call a function if a query returns no rows, or when a cursor reaches the end of a result set:

EXEC SQL WHENEVER NOT FOUND CALL error_handler(__LINE__);

8.7 Conclusion

EDB Postgres Advanced Server ecpgPlus Guide

Copyright © 2012 - 2020 EnterpriseDB Corporation. All rights reserved.

EnterpriseDB Corporation 34 Crosby Drive, Suite 201, Bedford, MA 01730, USA

T +1 781 357 3390 F +1 978 467 1307 E info@enterprisedb.com www.enterprisedb.com

- EDB designs, establishes coding best practices, reviews, and verifies input validation for the logon UI for EDB products where present. EDB follows the same approach for additional input components, however the nature of the product may require that it accepts freeform SQL, WMI or other strings to be entered and submitted by trusted users for which limited validation is possible. In such cases it is not possible to prevent users from entering incorrect or otherwise dangerous inputs.
- EDB reserves the right to add features to products that accept freeform SQL, WMI or other potentially dangerous inputs from authenticated, trusted users in the future, but will ensure all such features are designed and tested to ensure they provide the minimum possible risk, and where possible, require superuser or equivalent privileges.
- EDB does not that warrant that we can or will anticipate all potential threats and therefore our process cannot fully guarantee that all potential vulnerabilities have been addressed or considered.

9.0 EDB Postgres Language Pack Guide

Language pack installers contain supported languages that may be used with EDB Postgres Advanced Server and EnterpriseDB PostgreSQL database installers. The language pack installer allows you to install Perl, TCL/TK, and Python without installing supporting software from third party vendors. The Language Pack installer includes:

- TCL with TK version 8.6
- · Perl version 5.26
- Python version 3.7

The Perl package contains the cpan package manager, and Python contains pip and easy_install package managers. There is no package manager for TCL/TK.

In previous Postgres releases, plpython was statically linked with ActiveState's python library. The Language Pack Installer dynamically links with our shared object for python. In ActiveState Linux installers for Python, there is no dynamic library. As a result of these changes, plpython will no longer work with ActiveState installers.

This document uses the term *Postgres* to mean either EDB Postgres Advanced Server or EDB PostgreSQL. For more information about using EDB Postgres products, please visit the EnterpriseDB website at:

https://www.enterprisedb.com/edb-docs

StackBuilder Plus is distributed with Advanced Server; Stack Builder (distributed with PostgreSQL) provides comparable functionality. This document uses the term *StackBuilder Plus* to mean either StackBuilder Plus or Stack Builder.

9.1 Supported Database Server Versions

Language Pack installers are version and platform specific; select the Language Pack installer that corresponds to your Advanced Server or PostgreSQL server version:

Linux:

Advanced Server or PostgreSQL Version	Language Pack Installer Version	Installs Language Versions
9.4	9.4	Perl 5.16, Python 3.3, Tcl 8.5
9.5	9.5	Perl 5.20, Python 3.3, Tcl 8.5
9.6 through 10	1.0	Perl 5.26, Python 3.7, Tcl 8.6

For detailed information about using an RPM package to add Language Pack, please see the EDB Postgres Advanced Server Installation Guide for Linux, available at:

https://www.enterprisedb.com/edb-docs/p/edb-postgres-advanced-server

Mac OS:

Advanced Server or PostgreSQL Version	Language Pack Installer Version	Installs Language Version
9.4 through 12	1.0	Perl 5.26, Python 3.7, Tcl 8.6

Windows 32:

Advanced Server or PostgreSQL Version	Language Pack Installer Version	Installs Language Version
9.4	9.4	Perl 5.16, Python 3.3, Tcl 8.5
9.5	9.5	Perl 5.20, Python 3.3, Tcl 8.5
9.6 through 12	1.0	Perl 5.26, Python 3.7, Tcl 8.6

Windows 64:

Advanced Server or PostgreSQL Version	Language Pack Installer Version	Installs Language Version
9.4	9.4	Perl 5.16, Python 3.3, Tcl 8.5
PostgreSQL 9.5	9.5	Perl 5.20, Python 3.3, Tcl 8.5
PostgreSQL 9.6 through 12	1.0	Perl 5.26, Python 3.7, Tcl 8.8
Advanced Server 12	1.0	Perl 5.26, Python 3.7, Tcl 8.6

9.2 Installing Language Pack

The graphical installer is available from the EnterpriseDB website or via StackBuilder Plus.

Invoking the Graphical Installer

Invoking the Graphical Installer

Assume Administrator privileges, and double-click the installer icon; if prompted, provide the password associated with the Administrator account. When prompted, select an installation language, and click OK.

The installer Welcome window opens.

The Language Pack Welcome Window

Click Next to continue.

The Ready to Install dialog

The Ready to Install window displays the Language Pack installation directory:

On Windows 64: C:\edb\languagepack/v1

On OSX: /Library/edb/languagepack/v1

You cannot modify the installation directory. Click Next to continue.

The Installing dialog

A progress bar marks installation progress; click Next to continue.

The Language Pack Setup Complete dialog

The installer will inform you that the Language Pack installation has completed; click Finish to exit the installer.

Installing Language Pack with StackBuilder Plus

Installing Language Pack with StackBuilder Plus

You can use StackBuilder Plus to download and invoke the Language Pack graphical installer. To open Stack-Builder Plus, select the StackBuilder Plus menu item from the version-specific EDB Postgres sub-menu.

The StackBuilder Plus Welcome Window

Select your server from the drop-down menu on the StackBuilder Plus Welcome window and click Next to continue.

Expand the Add-ons, tools and utilities node of the Categories tree control, and check the box to the left of EDB Language Pack; click Next to continue.

StackBuilder Plus will confirm your package selection before downloading the installer. When the download completes, StackBuilder Plus will offer to invoke the installer for you, or will delay the installation until a more convenient time.

For details about using the graphical installer, see [Invoking the Graphical Installer](02_installing_language_pack#invoking_t Configuring Language Pack on an Advanced Server Host

Configuring Language Pack on an Advanced Server Host

After installing Language Pack on an Advanced Server host, you must configure the installation.

Configuring Language Pack on Windows

Configuring Language Pack on Windows

On Windows, the Language Pack installer places the languages in:

C:\edb\languagepack\v1

After installing Language Pack, you must set the following variables:

set PYTHONHOME=C:\edb\languagepack\v1\Python-3.7

Use the following commands to add Python, Perl and Tcl to your search path:

```
set PATH=C:\edb\languagepack\v1\Python-3.7;
C:\edb\languagepack\v1\Perl-5.26\bin;
C:\edb\languagepack\v1\Tcl-8.6\bin;%PATH%
```

After performing the steps required to configure Language Pack on Windows, use the Windows Services applet to restart the Advanced Server database server.

Configuring Language Pack on a PostgreSQL Host

Configuring Language Pack on a PostgreSQL Host

After installing Language Pack on a PostgreSQL host, you must configure the installation.

Configuring Language Pack on Windows

After installing Language Pack, you must tell the Python interpreter where to find Python:

```
set PYTHONHOME=C:\edb\languagepack\v1\Python-3.7
```

Then, use the following commands to add Language Pack to your search path:

```
set PATH=C:\edb\languagepack\v1\Python-3.7;
C:\edb\languagepack\v1\Perl-5.26\bin;
C:\edb\languagepack\v1\Tcl-8.6\bin;%PATH%
```

After setting the system-specific steps required to configure Language Pack on Windows, restart the database server.

Configuring Language Pack on OSX

To simplify setting the value of PATH or LD_LIBRARY_PATH, you can create environment variables that identify the installation location:

```
PERLHOME=/Library/edb/languagepack/v1/Perl-5.26
PYTHONHOME=/Library/edb/languagepack/v1/Python-3.7
TCLHOME=/Library/edb/languagepack/v1/Tcl-8.6
```

Then, instruct the Python interpreter where to find Python:

```
export PYTHONHOME
```

You can use the same environment variables when setting the value of PATH:

```
export PATH=$PYTHONHOME/bin:
$PERLHOME/bin:
$TCLHOME/bin:$PATH
```

Lastly, use the variables to tell OSX where to find the shared libraries:

```
export DYLD_LIBRARY_PATH=$PYTHONHOME/lib:
$PERLHOME/lib/CORE:$TCLHOME/lib:
$DYLD_LIBRARY_PATH
```

9.3 Using the Procedural Languages

The Postgres procedural languages (PL/Perl, PL/Python, and PL/Java) are installed by the Language Pack installer. You can also use an RPM package to add procedural language functionality to your Advanced Server installation. For more information about using an RPM package, please see the EDB Advanced Server Installation Guide, available at:

https://www.enterprisedb.com/edb-docs

PL/Perl

PL/Perl

The PL/Perl procedural language allows you to use Perl functions in Postgres applications.

You must install PL/Perl in each database (or in a template database) before creating a PL/Perl function. Use the `CREATE LANGUAGE command at the EDB-PSQL command line to install PL/Perl. Open the EDB-PSQL client, establish a connection to the database in which you wish to install PL/Perl, and enter the command:

```
CREATE EXTENSION plperl;
```

You can now use a Postgres client application to access the features of the PL/Perl language. The following PL/Perl example creates a function named perl_max that returns the larger of two integer values:

```
CREATE OR REPLACE FUNCTION perl_max (integer, integer) RETURNS integer
AS
$$
if ($_[0] > $_[1])
{ return $_[0]; }
return $_[1];
$$ LANGUAGE plperl;
```

Pass two values when calling the function:

```
SELECT perl_max(1, 2);
```

The server returns:

```
perl_max
------
2
(1 row)
```

For more information about using the Perl procedural language, consult the official Postgres documentation available at:

https://www.postgresql.org/docs/12/static/plperl.html

PL/Python

PL/Python

The PL/Python procedural language allows you to create and execute functions written in Python within Postgres applications. The version of PL/Python used by Advanced Server and PostgreSQL is untrusted (plpython3u); it offers no restrictions on users to prevent potential security risks.

Install PL/Python in each database (or in a template database) before creating a PL/Python function. You can use the CREATE LANGUAGE command at the EDB-PSQL command line to install PL/Python. Use EDB-PSQL to connect to the database in which you wish to install PL/Python, and enter the command:

```
CREATE EXTENSION plpython3u;
```

After installing PL/Python in your database, you can use the features of the PL/Python language.

Please note: The indentation shown in the following example must be included as you enter the sample function in EDB-PSQL. The following PL/Python example creates a function named pymax that returns the larger of two integer values:

```
CREATE OR REPLACE FUNCTION pymax (a integer, b integer) RETURNS
integer AS
$$
if a > b:
return a
return b
$$ LANGUAGE plpython3u;
```

When calling the pymax function, pass two values as shown below:

```
SELECT pymax(12, 3);
```

The server returns:

```
pymax
-----
12
(1 row)
```

For more information about using the Python procedural language, consult the official PostgreSQL documentation available at:

https://www.postgresql.org/docs/12/static/plpython.html

PL/Tcl

PL/Tcl

The PL/Tcl procedural language allows you to use Tcl/Tk functions in applications.

You must install PL/Tcl in each database (or in a template database) before creating a PL/Tcl function. Use the CREATE LANGUAGE command at the EDB-PSQL command line to install PL/Tcl. Use the psql client to connect to the database in which you wish to install PL/Tcl, and enter the command:

```
CREATE EXTENSION pltcl;
```

After creating the pltcl language, you can use the features of the PL/Tcl language from within your Postgres server.

The following PL/Tcl example creates a function named tcl_max that returns the larger of two integer values:

```
CREATE OR REPLACE FUNCTION tcl_max(integer, integer) RETURNS integer
AS $$
if {[argisnull 1]} {
if {[argisnull 2]} {
    return_null }
    return $2
}
if {[argisnull 2]} {
        return $1
}
if {$1 > $2} {
        return $1}
return $2
$$
LANGUAGE pltcl;
```

Pass two values when calling the function:

```
SELECT tcl_max(1, 2);
```

The server returns:

```
tcl_max
------
2
(1 row)
```

For more information about using the Tcl procedural language, consult the official Postgres documentation available at:

https://www.postgresql.org/docs/12/static/pltcl.html

9.4 Conclusion

EDB Postgres Language Pack Guide

Copyright © 2013 - 2020 EnterpriseDB Corporation. All rights reserved.

EnterpriseDB Corporation 34 Crosby Drive, Suite 201, Bedford, MA 01730, USA

T +1 781 357 3390 F +1 978 467 1307 E info@enterprisedb.com www.enterprisedb.com

- EDB designs, establishes coding best practices, reviews, and verifies input validation for the logon UI for EDB products where present. EDB follows the same approach for additional input components, however the nature of the product may require that it accepts freeform SQL, WMI or other strings to be entered and submitted by trusted users for which limited validation is possible. In such cases it is not possible to prevent users from entering incorrect or otherwise dangerous inputs.
- EDB reserves the right to add features to products that accept freeform SQL, WMI or other potentially dangerous inputs from authenticated, trusted users in the future, but will ensure all such features are designed and tested to ensure they provide the minimum possible risk, and where possible, require superuser or equivalent privileges.
- EDB does not that warrant that we can or will anticipate all potential threats and therefore our process cannot fully guarantee that all potential vulnerabilities have been addressed or considered.

-	
10.0 Index	

10.1.0 Introduction

Advanced Server adds extended functionality to the open-source PostgreSQL database. The extended functionality supports database administration, enhanced SQL capabilities, database and application security, performance monitoring and analysis, and application development utilities. This guide documents those features that are exclusive to Advanced Server.

- Enhanced Compatibility Features. This section provides an overview of compatibility features supported by Advanced Server.
- Database Administration. This section contains information about features and tools that are helpful to the database administrator.
 - Index Advisor helps to determine the additional indexes needed on tables to improve application performance.
 - SQL Profiler locates and diagnoses poorly running SQL queries in applications.
 - pgsnmpd is an SNMP agent that returns hierarchical monitoring information regarding the current state of Advanced Server.
- Security. This section contains information about security features supported by Advanced Server.
 - SQL/Protect provides protection against SQL injection attacks.
 - Virtual Private Database provides fine-grained, row level access.
 - sslutils provides SSL certificate generation functions.
 - Data redaction provides protection against sensitive data exposure.
- EDB Resource Manager. This section contains information about the EDB Resource Manager feature, which provides the capability to control system resource usage by Advanced Server processes.
 - Resource Groups shows how to create and maintain the groups on which resource limits can be defined.
 - CPU Usage Throttling provides a method to control CPU usage by Advanced Server processes.
 - Dirty Buffer Throttling provides a method to control the dirty rate of shared buffers by Advanced Server processes.
- The libpq C Library. The libpq C library is the C application programming interface (API) lanquage for Advanced Server.
- The PL Debugger. The PL Debugger is a graphically oriented debugging tool for PL/pgSQL.
- **Performance Analysis and Tuning.** This section contains the various tools for analyzing and improving application and database server performance.
 - Dynatune provides a quick and easy means for configuring Advanced Server depending upon the type of application usage.
 - EDB wait states provides a way to capture wait events and other data for performance diagnosis.

- EDB Clone Schema. This section contains information about the EDB Clone Schema feature, which provides the capability to copy a schema and its database objects within a single database or from one database to another database.
- Enhanced SQL and Other Miscellaneous Features. This section contains information on enhanced SQL functionality and other features that provide additional flexibility and convenience.
- System Catalog Tables. This section contains additional system catalog tables added for Advanced Server specific database objects.
- Advanced Server Keywords. This section contains information about the words that Advanced Server recognizes as keywords.

For information about the features that are shared by Advanced Server and PostgreSQL, see the PostgreSQL core documentation, available at:

https://www.postgresql.org/docs/current/index.html	

10.1.1 What's New

What's New

The following features have been changed in EDB Postgres Advanced Server 11 to create Advanced Server 12:

- Advanced Server introduces COMPOUND TRIGGERS, which are stored as a PL block that executes in response to a specified triggering event. For information, see the *Database Compatibility for Oracle Developer's Guide*.
- Advanced Server now supports new DATA DICTIONARY VIEWS that provide information that is compatible with the Oracle data dictionary views. For information, see the Database Compatibility for Oracle Developer's Reference Guide.
- Advanced Server has added the LISTAGG function to support string aggregation that concatenates data from multiple rows into a single row in an ordered manner. For information, see the *Database Compatibility for Oracle Developer's Reference Guide*.
- Advanced Server now supports CAST(MULTISET) function, allowing subquery output to be CAST to a nested table type. For information, see the *Database Compatibility for Oracle Developer's Reference Guide*.
- Advanced Server has added the MEDIAN function to calculate a median value from the set of provided values. For information, see the *Database Compatibility for Oracle Developer's Reference Guide*.
- Advanced Server has added the SYS_GUID function to generate and return a globally unique identifier in the form of 16-bytes of RAW data. For information, see the *Database Compatibility for Oracle Developer's Reference Guide*.
- Advanced Server now supports an Oracle-compatible SELECT UNIQUE clause in addition to an existing SELECT DISTINCT clause. For information, see the *Database Compatibility for Oracle Developer's Reference Guide*.
- Advanced Server has re-implemented default_with_rowids , which is used to create a table that includes a ROWID column in the newly created table.
- Advanced Server now supports logical decoding on the standby server, which allows creating a logical replication slot on a standby, independently of a primary server.
- Advanced Server introduces INTERVAL PARTITIONING, which allows a database to automatically create partitions of a specified interval as new data is inserted into a table. For information, see the Database Compatibility for Oracle Developer's Guide.

10.1.2 Conventions Used in this Guide

Conventions Used in Guide

The following is a list of conventions used throughout this document.

• This guide applies to both Linux and Windows systems. Directory paths are presented in the Linux format with forward slashes. When working on Windows systems, start the directory path with the drive letter followed by a colon and substitute back slashes for forward slashes.

- Some of the information in this document may apply interchangeably to the PostgreSQL and EDB Postgres Advanced Server database systems. The term *Advanced Server* is used to refer to EDB Postgres Advanced Server. The term *Postgres* is used to generically refer to both PostgreSQL and Advanced Server. When a distinction needs to be made between these two database systems, the specific names, PostgreSQL or Advanced Server are used.
- The installation directory path of the PostgreSQL or Advanced Server products is referred to as POST-GRES INSTALL HOME.
 - For PostgreSQL Linux installations, this defaults to /opt/PostgreSQL/<x.x> for version 10 and earlier. For later versions, use the PostgreSQL community packages.
 - For Advanced Server Linux installations accomplished using the interactive installer for version 10 and earlier, this defaults to /opt/edb/as<x.x>.
 - For Advanced Server Linux installations accomplished using an RPM package, this defaults to /usr/edb/as<xx>.
 - For Advanced Server Windows installations, this defaults to C:\Program Files\edb\as\<xx>
 The product version number is represented by <x.x> or by <xx> for version 10 and later.

10.1.3 About the Examples Used in this Guide

About the Examples Used in this Guide

The examples in this guide are shown in the type and background illustrated below.

Examples and output from examples are shown in fixed-width, blue font on a light blue background.

The examples use the sample tables, dept, emp, and jobhist, created and loaded when Advanced Server is installed.

The tables and programs in the sample database can be re-created at any time by executing the following script:

/usr/edb/as<xx>/share/pg-sample.sql

where xx is the Advanced Server version number.

In addition there is a script in the same directory containing the database objects created using syntax compatible with Oracle databases. This script file is edb-sample.sql .

The script:

- Creates the sample tables and programs in the currently connected database.
- Grants all permissions on the tables to the PUBLIC group.

The tables and programs will be created in the first schema of the search path in which the current user has permission to create tables and procedures. You can display the search path by issuing the command:

SHOW SEARCH_PATH;

You can use PSQL commands to modify the search path.

Sample Database Description

The sample database represents employees in an organization. It contains three types of records: employees, departments, and historical records of employees.

Each employee has an identification number, name, hire date, salary, and manager. Some employees earn a commission in addition to their salary. All employee-related information is stored in the emp table.

The sample company is regionally diverse, so it tracks the locations of its departments. Each company employee is assigned to a department. Each department is identified by a unique department number and a short name. Each department is associated with one location. All department-related information is stored in the dept table.

The company also tracks information about jobs held by the employees. Some employees have been with the company for a long time and have held different positions, received raises, switched departments, etc. When a

change in employee status occurs, the company records the end date of the former position. A new job record is added with the start date and the new job title, department, salary, and the reason for the status change. All employee history is maintained in the jobhist table.

```
The following is the pg-sample.sql script:
SET datestyle TO 'iso, dmy';
-- Script that creates the 'sample' tables, views
-- functions, triggers, etc.
-- Start new transaction - commit all or nothing
BEGIN;
-- Create and load tables used in the documentation examples.
-- Create the 'dept' table
CREATE TABLE dept (
    deptno NUMERIC(2) NOT NULL CONSTRAINT dept_pk PRIMARY KEY,
    dname VARCHAR(14) CONSTRAINT dept_dname_uq UNIQUE,
    loc VARCHAR(13)
);
-- Create the 'emp' table
CREATE TABLE emp (
    empno NUMERIC(4) NOT NULL CONSTRAINT emp_pk PRIMARY KEY,
    ename VARCHAR(10),
    job VARCHAR(9),
    mgr NUMERIC(4),
    hiredate DATE,
    sal NUMERIC(7,2) CONSTRAINT emp_sal_ck CHECK (sal > 0).
    comm NUMERIC(7,2),
    deptno NUMERIC(2) CONSTRAINT emp_ref_dept_fk
    REFERENCES dept(deptno)
);
-- Create the 'jobhist' table
CREATE TABLE jobhist (
    empno NUMERIC(4) NOT NULL,
    startdate TIMESTAMP(0) NOT NULL,
    enddate TIMESTAMP(0),
    job VARCHAR(9),
    sal NUMERIC(7,2)
    comm NUMERIC(7,2),
    deptno NUMERIC(2),
    chgdesc VARCHAR(80),
    CONSTRAINT jobhist_pk PRIMARY KEY (empno, startdate),
    CONSTRAINT jobhist_ref_emp_fk FOREIGN KEY (empno)
    REFERENCES emp(empno) ON DELETE CASCADE,
    CONSTRAINT jobhist_ref_dept_fk FOREIGN KEY (deptno)
    REFERENCES dept (deptno) ON DELETE SET NULL,
    CONSTRAINT jobhist_date_chk CHECK (startdate <= enddate)
);
-- Create the 'salesemp' view
CREATE OR REPLACE VIEW salesemp AS
```

```
SELECT empno, ename, hiredate, sal, comm FROM emp WHERE job =
'SALESMAN';
-- Sequence to generate values for function 'new_empno'.
CREATE SEQUENCE next_empno START WITH 8000 INCREMENT BY 1;
-- Issue PUBLIC grants
-- GRANT ALL ON emp TO PUBLIC;
--GRANT ALL ON dept TO PUBLIC;
-- GRANT ALL ON jobhist TO PUBLIC;
--GRANT ALL ON salesemp TO PUBLIC;
--GRANT ALL ON next_empno TO PUBLIC;
-- Load the 'dept' table
--
INSERT INTO dept VALUES (10, 'ACCOUNTING', 'NEW YORK');
INSERT INTO dept VALUES (20, 'RESEARCH', 'DALLAS');
INSERT INTO dept VALUES (30, 'SALES', 'CHICAGO')
INSERT INTO dept VALUES (40, 'OPERATIONS', 'BOSTON');
-- Load the 'emp' table
INSERT INTO emp VALUES
(7369, 'SMITH', 'CLERK', 7902, '17-DEC-80', 800, NULL, 20);
INSERT INTO emp VALUES
(7499, 'ALLEN', 'SALESMAN', 7698, '20-FEB-81', 1600, 300, 30);
INSERT INTO emp VALUES
(7521, 'WARD', 'SALESMAN', 7698, '22-FEB-81', 1250, 500, 30);
INSERT INTO emp VALUES
(7566, 'JONES', 'MANAGER', 7839, '02-APR-81', 2975, NULL, 20);
INSERT INTO emp VALUES
(7654, 'MARTIN', 'SALESMAN', 7698, '28-SEP-81', 1250, 1400, 30);
INSERT INTO emp VALUES
(7698, 'BLAKE', 'MANAGER', 7839, '01-MAY-81', 2850, NULL, 30);
INSERT INTO emp VALUES
(7782, 'CLARK', 'MANAGER', 7839, '09-JUN-81', 2450, NULL, 10);
INSERT INTO emp VALUES
(7788, 'SCOTT', 'ANALYST', 7566, '19-APR-87', 3000, NULL, 20);
INSERT INTO emp VALUES
(7839, 'KING', 'PRESIDENT', NULL, '17-NOV-81', 5000, NULL, 10);
INSERT INTO emp VALUES
(7844, 'TURNER', 'SALESMAN', 7698, '08-SEP-81', 1500, 0, 30);
INSERT INTO emp VALUES
(7876, 'ADAMS', 'CLERK', 7788, '23-MAY-87', 1100, NULL, 20);
INSERT INTO emp VALUES
(7900, 'JAMES', 'CLERK', 7698, '03-DEC-81', 950, NULL, 30);
INSERT INTO emp VALUES
(7902, 'FORD', 'ANALYST', 7566, '03-DEC-81', 3000, NULL, 20);
INSERT INTO emp VALUES
(7934, 'MILLER', 'CLERK', 7782, '23-JAN-82', 1300, NULL, 10);
-- Load the 'jobhist' table
INSERT INTO jobhist VALUES
(7369, '17-DEC-80', NULL, 'CLERK', 800, NULL, 20, 'New Hire');
INSERT INTO jobhist VALUES
(7499, '20-FEB-81', NULL, 'SALESMAN', 1600, 300, 30, 'New Hire');
INSERT INTO jobhist VALUES
(7521, '22-FEB-81', NULL, 'SALESMAN', 1250, 500, 30, 'New Hire');
```

```
INSERT INTO jobhist VALUES
(7566, '02-APR-81', NULL, 'MANAGER', 2975, NULL, 20, 'New Hire');
INSERT INTO jobhist VALUES
(7654, '28-SEP-81', NULL, 'SALESMAN', 1250, 1400, 30, 'New Hire');
INSERT INTO jobhist VALUES
(7698, '01-MAY-81', NULL, 'MANAGER', 2850, NULL, 30, 'New Hire');
INSERT INTO jobhist VALUES
(7782, '09-JUN-81', NULL, 'MANAGER', 2450, NULL, 10, 'New Hire');
INSERT INTO jobhist VALUES
(7788, '19-APR-87', '12-APR-88', 'CLERK', 1000, NULL, 20, 'New Hire');
INSERT INTO jobhist VALUES
(7788, '13-APR-88', '04-MAY-89', 'CLERK', 1040, NULL, 20, 'Raise');
INSERT INTO jobhist VALUES
(7788,'05-MAY-90',NULL,'ANALYST',3000,NULL,20,'Promoted to Analyst');
INSERT INTO jobhist VALUES
(7839, '17-NOV-81', NULL, 'PRESIDENT', 5000, NULL, 10, 'New Hire');
INSERT INTO jobhist VALUES
(7844, '08-SEP-81', NULL, 'SALESMAN', 1500, 0, 30, 'New Hire');
INSERT INTO jobhist VALUES
(7876, '23-MAY-87', NULL, 'CLERK', 1100, NULL, 20, 'New Hire');
INSERT INTO jobhist VALUES
(7900, '03-DEC-81', '14-JAN-83', 'CLERK', 950, NULL, 10, 'New Hire');
INSERT INTO jobhist VALUES
(7900, '15-JAN-83', NULL, 'CLERK', 950, NULL, 30, 'Changed to Dept 30');
INSERT INTO jobhist VALUES
(7902, '03-DEC-81', NULL, 'ANALYST', 3000, NULL, 20, 'New Hire');
INSERT INTO jobhist VALUES
(7934, '23-JAN-82', NULL, 'CLERK', 1300, NULL, 10, 'New Hire');
-- Populate statistics table and view (pg_statistic/pg_stats)
ANALYZE dept;
ANALYZE emp;
ANALYZE jobhist;
-- Function that lists all employees' numbers and names
-- from the 'emp' table using a cursor.
CREATE OR REPLACE FUNCTION list_emp() RETURNS VOID
AS $$
DECLARE
    v_empno NUMERIC(4);
    v_{ename} VARCHAR(10);
    emp_cur CURSOR FOR
        SELECT empno, ename FROM emp ORDER BY empno;
BEGIN
    OPEN emp_cur;
    RAISE INFO 'EMPNO ENAME';
    RAISE INFO '----';
    L00P
        FETCH emp_cur INTO v_empno, v_ename;
        EXIT WHEN NOT FOUND;
        RAISE INFO '% %', v_empno, v_ename;
    END LOOP:
CLOSE emp_cur;
RETURN;
END;
$$ LANGUAGE 'plpgsql';
-- Function that selects an employee row given the employee
-- number and displays certain columns.
```


```
CREATE OR REPLACE FUNCTION select_emp (
    p_empno NUMERIC
) RETURNS VOID
AS $$
DECLARE
    v_ename emp.ename%TYPE;
    v_hiredate emp.hiredate%TYPE;
    v_sal emp.sal%TYPE;
    v_comm emp.comm%TYPE;
    v_dname dept.dname%TYPE;
    v_disp_date VARCHAR(10);
BEGIN
  SELECT INTO
    v_ename, v_hiredate, v_sal, v_comm, v_dname
    ename, hiredate, sal, COALESCE(comm, 0), dname
    FROM emp e, dept d
    WHERE empno = p_empno
      AND e.deptno = d.deptno;
IF NOT FOUND THEN
  RAISE INFO 'Employee % not found', p_empno;
  RETURN;
END IF;
v_disp_date := TO_CHAR(v_hiredate, 'MM/DD/YYYY');
RAISE INFO 'Number : %', p_empno;
RAISE INFO 'Name : %', v_ename;
RAISE INFO 'Hire Date : %', v_disp_date;
RAISE INFO 'Salary : %', v_sal;
RAISE INFO 'Commission: %', v_comm;
RAISE INFO 'Department: %', v_dname;
RETURN;
EXCEPTION
  WHEN OTHERS THEN
    RAISE INFO 'The following is SQLERRM: %', SQLERRM;
    RAISE INFO 'The following is SQLSTATE: %', SQLSTATE;
    RETURN;
END;
$$ LANGUAGE 'plpgsql';
-- A RECORD type used to format the return value of
-- function, 'emp_query'.
CREATE TYPE emp_query_type AS (
    empno NUMERIC,
    ename VARCHAR(10),
    job VARCHAR(9),
    hiredate DATE,
    sal NUMERIC
);
-- Function that queries the 'emp' table based on
-- department number and employee number or name. Returns
-- employee number and name as INOUT parameters and job,
-- hire date, and salary as OUT parameters. These are
-- returned in the form of a record defined by
-- RECORD type, 'emp_query_type'.
CREATE OR REPLACE FUNCTION emp_query (
  IN p_deptno NUMERIC,
  INOUT p_empno NUMERIC,
  INOUT p_ename VARCHAR,
```

```
OUT p_job VARCHAR,
  OUT p_hiredate DATE,
  OUT p_sal NUMERIC
)
AS $$
BEGIN
  SELECT INTO
  p_empno, p_ename, p_job, p_hiredate, p_sal
  empno, ename, job, hiredate, sal
  FROM emp
  WHERE deptno = p_deptno
    AND (empno = p_empno)
    OR ename = UPPER(p_ename);
END:
$$ LANGUAGE 'plpgsql';
-- Function to call 'emp_query_caller' with IN and INOUT
-- parameters. Displays the results received from INOUT and
-- OUT parameters.
CREATE OR REPLACE FUNCTION emp_query_caller() RETURNS VOID
AS $$
DECLARE
    v_deptno NUMERIC;
    v_empno NUMERIC;
    v_ename VARCHAR;
    v_rows INTEGER;
    r_emp_query EMP_QUERY_TYPE;
BEGIN
    v_{deptno} := 30;
    v_{empno} := 0;
    v_ename := 'Martin';
    r_emp_query := emp_query(v_deptno, v_empno, v_ename);
    RAISE INFO 'Department : %', v_deptno;
RAISE INFO 'Employee No: %', (r_emp_query).empno;
    RAISE INFO 'Name : %', (r_emp_query).ename; RAISE INFO 'Job : %', (r_emp_query).job;
    RAISE INFO 'Hire Date : %', (r_emp_query).hiredate;
    RAISE INFO 'Salary : %', (r_emp_query).sal;
    RETURN;
EXCEPTION
  WHEN OTHERS THEN
    RAISE INFO 'The following is SQLERRM: %', SQLERRM;
    RAISE INFO 'The following is SQLSTATE: %', SQLSTATE;
    RETURN;
END;
$$ LANGUAGE 'plpgsql';
-- Function to compute yearly compensation based on semimonthly
-- salary.
CREATE OR REPLACE FUNCTION emp_comp (
    p_sal NUMERIC,
    p_comm NUMERIC
) RETURNS NUMERIC
AS $$
BEGIN
    RETURN (p_sal + COALESCE(p_comm, 0)) * 24;
END;
$$ LANGUAGE 'plpgsql';
```

```
-- Function that gets the next number from sequence, 'next_empno',
-- and ensures it is not already in use as an employee number.
CREATE OR REPLACE FUNCTION new_empno() RETURNS INTEGER
AS $$
DECLARE
    v_cnt INTEGER := 1;
    v_new_empno INTEGER;
BEGIN
    WHILE v_{cnt} > 0 LOOP
      SELECT INTO v_new_empno nextval('next_empno');
      SELECT INTO v_cnt COUNT(*) FROM emp WHERE empno = v_new_empno;
    END LOOP;
    RETURN v_new_empno;
END;
$$ LANGUAGE 'plpgsql';
-- Function that adds a new clerk to table 'emp'.
CREATE OR REPLACE FUNCTION hire_clerk (
    p_ename VARCHAR,
    p_deptno NUMERIC
) RETURNS NUMERIC
AS $$
DECLARE
    v_empno NUMERIC(4);
    v_ename VARCHAR(10);
    v_job VARCHAR(9);
    v_mgr NUMERIC(4);
    v_hiredate DATE;
    v_sal\ NUMERIC(7,2);
    v_{comm} NUMERIC(7,2);
    v_deptno NUMERIC(2);
BEGIN
    v_empno := new_empno();
    INSERT INTO emp VALUES (v_empno, p_ename, 'CLERK', 7782,
      CURRENT_DATE, 950.00, NULL, p_deptno);
    SELECT INTO
      v_empno, v_ename, v_job, v_mgr, v_hiredate, v_sal, v_comm, v_deptno
      empno, ename, job, mgr, hiredate, sal, comm, deptno
      FROM emp WHERE empno = v_{empno};
    RAISE INFO 'Department : %', v_deptno;
    RAISE INFO 'Employee No: %', v_empno;
    RAISE INFO 'Name : %', v_ename;
    RAISE INFO 'Job : %', v_job;
RAISE INFO 'Manager : %', v_mgr;
    RAISE INFO 'Hire Date : %', v_hiredate;
    RAISE INFO 'Salary : %', v_sal;
    RAISE INFO 'Commission : %', v_comm;
    RETURN v_empno;
EXCEPTION
  WHEN OTHERS THEN
    RAISE INFO 'The following is SQLERRM: %', SQLERRM;
    RAISE INFO 'The following is SQLSTATE: %', SQLSTATE;
    RETURN -1;
END;
$$ LANGUAGE 'plpgsql';
-- Function that adds a new salesman to table 'emp'.
CREATE OR REPLACE FUNCTION hire_salesman (
```

```
p_ename VARCHAR,
    p_sal NUMERIC,
    p_comm NUMERIC
) RETURNS NUMERIC
AS $$
DECLARE
    v_empno NUMERIC(4);
    v_ename VARCHAR(10);
    v_job VARCHAR(9);
    v_mgr NUMERIC(4);
    v_hiredate DATE;
    v_sal\ NUMERIC(7,2);
    V_comm NUMERIC(7,2);
    v_deptno NUMERIC(2);
BEGIN
    v_empno := new_empno();
    INSERT INTO emp VALUES (v_empno, p_ename, 'SALESMAN', 7698,
      CURRENT_DATE, p_sal, p_comm, 30);
    SELECT INTO
      v_empno, v_ename, v_job, v_mgr, v_hiredate, v_sal, v_comm, v_deptno
      empno, ename, job, mgr, hiredate, sal, comm, deptno
      FROM emp WHERE empno = v_{empno};
    RAISE INFO 'Department : %', v_deptno;
    RAISE INFO 'Employee No: %', v_empno;
    RAISE INFO 'Name : %', v_ename;
    RAISE INFO 'Job : %', v_job;
    RAISE INFO 'Manager : %', v_mgr;
    RAISE INFO 'Hire Date : %', v_hiredate;
    RAISE INFO 'Salary : %', v_sal;
    RAISE INFO 'Commission : %', v_comm;
    RETURN v_empno;
EXCEPTION
  WHEN OTHERS THEN
    RAISE INFO 'The following is SQLERRM: %', SQLERRM;
    RAISE INFO 'The following is SQLSTATE: %', SQLSTATE;
    RETURN -1;
END;
$$ LANGUAGE 'plpgsql';
-- Rule to INSERT into view 'salesemp'
CREATE OR REPLACE RULE salesemp_i AS ON INSERT TO salesemp
DO INSTEAD
INSERT INTO emp VALUES (NEW.empno, NEW.ename, 'SALESMAN', 7698,
NEW.hiredate, NEW.sal, NEW.comm, 30);
-- Rule to UPDATE view 'salesemp'
CREATE OR REPLACE RULE salesemp_u AS ON UPDATE TO salesemp
DO INSTEAD
  UPDATE emp SET empno
                          = NEW.empno,
                 ename
                          = NEW.ename,
                 hiredate = NEW.hiredate,
                 sal
                          = NEW.sal,
                 comm
                          = NEW.comm
  WHERE empno = OLD.empno;
-- Rule to DELETE from view 'salesemp'
CREATE OR REPLACE RULE salesemp_d AS ON DELETE TO salesemp
DO INSTEAD
```

```
DELETE FROM emp WHERE empno = OLD.empno;
-- After statement-level trigger that displays a message after
-- an insert, update, or deletion to the 'emp' table. One message
-- per SQL command is displayed.
CREATE OR REPLACE FUNCTION user_audit_trig() RETURNS TRIGGER
AS $$
DECLARE
    v_action VARCHAR(24);
    v_text TEXT;
BEGIN
    IF TG_OP = 'INSERT' THEN
      v_action := ' added employee(s) on ';
    ELSIF TG_OP = 'UPDATE' THEN
      v_action := ' updated employee(s) on ';
    ELSIF TG_OP = 'DELETE' THEN
      v_action := ' deleted employee(s) on ';
    END IF;
v_text := 'User ' || USER || v_action || CURRENT_DATE;
RAISE INFO ' %', v_text;
RETURN NULL;
END;
$$ LANGUAGE 'plpgsql';
CREATE TRIGGER user_audit_trig
    AFTER INSERT OR UPDATE OR DELETE ON emp
    FOR EACH STATEMENT EXECUTE PROCEDURE user_audit_trig();
-- Before row-level trigger that displays employee number and
-- salary of an employee that is about to be added, updated,
-- or deleted in the 'emp' table.
CREATE OR REPLACE FUNCTION emp_sal_trig() RETURNS TRIGGER
AS $$
DECLARE
    sal_diff NUMERIC(7,2);
BEGIN
    IF TG_OP = 'INSERT' THEN
      RAISE INFO 'Inserting employee %', NEW.empno;
      RAISE INFO '...New salary: %', NEW.sal;
      RETURN NEW;
    END IF;
    IF TG_OP = 'UPDATE' THEN
      sal_diff := NEW.sal - OLD.sal;
      RAISE INFO 'Updating employee %', OLD.empno;
      RAISE INFO '..Old salary: %', OLD.sal;
      RAISE INFO '...New salary: %', NEW.sal;
      RAISE INFO '...Raise : %', sal_diff;
      RETURN NEW;
    END IF;
    IF TG_OP = 'DELETE' THEN
      RAISE INFO 'Deleting employee %', OLD.empno;
      RAISE INFO '...Old salary: %', OLD.sal;
      RETURN OLD;
    END IF;
END;
$$ LANGUAGE 'plpgsql';
CREATE TRIGGER emp_sal_tria
    BEFORE DELETE OR INSERT OR UPDATE ON emp
```



10.2 Enhanced Compatibility Features

Advanced Server includes extended functionality that provides compatibility for syntax supported by Oracle applications. Detailed information about the compatibility features supported by Advanced Server is provided in the Database Compatibility for Oracle Developers Guides; the version-specific guides are available at:

https://www.enterprisedb.com/edb-docs

The following sections highlight some of the compatibility features supported by Advanced Server.

Enabling Compatibility Features

There are several ways to install Advanced Server that will allow you to take advantage of compatibility features:

- Use the INITDBOPTS variable (in the Advanced Server service configuration file) to specify --redwood-like before initializing your cluster.
- When invoking initdb to initialize your cluster, include the --redwood-like option.

For more information about the installation options supported by the Advanced Server installers, please see the EDB Postgres Advanced Server Installation Guide, available from the EDB website at:

https://www.enterprisedb.com/edb-docs

Stored Procedural Language

Advanced Server supports a highly productive procedural language that allows you to write custom procedures, functions, triggers and packages. The procedural language:

- · complements the SQL language and built-in packages.
- provides a seamless development and testing environment.
- · allows you to create reusable code.

For information about using the Stored Procedural Language, see the *Database Compatibility for Oracle Developers Guide*, available at:

https://www.enterprisedb.com/edb-docs

Optimizer Hints

When you invoke a DELETE, INSERT, SELECT, or UPDATE command, the server generates a set of execution plans; after analyzing those execution plans, the server selects a plan that will (generally) return the result set in the least amount of time. The server's choice of plan is dependent upon several factors:

- The estimated execution cost of data handling operations.
- Parameter values assigned to parameters in the Query Tuning section of the postgresql.conf file.
- Column statistics that have been gathered by the ANALYZE command.

As a rule, the query planner will select the least expensive plan. You can use an optimizer hint to influence the server as it selects a query plan.

An optimizer hint is a directive (or multiple directives) embedded in a comment-like syntax that immediately follows a <code>DELETE</code> , <code>INSERT</code> , <code>SELECT</code> or <code>UPDATE</code> command. Keywords in the comment instruct the server to employ or avoid a specific plan when producing the result set. For information about using optimizer hints, see the <code>Database Compatibility for Oracle Developers Guide</code>, available at:

https://www.enterprisedb.com/edb-docs

Data Dictionary Views

Advanced Server includes a set of views that provide information about database objects in a manner compatible with the Oracle data dictionary views. For detailed information about the views available with Advanced Server, please see the *Database Compatibility for Oracle Developers Reference Guide*, available at:

https://www.enterprisedb.com/edb-docs

dblink_ora

dblink_ora provides an OCI-based database link that allows you to SELECT, INSERT, UPDATE or DELETE data stored on an Oracle system from within Advanced Server. For detailed information about using dblink_ora, and the supported functions and procedures, see the *Database Compatibility for Oracle Developers Guide*, available at:

https://www.enterprisedb.com/edb-docs

Profile Management

Advanced Server supports compatible SQL syntax for profile management. Profile management commands allow a database superuser to create and manage named *profiles*. Each profile defines rules for password management that augment password and md5 authentication. The rules in a profile can:

- · count failed login attempts
- · lock an account due to excessive failed login attempts
- mark a password for expiration
- define a grace period after a password expiration
- · define rules for password complexity
- · define rules that limit password re-use

A profile is a named set of attributes that allow you to easily manage a group of roles that share comparable authentication requirements. If password requirements change, you can modify the profile to have the new requirements applied to each user that is associated with that profile.

After creating the profile, you can associate the profile with one or more users. When a user connects to the server, the server enforces the profile that is associated with their login role. Profiles are shared by all databases within a cluster, but each cluster may have multiple profiles. A single user with access to multiple databases will use the same profile when connecting to each database within the cluster.

For information about using profile management commands, see the *Database Compatibility for Oracle Developers Guide*, available at:

https://www.enterprisedb.com/edb-docs

Built-In Packages

DBMS REDACT

DBMS_RLS

Advanced Server supports a number of built-in packages that provide compatibility with Oracle procedures and functions.

The DBMS_REDACT package enables the redacting or masking of data that is returned by a quei

The DBMS_RLS package enables the implementation of Virtual Private Database on certain Adva

Package Name	Description
DBMS_SCHEDULER	The DBMS_SCHEDULER package provides a way to create and manage jobs, programs and job
DBMS_SESSION	Advanced Server provides support for the DBMS_SESSION.SET_ROLE procedure.
DBMS_SQL	The DBMS_SQL package provides an application interface to the EnterpriseDB dynamic SQL fund
DBMS_UTILITY	The DBMS_UTILITY package provides various utility programs.
UTL_ENCODE	The UTL_ENCODE package provides a way to encode and decode data.
UTL_FILE	The UTL_FILE package provides the capability to read from, and write to files on the operating sys
UTL_HTTP	The UTL_HTTP package provides a way to use the HTTP or HTTPS protocol to retrieve information
UTL_MAIL	The UTL_MAIL package provides the capability to manage e-mail.
UTL_RAW	The UTL_RAW package allows you to manipulate or retrieve the length of raw data types.
UTL_SMTP	The UTL_SMTP package provides the capability to send e-mails over the Simple Mail Transfer Pro
UTL_URL	The UTL_URL package provides a way to escape illegal and reserved characters within an URL.

For detailed information about the procedures and functions available within each package, please see the *Database Compatibility for Oracle Developers Built-In Package Guide*, available at:

https://www.enterprisedb.com/edb-docs

Open Client Library

The Open Client Library provides application interoperability with the Oracle Call Interface – an application that was formerly "locked in" can now work with either an Advanced Server or an Oracle database with minimal to no changes to the application code. The EnterpriseDB implementation of the Open Client Library is written in C.

The following diagram compares the Open Client Library and Oracle Call Interface application stacks.

The Open Client Library

For detailed information about the functions supported by the Open Client Library, see the EDB Postgres Advanced Server OCL Connector Guide, available at:

https://www.enterprisedb.com/edb-docs

Utilities

For detailed information about the compatible syntax supported by the utilities listed below, visit:

https://www.enterprisedb.com/edb-docs

EDB*Plus

EDBPlus is a utility program that provides a command line user interface to the Advanced Server that will be familiar to Oracle developers and users. EDBPlus accepts SQL commands, SPL anonymous blocks, and EDB*Plus commands.

EDB*Plus allows you to:

- Query certain database objects
- Execute stored procedures
- · Format output from SQL commands
- · Execute batch scripts
- Execute OS commands
- Record output

For detailed information about EDBPlus, please see the EDBPlus User's Guide available at:

https://www.enterprisedb.com/edb-docs/p/edbplus

EDB*Loader

EDBLoader is a high-performance bulk data loader that provides an interface compatible with Oracle databases for Advanced Server. The EDBLoader command line utility loads data from an input source, typically a file, into one or more tables using a subset of the parameters offered by Oracle SQL*Loader.

EDB*Loader features include:

- Support for the Oracle SQL*Loader data loading methods conventional path load, direct path load, and parallel direct path load
- Oracle SQL*Loader compatible syntax for control file directives
- · Input data with delimiter-separated or fixed-width fields
- · Bad file for collecting rejected records
- · Loading of multiple target tables
- Discard file for collecting records that do not meet the selection criteria of any target table
- · Data loading from standard input and remote loading

EDB*Wrap

The EDB*Wrap utility protects proprietary source code and programs (functions, stored procedures, triggers, and packages) from unauthorized scrutiny. The EDBWrap program translates a file that contains SPL or PL/pgSQL source code (the plaintext) into a file that contains the same code in a form that is nearly impossible to read. Once you have the obfuscated form of the code, you can send that code to Advanced Server and it will store those programs in obfuscated form. While EDB*Wrap does obscure code, table definitions are still exposed.*

Everything you wrap is stored in obfuscated form. If you wrap an entire package, the package body source, as well as the prototypes contained in the package header and the functions and procedures contained in the package body are stored in obfuscated form.

Dynamic Runtime Instrumentation Tools Architecture (DRITA)

The Dynamic Runtime Instrumentation Tools Architecture (DRITA) allows a DBA to query catalog views to determine the *wait events* that affect the performance of individual sessions or the system as a whole. DRITA records the number of times each event occurs as well as the time spent waiting; you can use this information to diagnose performance problems. DRITA offers this functionality, while consuming minimal system resources.

DRITA compares *snapshots* to evaluate the performance of a system. A snapshot is a saved set of system performance data at a given point in time. Each snapshot is identified by a unique ID number; you can use snapshot ID numbers with DRITA reporting functions to return system performance statistics.

ECPGPlus

EnterpriseDB has enhanced ECPG (the PostgreSQL pre-compiler) to create ECPGPlus. ECPGPlus allows you to include embedded SQL commands in C applications; when you use ECPGPlus to compile an application that contains embedded SQL commands, the SQL code is syntax-checked and translated into C.

ECPGPlus supports Pro*C syntax in C programs when connected to an Advanced Server database. ECPGPlus supports:

- Oracle Dynamic SQL Method 4 (ODS-M4)
- Pro*C compatible anonymous blocks
- A CALL statement compatible with Oracle databases

For information about using ECPGPlus, please see the *EDB Postgres Advanced Server ECPG Connector Guide*, available from the EnterpriseDB website at:

https://www.enterprisedb.com/edb-docs

Table Partitioning

In a partitioned table, one logically large table is broken into smaller physical pieces. Partitioning can provide several benefits:

- Query performance can be improved dramatically in certain situations, particularly when most of the heavily accessed rows of the table are in a single partition or a small number of partitions. Partitioning allows you to omit the partition column from the front of an index, reducing index size and making it more likely that the heavily used parts of the index fits in memory.
- When a query or update accesses a large percentage of a single partition, performance may improve because the server will perform a sequential scan of the partition instead of using an index and random access reads scattered across the whole table.
- A bulk load (or unload) can be implemented by adding or removing partitions, if you plan that requirement
 into the partitioning design. ALTER TABLE is far faster than a bulk operation. It also entirely avoids the
 VACUUM overhead caused by a bulk DELETE.
- Seldom-used data can be migrated to less-expensive (or slower) storage media.

Table partitioning is worthwhile only when a table would otherwise be very large. The exact point at which a table will benefit from partitioning depends on the application; a good rule of thumb is that the size of the table should exceed the physical memory of the database server.

For information about database compatibility features supported by Advanced Server see the *Database Compatibility for Oracle Developer's Guide*, available at:

https://www.enterprisedb.com/edb-docs

10.3.0 Configuration Parameters

Configuration Parameters

This section describes the database server configuration parameters of Advanced Server. These parameters control various aspects of the database server's behavior and environment such as data file and log file locations, connection, authentication, and security settings, resource allocation and consumption, archiving and replication settings, error logging and statistics gathering, optimization and performance tuning, locale and formatting settings, and so on.

Configuration parameters that apply only to Advanced Server are noted in the [Summary of Configuration Parameters](03_configuration_parameters/02_summary_of_configuration_parameters#summary_of_configuration_parameters section.

Additional information about configuration parameters can be found in the PostgreSQL Core Documentation available at:

https://www.postgresql.org/docs/12/static/runtime-config.html

10.3.1 Setting Configuration Parameters

Setting Configuration Parameters

This section provides an overview of how configuration parameters are specified and set.

Each configuration parameter is set using a name/value pair. Parameter names are case-insensitive. The parameter name is typically separated from its value by an optional equals sign (=).

The following is an example of some configuration parameter settings in the postgresql.conf file:

```
title: "This is a comment"
10.3.1 This is a comment
---
<div id="setting_new_parameters" class="registered_link"></div>
log_connections = yes
log_destination = 'syslog'
search_path = '"$user", public'
shared_buffers = 128MB
```

Parameter values are specified as one of five types:

- **Boolean.** Acceptable values can be written as on, off, true, false, yes, no, 1, 0, or any unambiguous prefix of these.
- · Integer. Number without a fractional part.
- Floating Point. Number with an optional fractional part separated by a decimal point.
- **String.** Text value. Enclose in single quotes if the value is not a simple identifier or number (that is, the value contains special characters such as spaces or other punctuation marks).
- Enum. Specific set of string values. The allowed values can be found in the system view pg_settings.enumvals. Enum values are case-insensitive.

Some settings specify a memory or time value. Each of these has an implicit unit, which is kilobytes, blocks (typically 8 kilobytes), milliseconds, seconds, or minutes. Default units can be found by referencing the system view pg_settings.unit. A different unit can be specified explicitly.

Valid memory units are kB (kilobytes), MB (megabytes), and GB (gigabytes). Valid time units are ms (milliseconds), s (seconds), min (minutes), h (hours), and d (days). The multiplier for memory units is 1024.

The configuration parameter settings can be established in a number of different ways:

- There is a number of parameter settings that are established when the Advanced Server database product is built. These are read-only parameters, and their values cannot be changed. There are also a couple of parameters that are permanently set for each database when the database is created. These parameters are read-only as well and cannot be subsequently changed for the database.
- The initial settings for almost all configurable parameters across the entire database cluster are listed in the configuration file, <code>postgresql.conf</code> . These settings are put into effect upon database server start or restart. Some of these initial parameter settings can be overridden as discussed in the following bullet points. All configuration parameters have built-in default settings that are in effect if not explicitly overridden.
- Configuration parameters in the postgresql.conf file are overridden when the same parameters are included in the postgresql.auto.conf file. The ALTER SYSTEM command is used to manage the configuration parameters in the postgresql.auto.conf file.
- Parameter settings can be modified in the configuration file while the database server is running. If the
 configuration file is then reloaded (meaning a SIGHUP signal is issued), for certain parameter types,
 the changed parameters settings immediately take effect. For some of these parameter types, the new
 settings are available in a currently running session immediately after the reload. For other of these parameter types, a new session must be started to use the new settings. And yet for other parameter types,
 modified settings do not take effect until the database server is stopped and restarted. See the following
 section of the PostgreSQL Core Documentation for information on how to reload the configuration file:

https://www.postgresql.org/docs/current/config-setting.html

- The SQL commands ALTER DATABASE, ALTER ROLE, or ALTER ROLE IN DATABASE can be used to modify certain parameter settings. The modified parameter settings take effect for new sessions after the command is executed. ALTER DATABASE affects new sessions connecting to the specified database. ALTER ROLE affects new sessions started by the specified role. ALTER ROLE IN DATABASE affects new sessions started by the specified role connecting to the specified database. Parameter settings established by these SQL commands remain in effect indefinitely, across database server restarts, overriding settings established by the methods discussed in the second and third bullet points. Parameter settings established using the ALTER DATABASE, ALTER ROLE, or ALTER ROLE IN DATABASE commands can only be changed by: a) re-issuing these commands with a different parameter value, or
 - b) issuing these commands using either of the [SET](#parameter> TO DEFAULT clause or the RESET <parameter) clause. These clauses change the parameter back to using the setting established by the methods set forth in the prior bullet points. See the "SQL Commands" section of Chapter VI "Reference" in the *PostgreSQL Core Documentation* for the exact syntax of these SQL commands:

https://www.postgresql.org/docs/current/sql-commands.html

 Changes can be made for certain parameter settings for the duration of individual sessions using the PGOPTIONS environment variable or by using the SET command within the EDB-PSQL or PSQL command line terminal programs. Parameter settings made in this manner override settings established using any of the methods described by the second, third, and fourth bullet points, but only for the duration of the session.

10.3.2 Summary of Configuration Parameters

Summary of Configuration Parameters

This section contains a summary table listing all Advanced Server configuration parameters along with a number of key attributes of the parameters.

These attributes are described by the following columns of the summary table:

- Parameter. Configuration parameter name.
- Scope of Effect. Scope of effect of the configuration parameter setting.
 - Cluster Setting affects the entire database cluster (that is, all databases managed by the database server instance).
 - Database Setting can vary by database and is established when the database is created. Applies
 to a small number of parameters related to locale settings.
 - Session Setting can vary down to the granularity of individual sessions.

In other words, different settings can be made for the following entities whereby the latter settings in this list override prior ones: a) the entire database cluster, b) specific databases in the database cluster, c) specific roles, d) specific roles when connected to specific databases, e) a specific session.

- · When Takes Effect. When a changed parameter setting takes effect.
 - Preset Established when the Advanced Server product is built or a particular database is created. This is a read-only parameter and cannot be changed.
 - Restart Database server must be restarted.
 - Reload Configuration file must be reloaded (or the database server can be restarted).
 - Immediate Immediately effective in a session if the PGOPTIONS environment variable or the SET command is used to change the setting in the current session. Effective in new sessions if ALTER DATABASE, ALTER ROLE, or ALTER ROLE IN DATABASE commands are used to change the setting.
- Authorized User. Type of operating system account or database role that must be used to put the parameter setting into effect.
 - EPAS service account EDB Postgres Advanced Server service account (enterprised for an installation compatible with Oracle databases, postgres for a PostgreSQL compatible mode installation).
 - Superuser Database role with superuser privileges.
 - User Any database role with permissions on the affected database object (the database or role to be altered with the ALTER command).
 - n/a Parameter setting cannot be changed by any user.
- **Description.** Brief description of the configuration parameter.
- **EPAS Only.** 'X' Configuration parameter is applicable to EDB Postgres Advanced Server only. No entry in this column indicates the configuration parameter applies to PostgreSQL as well.

Note

There are a number of parameters that should never be altered. These are designated as "**Note: For internal use only**" in the Description column.

Table 3-1 - Summary of Configuration Parameters	

10.3.3.0 Configuration Parameters by Functionality

Configuration Parameters by Functionality

This section provides more detail for certain groups of configuration parameters.

The section heading for each parameter is followed by a list of attributes:

• Parameter Type. Type of values the parameter can accept. See [Setting Configuration Parameters](../03_configuration_parameters/01_setting_new_parameters#setting_configuration_parameters) section for a discussion of parameter type values.

- Default Value. Default setting if a value is not explicitly set in the configuration file.
- Range. Permitted range of values.
- Minimum Scope of Effect. Smallest scope for which a distinct setting can be made. Generally, the minimal scope of a distinct setting is either the entire cluster (the setting is the same for all databases and sessions thereof, in the cluster), or per session (the setting may vary by role, database, or individual session). (This attribute has the same meaning as the Scope of Effect column in the table of [Summary of Configuration Parameters] (#summary_of_configuration_parameters) section).
- When Value Changes Take Effect. Least invasive action required to activate a change to a parameter's value. All parameter setting changes made in the configuration file can be put into effect with a restart of the database server; however certain parameters require a database server restart. Some parameter setting changes can be put into effect with a reload of the configuration file without stopping the database server. Finally, other parameter setting changes can be put into effect with some client side action whose result is immediate. (This attribute has the same meaning as the When Takes Effect column in the table of [Summary of Configuration Parameters] (#summary_of_configuration_parameters) section).
- Required Authorization to Activate. The type of user authorization to activate a change to a parameter's setting. If a database server restart or a configuration file reload is required, then the user must be a EPAS service account (enterprised or postgres depending upon the Advanced Server compatibility installation mode). (This attribute has the same meaning as the Authorized User column in the table of [Summary of Configuration Parameters] (#summary_of_configuration_parameters) section).

10.3.3.1.0 Top Performance Related Parameters

Top Performance Related Parameters

This section discusses the configuration parameters that have the most immediate impact on performance.

10.3.3.1.1 shared_buffers

shared buffers

Parameter Type: Integer Default Value: 32MB

Range: 128kB to system dependent

Minimum Scope of Effect: Cluster

When Value Changes Take Effect: Restart

Required Authorization to Activate: EPAS service account

Sets the amount of memory the database server uses for shared memory buffers. The default is typically 32 megabytes (32MB), but might be less if your kernel settings will not support it (as determined during initdb). This setting must be at least 128 kilobytes. (Non-default values of BLCKSZ change the minimum.) However, settings significantly higher than the minimum are usually needed for good performance.

If you have a dedicated database server with 1GB or more of RAM, a reasonable starting value for shared_buffers is 25% of the memory in your system. There are some workloads where even large settings for shared_buffers are effective, but because Advanced Server also relies on the operating system cache, it is unlikely that an allocation of more than 40% of RAM to shared_buffers will work better than a smaller amount.

On systems with less than 1GB of RAM, a smaller percentage of RAM is appropriate, so as to leave adequate space for the operating system (15% of memory is more typical in these situations). Also, on Windows, large

values for shared_buffers aren't as effective. You may find better results keeping the setting relatively low and using the operating system cache more instead. The useful range for shared_buffers on Windows systems is generally from 64MB to 512MB.

Increasing this parameter might cause Advanced Server to request more System V shared memory than your operating system's default configuration allows. See the section Shared Memory and Semaphores in the *PostgreSQL Core Documentation* for information on how to adjust those parameters, if necessary.

10.3.3.1.2 work mem

work mem

Parameter Type: Integer Default Value: 1MB

Range: 64kB to 2097151kB

Minimum Scope of Effect: Per session

When Value Changes Take Effect: Immediate

Required Authorization to Activate: Session user

Specifies the amount of memory to be used by internal sort operations and hash tables before writing to temporary disk files. The value defaults to one megabyte (1MB). Note that for a complex query, several sort work_mem; it is necessary to keep this fact in mind when choosing the value. Sort operations ORDERBY, DISTINCT, and merge joins. Hash tables are used in hash joins, hash-based aggregations are typically between 4MB and 64MB, depending on the size of max_connections"), and the complexity of your queries.

10.3.3.1.3 maintenance_work_mem

maintenance_work_mem
Parameter Type: Integer
Default Value: 16MB

Range: 1024kB to 2097151kB

Minimum Scope of Effect: Per session

When Value Changes Take Effect: Immediate

Required Authorization to Activate: Session user

Specifies the maximum amount of memory to be used by maintenance operations, such as VACUUM, CREATE INDEX, and ALTER TABLE ADD FOREIGN KEY. It defaults to 16 megabytes (16MB). Since only one of these operations can be executed at a time by a database session, and an installation normally doesn't have many of them running concurrently, it's safe to set this value significantly larger than work_mem. Larger settings might improve performance for vacuuming and for restoring database dumps.

Note that when autovacuum runs, up to autovacuum_max_workers times this memory may be allocated, so be careful not to set the default value too high.

A good rule of thumb is to set this to about 5% of system memory, but not more than about 512MB. Larger values won't necessarily improve performance.

10.3.3.1.4 wal buffers

wal buffers

Parameter Type: Integer
Default Value: 64kB

Range: 32kB to system dependent

Minimum Scope of Effect: Cluster

When Value Changes Take Effect: Restart

Required Authorization to Activate: EPAS service account

The amount of memory used in shared memory for WAL data. The default is 64 kilobytes (64kB). The setting need only be large enough to hold the amount of WAL data generated by one typical transaction, since the data is written out to disk at every transaction commit.

Increasing this parameter might cause Advanced Server to request more System V shared memory than your operating system's default configuration allows. See the section "Shared Memory and Semaphores" in the *PostgreSQL Core Documentation* for information on how to adjust those parameters, if necessary.

Although even this very small setting does not always cause a problem, there are situations where it can result in extra fsync calls, and degrade overall system throughput. Increasing this value to 1MB or so can alleviate this problem. On very busy systems, an even higher value may be needed, up to a maximum of about 16MB. Like shared_buffers, this parameter increases Advanced Server's initial shared memory allocation, so if increasing it causes an Advanced Server start failure, you will need to increase the operating system limit.

10.3.3.1.5 checkpoint_segments

checkpoint_segments

Now deprecated; this parameter is not supported by server versions 9.5 or later.

10.3.3.1.6 checkpoint_completion_target

checkpoint_completion_target

Parameter Type: Floating point

Default Value: 0.5 Range: 0 to 1

Minimum Scope of Effect: Cluster

When Value Changes Take Effect: Reload

Required Authorization to Activate: EPAS service account

Specifies the target of checkpoint completion as a fraction of total time between checkpoints. This spreads out the checkpoint writes while the system starts working towards the next checkpoint.

The default of 0.5 means aim to finish the checkpoint writes when 50% of the next checkpoint is ready. A value of 0.9 means aim to finish the checkpoint writes when 90% of the next checkpoint is done, thus throttling the checkpoint writes over a larger amount of time and avoiding spikes of performance bottlenecking.

10.3.3.1.7 checkpoint_timeout

checkpoint_timeout

Parameter Type: Integer

Default Value: 5min **Range:** 30s to 3600s

Minimum Scope of Effect: Cluster

When Value Changes Take Effect: Reload

Required Authorization to Activate: EPAS service account

Maximum time between automatic WAL checkpoints, in seconds. The default is five minutes (5min). Increasing this parameter can increase the amount of time needed for crash recovery.

Increasing checkpoint_timeout to a larger value, such as 15 minutes, can reduce the I/O load on your system, especially when using large values for shared_buffers.

The downside of making the aforementioned adjustments to the checkpoint parameters is that your system will use a modest amount of additional disk space, and will take longer to recover in the event of a crash. However, for most users, this is a small price to pay for a significant performance improvement.

10.3.3.1.8 max_wal_size

max_wal_size

Parameter Type: Integer Default Value: 1 GB

Range: 2 to 2147483647

Minimum Scope of Effect: Cluster

When Value Changes Take Effect: Reload

Required Authorization to Activate: EPAS service account

max_wal_size specifies the maximum size that the WAL will reach between automatic WAL checkpoints. This is a soft limit; WAL size can exceed max_wal_size under special circumstances (when under a heavy load, a failing archive_command, or a high wal_keep_segments setting).

Increasing this parameter can increase the amount of time needed for crash recovery. This parameter can only be set in the <code>postgresql.conf</code> file or on the server command line.

10.3.3.1.9 min wal size

min_wal_size

Parameter Type: Integer
Default Value: 80 MB
Range: 2 to 2147483647

Minimum Scope of Effect: Cluster

When Value Changes Take Effect: Reload

Required Authorization to Activate: EPAS service account

If WAL disk usage stays below the value specified by min_wal_size, old WAL files are recycled for future use at a checkpoint, rather than removed. This ensures that enough WAL space is reserved to handle spikes in WAL usage (like when running large batch jobs). This parameter can only be set in the postgresql.conf file or on the server command line.

10.3.3.1.10 bgwriter_delay

bgwriter_delay

Parameter Type: Integer
Default Value: 200ms
Range: 10ms to 10000ms

Minimum Scope of Effect: Cluster

When Value Changes Take Effect: Reload

Required Authorization to Activate: EPAS service account

Specifies the delay between activity rounds for the background writer. In each round the writer issues writes for some number of dirty buffers (controllable by the bgwriter_lru_maxpages and bgwriter_lru_multiplier parameters). It then sleeps for bgwriter_delay milliseconds, and repeats.

The default value is 200 milliseconds (200ms). Note that on many systems, the effective resolution of sleep delays is 10 milliseconds; setting bgwriter_delay to a value that is not a multiple of 10 might have the same results as setting it to the next higher multiple of 10.

Typically, when tuning bgwriter_delay, it should be reduced from its default value. This parameter is rarely increased, except perhaps to save on power consumption on a system with very low utilization.

10.3.3.1.11 seq_page_cost

seq_page_cost

Parameter Type: Floating point

Default Value: 1

Range: 0 to 1.79769e+308

Minimum Scope of Effect: Per session

When Value Changes Take Effect: Immediate

Required Authorization to Activate: Session user

Sets the planner's estimate of the cost of a disk page fetch that is part of a series of sequential fetches. The default is 1.0. This value can be overridden for a particular tablespace by setting the tablespace parameter of the same name. (Refer to the ALTER TABLESPACE command in the *PostgreSQL Core Documentation*.)

The default value assumes very little caching, so it's frequently a good idea to reduce it. Even if your database is significantly larger than physical memory, you might want to try setting this parameter to less than 1 (rather than its default value of 1) to see whether you get better query plans that way. If your database fits entirely within memory, you can lower this value much more, perhaps to 0.1.

10.3.3.1.12 random_page_cost

random_page_cost

Parameter Type: Floating point

Default Value: 4

Range: 0 to 1.79769e+308

Minimum Scope of Effect: Per session

When Value Changes Take Effect: Immediate

Required Authorization to Activate: Session user

Sets the planner's estimate of the cost of a non-sequentially-fetched disk page. The default is 4.0. This value can be overridden for a particular tablespace by setting the tablespace parameter of the same name. (Refer to the ALTER TABLESPACE command in the *PostgreSQL Core Documentation*.)

Reducing this value relative to seq_page_cost will cause the system to prefer index scans; raising it will make index scans look relatively more expensive. You can raise or lower both values together to change the importance of disk I/O costs relative to CPU costs, which are described by the cpu_tuple_cost and cpu_index_tuple_cost parameters.

The default value assumes very little caching, so it's frequently a good idea to reduce it. Even if your database is significantly larger than physical memory, you might want to try setting this parameter to 2 (rather than its default of 4) to see whether you get better query plans that way. If your database fits entirely within memory, you can lower this value much more, perhaps to 0.1.

Although the system will let you do so, never set random_page_cost less than seq_page_cost. However, setting them equal (or very close to equal) makes sense if the database fits mostly or entirely within memory, since in that case there is no penalty for touching pages out of sequence. Also, in a heavily-cached database you should lower both values relative to the CPU parameters, since the cost of fetching a page already in RAM is much smaller than it would normally be.

10.3.3.1.13 effective cache size

effective_cache_size

Parameter Type: Integer
Default Value: 128MB

Range: 8kB to 17179869176kB

Minimum Scope of Effect: Per session

When Value Changes Take Effect: Immediate

Required Authorization to Activate: Session user

Sets the planner's assumption about the effective size of the disk cache that is available to a single query. This is factored into estimates of the cost of using an index; a higher value makes it more likely index scans will be used, a lower value makes it more likely sequential scans will be used. When setting this parameter you should consider both Advanced Server's shared buffers and the portion of the kernel's disk cache that will be used for Advanced Server data files. Also, take into account the expected number of concurrent queries on different tables, since they will have to share the available space. This parameter has no effect on the size of shared memory allocated by Advanced Server, nor does it reserve kernel disk cache; it is used only for estimation purposes. The default is 128 megabytes (128MB).

If this parameter is set too low, the planner may decide not to use an index even when it would be beneficial to do so. Setting effective_cache_size to 50% of physical memory is a normal, conservative setting. A more aggressive setting would be approximately 75% of physical memory.

10.3.3.1.14 synchronous_commit

synchronous_commit

Parameter Type: Boolean

Default Value: true
Range: {true | false}

Minimum Scope of Effect: Per session

When Value Changes Take Effect: Immediate

Required Authorization to Activate: Session user

Specifies whether transaction commit will wait for WAL records to be written to disk before the command returns a success indication to the client. The default, and safe, setting is on. When off, there can be a delay between when success is reported to the client and when the transaction is really guaranteed to be safe against a server crash. (The maximum delay is three times wal_writer_delay .)

Unlike fsync, setting this parameter to off does not create any risk of database inconsistency: an operating system or database crash might result in some recent allegedly-committed transactions being lost, but the database state will be just the same as if those transactions had been aborted cleanly.

So, turning synchronous_commit off can be a useful alternative when performance is more important than exact certainty about the durability of a transaction. See the section Asynchronous Commit in the PostgreSQL Core Documentation for information.

This parameter can be changed at any time; the behavior for any one transaction is determined by the setting in effect when it commits. It is therefore possible, and useful, to have some transactions commit synchronously and others asynchronously. For example, to make a single multistatement transaction commit asynchronously when the default is the opposite, issue SET LOCAL synchronous_commit TO OFF within the transaction.

10.3.3.1.15 edb_max_spins_per_delay

edb_max_spins_per_delay
Parameter Type: Integer
Default Value: 1000

Range: 10 to 1000

Minimum Scope of Effect: Per cluster
When Value Changes Take Effect: Restart

Required Authorization to Activate: EPAS service account

Use edb_max_spins_per_delay to specify the maximum number of times that a session will spin while waiting for a spin-lock. If a lock is not acquired, the session will sleep. If you do not specify an alternative value for edb_max_spins_per_delay, the server will enforce the default value of 1000.

This may be useful for systems that use NUMA (non-uniform memory access) architecture.

10.3.3.1.16 pg_prewarm.autoprewarm

pg_prewarm.autoprewarm

Parameter Type: Boolean

Default Value: true Range: {true | false}

Minimum Scope of Effect: Cluster

When Value Changes Take Effect: Restart

Required Authorization to Activate: EPAS service account

This parameter controls whether or not the database server should run autoprewarm, which is a background worker process that automatically dumps shared buffers to disk before a shutdown. It then prewarms the shared buffers the next time the server is started, meaning it loads blocks from the disk back into the buffer pool.

The advantage is that it shortens the warm up times after the server has been restarted by loading the data that has been dumped to disk before shutdown.

If pg_prewarm.autoprewarm is set to on, the autoprewarm worker is enabled. If the parameter is set to off, autoprewarm is disabled. The parameter is on by default.

Before autoprewarm can be used, you must add \$libdir/pg_prewarm to the libraries listed in the shared_preload_libraries configuration parameter of the postgresql.conf file as shown by the following example:

shared_preload_libraries =

'\$libdir/dbms_pipe,\$libdir/edb_gen,\$libdir/dbms_aq,\$libdir/pg_prewarm'

After modifying the shared_preload_libraries parameter, restart the database server after which the autoprewarm background worker is launched immediately after the server has reached a consistent state.

The autoprewarm process will start loading blocks that were previously recorded in \$PGDATA/autoprewarm blocks until there is no free buffer space left in the buffer pool. In this manner, any new blocks that were loaded either by the recovery process or by the querying clients, are not replaced.

Once the autoprewarm process has finished loading buffers from disk, it will periodically dump shared buffers to disk at the interval specified by the pg_prewarm.autoprewarm_interval parameter. See the pg_prewarm.autoprewarm_interval <pg_prewarm.autoprewarm_interval> section for information on the autoprewarm background worker. Upon the next server restart, the autoprewarm process will prewarm shared buffers with the blocks that were last dumped to disk.

10.3.3.1.17 pg_prewarm.autoprewarm_interval

pg_prewarm.autoprewarm_interval

Parameter Type: Integer Default Value: 300s Range: 0s to 2147483s

Minimum Scope of Effect: Cluster

When Value Changes Take Effect: Reload

Required Authorization to Activate: EPAS service account

This is the minimum number of seconds after which the autoprewarm background worker dumps shared buffers to disk. The default is 300 seconds. If set to 0, shared buffers are not dumped at regular intervals, but only when the server is shut down.

See the pg_prewarm.autoprewarm <pg_prewarm.autoprewarm> section for information on the autoprewarm background worker.

10.3.3.2 Resource Usage / Memory

Resource Usage: Memory

The configuration parameters in this section control resource usage pertaining to memory.

edb_dynatune

Parameter Type: Integer

Default Value: 0 Range: 0 to 100

Minimum Scope of Effect: Cluster

When Value Changes Take Effect: Restart

Required Authorization to Activate: EPAS service account

Determines how much of the host system's resources are to be used by the database server based upon the host machine's total available resources and the intended usage of the host machine.

When Advanced Server is initially installed, the edb_dynatune parameter is set in accordance with the selected usage of the host machine on which it was installed (i.e., development machine, mixed use machine, or dedicated server). For most purposes, there is no need for the database administrator to adjust the various configuration parameters in the postgresql.conf file in order to improve performance.

The edb_dynatune parameter can be set to any integer value between 0 and 100, inclusive. A value of 0, turns off the dynamic tuning feature thereby leaving the database server resource usage totally under the control of the other configuration parameters in the postgresql.conf file.

A low non-zero, value (e.g., 1 - 33) dedicates the least amount of the host machine's resources to the database server. This setting would be used for a development machine where many other applications are being used.

A value in the range of 34 - 66 dedicates a moderate amount of resources to the database server. This setting might be used for a dedicated application server that may have a fixed number of other applications running on the same machine as Advanced Server.

The highest values (e.g., 67 - 100) dedicate most of the server's resources to the database server. This setting would be used for a host machine that is totally dedicated to running Advanced Server.

Once a value of edb_dynatune is selected, database server performance can be further fine-tuned by adjusting the other configuration parameters in the postgresql.conf file. Any adjusted setting overrides the corresponding value chosen by edb_dynatune. You can change the value of a parameter by un-commenting the configuration parameter, specifying the desired value, and restarting the database server.

edb_dynatune_profile

Parameter Type: Enum

Default Value: oltp

Range: {oltp | reporting | mixed}

Minimum Scope of Effect: Cluster

When Value Changes Take Effect: Restart

Required Authorization to Activate: EPAS service account

This parameter is used to control tuning aspects based upon the expected workload profile on the database server.

The following are the possible values:

- oltp. Recommended when the database server is processing heavy online transaction processing workloads.
- reporting. Recommended for database servers used for heavy data reporting.
- mixed. Recommended for servers that provide a mix of transaction processing and data reporting.

10.3.3.3 Resource Usage / EDB Resource Manager

Resource Usage: EDB Resource Manager

The configuration parameters in this section control resource usage through EDB Resource Manager.

edb_max_resource_groups

Parameter Type: Integer

Default Value: 16 Range: 0 to 65536

Minimum Scope of Effect: Cluster

When Value Changes Take Effect: Restart

Required Authorization to Activate: EPAS service account

This parameter controls the maximum number of resource groups that can be used simultaneously by EDB Resource Manager. More resource groups can be created than the value specified by however, the number of resource groups in active use by processes in these groups cannot exceed this value.

Parameter edb_max_resource_groups should be set comfortably larger than the number of groups you expect to maintain so as not to run out.

edb_resource_group

Parameter Type: String

Default Value: none

Range: n/a

Minimum Scope of Effect: Per session

When Value Changes Take Effect: Immediate

Required Authorization to Activate: Session user

Set the edb_resource_group parameter to the name of the resource group to which the current session

is to be controlled by EDB Resource Manager according to the group's resource type settings.

If the parameter is not set, then the current session does not utilize EDB Resource Manager.

10.3.3.4 Query Tuning

Query Tuning

This section describes the configuration parameters used for optimizer hints.

enable_hints

Parameter Type: Boolean

Default Value: true
Range: {true | false}

Minimum Scope of Effect: Per session

When Value Changes Take Effect: Immediate

Required Authorization to Activate: Session user

Optimizer hints embedded in SQL commands are utilized when enable_hints is on. Optimizer hints are

ignored when this parameter is off.

10.3.3.5 Query Tuning / Planner Method Configuration

Query Tuning: Planner Method Configuration

This section describes the configuration parameters used for planner method configuration.

edb_enable_pruning

edb_enable_pruning

Parameter Type: Boolean

Default Value: true
Range: {true | false}

Minimum Scope of Effect: Per session

When Value Changes Take Effect: Immediate

Required Authorization to Activate: Session user

When set to TRUE, edb_enable_pruning allows the query planner to early-prune partitioned tables. Early-pruning means that the query planner can prune (i.e., ignore) partitions that would not be searched in a query before generating query plans. This helps improve performance time as it eliminates the generation of query plans of partitions that would not be searched.

Conversely, late-pruning means that the query planner prunes partitions after generating query plans for each partition. (The constraint_exclusion configuration parameter controls late-pruning.)

The ability to early-prune depends upon the nature of the query in the \mbox{WHERE} clause. Early-pruning can be utilized in only simple queries with constraints of the type \mbox{WHERE} *column* = *literal* (e.g., WHERE deptno = 10)

Early-pruning is not used for more complex queries such as WHERE *column* = *expression* (e.g., WHERE depthology)

10.3.3.6 Reporting and Logging / What to Log

Reporting and Logging

The configuration parameters in this section control reporting and logging.

trace_hints

Parameter Type: Boolean

Default Value: false **Range:** {true | false}

Minimum Scope of Effect: Per session

When Value Changes Take Effect: Immediate

Required Authorization to Activate: Session user

Use with the optimizer hints feature to provide more detailed information regarding whether or not a hint was used by the planner. Set the client_min_messages and trace_hints configuration parameters as follows:

SET client_min_messages TO info;
SET trace_hints TO true;

The SELECT command with the NO_INDEX hint shown below illustrates the additional information produced when the aforementioned configuration parameters are set.

EXPLAIN SELECT /*+ NO_INDEX(accounts accounts_pkey) */ * FROM accounts WHERE aid = 100;

INFO: [HINTS] Index Scan of [accounts].[accounts_pkey] rejected because
of NO_INDEX hint.

INFO: [HINTS] Bitmap Heap Scan of [accounts].[accounts_pkey] rejected because of NO_INDEX hint.

QUERY PLAN

Seq Scan on accounts (cost=0.00..14461.10 rows=1 width=97)

Filter: (aid = 100)

(2 rows)

edb_log_every_bulk_value

Parameter Type: Boolean

Default Value: false **Range:** {true | false}

Minimum Scope of Effect: Per session

When Value Changes Take Effect: Immediate

Required Authorization to Activate: Superuser

Bulk processing logs the resulting statements into both the Advanced Server log file and the EDB Audit log file. However, logging each and every statement in bulk processing is costly. This can be controlled by the edb_log_every_bulk_value configuration parameter. When set to true, each and every statement in bulk processing is logged. When set to false, a log message is recorded once per bulk processing. In addition, the duration is emitted once per bulk processing. Default is set to false.

10.3.3.7.0 Auditing Settings

Auditing Settings

This section describes configuration parameters used by the Advanced Server database auditing feature.

10.3.3.7.1 edb_audit

edb audit

Parameter Type: Enum

Default Value: none

Range: {none | csv | xml}

Minimum Scope of Effect: Cluster

When Value Changes Take Effect: Reload

Required Authorization to Activate: EPAS service account

Enables or disables database auditing. The values xml or csv will enable database auditing. These values represent the file format in which auditing information will be captured. none will disable database auditing and is also the default.

10.3.3.7.2 edb_audit_directory

edb audit directory

Parameter Type: String

Default Value: edb_audit

Range: n/a

Minimum Scope of Effect: Cluster

When Value Changes Take Effect: Reload

Required Authorization to Activate: EPAS service account

Specifies the directory where the audit log files will be created. The path of the directory can be absolute or

relative to the Advanced Server data directory.

10.3.3.7.3 edb audit filename

edb_audit_filename

Parameter Type: String

Default Value: audit-%Y%m%d %H%M%S

Range: n/a

Minimum Scope of Effect: Cluster

When Value Changes Take Effect: Reload

Required Authorization to Activate: EPAS service account

Specifies the file name of the audit file where the auditing information will be stored. The default file name will be $audit-%Y\%m\%d_\%H\%M\%S$. The escape sequences, %Y, %m etc., will be replaced by the appropriate

current values according to the system date and time.

10.3.3.7.4 edb_audit_rotation_day

edb_audit_rotation_day

Parameter Type: String

Default Value: every

Range: {none | every | sun | mon | tue | wed | thu | fri | sat} ...

Minimum Scope of Effect: Cluster

When Value Changes Take Effect: Reload

Required Authorization to Activate: EPAS service account

Specifies the day of the week on which to rotate the audit files. Valid values are sun, mon, tue, wed, thu, fri, sat, every, and none. To disable rotation, set the value to none. To rotate the file every day, set the edb_audit_rotation_day value to every. To rotate the file on a specific day of the week, set the value to the desired day of the week.

555

10.3.3.7.5 edb audit rotation size

edb_audit_rotation_size

Parameter Type: Integer

Default Value: 0MB

Range: 0MB to 5000MB

Minimum Scope of Effect: Cluster

When Value Changes Take Effect: Reload

Required Authorization to Activate: EPAS service account

Specifies a file size threshold in megabytes when file rotation will be forced to occur. The default value is 0MB.

If the parameter is commented out or set to 0, rotation of the file on a size basis will not occur.

10.3.3.7.6 edb_audit_rotation_seconds

edb_audit_rotation_seconds

Parameter Type: Integer

Default Value: 0s

Range: 0s to 2147483647s

Minimum Scope of Effect: Cluster

When Value Changes Take Effect: Reload

Required Authorization to Activate: EPAS service account

Specifies the rotation time in seconds when a new log file should be created. To disable this feature, set this

parameter to 0.

10.3.3.7.7 edb_audit_connect

Parameter Type: Enum

Default Value: failed

Range: {none | failed | all}

Minimum Scope of Effect: Cluster

When Value Changes Take Effect: Reload

Required Authorization to Activate: EPAS service account

Enables auditing of database connection attempts by users. To disable auditing of all connection attempts, set edb_audit_connect to none. To audit all failed connection attempts, set the value to failed. To audit

all connection attempts, set the value to all.

10.3.3.7.8 edb_audit_disconnect

edb_audit_disconnect

Parameter Type: Enum
Default Value: none
Range: {none | all}

Minimum Scope of Effect: Cluster

When Value Changes Take Effect: Reload

Required Authorization to Activate: EPAS service account

Enables auditing of database disconnections by connected users. To enable auditing of disconnections, set

the value to all. To disable, set the value to none.

10.3.3.7.9 edb audit statement

edb_audit_statement

Parameter Type: String
Default Value: ddl, error

Range: {none| ddl | dml | insert | update | delete | truncate | select | error | create | drop | alter | grant | revoke |

rollback | all} ...

Minimum Scope of Effect: Cluster

When Value Changes Take Effect: Reload

Required Authorization to Activate: EPAS service account

This configuration parameter is used to specify auditing of different categories of SQL statements as well as those statements related to specific SQL commands. To log errors, set the parameter value to error. To audit all DDL statements such as CREATE TABLE, ALTER TABLE, etc., set the parameter value to ddl. To audit specific types of DDL statements, the parameter values can include those specific SQL commands (create, drop, or alter). In addition, the object type may be specified following the command such as create table, create view, drop role, etc. All modification statements such as INSERT, UPDATE, DELETE or TRUNCATE can be audited by setting edb_audit_statement to dml. To audit specific types of DML statements, the parameter values can include the specific SQL commands, insert, update, delete, or truncate. Include parameter values select, grant, revoke, or rollback to audit statements regarding those SQL commands. Setting the value to all will audit every statement while none disables this feature.

10.3.3.7.10 edb audit tag

edb_audit_tag

Parameter Type: String

Default Value: none

Minimum Scope of Effect: Session

When Value Changes Take Effect: Immediate Required Authorization to Activate: User

Use edb_audit_tag to specify a string value that will be included in the audit log when the edb_audit

parameter is set to csv or xml.

10.3.3.7.11 edb_audit_destination

edb_audit_destination

Parameter Type: Enum

Default Value: file

Range: {file | syslog}

Minimum Scope of Effect: Cluster

When Value Changes Take Effect: Reload

Required Authorization to Activate: EPAS service account

Specifies whether the audit log information is to be recorded in the directory as given by the edb_audit_directory parameter or to the directory and file managed by the syslog process. Set to file to use the directory specified by edb_audit_directory (the default setting).

Set to syslog to use the syslog process and its location as configured in the /etc/syslog.conf file. The syslog setting is valid only for Advanced Server running on a Linux host, and is not supported on Windows systems.

Note: In recent Linux versions, syslog has been replaced by rsyslog and the configuration file is in /etc/rsyslog.conf .

10.3.3.7.12 edb_log_every_bulk_value

For information on edb_log_every_bulk_value , see the edb_log_every_bulk_value <edb_log_every_bulk_value .3.8 Client Connection Defaults / Locale and Formatting

Client Connection Defaults: Locale and Formatting

This section describes configuration parameters affecting locale and formatting.

icu_short_form

icu_short_form

Parameter Type: String
Default Value: none

Range: n/a

Minimum Scope of Effect: Database
When Value Changes Take Effect: n/a
Required Authorization to Activate: n/a

The configuration parameter <code>icu_short_form</code> is a parameter containing the default ICU short form name assigned to a database or to the Advanced Server instance. See Section 3.6 for general information about the ICU short form and the Unicode Collation Algorithm.

This configuration parameter is set either when the CREATE DATABASE command is used with the ICU_SHORT_FORM parameter in which case the specified short form name is set and appears in the configuration parameter when connected to this database, or when an Advanced Server instance is created with the initdb command used with the --icu_short_form option in which case the specified short form name is set and appears in the icu_short_form configuration parameter when connected to a database in that Advanced Server instance, and the database does not override it with its own ICU_SHORT_FORM parameter with a different short form.

Once established in the manner described, the icu_short_form configuration parameter cannot be changed.

10.3.3.9 Client Connection Defaults / Statement Behavior

Client Connection Defaults: Statement Behavior

This section describes configuration parameters affecting statement behavior.

default_heap_fillfactor

default_heap_fillfactor

Parameter Type: Integer

Default Value: 100 Range: 10 to 100

Minimum Scope of Effect: Per session

When Value Changes Take Effect: Immediate

Required Authorization to Activate: Session user

Sets the fillfactor for a table when the FILLFACTOR storage parameter is omitted from a CREATE TABLE command.

The fillfactor for a table is a percentage between 10 and 100. 100 (complete packing) is the default. When a smaller fillfactor is specified, INSERT operations pack table pages only to the indicated percentage; the remaining space on each page is reserved for updating rows on that page. This gives UPDATE a chance to place the updated copy of a row on the same page as the original, which is more efficient than placing it on a different page. For a table whose entries are never updated, complete packing is the best choice, but in heavily updated tables smaller fillfactors are appropriate.

edb_data_redaction

edb_data_redaction

Parameter Type: Boolean

Default Value: true Range: {true | false}

Minimum Scope of Effect: Per session

When Value Changes Take Effect: Immediate

Required Authorization to Activate: Session user

Data redaction is the support of policies to limit the exposure of certain sensitive data to certain users by altering the displayed information.

The default setting is TRUE so the data redaction is applied to all users except for superusers and the table owner:

- Superusers and table owner bypass data redaction.
- All other users get the redaction policy applied and see the reformatted data.

If the parameter is disabled by setting it to FALSE, then the following occurs:

- · Superusers and table owner still bypass data redaction.
- All other users will get an error.

For information on data redaction, see the section "Data Redaction".

10.3.3.10 Client Connection Defaults / Other Defaults

Client Connection Defaults: Other Defaults

The parameters in this section set other miscellaneous client connection defaults.

oracle home

oracle home

Parameter Type: String

Default Value: none

Range: n/a

Minimum Scope of Effect: Cluster

When Value Changes Take Effect: Restart

Required Authorization to Activate: EPAS service account

Before creating an Oracle Call Interface (OCI) database link to an Oracle server, you must direct Advanced Server to the correct Oracle home directory. Set the LD_LIBRARY_PATH environment variable on Linux (or PATH on Windows) to the lib directory of the Oracle client installation directory.

For Windows only, you can instead set the value of the oracle_home configuration parameter in the postgresql.conf file. The value specified in the oracle_home configuration parameter will override the Windows PATH environment variable.

The LD_LIBRARY_PATH environment variable on Linux (PATH environment variable or oracle_home configuration parameter on Windows) must be set properly each time you start Advanced Server.

For Windows only: To set the oracle_home configuration parameter in the postgresql.conf file, edit the file, adding the following line:

oracle_home = '<lib_directory>'

Substitute the name of the Windows directory that contains oci.dll for lib_directory.

After setting the oracle_home configuration parameter, you must restart the server for the changes to take effect. Restart the server from the Windows Services console.

odbc_lib_path

odbc_lib_path

Parameter Type: String

Default Value: none

Range: n/a

Minimum Scope of Effect: Cluster

When Value Changes Take Effect: Restart

Required Authorization to Activate: EPAS service account

If you will be using an ODBC driver manager, and if it is installed in a non-standard location, you specify the location by setting the odbc_lib_path configuration parameter in the postgresql.conf file:

odbc_lib_path = '<complete_path_to_libodbc.so>'

The configuration file must include the complete pathname to the driver manager shared library (typically libodbc.so).

10.3.3.11 Compatibility Options

Compatibility Options

The configuration parameters described in this section control various database compatibility features.

edb redwood date

edb redwood date

Parameter Type: Boolean

Default Value: false **Range:** {true | false}

Minimum Scope of Effect: Per session

When Value Changes Take Effect: Immediate

Required Authorization to Activate: Session user

When DATE appears as the data type of a column in the commands, it is translated to TIMESTAMP at the time the table definition is stored in the database if the configuration parameter edb_redwood_date is set to TRUE. Thus, a time component will also be stored in the column along with the date.

If edb_redwood_date is set to FALSE the column's data type in a CREATE TABLE or ALTER TABLE command remains as a native PostgreSQL DATE data type and is stored as such in the database. The PostgreSQL DATE data type stores only the date without a time component in the column.

Regardless of the setting of edb_redwood_date , when DATE appears as a data type in any other context such as the data type of a variable in an SPL declaration section, or the data type of a formal parameter in an SPL procedure or SPL function, or the return type of an SPL function, it is always internally translated to a TIMESTAMP and thus, can handle a time component if present.

edb redwood greatest least

edb_redwood_greatest_least

Parameter Type: Boolean

Default Value: true Range: {true | false}

Minimum Scope of Effect: Per session

When Value Changes Take Effect: Immediate

Required Authorization to Activate: Session user

The GREATEST function returns the parameter with the greatest value from its list of parameters. The LEAST function returns the parameter with the least value from its list of parameters.

When edb_redwood_greatest_least is set to TRUE, the GREATEST and LEAST functions return null when at least one of the parameters is null.

```
SET edb_redwood_greatest_least TO on;
```

```
SELECT GREATEST(1, 2, NULL, 3);
```

greatest

(1 row)

When edb_redwood_greatest_least is set to FALSE, null parameters are ignored except when all parameters are null in which case null is returned by the functions.

```
SET edb_redwood_greatest_least TO off;
```

```
SELECT GREATEST(1, 2, NULL, 3);
```

```
greatest
_____
3
(1 row)
SELECT GREATEST(NULL, NULL, NULL);
greatest
_____
(1 row)
edb_redwood_raw_names
**Parameter Type:** Boolean
**Default Value:** false
**Range:** {true | false}
**Minimum Scope of Effect:** Per session
**When Value Changes Take Effect:** Immediate
**Required Authorization to Activate:** Session user
When edb_redwood_raw_names is set to its default value of FALSE, database object names such as
table names, column names, trigger names, program names, user names, etc. appear in uppercase letters
when viewed from Redwood catalogs (that is, system catalogs prefixed by ALL_, DBA_, or USER_). In
addition, quotation marks enclose names that were created with enclosing quotation marks.
with enclosing quotation marks appear exactly as they were created, but without the quotation marks.
```

When edb_redwood_raw_names is set to TRUE, the database object names are displayed exactly as they are stored in the PostgreSQL system catalogs when viewed from the Redwood catalogs. Thus, names created without enclosing quotation marks appear in lowercase as expected in PostgreSQL. Names created

For example, the following user name is created, and then a session is started with that user.

CREATE USER reduser IDENTIFIED BY password;

```
edb=# c - reduser
```

Password for user reduser:

You are now connected to database "edb" as user "reduser".

When connected to the database as reduser, the following tables are created.

CREATE TABLE all_lower (col INTEGER);

CREATE TABLE ALL_UPPER (COL INTEGER);

CREATE TABLE "Mixed_Case" ("Col" INTEGER);

When viewed from the Redwood catalog, USER_TABLES, with edb_redwood_raw_names set to the default value FALSE, the names appear in uppercase except for the Mixed_Case name, which appears as created and also with enclosing quotation marks.

```
edb=> SELECT * FROM USER_TABLES;
```

```
schema_name | table_name | tablespace_name | status | temporary
REDUSER | ALL_LOWER | | VALID | N
REDUSER | ALL_UPPER | | VALID | N
REDUSER | "Mixed_Case" | | VALID | N
(3 rows)
When viewed with edb_redwood_raw_names set to TRUE, the names appear in lowercase except for the
Mixed_Case name, which appears as created, but now without the enclosing quotation marks.
edb=> SET edb_redwood_raw_names TO true;
SET
edb=> SELECT * FROM USER_TABLES;
schema_name | table_name | tablespace_name | status | temporary
reduser | all_lower | | VALID | N
reduser | all_upper | | VALID | N
reduser | Mixed_Case | | VALID | N
(3 rows)
These names now match the case when viewed from the PostgreSQL pg_tables catalog.
    edb=> SELECT schemaname, tablename, tableowner FROM pg_tables WHERE tableowner = 're-
    duser';
    schemaname I tablename I tableowner
    -----+-----
    reduser I all_lower I reduser
    reduser | all_upper | reduser
    reduser | Mixed_Case | reduser
    (3 rows)
edb_redwood_strings
edb_redwood_strings
Parameter Type: Boolean
Default Value: false
Range: {true | false}
Minimum Scope of Effect: Per session
When Value Changes Take Effect: Immediate
Required Authorization to Activate: Session user
```

If the edb_redwood_strings parameter is set to TRUE, when a string is concatenated with a null variable or null column, the result is the original string. If edb_redwood_strings is set to FALSE, the native PostgreSQL behavior is maintained, which is the concatenation of a string with a null variable or null column gives a null result.

The following example illustrates the difference.

The sample application contains a table of employees. This table has a column named comm that is null for most employees. The following query is run with edb_redwood_string set to FALSE. The concatenation of a null column with non-empty strings produces a final result of null, so only employees that have a commission appear in the query result. The output line for all other employees is null.

The following is the same query executed when edb_redwood_strings is set to TRUE. Here, the value of a null column is treated as an empty string. The concatenation of an empty string with a non-empty string produces the non-empty string.

```
SET edb_redwood_strings TO on;

SELECT RPAD(ename,10) || ' ' || TO_CHAR(sal,'99,999.99') || ' ' |

II TO_CHAR(comm,'99,999.99') "EMPLOYEE COMPENSATION" FROM emp;
```

EMPLOYEE COMPENSATION

(14 rows)

SMITH 800.00
ALLEN 1,600.00 300.00
WARD 1,250.00 500.00
JONES 2,975.00
MARTIN 1,250.00 1,400.00
BLAKE 2,850.00
CLARK 2,450.00
SCOTT 3,000.00
KING 5,000.00
TURNER 1,500.00 .00
ADAMS 1,100.00
JAMES 950.00
FORD 3,000.00
MILLER 1,300.00
(14 rows)

edb stmt level tx

edb stmt level tx

Parameter Type: Boolean

Default Value: false **Range:** {true | false}

Minimum Scope of Effect: Per session

When Value Changes Take Effect: Immediate

Required Authorization to Activate: Session user

The term statement level transaction isolation describes the behavior whereby when a runtime error occurs in a SQL command, all the updates on the database caused by that single command are rolled back. For example, if a single UPDATE command successfully updates five rows, but an attempt to update a sixth row results in an exception, the updates to all six rows made by this UPDATE command are rolled back. The effects of prior SQL commands that have not yet been committed or rolled back are pending until a COMMIT or ROLLBACK command is executed.

In Advanced Server, if an exception occurs while executing a SQL command, all the updates on the database since the start of the transaction are rolled back. In addition, the transaction is left in an aborted state and either a COMMIT or ROLLBACK command must be issued before another transaction can be started.

If $edb_stmt_level_tx$ is set to TRUE, then an exception will not automatically roll back prior uncommitted database updates. If $edb_stmt_level_tx$ is set to FALSE, then an exception will roll back uncommitted database updates.

Note

Use edb_stmt_level_tx set to TRUE only when absolutely necessary, as this may cause a negative performance impact.

The following example run in PSQL shows that when edb_stmt_level_tx is FALSE, the abort of the second INSERT command also rolls back the first INSERT command. Note that in PSQL, the command set AUTOCOMMIT off must be issued, otherwise every statement commits automatically defeating the purpose of this demonstration of the effect of edb_stmt_level_tx.

In the following example, with edb_stmt_level_tx set to TRUE, the first INSERT command has not been rolled back after the error on the second INSERT command. At this point, the first INSERT command can either be

committed or rolled back.

```
\set AUTOCOMMIT off
```

A ROLLBACK command could have been issued instead of the COMMIT command in which case the insert of employee number 9001 would have been rolled back as well.

db_dialect

db_dialect

Parameter Type: Enum

Default Value: postgres

Range: {postgres | redwood}

rianger (postgree rioameea)

Minimum Scope of Effect: Per session

When Value Changes Take Effect: Immediate

Required Authorization to Activate: Session user

In addition to the native PostgreSQL system catalog, <code>pg_catalog</code> , Advanced Server contains an extended catalog view. This is the <code>sys</code> catalog for the expanded catalog view. The <code>db_dialect</code> parameter controls the order in which these catalogs are searched for name resolution.

When set to postgres, the namespace precedence is pg_catalog then sys, giving the PostgreSQL catalog the highest precedence. When set to redwood, the namespace precedence is sys then pg_catalog, giving the expanded catalog views the highest precedence.

default_with_rowids

default_with_rowids

Parameter Type: Boolean

Default Value: false
Range: {true | false}

Minimum Scope of Effect: Per session

When Value Changes Take Effect: Immediate

Required Authorization to Activate: Session user

When set to on , CREATE TABLE includes a ROWID column in newly created tables, which can then be referenced in SQL commands. In earlier versions of Advanced Server ROWIDs were mapped to 0IDs , but from Advanced Server version 12 onwards, the ROWID is an auto-incrementing value based on a sequence that starts with 1 and assigned to each row of a table created with ROWIDs option. By default, a unique index is created on a ROWID column.

The ALTER and DROP operations are restricted on a ROWID column.

To restore a database with ROWIDs from Advanced Server 11 or an earlier version, you must perform the following:

- pg_dump: If a table includes OIDs then specify --convert-oids-to-rowids to dump a database. Otherwise, ignore the OIDs to continue table creation on Advanced Server version 12 onwards.
- pg_upgrade: Errors out. But if a table includes OIDs or ROWIDs , then you must perform the following steps:
 - 1. Take a dump of the tables by specifying --convert-oids-to-rowids option.
 - 2. Drop the tables and then perform the upgrade.
 - 3. Restore the dump after the upgrade is successful into a new cluster that contains the dumped tables into a target database.

optimizer mode

optimizer_mode

Parameter Type: Enum

Default Value: choose

Range: {choose | ALL_ROWS | FIRST_ROWS | FIRST_ROWS_10 | FIRST_ROWS_100 | FIRST_ROWS_1000}

Minimum Scope of Effect: Per session

When Value Changes Take Effect: Immediate Required Authorization to Activate: Session user

riequired Authorization to Activate: Occasion date

Sets the default optimization mode for analyzing optimizer hints.

The following table shows the possible values:

Table - Optimizer Modes

Hint	Description
ALL_ROWS	Optimizes for retrieval of all rows of the result set.
CHOOSE	Does no default optimization based on assumed number of rows to be retrieved from the result set
FIRST_ROWS	Optimizes for retrieval of only the first row of the result set.
FIRST_ROWS_10	Optimizes for retrieval of the first 10 rows of the results set.
FIRST_ROWS_100	Optimizes for retrieval of the first 100 rows of the result set.
FIRST_ROWS_1000	Optimizes for retrieval of the first 1000 rows of the result set.

These optimization modes are based upon the assumption that the client submitting the SQL command is interested in viewing only the first n rows of the result set and will then abandon the remainder of the result set. Resources allocated to the query are adjusted as such.

10.3.3.12 Customized Options

Customized Options

In previous releases of Advanced Server, the custom_variable_classes was required by those parameters not normally known to be added by add-on modules (such as procedural languages).

custom_variable_classes

custom_variable_classes

The custom_variable_classes parameter is deprecated in Advanced Server 9.2; parameters that previously depended on this parameter no longer require its support.

dbms_alert.max_alerts

dbms_alert.max_alerts

Parameter Type: Integer

Default Value: 100 Range: 0 to 500

Minimum Scope of Effect: Cluster

When Value Changes Take Effect: Restart

Required Authorization to Activate: EPAS service account

Specifies the maximum number of concurrent alerts allowed on a system using the DBMS_ALERTS package.

dbms_pipe.total_message_buffer

dbms_pipe.total_message_buffer

Parameter Type: Integer

Default Value: 30 Kb

Range: 30 Kb to 256 Kb

Minimum Scope of Effect: Cluster

When Value Changes Take Effect: Restart

Required Authorization to Activate: EPAS service account

Specifies the total size of the buffer used for the DBMS_PIPE package.

index_advisor.enabled

index advisor.enabled

Parameter Type: Boolean

Default Value: true Range: {true | false}

Minimum Scope of Effect: Per session

When Value Changes Take Effect: Immediate

Required Authorization to Activate: Session user

Provides the capability to temporarily suspend Index Advisor in an EDB-PSQL or PSQL session. The Index Advisor plugin, index_advisor, must be loaded in the EDB-PSQL or PSQL session in order to use the index_advisor.enabled configuration parameter.

The Index Advisor plugin can be loaded as shown by the following example:

```
$ psql -d edb -U <user>
Password for user <user>:
psql (12.0.0)
Type "help" for help.
edb=# LOAD 'index_advisor';
```

Use the SET command to change the parameter setting to control whether or not Index Advisor generates an alternative query plan as shown by the following example:

edb_sql_protect.enabled

edb_sql_protect.enabled

Parameter Type: Boolean

Default Value: false **Range:** {true | false}

Minimum Scope of Effect: Cluster

When Value Changes Take Effect: Reload

Required Authorization to Activate: EPAS service account

Controls whether or not SQL/Protect is actively monitoring protected roles by analyzing SQL statements issued by those roles and reacting according to the setting of begin monitoring with SQL/Protect set this parameter to on.

edb_sql_protect.level

edb_sql_protect.level
Parameter Type: Enum
Default Value: passive

Range: {learn | passive | active}

Minimum Scope of Effect: Cluster

When Value Changes Take Effect: Reload

Required Authorization to Activate: EPAS service account

Sets the action taken by SQL/Protect when a SQL statement is issued by a protected role.

The edb_sql_protect.level configuration parameter can be set to one of the following values to use either learn mode, passive mode, or active mode:

- **learn.** Tracks the activities of protected roles and records the relations used by the roles. This is used when initially configuring SQL/Protect so the expected behaviors of the protected applications are learned.
- passive. Issues warnings if protected roles are breaking the defined rules, but does not stop any SQL statements from executing. This is the next step after SQL/Protect has learned the expected behavior of the protected roles. This essentially behaves in intrusion detection mode and can be run in production when properly monitored.

active. Stops all invalid statements for a protected role. This behaves as a SQL firewall preventing
dangerous queries from running. This is particularly effective against early penetration testing when the
attacker is trying to determine the vulnerability point and the type of database behind the application.
Not only does SQL/Protect close those vulnerability points, but it tracks the blocked queries allowing
administrators to be alerted before the attacker finds an alternate method of penetrating the system.

If you are using SQL/Protect for the first time, set edb_sql_protect .level to learn.

edb sql protect.max protected relations

edb_sql_protect.max_protected_relations

Parameter Type: Integer Default Value: 1024 Range: 1 to 2147483647

Minimum Scope of Effect: Cluster

When Value Changes Take Effect: Restart

Required Authorization to Activate: EPAS service account

Sets the maximum number of relations that can be protected per role. Please note the total number of protected relations for the server will be the number of protected relations times the number of protected roles. Every protected relation consumes space in shared memory. The space for the maximum possible protected relations is reserved during database server startup.

If the server is started when edb_sql_protect.max_protected_relations is set to a value outside of the valid range (for example, a value of 2,147,483,648), then a warning message is logged in the database server log file:

2014-07-18 16:04:12 EDT WARNING: invalid value for parameter "edb_sql_protect.max_protected_relations": "2147483648"

2014-07-18 16:04:12 EDT HINT: Value exceeds integer range.

The database server starts successfully, but with edb_sql_protect.max_protected_relations set to the default value of 1024.

Though the upper range for the parameter is listed as the maximum value for an integer data type, the practical setting depends on how much shared memory is available and the parameter value used during database server startup.

As long as the space required can be reserved in shared memory, the value will be acceptable. If the value is such that the space in shared memory cannot be reserved, the database server startup fails with an error message such as the following:

2014-07-18 15:22:17 EDT FATAL: could not map anonymous shared memory: Cannot allocate memory

2014-07-18 15:22:17 EDT HINT: This error usually means that PostgreSQL's request for a shared memory segment exceeded available memory, swap space or huge pages. To reduce the request size (currently 2070118400 bytes), reduce PostgreSQL's shared memory usage, perhaps by reducing shared_buffers or max_connections.

In such cases, reduce the parameter value until the database server can be started successfully.

edb_sql_protect.max_protected_roles

edb_sql_protect.max_protected_roles

Parameter Type: Integer

Default Value: 64

Range: 1 to 2147483647

Minimum Scope of Effect: Cluster

When Value Changes Take Effect: Restart

Required Authorization to Activate: EPAS service account

Sets the maximum number of roles that can be protected.

Every protected role consumes space in shared memory. Please note that the server will reserve space for the number of protected roles times the number of protected relations (edb_sql_protect.max_protected_relations). The space for the maximum possible protected roles is reserved during database server startup.

If the database server is started when edb_sql_protect.max_protected_roles is set to a value outside of the valid range (for example, a value of 2,147,483,648), then a warning message is logged in the database server log file:

2014-07-18 16:04:12 EDT WARNING: invalid value for parameter "edb_sql_protect.max_protected_roles": "2147483648"

2014-07-18 16:04:12 EDT HINT: Value exceeds integer range.

The database server starts successfully, but with edb_sql_protect.max_protected_roles set to the default value of 64.

Though the upper range for the parameter is listed as the maximum value for an integer data type, the practical setting depends on how much shared memory is available and the parameter value used during database server startup.

As long as the space required can be reserved in shared memory, the value will be acceptable. If the value is such that the space in shared memory cannot be reserved, the database server startup fails with an error message such as the following:

2014-07-18 15:22:17 EDT FATAL: could not map anonymous shared memory: Cannot allocate memory

2014-07-18 15:22:17 EDT HINT: This error usually means that PostgreSQL's request for a shared memory segment exceeded available memory, swap space or huge pages. To reduce the request size (currently 2070118400 bytes), reduce PostgreSQL's shared memory usage, perhaps by reducing shared_buffers or max_connections.

In such cases, reduce the parameter value until the database server can be started successfully.

edb_sql_protect.max_queries_to_save

edb_sql_protect.max_queries_to_save

Parameter Type: Integer Default Value: 5000

Range: 100 to 2147483647

Minimum Scope of Effect: Cluster

When Value Changes Take Effect: Restart

Required Authorization to Activate: EPAS service account

Sets the maximum number of offending queries to save in view edb_sql_protect_queries .

Every query that is saved consumes space in shared memory. The space for the maximum possible queries that can be saved is reserved during database server startup.

If the database server is started when edb_sql_protect.max_queries_to_save is set to a value outside of the valid range (for example, a value of 10), then a warning message is logged in the database server log file:

2014-07-18 13:05:31 EDT WARNING: 10 is outside the valid range for parameter "edb_sql_protect.max_queries_to_save" (100 .. 2147483647)

The database server starts successfully, but with edb_sql_protect.max_queries_to_save set to the default value of 5000.

Though the upper range for the parameter is listed as the maximum value for an integer data type, the practical setting depends on how much shared memory is available and the parameter value used during database server startup.

As long as the space required can be reserved in shared memory, the value will be acceptable. If the value is such that the space in shared memory cannot be reserved, the database server startup fails with an error message such as the following:

2014-07-18 15:22:17 EDT FATAL: could not map anonymous shared memory: Cannot allocate memory

2014-07-18 15:22:17 EDT HINT: This error usually means that PostgreSQL's request for a shared memory segment exceeded available memory, swap space or huge pages. To reduce the request size (currently 2070118400 bytes), reduce PostgreSQL's shared memory usage, perhaps by reducing shared_buffers or max_connections.

In such cases, reduce the parameter value until the database server can be started successfully.

edb_wait_states.directory

edb_wait_states.directory

Parameter Type: String

Default Value: edb_wait_states

Range: n/a

Minimum Scope of Effect: Cluster

When Value Changes Take Effect: Restart

Required Authorization to Activate: EPAS service account

Sets the directory path where the EDB wait states log files are stored. The specified path should be a full, absolute path and not a relative path. However, the default setting is edb_wait_states , which makes \$PGDATA/edb_wait_states the default directory location. See Section 8.2 for information on EDB wait states.

edb_wait_states.retention_period

edb_wait_states.retention_period

Parameter Type: Integer Default Value: 604800s

Range: 86400s to 2147483647s

Minimum Scope of Effect: Cluster

When Value Changes Take Effect: Reload

Required Authorization to Activate: EPAS service account

Sets the period of time after which the log files for EDB wait states will be deleted. The default is 604800 seconds, which is 7 days. See Section 8.2 for information on EDB wait states.

edb_wait_states.sampling_interval

edb wait states.sampling interval

Parameter Type: Integer

Default Value: 1s

Range: 1s to 2147483647s

Minimum Scope of Effect: Cluster

When Value Changes Take Effect: Reload

Required Authorization to Activate: EPAS service account

Sets the timing interval between two sampling cycles for EDB wait states. The default setting is 1 second. See

Section 8.2 for information on EDB wait states.

edbldr.empty_csv_field

edbldr.empty_csv_field

Parameter Type: Enum

Default Value: NULL

Range: {NULL | empty_string | pgsql}
Minimum Scope of Effect: Per session

When Value Changes Take Effect: Immediate

Required Authorization to Activate: Session user

Use the edbldr.empty_csv_field parameter to specify how EDB*Loader will treat an empty string. The

valid values for the edbldr.empty_csv_field parameter are:

Parameter Setting	EDB*Loader Behavior
NULL	An empty field is treated as NULL.
empty_string	An empty field is treated as a string of length zero.
pgsql	An empty field is treated as a NULL if it does not contain quotes and as an empty string if it contains o

For more information about the edbldr.empty_csv_field parameter in EDB*Loader, see the *Database Compatibility for Oracle Developers Tools and Utilities Guide* at the EnterpriseDB website:

https://www.enterprisedb.com/edb-docs

utl_encode.uudecode_redwood

utl_encode.uudecode_redwood

Parameter Type: Boolean

Default Value: false
Range: {true | false}

Minimum Scope of Effect: Per session

When Value Changes Take Effect: Immediate

Required Authorization to Activate: Session user

When set to TRUE, Advanced Server's UTL_ENCODE.UUDECODE function can decode uuencoded data that was created by the Oracle implementation of the UTL_ENCODE.UUENCODE function.

When set to the default setting of FALSE, Advanced Server's UTL_ENCODE.UUDECODE function can decode uuencoded data created by Advanced Server's UTL_ENCODE.UUENCODE function.

utl_file.umask

utl file.umask

Parameter Type: String
Default Value: 0077

Range: Octal digits for umask settings

Minimum Scope of Effect: Per session

When Value Changes Take Effect: Immediate

Required Authorization to Activate: Session user

The utl_file.umask parameter sets the *file mode creation mask* or simply, the *mask*, in a manner similar to the Linux umask command. This is for usage only within the Advanced Server UTL_FILE package.

Note: The utl_file.umask parameter is not supported on Windows systems.

The value specified for utl_file.umask is a 3 or 4-character octal string that would be valid for the Linux umask command. The setting determines the permissions on files created by the UTL_FILE functions and procedures. (Refer to any information source regarding Linux or Unix systems for information on file permissions and the usage of the umask command.)

The following shows the results of the default utl_file.umask setting of 0077. Note that all permissions are denied on users belonging to the enterprised group as well as all other users. Only user enterprised has read and write permissions on the file.

-rw----- 1 enterprisedb enterprisedb 21 Jul 24 16:08 utlfile

10.3.3.13 Ungrouped

Ungrouped

Configuration parameters in this section apply to Advanced Server only and are for a specific, limited purpose.

nls_length_semantics

Parameter Type: Enum
Default Value: byte

Range: {byte | char}

....

Minimum Scope of Effect: Per session

When Value Changes Take Effect: Immediate
Required Authorization to Activate: Superuser

This parameter has no effect in Advanced Server.

For example, the form of the ALTER SESSION command is accepted in Advanced Server without throwing a syntax error, but does not alter the session environment:

ALTER SESSION SET nls_length_semantics = char;

Note: Since the setting of this parameter has no effect on the server environment, it does not appear in the system view pg_settings.

query_rewrite_enabled

Parameter Type: Enum

Default Value: false

Range: {true | false | force}

Minimum Scope of Effect: Per session

When Value Changes Take Effect: Immediate

Required Authorization to Activate: Session user

This parameter has no effect in Advanced Server.

For example, the following form of the ALTER SESSION command is accepted in Advanced Server without throwing a syntax error, but does not alter the session environment:

ALTER SESSION SET query_rewrite_enabled = force;

Note: Since the setting of this parameter has no effect on the server environment, it does not appear in the system view pg_settings.

query rewrite integrity

Parameter Type: Enum

Default Value: enforced

Range: {enforced | trusted | stale_tolerated}
Minimum Scope of Effect: Per session

When Value Changes Take Effect: Immediate
Required Authorization to Activate: Superuser
This parameter has no effect in Advanced Server.

For example, the following form of the ALTER SESSION command is accepted in Advanced Server without throwing a syntax error, but does not alter the session environment:

ALTER SESSION SET query_rewrite_integrity = stale_tolerated;

Note: Since the setting of this parameter has no effect on the server environment, it does not appear in the system view pg_settings.

timed_statistics

Parameter Type: Boolean

Default Value: true Range: {true | false}

Minimum Scope of Effect: Per session

When Value Changes Take Effect: Immediate

Required Authorization to Activate: Session user

Controls the collection of timing data for the Dynamic Runtime Instrumentation Tools Architecture (DRITA) feature. When set to on, timing data is collected.

Note: When Advanced Server is installed, the postgresql.conf file contains an explicit entry setting timed_statistics to off. If this entry is commented out letting timed_statistics to default, and the configuration file is reloaded, timed statistics collection would be turned on.

10.4.0 Index Advisor

Index Advisor

The Index Advisor utility helps determine which columns you should index to improve performance in a given workload. Index Advisor considers B-tree (single-column or composite) index types, and does not identify other index types (GIN, GiST, Hash) that may improve performance. Index Advisor is installed with EDB Postgres Advanced Server.

Index Advisor works with Advanced Server's query planner by creating *hypothetical indexes* that the query planner uses to calculate execution costs as if such indexes were available. Index Advisor identifies the indexes by analyzing SQL queries supplied in the workload.

There are three ways to use Index Advisor to analyze SQL queries:

- Invoke the Index Advisor utility program, supplying a text file containing the SQL queries that you wish to analyze; Index Advisor will generate a text file with CREATE INDEX statements for the recommended indexes.
- Provide queries at the EDB-PSQL command line that you want Index Advisor to analyze.
- Access Index Advisor through the Postgres Enterprise Manager client. When accessed via the PEM client, Index Advisor works with SQL Profiler, providing indexing recommendations on code captured in SQL traces. For more information about using SQL Profiler and Index Advisor with PEM, please see the PEM Getting Started Guide available from the EnterpriseDB website at:

https://www.enterprisedb.com/edb-docs

Index Advisor will attempt to make indexing recommendations on INSERT, UPDATE, DELETE and SELECT statements. When invoking Index Advisor, you supply the workload in the form of a set of queries (if you are providing the command in an SQL file) or an EXPLAIN statement (if you are specifying the SQL statement at the psql command line). Index Advisor displays the query plan and estimated execution cost for the supplied query, but does not actually execute the query.

During the analysis, Index Advisor compares the query execution costs with and without hypothetical indexes. If the execution cost using a hypothetical index is less than the execution cost without it, both plans are reported in the EXPLAIN statement output, metrics that quantify the improvement are calculated, and Index Advisor generates the CREATE INDEX statement needed to create the index.

If no hypothetical index can be found that reduces the execution cost, Index Advisor displays only the original query plan output of the EXPLAIN statement.

Index Advisor does not actually create indexes on the tables. Use the "CREATE INDEX" statements supplied by Index Advisor to add any recommended indexes to your tables.

A script supplied with Advanced Server creates the table in which Index Advisor stores the indexing recommendations generated by the analysis; the script also creates a function and a view of the table to simplify the retrieval and interpretation of the results.

If you choose to forego running the script, Index Advisor will log recommendations in a temporary table that is available only for the duration of the Index Advisor session.

10.4.1 Index Advisor Components

Index Advisor Components

The Index Advisor shared library interacts with the query planner to make indexing recommendations. On Windows, the Advanced Server installer creates the following shared library in the libdir subdirectory of your Advanced Server home directory. For Linux, install the edb-as<xx>-server-indexadvisor RPM package where xx is the Advanced Server version number.

On Linux:

index_advisor.so

On Windows:

index advisor.dll

Please note that libraries in the libdir directory can only be loaded by a superuser. A database administrator can allow a non-superuser to use Index Advisor by manually copying the Index Advisor file from the libdir directory into the libdir/plugins directory (under your Advanced Server home directory). Only a trusted non-superuser should be allowed access to the plugin; this is an unsafe practice in a production environment.

The installer also creates the Index Advisor utility program and setup script:

pg_advise_index

pg_advise_index is a utility program that reads a user-supplied input file containing SQL queries and produces a text file containing CREATE INDEX statements that can be used to create the indexes recommended by the Index Advisor. The pg_advise_index program is located in the bin subdirectory of the Advanced Server home directory.

index_advisor.sql

index_advisor.sql is a script that creates a permanent Index Advisor log table along with a function and view to facilitate reporting of recommendations from the log table. The script is located in the share/contrib subdirectory of the Advanced Server directory.

The index_advisor.sql script creates the index_advisor_log table, the show_index_recommendations() function and the index_recommendations view. These database objects must be created in a schema that is accessible by, and included in the search path of the role that will invoke Index Advisor.

index_advisor_log

Index Advisor logs indexing recommendations in the <code>index_advisor_log</code> table. If Index Advisor does not find the <code>index_advisor_log</code> table in the user's search path, Index Advisor will store any indexing recommendations in a temporary table of the same name. The temporary table exists only for the duration of the current session.

show_index_recommendations()

show_index_recommendations() is a PL/pgSQL function that interprets and displays the recommendations made during a specific Index Advisor session (as identified by its backend process ID).

index_recommendations

Index_Advisor creates the index_recommendations view based on information stored in the index_advisor_log table during a query analysis. The view produces output in the same format as the show_index_recommendations() function, but contains Index Advisor recommendations for all stored sessions, while the result set returned by the show_index_recommendations() function are limited to a specified session.

10.4.2 Index Advisor Configuration

Index Advisor Configuration

Index Advisor does not require configuration to generate recommendations that are available only for the duration of the current session; to store the results of multiple sessions, you must create the <code>index_advisor_log</code> table. To create the <code>index_advisor_log</code> table, you must run the <code>index_advisor.sql</code> script.

When selecting a storage schema for the Index Advisor table, function and view, keep in mind that all users that invoke Index Advisor (and query the result set) must have USAGE privileges on the schema. The schema must be in the search path of all users that are interacting with the Index Advisor.

1. Place the selected schema at the start of your search_path parameter. For example, if your search path is currently:

search_path=public, accounting

and you want the Index Advisor objects to be created in a schema named advisor, use the command:

SET search_path = advisor, public, accounting;

2. Run the index_advisor.sql script to create the database objects. If you are running the psql client, you can use the command:

i <full pathname>/index advisor.sql

Specify the pathname to the index_advisor.sql script in place of full_pathname.

- 3. Grant privileges on the index_advisor_log table to all Index Advisor users; this step is not necessary if the Index Advisor user is a superuser, or the owner of these database objects.
- Grant SELECT and INSERT privileges on the index_advisor_log table to allow a user to invoke Index Advisor.
- Grant DELETE privileges on the index_advisor_log table to allow the specified user to delete the table contents.
- Grant SELECT privilege on the index_recommendations view.

The following example demonstrates the creation of the Index Advisor database objects in a schema named ia, which will then be accessible to an Index Advisor user with user name ia_user:

```
$ edb-psql -d edb -U enterprisedb
psql.bin (12.0.0, server 12.0.0)
Type "help" for help.
 edb=# CREATE SCHEMA ia;
CREATE SCHEMA
 edb=# SET search_path TO ia;
 edb=# \i /usr/edb/as12/share/contrib/index_advisor.sql
CREATE TABLE
CREATE INDEX
CREATE INDEX
 CREATE FUNCTION
 CREATE FUNCTION
 CREATE VIEW
 edb=# GRANT USAGE ON SCHEMA ia TO ia_user;
GRANT
 edb=# GRANT SELECT, INSERT, DELETE ON index_advisor_log TO ia_user;
edb=# GRANT SELECT ON index_recommendations TO ia_user;
GRANT
```

While using Index Advisor, the specified schema (ia) must be included in *ia_user*'s search_path parameter.

10.4.3 Using Index Advisor

Using Index advisor

When you invoke Index Advisor, you must supply a workload; the workload is either a query (specified at the command line), or a file that contains a set of queries (executed by the pg_advise_index() function). After analyzing the workload, Index Advisor will either store the result set in a temporary table, or in a permanent table. You can review the indexing recommendations generated by Index Advisor and use the Statements generated by Index Advisor to create the recommended indexes.

Note

You should not run Index Advisor in read-only transactions.

The following examples assume that superuser enterprisedb is the Index Advisor user, and the Index Advisor database objects have been created in a schema in the search_path of superuser enterprisedb

The examples in the following sections use the table created with the statement shown below:

```
CREATE TABLE t( a INT, b INT );
INSERT INTO t SELECT s, 99999 - s FROM generate_series(0,99999) AS s;
ANALYZE t;
```

The resulting table contains the following rows:

Using the pg_advise_index Utility

When invoking the pg_advise_index utility, you must include the name of a file that contains the queries that will be executed by pg_advise_index; the queries may be on the same line, or on separate lines, but each query must be terminated by a semicolon. Queries within the file should not begin with the EXPLAIN keyword.

The following example shows the contents of a sample workload.sql file:

```
SELECT * FROM t WHERE a = 500;
SELECT * FROM t WHERE b < 1000;
```

Run the pq_advise_index program as shown in the code sample below:

```
$ pg_advise_index -d edb -h localhost -U enterprisedb -s 100M -o
advisory.sql workload.sql
poolsize = 102400 KB
ad workload from file 'workload.sql'
Analyzing queries .. done.
size = 2184 KB, benefit = 1684.720000
size = 2184 KB, benefit = 1655.520000
/* 1. t(a): size=2184 KB, benefit=1684.72 */
/* 2. t(b): size=2184 KB, benefit=1655.52 */
/* Total size = 4368KB */
```

In the code sample, the -d, -h, and -U options are psql connection options.

-s

-s is an optional parameter that limits the maximum size of the indexes recommended by Index Advisor. If Index Advisor does not return a result set, -s may be set too low.

-0

The recommended indexes are written to the file specified after the -o option.

The information displayed by the pg_advise_index program is logged in the index_advisor_log table. In response to the command shown in the example, Index Advisor writes the following CREATE INDEX statements to the advisory.sql output file.

```
create index idx_t_1 on t (a);
create index idx_t_2 on t (b);
```

You can create the recommended indexes at the psql command line with the CREATE INDEX statements in the file, or create the indexes by executing the advisory.sql script.

```
$ edb-psql -d edb -h localhost -U enterprisedb -e -f advisory.sql
create index idx_t_1 on t (a);
CREATE INDEX
create index idx_t_2 on t (b);
```

Using Index Advisor at the psql Command Line

You can use Index Advisor to analyze SQL statements entered at the edb-psql (or psql) command line; the following steps detail loading the Index Advisor plugin and using Index Advisor:

1. Connect to the server with the edb-psql command line utility, and load the Index Advisor plugin:

```
$ edb-psql -d edb -U enterprisedb
...
edb=# LOAD 'index_advisor';
LOAD
```

2. Use the edb-psql command line to invoke each SQL command that you would like Index Advisor to analyze. Index Advisor stores any recommendations for the queries in the index_advisor_log table. If the index_advisor_log table does not exist in the user's search_path, a temporary table is created with the same name. This temporary table exists only for the duration of the user's session.

After loading the Index Advisor plugin, Index Advisor will analyze all SQL statements and log any indexing recommendations for the duration of the session.

If you would like Index Advisor to analyze a query (and make indexing recommendations) without actually executing the query, preface the SQL statement with the EXPLAIN keyword.

If you do not preface the statement with the EXPLAIN keyword, Index Advisor will analyze the statement while the statement executes, writing the indexing recommendations to the index_advisor_log table for later review.

In the example that follows, the EXPLAIN statement displays the normal query plan, followed by the query plan of the same query, if the query were using the recommended hypothetical index:

```
edb=# EXPLAIN SELECT * FROM t WHERE a < 10000;
```

```
QUERY PLAN
Seq Scan on t (cost=0.00..1693.00 rows=10105 width=8)
Filter: (a < 10000)
Result (cost=0.00..337.10 rows=10105 width=8)
One-Time Filter: '===[ HYPOTHETICAL PLAN ]==='::text
 -> Index Scan using "<hypothetical-index>:1" on t
 (cost=0.00..337.10 rows=10105 width=8)
Index Cond: (a < 10000)
(6 rows)
edb=# EXPLAIN SELECT * FROM t WHERE a = 100;
                        QUERY PLAN
Seq Scan on t (cost=0.00..1693.00 rows=1 width=8)
Filter: (a = 100)
Result (cost=0.00..8.28 rows=1 width=8)
One-Time Filter: '===[ HYPOTHETICAL PLAN ]==='::text
 -> Index Scan using "<hypothetical-index>:3" on t
 (cost=0.00..8.28 rows=1 width=8)
Index Cond: (a = 100)
(6 rows)
```

After loading the Index Advisor plugin, the default value of <code>index_advisor.enabled</code> is <code>on</code> . The Index Advisor plugin must be loaded to use a <code>SET</code> or <code>SHOW</code> command to display the current value of index_advisor.enabled.

You can use the index_advisor.enabled parameter to temporarily disable Index Advisor without interrupting the psql session:

```
edb=# SET index_advisor.enabled TO off;
SET

To enable Index Advisor, set the parameter to on:
edb=# SET index_advisor.enabled TO on;
SET
```

10.4.4 Reviewing the Index Advisor Recommendations

Reviewing the Index Advisor Recommendations

There are several ways to review the index recommendations generated by Index Advisor. You can:

- Query the index_advisor_log table.
- Run the show_index_recommendations function.
- Query the index_recommendations view.

Using the show_index_recommendations() Function

To review the recommendations of the Index Advisor utility using the show_index_recommendations() function, call the function, specifying the process ID of the session:

```
SELECT show_index_recommendations( *pid* );
```

Where *pid* is the process ID of the current session. If you do not know the process ID of your current session, passing a value of NULL will also return a result set for the current session.

The following code fragment shows an example of a row in a result set:

In the example, create index idx_t_a on t(a) is the SQL statement needed to create the index suggested by Index Advisor. Each row in the result set shows: - The command required to create the recommended index. - The maximum estimated size of the index. - The calculated benefit of using the index. - The estimated gain that will result from implementing the index.

You can display the results of all Index Advisor sessions from the following view:

```
SELECT * FROM index_recommendations;
```

Querying the index_advisor_log Table

Index Advisor stores indexing recommendations in a table named <code>index_advisor_log</code> . Each row in the <code>index_advisor_log</code> table contains the result of a query where Index Advisor determines it can recommend a hypothetical index to reduce the execution cost of that query.

Column	Туре	Description
reloid relname attrs benefit index_size backend_pid timestamp	oid name integer[] real integer integer timestamp	OID of the base table for the index Name of the base table for the index Recommended index columns (identified by column number) Calculated benefit of the index for this query Estimated index size in disk-pages Process ID of the process generating this recommendation Date/Time when the recommendation was generated

You can query the <code>index_advisor_log</code> table at the psql command line. The following example shows the <code>index_advisor_log</code> table entries resulting from two Index Advisor sessions. Each session contains two queries, and can be identified (in the table below) by a different <code>backend_pid</code> value. For each session, Index Advisor generated two index recommendations.

```
edb=# SELECT * FROM index_advisor_log;
reloid | relname | attrs | benefit | index_size | backend_pid | timestamp
_____
16651 | t | {1} | 1684.72 | 2184 |
                                    3442 | 22-MAR-11 16:44:32.712638 -
04:00
    | t | {2} | 1655.52 |
                                    3442 | 22-MAR-11 16:44:32.759436 -
16651
                           2184 l
04:00
16651
    | t | {1} | 1355.9 | 2184 |
                                    3506 | 22-MAR-11 16:48:28.317016 -
04:00
        t | {1} | 1684.72 |
                           2184 l
                                    3506 | 22-MAR-11 16:51:45.927906 -
16651
04:00
(4 rows)
```

Index Advisor added the first two rows to the table after analyzing the following two queries executed by the pg_advise_index utility:

```
SELECT * FROM t WHERE a = 500;
SELECT * FROM t WHERE b < 1000;
```

(6 rows)

The value of 3442 in column backend_pid identifies these results as coming from the session with process ID 3442.

The value of 1 in column attrs in the first row indicates that the hypothetical index is on the first column of the table (column a of table t).

The value of 2 in column attrs in the second row indicates that the hypothetical index is on the second column of the table (column b of table t).

Index Advisor added the last two rows to the table after analyzing the following two queries (executed at the psql command line):

```
edb=# EXPLAIN SELECT * FROM t WHERE a < 10000;
                                    OUERY PLAN
Seg Scan on t (cost=0.00..1693.00 rows=10105 width=8)
Filter: (a < 10000)
Result (cost=0.00..337.10 rows=10105 width=8)
 One-Time Filter: '===[ HYPOTHETICAL PLAN ]==='::text
-> Index Scan using "<hypothetical-index>:1" on t (cost=0.00..337.10
rows=10105 width=8)
  Index Cond: (a < 10000)
(6 rows)
edb=# EXPLAIN SELECT * FROM t WHERE a = 100;
                              OUERY PLAN
Seq Scan on t (cost=0.00..1693.00 rows=1 width=8)
  Filter: (a = 100)
Result (cost=0.00..8.28 rows=1 width=8)
 One-Time Filter: '===[ HYPOTHETICAL PLAN ]==='::text
-> Index Scan using "<hypothetical-index>:3" on t (cost=0.00..8.28
rows=1 width=8)
Index Cond: (a = 100)
```

The values in the benefit column of the index_advisor_log table are calculated using the following formula:

```
benefit = (normal execution cost) - (execution cost with hypothetical index)
```

The value of the benefit column for the last row of the index_advisor_log table (shown in the example) is calculated using the query plan for the following SQL statement:

```
EXPLAIN SELECT * FROM t WHERE a = 100;
```

The execution costs of the different execution plans are evaluated and compared:

```
benefit = (Seq Scan on t cost) - (Index Scan using <hypothetical-index>)
```

and the benefit is added to the table:

```
benefit = 1693.00 - 8.28 benefit = 1684.72
```

You can delete rows from the index_advisor_log table when you no longer have the need to review the results of the queries stored in the row.

Querying the index_recommendations View

The index_recommendations view contains the calculated metrics and the CREATE INDEX statements to create the recommended indexes for all sessions whose results are currently in the index_advisor_log table. You can display the results of all stored Index Advisor sessions by querying the index_recommendations view as shown below:

```
SELECT * FROM index_recommendations;
```

Using the example shown in the previous section (*Querying the index_advisor_log Table*), the index_recommendations view displays the following:

```
3506 | create index idx_t_a on t(a);/* size: 2184 KB, benefit: \3040.62, gain: 1.392226669814 (3 rows)
```

l create index idx_t_b on t(b);/* size: 2184 KB, benefit: 1655.52, gain: 0.7580215398208

Within each session, the results of all queries that benefit from the same recommended index are combined to produce one set of metrics per recommended index, reflected in the fields named benefit and gain.

The formulas for the fields are as follows:

3442

04:00

```
size = MAX(index size of all queries)
benefit = SUM(benefit of each query)
gain = SUM(benefit of each query) / MAX(index size of all queries)
```

So for example, using the following query results from the process with a backend_pid of 3506:

```
reloid | relname | attrs | benefit | index_size | backend_pid | timestamp
------
           | {1} | 1355.9 |
                          2184
                                3506
                                         | 22-MAR-11 16:48:28.317016 -
16651
    - 1
        t
04:00
16651
           | {1} | 1684.72 |
                          2184
                                   3506
                                         | 22-MAR-11 16:51:45.927906 -
```

The metrics displayed from the index_recommendations view for backend_pid 3506 are:

```
backend_pid | show_index_recommendations
```

```
------
```

```
3506 | create index idx_t_a on t(a);/* size: 2184 KB, benefit: 3040.62, gain: 1.3922266698145
```

The metrics from the view are calculated as follows:

```
benefit = (benefit from 1st query) + (benefit from 2nd query)
benefit = 1355.9 + 1684.72
benefit = 3040.62
and
gain = ((benefit from 1st query) + (benefit from 2nd query)) / MAX(index size of all queries)
gain = (1355.9 + 1684.72) / MAX(2184, 2184)
gain = 3040.62 / 2184
gain = 1.39223
```

The gain metric is useful when comparing the relative advantage of the different recommended indexes derived during a given session. The larger the gain value, the better the cost effectiveness derived from the index weighed against the possible disk space consumption of the index.

10.4.5 Limitations

Index Advisor Limitations

Index Advisor does not consider Index Only scans; it does consider Index scans when making recommendations.

Index Advisor ignores any computations found in the WHERE clause. Effectively, the index field in the recommendations will not be any kind of expression; the field will be a simple column name.

Index Advisor does not consider inheritance when recommending hypothetical indexes. If a query references a parent table, Index Advisor does not make any index recommendations on child tables.

Restoration of a pg_dump backup file that includes the index_advisor_log table or any tables for which indexing recommendations were made and stored in the index_advisor_log table, may result in "broken links" between the index_advisor_log table and the restored tables referenced by rows in the index_advisor_log table because of changes in object identifiers (OIDs).

If it is necessary to display the recommendations made prior to the backup, you can replace the old OIDs in the reloid column of the index_advisor_log table with the new OIDs of the referenced tables using the SQL UPDATE statement:

UPDATE index_advisor_log SET reloid = new_oid WHERE reloid = old_oid;

10.5 SQL Profiler

SQL Profiler

Inefficient SQL code is one of, if not the leading cause of database performance problems. The challenge for database administrators and developers is locating and then optimizing this code in large, complex systems.

SQL Profiler helps you locate and optimize poorly running SQL code.

Specific features and benefits of SQL Profiler include the following:

- On-Demand Traces. You can capture SQL traces at any time by manually setting up your parameters and starting the trace.
- Scheduled Traces. For inconvenient times, you can also specify your trace parameters and schedule them to run at some later time.
- Save Traces. Execute your traces and save them for later review.
- Trace Filters. Selectively filter SQL captures by database and by user, or capture every SQL statement sent by all users against all databases.
- Trace Output Analyzer. A graphical table lets you quickly sort and filter queries by duration or statement, and a graphical or text based EXPLAIN plan lays out your query paths and joins.

• Index Advisor Integration. Once you have found your slow queries and optimized them, you can also let the Index Advisor recommend the creation of underlying table indices to further improve performance.

The following describes the installation process.

Step 1: Install SQL Profiler

SQL Profiler is installed by the Advanced Server installer on Windows or from the edb-as<xx>-server-sqlprofiler RPM package on Linux where *xx* is the Advanced Server version number.

Step 2: Add the SQL Profiler library

Modify the postgresql.conf parameter file for the instance to include the SQL Profiler library in the shared_preload_libraries configuration parameter.

For Linux installations, the parameter value should include:

\$libdir/sql-profiler

On Windows, the parameter value should include:

\$libdir\sql-profiler.dll

Step 3: Create the functions used by SQL Profiler

The SQL Profiler installation program places a SQL script (named sql-profiler.sql) in:

On Linux:

/usr/edb/as12/share/contrib/

On Windows:

C:\Program Files\edb\as12\share\contrib\

Use the <code>psql</code> command line interface to run the <code>sql-profiler.sql</code> script in the database specified as the Maintenance Database on the server you wish to profile. If you are using Advanced Server, the default maintenance database is named <code>edb</code> . If you are using a PostgreSQL instance, the default maintenance database is named <code>postgres</code> .

The following command uses the psql command line to invoke the sql-profiler.sql script on a Linux system:

\$ /usr/edb/as12/bin/psql -U user_name database_name <
/usr/edb/as12/share/contrib/sql-profiler.sql</pre>

Step 4: Stop and restart the server for the changes to take effect.

After configuring SQL Profiler, it is ready to use with all databases that reside on the server. You can take advantage of SQL Profiler functionality with EDB Postgres Enterprise Manager; for more information about Postgres Enterprise Manager, visit the EnterpriseDB website at:

https://www.enterprisedb.com/edb-docs

Troubleshooting

If (after performing an upgrade to a newer version of SQL Profiler) you encounter an error that contains the following text:

An error has occurred:

ERROR: function return row and query-specified return row do not match. DETAIL: Returned row contains 11 attributes, but the query expects 10.

To correct this error, you must replace the existing query set with a new query set. First, uninstall SQL Profiler by invoking the uninstall-sql-profiler.sql script, and then reinstall SQL Profiler by invoking the sql-profiler.sql script.

10.6 pgsnmpd

pgsnmpd

pgsnmpd is an SNMP agent that can return hierarchical information about the current state of Advanced Server on a Linux system. pgsnmpd is distributed and installed using the edb-as<xx>-pgsnmpd RPM package where xx is the Advanced Server version number. The pgsnmpd agent can operate as a stand-alone SNMP agent, as a pass-through sub-agent, or as an AgentX sub-agent.

After installing Advanced Server, you will need to update the LD_LIBRARY_PATH variable. Use the command:

```
$ export LD_LIBRARY_PATH=/usr/edb/as12/lib:$LD_LIBRARY_PATH
```

This command does not persistently alter the value of LD_LIBRARY_PATH . Consult the documentation for your distribution of Linux for information about persistently setting the value of LD_LIBRARY_PATH .

The examples that follow demonstrate the simplest usage of pgsnmpd , implementing read only access. pgsnmpd is based on the net-snmp library; for more information about net-snmp, visit:

http://net-snmp.sourceforge.net/

Configuring pgsnmpd

The pgsnmpd configuration file is named snmpd.conf. For information about the directives that you can specify in the configuration file, please review the snmpd.conf man page (man snmpd.conf).

You can create the configuration file by hand, or you can use the snmpconf perl script to create the configuration file. The perl script is distributed with net-snmp package.

net-snmp is an open-source package available from:

```
http://www.net-snmp.org/
```

To use the snmpconf configuration file wizard, download and install net-snmp. When the installation completes, open a command line and enter:

```
snmpconf
```

When the configuration file wizard opens, it may prompt you to read in an existing configuration file. Enter none to generate a new configuration file (not based on a previously existing configuration file).

snmpconf is a menu-driven wizard. Select menu item 1: snmpd.conf to start the configuration wizard. As you select each top-level menu option displayed by snmpconf, the wizard walks through a series of questions, prompting you for information required to build the configuration file. When you have provided information in each of the category relevant to your system, enter Finished to generate a configuration file named snmpd.conf. Copy the file to:

/usr/edb/as12/share/

Setting the Listener Address

By default, pgsnmpd listens on port 161. If the listener port is already being used by another service, you may receive the following error:

```
Error opening specified endpoint "udp:161".
```

You can specify an alternate listener port by adding the following line to your snmpd.conf file:

```
agentaddress *$host_address*:2000
```

The example instructs pgsnmpd to listen on UDP port 2000, where \$host_address is the IP address of the server (e.g., 127.0.0.1).

Invoking pgsnmpd

Ensure that an instance of Advanced Server is up and running (pgsnmpd will connect to this server). Open a command line and assume superuser privileges, before invoking pgsnmpd with a command that takes the following form:

<POSTGRES_INSTALL_HOME>/bin/pgsnmpd -b -c *POSTGRES_INSTALL_HOME*/share/snmpd.conf -C "user=enterprisedb dbname=edb password=safe_password port=5444"

Where POSTGRES_INSTALL_HOME specifies the Advanced Server installation directory.

Include the -b option to specify that pgsnmpd should run in the background.

Include the -c option, specifying the path and name of the pgsnmpd configuration file.

Include connection information for your installation of Advanced Server (in the form of a libpq connection string) after the -C option.

Viewing pgsnmpd Help

Include the --help option when invoking the pgsnmpd utility to view other pgsnmpd command line options:

```
pgsnmpd --help
Version PGSQL-SNMP-Ver1.0
```

usage: pgsnmpd [-s] [-b] [-c FILE] [-x address] [-g] [-C "Connect String"]

-s : run as AgentX sub-agent of an existing snmpd process

-b : run in the background

-c : configuration file name

-g : use syslog

-C : libpq connection string

-x : address:port of a network interface

-V : display version strings

Requesting Information from pgsnmpd

You can use net-snmp commands to query the pgsnmpd service. For example: snmpgetnext -v 2c -c public localhost .1.3.6.1.4.1.5432.1.4.2.1.1.0

In the above example:

- -v 2c option instructs the snmpgetnext client to send the request in SNMP version 2c format.
- -c public specifies the community name.

localhost indicates the host machine running the pgsnmpd server.

.1.3.6.1.4.1.5432.1.4.2.1.1.0 is the identity of the requested object. To see a list of all databases, increment the last digit by one (e.g. .1.1, .1.2, .1.3 etc.).

The encodings required to query any given object are defined in the MIB (Management Information Base). An SNMP client can monitor a variety of servers; the server type determines the information exposed by a given server. Each SNMP server describes the exposed data in the form of a MIB (Management information base). By default, pgsnmpd searches for MIB's in the following locations:

/usr/share/snmp/mibs

\$HOME/.snmp/mibs

10.7.0 EDB Audit Logging

EDB Audit Logging

Advanced Server allows database and security administrators, auditors, and operators to track and analyze database activities using the *EDB Audit Logging* functionality. EDB Audit Logging generates audit log files, which contains all of the relevant information. The audit logs can be configured to record information such as:

- · When a role establishes a connection to an Advanced Server database
- · What database objects a role creates, modifies, or deletes when connected to Advanced Server
- · When any failed authentication attempts occur

The parameters specified in the configuration files, postgresql.conf or postgresql.auto.conf , control the information included in the audit logs.

10.7.1 Audit Logging Configuration Parameters

Audit Logging Configuration Parameters

Use the following configuration parameters to control database auditing. See Section 3.1.2 to determine if a change to the configuration parameter takes effect immediately, or if the configuration needs to be reloaded, or if the database server needs to be restarted.

edb_audit

Enables or disables database auditing. The values xml or csv will enable database auditing. These values represent the file format in which auditing information will be captured. none will disable database auditing and is also the default.

edb_audit_directory

Specifies the directory where the log files will be created. The path of the directory can be relative or absolute to the data folder. The default is the PGDATA/edb_audit directory.

edb_audit_filename

Specifies the file name of the audit file where the auditing information will be stored. The default file name will be audit-%Y%m%d_%H%M%S . The escape sequences, %Y , %m etc., will be replaced by the appropriate current values according to the system date and time.

edb_audit_rotation_day

Specifies the day of the week on which to rotate the audit files. Valid values are sun, mon, tue, wed, thu, fri, sat, every, and none. To disable rotation, set the value to none. To rotate the file every day, set the edb_audit_rotation_day value to every. To rotate the file on a specific day of the week, set the value to the desired day of the week. every is the default value.

edb_audit_rotation_size

Specifies a file size threshold in megabytes when file rotation will be forced to occur. The default value is 0 MB. If the parameter is commented out or set to 0, rotation of the file on a size basis will not occur.

edb_audit_rotation_seconds

Specifies the rotation time in seconds when a new log file should be created. To disable this feature, set this parameter to 0, which is the default.

edb audit connect

Enables auditing of database connection attempts by users. To disable auditing of all connection attempts, set edb_audit_connect to none. To audit all failed connection attempts, set the value to failed, which is the default. To audit all connection attempts, set the value to all.

edb_audit_disconnect

Enables auditing of database disconnections by connected users. To enable auditing of disconnections, set the value to all. To disable, set the value to none, which is the default.

edb_audit_statement

This configuration parameter is used to specify auditing of different categories of SQL statements. Various combinations of the following values may be specified: none , dml , insert , update , delete , truncate , select , error , rollback , ddl , create , drop , alter , grant , revoke , and all . The default is ddl and error . See Section 3.5.2 for information regarding the setting of this parameter.

```
edb_audit_tag
```

Use this configuration parameter to specify a string value that will be included in the audit log file for each entry as a tracking tag.

```
edb_log_every_bulk_value
```

Bulk processing logs the resulting statements into both the Advanced Server log file and the EDB Audit log file. However, logging each and every statement in bulk processing is costly. This can be controlled by the edb_log_every_bulk_value configuration parameter. When set to true, each and every statement in bulk processing is logged. When set to false, a log message is recorded once per bulk processing. In addition, the duration is emitted once per bulk processing. Default is

```
edb audit destination
```

Specifies whether the audit log information is to be recorded in the directory as given by the edb_audit_directory parameter or to the directory and file managed by the *syslog* process. Set to file to use the directory specified by edb_audit_directory, which is the default setting.

Set to syslog to use the syslog process and its location as configured in the /etc/syslog.conf file. The syslog setting is valid for Advanced Server running on a Linux host and is not supported on Windows systems. **Note:** In recent Linux versions, syslog has been replaced by *rsyslog* and the configuration file is in /etc/rsyslog.conf.

The following section describes selection of specific SQL statements for auditing using the edb_audit_statement parameter.

10.7.2 Selecting SQL Statements to Audit

Selecting SQL Statements to Audit

The edb_audit_statement permits inclusion of one or more, comma-separated values to control which SQL statements are to be audited. The following is the general format:

```
edb_audit_statement = '*value_1*[, *value_2*]...'
```

The comma-separated values may include or omit space characters following the comma. The values can be specified in any combination of lowercase or uppercase letters.

The basic parameter values are the following:

- all Results in the auditing and logging of every statement including any error messages on statements.
- none Disables all auditing and logging. A value of none overrides any other value included in the list.
- ddl Results in the auditing of all data definition language (DDL) statements (CREATE , ALTER , and DROP) as well as GRANT and REVOKE data control language (DCL) statements.
- dml Results in the auditing of all data manipulation language (DML) statements (INSERT , UPDATE , DELETE , and TRUNCATE).

- select Results in the auditing of SELECT statements.
- rollback Results in the auditing of ROLLBACK statements.
- error Results in the logging of all error messages that occur. Unless the error value is included, no error messages are logged regarding any errors that occur on SQL statements related to any of the other preceding parameter values except when all is used.

Section 3.5.2.1 describes additional parameter values for selecting particular DDL or DCL statements for auditing.

Section 3.5.2.2 describes additional parameter values for selecting particular DML statements for auditing.

If an unsupported value is included in the edb_audit_statement
parameter, then an error occurs
when applying the setting to the database server. See the database server log file for the error such as
in the following example where create materialized vw
results in the error. (The correct value is
create materialized view .)

```
2017-07-16 11:20:39 EDT LOG: invalid value for parameter "edb_audit_statement": "create materialized vw, create sequence, grant"
```

```
2017-07-16 11:20:39 EDT FATAL: configuration file "/var/lib/edb/as12/data/postgresql.conf" contains errors
```

The following sections describe the values for the SQL language types DDL, DCL, and DML.

Data Definition Language and Data Control Language Statements

This section describes values that can be included in the edb_audit_statement parameter to audit DDL and DCL statements.

The following general rules apply:

- If the edb_audit_statement parameter includes either ddl or all, then all DDL statements are audited. In addition, the DCL statements GRANT and REVOKE are audited as well.
- If the edb_audit_statement is set to none, then no DDL nor DCL statements are audited.
- Specific types of DDL and DCL statements can be chosen for auditing by including a combination of values within the edb_audit_statement parameter.

Use the following syntax to specify an edb_audit_statement parameter value for DDL statements:

```
{ create * alter * drop } [ *object_type* ]
```

object_type is any of the following:

ACCESS METHOD AGGREGATE CAST COLLATION CONVERSION DATABASE EVENT TRIGGER **EXTENSION** FOREIGN TABLE FUNCTION INDEX LANGUAGE LARGE OBJECT MATERIALIZED VIEW OPERATOR OPERATOR CLASS OPERATOR FAMILY POLICY PUBLICATION ROLE RULE SCHEMA SEQUENCE SERVER SUBSCRIPTION TABLE TABLESPACE TEXT SEARCH CONFIGURATION TEXT SEARCH DICTIONARY TEXT SEARCH PARSER TEXT SEARCH TEMPLATE TRANSFORM **TYPF** TRIGGER USER MAPPING VIEW

Descriptions of object types as used in SQL commands can be found in the PostgreSQL core documentation available at:

```
https://www.postgresql.org/docs/12/static/sql-commands.html
```

If object_type is omitted from the parameter value, then all of the specified command statements (either create, alter, or drop) are audited.

Use the following syntax to specify an edb_audit_statement parameter value for DCL statements: { grant * revoke }

The following are some DDL and DCL examples.

Example 1

The following is an example where edb_audit_connect and edb_audit_statement are set with the following non-default values:

```
edb_audit_connect = 'all'
edb_audit_statement = 'create, alter, error'
```

Thus, only SQL statements invoked by the CREATE and ALTER commands are audited. Error messages are also included in the audit log.

The database session that occurs is the following:

```
$ psql edb enterprisedb
Password for user enterprisedb:
psql.bin (12.0.0)
Type "help" for help.
edb=# SHOW edb_audit_connect;
edb_audit_connect
all
(1 row)
edb=# SHOW edb_audit_statement;
edb_audit_statement
create, alter, error
edb=# CREATE ROLE adminuser;
CREATE ROLE
edb=# ALTER ROLE adminuser WITH LOGIN, SUPERUSER, PASSWORD 'password';
ERROR: syntax error at or near ","
LINE 1: ALTER ROLE adminuser WITH LOGIN, SUPERUSER, PASSWORD 'passwo...
edb=# ALTER ROLE adminuser WITH LOGIN SUPERUSER PASSWORD 'password';
ALTER ROLE
edb=# CREATE DATABASE auditdb;
CREATE DATABASE
edb=# ALTER DATABASE auditdb OWNER TO adminuser;
ALTER DATABASE
edb=# \\c auditdb adminuser
Password for user adminuser:
You are now connected to database "auditdb" as user "adminuser".
auditdb=# CREATE SCHEMA edb;
CREATE SCHEMA
auditdb=# SET search_path TO edb;
auditdb=# CREATE TABLE department (
auditdb(# deptno NUMBER(2) NOT NULL CONSTRAINT dept_pk PRIMARY KEY,
auditdb(# dname VARCHAR2(14) CONSTRAINT dept_dname_uq UNIQUE,
auditdb(# loc VARCHAR2(13)
auditdb(# );
CREATE TABLE
auditdb=# DROP TABLE department;
DROP TABLE
auditdb=# CREATE TABLE dept (
auditdb(# deptno NUMBER(2) NOT NULL CONSTRAINT dept_pk PRIMARY KEY,
auditdb(# dname VARCHAR2(14) CONSTRAINT dept_dname_uq UNIQUE,
auditdb(# loc VARCHAR2(13)
auditdb(# );
CREATE TABLE
```

The resulting audit log file contains the following.

Each audit log entry has been split and displayed across multiple lines, and a blank line has been inserted between the audit log entries for more clarity in the appearance of the results.

```
2017-07-16 12:59:42.125 EDT, "enterprisedb", "edb", 3356, "[local]",
596b9b7e.d1c,1,"authentication",2017-07-16 12:59:42
EDT, 6/2, 0, AUDIT, 00000,
"connection authorized: user=enterprisedb database=edb",,,,,,,,"","",""
2017-07-16 12:59:42.125 EDT, "enterprisedb", "edb", 3356, "[local]",
596b9b7e.d1c,2,"idle",2017-07-16 12:59:42 EDT,6/6,0,AUDIT,00000,
"statement: CREATE ROLE adminuser;",,,,,,,"psql.bin","CREATE ROLE",""
2017-07-16 13:00:28.469 EDT, "enterprisedb", "edb", 3356, "[local]",
596b9b7e.d1c,3,"idle",2017-07-16 12:59:42 EDT,6/7,0,ERROR,42601,
"syntax error at or near "",""",
"ALTER ROLE adminuser WITH LOGIN, SUPERUSER, PASSWORD
'password';",32,,"psql.bin","","
2017-07-16 13:00:28.469 EDT, "enterprisedb", "edb", 3356, "[local]",
596b9b7e.d1c,4,"idle",2017-07-16 12:59:42 EDT,6/8,0,AUDIT,00000,
"statement: ALTER ROLE adminuser WITH LOGIN SUPERUSER PASSWORD
'password';",,,,,,
"psql.bin", "ALTER ROLE", ""
2017-07-16 13:00:28.469 EDT, "enterprisedb", "edb", 3356, "[local]",
596b9b7e.d1c,5,"idle",2017-07-16 12:59:42 EDT,6/9,0,AUDIT,00000,
"statement: CREATE DATABASE auditdb;",,,,,,,"psql.bin","CREATE
DATABASE",""
2017-07-16 13:00:28.469 EDT, "enterprisedb", "edb", 3356, "[local]"
596b9b7e.d1c,6,"idle",2017-07-16 12:59:42 EDT,6/10,0,AUDIT,00000,
"statement: ALTER DATABASE auditdb OWNER TO
adminuser; ",,,,,,, "psql.bin", "ALTER DATABASE", ""
2017-07-16 13:01:13.735 EDT, "adminuser", "auditdb", 3377, "[local]",
596b9bd9.d31,1,"authentication",2017-07-16 13:01:13
EDT, 4/15, 0, AUDIT, 00000,
"connection authorized: user=adminuser
database=auditdb",,,,,,,"","",""
2017-07-16 13:01:13.735 EDT, "adminuser", "auditdb", 3377, "[local]",
596b9bd9.d31,2,"idle",2017-07-16 13:01:13 EDT,4/17,0,AUDIT,00000,
"statement: CREATE SCHEMA edb;",,,,,,,"psql.bin","CREATE SCHEMA",""
2017-07-16 13:01:13.735 EDT, "adminuser", "auditdb", 3377, "[local]",
596b9bd9.d31,3,"idle",2017-07-16 13:01:13 EDT,4/19,0,AUDIT,00000,
"statement: CREATE TABLE department (
deptno NUMBER(2) NOT NULL CONSTRAINT dept_pk PRIMARY KEY.
dname VARCHAR2(14) CONSTRAINT dept_dname_uq UNIQUE,
loc VARCHAR2(13)
);",,,,,,"psql.bin","CREATE TABLE",""
2017-07-16 13:01:13.735 EDT, "adminuser", "auditdb", 3377, "[local]",
596b9bd9.d31,4,"idle",2017-07-16 13:01:13 EDT,4/21,0,AUDIT,00000,
"statement: CREATE TABLE dept (
deptno NUMBER(2) NOT NULL CONSTRAINT dept_pk PRIMARY KEY,
dname VARCHAR2(14) CONSTRAINT dept_dname_uq UNIQUE,
loc VARCHAR2(13)
);",,,,,,,"psql.bin","CREATE TABLE",""
    CREATE and ALTER statements for the adminuser role and auditdb database are au-
dited. The error for the ALTER ROLE adminuser statement is also logged since error is included in the
edb_audit_statement parameter.
```

Similarly, the CREATE statements for schema edb and tables department and dept are audited.

Note that the DROP TABLE department statement is not in the audit log since there is no edb_audit_statement setting that would result in the auditing of successfully processed DROP statements such as $\frac{ddl}{dl}$, $\frac{all}{dl}$, or $\frac{drop}{dl}$.

```
Example 2
The following is an example where edb_audit_connect and edb_audit_statement are set with the
following non-default values:
edb_audit_connect = 'all'
edb_audit_statement = create view,create materialized view,create
sequence, grant'
Thus, only SQL statements invoked by the CREATE VIEW . CREATE MATERIALIZED VIEW . CREATE SEQUENCE
and GRANT commands are audited. The database session that occurs is the following:
$ psql auditdb adminuser
Password for user adminuser:
psql.bin (12.0.0)
Type "help" for help.
auditdb=# SHOW edb_audit_connect;
edb_audit_connect
all
(1 row)
auditdb=# SHOW edb_audit_statement;
edb_audit_statement
create view, create materialized view, create sequence, grant
(1 row)
auditdb=# SET search_path TO edb;
SET
auditdb=# CREATE TABLE emp (
auditdb(# empno NUMBER(4) NOT NULL CONSTRAINT emp_pk PRIMARY KEY,
auditdb(# ename VARCHAR2(10),
auditdb(# job VARCHAR2(9),
auditdb(# mgr NUMBER(4),
auditdb(# hiredate DATE,
auditdb(# sal NUMBER(7,2) CONSTRAINT emp_sal_ck CHECK (sal > 0),
auditdb(\# comm NUMBER(7,2),
auditdb(# deptno NUMBER(2) CONSTRAINT emp_ref_dept_fk
auditdb(# REFERENCES dept(deptno)
auditdb(# );
CREATE TABLE
auditdb=# CREATE VIEW salesemp AS
auditdb-# SELECT empno, ename, hiredate, sal, comm FROM emp WHERE job =
'SALESMAN';
CREATE VIEW
auditdb=# CREATE MATERIALIZED VIEW managers AS
auditdb-# SELECT empno, ename, hiredate, sal, comm FROM emp WHERE job =
'MANAGER';
SELECT 0
auditdb=# CREATE SEQUENCE next_empno START WITH 8000 INCREMENT BY 1;
CREATE SEQUENCE
auditdb=# GRANT ALL ON dept TO PUBLIC;
auditdb=# GRANT ALL ON emp TO PUBLIC;
GRANT
```

The resulting audit log file contains the following.

Each audit log entry has been split and displayed across multiple lines, and a blank line has been inserted between the audit log entries for more clarity in the appearance of the results.

```
2017-07-16 13:20:09.836 EDT, "adminuser", "auditdb", 4143, "[local]",
596ba049.102f,1,"authentication",2017-07-16 13:20:09 EDT,4/10,0,AUDIT,00000,
"connection authorized: user=adminuser database=auditdb",,,,,,,,"","",""
2017-07-16 13:20:09.836 EDT, "adminuser", "auditdb", 4143, "[local]"
596ba049.102f,2,"idle",2017-07-16 13:20:09 EDT,4/16,0,AUDIT,00000,
"statement: CREATE VIEW salesemp AS
SELECT empno, ename, hiredate, sal, comm FROM emp WHERE job =
'SALESMAN';",,,,,,,,"psql.bin","CREATE VIEW",""
2017-07-16 13:20:09.836 EDT, "adminuser", "auditdb", 4143, "[local]"
596ba049.102f,3,"idle",2017-07-16 13:20:09 EDT,4/17,0,AUDIT,00000,
"statement: CREATE MATERIALIZED VIEW managers AS
SELECT empno, ename, hiredate, sal, comm FROM emp WHERE job =
'MANAGER';",,,,,,,,"psql.bin","CREATE MATERIALIZED VIEW",""
2017-07-16 13:20:09.836 EDT, "adminuser", "auditdb", 4143, "[local]"
596ba049.102f,4,"idle",2017-07-16 13:20:09 EDT,4/18,0,AUDIT,00000
"statement: CREATE SEQUENCE next_empno START WITH 8000 INCREMENT BY
1;",,,,,,,"psql.bin","CREATE SEQUENCE",""
2017-07-16 13:20:09.836 EDT, "adminuser", "auditdb", 4143, "[local]"
596ba049.102f,5,"idle",2017-07-16 13:20:09 EDT,4/19,0,AUDIT,00000,
"statement: GRANT ALL ON dept TO PUBLIC;",,,,,,,,"psql.bin","GRANT",""
2017-07-16 13:20:09.836 EDT, "adminuser", "auditdb", 4143, "[local]"
596ba049.102f,6,"idle",2017-07-16 13:20:09 EDT,4/20,0,AUDIT,00000,
"statement: GRANT ALL ON emp TO PUBLIC;",,,,,,,"psql.bin","GRANT",""
The CREATE VIEW and CREATE MATERIALIZED VIEW statements are audited. Note that the prior
```

The CREATE VIEW and CREATE MATERIALIZED VIEW statements are audited. Note that the prior CREATE TABLE emp statement is not audited since none of the values create, create table, ddl, nor all are included in the edb_audit_statement parameter.

The CREATE SEQUENCE and GRANT statements are audited since those values are included in the edb_audit_statement parameter.

Data Manipulation Language Statements

This section describes the values that can be included in the edb_audit_statement parameter to audit DML statements.

The following general rules apply:

- If the edb_audit_statement parameter includes either dml or all , then all DML statements are audited.
- If the edb_audit_statement is set to none, then no DML statements are audited.
- Specific types of DML statements can be chosen for auditing by including a combination of values within the edb_audit_statement parameter.

Use the following syntax to specify an edb_audit_statement parameter value for SQL INSERT , UPDATE , DELETE , or TRUNCATE statements:

{ insert I update I delete I truncate }

Example

The following is an example where edb_audit_connect and edb_audit_statement are set with the following non-default values:

```
edb_audit_statement = 'UPDATE, DELETE, error'
Thus, only SQL statements invoked by the UPDATE and DELETE commands are audited. All errors are
also included in the audit log (even errors not related to the UPDATE and DELETE commands).
The database session that occurs is the following:
$ psql auditdb adminuser
Password for user adminuser:
psql.bin (12.0.0)
Type "help" for help.
auditdb=# SHOW edb_audit_connect;
edb_audit_connect
all
(1 row)
auditdb=# SHOW edb_audit_statement;
edb_audit_statement
_____
UPDATE, DELETE, error
(1 row)
auditdb=# SET search_path TO edb;
auditdb=# INSERT INTO dept VALUES (10, 'ACCOUNTING', 'NEW YORK');
INSERT 0 1
auditdb=# INSERT INTO dept VALUES (20, 'RESEARCH', 'DALLAS');
INSERT 0 1
auditdb=# INSERT INTO dept VALUES (30, 'SALES', 'CHICAGO');
INSERT 0 1
auditdb=# INSERT INTO dept VALUES (40, 'OPERATIONS', 'BOSTON');
INSERT 0 1
auditdb=# INSERT INTO emp VALUES
(7369, 'SMITH', 'CLERK', 7902, '17-DEC-80', 800, NULL, 20);
INSERT 0 1
auditdb=# INSERT INTO emp VALUES
(7499, 'ALLEN', 'SALESMAN', 7698, '20-FEB-81', 1600, 300, 30);
INSERT 0 1
auditdb=# INSERT INTO emp VALUES
(7521, 'WARD', 'SALESMAN', 7698, '22-FEB-81', 1250, 500, 30);
INSERT 0 1
auditdb=# INSERT INTO emp VALUES
(7934, 'MILLER', 'CLERK', 7782, '23-JAN-82', 1300, NULL, 10);
INSERT 0 1
auditdb=# UPDATE dept SET loc = 'BEDFORD' WHERE deptno = 40;
UPDATE 1
auditdb=# SELECT * FROM dept;
deptno | dname | loc
-----
10
        | ACCOUNTING | NEW YORK
20
        IRESEARCH | DALLAS
30
                    | CHICAGO
        ISALES
        IOPERATIONS | BEDFORD
40
(4 rows)
auditdb=# DELETE FROM emp WHERE deptno = 10;
auditdb=# TRUNCATE employee;
ERROR: relation "employee" does not exist
```

edb_audit_connect = 'all'

```
auditdb=# TRUNCATE emp;
TRUNCATE TABLE
auditdb=# \q
```

The resulting audit log file contains the following.

Each audit log entry has been split and displayed across multiple lines, and a blank line has been inserted between the audit log entries for more clarity in the appearance of the results.

```
2017-07-16 13:43:26.638 EDT, "adminuser", "auditdb", 4574, "[local]",
596ba5be.11de,1,"authentication",2017-07-16 13:43:26
EDT, 4/11, 0, AUDIT, 00000,
"connection authorized: user=adminuser
database=auditdb",,,,,,,"","",""
2017-07-16 13:43:26.638 EDT, "adminuser", "auditdb", 4574, "[local]"
596ba5be.11de,2,"idle",2017-07-16 13:43:26 EDT,4/34,0,AUDIT,00000,
"statement: UPDATE dept SET loc = 'BEDFORD' WHERE deptno =
\textbf{40;",,,,,,,,psql.bin","UPDATE",""}
2017-07-16 13:43:26.638 EDT, "adminuser", "auditdb", 4574, "[local]",
596ba5be.11de,3,"idle",2017-07-16 13:43:26 EDT,4/36,0,AUDIT,00000,
"statement: DELETE FROM emp WHERE deptno =
10;",,,,,,"psql.bin","DELETE",""
2017-07-16 13:45:46.999 EDT, "adminuser", "auditdb", 4574, "[local]",
596ba5be.11de,4,"TRUNCATE TABLE",2017-07-16 13:43:26
EDT,4/37,0,ERROR,42P01,
"relation ""employee" does not exist",,,,,,"TRUNCATE
employee;",,,"psql.bin","",""
2017-07-16 13:46:26.362 EDT,,,4491,,596ba59c.118b,1,,2017-07-16 13:42:52
EDT,,0,LOG,00000,
"database system is shut down",,,,,,,"","",""
```

The UPDATE dept and DELETE FROM emp statements are audited. Note that all of the prior INSERT statements are not audited since none of the values insert, dml, nor all are included in the edb_audit_statement parameter.

The SELECT * FROM dept statement is not audited as well since neither select nor all is included in the edb_audit_statement parameter.

Since error is specified in the edb_audit_statement parameter, but not the truncate value, the error on the TRUNCATE employee statement is logged in the audit file, but not the successful TRUNCATE emp statement.

10.7.3 Enabling Audit Logging

Enabling Audit Logging

The following steps describe how to configure Advanced Server to log all connections, disconnections, DDL statements, DCL statements, DML statements, and any statements resulting in an error.

- 1. Enable auditing by the setting the edb_audit parameter to xml or csv.
- 2. Set the file rotation day when the new file will be created by setting the parameter edb_audit_rotation_day to the desired value
- 3. To audit all connections, set the parameter, edb_audit_connect, to all.
- 4. To audit all disconnections, set the parameter, edb_audit_disconnect, to all.
- 5. To audit DDL, DCL, DML and other statements, set the parameter, edb_audit_statement according to the instructions in Section 3.5.2.

The setting of the edb_audit_statement parameter in the configuration file affects the entire database cluster.

The type of statements that are audited as controlled by the edb_audit_statement parameter can be further refined according to the database in use as well as the database role running the session:

- The edb_audit_statement parameter can be set as an attribute of a specified database with the ALTER DATABASE <dbname> SET edb_audit_statement command. This setting overrides the edb_audit_statement parameter in the configuration file for statements executed when connected to database dbname.
- The edb_audit_statement parameter can be set as an attribute of a specified role with the ALTER ROLE <rolename> SET edb_audit_statement command. This setting overrides the edb_audit_statement parameter in the configuration file as well as any setting assigned to the database by the previously described ALTER DATABASE command when the specified role is running the current session.
- The edb_audit_statement parameter can be set as an attribute of a specified role when using a specified database with the ALTER ROLE <rolename> IN DATABASE <dbname> SET edb_audit_statement command. This setting overrides the edb_audit_statement parameter in the configuration file as well as any setting assigned to the database by the previously described ALTER DATABASE command as well as any setting assigned to the role with the ALTER ROLE command without the IN DATABASE clause as previously described.

The following are examples of this technique.

The database cluster is established with edb_audit_statement set to all as shown in its postgresql.conf file:

A database and role are established with the following settings for the edb_audit_statement parameter:

- Database auditdb with ddl , insert , update , and delete
- Role admin with select and truncate
- Role admin in database auditdb with create table, insert, and update

Creation and alteration of the database and role are shown by the following:

```
$ psql edb enterprisedb
Password for user enterprisedb:
psql.bin (12.0.0)
Type "help" for help.
edb=# SHOW edb_audit_statement;
edb_audit_statement
all
(1 row)
edb=# CREATE DATABASE auditdb;
CREATE DATABASE
edb=# ALTER DATABASE auditdb SET edb_audit_statement TO 'ddl, insert,
update, delete';
ALTER DATABASE
edb=# CREATE ROLE admin WITH LOGIN SUPERUSER PASSWORD 'password';
CREATE ROLE
edb=# ALTER ROLE admin SET edb_audit_statement TO 'select, truncate';
edb=# ALTER ROLE admin IN DATABASE auditdb SET edb_audit_statement TO
'create table, insert, update';
ALTER ROLE
```

The following demonstrates the changes made and the resulting audit log file for three cases.

Case 1: Changes made in database auditdb by role enterprisedb. Only ddl, insert, update, and delete statements are audited:

```
$ psql auditdb enterprisedb
Password for user enterprisedb:
psql.bin (12.0.0)
Type "help" for help.
auditdb=# SHOW edb_audit_statement;
edb_audit_statement
ddl, insert, update, delete
(1 row)
auditdb=# CREATE TABLE audit_tbl (f1 INTEGER PRIMARY KEY, f2 TEXT);
CREATE TABLE
auditdb=# INSERT INTO audit_tbl VALUES (1, 'Row 1');
INSERT 0 1
auditdb=# UPDATE audit_tbl SET f2 = 'Row A' WHERE f1 = 1;
UPDATE 1
auditdb=# SELECT * FROM audit_tbl; <== Should not be audited</pre>
f1 | f2
----+----
1 | Row A
(1 row)
auditdb=# TRUNCATE audit_tbl; <== Should not be audited</pre>
TRUNCATE TABLE
The following audit log file shows entries only for the CREATE TABLE, INSERT INTO audit_tbl, and
UPDATE audit_tbl statements. The SELECT * FROM audit_tbl and TRUNCATE audit_tbl state-
ments were not audited.
Each audit log entry has been split and displayed across multiple lines, and a blank line has been inserted
between the audit log entries for more clarity in the appearance of the results.
2017-07-13 15:26:17.426 EDT, "enterprisedb", "auditdb", 4024, "[local]",
5967c947.fb8,1,"idle",2017-07-13 15:25:59 EDT,7/4,0,AUDIT,00000,
"statement: CREATE TABLE audit_tbl (f1 INTEGER PRIMARY KEY, f2
TEXT);",,,,,,,,
"psql.bin","CREATE TABLE",""
2017-07-13 15:26:17.426 EDT, "enterprisedb", "auditdb", 4024, "[local]",
5967c947.fb8,2,"idle",2017-07-13 15:25:59 EDT,7/5,0,AUDIT,00000,
"statement: INSERT INTO audit_tbl VALUES (1, 'Row
1');",,,,,,,psql.bin","INSERT",""
2017-07-13 15:26:17.426 EDT, "enterprisedb", "auditdb", 4024, "[local]",
5967c947.fb8,3,"idle",2017-07-13 15:25:59 EDT,7/6,0,AUDIT,00000,
"statement: UPDATE audit_tbl SET f2 = 'Row A' WHERE f1 =
1;",,,,,,,"psql.bin","UPDATE",""
Case 2: Changes made in database edb by role admin. Only select and truncate statements are audited:
$ psql edb admin
Password for user admin:
psql.bin (12.0.0)
Type "help" for help.
edb=# SHOW edb_audit_statement;
edb_audit_statement
______
select, truncate
(1 row)
edb=# CREATE TABLE edb_tbl (f1 INTEGER PRIMARY KEY, f2 TEXT) <== Should
not be audited
CREATE TABLE
```

edb=# INSERT INTO edb_tbl VALUES (1, 'Row 1'); <== Should not be audited

```
INSERT 0 1
edb=# SELECT * FROM edb_tbl;
f1 | f2
----+----
1 | Row 1
(1 row)
edb=# TRUNCATE edb_tbl;
TRUNCATE TABLE
Continuation of the audit log file now appears as follows. The last two entries representing the sec-
ond case show only the SELECT * FROM edb_tbl
                                                and TRUNCATE edb_tbl
                                                                         statements.
CREATE TABLE edb_tbl and INSERT INTO edb_tbl statements were not audited.
2017-07-13 15:26:17.426 EDT, "enterprisedb", "auditdb", 4024, "[local]",
5967c947.fb8,1,"idle",2017-07-13 15:25:59 EDT,7/4,0,AUDIT,00000,
"statement: CREATE TABLE audit_tbl (f1 INTEGER PRIMARY KEY, f2
TEXT);",,,,,
"psql.bin", "CREATE TABLE", ""
2017-07-13 15:26:17.426 EDT, "enterprisedb", "auditdb", 4024, "[local]",
5967c947.fb8,2,"idle",2017-07-13 15:25:59 EDT,7/5,0,AUDIT,00000,
"statement: INSERT INTO audit_tbl VALUES (1, 'Row
1');",,,,,,,"psql.bin","INSERT",""
2017-07-13 15:26:17.426 EDT, "enterprisedb", "auditdb", 4024, "[local]",
5967c947.fb8,3,"idle",2017-07-13 15:25:59 EDT,7/6,0,AUDIT,00000,
"statement: UPDATE audit_tbl SET f2 = 'Row A' WHERE f1 =
1;",,,,,,,"psql.bin","UPDATE",""
2017-07-13 15:29:45.616 EDT, "admin", "edb", 4047, "[local]"
5967ca05.fcf,1,"idle",2017-07-13 15:29:09 EDT,4/33,0,AUDIT,00000,
"statement: SELECT * FROM edb_tbl;",,,,,,,"psql.bin","SELECT",""
2017-07-13 15:29:45.616 EDT, "admin", "edb", 4047, "[local]"
5967ca05.fcf,2,"idle",2017-07-13 15:29:09 EDT,4/34,0,AUDIT,00000,
"statement: TRUNCATE edb_tbl;",,,,,,,"psql.bin","TRUNCATE TABLE",""
Case 3: Changes made in database auditdb by role admin. Only create table, insert, and update statements
are audited:
$ psql auditdb admin
Password for user admin:
psql.bin (12.0.0)
Type "help" for help.
auditdb=# SHOW edb_audit_statement;
edb_audit_statement
create table, insert, update
auditdb=# CREATE TABLE audit_tbl_2 (f1 INTEGER PRIMARY KEY, f2 TEXT);
CREATE TABLE
auditdb=# INSERT INTO audit_tbl_2 VALUES (1, 'Row 1');
INSERT 0 1
auditdb=# SELECT * FROM audit_tbl_2; <== Should not be audited</pre>
f1 | f2
----+----
1 | Row 1
(1 row)
auditdb=# TRUNCATE audit_tbl_2; <== Should not be audited</pre>
TRUNCATE TABLE
Continuation of the audit log file now appears as follows. The next to last two entries representing the third
```

```
case show only CREATE TABLE audit_tbl_2 and INSERT INTO audit_tbl_2 statements. The
SELECT * FROM audit_tbl_2 and TRUNCATE audit_tbl_2 statements were not audited.
2017-07-13 15:26:17.426 EDT, "enterprisedb", "auditdb", 4024, "[local]",
5967c947.fb8,1,"idle",2017-07-13 15:25:59 EDT,7/4,0,AUDIT,00000,
"statement: CREATE TABLE audit_tbl (f1 INTEGER PRIMARY KEY, f2
TEXT);",,,,,,,
"psql.bin","CREATE TABLE",""
2017-07-13 15:26:17.426 EDT, "enterprisedb", "auditdb", 4024, "[local]",
5967c947.fb8,2,"idle",2017-07-13 15:25:59 EDT,7/5,0,AUDIT,00000,
"statement: INSERT INTO audit_tbl VALUES (1, 'Row
1');",,,,,,,"psql.bin","INSERT",""
2017-07-13 15:26:17.426 EDT, "enterprisedb", "auditdb", 4024, "[local]",
5967c947.fb8,3,"idle",2017-07-13 15:25:59 EDT,7/6,0,AUDIT,00000,
"statement: UPDATE audit_tbl SET f2 = 'Row A' WHERE f1 =
1;",,,,,,,"psql.bin","UPDATE",""
2017-07-13 15:29:45.616 EDT, "admin", "edb", 4047, "[local]",
5967ca05.fcf,1,"idle",2017-07-13 15:29:09 EDT,4/33,0,AUDIT,00000,
"statement: SELECT * FROM edb_tbl;",,,,,,,"psql.bin","SELECT",""
2017-07-13 15:29:45.616 EDT, "admin", "edb", 4047, "[local]"
5967ca05.fcf,2,"idle",2017-07-13 15:29:09 EDT,4/34,0,AUDIT,00000,
"statement: TRUNCATE edb_tbl;",,,,,,,"psql.bin","TRUNCATE TABLE",""
2017-07-13 15:35:45.309 EDT, "admin", "auditdb", 4085, "[local]".
5967cb81.ff5,1,"idle",2017-07-13 15:35:29 EDT,4/72,0,AUDIT,00000,
"statement: CREATE TABLE audit_tbl_2 (f1 INTEGER PRIMARY KEY, f2
TEXT);",,,,,,,,
"psql.bin","CREATE TABLE",""
2017-07-13 15:35:45.309 EDT, "admin", "auditdb", 4085, "[local]",
5967cb81.ff5,2,"idle",2017-07-13 15:35:29 EDT,4/73,0,AUDIT,00000,
"statement: INSERT INTO audit_tbl_2 VALUES (1, 'Row
1');",,,,,,,"psql.bin","INSERT",""
2017-07-13 15:38:42.028 EDT,,,3942,,5967c934.f66,1,,2017-07-13 15:25:40
EDT,,0,LOG,00000,"database system is shut down",,,,,,,"","",""
```

10.7.4 Audit Log File

Audit Log File

The audit log file can be generated in either CSV or XML format depending upon the setting of the edb_audit configuration parameter. The XML format contains less information than the CSV format.

The information in the audit log is based on the logging performed by PostgreSQL as described in the section "Using CSV-Format Log Output" within Section "Error Reporting and Logging" in the PostgreSQL core documentation, available at:

https://www.postgresql.org/docs/current/static/runtime-config-logging.html

The following table lists the fields in the order they appear in the CSV audit log format. The table contains the following information:

- Field. Name of the field as shown in the sample table definition in the PostgreSQL documentation as previously referenced.
- XML Element/Attribute. For the XML format, name of the XML element and its attribute (if used), referencing the value. Note: n/a indicates that there is no XML representation for this field.

- Data Type. Data type of the field as given by the PostgreSQL sample table definition.
- **Description.** Description of the field. For certain fields, no output is generated in the audit log as those fields are not supported by auditing. Those fields are indicated by "Not supported".

The fields with the Description of "Not supported" appear as consecutive commas (") in the CSV format.

Field	XML Element/Attribute	Data Type	Description
log_time	event/time	timestamp with time zone	Log date/time of the statement.
user_name	event/user	text	Database user who executed the statement.
database_name	event/database	text	Database in which the statement was execut
process_id	event/process_id	integer	Operating system process ID in which the sta
connection_from	event/remote_host	text	Host and port location from where the statem
session_id	event/session_id	text	Session ID in which the statement was execu
session_line_num	n/a	bigint	Order of the statement within the session.
process_status	n/a	text	Processing status.
session_start_time	n/a	timestamp with time zone	Date/time when the session was started.
virtual_transaction_id	n/a	text	Virtual transaction ID of the statement.
transaction_id	event/transaction_id	bigint	Regular transaction ID of the statement.
error_severity	message	text	Statement severity. Values are AUDIT for au
sql_state_code	n/a	text	SQL state code returned for the statement.
message	message	text	The SQL statement that was attempted for e
detail	n/a	text	Error message detail. (Not supported)
hint	n/a	text	Hint (Not supported)
internal_query	n/a	text	Internal query that led to the error, if any. (No
internal_query_pos	n/a	integer	Character count of the error position, therein
context	n/a	text	Error context. (Not supported)
query	n/a	text	User query that led to the error. (For errors o
query_pos	n/a	integer	Character count of the error position, therein
location	n/a	text	Location of the error in the PostgreSQL sour
application_name	n/a	text	Name of the application from which the state
command_tag	event/command_tag	text	SQL command of the statement.
audit_tag	event/audit_tag	text	Value specified by the audit_tag parameter in

The following examples are generated in the CSV and XML formats.

The non-default audit settings in the postgresql.conf file are as follows:

```
edb_audit = 'csv'
edb_audit_connect = 'all'
edb_audit_disconnect = 'all'
edb_audit_statement = 'ddl, dml, select, error'
edb_audit_tag = 'edbaudit'
```

The edb_audit parameter is changed to xml when generating the XML format.

The audited session is the following:

```
$ psql edb enterprisedb
Password for user enterprisedb:
psql.bin (12.0.0)
Type "help" for help.
edb=# CREATE SCHEMA edb;
CREATE SCHEMA
edb=# SET search_path TO edb;
SET
edb=# CREATE TABLE dept (
edb(# deptno NUMBER(2) NOT NULL CONSTRAINT dept_pk PRIMARY KEY,
edb(# dname VARCHAR2(14) CONSTRAINT dept_dname_uq UNIQUE,
edb(# loc VARCHAR2(13))
edb(# );
CREATE TABLE
```

CSV Audit Log File

The following is the CSV format of the audit log file.

Each audit log entry has been split and displayed across multiple lines, and a blank line has been inserted between the audit log entries for more clarity in the appearance of the results.

```
2017-07-17 13:28:44.235 EDT, "enterprisedb", "edb", 4068, "[local]",
596cf3cc.fe4,1,"authentication",2017-07-17 13:28:44
EDT,6/2,0,AUDIT,00000,
"connection authorized: user=enterprisedb
database=edb",,,,,,,,"","","edbaudit"
2017-07-17 13:28:44.235 EDT, "enterprisedb", "edb", 4068, "[local]",
596cf3cc.fe4,2,"idle",2017-07-17 13:28:44 EDT,6/4,0,AUDIT,00000,
"statement: CREATE SCHEMA edb;",,,,,,,"psql.bin","CREATE
SCHEMA", "edbaudit"
2017-07-17 13:28:44.235 EDT, "enterprisedb", "edb", 4068, "[local]",
596cf3cc.fe4,3,"idle",2017-07-17 13:28:44 EDT,6/6,0,AUDIT,00000,
"statement: CREATE TABLE dept (
deptno NUMBER(2) NOT NULL CONSTRAINT dept_pk PRIMARY KEY,
dname VARCHAR2(14) CONSTRAINT dept_dname_uq UNIQUE,
loc VARCHAR2(13)
);",,,,,,,"psql.bin","CREATE TABLE","edbaudit"
2017-07-17 13:28:44.235 EDT, "enterprisedb", "edb", 4068, "[local]",
596cf3cc.fe4,4,"idle",2017-07-17 13:28:44 EDT,6/7,0,AUDIT,00000,
"statement: INSERT INTO dept VALUES (10, 'ACCOUNTING', 'NEW
YORK');",,,,,,,,
"psql.bin","INSERT","edbaudit"
2017-07-17 13:28:44.235 EDT, "enterprisedb", "edb", 4068, "[local]",
596cf3cc.fe4,5,"idle",2017-07-17 13:28:44 EDT,6/8,0,AUDIT,00000,
"statement: UPDATE department SET loc = 'BOSTON' WHERE deptno =
10;",,,,,,,,
"psql.bin","UPDATE","edbaudit"
2017-07-17 13:29:59.833 EDT, "enterprisedb", "edb", 4068, "[local]"
596cf3cc.fe4,6,"UPDATE",2017-07-17 13:28:44 EDT,6/8,0,ERROR,42P01,
"relation ""department" does not exist",,,,,
"UPDATE department SET loc = 'BOSTON' WHERE deptno =
10; ", 8, , "psql.bin", "", "edbaudit"
2017-07-17 13:29:59.833 EDT, "enterprisedb", "edb", 4068, "[local]",
596cf3cc.fe4,7,"idle",2017-07-17 13:28:44 EDT,6/9,0,AUDIT,00000,
"statement: UPDATE dept SET loc = 'BOSTON' WHERE deptno = 10;",,,,,,,
"psql.bin","UPDATE","edbaudit"
```

```
2017-07-17 13:29:59.833 EDT,"enterprisedb","edb",4068,"[local]",
596cf3cc.fe4,8,"idle",2017-07-17 13:28:44 EDT,6/10,0,AUDIT,00000,
"statement: SELECT * FROM dept;",,,,,,"psql.bin","SELECT","edbaudit"

2017-07-17 13:29:59.833 EDT,"enterprisedb","edb",4068,"[local]",
596cf3cc.fe4,9,"idle",2017-07-17 13:28:44 EDT,,0,AUDIT,00000,
"disconnection: session time: 0:02:01.511 user=enterprisedb database=edb
host=[local]",,,,,,,"psql.bin","SELECT","edbaudit"

2017-07-17 13:30:53.617 EDT,,,3987,,596cf3b3.f93,1,,2017-07-17 13:28:19
EDT,,0,LOG,000000,
"database system is shut down",,,,,,,"","","edbaudit"
```

XML Audit Log File

The following is the XML format of the audit log file. The output has been formatted for more clarity in the appearance in the example.

```
<event user="enterprisedb" database="edb" remote_host="[local]"</pre>
    session_id="596cf5b7.12a8" process_id="4776" time="2017-07-17 13:36:55 EDT"
    transaction_id="0" type="connect" audit_tag="edbaudit">
  <message>AUDIT: connection authorized: user=enterprisedb database=edb</message>
</event>
<event user="enterprisedb" database="edb" remote_host="[local]"</pre>
    session_id="596cf5b7.12a8" process_id="4776" time="2017-07-17 13:37:02 EDT"
   transaction_id="0" type="create" command_tag="CREATE SCHEMA" audit_tag="edbaudit">
  <message>AUDIT: statement: CREATE SCHEMA edb;</message>
</event>
<event user="enterprisedb" database="edb" remote_host="[local]"</pre>
    session_id="596cf5b7.12a8" process_id="4776" time="2017-07-17 13:37:19 EDT"
   transaction_id="0" type="create" command_tag="CREATE TABLE" audit_tag="edbaudit">
  <message>AUDIT: statement: CREATE TABLE dept (
        deptno NUMBER(2) NOT NULL CONSTRAINT dept_pk PRIMARY KEY,
                 VARCHAR2(14) CONSTRAINT dept_dname_uq UNIQUE,
        loc
                 VARCHAR2(13));
  </message>
</event>
<event user="enterprisedb" database="edb" remote_host="[local]"</pre>
    session_id="596cf5b7.12a8" process_id="4776" time="2017-07-17 13:37:29 EDT"
    transaction_id="0" type="insert" command_tag="INSERT" audit_tag="edbaudit">
  <message>AUDIT: statement: INSERT INTO dept VALUES
  (10,' ACCOUNTING' ,' NEW YORK');
  </message>
</event>
<event user="enterprisedb" database="edb" remote_host="[local]"</pre>
    session_id="596cf5b7.12a8" process_id="4776" time="2017-07-17 13:37:40 EDT"
    transaction_id="0" type="update" command_tag="UPDATE" audit_tag="edbaudit">
  <message>AUDIT: statement: UPDATE department SET
  loc = 'BOSTON' WHERE deptno = 10;
  </message>
</event>
<event user="enterprisedb" database="edb" remote_host="[local]"</pre>
    session_id="596cf5b7.12a8" process_id="4776" time="2017-07-17 13:37:40 EDT"
    transaction_id="0" type="error" audit_tag="edbaudit">
  <message>ERROR: relation &quot;department&quot; does not exist at
  character 8
  </message>
</event>
<event user="enterprisedb" database="edb" remote_host="[local]"</pre>
    session_id="596cf5b7.12a8" process_id="4776" time="2017-07-17 13:37:51 EDT"
    transaction_id="0" type="update" command_tag="UPDATE" audit_tag="edbaudit">
```

```
<message>AUDIT: statement: UPDATE dept SET loc = &apos;BOSTON&apos;
 WHERE deptno = 10;
 </message>
</event>
    <event user="enterprisedb" database="edb" remote_host="[local]"</pre>
    session_id="596cf5b7.12a8" process_id="4776" time="2017-07-17 13:37:59 EDT"
    transaction_id="0" type="select" command_tag="SELECT"
    audit_tag="edbaudit">
 <message>AUDIT: statement: SELECT * FROM dept;</message>
</event>
    <event user="enterprisedb" database="edb" remote_host="[local]"</pre>
    session_id="596cf5b7.12a8" process_id="4776" time="2017-07-17 13:38:01 EDT"
    transaction_id="0" type="disconnect" command_tag="SELECT"
    audit_tag="edbaudit">
 <message>AUDIT: disconnection: session time: 0:01:05.814
 user=enterprisedb database=edb host=[local]
</message>
</event>
    <event process_id="4696" time="2017-07-17 13:38:08 EDT"</pre>
    transaction_id="0" type="shutdown" audit_tag="edbaudit">
 <message>LOG: database system is shut down</message>
</event>
```

10.7.5 Using Error Codes to Filter Audit Logs

Using Error Codes to Filter Audit Logs

Advanced Server includes an extension that you can use to exclude log file entries that include a user-specified error code from the Advanced Server log files. To filter audit log entries, you must first enable the extension by modifying the postgresql.conf file, adding the following value to the values specified in the shared_preload_libraries parameter:

```
$libdir/edb_filter_log
```

Then, use the edb_filter_log.errcodes parameter to specify any error codes you wish to omit from the log files:

```
edb_filter_log.errcode = '<error_code>'
```

Where *error_code* specifies one or more error codes that you wish to omit from the log file. Provide multiple error codes in a comma-delimited list.

For example, if edb_filter_log is enabled, and edb_filter_log.errcode is set to '23505,23502,22012', any log entries that return one of the following SQLSTATE errors:

```
23505 (for violating a unique constraint)
```

23502 (for violating a not-null constraint)

22012 (for dividing by zero)

will be omitted from the log file.

For a complete list of the error codes supported by Advanced Server audit log filtering, please see the core documentation at:

https://www.postgresql.org/docs/current/static/errcodes-appendix.html

10.7.6 Using Command Tags to Filter Audit Logs

Using Command Tags to Filter Audit Logs

Each entry in the log file except for those displaying an error message contains a *command tag*, which is the SQL command executed for that particular log entry. The command tag makes it possible to use subsequent tools to scan the log file to find entries related to a particular SQL command.

The following is an example in XML form. The example has been formatted for easier review. The command tag is displayed as the command_tag attribute of the event element with values CREATE ROLE, and DROP ROLE in the example.

```
<event user="enterprisedb" database="edb" remote_host="[local]"</pre>
    session_id="595e8537.10f1" process_id="4337" time="2017-07-06 14:45:18 EDT"
    transaction_id="0" type="create"
    command_tag="CREATE ROLE">
  <message>AUDIT: statement: CREATE ROLE newuser WITH LOGIN;</message>
</event>
    <event user="enterprisedb" database="edb" remote_host="[local]"</pre>
    session_id="595e8537.10f1" process_id="4337" time="2017-07-06 14:45:31 EDT"
    transaction_id="0" type="error">
  <message>ERROR: unrecognized role option &quot;super&quot; at character 25
  STATEMENT: ALTER ROLE newuser WITH SUPER USER; </message>
</event>
    <event user="enterprisedb" database="edb" remote_host="[local]"</pre>
    session_id="595e8537.10f1" process_id="4337" time="2017-07-06 14:45:38 EDT"
    transaction_id="0" type="alter" command_tag="ALTER ROLE">
  <message>AUDIT: statement: ALTER ROLE newuser WITH SUPERUSER;</message>
</event>
    <event user="enterprisedb" database="edb" remote_host="[local]"</pre>
    session_id="595e8537.10f1" process_id="4337" time="2017-07-06 14:45:46 EDT"
    transaction_id="0" type="drop" command_tag="DROP ROLE">
  <message>AUDIT: statement: DROP ROLE newuser;</message>
</event>
```

The following is the same example in CSV form. The command tag is the next to last column of each entry. (The last column appears empty as "", which would be the value provided by the edb_audit_tag parameter.)

Each audit log entry has been split and displayed across multiple lines, and a blank line has been inserted between the audit log entries for more clarity in the appearance of the results.

```
2017-07-06 14:47:22.294 EDT, "enterprisedb", "edb", 4720, "[local]"
595e85b2.1270,1,"idle",2017-07-06 14:47:14 EDT,6/4,0,AUDIT,00000,
"statement: CREATE ROLE newuser WITH LOGIN;",,,,,,,"psql.bin","CREATE
ROLE",""
2017-07-06 14:47:29.694 EDT, "enterprisedb", "edb", 4720, "[local]",
595e85b2.1270,2,"idle",2017-07-06 14:47:14 EDT,6/5,0,ERROR,42601,
"unrecognized role option ""super"",,,,,,"ALTER ROLE newuser WITH SUPER
USER;",25,,
"psql.bin","",""
2017-07-06 14:47:29.694 EDT, "enterprisedb", "edb", 4720, "[local]"
595e85b2.1270,3,"idle",2017-07-06 14:47:14 EDT,6/6,0,AUDIT,00000,
"statement: ALTER ROLE newuser WITH
SUPERUSER;",,,,,,,"psql.bin","ALTER ROLE",""
2017-07-06 14:47:29.694 EDT, "enterprisedb", "edb", 4720, "[local]"
595e85b2.1270,4,"idle",2017-07-06 14:47:14 EDT,6/7,0,AUDIT,00000,
"statement: DROP ROLE newuser;",,,,,,,,"psql.bin","DROP ROLE",""
```

10.7.7 Redacting Passwords from Audit Logs

Redacting Passwords from Audit Logs

You can use the <code>edb_filter_log.redact_password_commands</code> extension to instruct the server to redact stored passwords from the log file. Note that the module only recognizes the following syntax:

```
{CREATE|ALTER} {USER|ROLE|GROUP} <identifier> { [WITH] [ENCRYPTED] PASSWORD '<nonempty_string_li
```

When such a statement is logged by log_statement, the server will redact the old and new passwords to 'x'. For example, the command:

```
ALTER USER carol PASSWORD '1safepwd' REPLACE 'old_pwd';
```

Will be added to log files as:

```
statement: ALTER USER carol PASSWORD 'x' REPLACE 'x';
```

When a statement that includes a redacted password is logged, the server redacts the statement text. When the statement is logged as context for some other message, the server omits the statement from the context.

To enable password redaction, you must first enable the extension by modifying the postgresql.conf file, adding the following value to the values specified in the shared_preload_libraries parameter:

```
$libdir/edb_filter_log
```

Then, set edb_filter_log.redact_password_commands to true :

```
edb_filter_log.redact_password_commands = true
```

After modifying the postgresql.conf file, you must restart the server for the changes to take effect.

10.8 Unicode Collation Algorithm

Unicode Collation Algorithm

The *Unicode Collation Algorithm* (UCA) is a specification (*Unicode Technical Report #10*) that defines a customizable method of collating and comparing Unicode data. *Collation* means how data is sorted as with a SELECT ... ORDER BY clause. *Comparison* is relevant for searches that use ranges with less than, greater than, or equal to operators.

Customizability is an important factor for various reasons such as the following.

- Unicode supports a vast number of languages. Letters that may be common to several languages may be expected to collate in different orders depending upon the language.
- Characters that appear with letters in certain languages such as accents or umlauts have an impact on the expected collation depending upon the language.
- In some languages, combinations of several consecutive characters should be treated as a single character with regards to its collation sequence.
- There may be certain preferences as to the collation of letters according to case. For example, should the lowercase form of a letter collate before the uppercase form of the same letter or vice versa.
- There may be preferences as to whether punctuation marks such as underscore characters, hyphens, or space characters should be considered in the collating sequence or should they simply be ignored as if they did not exist in the string.

Given all of these variations with the vast number of languages supported by Unicode, there is a necessity for a method to select the specific criteria for determining a collating sequence. This is what the Unicode Collation Algorithm defines.

Note

In addition, another advantage for using ICU collations (the implementation of the Unicode Collation Algorithm) is for performance. Sorting tasks, including B-tree index creation, can complete in less than half the time it takes with a non-ICU collation. The exact performance gain depends on your operating system version, the language of your text data, and other factors.

The following sections provide a brief, simplified explanation of the Unified Collation Algorithm concepts. As the algorithm and its usage are quite complex with numerous variations, refer to the official documents cited in these sections for complete details.

Basic Unicode Collation Algorithm Concepts

The official information for the Unicode Collation Algorithm is specified in *Unicode Technical Report #10*, which can be found on The Unicode Consortium website at:

http://www.unicode.org/reports/tr10/

The ICU – International Components for Unicode also provides much useful information. An explanation of the collation concepts can be found on their website located at:

http://userguide.icu-project.org/collation/concepts

The basic concept behind the Unicode Collation Algorithm is the use of multilevel comparison. This means that a number of levels are defined, which are listed as level 1 through level 5 in the following bullet points. Each level defines a type of comparison. Strings are first compared using the primary level, also called level 1.

If the order can be determined based on the primary level, then the algorithm is done. If the order cannot be determined based on the primary level, then the secondary level, level 2, is applied. If the order can be determined based on the secondary level, then the algorithm is done, otherwise the tertiary level is applied, and so on. There is typically, a final tie-breaking level to determine the order if it cannot be resolved by the prior levels.

- Level 1 Primary Level for Base Characters. The order of basic characters such as letters and digits determines the difference such as A < B.
- Level 2 Secondary Level for Accents. If there are no primary level differences, then the presence or absence of accents and other such characters determine the order such as $a < \dot{a}$.
- Level 3 Tertiary Level for Case. If there are no primary level or secondary level differences, then a difference in case determines the order such as a < A.
- Level 4 Quaternary Level for Punctuation. If there are no primary, secondary, or tertiary level differences, then the presence or absence of white space characters, control characters, and punctuation determine the order such as -A < A.
- Level 5 Identical Level for Tie-Breaking. If there are no primary, secondary, tertiary, or quaternary level differences, then some other difference such as the code point values determines the order.

International Components for Unicode

The Unicode Collation Algorithm is implemented by open source software provided by the *International Components for Unicode* (ICU). The software is a set of C/C++ and Java libraries.

When Advanced Server is used to create a collation that invokes the ICU components to produce the collation, the result is referred to as an *ICU collation*.

Locale Collations

When creating a collation for a locale, a predefined ICU short form name for the given locale is typically provided.

An *ICU short form* is a method of specifying *collation attributes*, which are the properties of a collation. Section *Collation Attributes* provides additional information on collation attributes.

There are predefined ICU short forms for locales. The ICU short form for a locale incorporates the collation attribute settings typically used for the given locale. This simplifies the collation creation process by eliminating the need to specify the entire list of collation attributes for that locale.

The system catalog pg_catalog.pg_icu_collate_names contains a list of the names of the ICU short forms for locales. The ICU short form name is listed in column icu_short_form.

edb=# SELECT icu_short_form, valid_locale FROM pg_icu_collate_names
ORDER BY valid_locale;

LAF af LAR ar LAS as LAZ az	icu_short_form	1	valid_locale
LBE be	LAR LAS LAZ	İ	ar as az

```
I BG
                 I bg
LBN
                 l bn
LBS
                 l bs
                 | bs_Cyrl
LBS_ZCYRL
LR00T
                 l ca
LR00T
                   chr
LCS
                   CS
LCY
                 l cy
LDA
                 I da
LR00T
                   de
LR00T
                 l dz
LEE
                 l ee
LEL
                 l el
LR00T
                   en
LR00T
                 l en US
LEN_RUS_VPOSIX
                l en_US_POSIX
LE0
                 l eo
LES
                 l es
LET
                 I et
LFA
                 I fa
LFA RAF
                 I fa AF
```

If needed, the default characteristics of an ICU short form for a given locale can be overridden by specifying the collation attributes to override that property. This is discussed in the next section.

Collation Attributes

When creating an ICU collation, the desired characteristics of the collation must be specified. As discussed in Section *Locale Collations*, this can typically be done with an ICU short form for the desired locale. However, if more specific information is required, the specification of the collation properties can be done by using *collation attributes*.

Collation attributes define the rules of how characters are to be compared for determining the collation sequence of text strings. As Unicode covers a vast set of languages in numerous variations according to country, territory and culture, these collation attributes are quite complex.

For the complete, precise meaning and usage of collation attributes, see Section "Collator Naming Scheme" on the ICU – International Components for Unicode website at:

http://userguide.icu-project.org/collation/concepts

The following is a brief summary of the collation attributes and how they are specified using the ICU short form method

Each collation attribute is represented by an uppercase letter, which are listed in the following bullet points. The possible valid values for each attribute are given by codes shown within the parentheses. Some codes have general meanings for all attributes. **X** means to set the attribute off. **O** means to set the attribute to its default value.

- A Alternate (N, S, D). Handles treatment of *variable* characters such as white spaces, punctuation marks, and symbols. When set to non-ignorable (N), differences in variable characters are treated with the same importance as differences in letters. When set to shifted (S), then differences in variable characters are of minor importance (that is, the variable character is ignored when comparing base characters).
- C Case First (X, L, U, D). Controls whether a lowercase letter sorts before the same uppercase letter (L), or the uppercase letter sorts before the same lowercase letter (U). Off (X) is typically specified when lowercase first (L) is desired.
- E Case Level (X, O, D). Set in combination with the Strength attribute, the Case Level attribute is used when accents are to be ignored, but not case.
- F French Collation (X, O, D). When set to on, secondary differences (presence of accents) are sorted from the back of the string as done in the French Canadian locale.

- H Hiragana Quaternary (X, O, D). Introduces an additional level to distinguish between the Hiragana and Katakana characters for compatibility with the JIS X 4061 collation of Japanese character strings.
- N Normalization Checking (X, O, D). Controls whether or not text is thoroughly normalized for comparison. Normalization deals with the issue of canonical equivalence of text whereby different code point sequences represent the same character, which then present issues when sorting or comparing such characters. Languages such as Arabic, ancient Greek, Hebrew, Hindi, Thai, or Vietnamese should be used with Normalization Checking set to on.
- S Strength (1, 2, 3, 4, I, D). Maximum collation level used for comparison. Influences whether accents or case are taken into account when collating or comparing strings. Each number represents a level. A setting of I represents identical strength (that is, level 5).
- T Variable Top (hexadecimal digits). Applicable only when the Alternate attribute is not set to non-ignorable (N). The hexadecimal digits specify the highest character sequence that is to be considered ignorable. For example, if white space is to be ignorable, but visible variable characters are not to be ignorable, then Variable Top set to 0020 would be specified along with the Alternate attribute set to S and the Strength attribute set to 3. (The space character is hexadecimal 0020. Other non-visible variable characters such as backspace, tab, line feed, carriage return, etc. have values less than 0020. All visible punctuation marks have values greater than 0020.)

A set of collation attributes and their values is represented by a text string consisting of the collation attribute letter concatenated with the desired attribute value. Each attribute/value pair is joined to the next pair with an underscore character as shown by the following example.

```
AN_CX_EX_FX_HX_NO_S3
```

Collation attributes can be specified along with a locale's ICU short form name to override those default attribute settings of the locale.

The following is an example where the ICU short form named LR00T is modified with a number of other collation attribute/value pairs.

```
AN_CX_EX_LROOT_NO_S3
```

In the preceding example, the Alternate attribute (A) is set to non-ignorable (N). The Case First attribute (C) is set to off (X). The Case Level attribute (E) is set to off (X). The Normalization attribute (N) is set to on (O). The Strength attribute (S) is set to the tertiary level (S) is the ICU short form to which these other attributes are applying modifications.

Using a Collation

A newly defined ICU collation can be used anywhere the COLLATION "collation_name" clause can be used in a SQL command such as in the column specifications of the CREATE TABLE command or appended to an expression in the ORDER BY clause of a SELECT command.

The following are some examples of the creation and usage of ICU collations based on the English language in the United States (en_US.UTF8).

In these examples, ICU collations are created with the following characteristics.

Collation icu_collate_lowercase forces the lowercase form of a letter to sort before its uppercase counterpart (CL).

Collation icu_collate_uppercase forces the uppercase form of a letter to sort before its lowercase counterpart (CU).

Collation icu_collate_ignore_punct causes variable characters (white space and punctuation marks) to be ignored during sorting (AS).

Collation icu_collate_ignore_white_sp causes white space and other non-visible variable characters to be ignored during sorting, but visible variable characters (punctuation marks) are not ignored (AS , T0020).

```
CREATE COLLATION icu_collate_lowercase (
LOCALE = 'en_US.UTF8',
```

```
);
CREATE COLLATION icu_collate_uppercase (
LOCALE = 'en_US.UTF8'
ICU_SHORT_FORM = 'AN_CU_EX_NX_LROOT'
);
CREATE COLLATION icu_collate_ignore_punct (
LOCALE = 'en_US.UTF8',
ICU_SHORT_FORM = 'AS_CX_EX_NX_LROOT_L3'
);
CREATE COLLATION icu_collate_ignore_white_sp (
LOCALE = 'en_US.UTF8'
ICU_SHORT_FORM = 'AS_CX_EX_NX_LROOT_L3_T0020'
);
Note
When creating collations, ICU may generate notice and warning messages when attributes are given to modify
the LR00T collation.
The following psql command lists the collations.
edb=# \d0
                               List of collations
    Schema
              Name
                                              | Collate | Ctype
                                                                       l ICU
enterprisedb | icu_collate_ignore_punct | en_US.UTF8 | en_US.UTF8 | AS_CX_EX_NX_LROOT_L3
enterprisedb | icu_collate_ignore_white_sp | en_US.UTF8 | en_US.UTF8 | AS_CX_EX_NX_LROOT_L3_T002
enterprisedb | icu_collate_lowercase | en_US.UTF8 | en_US.UTF8 | AN_CL_EX_NX_LROOT
enterprisedb | icu_collate_uppercase
                                          | en_US.UTF8 | en_US.UTF8 | AN_CU_EX_NX_LROOT
(4 rows)
The following table is created and populated.
CREATE TABLE collate_tbl (
id INTEGER,
c2 VARCHAR(2)
INSERT INTO collate_tbl VALUES (1, 'A');
INSERT INTO collate_tbl VALUES (2, 'B');
INSERT INTO collate_tbl VALUES (3, 'C');
INSERT INTO collate_tbl VALUES (4, 'a');
INSERT INTO collate_tbl VALUES (5, 'b');
INSERT INTO collate_tbl VALUES (6, 'c');
INSERT INTO collate_tbl VALUES (7, '1');
INSERT INTO collate_tbl VALUES (8, '2');
INSERT INTO collate_tbl VALUES (9, '.B');
INSERT INTO collate_tbl VALUES (10, '-B');
INSERT INTO collate_tbl VALUES (11, ' B');
The following query sorts on column c2 using the default collation. Note that variable characters (white space
and punctuation marks) with id column values of 9, 10, and 11 are ignored and sort with the letter B.
edb=# SELECT * FROM collate_tbl ORDER BY c2;
id | c2
----+---
7 I 1
  12
```

ICU_SHORT_FORM = 'AN_CL_EX_NX_LROOT'

```
4
    Ιa
1
    ΙΑ
5
   Ιb
2
   I B
11 | B
10 I -B
9
   I.B
6
   l c
   1 C
3
(11 rows)
```

The following query sorts on column c2 using collation icu_collate_lowercase, which forces the lowercase form of a letter to sort before the uppercase form of the same base letter. Also note that the AN attribute forces variable characters to be included in the sort order at the same level when comparing base characters so rows with id values of 9, 10, and 11 appear at the beginning of the sort list before all letters and numbers.

```
edb=# SELECT * FROM collate_tbl ORDER BY c2 COLLATE
"icu_collate_lowercase";
id | c2
----+---
11 | B
   I -B
10
9
   I.B
    1 1
7
8
   1 2
    Ιa
   ΙΑ
1
5
   Ιb
2
   ΙB
6
   Ιc
3
    1 C
(11 rows)
```

The following query sorts on column c2 using collation icu_collate_uppercase, which forces the uppercase form of a letter to sort before the lowercase form of the same base letter.

```
edb=# SELECT * FROM collate_tbl ORDER BY c2 COLLATE
"icu_collate_uppercase";
id | c2
----+----
11 | B
10 I -B
9
   I.B
   1 1
7
8
   1 2
   ΙΑ
1
   l a
4
2
   l B
5
   Ιb
3
    I C
    l c
(11 rows)
```

The following query sorts on column $\ c2$ using collation $icu_collate_ignore_punct$, which causes variable characters to be ignored so rows with id values of $\ 9$, $\ 10$, and $\ 11$ sort with the letter $\ B$ as that is the character immediately following the ignored variable character.

```
edb=# SELECT * FROM collate_tbl ORDER BY c2 COLLATE
"icu_collate_ignore_punct";
id | c2
----+---
```

```
7
    I 1
8
    1 2
    l a
4
1
    ΙΔ
5
    l b
11 | B
2
    I B
9
    I.B
10 I -B
6
    Ιc
    1 C
3
(11 rows)
```

The following query sorts on column c2 using collation icu_collate_ignore_white_sp . The AS and T0020 attributes of the collation cause variable characters with code points less than or equal to hexadecimal 0020 to be ignored while variable characters with code points greater than hexadecimal 0020 are included in the sort.

The row with id value of 11, which starts with a space character (hexadecimal 0020) sorts with the letter B. The rows with id values of 9 and 10, which start with visible punctuation marks greater than hexadecimal 0020, appear at the beginning of the sort list as these particular variable characters are included in the sort order at the same level when comparing base characters.

```
edb=# SELECT * FROM collate_tbl ORDER BY c2 COLLATE
"icu_collate_ignore_white_sp";
id | c2
---+---
10 I -B
    l.B
9
    1 1
7
8
    1 2
4
    Ιa
1
    ΙΔ
5
    l b
11
   l B
    I B
2
6
    Ιc
3
    I C
(11 rows)
```

10.9 EDB Resource Manager

EDB Resource Manager

EDB Resource Manager is an Advanced Server feature that provides the capability to control the usage of operating system resources used by Advanced Server processes.

This capability allows you to protect the system from processes that may uncontrollably overuse and monopolize certain system resources.

The following are some key points about using EDB Resource Manager.

- The basic component of EDB Resource Manager is a resource group. A *resource group* is a named, global group, available to all databases in an Advanced Server instance, on which various resource usage limits can be defined. Advanced Server processes that are assigned as members of a given resource group are then controlled by EDB Resource Manager so that the aggregate resource usage of all processes in the group is kept near the limits defined on the group.
- Data definition language commands are used to create, alter, and drop resource groups. These commands can only be used by a database user with superuser privileges.
- The desired, aggregate consumption level of all processes belonging to a resource group is defined by resource type parameters. There are different resource type parameters for the different types of system

resources currently supported by EDB Resource Manager.

- Multiple resource groups can be created, each with different settings for its resource type parameters, thus defining different consumption levels for each resource group.
- EDB Resource Manager throttles processes in a resource group to keep resource consumption near the limits defined by the resource type parameters. If there are multiple resource type parameters with defined settings in a resource group, the actual resource consumption may be significantly lower for certain resource types than their defined resource type parameter settings. This is because EDB Resource Manager throttles processes attempting to keep all resources with defined resource type settings within their defined limits.
- The definition of available resource groups and their resource type settings are stored in a shared global system catalog. Thus, resource groups can be utilized by all databases in a given Advanced Server instance.
- The edb_max_resource_groups configuration parameter sets the maximum number of resource groups that can be active simultaneously with running processes. The default setting is 16 resource groups. Changes to this parameter take effect on database server restart.
- Use the SET edb_resource_group TO group_name command to assign the current process to a specified resource group. Use the RESET edb_resource_group command or SET edb_resource_group TO DEFAULT to remove the current process from a resource group.
- A default resource group can be assigned to a role using the ALTER ROLE ... SET command, or to a database by the ALTER DATABASE ... SET command. The entire database server instance can be assigned a default resource group by setting the parameter in the postgresql.conf file.
- In order to include resource groups in a backup file of the database server instance, use the pg_dumpall backup utility with default settings (That is, do not specify any of the --globals-only , --roles-only , or --tablespaces-only options.)

Creating and Managing Resource Groups

The data definition language commands described in this section provide for the creation and management of resource groups.

CREATE RESOURCE GROUP

Use the CREATE RESOURCE GROUP command to create a new resource group.

```
CREATE RESOURCE GROUP <group_name>;
```

Description

The CREATE RESOURCE GROUP command creates a resource group with the specified name. Resource limits can then be defined on the group with the ALTER RESOURCE GROUP command. The resource group is accessible from all databases in the Advanced Server instance.

To use the CREATE RESOURCE GROUP command you must have superuser privileges.

Parameters

group_name

The name of the resource group.

Example

The following example results in the creation of three resource groups named resgrp_a , resgrp_b , and resgrp_c .

```
edb=# CREATE RESOURCE GROUP resgrp_a;
CREATE RESOURCE GROUP
edb=# CREATE RESOURCE GROUP resgrp_b;
CREATE RESOURCE GROUP
edb=# CREATE RESOURCE GROUP resgrp_c;
CREATE RESOURCE GROUP
```

The following query shows the entries for the resource groups in the edb_resource_group catalog.

ALTER RESOURCE GROUP

Use the ALTER RESOURCE GROUP command to change the attributes of an existing resource group. The command syntax comes in three forms.

The first form renames the resource group:

```
ALTER RESOURCE GROUP *group_name* RENAME TO <new_name>;
```

The second form assigns a resource type to the resource group:

```
> ALTER RESOURCE GROUP <group_name> SET <resource_type> { TO | = } { <value> | DEFAULT };
```

The third form resets the assignment of a resource type to its default within the group:

Description

The ALTER RESOURCE GROUP command changes certain attributes of an existing resource group.

The first form with the RENAME TO clause assigns a new name to an existing resource group.

The second form with the SET <resource_type> TO clause either assigns the specified literal value to a resource type, or resets the resource type when DEFAULT is specified. Resetting or setting a resource type to DEFAULT means that the resource group has no defined limit on that resource type.

The third form with the [RESET](#resource_type) clause resets the resource type for the group as described previously.

To use the ALTER RESOURCE GROUP command, you must have superuser privileges.

Parameters

group_name

The name of the resource group to be altered.

new_name

The new name to be assigned to the resource group.

resource_type

The resource type parameter specifying the type of resource to which a usage value is to be set.

value | DEFAULT

When *value* is specified, the literal value to be assigned to *resource_type*. When DEFAULT is specified, the assignment of *resource_type* is reset for the resource group.

Example

```
The following are examples of the ALTER RESOURCE GROUP command.
```

```
edb=# ALTER RESOURCE GROUP resgrp_a RENAME TO newgrp;
ALTER RESOURCE GROUP
edb=# ALTER RESOURCE GROUP resgrp_b SET cpu_rate_limit = .5;
ALTER RESOURCE GROUP
edb=# ALTER RESOURCE GROUP resgrp_b SET dirty_rate_limit = 6144;
```

```
ALTER RESOURCE GROUP
edb=# ALTER RESOURCE GROUP resgrp_c RESET cpu_rate_limit;
ALTER RESOURCE GROUP
```

The following query shows the results of the ALTER RESOURCE GROUP commands to the entries in the edb_resource_group catalog.

DROP RESOURCE GROUP

Use the DROP RESOURCE GROUP command to remove a resource group.

```
DROP RESOURCE GROUP [ IF EXISTS ] *group_name*;
```

Description

The DROP RESOURCE GROUP command removes a resource group with the specified name.

To use the DROP RESOURCE GROUP command you must have superuser privileges.

Parameters

group_name

The name of the resource group to be removed.

IF EXISTS

Do not throw an error if the resource group does not exist. A notice is issued in this case.

Example

The following example removes resource group newgrp.

```
edb=# DROP RESOURCE GROUP newgrp
DROP RESOURCE GROUP
```

Assigning a Process to a Resource Group

Use the SET edb_resource_group TO <group_name> command to assign the current process to a specified resource group as shown by the following.

```
edb=# SET edb_resource_group T0 resgrp_b;
SET
edb=# SHOW edb_resource_group;
edb_resource_group
-----
resgrp_b
(1 row)
```

The resource type settings of the group immediately take effect on the current process. If the command is used to change the resource group assigned to the current process, the resource type settings of the newly assigned group immediately take effect.

Processes can be included by default in a resource group by assigning a default resource group to roles, databases, or an entire database server instance.

A default resource group can be assigned to a role using the ALTER ROLE ... SET command. For more information about the ALTER ROLE command, please refer to the PostgreSQL core documentation available at:

https://www.postgresql.org/docs/current/static/sql-alterrole.html

A default resource group can be assigned to a database by the ALTER DATABASE ... SET command. For more information about the ALTER DATABASE command, please refer to the PostgreSQL core documentation available at:

https://www.postgresql.org/docs/current/static/sql-alterdatabase.html

The entire database server instance can be assigned a default resource group by setting the edb_resource_group configuration parameter in the postgresql.conf file as shown by the following.

```
title: "- EDB Resource Manager -"
10.9 - EDB Resource Manager -
---
<div id="edb_resource_manager" class="registered_link"></div>
#edb_max_resource_groups = 16 # 0-65536 (change requires restart)
edb_resource_group = 'resgrp_b'
```

A change to edb_resource_group in the postgresql.conf file requires a configuration file reload before it takes effect on the database server instance.

Removing a Process from a Resource Group

Set edb_resource_group to DEFAULT or use RESET edb_resource_group to remove the current process from a resource group as shown by the following.

For removing a default resource group from a role, use the ALTER ROLE ... RESET form of the ALTER ROLE command.

For removing a default resource group from a database, use the ALTER DATABASE ... RESET form of the ALTER DATABASE command.

For removing a default resource group from the database server instance, set the edb_resource_group configuration parameter to an empty string in the postgresql.conf file and reload the configuration file.

Monitoring Processes in Resource Groups

After resource groups have been created, the number of processes actively using these resource groups can be obtained from the view edb_all_resource_groups .

The columns in edb_all_resource_groups are the following:

- group_name. Name of the resource group.
- active_processes. Number of active processes in the resource group.
- cpu rate limit. The value of the CPU rate limit resource type assigned to the resource group.
- per_process_cpu_rate_limit. The CPU rate limit applicable to an individual, active process in the resource group.
- dirty rate limit. The value of the dirty rate limit resource type assigned to the resource group.
- per_process_dirty_rate_limit. The dirty rate limit applicable to an individual, active process in the resource group.

Note

Columns per_process_cpu_rate_limit and per_process_dirty_rate_limit do not show the *actual* resource consumption used by the processes, but indicate how EDB Resource Manager sets the resource limit for an individual process based upon the number of active processes in the resource group.

The following shows <code>edb_all_resource_groups</code> when resource group <code>resgrp_a</code> contains no active processes, resource group <code>resgrp_b</code> contains two active processes, and resource group <code>resgrp_c</code> contains one active process.

```
edb=# SELECT * FROM edb_all_resource_groups ORDER BY group_name;
-[ RECORD 1 ]-----
group_name
                        l resgrp_a
active_processes
                        10
cpu_rate_limit
                        1 0.5
per_process_cpu_rate_limit
                        1 12288
dirty_rate_limit
per_process_dirty_rate_limit |
-[ RECORD 2 ]-----
                      l resgrp_b
aroup_name
active_processes | 2 cpu rate limit | 0
                       1 0.4
cpu_rate_limit
per_process_cpu_rate_limit | 0.195694289022895
dirty_rate_limit
                        | 6144
per_process_dirty_rate_limit | 3785.92924684337
-[ RECORD 3 ]-----
                 l resgrp_c
group_name
active_processes
                        1 1
                        1 0.3
per_process_cpu_rate_limit | 0.292342129631091
dirty_rate_limit
                        1 3072
per_process_dirty_rate_limit | 3072
```

The CPU rate limit and dirty rate limit settings that are assigned to these resource groups are as follows.

In the edb_all_resource_groups view, note that the per_process_cpu_rate_limit and per_process_dirty_rate_limit values are roughly the corresponding CPU rate limit and dirty rate limit divided by the number of active processes.

CPU Usage Throttling

CPU usage of a resource group is controlled by setting the cpu_rate_limit resource type parameter.

Set the cpu_rate_limit parameter to the fraction of CPU time over wall-clock time to which the combined, simultaneous CPU usage of all processes in the group should not exceed. Thus, the value assigned to cpu_rate_limit should typically be less than or equal to 1.

The valid range of the cpu_rate_limit parameter is 0 to 1.67772e+07. A setting of 0 means no CPU rate limit has been set for the resource group.

When multiplied by 100, the cpu_rate_limit can also be interpreted as the CPU usage percentage for a resource group.

EDB Resource Manager utilizes *CPU throttling* to keep the aggregate CPU usage of all processes in the group within the limit specified by the cpu_rate_limit parameter. A process in the group may be interrupted and put

into sleep mode for a short interval of time to maintain the defined limit. When and how such interruptions occur is defined by a proprietary algorithm used by EDB Resource Manager.

Setting the CPU Rate Limit for a Resource Group

The ALTER RESOURCE GROUP command with the SET cpu_rate_limit clause is used to set the CPU rate limit for a resource group.

In the following example the CPU usage limit is set to 50% for $\ resgrp_a$, 40% for $\ resgrp_b$ and 30% for $\ resgrp_c$. This means that the combined CPU usage of all processes assigned to $\ resgrp_a$ is maintained at approximately 50%. Similarly, for all processes in $\ resgrp_b$, the combined CPU usage is kept to approximately 40%, etc.

Changing the cpu_rate_limit of a resource group not only affects new processes that are assigned to the group, but any currently running processes that are members of the group are immediately affected by the change. That is, if the cpu_rate_limit is changed from .5 to .3, currently running processes in the group would be throttled downward so that the aggregate group CPU usage would be near 30% instead of 50%.

To illustrate the effect of setting the CPU rate limit for resource groups, the following examples use a CPU-intensive calculation of 20000 factorial (multiplication of 20000 * 19999 * 19998, etc.) performed by the query SELECT 20000!; run in the psql command line utility.

The resource groups with the CPU rate limit settings shown in the previous query are used in these examples.

Example - Single Process in a Single Group

The following shows that the current process is set to use resource group resgrp_b. The factorial calculation is then started.

```
edb=# SET edb_resource_group TO resgrp_b;
SET
edb=# SHOW edb_resource_group;
edb_resource_group
------
resgrp_b
(1 row)
edb=# SELECT 20000!;
```

In a second session, the Linux top command is used to display the CPU usage as shown under the %CPU column. The following is a snapshot at an arbitrary point in time as the top command output periodically changes.

```
$ top
top - 16:37:03 up 4:15, 7 users, load average: 0.49, 0.20, 0.38
Tasks: 202 total, 1 running, 201 sleeping, 0 stopped, 0 zombie
Cpu(s): 42.7%us, 2.3%sy, 0.0%ni, 55.0%id, 0.0%wa, 0.0%hi, 0.0%si, 0.0
Mem: 1025624k total, 791160k used, 234464k free, 23400k buffers
```

```
Swap: 103420k total, 13404k used, 90016k free, 373504k cached
```

```
PID
               PR NI
                      VIRT
                            RES
                                 SHR S
                                         %CPU
                                               %MEM
                                                     TIME+
      USER
28915 enterpri 20
                  0
                       195m
                            5900 4212 S
                                         39.9
                                                0.6
                                                     3:36.98 edb-postgres
                                                7.8
1033 root
              20
                  0
                       171m
                            77m
                                 2960 S
                                         1.0
                                                     3:43.96 Xorg
3040
     user
               20
                  0
                       278m
                            22m
                                 14m S
                                         1.0
                                                2.2 3:41.72 knotify4
```

The psql session performing the factorial calculation is shown by the row where edb-postgres appears under the COMMAND column. The CPU usage of the session shown under the %CPU column shows 39.9, which is close to the 40% CPU limit set for resource group resgrp_b.

By contrast, if the psql session is removed from the resource group and the factorial calculation is performed again, the CPU usage is much higher.

Under the %CPU column for edb-postgres, the CPU usage is now 93.6, which is significantly higher than the 39.9 when the process was part of the resource group.

```
$ top top - 16:43:03 up 4:21, 7 users, load average: 0.66, 0.33, 0.37 Tasks: 202 total, 5 running, 197 sleeping, 0 stopped, 0 zombie Cpu(s): 96.7%us, 3.3%sy, 0.0%ni, 0.0%id, 0.0%wa, 0.0%hi, 0.0%si, 0.0 Mem: 1025624k total, 791228k used, 234396k free, 23560k buffers Swap: 103420k total, 13404k used, 90016k free, 373508k cached PID USER PR NI VIRT RES SHR S %CPU %MEM TIME+ COMMAND 28915 enterpri 20 0 195m 5900 4212 R 93.6 0.6 5:01.56 edb-postgres 1033 root 20 0 171m 77m 2960 S 1.0 7.8 3:48.15 Xorg 2907 user 20 0 98.7m 11m 9100 S 0.3 1.2 0:46.51 vmware-user-lo .
```

Example - Multiple Processes in a Single Group

As stated previously, the CPU rate limit applies to the aggregate of all processes in the resource group. This concept is illustrated in the following example.

The factorial calculation is performed simultaneously in two separate psql sessions, each of which has been added to resource group resgrp_b that has cpu_rate_limit set to .4 (CPU usage of 40%).

Session 1:

```
edb=# SET edb_resource_group T0 resgrp_b;
SET
edb=# SHOW edb_resource_group;
edb_resource_group
------
resgrp_b
(1 row)
edb=# SELECT 20000!;
```

```
Session 2:
```

```
edb=# SET edb_resource_group TO resgrp_b;
SET
edb=# SHOW edb_resource_group;
edb_resource_group
resgrp_b
(1 row)
edb=# SELECT 20000!;
A third session monitors the CPU usage.
$ top
top - 16:53:03 up 4:31, 7 users, load average: 0.31, 0.19, 0.27
Tasks: 202 total, 1 running, 201 sleeping, 0 stopped, 0 zombie
Cpu(s): 41.2%us, 3.0%sy, 0.0%ni, 55.8%id, 0.0%wa, 0.0%hi, 0.0%si, 0.0
Mem: 1025624k total, 792020k used, 233604k free, 23844k buffers
Swap: 103420k total, 13404k used, 90016k free, 373508k cached
PID USER PR NI VIRT RES SHR S %CPU %MEM TIME+ COMMAND
29857 enterpri 20 0 195m 4708 3312 S 19.9 0.5 0:57.35 edb-postgres
28915 enterpri 20 0 195m 5900 4212 S 19.6 0.6 5:35.49 edb-postgres
3040 user 20 0 278m 22m 14m S 1.0 2.2 3:54.99 knotify4
1033 root 20 0 171m 78m 2960 S 0.3 7.8 3:55.71 Xorg
```

There are now two processes named edb-postgres with %CPU values of 19.9 and 19.6, whose sum is close to the 40% CPU usage set for resource group resgrp_b.

The following command sequence displays the sum of all edb-postgres processes sampled over half second time intervals. This shows how the total CPU usage of the processes in the resource group changes over time as EDB Resource Manager throttles the processes to keep the total resource group CPU usage near 40%.

```
$ while [[ 1 -eq 1 ]]; do top -d0.5 -b -n2 | grep edb-postgres | awk
'{ SUM += $9} END { print SUM / 2 }'; done
37.2
39.1
38.9
38.3
44.7
39.2
42.5
39.1
39.2
39.2
41
42.85
46.1
.
```

Example – Multiple Processes in Multiple Groups

In this example, two additional psql sessions are used along with the previous two sessions. The third and fourth sessions perform the same factorial calculation within resource group resgrp_c with a cpu_rate_limit of .3 (30% CPU usage).

```
Session 3:
```

```
edb=# SET edb_resource_group TO resgrp_c;
edb=# SHOW edb_resource_group;
edb_resource_group
resgrp_c
(1 row)
edb=# SELECT 20000!;
Session 4:
edb=# SET edb_resource_group TO resgrp_c;
SET
edb=# SHOW edb_resource_group;
edb_resource_group
resgrp_c
(1 row)
edb=# SELECT 20000!;
The top command displays the following output.
top - 17:45:09 up 5:23, 8 users, load average: 0.47, 0.17, 0.26
Tasks: 203 total, 4 running, 199 sleeping, 0 stopped, 0 zombie
Cpu(s): 70.2%us, 0.0%sy, 0.0%ni, 29.8%id, 0.0%wa, 0.0%hi, 0.0%si, 0.0
Mem: 1025624k total, 806140k used, 219484k free, 25296k buffers
Swap: 103420k total, 13404k used, 90016k free, 374092k cached
               PR NI VIRT RES SHR S %CPU %MEM TIME+
PID
     USER
                                                        COMMAND
29857 enterpri 20 0 195m 4820 3324 S 19.9 0.5 4:25.02 edb-postgres
28915 enterpri 20 0 195m 5900 4212 R 19.6 0.6 9:07.50 edb-postgres
29023 enterpri 20 0 195m 4744 3248 R 16.3 0.5 4:01.73 edb-postgres
11019 enterpri 20 0 195m 4120 2764 R 15.3 0.4 0:04.92 edb-postgres
               20 0 98.7m 12m 9112 S 1.3 1.2
2907 user
                                                0:56.54 vmware-user-lo
3040
     user
               20 0 278m 22m 14m S 1.3 2.2 4:38.73 knotify4
```

The two resource groups in use have CPU usage limits of 40% and 30%. The sum of the %CPU column for the first two edb-postgres processes is 39.5 (approximately 40%, which is the limit for resgrp_b) and the sum of the %CPU column for the third and fourth edb-postgres processes is 31.6 (approximately 30%, which is the limit for resgrp_c).

The sum of the CPU usage limits of the two resource groups to which these processes belong is 70%. The following output shows that the sum of the four processes borders around 70%.

```
$ while [[ 1 -eq 1 ]]; do top -d0.5 -b -n2 | grep edb-postgres | awk
'{ SUM += $9} END { print SUM / 2 }'; done
61.8
76.4
72.6
69.55
64.55
79.95
68.55
71.25
74.85
62
74.85
76.9
72.4
65.9
```

```
74.9
68.25
```

By contrast, if three sessions are processing where two sessions remain in resgrp_b, but the third session does not belong to any resource group, the top command shows the following output.

```
$ top
top - 17:24:55 up 5:03, 7 users, load average: 1.00, 0.41, 0.38
Tasks: 199 total, 3 running, 196 sleeping, 0 stopped, 0 zombie
Cpu(s): 99.7%us, 0.3%sy, 0.0%ni, 0.0%id, 0.0%wa, 0.0%hi, 0.0%si, 0.0
Mem: 1025624k total, 797692k used, 227932k free, 24724k buffers
Swap: 103420k total, 13404k used, 90016k free, 374068k cached
PID
     USER
              PR NI VIRT
                            RES SHR S
                                         %CPU %MEM TIME+
                                                            COMMAND
                   0
29023 enterpri 20
                      195m
                            4744 3248 R
                                         58.6 0.5 2:53.75 edb-postgres
28915 enterpri 20
                   0 195m
                            5900 4212 S
                                         18.9 0.6 7:58.45 edb-postgres
29857 enterpri 20
                   0 195m
                            4820 3324 S
                                         18.9
                                               0.5
                                                    3:14.85 edb-postgres
 1033 root
              20
                   0 174m
                             81m 2960 S
                                          1.7
                                               8.2 4:26.50 Xorg
 3040 user
                      278m
                             22m 14m S
                                          1.0 2.2
                                                    4:21.20 knotify4
              20
                   0
```

The second and third edb-postgres processes belonging to the resource group where the CPU usage is limited to 40%, have a total CPU usage of 37.8. However, the first edb-postgres process has a 58.6% CPU usage as it is not within a resource group, and basically utilizes the remaining, available CPU resources on the system.

Likewise, the following output shows the sum of all three sessions is around 95% since one of the sessions has no set limit on its CPU usage.

```
$ while [[ 1 -eq 1 ]]; do top -d0.5 -b -n2 | grep edb-postgres | awk
'{ SUM += $9} END { print SUM / 2 }'; done
96
90.35
92.55
96.4
94.1
90.7
95.7
95.45
93.65
87.95
96.75
94.25
95.45
97.35
92.9
96.05
96.25
94.95
```

Dirty Buffer Throttling

Writing to shared buffers is controlled by setting the dirty_rate_limit resource type parameter.

Set the dirty_rate_limit parameter to the number of kilobytes per second for the combined rate at which all the processes in the group should write to or "dirty" the shared buffers. An example setting would be 3072 kilobytes per seconds.

The valid range of the dirty_rate_limit parameter is 0 to 1.67772e+07. A setting of 0 means no dirty rate limit has been set for the resource group.

EDB Resource Manager utilizes *dirty buffer throttling* to keep the aggregate, shared buffer writing rate of all processes in the group near the limit specified by the <code>dirty_rate_limit</code> parameter. A process in the group may be interrupted and put into sleep mode for a short interval of time to maintain the defined limit. When and how such interruptions occur is defined by a proprietary algorithm used by EDB Resource Manager.

Setting the Dirty Rate Limit for a Resource Group

The ALTER RESOURCE GROUP command with the SET dirty_rate_limit clause is used to set the dirty rate limit for a resource group.

In the following example the dirty rate limit is set to 12288 kilobytes per second for <code>resgrp_a</code>, 6144 kilobytes per second for <code>resgrp_b</code> and 3072 kilobytes per second for <code>resgrp_c</code>. This means that the combined writing rate to the shared buffer of all processes assigned to <code>resgrp_a</code> is maintained at approximately 12288 kilobytes per second. Similarly, for all processes in <code>resgrp_b</code>, the combined writing rate to the shared buffer is kept to approximately 6144 kilobytes per second, etc.

```
edb=# ALTER RESOURCE GROUP resgrp_a SET dirty_rate_limit TO 12288;
ALTER RESOURCE GROUP
edb=# ALTER RESOURCE GROUP resgrp_b SET dirty_rate_limit TO 6144;
ALTER RESOURCE GROUP
edb=# ALTER RESOURCE GROUP resgrp_c SET dirty_rate_limit TO 3072;
ALTER RESOURCE GROUP
The following query shows the settings of dirty_rate_limit in the catalog.
edb=# SELECT_rarpname rarpdirtyrate_limit FROM edb_resource_aroun;
```

Changing the <code>dirty_rate_limit</code> of a resource group not only affects new processes that are assigned to the group, but any currently running processes that are members of the group are immediately affected by the change. That is, if the <code>dirty_rate_limit</code> is changed from 12288 to 3072, currently running processes in the group would be throttled downward so that the aggregate group dirty rate would be near 3072 kilobytes per second instead of 12288 kilobytes per second.

To illustrate the effect of setting the dirty rate limit for resource groups, the following examples use the following table for intensive I/O operations.

```
CREATE TABLE t1 (c1 INTEGER, c2 CHARACTER(500)) WITH (FILLFACTOR = 10);
```

The FILLFACTOR = 10 clause results in INSERT commands packing rows up to only 10% per page. This results in a larger sampling of dirty shared blocks for the purpose of these examples.

The pg_stat_statements module is used to display the number of shared buffer blocks that are dirtied by a SQL command and the amount of time the command took to execute. This provides the information to calculate the actual kilobytes per second writing rate for the SQL command, and thus compare it to the dirty rate limit set for a resource group.

In order to use the pg_stat_statements module, perform the following steps.

Step 1: In the postgresql.conf file, add \$libdir/pg_stat_statements to the shared_preload_libraries configuration parameter as shown by the following.

```
shared_preload_libraries =
'$libdir/dbms_pipe,$libdir/edb_gen,$libdir/pg_stat_statements'
```

Step 2: Restart the database server.

Step 3: Use the CREATE EXTENSION command to complete the creation of the pg_stat_statements module.

```
edb=# CREATE EXTENSION pg_stat_statements SCHEMA public;
CREATE EXTENSION
```

The pg_stat_statements_reset() function is used to clear out the pg_stat_statements view for clarity of each example.

The resource groups with the dirty rate limit settings shown in the previous query are used in these examples.

Example - Single Process in a Single Group

The following sequence of commands shows the creation of table t1. The current process is set to use resource group resgrp_b . The pg_stat_statements view is cleared out by running the pg_stat_statements_reset() function.

Finally, the INSERT command generates a series of integers from 1 to 10,000 to populate the table, and dirty approximately 10,000 blocks.

```
edb=# CREATE TABLE t1 (c1 INTEGER, c2 CHARACTER(500)) WITH (FILLFACTOR =
10);
CREATE TABLE
edb=# SET edb_resource_group TO resgrp_b;
edb=# SHOW edb_resource_group;
edb_resource_group
resgrp_b
(1 row)
edb=# SELECT pg_stat_statements_reset();
pg_stat_statements_reset
(1 row)
edb=# INSERT INTO t1 VALUES (generate_series (1,10000), 'aaa');
INSERT 0 10000
The following shows the results from the INSERT command.
edb=# SELECT query, rows, total_time, shared_blks_dirtied FROM
pg_stat_statements;
-[ RECORD 1 ]-----+
query
                   | INSERT INTO t1 VALUES (generate_series (?,?), ?);
                   1 10000
rows
                   | 13496.184
total_time
shared_blks_dirtied | 10003
```

The actual dirty rate is calculated as follows.

- The number of blocks dirtied per millisecond (ms) is 10003 blocks / 13496.184 ms, which yields 0.74117247 blocks per millisecond.
- Multiply the result by 1000 to give the number of shared blocks dirtied per second (1 second = 1000 ms), which yields 741.17247 blocks per second.
- Multiply the result by 8.192 to give the number of kilobytes dirtied per second (1 block = 8.192 kilobytes), which yields approximately *6072 kilobytes per second*.

Note that the actual dirty rate of 6072 kilobytes per second is close to the dirty rate limit for the resource group, which is 6144 kilobytes per second.

By contrast, if the steps are repeated again without the process belonging to any resource group, the dirty buffer rate is much higher.

```
edb=# CREATE TABLE t1 (c1 INTEGER, c2 CHARACTER(500)) WITH (FILLFACTOR =
10);
CREATE TABLE
edb=# SHOW edb_resource_group;
```

```
edb_resource_group
_____
(1 row)
edb=# SELECT pg_stat_statements_reset();
pg_stat_statements_reset
(1 row)
edb=# INSERT INTO t1 VALUES (generate_series (1,10000), 'aga');
INSERT 0 10000
The following shows the results from the INSERT command without the usage of a resource group.
edb=# SELECT query, rows, total_time, shared_blks_dirtied FROM
pg_stat_statements;
-[ RECORD 1 ]-----+
                  | INSERT INTO t1 VALUES (generate_series (?,?), ?);
query
rows
                  1 10000
total_time
                  | 2432.165
shared_blks_dirtied | 10003
```

First, note the total time was only 2432.165 milliseconds as compared to 13496.184 milliseconds when a resource group with a dirty rate limit set to 6144 kilobytes per second was used.

The actual dirty rate without the use of a resource group is calculated as follows.

- The number of blocks dirtied per millisecond (ms) is 10003 blocks / 2432.165 ms, which yields 4.112797 blocks per millisecond.
- Multiply the result by 1000 to give the number of shared blocks dirtied per second (1 second = 1000 ms), which yields 4112.797 blocks per second.
- Multiply the result by 8.192 to give the number of kilobytes dirtied per second (1 block = 8.192 kilobytes), which yields approximately *33692 kilobytes per second*.

Note that the actual dirty rate of 33692 kilobytes per second is significantly higher than when the resource group with a dirty rate limit of 6144 kilobytes per second was used.

Example – Multiple Processes in a Single Group

As stated previously, the dirty rate limit applies to the aggregate of all processes in the resource group. This concept is illustrated in the following example.

For this example the inserts are performed simultaneously on two different tables in two separate psql sessions, each of which has been added to resource group resgrp_b that has a dirty_rate_limit set to 6144 kilobytes per second.

Session 1:

Note

The INSERT commands in session 1 and session 2 were started after the SELECT pg_stat_statements_reset() command in session 2 was run.

The following shows the results from the INSERT commands in the two sessions. RECORD 3 shows the results from session 1. RECORD 2 shows the results from session 2.

```
edb=# SELECT query, rows, total_time, shared_blks_dirtied FROM
pq_stat_statements;
-[ RECORD 1 ]-----+
              | SELECT pg_stat_statements_reset();
query
rows
              | 1
total time
              1 0.43
shared_blks_dirtied | 0
| INSERT INTO t2 VALUES (generate_series (?,?), ?);
query
rows
              1 10000
total_time
              | 30591.551
shared_blks_dirtied | 10003
-[ RECORD 3 ]-----+-----
              | INSERT INTO t1 VALUES (generate_series (?,?), ?);
query
              1 10000
rows
total_time
              | 33215.334
shared_blks_dirtied | 10003
```

First, note the total time was 33215.334 milliseconds for session 1 and 30591.551 milliseconds for session 2. When only one session was active in the same resource group as shown in the first example, the time was 13496.184 milliseconds. Thus more active processes in the resource group result in a slower dirty rate for each active process in the group. This is shown in the following calculations.

The actual dirty rate for session 1 is calculated as follows.

- The number of blocks dirtied per millisecond (ms) is 10003 blocks / 33215.334 ms, which yields 0.30115609 blocks per millisecond.
- Multiply the result by 1000 to give the number of shared blocks dirtied per second (1 second = 1000 ms), which yields 301.15609 blocks per second.
- Multiply the result by 8.192 to give the number of kilobytes dirtied per second (1 block = 8.192 kilobytes), which yields approximately *2467 kilobytes per second*.

The actual dirty rate for session 2 is calculated as follows.

- The number of blocks dirtied per millisecond (ms) is 10003 blocks / 30591.551 ms, which yields 0.32698571 blocks per millisecond.
- Multiply the result by 1000 to give the number of shared blocks dirtied per second (1 second = 1000 ms), which yields 326.98571 blocks per second.
- Multiply the result by 8.192 to give the number of kilobytes dirtied per second (1 block = 8.192 kilobytes), which yields approximately *2679 kilobytes per second*.

The combined dirty rate from session 1 (2467 kilobytes per second) and from session 2 (2679 kilobytes per second) yields 5146 kilobytes per second, which is below the set dirty rate limit of the resource group (6144 kilobytes per seconds).

Example - Multiple Processes in Multiple Groups

In this example, two additional psql sessions are used along with the previous two sessions. The third and fourth sessions perform the same INSERT command in resource group resgrp_c with a dirty_rate_limit of 3072 kilobytes per second.

Sessions 1 and 2 are repeated as illustrated in the prior example using resource group resgrp_b with a dirty_rate_limit of 6144 kilobytes per second.

```
Session 3:
```

```
edb=# CREATE TABLE t3 (c1 INTEGER, c2 CHARACTER(500)) WITH (FILLFACTOR =
10);
CREATE TABLE
edb=# SET edb_resource_group TO resgrp_c;
edb=# SHOW edb_resource_group;
edb_resource_group
resgrp_c
(1 row)
edb=# INSERT INTO t3 VALUES (generate_series (1,10000), 'aaa');
INSERT 0 10000
Session 4:
edb=# CREATE TABLE t4 (c1 INTEGER, c2 CHARACTER(500)) WITH (FILLFACTOR =
10);
CREATE TABLE
edb=# SET edb_resource_group TO resgrp_c;
edb=# SHOW edb_resource_group;
edb_resource_group
resgrp_c
(1 row)
edb=# SELECT pg_stat_statements_reset();
pg_stat_statements_reset
-----
(1 row)
edb=# INSERT INTO t4 VALUES (generate_series (1,10000), 'aaa');
INSERT 0 10000
```

Note: The INSERT commands in all four sessions were started after the command in session 4 was run. SELECT pg_stat_statements_reset()

The following shows the results from the INSERT commands in the four sessions. RECORD 3 shows the results from session 1. RECORD 2 shows the results from session 2. RECORD 4 shows the results from session 3. RECORD 5 shows the results from session 4.

```
shared_blks_dirtied | 0
- [ RECORD 2 ]-----+------
               | INSERT INTO t2 VALUES (generate_series (?,?), ?);
query
               1 10000
rows
               | 31343.458
total_time
shared_blks_dirtied | 10003
-[ RECORD 3 ]-----+
               | INSERT INTO t1 VALUES (generate_series (?,?), ?);
query
               1 10000
rows
total_time
               1 28407.435
shared_blks_dirtied | 10003
-[ RECORD 4 ]-----
              | INSERT INTO t3 VALUES (generate_series (?,?), ?);
query
               1 10000
rows
          l 52727.846
total_time
shared_blks_dirtied | 10003
-[ RECORD 5 ]-----+
query
               | INSERT INTO t4 VALUES (generate_series (?,?), ?);
rows
               1 10000
               1 56063.697
total_time
shared_blks_dirtied | 10003
```

First note that the times of session 1 (28407.435) and session 2 (31343.458) are close to each other as they are both in the same resource group with dirty_rate_limit set to 6144, as compared to the times of session 3 (52727.846) and session 4 (56063.697), which are in the resource group with dirty_rate_limit set to 3072. The latter group has a slower dirty rate limit so the expected processing time is longer as is the case for sessions 3 and 4.

The actual dirty rate for session 1 is calculated as follows.

- The number of blocks dirtied per millisecond (ms) is 10003 blocks / 28407.435 ms, which yields 0.35212612 blocks per millisecond.
- Multiply the result by 1000 to give the number of shared blocks dirtied per second (1 second = 1000 ms), which yields 352.12612 blocks per second.
- Multiply the result by 8.192 to give the number of kilobytes dirtied per second (1 block = 8.192 kilobytes), which yields approximately *2885 kilobytes per second*.

The actual dirty rate for session 2 is calculated as follows.

- The number of blocks dirtied per millisecond (ms) is 10003 blocks / 31343.458 ms, which yields 0.31914156 blocks per millisecond.
- Multiply the result by 1000 to give the number of shared blocks dirtied per second (1 second = 1000 ms), which yields 319.14156 blocks per second.
- Multiply the result by 8.192 to give the number of kilobytes dirtied per second (1 block = 8.192 kilobytes), which yields approximately *2614 kilobytes per second*.

The combined dirty rate from session 1 (2885 kilobytes per second) and from session 2 (2614 kilobytes per second) yields 5499 kilobytes per second, which is near the set dirty rate limit of the resource group (6144 kilobytes per seconds).

The actual dirty rate for session 3 is calculated as follows.

- The number of blocks dirtied per millisecond (ms) is 10003 blocks / 52727.846 ms, which yields 0.18971001 blocks per millisecond.
- Multiply the result by 1000 to give the number of shared blocks dirtied per second (1 second = 1000 ms), which yields 189.71001 blocks per second.
- Multiply the result by 8.192 to give the number of kilobytes dirtied per second (1 block = 8.192 kilobytes), which yields approximately 1554 kilobytes per second.

The actual dirty rate for session 4 is calculated as follows.

- The number of blocks dirtied per millisecond (ms) is 10003 blocks / 56063.697 ms, which yields 0.17842205 blocks per millisecond.
- Multiply the result by 1000 to give the number of shared blocks dirtied per second (1 second = 1000 ms), which yields 178.42205 blocks per second.

 Multiply the result by 8.192 to give the number of kilobytes dirtied per second (1 block = 8.192 kilobytes), which yields approximately 1462 kilobytes per second.

The combined dirty rate from session 3 (1554 kilobytes per second) and from session 4 (1462 kilobytes per second) yields 3016 kilobytes per second, which is near the set dirty rate limit of the resource group (3072 kilobytes per seconds).

Thus, this demonstrates how EDB Resource Manager keeps the aggregate dirty rate of the active processes in its groups close to the dirty rate limit set for each group.

System Catalogs

This section describes the system catalogs that store the resource group information used by EDB Resource Manager.

edb all resource groups

The following table lists the information available in the edb_all_resource_groups catalog:

Column	Туре	Description
group_name active_processes cpu_rate_limit per_process_cpu_rate_limit dirty_rate_limit per_process_dirty_rate_limit	name integer float8 float8 float8 float8	The name of the resource group. Number of currently active processes in the resource group. Maximum CPU rate limit for the resource group. 0 means no limit. Maximum CPU rate limit per currently active process in the resource group. Maximum dirty rate limit for a resource group. 0 means no limit. Maximum dirty rate limit per currently active process in the resource group.

edb resource group

The following table lists the information available in the edb_resource_group catalog:

Column	Туре	Description
rgrpname rgrpcpuratelimit rgrpdirtyratelimit	name float8 float8	The name of the resource group. Maximum CPU rate limit for a resource group. 0 means no limit. Maximum dirty rate limit for a resource group. 0 means no limit.

10.10 libpq C Library

libpq C Library

libpq is the C application programmer's interface to Advanced Server. libpq is a set of library functions that allow client programs to pass queries to the Advanced Server and to receive the results of these queries.

libpq is also the underlying engine for several other EnterpriseDB application interfaces including those written for C++, Perl, Python, Tcl and ECPG. So some aspects of libpq's behavior will be important to the user if one of those packages is used.

Client programs that use libpq must include the header file libpq-fe.h and must link with the libpq library.

Using libpq with EnterpriseDB SPL

The EnterpriseDB SPL language can be used with the libpq interface library, providing support for:

- · Procedures, functions, packages
- Prepared statements
- REFCURSORs
- · Static cursors

- structs and typedefs
- Arrays
- · DML and DDL operations
- IN / OUT / IN OUT parameters

REFCURSOR Support

In earlier releases, Advanced Server provided support for REFCURSORs through the following libpq functions; these functions should now be considered deprecated:

- POCursorResult()
- PQgetCursorResult()
- PQnCursor()

You may now use PQexec() and PQgetvalue() to retrieve a REFCURSOR returned by an SPL (or PL/pgSQL) function. A REFCURSOR is returned in the form of a null-terminated string indicating the name of the cursor. Once you have the name of the cursor, you can execute one or more FETCH statements to retrieve the values exposed through the cursor.

Please note that the samples that follow do not include error-handling code that would be required in a real-world client application.

Returning a Single REFCURSOR

The following example shows an SPL function that returns a value of type REFCURSOR:

```
CREATE OR REPLACE FUNCTION getEmployees(p_deptno NUMERIC) RETURN REFCURSOR AS result REFCURSOR;
BEGIN
OPEN result FOR SELECT * FROM emp WHERE deptno = p_deptno;
RETURN result;
END;
```

This function expects a single parameter, p_deptno, and returns a REFCURSOR that holds the result set for the SELECT query shown in the OPEN statement. The OPEN statement executes the query and stores the result set in a cursor. The server constructs a name for that cursor and stores the name in a variable (named result). The function then returns the name of the cursor to the caller.

To call this function from a C client using libpq, you can use PQexec() and PQgetvalue():

```
#include <stdio.h>
#include <stdlib.h>
#include "libpq-fe.h"
static void fetchAllRows(PGconn *conn,
const char *cursorName,
const char *description);
static void fail(PGconn *conn, const char *msg);
main(int argc, char *argv[])
PGconn *conn = PQconnectdb(argv[1]);
PGresult *result;
if (PQstatus(conn) != CONNECTION_OK)
fail(conn, PQerrorMessage(conn));
result = PQexec(conn, "BEGIN TRANSACTION");
if (PQresultStatus(result) != PGRES_COMMAND_OK)
fail(conn, PQerrorMessage(conn));
PQclear(result);
result = PQexec(conn, "SELECT * FROM getEmployees(10)");
if (PQresultStatus(result) != PGRES_TUPLES_OK)
fail(conn, PQerrorMessage(conn));
fetchAllRows(conn, PQgetvalue(result, 0, 0), "employees");
```

```
PQclear(result);
PQexec(conn, "COMMIT");
PQfinish(conn);
exit(0);
static void
fetchAllRows(PGconn *conn,
const char *cursorName,
const char *description)
{
size_t commandLength = strlen("FETCH ALL FROM ") +
strlen(cursorName) + 3;
char *commandText = malloc(commandLength);
PGresult *result;
int row;
sprintf(commandText, "FETCH ALL FROM \\"%s\"", cursorName);
result = PQexec(conn, commandText);
if (PQresultStatus(result) != PGRES_TUPLES_OK)
fail(conn, PQerrorMessage(conn));
printf("-- %s --\n", description);
for (row = 0; row < PQntuples(result); row++)</pre>
const char *delimiter = "\t";
int col;
for (col = 0; col < PQnfields(result); col++)</pre>
printf("%s%s", delimiter, PQgetvalue(result, row, col));
delimiter = ",";
printf("\n");
PQclear(result);
free(commandText);
static void
fail(PGconn *conn, const char *msg)
fprintf(stderr, "%s\n", msg);
if (conn != NULL)
PQfinish(conn);
exit(-1);
}
```

The code sample contains a line of code that calls the <code>getEmployees()</code> function, and returns a result set that contains all of the employees in department 10:

```
result = PQexec(conn, "SELECT * FROM getEmployees(10)");
```

The PQexec() function returns a result set handle to the C program. The result set will contain exactly one value; that value is the name of the cursor as returned by getEmployees().

Once you have the name of the cursor, you can use the SQL FETCH statement to retrieve the rows in that cursor. The function fetchAllRows() builds a FETCH ALL statement, executes that statement, and then prints the result set of the FETCH ALL statement.

The output of this program is shown below:

```
-- employees -- 7782, CLARK, MANAGER, 7839, 09-JUN-81 00:00:00, 2450.00, 10 7839, KING, PRESIDENT, 17-NOV-81 00:00:00, 5000.00, 10 7934, MILLER, CLERK, 7782, 23-JAN-82 00:00:00, 1300.00, 10
```

Returning Multiple REFCURSORs

The next example returns two REFCURSORs:

- The first REFCURSOR contains the name of a cursor (employees) that contains all employees who work in a department within the range specified by the caller.
- The second REFCURSOR contains the name of a cursor (departments) that contains all of the departments in the range specified by the caller.

In this example, instead of returning a single REFCURSOR, the function returns a SETOF REFCURSOR (which means 0 or more REFCURSORS). One other important difference is that the libpq program should not expect a single REFCURSOR in the result set, but should expect two rows, each of which will contain a single value (the first row contains the name of the employees cursor, and the second row contains the name of the departments cursor).

CREATE OR REPLACE FUNCTION getEmpsAndDepts(p_min NUMERIC,

```
p_max NUMERIC)
RETURN SETOF REFCURSOR AS
employees REFCURSOR;
departments REFCURSOR;
BEGIN
OPEN employees FOR
SELECT * FROM emp WHERE deptno BETWEEN p_min AND p_max;
RETURN NEXT employees:
OPEN departments FOR
SELECT * FROM dept WHERE deptno BETWEEN p_min AND p_max;
RETURN NEXT departments;
As in the previous example, you can use PQexec() and PQgetvalue() to call the SPL function:
#include <stdio.h>
#include <stdlib.h>
#include "libpq-fe.h"
static void fetchAllRows(PGconn *conn.
const char *cursorName,
const char *description);
static void fail(PGconn *conn, const char *msq);
main(int argc, char *argv□)
PGconn *conn = PQconnectdb(argv[1]);
PGresult *result;
if (PQstatus(conn) != CONNECTION_OK)
fail(conn, PQerrorMessage(conn));
result = PQexec(conn, "BEGIN TRANSACTION");
if (PQresultStatus(result) != PGRES_COMMAND_OK)
fail(conn, PQerrorMessage(conn));
PQclear(result);
result = PQexec(conn, "SELECT * FROM getEmpsAndDepts(20, 30)");
if (PQresultStatus(result) != PGRES_TUPLES_OK)
fail(conn, PQerrorMessage(conn));
fetchAllRows(conn, PQgetvalue(result, 0, 0), "employees");
fetchAllRows(conn, PQgetvalue(result, 1, 0), "departments");
PQclear(result);
PQexec(conn, "COMMIT");
PQfinish(conn);
exit(0);
static void
fetchAllRows(PGconn *conn,
const char *cursorName,
const char *description)
```

```
{
size_t commandLength = strlen("FETCH ALL FROM ") +
strlen(cursorName) + 3;
char *commandText = malloc(commandLength);
PGresult *result;
int row;
sprintf(commandText, "FETCH ALL FROM \\"%s\"", cursorName);
result = PQexec(conn, commandText);
if (PQresultStatus(result) != PGRES_TUPLES_OK)
fail(conn, PQerrorMessage(conn));
printf("-- %s --\n", description);
for (row = 0; row < PQntuples(result); row++)</pre>
const char *delimiter = "\t";
int col;
for (col = 0; col < PQnfields(result); col++)</pre>
printf("%s%s", delimiter, PQgetvalue(result, row, col));
delimiter = ",";
printf("\n");
POclear(result):
free(commandText);
static void
fail(PGconn *conn, const char *msg)
fprintf(stderr, "%s\n", msg);
if (conn != NULL)
PQfinish(conn);
exit(-1);
If you call getEmpsAndDepts(20, 30), the server will return a cursor that contains all employees who work
in department 20 or 30, and a second cursor containing the description of departments 20 and 30.
-- employees --
7369, SMITH, CLERK, 7902, 17-DEC-80 00:00:00, 800.00, 20
```

```
7369, SMITH, CLERK, 7902, 17-DEC-80 00:00:00, 800.00, 20
7499, ALLEN, SALESMAN, 7698, 20-FEB-81 00:00:00, 1600.00, 300.00, 30
7521, WARD, SALESMAN, 7698, 22-FEB-81 00:00:00, 1250.00, 500.00, 30
7566, JONES, MANAGER, 7839, 02-APR-81 00:00:00, 2975.00, ,20
7654, MARTIN, SALESMAN, 7698, 28-SEP-81 00:00:00, 1250.00, 1400.00, 30
7698, BLAKE, MANAGER, 7839, 01-MAY-81 00:00:00, 2850.00, ,30
7788, SCOTT, ANALYST, 7566, 19-APR-87 00:00:00, 3000.00, ,20
7844, TURNER, SALESMAN, 7698, 08-SEP-81 00:00:00, 1500.00, 0.00, 30
7876, ADAMS, CLERK, 7788, 23-MAY-87 00:00:00, 1100.00, ,20
7900, JAMES, CLERK, 7698, 03-DEC-81 00:00:00, 950.00, ,30
7902, FORD, ANALYST, 7566, 03-DEC-81 00:00:00, 3000.00, ,20
-- departments --
20, RESEARCH, DALLAS
30, SALES, CHICAGO
```

Array Binding

Advanced Server's array binding functionality allows you to send an array of data across the network in a single round-trip. When the back end receives the bulk data, it can use the data to perform insert or update operations.

Perform bulk operations with a prepared statement; use the following function to prepare the statement:

```
PGresult *PQprepare(PGconn *conn, const char *stmtName,
```

```
const char *query,
int nParams,
const Oid *paramTypes);
```

Details of PQprepare() can be found in the prepared statement section.

The following functions can be used to perform bulk operations:

- PQBulkStart
- PQexecBulk
- PQBulkFinish
- PQexecBulkPrepared

PQBulkStart

PQBulkStart() initializes bulk operations on the server. You must call this function before sending bulk data to the server. PQBulkStart() initializes the prepared statement specified in stmtName to receive data in a format specified by paramFmts.

API Definition

```
PGresult *PQBulkStart(PGconn *conn,
const char *Stmt_Name,
unsigned int nCol,
const int *paramFmts);
```

PQexecBulk

PQexecBulk() is used to supply data (paramValues) for a statement that was previously initialized for bulk operation using PQBulkStart().

This function can be used more than once after PQBulkStart() to send multiple blocks of data. See the example for more details.

API Definition

```
PGresult *PQexecBulk(PGconn *conn,
unsigned int nRows,
const char *const * paramValues,
const int *paramLengths);
```

PQBulkFinish

This function completes the current bulk operation. You can use the prepared statement again without repreparing it.

API Definition

```
PGresult *PQBulkFinish(PGconn *conn);
```

PQexecBulkPrepared

Alternatively, you can use the PQexecBulkPrepared() function to perform a bulk operation with a single function call. PQexecBulkPrepared() sends a request to execute a prepared statement with the given parameters, and waits for the result. This function combines the functionality of PQbulkStart(), PQexecBulk(), and PQBulkFinish(). When using this function, you are not required to initialize or terminate the bulk operation; this function starts the bulk operation, passes the data to the server, and terminates the bulk operation.

Specify a previously prepared statement in the place of stmtName. Commands that will be used repeatedly will be parsed and planned just once, rather than each time they are executed.

API Definition

Example Code (Using PQBulkStart, PQexecBulk, PQBulkFinish)

```
The following example uses PGBulkStart, PQexecBulk, and PQBulkFinish.
void InsertDataUsingBulkStyle( PGconn *conn )
PGresult *res;
Oid paramTypes[2];
char *paramVals[5][2];
int paramLens[5][2];
int paramFmts[2];
int i;
int a[5] = \{ 10, 20, 30, 40, 50 \};
char b[5][10] = { "Test_1", "Test_2", "Test_3", "Test_4", "Test_5" };
paramTypes[0] = 23;
paramTypes[1] = 1043;
res = PQprepare( conn, "stmt_1", "INSERT INTO testtable1 values( $1, $2
)", 2, paramTypes );
PQclear( res );
paramFmts[0] = 1; /* Binary format */
paramFmts[1] = 0;
for(i = 0; i < 5; i++)
a[i] = htonl(a[i]);
paramVals[i][0] = &(a[i]);
paramVals[i][1] = b[i];
paramLens[i][0] = 4;
paramLens[i][1] = strlen( b[i] );
res = PQBulkStart(conn, "stmt_1", 2, paramFmts);
PQclear( res );
printf( "< -- PQBulkStart -- >\n" );
res = PQexecBulk(conn, 5, (const char *const *)paramVals, (const int
*)paramLens);
PQclear( res );
printf( "< -- PQexecBulk -- >\n" );
res = PQexecBulk(conn, 5, (const char *const *)paramVals, (const int
*)paramLens);
PQclear( res );
printf( "< -- PQexecBulk -- >\n" );
res = PQBulkFinish(conn);
PQclear( res );
printf( "< -- PQBulkFinish -- >\n" );
```

Example Code (Using PQexecBulkPrepared)

```
The following example uses PQexecBulkPrepared .

void InsertDataUsingBulkStyleCombinedVersion( PGconn *conn )
{
PGresult *res;
Oid paramTypes[2];
```

```
char *paramVals[5][2];
int paramLens[5][2];
int paramFmts[2];
int i;
int a[5] = \{ 10, 20, 30, 40, 50 \};
char b[5][10] = { "Test_1", "Test_2", "Test_3", "Test_4", "Test_5" };
paramTypes[0] = 23;
paramTypes[1] = 1043;
res = PQprepare( conn, "stmt_2", "INSERT INTO testtable1 values( $1, $2
)", 2, paramTypes );
PQclear( res );
paramFmts[0] = 1; /* Binary format */
paramFmts[1] = 0;
for(i = 0; i < 5; i++)
{
a[i] = htonl(a[i]);
paramVals[i][0] = &(a[i]);
paramVals[i][1] = b[i];
paramLens[i][0] = 4;
paramLens[i][1] = strlen( b[i] );
res = PQexecBulkPrepared(conn, "stmt_2", 2, 5, (const char *const
*)paramVals,(const int *)paramLens, (const int *)paramFmts);
PQclear( res );
}
```

10.11 Debugger

The Debugger gives developers and DBAs the ability to test and debug server-side programs using a graphical, dynamic environment. The types of programs that can be debugged are SPL stored procedures, functions, triggers, and packages as well as PL/pgSQL functions and triggers.

The Debugger is integrated with *pgAdmin 4* and *EDB Postgres Enterprise Manager*. If you have installed Advanced Server on a Windows host, pgAdmin 4 is automatically installed; you will find the pgAdmin 4 icon in the Windows Start menu. If your Advanced Server host is a CentOS or Linux system, you can use yum to install pgAdmin4. Open a command line, assume superuser privileges, and enter:

```
yum install edb-pgadmin4*
```

The RPM installation will add the pgAdmin4 icon to your Applications menu.

There are two basic ways the Debugger can be used to test programs:

- Standalone Debugging. The Debugger is used to start the program to be tested. You supply any input parameter values required by the program and you can immediately observe and step through the code of the program. Standalone debugging is the typical method used for new programs and for initial problem investigation.
- In-Context Debugging. The program to be tested is initiated by an application other than the Debugger. You first set a *global breakpoint* on the program to be tested. The application that makes the first call to the program encounters the global breakpoint. The application suspends execution at which point the Debugger takes control of the called program. You can then observe and step through the code of the called program as it runs within the context of the calling application. After you have completely stepped through the code of the called program in the Debugger, the suspended application resumes execution. In-context debugging is useful if it is difficult to reproduce a problem using standalone debugging due to complex interaction with the calling application.

The debugging tools and operations are the same whether using standalone or in-context debugging. The difference is in how the program to be debugged is invoked.

The following sections discuss the features and functionality of the Debugger using the standalone debugging method. The directions for starting the Debugger for in-context debugging are discussed in the [Setting Global

Breakpoint for In-Context Debugging](11_debugger#setting_global_breakpoint_for_in_context_debugging) section.

Configuring the Debugger

Configuring the Debugger

Before using the Debugger, you must edit the postgresql.conf file, adding \$libdir/plugin_debugger to the libraries listed in the shared_preload_libraries configuration parameter.

shared_preload_libraries =

- '\$libdir/dbms_pipe,\$libdir/edb_gen,\$libdir/dbms_aq,\$libdir/plugin_debugger'
 - On Linux, the postgresql.conf file is located in: /var/lib/edb/as<x>/data
 - On Windows, the postgresql.conf file is located in: C:\Program Files\edb\as<x>\data

Where x is the version of Advanced Server.

After modifying the shared_preload_libraries parameter, you must restart the database server.

Starting the Debugger

Starting the Debugger

Use pgAdmin 4 to access the Debugger for standalone debugging. To open the Debugger, highlight the name of the stored procedure or function you wish to debug in the pgAdmin 4 Browser panel. Then, navigate through the Object menu to the Debugging menu and select Debug from the submenu.

Starting the Debugger from the Object menu

You can also right-click on the name of the stored procedure or function in the pgAdmin 4 Browser, and select Debugging, and the Debug from the context menu.

Starting the Debugger from the object's context menu

Note that triggers cannot be debugged using standalone debugging. Triggers must be debugged using in-context debugging. See the [Setting Global Breakpoint for In-Context Debugging](11_debugger#setting_global_breakpoint_for_in_context_debugging) section for information on setting a global breakpoint for in-context debugging.

To debug a package, highlight the specific procedure or function under the package node of the package you wish to debug and follow the same directions as for stored procedures and functions.

The Debugger Window

You can use the Debugger window to pass parameter values when you are standalone-debugging a program that expects parameters. When you start the debugger, the Debugger window opens automatically to display any IN or IN OUT parameters expected by the program. If the program declares no IN or IN OUT parameters, the Debugger window does not open.

The Debugger window

Use the fields on the Debugger window to provide a value for each parameter:

- The Name field contains the formal parameter name.
- The Type field contains the parameter data type.
- Check the Null? checkbox to indicate that the parameter is a NULL value.
- Check the Expression? checkbox if the Value field contains an expression.
- The Value field contains the parameter value that will be passed to the program.
- Check the Use Default? checkbox to indicate that the program should use the value in the Default Value field.
- The Default Value field contains the default value of the parameter.

Press the Tab key to select the next parameter in the list for data entry, or click on a Value field to select the parameter for data entry.

If you are debugging a procedure or function that is a member of a package that has an initialization section, check the Debug Package Initializer check box to instruct the Debugger to step into the package initialization section, allowing you to debug the initialization section code before debugging the procedure or function. If you do not select the check box, the Debugger executes the package initialization section without allowing you to see or step through the individual lines of code as they are executed.

After entering the desired parameter values, click the Debug button to start the debugging process. Click the Cancel button to terminate the Debugger.

Note: The Debugger window does not open during in-context debugging. Instead, the application calling the program to be debugged must supply any required input parameter values.

When you have completed a full debugging cycle by stepping through the program code, the Debugger window re-opens, allowing you to enter new parameter values and repeat the debugging cycle, or end the debugging session.

Main Debugger Window

The Main Debugger window contains two panels:

- The top Program Body panel displays the program source code.
- The bottom Tabs panel provides a set of tabs for different information.

Use the Tool Bar icons located at the top panel to access debugging functions.

The Main Debugger window

The two panels are described in the following sections.

The Program Body Panel

The Program Body panel displays the source code of the program that is being debugged.

The Program Body

The figure shows that the Debugger is about to execute the SELECT statement. The blue indicator in the program body highlights the next statement to execute.

The Tabs Panel

You can use the bottom Tabs panel to view or modify parameter values or local variables, or to view messages generated by RAISE INFO and function results.

The following is the information displayed by the tabs in the panel:

- · The Parameters tab displays the current parameter values.
- The Local variables tab displays the value of any variables declared within the program.
- The Messages tab displays any results returned by the program as it executes.
- The Results tab displays program results (if applicable) such as the value from the RETURN statement of a function.
- · The Stack tab displays the call stack.

The following figures show the results from the various tabs.

The Parameters tab

The Local variables tab

The Messages tab

The Results tab

The Stack Tab

The Stack tab displays a list of programs that are currently on the call stack (programs that have been invoked, but which have not yet completed). When a program is called, the name of the program is added to the top of the list displayed in the Stack tab. When the program ends, its name is removed from the list.

The Stack tab also displays information about program calls. The information includes:

- · The location of the call within the program
- · The call arguments
- · The name of the program being called

Reviewing the call stack can help you trace the course of execution through a series of nested programs.

A debugged program calling a subprogram

The above figure shows that emp_query_caller is about to call a subprogram named emp_query . emp_query_caller is currently at the top of the call stack.

After the call to emp_query executes, emp_query is displayed at the top of the Stack tab, and its code is displayed in the Program Body panel.

Debugging the called subprogram

Upon completion of execution of the subprogram, control returns to the calling program (emp_query_caller), now displayed at the top of the Stack tab.

Control returns from debugged subprogram

Debugging a Program

Debugging a Program

You can perform the following operations to debug a program:

- · Step through the program one line at a time
- · Execute the program until you reach a breakpoint
- View and change local variable values within the program

Stepping Through the Code

Use the tool bar icons to step through a program with the Debugger:

The Tool bar icons

The icons serve the following purposes:

- Step into. Click the Step into icon to execute the currently highlighted line of code.
- Step over. Click the Step over icon to execute a line of code, stepping over any sub-functions invoked by the code. The sub-function executes, but is not debugged unless it contains a breakpoint.
- Continue/Start. Click the Continue/Start icon to execute the highlighted code, and continue until the program encounters a breakpoint or completes.
- Stop. Click the Stop icon to halt the execution of a program.

Using Breakpoints

As the Debugger executes a program, it pauses whenever it reaches a breakpoint. When the Debugger pauses, you can observe or change local variables, or navigate to an entry in the call stack to observe variables or set other breakpoints. The next step into, step over, or continue operation forces the debugger to resume execution with the next line of code following the breakpoint. There are two types of breakpoints:

Local Breakpoint - A local breakpoint can be set at any executable line of code within a program. The Debugger pauses execution when it reaches a line where a local breakpoint has been set.

Global Breakpoint - A global breakpoint will trigger when *any* session reaches that breakpoint. Set a global breakpoint if you want to perform in-context debugging of a program. When a global breakpoint is set on a program, the debugging session that set the global breakpoint waits until that program is invoked in another session. A global breakpoint can only be set by a superuser.

To create a local breakpoint, left-click within the grey shaded margin to the left of the line of code where you want the local breakpoint set. Where you click in the grey shaded margin should be close to the right side of the margin as in the spot where the breakpoint dot is shown on source code line 12.

When created, the Debugger displays a dark dot in the margin, indicating a breakpoint has been set at the selected line of code.

Set a breakpoint by clicking in left-hand margin

You can set as many local breakpoints as desired. Local breakpoints remain in effect for the duration of a debugging session until they are removed.

Removing a Local Breakpoint

To remove a local breakpoint, left-click the mouse on the breakpoint dot in the grey shaded margin of the Program Body panel. The dot disappears, indicating that the breakpoint has been removed.

You can remove all of the breakpoints from the program that currently appears in the Program Body frame by clicking the Clear all breakpoints icon.

Clear all breakpoints icon

Note

When you perform any of the preceding actions, only the breakpoints in the program that currently appears in the Program Body panel are removed. Breakpoints in called subprograms or breakpoints in programs that call the program currently appearing in the Program Body panel are not removed.

Setting a Global Breakpoint for In-Context Debugging

To set a global breakpoint for in-context debugging, highlight the stored procedure, function, or trigger on which you wish to set the breakpoint in the Browser panel. Navigate through the Object menu to select Debugging, and then Set Breakpoint.

Setting a global breakpoint from the Object men

Alternatively, you can right-click on the name of the stored procedure, function, or trigger on which you wish to set a global breakpoint and select Debugging, then Set Breakpoint from the context menu as shown by the following.

Setting a global breakpoint from the object's context menu

To set a global breakpoint on a trigger, expand the table node that contains the trigger, highlight the specific trigger you wish to debug, and follow the same directions as for stored procedures and functions.

To set a global breakpoint in a package, highlight the specific procedure or function under the package node of the package you wish to debug and follow the same directions as for stored procedures and functions.

After you choose Set Breakpoint, the Debugger window opens and waits for an application to call the program to be debugged.

Waiting for invocation of program to be debugged

The PSQL client invokes the select_emp function (on which a global breakpoint has been set).

```
$ psql edb enterprisedb
psql.bin (12.0.0, server 12.0.0)
Type "help" for help.
edb=# SELECT select_emp(7900);
```

The select_emp function does not complete until you step through the program in the Debugger.

Program on which a global breakpoint has been set

You can now debug the program using any of the previously discussed operations such as step into, step over, and continue, or set local breakpoints. When you have stepped through execution of the program, the calling application (PSQL) regains control and the select_emp function completes execution and its output is displayed.

```
$ psql edb enterprisedb
psql.bin (12.0.0, server 12.0.0)
Type "help" for help.
edb=# SELECT select_emp(7900);
INFO: Number : 7900
INFO: Name : JAMES
INFO: Hire Date : 12/03/1981
INFO: Salary : 950.00
```

INFO: Commission: 0.00
INFO: Department: SALES

select_emp -----(1 row)

At this point, you can end the Debugger session. If you do not end the Debugger session, the next application that invokes the program will encounter the global breakpoint and the debugging cycle will begin again.

Exiting the Debugger

To end a Debugger session and exit the Debugger, click on the close icon (x) located in the upper-right corner to close the tab.

Exiting from the Debugger

10.12 Performance Analysis and Tuning

Performance Analysis and Tuning

Advanced Server provides various tools for performance analysis and tuning. These features are described in this section.

Dynatune

Advanced Server supports dynamic tuning of the database server to make the optimal usage of the system resources available on the host machine on which it is installed. The two parameters that control this functionality are located in the postgresql.conf file. These parameters are:

- edb_dynatune
- edb_dynatune_profile

edb_dynatune

edb_dynatune determines how much of the host system's resources are to be used by the database server based upon the host machine's total available resources and the intended usage of the host machine.

When Advanced Server is initially installed, the edb_dynatune parameter is set in accordance with the selected usage of the host machine on which it was installed - i.e., development machine, mixed use machine, or dedicated server. For most purposes, there is no need for the database administrator to adjust the various configuration parameters in the postgresql.conf file in order to improve performance.

You can change the value of the edb_dynatune parameter after the initial installation of Advanced Server by editing the postgresql.conf file. The postmaster must be restarted in order for the new configuration to take effect.

The edb_dynatune parameter can be set to any integer value between 0 and 100, inclusive. A value of 0, turns off the dynamic tuning feature thereby leaving the database server resource usage totally under the control of the other configuration parameters in the postgresql.conf file.

A low non-zero, value (e.g., 1 - 33) dedicates the least amount of the host machine's resources to the database server. This setting would be used for a development machine where many other applications are being used.

A value in the range of 34 - 66 dedicates a moderate amount of resources to the database server. This setting might be used for a dedicated application server that may have a fixed number of other applications running on the same machine as Advanced Server.

The highest values (e.g., 67 - 100) dedicate most of the server's resources to the database server. This setting would be used for a host machine that is totally dedicated to running Advanced Server.

Once a value of edb_dynatune is selected, database server performance can be further fine-tuned by adjusting the other configuration parameters in the postgresql.conf file. Any adjusted setting overrides the corresponding value chosen by edb_dynatune. You can change the value of a parameter by un-commenting the configuration parameter, specifying the desired value, and restarting the database server.

edb_dynatune_profile

The edb_dynatune_profile parameter is used to control tuning aspects based upon the expected workload profile on the database server. This parameter takes effect upon startup of the database server.

The possible values for edb_dynatune_profile are:

Value	Usage
oltp reporting mixed	Recommended when the database server is processing heavy online transaction processing workloads. Recommended for database servers used for heavy data reporting. Recommended for servers that provide a mix of transaction processing and data reporting.

EDB Wait States

The EDB wait states contrib module contains two main components.

EDB Wait States Background Worker (EWSBW)

When the wait states background worker is registered as one of the shared preload libraries, EWSBW probes each of the running sessions at regular intervals.

For every session it collects information such as the database to which it is connected, the logged in user of the session, the query running in that session, and the wait events on which it is waiting.

This information is saved in a set of files in a user-configurable path and directory folder given by the edb_wait_states.directory parameter to be added to the postgresql.conf file. The specified path must be a full, absolute path and not a relative path.

The following describes the installation process on a Linux system.

Step 1: EDB wait states is installed with the edb-as<xx>-server-edb-modules RPM package where *xx* is the Advanced Server version number.

Step 2: To launch the worker, it must be registered in the postgresql.conf file using the shared_preload_libraries parameter, for example:

shared_preload_libraries = '\$libdir/edb_wait_states'

Step 3: Restart the database server. After a successful restart, the background worker begins collecting data.

Step 4: To review the data, create the following extension:

CREATE EXTENSION edb_wait_states;

Step 5: To terminate the EDB wait states worker, remove \$libdir/edb_wait_states from the shared_preload_libraries parameter and restart the database server.

The following describes the installation process on a Windows system.

Step 1: EDB wait states module is installed with the EDB Modules installer by invoking StackBuilder Plus utility. Follow the onscreen instructions to complete the installation of the EDB Modules.

Step 2: To register the worker, modify the postgresql.conf file to include the wait states library in the shared_preload_libraries configuration parameter. The parameter value must include:

shared_preload_libraries = '\$libdir/edb_wait_states.dll'

The EDB wait states installation places the edb_wait_states.dll library file in the following path:

C:\Program Files\edb\as12\lib\\

Step 3: Restart the database server for the changes to take effect. After a successful restart, the background worker gets started and starts collecting the data.

Step 4: To view the data, create the following extension:

```
CREATE EXTENSION edb_wait_states;
```

The installer places the edb_wait_states.control file in the following path:

C:\Program Files\edb\as12\share\extension

Terminating the Wait States Worker

To terminate the EDB wait states worker, use the DROP EXTENSION command to drop the edb_wait_states extension; then modify the postgresql.conf file, removing \$libdir/edb_wait_states.dll from the shared_preload_libraries parameter. Restart the database server after modifying the postgresql.conf file to apply your changes.

The Wait States Interface

The interface includes the functions listed in the following sections. Each of these functions has common input and output parameters. Those parameters are as follows:

- start_ts and end_ts (IN). Together these specify the time interval and the data within which is to be read. If only start_ts is specified, the data starting from start_ts is output. If only end_ts is provided, data up to end_ts is output. If none of those are provided, all the data is output. Every function outputs different data. The output of each function will be explained below.
- query_id (OUT). Identifies a normalized query. It is internal hash code computed from the query.
- session_id (OUT). Identifies a session.
- ref_start_ts and ref_end_ts (OUT). Provide the timestamps of a file containing a particular data point. A data point may be a wait event sample record or a query record or a session record.

The syntax of each function is given in the following sections.

Note: The examples shown in the following sections are based on the following three queries executed on four different sessions connected to different databases using different users, simultaneously:

```
SELECT schemaname FROM pg_tables, pg_sleep(15) WHERE schemaname <>
'pg_catalog'; * ran on 2 sessions */
SELECT tablename FROM pg_tables, pg_sleep(10) WHERE schemaname <>
'pg_catalog';
SELECT tablename, schemaname FROM pg_tables, pg_sleep(10) WHERE schemaname <> 'pg_catalog';
```

edb wait states data

This function is used to read the data collected by the background worker.

```
edb_wait_states_data(
IN *start_ts* timestamptz default '-infinity'::timestamptz,
IN *end_ts* timestamptz default 'infinity'::timestamptz,
OUT *session_id* int4,
OUT *dbname* text,
OUT *username* text,
OUT *query* text,
OUT *query_start_time* timestamptz,
OUT *sample_time* timestamptz,
OUT *wait_event_type* text,
OUT *wait_event* text
)
```

This function can be used to find out the following:

The queries running in the given duration (defined by *start_ts* and *end_ts*) in all the sessions, and the wait events, if any, they were waiting on. For example:

```
SELECT query, session_id, wait_event_type, wait_event
FROM edb_wait_states_data(start_ts, end_ts);
```

The progress of a session within a given duration (that is, the queries run in a session (session_id = 100000) and the wait events the queries waited on). For example:

```
SELECT query, wait_event_type, wait_event
FROM edb_wait_states_data(start_ts, end_ts)
WHERE session_id = 100000;
```

The duration for which the samples are available. For example:

```
SELECT min(sample_time), max(sample_time)
FROM edb_wait_states_data();
```

Parameters

In addition to the common parameters described previously, each row of the output gives the following:

dbname

The session's database

username

The session's logged in user

query

The query running in the session

query_start_time

The time when .the query started

sample_time

The time when wait event data was collected

wait_event_type

The type of wait event the session (backend) is waiting on

wait_event

The wait event the session (backend) is waiting on

Example

<> \$2

The following is a sample output from the edb_wait_states_data() function.

```
edb=# SELECT * FROM edb_wait_states_data();
-[ RECORD 1]----+
           1 4398
session_id
            l edb
dbname
username
            l enterprisedb
            | SELECT schemaname FROM pg_tables, pg_sleep($1) WHERE schemaname
query
<> $2
query_start_time| 17-AUG-18 11:56:05.271962 -04:00
sample_time | 17-AUG-18 11:56:19.700236 -04:00
wait_event_type | Timeout
wait_event | PgSleep
- [ RECORD 2]----+-----
           1 4398
session_id
            l edb
dbname
            l enterprisedb
username
             | SELECT schemaname FROM pg_tables, pg_sleep($1) WHERE schemaname
query
```

```
query_start_timel 17-AUG-18 11:56:05.271962 -04:00
sample_time | 17-AUG-18 11:56:18.699938 -04:00
wait_event_type | Timeout
wait_event | PgSleep
-[ RECORD 3]---+----------
session_id
           l 4398
            l edb
dbname
            l enterprisedb
username
            | SELECT schemaname FROM pa_tables, pa_sleep($1) WHERE schemaname
auery
<> $2
query_start_timel 17-AUG-18 11:56:05.271962 -04:00
sample_time | 17-AUG-18 11:56:17.700253 -04:00
wait_event_type | Timeout
wait_event | PaSleep
```

edb_wait_states_queries

This function gives information about the queries sampled by the background worker.

```
edb_wait_states_queries(
IN *start_ts* timestamptz default '-infinity'::timestamptz,
IN *end_ts* timestamptz default 'infinity'::timestamptz,
OUT *query_id* int8,
OUT *query* text,
OUT *ref_start_ts* timestamptz
OUT *ref_end_ts* timestamptz
)
```

A new queries file is created periodically and thus, there can be multiple query files generated corresponding to specific intervals.

This function returns all the queries in query files that overlap with the given time interval. A query as shown below, gives all the queries in query files that contained queries sampled between *start_ts* and *end_ts*.

In other words, the function may output queries that did not run in the given interval. To exactly know that the user should use $edb_wait_states_data()$.

```
SELECT query FROM edb_wait_states_queries(start_ts, end_ts);
```

Parameters

In addition to the common parameters described previously, each row of the output gives the following:

query

Normalized query text

Example

The following is a sample output from the edb_wait_states_queries() function.

edb wait states sessions

This function gives information about the sessions sampled by the background worker.

```
edb_wait_states_sessions(
IN *start_ts* timestamptz default '-infinity'::timestamptz,
IN *end_ts* timestamptz default 'infinity'::timestamptz,
OUT *session_id* int4,
OUT *dbname* text,
OUT *username* text,
OUT *ref_start_ts* timestamptz
OUT *ref_end_ts* timestamptz
```

This function can be used to identify the databases that were connected and/or which users started those sessions. For example:

```
SELECT dbname, username, session_id
FROM edb_wait_states_sessions();
```

Similar to edb_wait_states_queries(), this function outputs all the sessions logged in session files that contain sessions sampled within the given interval and not necessarily only the sessions sampled within the given interval. To identify that one should use edb_wait_states_data().

Parameters

In addition to the common parameters described previously, each row of the output gives the following:

dbname

The database to which the session is connected

username

Login user of the session

Example

The following is a sample output from the edb_wait_states_sessions() function.

```
edb=# SELECT * FROM edb_wait_states_sessions();
-[ RECORD 1 ]+-----
session_id | 4340
dbname | edb
username | enterprisedb
ref_start_ts | 17-AUG-18 11:52:38.698793 -04:00
ref_end_ts | 18-AUG-18 11:52:38.698793 -04:00
-[ RECORD 2 ]+-----
session_id | 4398
       l edb
dbname
username | l enterprisedb
ref_start_ts | 17-AUG-18 11:52:38.698793 -04:00
ref_end_ts | 18-AUG-18 11:52:38.698793 -04:00
-[ RECORD 3 ]+----
session_id | 4410
           l db1
dbname
username
          l user1
ref_start_ts | 17-AUG-18 11:52:38.698793 -04:00
```

edb_wait_states_samples

This function gives information about wait events sampled by the background worker.

```
edb_wait_states_samples(
IN *start_ts* timestamptz default '-infinity'::timestamptz,
IN *end_ts* timestamptz default 'infinity'::timestamptz,
OUT *query_id* int8,
OUT *session_id* int4,
OUT *query_start_time* timestamptz,
OUT *sample_time* timestamptz,
OUT *wait_event_type* text,
OUT *wait_event* text
)
```

Usually, a user would not be required to call this function directly.

Parameters

In addition to the common parameters described previously, each row of the output gives the following:

```
query_start_time
```

The time when the query started in this session

sample_time

The time when wait event data was collected

wait_event_type

The type of wait event on which the session is waiting

wait event

The wait event on which the session (backend) is waiting

Example

The following is a sample output from the edb_wait_states_samples() function.

```
edb=# SELECT * FROM edb_wait_states_samples();
-[ RECORD 1 ]----+
query_start_time | 17-AUG-18 11:56:00.39421 -04:00
sample_time | 17-AUG-18 11:56:00.699934 -04:00
wait_event_type | Timeout
wait_event | PgSleep
-[ RECORD 2 ]----+
query_start_time | 17-AUG-18 11:56:00.39421 -04:00
sample_time | 17-AUG-18 11:56:01.699003 -04:00
wait_event_type | Timeout
wait_event | PgSleep
query_id | 4292540138852956818
session_id | 4340
query_start_time | 17-AUG-18 11:56:00.39421 -04:00
```

edb_wait_states_purge

The function deletes all the sampled data files (queries, sessions and wait event samples) that were created after *start_ts* and aged (rotated) before *end_ts*.

```
edb_wait_states_purge(
IN *start_ts* timestamptz default '-infinity'::timestamptz,
IN *end_ts* timestamptz default 'infinity'::timestamptz)
```

Usually a user does not need to run this function. The backend should purge those according to the retention age, but in case, that doesn't happen for some reason, this function may be used.

In order to know the duration for which the samples have been retained, use edb_wait_states_data()
as explained in the previous examples of that function.

Example

```
The $PGDATA/edb_wait_states directory before running edb_wait_states_purge():
[root@localhost data]# pwd
/var/lib/edb/as12/data
[root@localhost data]# ls -l edb_wait_states
total 12
-rw----- 1 enterprisedb ... 253 Aug 17 11:56
edb_ws_queries_587836358698793_587922758698793
-rw----- 1 enterprisedb ... 1600 Aug 17 11:56
edb_ws_samples_587836358698793_587839958698793
-rw----- 1 enterprisedb ... 94 Aug 17 11:56
edb_ws_sessions_587836358698793_587922758698793
The $PGDATA/edb_wait_states directory after running edb_wait_states_purge():
edb=# SELECT * FROM edb_wait_states_purge();
edb_wait_states_purge
_____
(1 row)
[root@localhost data]# pwd
/var/lib/edb/as12/data
[root@localhost data]# ls -l edb_wait_states
total 0
```

10.13 EDB Clone Schema

EDB Clone Schema

EDB Clone Schema is an extension module for Advanced Server that allows you to copy a schema and its database objects from a local or remote database (the source database) to a receiving database (the target database).

The source and target databases can be the same physical database, or different databases within the same database cluster, or separate databases running under different database clusters on separate database server bosts

Use the following functions with EDB Clone Schema:

- localcopyschema. This function makes a copy of a schema and its database objects from a source database back into the same database (the target), but with a different schema name than the original. Use this function when the original source schema and the resulting copy are to reside within the same database. See [localcopyschema](13_edb_clone_schema#localcopyschema) for information on the [localcopyschema function.
- localcopyschema_nb. This function performs the same purpose as localcopyschema, but as a background job, thus freeing up the terminal from which the function was initiated. This is referred to as a non-blocking function. See localcopyschema_nb <localcopyschema_nb for information on the localcopyschema_nb function.
- remotecopyschema. This function makes a copy of a schema and its database objects from a source database to a different target database. Use this function when the original source schema and the resulting copy are to reside in two, separate databases. The separate databases can reside in the same, or in different Advanced Server database clusters. See [remotecopyschema l(13 edb clone schema#remotecopyschema) for information on the [remotecopyschema function.
- remotecopyschema_nb. This function performs the same purpose as remotecopyschema, but as a background job, thus freeing up the terminal from which the function was initiated. This is referred to as a non-blocking function. See remotecopyschema_nb remotecopyschema_nb for information on the remotecopyschema_nb function.
- process_status_from_log. This function displays the status of the cloning functions. The information is obtained from a log file that must be specified when a cloning function is invoked. See process_status_from_log process_status_from_log for information on the process_status_from_log
- remove_log_file_and_job. This function deletes the log file created by a cloning function. This function can also be used to delete a job created by the non-blocking form of the function. See remove_log_file_and_job <remove_log_file_and_job for information on the remove_log_file_and_job function.

The database objects that can be cloned from one schema to another are the following:

- Data types
- Tables including partitioned tables, excluding foreign tables
- Indexes
- · Constraints
- Sequences
- · View definitions
- · Materialized views
- · Private synonyms
- · Table triggers, but excluding event triggers
- Rules
- Functions
- · Procedures
- Packages
- Comments for all supported object types
- Access control lists (ACLs) for all supported object types

The following database objects cannot be cloned:

- · Large objects (Postgres LOBs and BFILEs)
- · Logical replication attributes for a table
- · Database links
- · Foreign data wrappers
- · Foreign tables
- · Event triggers
- Extensions (For cloning objects that rely on extensions, see the third bullet point in the following limitations list.)

- · Row level security
- · Policies
- · Operator class

In addition, the following limitations apply:

- EDB Clone Schema is supported on Advanced Server only when a dialect of Compatible with Oracle is specified on the Advanced Server Dialect dialog during installation, or when the --redwood-like keywords are included during a text mode installation or cluster initialization.
- The source code within functions, procedures, triggers, packages, etc., are not modified after being copied
 to the target schema. If such programs contain coded references to objects with schema names, the
 programs may fail upon invocation in the target schema if such schema names are no longer consistent
 within the target schema.
- Cross schema object dependencies are not resolved. If an object in the target schema depends upon an object in another schema, this dependency is not resolved by the cloning functions.
- For remote cloning, if an object in the source schema is dependent upon an extension, then this extension must be created in the public schema of the remote database before invoking the remote cloning function.
- At most, 16 copy jobs can run in parallel to clone schemas, whereas each job can have at most 16 worker processes to copy table data in parallel.
- · Queries being run by background workers cannot be cancelled.

The following section describes how to set up EDB Clone Schema on the databases.

Setup Process

Several extensions along with the PL/Perl language must be installed on any database to be used as the source or target database by an EDB Clone Schema function.

In addition, some configuration parameters in the postgresql.conf file of the database servers may benefit from some modification.

The following is the setup instructions for these requirements.

Installing Extensions and PL/Perl

The following describes the steps to install the required extensions and the PL/Perl language.

These steps must be performed on any database to be used as the source or target database by an EDB Clone Schema function.

Step 1: The following extensions must be installed on the database:

- postgres_fdw
- dblink
- adminpack
- pgagent

Ensure that pgAgent is installed before creating the pgagent extension. On Linux, you can use the edb-as<xx>-pgagent RPM package where xx is the Advanced Server version number to install pgAgent. On Windows, use StackBuilder Plus to download and install pgAgent.

The previously listed extensions can be installed by the following commands if they do not already exist:

CREATE EXTENSION postgres_fdw SCHEMA public;

CREATE EXTENSION dblink SCHEMA public;

CREATE EXTENSION adminpack;

CREATE EXTENSION pgagent;

For more information about using the CREATE EXTENSION command, see the PostgreSQL core documentation at:

https://www.postgresgl.org/docs/current/static/sgl-createextension.html

Step 2: Modify the postgresql.conf file.

Modify the postgresql.conf file by adding \$libdir/parallel_clone to the shared_preload_libraries configuration parameter as shown by the following example:

shared_preload_libraries =

'\$libdir/dbms_pipe,\$libdir/dbms_aq,\$libdir/parallel_clone'

Step 3: The Perl Procedural Language (PL/Perl) must be installed on the database and the CREATE TRUSTED LANGUAGE procedural command must be run. For Linux, install PL/Perl using the edb-as<xx>-server-plperl RPM package where xx is the Advanced Server version number. For Windows, use the EDB Postgres Language Pack. For information on EDB Language Pack, see the EDB Postgres Language Pack Guide available at:

https://www.enterprisedb.com/edb-docs

Step 4: Connect to the database as a superuser and run the following command:

CREATE TRUSTED LANGUAGE plperl;

For more information about using the CREATE LANGUAGE command, see the PostgreSQL core documentation at:

https://www.postgresql.org/docs/current/static/sql-createlanguage.html

Setting Configuration Parameters

The following sections describe configuration parameters that may need to be altered in the postgresql.conf file.

Performance Configuration Parameters You may need to tune the system for copying a large schema as part of one transaction.

Tuning of configuration parameters is for the source database server referenced in a cloning function.

The configuration parameters in the postgresql.conf file that may need to be tuned include the following:

- work_mem. Specifies the amount of memory to be used by internal sort operations and hash tables before writing to temporary disk files.
- maintenance_work_mem. Specifies the maximum amount of memory to be used by maintenance operations, such as VACUUM, CREATE INDEX, and ALTER TABLE ADD FOREIGN KEY.
- max_worker_processes. Sets the maximum number of background processes that the system can support.
- checkpoint timeout. Maximum time between automatic WAL checkpoints, in seconds.
- **checkpoint_completion_target.** Specifies the target of checkpoint completion, as a fraction of total time between checkpoints.
- **checkpoint_flush_after.** Whenever more than checkpoint_flush_after bytes have been written while performing a checkpoint, attempt to force the OS to issue these writes to the underlying storage.
- max wal size. Maximum size to let the WAL grow to between automatic WAL checkpoints.
- max_locks_per_transaction. This parameter controls the average number of object locks allocated for each transaction; individual transactions can lock more objects as long as the locks of all transactions fit in the lock table.

For information about the configuration parameters, see the PostgreSQL core documentation at:

https://www.postgresql.org/docs/current/static/runtime-config.html

Status Logging Status logging by the cloning functions creates log files in the directory specified by the log_directory parameter in the postgresql.conf file for the database server to which you are connected when invoking the cloning function.

The default location is PGDATA/log as shown by the following:

This directory must exist prior to running a cloning function.

The name of the log file is determined by what you specify in the parameter list when invoking the cloning function.

To display the status from a log file, use the process_status_from_log function.

To delete a log file, use the remove_log_file_and_job function, or simply navigate to the log directory and delete it manually.

Installing EDB Clone Schema

The following are the directions for installing EDB Clone Schema.

These steps must be performed on any database to be used as the source or target database by an EDB Clone Schema function.

Step 1: If you had previously installed an older version of the edb_cloneschema extension, then you must run the following command:

```
DROP EXTENSION parallel_clone CASCADE;
```

This command also drops the edb_cloneschema extension.

Step 2: Install the extensions using the following commands:

CREATE EXTENSION parallel_clone SCHEMA public;

CREATE EXTENSION edb_cloneschema;

Make sure you create the parallel_clone extension before creating the edb_cloneschema extension.

Creating the Foreign Servers and User Mappings

When using one of the local cloning functions, local copyschema or local copyschema_nb, one of the required parameters includes a single, foreign server for identifying the database server along with its database that is the source and the receiver of the cloned schema.

When using one of the remote cloning functions, remotecopyschema or remotecopyschema_nb , two of the required parameters include two foreign servers. The foreign server specified as the first parameter identifies the source database server along with its database that is the provider of the cloned schema. The foreign server specified as the second parameter identifies the target database server along with its database that is the receiver of the cloned schema.

For each foreign server, a user mapping must be created. When a selected database superuser invokes a cloning function, that database superuser who invokes the function must have been mapped to a database user name and password that has access to the foreign server that is specified as a parameter in the cloning function.

For general information about foreign data, foreign servers, and user mappings, see the PostgreSQL core documentation at:

https://www.postgresql.org/docs/current/static/ddl-foreign-data.html

The following two sections describe how these foreign servers and user mappings are defined.

Foreign Server and User Mapping for Local Cloning Functions For the localcopyschema and localcopyschema_nb functions, the source and target schemas are both within the same database of the same database server. Thus, only one foreign server must be defined and specified for these functions. This foreign server is also referred to as the *local server*.

This server is referred to as the local server because this server is the one to which you must be connected when invoking the localcopyschema or localcopyschema_nb function.

The user mapping defines the connection and authentication information for the foreign server.

This foreign server and user mapping must be created within the database of the local server in which the cloning is to occur.

The database user for whom the user mapping is defined must be a superuser and the user connected to the local server when invoking an EDB Clone Schema function.

The following example creates the foreign server for the database containing the schema to be cloned, and to receive the cloned schema as well.

```
CREATE SERVER local_server FOREIGN DATA WRAPPER postgres_fdw OPTIONS(
host 'localhost',
port '5444',
dbname 'edb'
);
```

For more information about using the CREATE SERVER command, see the PostgreSQL core documentation at:

https://www.postgresql.org/docs/current/static/sql-createserver.html

The user mapping for this server is the following:

```
CREATE USER MAPPING FOR enterprisedb SERVER local_server
OPTIONS (
user 'enterprisedb',
password 'password'
);
```

For more information about using the CREATE USER MAPPING command, see the PostgreSQL core documentation at:

https://www.postgresgl.org/docs/current/static/sgl-createusermapping.html

The following psql commands show the foreign server and user mapping:

```
edb=# \des+
```

```
List of foreign servers
-[ RECORD 1 ]-----+
                | local_server
Name
0wner
                | enterprisedb
Foreign-data wrapper | postgres_fdw
Access privileges
                Т
Type
                Ι
Version
                1
               | (host 'localhost', port '5444', dbname 'edb')
FDW options
Description
edb=# \deu+
                 List of user mappings
Server
       | User name | FDW options
-----
local_server | enterprisedb | ("user" 'enterprisedb', password 'password')
(1 row)
```

When database superuser enterprisedb invokes a cloning function, the database user enterprisedb with its password is used to connect to local_server on the localhost with port 5444 to database edb.

In this case, the mapped database user, enterprisedb, and the database user, enterprisedb, used to connect to the local edb database happen to be the same, identical database user, but that is not an absolute requirement.

Foreign Server and User Mapping for Remote Cloning Functions For the remotecopyschema and remotecopyschema_nb functions, the source and target schemas are in different databases of either the same or different database servers. Thus, two foreign servers must be defined and specified for these functions.

The foreign server defining the originating database server and its database containing the source schema to be cloned is referred to as the *source server* or the *remote server*.

The foreign server defining the database server and its database to receive the schema to be cloned is referred to as the *target server* or the *local server*.

The target server is also referred to as the local server because this server is the one to which you must be connected when invoking the remotecopyschema or remotecopyschema_nb function.

The user mappings define the connection and authentication information for the foreign servers.

All of these foreign servers and user mappings must be created within the target database of the target/local server.

The database user for whom the user mappings are defined must be a superuser and the user connected to the local server when invoking an EDB Clone Schema function.

The following example creates the foreign server for the local, target database that is to receive the cloned schema.

```
CREATE SERVER tgt_server FOREIGN DATA WRAPPER postgres_fdw
OPTIONS(
host 'localhost',
port '5444',
dbname 'tatdb'
);
The user mapping for this server is the following:
CREATE USER MAPPING FOR enterprised SERVER tgt_server
OPTIONS (
user 'tgtuser',
password 'tgtpassword'
);
The following example creates the foreign server for the remote, source database that is to be the source for
the cloned schema.
CREATE SERVER src_server FOREIGN DATA WRAPPER postgres_fdw
OPTIONS(
host '192.168.2.28',
port '5444',
dbname 'srcdb'
);
The user mapping for this server is the following:
CREATE USER MAPPING FOR enterprised SERVER src_server
OPTIONS (
user 'srcuser',
password 'srcpassword'
);
The following psql commands show the foreign servers and user mappings:
tgtdb=# \des+
                        List of foreign servers
Name
                     | src_server
0wner
                     l tgtuser
Foreign-data wrapper | postgres_fdw
Access privileges
                    Ι
Type
```

Version

1

```
| (host '192.168.2.28', port '5444', dbname 'srcdb')
FDW options
Description
                 1
-[ RECORD 2]-----+------
                l tgt_server
Name
0wner
                 l tgtuser
Foreign-data wrapper | postgres_fdw
Access privileges
Type
Version
FDW options
                 | (host 'localhost', port '5444', dbname 'tgtdb')
Description
tgtdb=# \\deu+
                   List of user mappings
Server
         l User name
                    | FDW options
-----
                                     src_server | enterprisedb | ("user" 'srcuser', password 'srcpassword')
tqt_server | enterprisedb | ("user" 'tgtuser', password 'tgtpassword')
(2 rows)
```

When database superuser enterprisedb invokes a cloning function, the database user tgtuser with password tgtpassword is used to connect to tgt_server on the localhost with port 5444 to database tgtdb.

In addition, database user srcuser with password srcpassword connects to src_server on host 192.168.2.28 with port 5444 to database srcdb .

Note: Be sure the <code>pg_hba.conf</code> file of the database server running the source database <code>srcdb</code> has an appropriate entry permitting connection from the target server location (address <code>192.168.2.27</code> in the following example) connecting with the database user <code>srcuser</code> that was included in the user mapping for the foreign server <code>src_server</code> defining the source server and database.

```
title: "TYPE
                 DATABASE
                               USER
                                          ADDRESS
                                                           METHOD"
10.13 TYPE
               DATABASE
                                        ADDRESS
                                                         METHOD
                              USER
<div id="edb_clone_schema" class="registered_link"></div>
title: ""local" is for Unix domain socket connections only"
10.13 local is for Unix domain socket connections only
<div id="edb_clone_schema" class="registered_link"></div>
local
            all
                                                      md5
title: "IPv4 local connections:"
10.13 IPv4 local connections:
<div id="edb_clone_schema" class="registered_link"></div>
```

srcuser

EDB Clone Schema Functions

srcdb

host

The EDB Clone Schema functions are created in the edb_util schema when the parallel_clone and edb_cloneschema extensions are installed.

192.168.2.27/32

Verify the following conditions before using an EDB Clone Schema function:

- You are connected to the target or local database as the database superuser defined in the CREATE USER MAPPING command for the foreign server of the target or local database.
- The edb_util schema is in the search path, or the cloning function is to be invoked with the edb_util prefix .
- The target schema does not exist in the target database.
- When using the remote copy functions, if the *on_tblspace* parameter is to be set to true, then the target database cluster contains all tablespaces that are referenced by objects in the source schema, otherwise creation of the DDL statements for those database objects will fail in the target schema. This causes a failure of the cloning process.
- When using the remote copy functions, if the *copy_acls* parameter is to be set to true, then all roles that have GRANT privileges on objects in the source schema exist in the target database cluster, otherwise granting of privileges to those roles will fail in the target schema. This causes a failure of the cloning process.
- pgAgent is running against the target database if the non-blocking form of the function is to be used.

For information about pgAgent, see the pgAdmin documentation available at:

https://www.pgadmin.org/docs/pgadmin4/dev/pgagent.html

Note that pgAgent is provided as a component with Advanced Server.

localcopyschema

The localcopyschema function copies a schema and its database objects within a local database specified within the *source_fdw* foreign server from the source schema to the specified target schema within the same database.

```
localcopyschema(
*source_fdw* TEXT,
*source_schema* TEXT,
*target_schema* TEXT,
*log_filename* TEXT
[, *on_tblspace* BOOLEAN
[, *verbose_on* BOOLEAN
[, *copy_acls* BOOLEAN
[, *worker_count* INTEGER ]]]]
```

A BOOLEAN value is returned by the function. If the function succeeds, then true is returned. If the function fails, then false is returned.

The *source_fdw*, *source_schema*, *target_schema*, and *log_filename* are required parameters while all other parameters are optional.

Parameters

source_fdw

Name of the foreign server managed by the postgres_fdw foreign data wrapper from which database objects are to be cloned.

source_schema

Name of the schema from which database objects are to be cloned.

target_schema

Name of the schema into which database objects are to be cloned from the source schema.

log_filename

Name of the log file in which information from the function is recorded. The log file is created under the directory specified by the log_directory configuration parameter in the postgresql.conf file.

on tblspace

BOOLEAN value to specify whether or not database objects are to be created within their tablespaces. If false is specified, then the TABLESPACE clause is not included in the applicable CREATE DDL statement when added to the target schema. If true is specified, then the TABLESPACE clause is included in the CREATE DDL statement when added to the target schema. If the *on_tblspace* parameter is omitted, the default value is false.

verbose_on

BOOLEAN value to specify whether or not the DDLs are to be printed in *log_filename* when creating objects in the target schema. If false is specified, then DDLs are not printed. If true is specified, then DDLs are printed. If omitted, the default value is false.

copy_acls

BOOLEAN value to specify whether or not the access control list (ACL) is to be included while creating objects in the target schema. The access control list is the set of GRANT privilege statements. If false is specified, then the access control list is not included for the target schema. If true is specified, then the access control list is included for the target schema. If the copy_acls parameter is omitted, the default value is false.

worker_count

Number of background workers to perform the clone in parallel. If omitted, the default value is 1.

Example

The following example shows the cloning of schema edb containing a set of database objects to target schema edbcopy, both within database edb as defined by local_server.

The example is for the following environment:

- Host on which the database server is running: localhost
- Port of the database server: 5444
- Database source/target of the clone: edb
- Foreign server (local_server) and user mapping with the information of the preceding bullet points
- · Source schema: edb
- Target schema: edbcopy
- Database superuser to invoke localcopyschema: enterprisedb

Before invoking the function, the connection is made by database user enterprisedb to database edb.

```
(1 row)
 After the clone has completed, the following shows some of the database objects copied to the edbcopy
 edb=# SET search_path TO edbcopy;
 SET
 edb=# \dt+
 List of relations
 Schema | Name | Type | Owner | Size | Description
 ------
 edbcopy | dept | table | enterprisedb | 8192 bytes | edbcopy | emp | table | enterprisedb | 8192 bytes |
 edbcopy | jobhist | table | enterprisedb | 8192 bytes |
 (3 rows)
 edb=# \dv
 List of relations
 Schema | Name | Type | Owner
 -----
 edbcopy | salesemp | view | enterprisedb
 (1 row)
 edb=# \di
 List of relations
 Schema | Name | Type | Owner | Table
 -----
 edbcopy | dept_dname_uq| index | enterprisedb | dept
 edbcopy | jobhist_pk | index | enterprisedb | jobhist
 (4 rows)
 edb=# \ds
 List of relations
 Schema | Name | Type | Owner
 -----
 edbcopy | next_empno | sequence | enterprisedb
 (1 row)
 edb=# SELECT DISTINCT schema_name, name, type FROM user_source WHERE
 schema_name = 'EDBCOPY' ORDER BY type, name;
 schema_name | name
                                                                                                 l type
EDBCOPY | EMP_COMP | FUNCTION |
EDBCOPY | HIRE_CLERK | FUNCTION |
EDBCOPY | HIRE_SALESMAN | FUNCTION |
EDBCOPY | NEW_EMPNO | FUNCTION |
EDBCOPY | EMP_ADMIN | PACKAGE |
EDBCOPY | EMP_ADMIN | PACKAGE |
EDBCOPY | EMP_QUERY | PROCEDURE |
EDBCOPY | EMP_QUERY | PROCEDURE |
EDBCOPY | LIST_EMP | PROCEDURE |
EDBCOPY | SELECT_EMP | PROCEDURE |
EDBCOPY | EMP_SAL_TRIG | TRIGGER |
EDBCOPY | "RI_ConstraintTrigger_a_19991" | TRIGGER |
EDBCOPY | "RI_ConstraintTrigger_a_19992" | TRIGGER |
EDBCOPY | "RI_ConstraintTrigger_a_19999" | TRIGGER |
EDBCOPY | "RI_ConstraintTrigger_a_19999" | TRIGGER |
EDBCOPY | "RI_ConstraintTrigger_a_19999" | TRIGGER |
EDBCOPY | "RI_ConstraintTrigger_a_19999" | TRIGGER |
EDBCOPY | "RI_ConstraintTrigger_a_19999" | TRIGGER |
EDBCOPY | "RI_ConstraintTrigger_a_20000" | TRIGGER |
EDBCOPY | "RI_ConstraintTrigger_a_20000" | TRIGGER |
EDBCOPY | "RI_ConstraintTrigger_a_20000" | TRIGGER |
EDBCOPY | "RI_ConstraintTrigger_a_20000" | TRIGGER |
EDBCOPY | "RI_ConstraintTrigger_a_20000" | TRIGGER |
EDBCOPY | "RI_ConstraintTrigger_a_20000" | TRIGGER |
EDBCOPY | "RI_ConstraintTrigger_a_20000" | TRIGGER |
EDBCOPY | "RI_ConstraintTrigger_a_20000" | TRIGGER |
EDBCOPY | "RI_ConstraintTrigger_a_20000" | TRIGGER |
EDBCOPY | "RI_ConstraintTrigger_a_20000" | TRIGGER |
EDBCOPY | "RI_ConstraintTrigger_a_20000" | TRIGGER |
EDBCOPY | "RI_ConstraintTrigger_a_20000" | TRIGGER |
EDBCOPY | "RI_ConstraintTrigger_a_20000" | TRIGGER |
EDBCOPY | "RI_ConstraintTrigger_a_20000" | TRIGGER |
EDBCOPY | "RI_ConstraintTrigger_a_20000" | TRIGGER |
EDBCOPY | "RI_COnstraintTrigger_a_20000" | TRIGGER |
EDBCOPY | "RI_COnstraintTrigger_a_20000" | TRIGGER |
EDBCOPY | "RI_COnstraintTrigger_a_20000" | TRIGGER |
EDBCOPY | "RI_COnstraintTrigger_a_20000" | TRIGGER |
EDBCOPY | "RI_COnstraintTrigger_a_20000" | TRIGGER |
```

FINAL", "successfully cloned schema")

```
FDBCOPY
             | "RI_ConstraintTrigger_a_20005" | TRIGGER
             | "RI_ConstraintTrigger_c_19993" | TRIGGER
EDBCOPY
EDBCOPY
             | "RI_ConstraintTrigger_c_19994" | TRIGGER
             | "RI_ConstraintTrigger_c_20001" | TRIGGER
EDBCOPY
             | "RI_ConstraintTrigger_c_20002" | TRIGGER
EDBCOPY
             | "RI_ConstraintTrigger_c_20006" | TRIGGER
EDBCOPY
             | "RI_ConstraintTrigger_c_20007" | TRIGGER
EDBCOPY
EDBCOPY
             | USER_AUDIT_TRIG
                                               | TRIGGER
(24 rows)
```

localcopyschema_nb

The localcopyschema_nb function copies a schema and its database objects within a local database specified within the *source_fdw* foreign server from the source schema to the specified target schema within the same database, but in a non-blocking manner as a job submitted to pgAgent.

```
localcopyschema_nb(
*source_fdw* TEXT,
*source* TEXT,
*target* TEXT,
*log_filename* TEXT
[, *on_tblspace* BOOLEAN
[, *verbose_on* BOOLEAN
[, *copy_acls* BOOLEAN
[, *worker_count* INTEGER ]]]]
)
```

An INTEGER value job ID is returned by the function for the job submitted to pgAgent. If the function fails, then null is returned.

The source_fdw, source, target, and log_filename are required parameters while all other parameters are optional

After completion of the pgAgent job, remove the job with the remove_log_file_and_job function.

Parameters

source_fdw

Name of the foreign server managed by the postgres_fdw foreign data wrapper from which database objects are to be cloned.

source

Name of the schema from which database objects are to be cloned.

target

Name of the schema into which database objects are to be cloned from the source schema.

log_filename

Name of the log file in which information from the function is recorded. The log file is created under the directory specified by the log_directory configuration parameter in the postgresql.conf file.

on_tblspace

BOOLEAN value to specify whether or not database objects are to be created within their tablespaces. If false is specified, then the TABLESPACE clause is not included in the applicable CREATE DDL statement when added to the target schema. If true is specified, then the TABLESPACE clause is included in the CREATE DDL statement when added to the target schema. If the *on_tblspace* parameter is omitted, the default value is false.

verbose_on

BOOLEAN value to specify whether or not the DDLs are to be printed in *log_filename* when creating objects in the target schema. If false is specified, then DDLs are not printed. If true is specified, then DDLs are printed. If omitted, the default value is false.

```
copy_acls
```

BOOLEAN value to specify whether or not the access control list (ACL) is to be included while creating objects in the target schema. The access control list is the set of GRANT privilege statements. If false is specified, then the access control list is not included for the target schema. If true is specified, then the access control list is included for the target schema. If the copy_acls parameter is omitted, the default value is false.

```
worker_count
```

Number of background workers to perform the clone in parallel. If omitted, the default value is 1.

Example

The following command can be used to observe if pgAgent is running on the appropriate local database:

```
[root@localhost ~]# ps -ef | grep pgagent
root 4518 1 0 11:35 pts/1 00:00:00 pgagent -s /tmp/pgagent_edb_log
hostaddr=127.0.0.1 port=5444 dbname=edb user=enterprisedb
password=password
root 4525 4399 0 11:35 pts/1 00:00:00 grep --color=auto pgagent
```

If pgAgent is not running, it can be started as shown by the following. The pgagent program file is located in the bin subdirectory of the Advanced Server installation directory.

```
[root@localhost bin]# ./pgagent -l 2 -s /tmp/pgagent_edb_log
hostaddr=127.0.0.1 port=5444 dbname=edb user=enterprisedb
password=password
```

Note: The pgagent -1 2 option starts pgAgent in DEBUG mode, which logs continuous debugging information into the log file specified with the -s option. Use a lower value for the -1 option, or omit it entirely to record less information.

```
The localcopyschema_nb function returns the job ID shown as 4 in the example.
```

remotecopyschema

The remotecopyschema function copies a schema and its database objects from a source schema in the remote source database specified within the *source_fdw* foreign server to a target schema in the local target database specified within the *target_fdw* foreign server.

```
remotecopyschema(
*source_fdw* TEXT,
*target_fdw* TEXT,
*source_schema* TEXT,
*target_schema* TEXT,
*log_filename* TEXT
[, *on_tblspace* BOOLEAN
[, *verbose_on* BOOLEAN
[, *copy_acls* BOOLEAN
[, *worker_count* INTEGER ]]]]
)
```

A BOOLEAN value is returned by the function. If the function succeeds, then true is returned. If the function fails, then false is returned.

The source_fdw, target_fdw, source_schema, target_schema, and log_filename are required parameters while all other parameters are optional.

Parameters

source fdw

Name of the foreign server managed by the postgres_fdw foreign data wrapper from which database objects are to be cloned.

target_fdw

Name of the foreign server managed by the postgres_fdw foreign data wrapper to which database objects are to be cloned.

source_schema

Name of the schema from which database objects are to be cloned.

target_schema

Name of the schema into which database objects are to be cloned from the source schema.

log_filename

Name of the log file in which information from the function is recorded. The log file is created under the directory specified by the log_directory configuration parameter in the postgresql.conf file.

on_tblspace

BOOLEAN value to specify whether or not database objects are to be created within their tablespaces. If false is specified, then the TABLESPACE clause is not included in the applicable CREATE DDL statement when added to the target schema. If true is specified, then the TABLESPACE clause is included in the CREATE DDL statement when added to the target schema. If the *on_tblspace* parameter is omitted, the default value is false.

If true is specified and a database object has a TABLESPACE clause, but that tablespace does not exist in the target database cluster, then the cloning function fails.

```
verbose_on
```

BOOLEAN value to specify whether or not the DDLs are to be printed in *log_filename* when creating objects in the target schema. If false is specified, then DDLs are not printed. If true is specified, then DDLs are printed. If omitted, the default value is false.

copy_acls

BOOLEAN value to specify whether or not the access control list (ACL) is to be included while creating objects in the target schema. The access control list is the set of GRANT privilege statements. If false is specified, then the access control list is not included for the target schema. If true is specified, then the access control list is included for the target schema. If the copy_acls parameter is omitted, the default value is false.

If true is specified and a role with GRANT privilege does not exist in the target database cluster, then the cloning function fails.

worker_count

Number of background workers to perform the clone in parallel. If omitted, the default value is 1.

Example

The following example shows the cloning of schema srcschema within database srcdb as defined by src_server to target schema tgtschema within database tgtdb as defined by tgt_server.

The source server environment:

- Host on which the source database server is running: 192.168.2.28
- Port of the source database server: 5444
- Database source of the clone: srcdb
- Foreign server (src_server) and user mapping with the information of the preceding bullet points
- Source schema: srcschema

The target server environment:

- Host on which the target database server is running: localhost
- Port of the target database server: 5444
- Database target of the clone: tgtdb
- Foreign server (tgt_server) and user mapping with the information of the preceding bullet points
- Target schema: tgtschema
- Database superuser to invoke remotecopyschema: enterprisedb

Before invoking the function, the connection is made by database user enterprised to database tgtdb . A worker_count of 4 is specified for this function.

```
tqtdb=# SELECT edb_util.remotecopyschema
('src_server','tgt_server','srcschema','tgtschema','clone_rmt_src_tgt',worker_count
=> 4);
remotecopyschema
t
(1 row)
The following displays the status from the log file during various points in the cloning process:
tgtdb=# SELECT edb_util.process_status_from_log('clone_rmt_src_tgt');
process_status_from_log
(RUNNING, "28-JUN-17 13:18:05.299953 -04:00", 4021, INFO, "STAGE:
DATA-COPY","[0][0] successfully copied data in
[tgtschema.pgbench_tellers]
")
(1 row)
tqtdb=# SELECT edb_util.process_status_from_log('clone_rmt_src_tqt');
process_status_from_log
```

662

```
(RUNNING, "28-JUN-17 13:18:06.634364 -04:00", 4022, INFO, "STAGE:
DATA-COPY", "[0][1] successfully copied data in
[tgtschema.pgbench_history]
")
(1 row)
tgtdb=# SELECT edb_util.process_status_from_log('clone_rmt_src_tgt');
process_status_from_log
·_____
(RUNNING, "28-JUN-17 13:18:10.550393 -04:00", 4039, INFO, "STAGE:
POST-DATA", "CREATE PRIMARY KEY CONSTRAINT pgbench_tellers_pkey
successful"
)
(1 row)
tgtdb=# SELECT edb_util.process_status_from_log('clone_rmt_src_tgt');
process_status_from_log
(FINISH, "28-JUN-17 13:18:12.019627 -04:00", 4039, INFO, "STAGE:
FINAL", "successfully clone schema into tgtschema")
(1 row)
The following shows the cloned tables:
tatdb=# \dt+
List of relations
                   | Type | Owner | | Size | Description
Schema I Name
tgtschema | pgbench_accounts | table | enterprisedb | 256 MB | |
tgtschema | pgbench_branches | table | enterprisedb | 8192 bytes|
tqtschema | pqbench_history | table | enterprisedb | 25 MB |
tqtschema | pqbench_tellers | table | enterprisedb | 16 kB
(4 rows)
When the remotecopyschema function was invoked, four background workers were specified.
The following portion of the log file clone_rmt_src_tgt shows the status of the parallel data copying
operation using four background workers:
Wed Jun 28 13:18:05.232949 2017 EDT: [4019] INFO: [STAGE: DATA-COPY] [0]
table count [4]
Wed Jun 28 13:18:05.233321 2017 EDT: [4019] INFO: [STAGE: DATA-COPY]
[0][0] worker started to copy data
Wed Jun 28 13:18:05.233640 2017 EDT: [4019] INFO: [STAGE: DATA-COPY]
[0][1] worker started to copy data
Wed Jun 28 13:18:05.233919 2017 EDT: [4019] INFO: [STAGE: DATA-COPY]
[0][2] worker started to copy data
Wed Jun 28 13:18:05.234231 2017 EDT: [4019] INFO: [STAGE: DATA-COPY]
[0][3] worker started to copy data
Wed Jun 28 13:18:05.298174 2017 EDT: [4024] INFO: [STAGE: DATA-COPY]
[0][3] successfully copied data in [tgtschema.pgbench_branches]
Wed Jun 28 13:18:05.299913 2017 EDT: [4021] INFO: [STAGE: DATA-COPY]
[0][0] successfully copied data in [tqtschema.pgbench_tellers]
Wed Jun 28 13:18:06.634310 2017 EDT: [4022] INFO: [STAGE: DATA-COPY]
[0][1] successfully copied data in [tgtschema.pgbench_history]
Wed Jun 28 13:18:10.477333 2017 EDT: [4023] INFO: [STAGE: DATA-COPY]
[0][2] successfully copied data in [tgtschema.pgbench_accounts]
Wed Jun 28 13:18:10.477609 2017 EDT: [4019] INFO: [STAGE: DATA-COPY] [0]
all workers finished [4]
```

```
Wed Jun 28 13:18:10.477654 2017 EDT: [4019] INFO: [STAGE: DATA-COPY] [0] copy done [4] tables
Wed Jun 28 13:18:10.493938 2017 EDT: [4019] INFO: [STAGE: DATA-COPY] successfully copied data into tgtschema
```

Note that the DATA-COPY log message includes two, square bracket numbers (for example, [0][3]).

The first number is the job index whereas the second number is the worker index. The worker index values range from 0 to 3 for the four background workers.

In case two clone schema jobs are running in parallel, the first log file will have 0 as the job index whereas the second will have 1 as the job index.

remotecopyschema_nb

The remotecopyschema_nb function copies a schema and its database objects from a source schema in the remote source database specified within the *source_fdw* foreign server to a target schema in the local target database specified within the *target_fdw* foreign server, but in a non-blocking manner as a job submitted to pgAgent.

```
remotecopyschema_nb(
*source_fdw* TEXT,
*target_fdw* TEXT,
*source* TEXT,
*target* TEXT,
*log_filename* TEXT
[, *on_tblspace* BOOLEAN
[, *verbose_on* BOOLEAN
[, *copy_acls* BOOLEAN
[, *worker_count* INTEGER ]]]]
)
```

An INTEGER value job ID is returned by the function for the job submitted to pgAgent. If the function fails, then null is returned.

The source_fdw, target_fdw, source, target, and log_filename are required parameters while all other parameters are optional.

After completion of the pgAgent job, remove the job with the remove_log_file_and_job function.

Parameters

source_fdw

Name of the foreign server managed by the postgres_fdw foreign data wrapper from which database objects are to be cloned.

target_fdw

Name of the foreign server managed by the postgres_fdw foreign data wrapper to which database objects are to be cloned.

source

Name of the schema from which database objects are to be cloned.

taraei

Name of the schema into which database objects are to be cloned from the source schema.

log_filename

Name of the log file in which information from the function is recorded. The log file is created under the directory specified by the log_directory configuration parameter in the postgresql.conf file.

on_tblspace

BOOLEAN value to specify whether or not database objects are to be created within their tablespaces. If false is specified, then the TABLESPACE clause is not included in the applicable CREATE DDL statement when added to the target schema. If true is specified, then the TABLESPACE clause is included in the CREATE DDL statement when added to the target schema. If the *on_tblspace* parameter is omitted, the default value is false.

If true is specified and a database object has a TABLESPACE clause, but that tablespace does not exist in the target database cluster, then the cloning function fails.

```
verbose_on
```

BOOLEAN value to specify whether or not the DDLs are to be printed in *log_filename* when creating objects in the target schema. If false is specified, then DDLs are not printed. If true is specified, then DDLs are printed. If omitted, the default value is false.

```
copy_acls
```

BOOLEAN value to specify whether or not the access control list (ACL) is to be included while creating objects in the target schema. The access control list is the set of GRANT privilege statements. If false is specified, then the access control list is not included for the target schema. If true is specified, then the access control list is included for the target schema. If the copy_acls parameter is omitted, the default value is false.

If true is specified and a role with GRANT privilege does not exist in the target database cluster, then the cloning function fails.

```
worker_count
```

Number of background workers to perform the clone in parallel. If omitted, the default value is 1.

Example

(1 row)

The following command starts pgAgent on the target database tgtdb. The pgagent program file is located in the bin subdirectory of the Advanced Server installation directory.

```
[root@localhost bin]# ./pgagent -l 1 -s /tmp/pgagent_tgtdb_log hostaddr=127.0.0.1 port=5444 user=enterprisedb dbname=tgtdb password=password
```

The remotecopyschema_nb function returns the job ID shown as 2 in the example.

process_status_from_log

The process_status_from_log function provides the status of a cloning function from its log file.

```
process_status_from_log (
*log_file* TEXT
)
```

The function returns the following fields from the log file:

Table - Clone Schema Log File

Field Name Description

status Displays either STARTING, RUNNING, FINISH, or FAILED.

execution_time When the command was executed. Displayed in timestamp format.

pid Session process ID in which clone schema is getting called.

level Displays either INFO, ERROR, or SUCCESSFUL.

stage Displays either STARTUP, INITIAL, DDL-COLLECTION, PRE-DATA, DATA-COPY, POST-DATA, or FINA

message Information respective to each command or failure.

Parameters

log_file

Name of the log file recording the cloning of a schema as specified when the cloning function was invoked.

Example

```
The following shows usage of the process_status_from_log function:
```

remove_log_file_and_job

The remove_log_file_and_job function performs cleanup tasks by removing the log files created by the schema cloning functions and the jobs created by the non-blocking functions.

```
remove_log_file_and_job (
{ *log_file* TEXT |
*job_id* INTEGER |
*log_file* TEXT, *job_id* INTEGER
}
)
```

Values for any or both of the two parameters may be specified when invoking the remove_log_file_and_job function:

- If only *log_file* is specified, then the function will only remove the log file.
- If only *job_id* is specified, then the function will only remove the job.
- If both are specified, then the function will remove the log file and the job.

Parameters

log_file

Name of the log file to be removed.

job_id

Job ID of the job to be removed.

Example

```
The following examples removes only the log file, given the log filename.
edb=# SELECT edb_util.remove_log_file_and_job ('clone_edb_edbcopy');
remove_log_file_and_job
t
(1 row)
The following example removes only the job, given the job ID.
edb=# SELECT edb_util.remove_log_file_and_job (3);
remove_log_file_and_job
t
(1 row)
The following example removes the log file and the job, given both values:
tgtdb=# SELECT edb_util.remove_log_file_and_job ('clone_rmt_src_tgt',2);
remove_log_file_and_job
______
t
(1 row)
```

10.14 Enhanced SQL and Other Miscellaneous Features

Enhanced SQL and Other Miscellaneous Features

Advanced Server includes enhanced SQL functionality and various other features that provide additional flexibility and convenience. This chapter discusses some of these additions.

COMMENT

In addition to commenting on objects supported by the PostgreSQL COMMENT command, Advanced Server supports comments on additional object types. The complete supported syntax is:

```
COMMENT ON
AGGREGATE <aggregate_name> ( <aggregate_signature> ) |
CAST (<source_type> AS <target_type>) |
COLLATION <object_name> |
COLUMN <relation_name>.<column_name> |
CONSTRAINT <constraint_name> ON <table_name> |
CONSTRAINT <constraint_name> ON DOMAIN <domain_name> |
CONVERSION <object_name> |
DATABASE <object_name> |
DOMAIN <object_name> |
EXTENSION <object_name> |
EVENT TRIGGER <object_name> |
FOREIGN DATA WRAPPER <object_name> |
FOREIGN TABLE <object_name> |
FUNCTION <func_name> ([[<argmode>] [<argname>] <argtype> [,...]])|
INDEX <object_name> |
LARGE OBJECT <large_object_oid> |
MATERIALIZED VIEW <object_name> |
OPERATOR <operator_name> (left_type, right_type) |
OPERATOR CLASS <object_name> USING <index_method> |
OPERATOR FAMILY <object_name> USING <index_method> |
PACKAGE <object_name>
POLICY <policy_name> ON <table_name> |
[ PROCEDURAL ] LANGUAGE <object_name> |
```

```
PROCEDURE  [([[<argmode>] [<argname>] <argtype> [, ...]])]
PUBLIC SYNONYM <object_name>
ROLE <object_name> |
RULE <rule_name> ON <table_name> I
SCHEMA <object_name> |
SEQUENCE <object_name> |
SERVER <object_name> |
TABLE <object_name> |
TABLESPACE <object_name> |
TEXT SEARCH CONFIGURATION <object_name> |
TEXT SEARCH DICTIONARY <object_name> |
TEXT SEARCH PARSER <object_name> |
TEXT SEARCH TEMPLATE <object_name> |
TRANSFORM FOR <type_name> LANGUAGE <lang_name> |
TRIGGER <trigger_name> ON <table_name> |
TYPE <object_name> |
VIEW <object_name>
} IS <'text'>
where aggregate_signature is:
* |
[ <argmode> ] [ <argname> ] <argtype> [ , ... ] |
[ [ <argmode> ] [ <argname> ] <argtype> [ , ... ] ]
ORDER BY [ <argmode> ] [ <argname> ] <argtype> [ , ... ]
Parameters
object_name
     The name of the object on which you are commenting.
AGGREGATE <aggregate_name> (<aggregate_signature>)
     Include the AGGREGATE clause to create a comment about an aggregate. aggregate_name spec-
     ifies the name of an aggregate, and aggregate_signature specifies the associated signature in one
     of the following forms:
* |
[ <argmode> ] [ <argname> ] <argtype> [ , ... ] |
[ [ <argmode> ] [ <argname> ] <argtype> [ , ... ] ]
ORDER BY [ <argmode> ] [ <argname> ] <argtype> [ , ... ]
Where *argmode* is the mode of a function, procedure, or aggregate argument, argmode may be ``IN``, ``OUT``, ``INOUT``, or ``VARIADIC``. If omitted, the
default is ``IN``.
*argname* is the name of an aggregate argument.
*argtype* is the data type of an aggregate argument.
CAST (<source_type> AS <target_type>)
     Include the CAST clause to create a comment about a cast. When creating a comment about a
     cast, source_type specifies the source data type of the cast, and target_type specifies the target
     data type of the cast.
[COLUMN](#relation name>.<column name)
```

[CONSTRAINT](#constraint_name>ON <table_name) [CONSTRAINT](#constraint_name>ON DOMAIN <do-main_name)

Include the COLUMN clause to create a comment about a column. *column_name* specifies name of the column to which the comment applies. *relation_name* is the table, view, composite type, or

foreign table in which a column resides.

Include the CONSTRAINT clause to add a comment about a constraint. When creating a comment about a constraint, *constraint_name* specifies the name of the constraint. *table_name* or *domain_name* specifies the name of the table or domain on which the constraint is defined.

FUNCTION <func_name> ([[<argmode>] [<argname>] <argtype> [,...]])

Include the FUNCTION clause to add a comment about a function. *func_name* specifies the name of the function. *argmode* specifies the mode of the function. *argmode* may be IN, OUT, INOUT, or VARIADIC. If omitted, the default is IN. *argname* specifies the name of a function, procedure, or aggregate argument. *argtype* specifies the data type of a function, procedure, or aggregate argument.

large_object_oid

large_object_oid is the system-assigned OID of the large object about which you are commenting.

OPERATOR <operator_name> (left_type, right_type)

Include the OPERATOR clause to add a comment about an operator. *operator_name* specifies the (optionally schema-qualified) name of an operator on which you are commenting. *left_type* and *right_type* are the (optionally schema-qualified) data type(s) of the operator's arguments.

[OPERATOR CLASS](#object_name> USING <index_method)

Include the OPERATOR CLASS clause to add a comment about an operator class. *object_name* specifies the (optionally schema-qualified) name of an operator on which you are commenting. *index_method* specifies the associated index method of the operator class.

[OPERATOR FAMILY](#object_name> USING <index_method)

Include the OPERATOR FAMILY clause to add a comment about an operator family. *object_name* specifies the (optionally schema-qualified) name of an operator family on which you are commenting. *index_method* specifies the associated index method of the operator family.

[POLICY](#policy_name>ON <table_name)

Include the POLICY clause to add a comment about a policy. *policy_name* specifies the name of the policy, and *table_name* specifies the table that the policy is associated with.

PROCEDURE [([[<argmode>] [<argname>] <argtype> [,...]])]

Include the PROCEDURE clause to add a comment about a procedure. *proc_name* specifies the name of the procedure. *argmode* specifies the mode of the procedure. *argmode* may be IN , OUT , INOUT , or VARIADIC . If omitted, the default is IN . *argname* specifies the name of a function, procedure, or aggregate argument. *argtype* specifies the data type of a function, procedure, or aggregate argument.

[RULE](#rule_name> ON <table_name)

Include the RULE clause to specify a COMMENT on a rule. *rule_name* specifies the name of the rule, and *table_name* specifies the name of the table on which the rule is defined.

[TRANSFORM FOR](#type_name> LANGUAGE < lang_name)

Include the TRANSFORM FOR clause to specify a COMMENT on a TRANSFORM . *type_name* specifies the name of the data type of the transform and *lang_name* specifies the name of the language of the transform.

[TRIGGER](#trigger_name> ON <table_name)

Include the TRIGGER clause to specify a COMMENT on a trigger. *trigger_name* specifies the name of the trigger, and *table_name* specifies the name of the table on which the trigger is defined.

text

The comment, written as a string literal or NULL to drop the comment.

Notes:

Names of tables, aggregates, collations, conversions, domains, foreign tables, functions, indexes, operators, operator classes, operator families, packages, procedures, sequences, text search objects, types, and views can be schema-qualified.

Example:

The following example adds a comment to a table named new_emp:

COMMENT ON TABLE new_emp IS 'This table contains information about new employees.';

For more information about using the COMMENT command, please see the PostgreSQL core documentation at:

https://www.postgresql.org/docs/current/static/sql-comment.html

Output of Function version()

The text string output of the version() function displays the name of the product, its version, and the host system on which it has been installed.

For Advanced Server, the version() output is in a format similar to the PostgreSQL community version in that the first text word is *PostgreSQL* instead of *EnterpriseDB* as in Advanced Server version 10 and earlier.

The general format of the version() output is the following:

PostgreSQL \$PG_VERSION_EXT (EnterpriseDB Advanced Server \$PG_VERSION) on \$host

So for the current Advanced Server the version string appears as follows:

In contrast, for Advanced Server 10, the version string was the following:

```
version
-------
```

EnterpriseDB 10.4.9 on x86_64-pc-linux-gnu, compiled by gcc (GCC) 4.4.7 20120313 (Red Hat 4.4.7-18), 64-bit (1 row)

Logical Decoding on Standby

edb=# select version();

Logical decoding on a standby server allows you to create a logical replication slot on a standby server that can respond to API operations such as get, peek, advance, etc..

For more information about the LOGICAL DECODING , please refer to the PostgreSQL core documentation available at:

https://www.postgresql.org/docs/current/logicaldecoding-explanation.html

For a logical slot on a standby server to work, the hot_standby_feedback parameter must be set to ON on the standby. The hot_standby_feedback parameter prevents VACCUM from removing recently-dead rows that are required by an existing logical replication slot on the standby server. If a slot conflict occurs on the standby, the slots will be dropped.

For logical decoding on a standby to work, wal_level must be set to logical on both the primary and standby server. If wal_level is set to a value other than logical, then slots are not created. If you set wal_level

to a value other than logical on primary and if there are existing logical slots on standby, such slots are dropped and new slots cannot be created.

When transactions are written to the primary server, the activity will trigger the creation of a logical slot on the standby server. If a primary server is idle, creating a logical slot on a standby server may take noticeable time.

For more information about functions that support replication and logical decoding example, please refer to the PostgreSQL documentation available at:

https://www.postgresql.org/docs/current/functions-admin.html#FUNCTIONS-REPLICATION https://www.postgresql.org/docs/current/logicaldecoding-example.html

10.15 System Catalog Tables

System Catalog Tables

The following system catalog tables contain definitions of database objects. The layout of the system tables is subject to change, if you are writing an application that depends on information stored in the system tables, it would be prudent to use an existing catalog view, or create a catalog view to isolate the application from changes to the system table.

edb_dir

The edb_dir table contains one row for each alias that points to a directory created with the CREATE DIRECTORY command. A directory is an alias for a pathname that allows a user limited access to the host file system.

You can use a directory to fence a user into a specific directory tree within the file system. For example, the UTL_FILE package offers functions that permit a user to read and write files and directories in the host file system, but only allows access to paths that the database administrator has granted access to via a CREATE DIRECTORY command.

Column	Туре	Modifiers	Description
dirname	"name" oid text aclitem[]	not null	The name of the alias.
dirowner dirpath diracl		not null	The OID of the user that owns the alias. The directory name to wh

edb_all_resource_groups

The edb_all_resource_groups table contains one row for each resource group created with the CREATE RESOURCE GROUP command and displays the number of active processes in each resource group.

Column	Т
group_name active_processes cpu_rate_limit per_process_cpu_rate_limit dirty_rate_limit per_process_dirty_rate_limit	"r

edb_policy

The edb_policy table contains one row for each policy.

edb_profile

The edb_profile table stores information about the available profiles. edb_profiles is shared across all databases within a cluster.

Column

oid prfname prffailedloginattempts prfpasswordlocktime prfpasswordlifetime prfpasswordgracetime prfpasswordreusetime prfpasswordverifyfuncdb

Column	
prfpasswordverifyfunc	

edb_redaction_column

The catalog edb_redaction_column stores information of data redaction policy attached to the columns of the table.

Column	Туре	References	Description
oid	oid		Row identifier (hidder
rdpolicyid	oid	edb_redaction_policy.oid	The data redaction po
rdrelid	oid	pg_class.oid	The table that the des
rdattnum rdscope rdexception rdfuncexpr	int2 int2 pg_node_tree	pg_attribute.attnum	The number of the de

Note: The described column will be redacted if the redaction policy edb_redaction_column.rdpolicyid on the table is enabled and the redaction policy expression true. edb_redaction_policy.rdexpr evaluates to

edb_redaction_policy

The catalog edb_redaction_policy stores information of the redaction policies for tables.

Column	Туре	References	Description
oid rdname rdrelid rdenable rdexpr	oid name oid boolean pg_node_tree	pg_class.oid	Row identifier (hidden attribute, must be explicitly sel The table to which the data redaction policy applies I

Note: The data redaction policy applies for the table if it is enabled and the expression ever evaluated true.

edb_resource_group

The edb_resource_group table contains one row for each resource group created with the CREATE RESOURCE GROUP command.

Column	Type	Modifiers	Description		
rgrpname rgrpcpuratelimit	"name" float8	not null not null	The name of the resource group. Maximum CPU rate limit for a resource group.	0	means no limit.
rgrpdirtyratelimit	float8	not null	Maximum dirty rate limit for a resource group.	0	means no limit.

edb_variable

The edb_variable table contains one row for each package level variable (each variable declared within a package).

pg_synonym

The pg_synonym table contains one row for each synonym created with the CREATE SYNONYM command or CREATE PUBLIC SYNONYM command.

Column	Type	Modifiers	Description
synname	"name"	not null	The name of the synonym. Replaces synowner. Contains the OID of the pg_namespace row where the OID of the user that owns the synonym.
synnamespace	oid	not null	
synowner	oid	not null	

Column	Туре	Modifiers	Description
synobjschema	"name"	not null	The schema in which the referenced object is defined. The name of the referenced object. The (optional) name of the database li
synobjname synlink	"name" text	not null	

product_component_version

The product_component_version table contains information about feature compatibility, an application can query this table at installation or run time to verify that features used by the application are available with this deployment.

Column	Туре	Description
product version status	character varying (74) character varying (74) character varying (74)	The name of the product. The version number of the product. The status of the release.

10.16 Advanced Server Keywords

Advanced Server Keywords

A keyword is a word that is recognized by the Advanced Server parser as having a special meaning or association. You can use the pg_get_keywords() function to retrieve an up-to-date list of the Advanced Server keywords:

acctg=# acctg=# SELECT word	* FRC	M pg_get_k catcode	-	ds(); catdesc	
abort absolute	 		-	unreserved unreserved	
access	l	Ü		unreserved	

pg_get_keywords returns a table containing the keywords recognized by Advanced Server:

- The word column displays the keyword.
- The catcode column displays a category code.
- The catdesc column displays a brief description of the category to which the keyword belongs.

Note that any character can be used in an identifier if the name is enclosed in double quotes. You can selectively query the pg_get_keywords() function to retrieve an up-to-date list of the Advanced Server keywords that belong to a specific category:

```
SELECT * FROM pg_get_keywords() WHERE catcode = 'code';
```

Where code is:

- R The word is reserved. Reserved keywords may never be used as an identifier, they are reserved for use by the server.
- U The word is unreserved. Unreserved words are used internally in some contexts, but may be used as a name for a database object.
- T The word is used internally, but may be used as a name for a function or type.
- C The word is used internally, and may not be used as a name for a function or type.

For more information about Advanced Server identifiers and keywords, please refer to the PostgreSQL core documentation at:

https://www.postgresql.org/docs/current/static/sql-syntax-lexical.html

10.17 Conclusion

EDB Postgres Advanced Server Guide Copyright © 2007 - 2020 EnterpriseDB Corporation. All rights reserved. EnterpriseDB Corporation 34 Crosby Drive, Suite 201, Bedford, MA 01730, USA

T +1 781 357 3390 F +1 978 467 1307 E info@enterprisedb.com www.enterprisedb.com

- EnterpriseDB and Postgres Enterprise Manager are registered trademarks of EnterpriseDB Corporation. EDB and EDB Postgres are trademarks of EnterpriseDB Corporation. Oracle is a registered trademark of Oracle, Inc. Other trademarks may be trademarks of their respective owners.
- EDB designs, establishes coding best practices, reviews, and verifies input validation for the logon UI for EDB Postgres products where present. EDB follows the same approach for additional input components, however the nature of the product may require that it accepts freeform SQL, WMI or other strings to be entered and submitted by trusted users for which limited validation is possible. In such cases it is not possible to prevent users from entering incorrect or otherwise dangerous inputs.
- EDB reserves the right to add features to products that accept freeform SQL, WMI or other potentially dangerous inputs from authenticated, trusted users in the future, but will ensure all such features are designed and tested to ensure they provide the minimum possible risk, and where possible, require superuser or equivalent privileges.
- EDB does not warrant that we can or will anticipate all potential threats and therefore our process cannot fully guarantee that all potential vulnerabilities have been addressed or considered.