LSP PlayerKit

Version v1.3.1 · generated from README

> A desktop toolbox for LSP server players. It merges the Universal Pearl Cannon Configurator, the Border Cannon Configurator, a Material Converter, Puppet Logistics and a Slime Chunk Finder into one app.
> Everything runs locally — no network, no uploads.
> Download the latest build from Baidu Netdisk (code `1234`). 😘 😘 😘

简体中文 · Adding a tool

Contents

- LSP PlayerKit
  - Contents
  - Download
  - 1. Quick start
  - 2. Pearl cannon
    - 2.1 Usage
    - 2.2 Settings
  - 3. Border cannon
    - 3.1 Usage
    - 3.2 Settings
  - 4. Material converter
    - 4.1 Import a material list
    - 4.2 Search and sorting
    - 4.3 Stack size: default and batch
    - 4.4 Ignoring materials
    - 4.5 Conversion result
    - 4.6 Loading plan
    - 4.7 Export CSV
    - 4.8 Settings
  - 5. Puppet Logistics
    - 5.1 Stations
    - 5.2 Generating commands
    - 5.3 Running commands (optional)

    - 5.4 Ledger
    - 5.5 Settings
  - 6. Slime chunk finder
    - 6.1 Usage
    - 6.2 Map and results
    - 6.3 Large areas and performance
    - 6.4 Settings
  - 7. Settings
  - 8. Data and storage
  - 9. Calculation notes and limitations
  - Bundled mini-tools
  - Stack
  - License

Download

The latest build is shared on Baidu Netdisk:

Item	Value
Current version	**v1.3.0**
Link	https://pan.baidu.com/s/1V3FcoPrWUt3bGQZ-vHqBZg?pwd=1234
Access code	`1234`

---


1. Quick start

Unzip the downloaded package and double-click `LSP_PlayerKit.exe`. Python and Node are not required.

The window has three parts:

- **Left rail**: Pearl Cannon, Border Cannon, Material Converter, Puppet Logistics, Slime Chunk Finder, a "Coming soon" placeholder, and About.
- **Top bar**: active tool name and description, language (English / 简体中文 / 繁體中文), light/dark theme, and the settings gear.
- **Workspace**: parameters on the left, results on the right.

Shortcuts: `Ctrl+1` … `Ctrl+5` switch tools, `Ctrl+,` opens settings. Window size and the maximized state are remembered.



2. Pearl cannon

2.1 Usage


Start from **Input pearl coordinates**:

1. Fill in **muzzle X / Z**, **target X / Z** and **max TNT**.
2. Pick a **launch mode**: Flat or Arc (Arc is disabled if you turn off “Arc enabled” in settings).
3. The **direction** compass points at the result automatically after a calculation; you can also pick one of the four directions manually, which shows a “Manual” badge.
4. Click **Calculate TNT**.


Results and actions:

- Columns: **Distance error / Flight time / Blue TNT / Red TNT / Total TNT**, sorted by **flight time ascending** by default. Click the **Distance error** or **Flight time** header to sort; click again to reverse.
- Selecting a row shows the blue and red TNT array breakdown at the bottom, e.g. `20 + 10 + 2 + 1 = 33`; **Copy** puts it on the clipboard.
- **Simulate** steps the pearl tick by tick for the selected configuration and switches to the **Trace** tab: columns are **tick / X / Y / Z**, and the expected arrival tick is highlighted in orange and scrolled into view.

- **Manual simulation**: enter **blue / red TNT counts**, pick a direction on the compass and press **Simulate counts** — no target calculation needed. The trace jumps to the landing tick and reports the landing X / Z and horizontal distance (Flat lands at Y ≤ 0, Arc at Y ≤ 128). The trace list still starts at row 1 (0 gt); the landing row stays highlighted.
- **Save as default** writes the current muzzle, target, max TNT and launch mode back to settings; **Fill from defaults** overwrites the inputs with the saved values.



Tick	X	Y	Z
0	-31.938	178.347	-8.063
1	2014.986	174.827	2034.040
2	4041.440	171.312	4055.722
3	6047.629	167.802	6057.187
4	8033.757	164.298	8038.637
5	10000.023	160.798	10000.272
6	11946.626	157.304	11942.292
7	13873.764	153.814	13864.891
8	15781.630	150.329	15768.264
9	17670.418	146.849	17652.604
10	19540.318	143.374	19518.100
11	21391.519	139.904	21364.941
12	23224.207	136.438	23193.314
13	25038.569	132.977	25003.403
14	26834.788	129.521	26795.391
15	28613.044	126.069	28569.459
16	30373.517	122.621	30325.787
17	32116.386	119.179	32064.551
18	33841.826	115.740	33785.928
19	35550.012	112.306	35490.091



2.2 Settings

Open Settings → Tool options:

Setting	Description
Max TNT	Upper bound for one calculation, default 3640
TNT per array	TNT equivalent of one array, default 260
Muzzle X / Z	Default muzzle position, default `-31.9375 / -8.0625`
Target X / Z	Target coordinates pre-filled when the tool opens, default `0 / 0`
Launch mode	Default Flat or Arc
Arc enabled	When off, the Arc mode is unavailable
Flat: XZ motion / Y motion / initial Y motion / initial Y position	Flat trajectory parameters measured in game — **do not change casually**
Arc: the same four	Arc trajectory parameters

Settings apply immediately. The numbers are line-by-line compatible with the legacy `LSP_PearlCannonConfig`; changing the motion parameters changes the results.

3. Border cannon

3.1 Usage


The inputs are two separate cards, so the destination is hard to type into the muzzle by mistake:

1. **Muzzle (pearl start position)**: X / Y / Z.
2. **Destination (pearl landing)**: X / Y / Z.
3. **Expected flight time** in gt.


Click **Calculate TNT**; the table lists three TNT charges and a direction per tick (100 rows by default). Selecting a row shows the **configuration decode** panel:

- **Predicted landing coordinates** (X / Z, three decimals)
- **minor** (remaining TNT) and **major** (780-charge) breakdowns for each of the three TNT, e.g. `371 = 260 + 80 + 20 + 10 + 1`, `78 = 40 + 20 + 10 + 8`
- three-axis momentum, plus one-click copy of the full decode text

You can also skip the calculation: enter the three TNT charges, a direction and a **flight time** under **Manual landing forecast**, press **Forecast landing**, and the panel shows the landing point, the pearl position at that tick (X / Y / Z), momentum and configuration text right away. The eight directions match the ones the cannon geometry produces, so a forecast with the auto-detected direction agrees with the table.



Save as default and **Fill from defaults** work the same way as in the pearl cannon.



3.2 Settings


Setting	Description
Muzzle X / Y / Z	Default muzzle position
Destination X / Y / Z	Default destination
Expected flight time	Default flight time (gt)
Direction reference	`Real muzzle`: direction from the current muzzle (recommended); `Legacy`: the old hard-coded `(10000, 10000)`

> Long flight times may produce negative TNT (the legacy app had no solution either). The table then shows “No valid configuration for this flight time” — shorten the flight time or adjust the destination.

---

4. Material converter

Converts a Litematica material list into **shulker boxes / stacks / items** and produces a loading plan.



4.1 Import material lists

- Click **Import material list** to pick **several** files at once (click again to append): material lists (**CSV / TXT**, GBK or UTF-8) and `.litematic` **schematics** can be mixed.
- A `.litematic` is counted by **item form**, not by block form: wall signs/torches/heads, water/lava/powder-snow cauldrons, redstone wire and crops are folded into their collectable items (sign, torch, cauldron, redstone dust, seeds and so on), while facing or waterlogged variants are merged.
- Water and lava count only at the **source** (the state that can be bucketed); bubble columns, fire, soul fire, piston heads, nether portals, barrier-like blocks and other blocks **without an item form** are filtered out. Hover a row to see its region, block and filtered counts.
- The result matches Litematica's Chinese material list exactly: for the same structure both the schematic and the CSV report **51 kinds / 17 091 items** with identical per-item counts.
- Schematic material names follow the **current interface language** (简体中文 / 繁體中文 / English): switching the language re-counts imported schematics immediately, no re-import needed.
- Each list gets a row on the left: the checkbox decides whether it takes part, the row shows that list's kinds · items, and × removes it. Unticking recalculates immediately.
- Lists are merged by **material name** with counts summed: schematic names match Litematica's CSV export in the same language, so the same material from both kinds of source adds up correctly.
- Header detection: name/count columns are read from the header (Litematica's `Item, Total, Missing, Available` uses **Total**), otherwise `name count` lines are parsed.

- The pending list, result, loading plan and export use only the **ticked** lists; stack overrides and the ignore list apply globally by material name.
- Appending lists keeps your stack overrides and ignore list, but clears the material selection and export file name.

4.2 Search and sorting

- The search box filters as you type and shows up to **8 suggestions** (click or press `Enter` to apply, `Esc` or × to clear).
- **Select all** applies only to the **filtered** rows, handy for "search then batch-process".
- Click **Count ▼** above the list to toggle ascending/descending (descending by default).
- The result panel has a **stack filter**: `All / 64 / 16 / 1`; the **Count** header sorts the table.

4.3 Stack size: default and batch

- **Default stack size**: `64` / `16` / `1 (unstackable)`.
- **Batch**: select materials, choose 64/16/1 in the batch bar, click **Apply to selected**. The selection is cleared afterwards so you do not accidentally touch the next batch.
- Materials with a custom stack size show a teal chip; the result table has a **Stack** column with the value actually used.
- With `1`, each slot holds one item and the "stacks" column is always 0.

4.4 Ignoring materials

- Select materials and click **Ignore selected**; they are excluded from conversion, loading plans and export. When every selected material is already ignored, the button becomes **Restore selected**.
- The **Ignored materials** panel below the list shows what is ignored and lets you restore one or all of them.
- Ignored rows stay in the list, struck through with an "Ignored" tag.

4.5 Conversion result

Columns: **Material / Stack / Count / Shulkers / Stacks / Items**.


- **Shulkers** counts full boxes; **stacks** and **items** are the remainder — e.g. 4766 at stack 64 = 2 boxes + 20 stacks + 30 items.
- The footer shows kinds, total items, full boxes, **boxes needed** (per-material ceiling summed up, i.e. how many boxes to carry) and the default box capacity.
- Names and counts come from the imported list; the loading plan and CSV export use the same data.

4.6 Loading plan

Loading plan packs everything into the fewest shulker boxes:

- Each material is first converted to **slots**: `full stacks + (remainder ? 1 : 0)`, with 27 slots per box.

- Boxes are filled largest-first until full, so the box count equals `ceil(total slots / 27)`, the theoretical minimum.
- When one material fills several boxes in a row, those boxes are **merged into a single card** (titled like `Boxes 1–2` with a "N boxes merged" tag) so long plans stay compact; mixed or partly filled boxes are still shown one by one.
- The dialog has two views: **Cards** (one card per box, ≤ 12 boxes by default) and **List** (box index on the left, details on the right, used automatically for larger plans). Switch any time from the title bar; both have their own scrollbars.
- Card height depends on how many material kinds a box holds, so cards are laid out **masonry-style**: each card spans exactly its measured height, leaving no empty row under short cards.
- Each box lists "material · stacks/items · slots", and **Copy plan** exports the whole plan as text.



4.7 Export CSV

Two export settings at the bottom of the left column:

- **Export name**: empty means `<imported file name>_converted.csv`; with several lists ticked it falls back to `merged_converted.csv`.
- **Export folder**: empty means `<data folder>/output` (by default `<exe folder>/data/output`). Use **Choose…** to pick another folder; the choice is saved.

The export follows the current **filter and sort**, is UTF-8 with BOM, and opens correctly in Excel.

4.8 Settings

Setting	Description
Max stack size	`64` / `16` / `1`, default for new conversions
Slots per shulker	Slots in one shulker box, default 27
Export folder	Default CSV folder, empty means `<data folder>/output`

---

5. Puppet Logistics

Works out “boxes → bots → batches → commands” and can type them into the game. The tool only spawns and kills fake players; loading, moving and unloading are still done by the in-game station.

5.1 Stations

A station stores a **group tag**, a name, a dimension, coordinates and a short prefix. The group tag shows up in the shipment dropdowns and the station list: opening a dropdown shows the group tags first, clicking one filters the list to that group's places (names no longer repeat the tag), and the closed control shows `重溟洋工业区 · 全物品`. That means the name itself can stay short (`全物品`) instead of repeating the district in every name.


You can add, edit and delete stations, or import the legacy configuration:

- the old `stops.json` (same object shape as the legacy tool);
- lines of `name x y z prefix [group] dimension`; the `end_` / `ov_` / `nether_` prefixes set the dimension and are stripped.

Names written as `district·place` are split into group + name when read; a group tag cannot contain spaces. A note holds at most 60 characters and appears inside the card on hover, wrapping to at most two lines. The station list below can also be filtered by group tag (All / each group), matching the dropdowns in the shipment panel.

Stations can also be exported as JSON (importable again) or as `name x y z prefix group dimension` text; exports go to the `output` folder inside the data directory by default.


Bot names come from a template, `bot_{origin}_{dest}_{index}` by default. The final name must be 3–16 characters (Minecraft username limit); prefixes that are too long raise an error asking you to shorten them.



5.2 Generating commands

Pick the origin, destination, number of boxes and the operation:

- 36 boxes per bot and 24 bots per batch (864 boxes) by default, both configurable;
- bot count = ⌈boxes / boxes-per-bot⌉, then split into batches;
- “Spawn at origin” / “Spawn at destination” decides which station the spawn command targets; they are normally used as a pair: spawn at the origin and load, kill them, then spawn the same bots at the destination to unload;
- results are split into Spawn and Kill tabs, with copy-all and `.txt` export (also usable as a `.mcfunction`). The **Clear commands** button next to Copy all empties the current preview.
- the order (from / to / boxes / operation) is remembered in the data folder and restored the next time the app starts; deleted stations fall back to the default selection.



Commands look like:

```
/execute in minecraft:the_end run player bot_all_con_1 spawn at 136 48 8
/player bot_all_con_1 kill
```

Example: moving 600 boxes from A to B (load, then unload at the destination)

Say A is the source warehouse (Overworld, `100 64 -200`, prefix `a`) and B is the destination (The End, `200 48 50`, prefix `b`):

1. **Spawn at the origin**: add both stations under **Stations** (group tag `Example`); pick A as From, B as To, enter `600` boxes, choose "Spawn at origin" and generate. `ceil(600 / 36) = 17` bots (17 ≤ 24, one batch) named `bot_a_b_1` … `bot_a_b_17`:

```
/execute in minecraft:overworld run player bot_a_b_1 spawn at 100 64 -200
...
```

Copy them into the game (or enable auto input); the bots appear at A. At the default 1 s interval this takes about 32 seconds.

1. **Load**: operate the fake-player cargo station at A and fill the 17 bots with the 600 boxes.

2. **Clear, then spawn at the destination**: run the 17 `/player bot_a_b_N kill` commands from the Kill tab to clear the bots at A; switch the operation to “Spawn at destination”, generate and run again so the same bot names appear at B:

```
/execute in minecraft:the_end run player bot_a_b_1 spawn at 200 48 50
...
```

1. **Unload**: operate the cargo station at B to unload; afterwards you can clear this batch from the Kill tab again.
2. The ledger records every spawn/kill: route A → B, operation location A · Overworld (or B · The End), 600 boxes / 17 bots; clicking a row restores the commands.

For 1000 boxes: `ceil(1000 / 36) = 28` bots, split into batches of 24 + 4; repeat steps 1 → 4 for each batch. With auto input on, **Run** pauses at the end of every batch: the panel shows “Batch 1/2 done” and waits for you to finish that batch in-game (load / unload), then **Continue** sends the next batch so the bots do not all pile up at the station.

5.3 Running commands (optional)

Execution is off by default. Enable **Settings** → **Run** → **Allow auto input** to type the commands into Minecraft:

- Run opens a confirmation first, then counts down and brings the game window to the front;
- with several batches it pauses after each one and waits for **Continue**; you can still stop while it waits;
- the log under **Run** scrolls like a terminal and shows live progress (sent count, current command, per-command lines);
- clipboard paste (`Ctrl+A`, `Ctrl+V`) with keys held for 0.12 s; before pressing Enter the runner probes whether the game stalled and retries the whole command if it did;
- press `ESC` in-game to stop; afterwards “Build cleanup” kills any bots that may already exist, and the sent count is written to the ledger;
- when every command has been sent, the runner sends one extra English chat message, `Operation completed successfully`, so you can tell the batch finished;
- **Diagnose** checks the window, focus, clipboard and administrator rights;
- if Minecraft runs as administrator, this app must run as administrator too, otherwise Windows drops the injected keys.

5.4 Ledger

Every run (done / stopped / error) appends a row: number, time, route, **operation location** (the station and dimension this run operated at), boxes, bots, phase, state and sent count. The last 200 rows are kept and can be cleared at once.

Click a row to restore the commands that run saved into the command preview above (spawn / kill); you can copy, export or run them again. “Back to current order” returns to the commands generated from the current form.

5.5 Settings

Setting	Meaning
Boxes per bot	Default 36; a bot has 36 slots, one box each
Bots per batch	Default 24, i.e. 864 boxes per batch
Bot name template	Supports `{origin}` / `{dest}` / `{index}`
Allow auto input	Required to run; briefly takes keyboard focus
Command interval	Delay between commands, 1 s by default
Start countdown	Preparation time before running, 3 s by default
Input mode	Clipboard paste (recommended) or character typing
Force game window to front	Re-check focus before every command
Lag retries	3 by default
Restore clipboard afterwards	On by default

---


6. Slime chunk finder

Find the AFK spot whose **24–128 block spawn ring** contains the most slime-chunk area. Mobs do not spawn within 24 blocks and despawn beyond 128 blocks.

6.1 Usage


1. Enter the **world seed** (a number, or text such as `hello`, hashed like Java). The field remembers recent seeds — focus it or click `▾` to pick one from history;
2. Enter the **center X / Z** (block coordinates) and the **search radius** in chunks; `4,096` chunks covers 8192×8192 chunks, and `1,875,000` chunks is roughly the whole world;
3. Adjust the **ring inner / outer** radii (default 24 / 128) and the **simulation distance** (server `simulation-distance`; chunks beyond it do not tick);
4. Pick a **search mode**: `Auto` (unlimited by default, so always exact; only areas above a limit you set in Settings are sampled), `Exact`, or `Sampled`;
5. Press **Find**.

Results are sorted by slime-chunk block area inside the ring, with **non-maximum suppression** (8 chunks by default) so the list contains distinct spots instead of one hotspot.




6.2 Map and results

- Selecting a result centres the map on it and zooms to about 40×40 chunks: green cells are slime chunks, orange is the score heatmap, dashed circles are the 24 / 128 rings;
- **A search first shows an overview** covering the whole search area, with the search centre marked by an orange ring; beyond 1024 chunks it samples at “N chunks per cell” (shown in the legend — e.g. 8 chunks per cell at a 4,096-chunk radius). Click a result row for a ~192-chunk detail view, and **Whole area** returns to the overview;
- The top and left edges show coordinate ticks whose step adapts to zoom (16 / 32 / 64 … blocks); hovering shows both the chunk and the block coordinate;
- **Coordinate view** on the left takes any X / Z: **Show point** reloads the map centred on it with an edge length of **2 × search radius** (same size as the search area, up to 1024 chunks; larger radii show 1024 chunks) and zooms to about 40×40 chunks for a clear look (**Fit** shows the whole area); it marks the point with a blue “Viewed point” and also draws the 24 / 128 ring and the default perimeter square around it (with the corner coordinates), and works without any search results;



- **Perimeter** draws a default 21×21-chunk square around the selected result with the ring kept as centred as possible, and lists the four corner coordinates; the size can be changed in settings or in the card, and a size too small to cover the ring triggers a warning;
- Results live in a sidebar on the right; click a row to locate and zoom. The **Results** button collapses/expands the sidebar so the map can use the full width;
- Opening or closing the **Perimeter** panel, collapsing/expanding the results sidebar and resizing the window keep the current zoom and centre instead of snapping back to the whole map;
- Click a marker on the map to switch results; wheel to zoom, drag to pan, hover to see chunk coordinates and slime state; **Locate** re-focuses the selected result;
- The table lists rank, AFK X / Z, score (blocks²) and coverage, with a copy button per row;
- **Export CSV** includes the seed, area and coordinates so a search can be reproduced.



6.3 Large areas and performance

- **Exact scan**: vectorised slime bitmap plus FFT convolution; 1000×1000 chunks (~1M) takes about a second, 10000×10000 chunks (100M, 160k×160k blocks) about 10 seconds on the development machine;
- **The exact scan has no limit by default**: any area is scanned exactly (in the background, stoppable). To cap run time, set a chunk limit in **Settings** → **Slime Chunk Finder** (0 = unlimited); larger areas then switch to **sampled search** (50,000 random points, hill climbing and per-chunk refinement, with the percentile among random samples). 8192×8192 takes about 9 seconds here. Larger areas switch to **sampled search**: 50,000 random points, hill climbing and per-chunk refinement, reported with the percentile among random samples;
- The full 60M×60M world is 1.4×10^{13} chunks and cannot be enumerated; without a limit an exact scan simply takes longer (background, stoppable). Set a limit to switch to sampled search automatically. Sampled search returns the best point within the budget, not a proven global optimum; narrow the area for an exact scan.

6.4 Settings

Setting	Description
World seed	Default `0`
Center X / Z	Default `-32` / `-8`; used as the initial center when the tool opens
Search radius	Default `4096` chunks (±4096 chunks = 8192×8192 chunks), minimum 1
Exact scan limit	Default `0` (unlimited); set 1–67,108,864 chunks and larger areas switch to sampled search

Setting	Description
Perimeter size	21×21 chunks by default; must cover the spawn ring, otherwise you get a warning
Ring inner / outer	24 / 128 blocks by default
Simulation distance	Server simulation-distance, default 8; the outer radius becomes `min(outer, distance × 16)`
Result count	100 by default, up to 500
Result spacing	NMS spacing, 8 chunks by default
Search mode	Auto / Exact / Sampled
Samples	50,000 by default


---

7. Settings

Click the gear (or press `Ctrl+,`) to open the settings drawer. The **Tool options** tab follows the active tool; the sections below describe it per app. Saved values apply immediately, and Reset / Import live at the bottom.


7.1 Pearl Cannon

Default muzzle and target coordinates, maximum TNT, per-array cap, firing mode and the rounding parameters for flat/arc shots. Full list: 2.2 Settings.




7.2 Border Cannon

Default muzzle and target coordinates, expected flight time, direction reference and legacy-compatibility mode. Full list: 3.2 Settings.




7.3 Material Converter

Maximum stack size, shulker slots, export folder and export format. Full list: 4.8 Settings.




7.4 Puppet Logistics

Boxes per bot, bots per batch and the bot name template, plus the run options (allow auto input, command interval, countdown, input mode, lag retries, clipboard restore). Full list: 5.5 Settings.



7.5 Slime Chunk Finder

Default world seed, center X / Z, exact-scan limit and perimeter size, plus the ring inner / outer radii, simulation distance, result count, result spacing, search mode and sample count. Full list: 6.4 Settings.




7.6 Data & storage

The **Data & storage** tab shows or changes the data folder, opens it, and exports/imports a settings bundle.


Import config accepts two kinds of files:

- a single JSON exported by this app (e.g. `pearl.json`);
- the legacy `resources/settings/settings.json` from either original project — detected and converted automatically (the legacy border cannon switches to the legacy direction mode).



7.7 About

The **About** tab shows the version, stack, privacy note and license, with shortcuts to the manual (the Chinese/English README as PDF) and the GitHub repository.



8. Data and storage

Settings live in `data` next to the executable by default. **Copy the whole folder to migrate.**


```
<folder containing the exe>/
├─ LSP_PlayerKit.exe
└─ data/
   ├─ settings/
   │  ├─ app.json          language, theme, window state
   │  ├─ pearl.json        pearl cannon settings
   │  ├─ border.json       border cannon settings
   │  ├─ material.json     material converter settings
   │  ├─ puppet.json       Puppet Logistics settings
   │  ├─ puppet_stations.json  Puppet Logistics stations
   │  ├─ puppet_orders.json    Puppet Logistics ledger
   │  └─ puppet_draft.json     last order (from / to / boxes / operation)
   ├─ output/              exported CSV files (default folder)
   ├─ backups/             snapshot before each save, last 5 kept
   └─ .lock                prevents two instances overwriting each other
```

Data folder resolution (first match wins):

1. `--data-dir` on the command line or the `LSPKIT_DATA_DIR` environment variable
2. `portable.json` next to the executable (portable mode)
3. `%APPDATA%\LSP_PlayerKit\location.json` (a location the user picked)
4. default `<exe folder>/data`; if it is not writable (e.g. installed in `Program Files`), the app falls back to `%APPDATA%\LSP_PlayerKit\data` and shows a notice

Other behaviour:

- Every write is "temp file + replace"; a corrupted JSON falls back to the latest backup.
- **Export / import bundle** produces a zip with every tool and preference.
- Window size and maximized state are stored in `app.json` and restored on the next launch.



---

9. Calculation notes and limitations

- Flat/arc rounding and enumeration order for the pearl cannon, and the three-TNT solve for the border cannon, are line-by-line compatible with the legacy implementations; golden snapshot tests keep the numbers identical.
- Some flight times produce negative TNT for the border cannon (the legacy app had no solution either); the table then reports "No valid configuration for this flight time".

- Box counts use 27 slots per box; **boxes needed** sums the per-material ceiling, which is the number of shulker boxes to carry.
- The loading plan uses the theoretical minimum number of boxes, but one material may be split across two adjacent boxes; the dialog lists them by box number.
- Material names and counts come straight from the imported list; conversion only changes boxes/stacks/items, never names.
- Puppet Logistics only spawns and kills fake players; loading and transport are done by the in-game station. A stopped run may leave bots behind — use “Build cleanup” next to the ledger.
- Execution is Windows-only and only targets windows of class `GLFW30` / `LWJGL` (launcher windows are never touched). Administrator rights depend on how Minecraft is launched.
- Whether auto input is allowed is up to the server's rules; check before using it.
- The Slime Chunk Finder supports **Java Edition** only. The score estimates slime-chunk block area inside the ring and does not model terrain, caves or spawn-layer height; real rates also depend on simulation distance, light and farm design.
- A full 60M×60M world cannot be enumerated: without a limit the exact scan just takes longer; set a limit to switch to sampled search, which returns the best result within the budget rather than a proven global optimum.

Bundled mini-tools

The download package also includes four console tools (double-click, follow the prompts, type `n` to quit). They are not part of this app and are not needed for normal use; their sources live in `src/tool_bundles/`, and the build specs are kept in a local-only `packaging/` folder (not tracked in git), so any of them can be rebuilt with PyInstaller.

Tool	Purpose	Notes
`ConfigGenerator.exe`	Pearl cannon parameter generator	Walks through `/log projectiles full` measurements and writes an importable `<name>.json` next to the exe. Every prompt states the expected format with an example, and the saved path is printed when done
`MainCannonConfigMaker.exe`	Main cannon record maker	Enter destination, coordinates, direction and blue/red array TNT; it prints a formatted record for announcements or archives
`BorderCannonConfigMaker.exe`	Border cannon record maker	Enter destination, coordinates, direction and the minor/major counts of the three TNT charges; it prints a formatted record

Tool	Purpose	Notes
`StationConfigMaker.exe`	Puppet Logistics station generator	Prompts for group tag, name, dimension, coordinates, prefix and note, then writes `{"version":1,"stations":[...]}` JSON next to the exe, which "Puppet Logistics → Import" can read directly

Coordinates use `(a, b)` with English parentheses and comma. The JSON written by `ConfigGenerator.exe` now uses `XZ_INIT_POSITION` and imports directly in the pearl cannon tool; files produced by the legacy generator still say `XZ_INIT_POSTION`, so that entry is ignored and the muzzle falls back to its default position — renaming the key fixes them.

Stack

Python 3.9 + pywebview 6 + Vue 3 + Vite + numpy

License

GPL-3.0 license