Settings Reference

Every setting of the Control Panel, with what it does, what it accepts and its default.

Version 4.0

General | Appearance | Display | Content | Filtering | Data Sources | Animations | Advanced

How to Read This Page

Every setting, in eight groups, in the order of the Control Panel's tabs.

Each entry is one setting, written the way the Control Panel shows it. You do not need this page to use the Control Panel: every setting also has a help icon there. Use it to look a setting up, to see its default, or to find which tab holds it.

PART OF AN ENTRY	WHAT IT TELLS YOU
Name and kind	The name is the one in the Control Panel. The kind says what you set: a switch, a number, a choice, a color, a text or a list.
Default	The value you get after Restore Defaults or Reset, and in a fresh settings file.
Choices, Range, Length	What the setting accepts. A number outside its range is not accepted.
Appears when, Needs	A setting that only matters while another one has a value. The Control Panel hides it or dims it until then.
Desktop and Phone	Some settings have one value for each. They are one entry with both values.
For each kind of result	Panoramas, videos, hotspots and the other kinds each have their own value. The entry names the setting once, and the table of defaults under it lists every kind.

Find a setting by typing a word in the box above: **tag**, **phone**, **border**, **delay**. Press `/` anywhere on this page to jump to the box. The settings file holds more than 400 values in all.

General

Choose how the search opens and closes, how it finds results, and where it sits on computers and phones

Opening and Closing

Choose what hides the Search Results (the list) and the Search Bar (the box visitors type in), when the Search Bar opens, and what happens when a result sits in a window your tour keeps hidden.

Hide the Search Results After Choosing a Result

Switch for Desktop and Phone

On: the Search Results, the list under the Search Bar, go away as soon as a visitor picks a result, and the field is emptied. Off: they stay.

DEFAULT Desktop: Off · Phone: Off

Also Hide the Search Bar After Choosing a Result

Switch for Desktop and Phone

On: the Search Bar, the box visitors type in, goes away too, so the whole search closes. Off: the Search Bar stays on screen, ready for the next search. This works only while Hide the Search Results After Choosing a Result is on.

DEFAULT Desktop: On · Phone: On

Hide the Search Results When Clicking or Tapping Outside

Switch for Desktop and Phone

On: clicking or tapping anywhere else hides the Search Results, the list under the Search Bar. Off: nothing happens until the visitor closes the search.

DEFAULT Desktop: On · Phone: On

Also Hide the Search Bar When Clicking or Tapping Outside

Switch for Desktop and Phone

On: the Search Bar, the box visitors type in, goes away too, so the whole search closes. Off: the Search Bar stays on screen. This works only while Hide the Search Results When Clicking or Tapping Outside is on.

DEFAULT Desktop: On · Phone: On

Hide the Search Results With the Escape Key

Switch

On: one press of Escape clears the typed text and hides the Search Results. Off: the search ignores Escape, so the tour can use it for its own windows and full screen.

DEFAULT On

Also Hide the Search Bar With the Escape Key

Switch

On: the Search Bar goes away too, so the whole search closes. Off: the Search Bar stays on screen, and the tour keeps Escape while the field is empty. This works only while Hide the Search Results With the Escape Key is on.

DEFAULT On

Open When the Tour Starts

Switch for Desktop and Phone

Open the search by itself as soon as the tour has started. If the tour waits on a start screen (3DVista Initialization: On Click or When Video Finished), it opens after the visitor starts the tour. Most tours leave this off. To keep the Search Bar on screen from then on, switch off the Also Hide the Search Bar settings above.

DEFAULT Desktop: Off · Phone: Off

Open With Ctrl or Cmd + K

Switch

Lets visitors open the search from the keyboard with Ctrl + K (Windows) or Cmd + K (Mac).

DEFAULT On

Open Hidden Windows and Containers

Switch

Some results live in a window or container your tour keeps hidden, such as the floor plan, a photo album or a flat video. On: choosing such a result shows that window first, the way the tour's own button does. Off: the result is still selected, but the window stays hidden.

DEFAULT On

Search Bar

Width, position and layer of the search bar on desktop.

Width

Text

Recommended: 95% at most instead of 100%, so the bar never touches the edges.

DEFAULT `350px`

Layer

Number

Raise this number if another part of the tour covers the search bar. Leave it at 9999 otherwise.

DEFAULT `9999`

RANGE 1 to 100000

Distance From the Side

Number

How far the bar sits from the left or right edge. Not used when it is centered.

DEFAULT `70 px`

RANGE 0 to 500 px, in steps of 5

Distance From the Top or Bottom

Number

How far the bar sits from the top or bottom edge. Not used when it is in the middle.

DEFAULT `70 px`

RANGE 0 to 500 px, in steps of 5

Position on the Screen

Four numberss

Pick where the search bar sits on a computer. Top and bottom bars open their results downward and upward.

DEFAULT vertical: `top` · horizontal: `right`

Phones

Choose when a phone gets its own layout and how the search bar looks there.

Phone Layout Is Used

Choice

3DVista loads a separate phone version of a tour (script_mobile.js) on phones and the computer version (script_general.js) on computers and iPads. "When the tour shows its phone version" follows that choice exactly, even for a phone held sideways. The other option only looks at the width of the screen.

DEFAULT When the screen is narrow (set below)

CHOICES When the screen is narrow (set below), When the tour shows its phone version

Phone Layout Starts at

Number

Screens this wide or narrower get the phone layout.

DEFAULT `768 px`

RANGE 320 to 1200 px

Separate Layout for Phones

Switch

On: phones use the placement and width below. Off: phones use the computer layout, kept inside the screen.

DEFAULT On

Placement on Phones

Choice

Top bars open their results downward, bottom bars upward.

DEFAULT Top

CHOICES Top, Bottom

Distance From the Top or Bottom

Number

How far the bar sits from the top or bottom edge on phones.

DEFAULT `60 px`

RANGE 0 to 300 px, in steps of 5

Space at the Sides

Number

Empty space left on the left and right of the bar on phones.

DEFAULT `20 px`

RANGE 0 to 100 px, in steps of 5

Width on Phones

Text

Recommended: 95% at most instead of 100%. The bar is never wider than the limit next to it.

DEFAULT `90%`

Never Wider Than

Number

The bar never grows wider than this on phones, whatever the width says.

DEFAULT `350 px`

RANGE 200 to 800 px, in steps of 10

Visitor Texts

Change the words visitors see in the search. Each field says where the text appears.

SEARCH FIELD

Hint in the Empty Search Field

Text

A short invitation to type, for example: Search the tour.

Appears inside the search field before anyone types.

DEFAULT `Search... Type * for all`

LENGTH Up to 120 characters

Name of the Clear Button

Text

Describes the small X button that empties the search field.

Read aloud by screen readers. Visitors do not see it.

DEFAULT `Clear search`

LENGTH Up to 120 characters

MESSAGES

Message When Too Few Letters

Text

Tells visitors to keep typing, for example: Type at least {count} letters.

Appears under the search field until enough letters are typed. {count} becomes the number set in Search Tuning (Advanced tab).

DEFAULT `Please type at least {count} characters to search`

LENGTH Up to 120 characters

Message When Nothing Is Found

Text

For example: Nothing found. Try another word.

Appears when a search has no results.

DEFAULT `No matching results`

LENGTH Up to 120 characters

RESULT LISTS

Word for One Result

Text

Used when a group has exactly one result.

Appears after the number in a group title, for example: 1 result.

DEFAULT `result`

LENGTH Up to 120 characters

Word for Several Results

Text

Used when a group has two or more results.

Appears after the number in a group title, for example: 5 results.

DEFAULT `results`

LENGTH Up to 120 characters

Word Before a Panorama Name

Text

Links an item to the panorama it belongs to.

Appears in front of the panorama an item belongs to, for example: in Kitchen.

DEFAULT `in`

LENGTH Up to 120 characters

Label Before Tags

Text

The word shown before the tags of a result. Leave it empty to show no word.

Appears in front of the tags of a result, for example: Tags: Kitchen. Leave it empty to show only the tags.

DEFAULT `Tags:`

LENGTH Up to 120 characters

Appearance

Choose the colors, corners and text of the search field and the results

Search Field

Colors, corners, border, focus ring and text of the search field.

COLORS

Search Background

Color

Background color of the search field.

DEFAULT `#f4f3f2`

Typed Text Color

Color

Color of the text a visitor types in the search field.

DEFAULT `#1a1a1a`

Placeholder Color

Color

Color of the hint shown in the empty search field.

DEFAULT `#5f6f86`

Search Icon

Color

Color of the magnifier icon in the search field.

DEFAULT `#94a3b8`

Clear Icon

Color

Color of the X button that empties the search field.

DEFAULT `#94a3b8`

Clear Icon on Hover

Color

Color of the X button while the mouse is over it.

DEFAULT `#64748b`

CORNER RADIUS

Top Left

Number

How round the top left corner of the search field is.

DEFAULT `35 px`

RANGE 0 to 50 px

Top Right

Number

How round the top right corner of the search field is.

DEFAULT `35 px`

RANGE 0 to 50 px

Bottom Left

Number

How round the bottom left corner of the search field is.

DEFAULT `35 px`

RANGE 0 to 50 px

Bottom Right

Number

How round the bottom right corner of the search field is.

DEFAULT `35 px`

RANGE 0 to 50 px

BORDER

Border Width

Number

Thickness of the line around the search field in pixels. 0 draws no border.

DEFAULT `0 px`

RANGE 0 to 10 px

Border Style

Choice

A solid, dashed, dotted or double line. A double line needs a width of 3 or more to show.

DEFAULT Solid

CHOICES Solid, Dashed, Dotted, Double

Border Color

Color

Color of the line around the search field.

DEFAULT `#cbd5e1`

Sides

Four switches

Choose which sides of the search field get the border. Leave all four on for a full frame.

DEFAULT Top: On · Right: On · Bottom: On · Left: On

FOCUS RING

Focus Ring Color

Color

Color of the ring drawn along the inside edge of the search field while it is active. It shows visitors who use the keyboard where they are.

DEFAULT `#3b82f6`

Focus Ring Width

Number

Thickness of the ring in pixels. 1 is the default, 0 draws no ring, 2 or 3 is easier to see.

DEFAULT `1 px`

RANGE 0 to 6 px

TYPED TEXT

Text Size

Number

Size of the text.

DEFAULT `16 px`

RANGE 10 to 40 px

Font

Choice

The font of the text. Fonts used by this tour are listed first.

DEFAULT Default (system font)

CHOICES Default (system font), Arial, Helvetica, Times New Roman, Georgia, Courier New, Verdana, Trebuchet MS, Impact, Comic Sans MS

Font Weight

Choice

How bold the text is.

DEFAULT 400 (Normal)

CHOICES 100 (Ultra Light), 200 (Extra Light), 300 (Light), 400 (Normal), 500 (Medium), 600 (Semi Bold), 700 (Bold), 800 (Extra Bold), 900 (Ultra Bold)

Font Style

Choice

Normal, italic or slanted text.

DEFAULT Normal

CHOICES Normal, Italic, Oblique

Line Height

Number

Height of a line of text as a multiple of the text size.

DEFAULT `1.5 x`

RANGE 0.8 to 3 x, in steps of 0.1

Letter Spacing

Number

Extra space between letters.

DEFAULT `0 px`

RANGE -2 to 10 px, in steps of 0.25

Letter Case

Choice

Show the text as typed, in capitals, in small letters, or with a capital first letter.

DEFAULT None

CHOICES None, Uppercase, Lowercase, Capitalize

PLACEHOLDER TEXT

Text Size

Number

Size of the text.

DEFAULT `16 px`

RANGE 10 to 40 px

Font

Choice

The font of the text. Fonts used by this tour are listed first.

DEFAULT Default (system font)

CHOICES Default (system font), Arial, Helvetica, Times New Roman, Georgia, Courier New, Verdana, Trebuchet MS, Impact, Comic Sans MS

Font Weight

Choice

How bold the text is.

DEFAULT 400 (Normal)

CHOICES 100 (Ultra Light), 200 (Extra Light), 300 (Light), 400 (Normal), 500 (Medium), 600 (Semi Bold), 700 (Bold), 800 (Extra Bold), 900 (Ultra Bold)

Font Style

Choice

Normal, italic or slanted text.

DEFAULT Italic

CHOICES Normal, Italic, Oblique

Strength

Slider

How strong the text is: 1 solid, lower is fainter. Keep it at 1 unless the color is already dark.

DEFAULT `1`

RANGE 0 to 1, in steps of 0.1

Letter Spacing

Number

Extra space between letters.

DEFAULT `0 px`

RANGE -2 to 10 px, in steps of 0.25

Letter Case

Choice

Show the text as typed, in capitals, in small letters, or with a capital first letter.

DEFAULT None

CHOICES None, Uppercase, Lowercase, Capitalize

Results List

Colors, corners, border and text of the list of results.

The words of the message are set in General > Visitor Texts > Message When Nothing Is Found.

COLORS

Results Background

Color

Background color of the results list.

DEFAULT `#ffffff`

Hovered and Selected Row

Color

Background of a result row while the mouse is over it or it is picked with the arrow keys.

DEFAULT `#f0f0f0`

Row Edge Line

Color

The thin line on the left edge of each result row.

DEFAULT `#ebebeb`

Result Name

Color

Color of the name of each result.

DEFAULT `#1e293b`

Description

Color

Color of the description under a result name.

DEFAULT `#000000`

Panorama Line

Color

Color of the small line that says which panorama an item is in, for example: in Kitchen.

DEFAULT `#64748b`

Icon

Color

Color of the built-in icons. The same setting as Icon Color in Display > Icon Appearance: changing one changes the other.

DEFAULT `#6e85f7`

RESULT TEXT

Font

Choice

The font of the whole results list. Fonts used by this tour are listed first.

DEFAULT Default (system font)

CHOICES Default (system font), Arial, Helvetica, Times New Roman, Georgia, Courier New, Verdana, Trebuchet MS, Impact, Comic Sans MS

Name Size

Number

Text size of the result names.

DEFAULT `14 px`

RANGE 10 to 28 px, in steps of 0.1

Description Size

Number

Text size of the descriptions under the names.

DEFAULT `12 px`

RANGE 8 to 24 px, in steps of 0.1

Panorama Line Size

Number

Text size of the line that says which panorama an item is in.

DEFAULT `11.2 px`

RANGE 8 to 24 px, in steps of 0.1

CORNER RADIUS

Top Left

Number

How round the top left corner of the results list is.

DEFAULT `5 px`

RANGE 0 to 50 px

Top Right

Number

How round the top right corner of the results list is.

DEFAULT `5 px`

RANGE 0 to 50 px

Bottom Left

Number

How round the bottom left corner of the results list is.

DEFAULT `5 px`

RANGE 0 to 50 px

Bottom Right

Number

How round the bottom right corner of the results list is.

DEFAULT `5 px`

RANGE 0 to 50 px

BORDER

Border Width

Number

Thickness of the line around the results list in pixels. 0 draws no border.

DEFAULT `0 px`

RANGE 0 to 10 px

Border Style

Choice

A solid, dashed, dotted or double line. A double line needs a width of 3 or more to show.

DEFAULT Solid

CHOICES Solid, Dashed, Dotted, Double

Border Color

Color

Color of the line around the results list.

DEFAULT `#cbd5e1`

Sides

Four switches

Choose which sides of the results list get the border. Leave all four on for a full frame.

DEFAULT Top: On · Right: On · Bottom: On · Left: On

LINE BETWEEN ROWS

Line Width

Number

Thickness of the thin line under every result row in pixels. 0 draws no line.

DEFAULT `0 px`

RANGE 0 to 6 px

Line Color

Color

Color of the line between result rows.

DEFAULT `#e5e7eb`

SCROLLBAR

Scrollbar Color

Color

Color of the scrollbar when the list is longer than the screen.

DEFAULT `#94a3b8`

Scrollbar Size

Choice

Thin keeps the bar slim, Normal uses the browser's usual width, Hidden removes it (the list still scrolls).

DEFAULT Thin

CHOICES Thin, Normal, Hidden

NOTHING FOUND MESSAGE

Message Text

Color

Color of the message shown when a search finds nothing. The icon above it uses the same color.

DEFAULT `#6b7280`

Message Background

Color

Background of the message shown when a search finds nothing.

DEFAULT `#ffffff`

Icon

Choice

Default shows the small face the message always had, None shows only the words, Custom lets you type an icon class (Font Awesome, Bootstrap Icons or Ionicons) or an emoji.

DEFAULT Default Face

CHOICES Default Face, No Icon, Custom

Custom Icon

Text

An icon class such as fas fa-search (Font Awesome), bi bi-search (Bootstrap Icons) or ion-md-search (Ionicons), or an emoji such as . Used when Icon is set to Custom.

An icon class of Font Awesome, Bootstrap Icons or Ionicons loads by itself. An emoji always works.

DEFAULT Empty

LENGTH Up to 40 characters

Icon Size

Number

Size of the icon above the message.

DEFAULT `24 px`

RANGE 12 to 64 px

Group Headers

Colors, layout, border, title and count of the bars that group the results.

To show or hide the titles and the counts, use Show Group Headers and Show Group Count in Display.

Top draws a line between one group and the one before it, Bottom a line between the title and its results. With a width of 0 the very faint line headers always had stays.

The count is the number of results next to the title, for example 5 results. Give it a background or a border to make it look like a small badge.

COLORS

Group Header Background

Color

Background of the title bar above each group of results.

DEFAULT `#ffffff`

Group Header Text

Color

Color of the group title, for example Panorama.

DEFAULT `#20293a`

Group Count Text

Color

Color of the number of results shown next to a group title.

DEFAULT `#5f6f86`

LAYOUT AND SIZE

Alignment

Choice

Put the group title on the left, in the center or on the right of its bar.

DEFAULT Left

CHOICES Left, Center, Right

Position

Choice

Show the group title above or below its results.

DEFAULT Top

CHOICES Top, Bottom

Space Above

Number

The empty space above the group title, in pixels.

DEFAULT `12 px`

RANGE 0 to 40 px

Space Below

Number

The empty space below the group title, in pixels.

DEFAULT `12 px`

RANGE 0 to 40 px

Corner Radius

Number

How round the corners of the title bar are. 0 keeps them square.

DEFAULT `0 px`

RANGE 0 to 24 px

Background Strength

Slider

How solid the title bar background is: 1 is solid, 0 is clear.

DEFAULT `1`

RANGE 0 to 1, in steps of 0.1

HEADER BORDER

Border Width

Number

Thickness of the line around the group header in pixels. 0 draws no border.

DEFAULT `0 px`

RANGE 0 to 10 px

Border Style

Choice

A solid, dashed, dotted or double line. A double line needs a width of 3 or more to show.

DEFAULT Solid

CHOICES Solid, Dashed, Dotted, Double

Border Color

Color

Color of the line around the group header.

DEFAULT `#e5e7eb`

Sides

Four switches

Choose which sides of the group header get the border. Leave all four on for a full frame.

DEFAULT Top: On · Right: On · Bottom: On · Left: On

TITLE TEXT

Title Size

Number

Text size of the group title.

DEFAULT `14 px`

RANGE 10 to 28 px, in steps of 0.5

Title Weight

Choice

How bold the group title is.

DEFAULT 400 (Normal)

CHOICES 300 (Light), 400 (Normal), 500 (Medium), 600 (Semi Bold), 700 (Bold)

Title Letter Case

Choice

Show the group title as it is, in capitals, in small letters, or with a capital first letter.

DEFAULT As Written

CHOICES As Written, Uppercase, Lowercase, Capitalize

Title Letter Spacing

Number

Extra space between the letters of the group title, as a fraction of the text size.

DEFAULT `0.01 em`

RANGE 0 to 0.3 em, in steps of 0.01

COUNT STYLE

Count Size

Number

Text size of the number of results next to the title.

DEFAULT `14 px`

RANGE 10 to 28 px, in steps of 0.5

Count Weight

Choice

How bold the count is.

DEFAULT 400 (Normal)

CHOICES 300 (Light), 400 (Normal), 500 (Medium), 600 (Semi Bold), 700 (Bold)

Count Letter Case

Choice

Show the count as it is, in capitals, in small letters, or with a capital first letter.

DEFAULT As Written

CHOICES As Written, Uppercase, Lowercase, Capitalize

Count Background

Color

Background of the count, like a small badge. It shows when Background Strength is above 0.

DEFAULT `#e2e8f0`

Background Strength

Slider

How solid the count background is: 0 shows no background (the default), 1 is solid.

DEFAULT `0`

RANGE 0 to 1, in steps of 0.1

Corner Radius

Number

How round the corners of the count badge are. A large number makes a pill.

DEFAULT `0 px`

RANGE 0 to 30 px

Space Inside

Four numbers

The empty space between the count text and the edge of its badge, set for each side.

DEFAULT `0px 0px 0px 0px`

COUNT BORDER

Border Width

Number

Thickness of the line around the group count in pixels. 0 draws no border.

DEFAULT `0 px`

RANGE 0 to 10 px

Border Style

Choice

A solid, dashed, dotted or double line. A double line needs a width of 3 or more to show.

DEFAULT Solid

CHOICES Solid, Dashed, Dotted, Double

Border Color

Color

Color of the line around the group count.

DEFAULT `#cbd5e1`

Sides

Four switches

Choose which sides of the group count get the border. Leave all four on for a full frame.

DEFAULT Top: On · Right: On · Bottom: On · Left: On

Tags and Highlight

How the letters a visitor typed are marked, and how the tags of a result look.

HIGHLIGHT OF TYPED LETTERS

Highlight Background

Color

Background behind the letters a visitor typed, wherever they appear in a result.

DEFAULT `#ffff00`

Highlight Text

Color

Color of the highlighted letters.

DEFAULT `#000000`

Background Strength

Slider

How strong the highlight background is: 0 invisible, 1 solid.

DEFAULT `0.5`

RANGE 0 to 1, in steps of 0.1

Font Weight

Choice

How bold the highlighted letters are.

DEFAULT Bold

CHOICES 100 (Ultra Light), 200 (Extra Light), 300 (Light), 400 (Normal), 500 (Medium), 600 (Semi Bold), 700 (Bold), 800 (Extra Bold), 900 (Ultra Bold), Normal, Bold

TAG COLORS AND STRENGTH

Tag Background

Color

Background of each tag.

DEFAULT `#e0f2fe`

NEEDS Show Tags in Results (Display) switched on

Tag Text

Color

Color of the text inside each tag.

DEFAULT `#0369a1`

NEEDS Show Tags in Results (Display) switched on

Tag Border

Color

Color of the line around each tag.

DEFAULT `#0891b2`

NEEDS Show Tags in Results (Display) switched on

Tag Strength

Slider

How solid the whole tag is, text included: 1 is solid, lower is fainter.

DEFAULT `1`

RANGE 0.1 to 1, in steps of 0.1

NEEDS Show Tags in Results (Display) switched on

Background Strength

Slider

How solid only the tag background is, while the text stays solid: 1 is solid, 0 is clear.

DEFAULT `1`

RANGE 0 to 1, in steps of 0.1

NEEDS Show Tags in Results (Display) switched on

WHAT TAGS SHOW

Most Tags Shown

Number

The most tags shown for one result. 0 shows all of them. With 1, visitors are not told that other tags exist.

To change or hide the word before the tags, use Label Before Tags in General > Visitor Texts.

DEFAULT `0 tags`

RANGE 0 to 20 tags

NEEDS Show Tags in Results (Display) switched on

Show +N for Hidden Tags

Switch

When 2 or more tags may show and a result has more, a small +2 tag tells visitors how many were left out. Switch off to say nothing. With a limit of 1 it is never shown.

DEFAULT On

NEEDS Show Tags in Results (Display) switched on

RENAME OR HIDE TAGS

Tag Names

List of pairs

Show a different name for a tag, or hide a tag, without changing the tour. Visitors can search for either name.

Type a tag exactly as it is written in the tour, then the name visitors should see. Leave the second box empty to hide that tag.

DEFAULT Empty list

TAG LOOK

Corner Radius

Number

How round the corners of a tag are.

DEFAULT `16 px`

RANGE 0 to 20 px

NEEDS Show Tags in Results (Display) switched on

Text Size

Number

Text size inside a tag.

DEFAULT `11 px`

RANGE 8 to 24 px

NEEDS Show Tags in Results (Display) switched on

Font Weight

Choice

How bold the tag text is.

DEFAULT 600 (Semi Bold)

CHOICES 100 (Ultra Light), 200 (Extra Light), 300 (Light), 400 (Normal), 500 (Medium), 600 (Semi Bold), 700 (Bold), 800 (Extra Bold), 900 (Ultra Bold)

NEEDS Show Tags in Results (Display) switched on

Letter Case

Choice

Show tag text as typed, in capitals, in small letters, or with a capital first letter.

DEFAULT Uppercase

CHOICES None, Uppercase, Lowercase, Capitalize

NEEDS Show Tags in Results (Display) switched on

Space Between

Number

Space between one tag and the next.

DEFAULT `2 px`

RANGE 0 to 20 px

NEEDS Show Tags in Results (Display) switched on

Space Inside

Four numbers

The empty space between the tag text and the edge of the tag, set for each side.

DEFAULT `3px 10px`

NEEDS Show Tags in Results (Display) switched on

TAG BORDER

Border

Switch

Draw a line around each tag.

DEFAULT On

NEEDS Show Tags in Results (Display) switched on

Border Width

Number

Thickness of the line around a tag.

DEFAULT `1 px`

RANGE 0 to 6 px

NEEDS Show Tags in Results (Display) switched on

Display

Control how results look and what they show

What Results Show

Choose which parts a result has and how roomy a result row is.

Pictures, icons and the names of the element types have their own sections below.

PARTS OF A RESULT

Show Group Headers — Switch

Show a title bar above each group of results, for example Panorama or Hotspot. How it looks is set in Appearance > Group Headers.

DEFAULT On

Show Group Count — Switch

Show how many results a group has, next to its title.

DEFAULT On

Show Tags in Results — Switch

Show the tags of a result under its name. How tags look is set in Appearance > Tags and Highlight.

DEFAULT On

Show Subtitles in Results — Switch

Show the subtitle (the description text) of an element under its name.

DEFAULT On

Subtitle Instead of Name — Switch

A result that has a subtitle shows the subtitle in place of its name, and the subtitle line under the name is hidden. A result without a subtitle keeps its name.

DEFAULT Off

Show Parent Info

Switch

For an element inside a panorama or 3D model, such as a hotspot, show a line like in Kitchen with the place it belongs to.

DEFAULT On

ROW LAYOUT

Row Spacing

Choice

How much empty space each result has above and below it and between its picture and its text.

DEFAULT Normal

CHOICES Compact, Normal, Roomy

Description Lines

Choice

The most lines a description (subtitle) may take. A longer text is cut with three dots.

DEFAULT 2 lines

CHOICES 1 line, 2 lines, 3 lines, 4 lines, 5 lines

Pictures

Show a small picture beside each result and choose how it looks.

SHOW PICTURES

Show Pictures in Results

Switch

Show a small picture beside each result: the tour's own preview for panoramas, 3D models and videos. Off: results show icons only.

DEFAULT Off

WHERE PICTURES COME FROM

Use the Tour's Own Pictures

Switch

Panoramas, 3D models and videos show their own preview from the tour instead of a placeholder.

DEFAULT On

NEEDS Show Pictures in Results (Display) switched on

Hotspots Use Their Room's Picture

Switch

Hotspots, webframes and objects that have no picture of their own show the picture of the panorama or 3D model they are in.

DEFAULT On

NEEDS Show Pictures in Results (Display) switched on

SIZE AND BORDER

Picture Size

Choice

The size of the pictures. A type can have its own size in Element Types.

DEFAULT Medium (48px)

CHOICES Extra Small (16px), Small (24px), Medium Small (32px), Medium (48px), Large (64px), Extra Large (80px), Huge (96px)

NEEDS Show Pictures in Results (Display) switched on

Corner Radius

Slider

How round the corners of a picture are, in pixels.

DEFAULT `4`

RANGE 0 to 50

NEEDS Show Pictures in Results (Display) switched on

Border Width

Slider

Thickness of the line around a picture, in pixels. 0 draws no border.

DEFAULT `4`

RANGE 0 to 10

NEEDS Show Pictures in Results (Display) switched on

Border Color

Color

Color of the line around a picture.

DEFAULT `#9cbbff`

NEEDS Show Pictures in Results (Display) switched on

SHAPE AND POSITION

Picture Shape

Choice

Square, circle or a wide box. Panorama 2:1 shows a whole panorama preview without cutting it.

DEFAULT Square

CHOICES Square, Circle, Landscape 4:3, Wide 16:9, Panorama 2:1 (whole preview)

NEEDS Show Pictures in Results (Display) switched on

Fit

Choice

Cover fills the box and cuts the edges. Contain shows the whole picture with empty bars.

DEFAULT Cover (fill the box)

CHOICES Cover (fill the box), Contain (whole picture)

NEEDS Show Pictures in Results (Display) switched on

Crop Position

Choice

Which part of a wide picture stays visible when it is cut to fit.

DEFAULT Center

CHOICES Left, Center, Right

NEEDS Show Pictures in Results (Display) switched on

Picture Side

Choice

Put the picture on the left or on the right of the text of a result.

DEFAULT Left of the text

CHOICES Left of the text, Right of the text

NEEDS Show Pictures in Results (Display) switched on

TYPE ICON ON PICTURES

Icon on Each Picture

Choice

A small icon of the element type (panorama, hotspot, video, 3D model …) in a corner of the picture. To show icons only, without pictures, switch Show Pictures in Results off.

DEFAULT Never (picture only)

CHOICES Never (picture only), On every picture, Only on borrowed pictures

NEEDS Show Pictures in Results (Display) switched on

Corner

Choice

Which corner of the picture holds the icon.

DEFAULT Bottom right

CHOICES Bottom right, Bottom left, Top right, Top left

NEEDS Show Pictures in Results (Display) switched on

Icon Shape

Choice

A corner tab or a round dot.

DEFAULT Corner tab

CHOICES Corner tab, Round

NEEDS Show Pictures in Results (Display) switched on

Icon Size

Choice

How much of the picture the icon covers.

DEFAULT Medium

CHOICES Small, Medium, Large

NEEDS Show Pictures in Results (Display) switched on

Show

Choice

The icon of the element type, or its name as a small text across the picture.

DEFAULT Type icon

CHOICES Type icon, Type name (text)

NEEDS Show Pictures in Results (Display) switched on

Icon Color

Color

Color of the icon (or of the text) on the picture.

DEFAULT `#6e85f7`

NEEDS Show Pictures in Results (Display) switched on

Background Color

Color

Color behind the icon or text.

DEFAULT `#ffffff`

NEEDS Show Pictures in Results (Display) switched on

Background Strength

Slider

How solid the background behind the icon is: 0 is clear, 1 is solid.

DEFAULT `0.92`

RANGE 0 to 1, in steps of 0.01

NEEDS Show Pictures in Results (Display) switched on

ON PHONES

Pictures on Phones

Choice

What a phone shows: the desktop setting, pictures only, pictures with an icon, or icons only (lighter and faster).

DEFAULT Same as desktop

CHOICES Same as desktop, Picture only, Picture + icon, Icons only (no pictures)

NEEDS Show Pictures in Results (Display) switched on

Size on Phones

Choice

One picture size on phones. It replaces the size of each element type.

DEFAULT Same as desktop

CHOICES Same as desktop, 24 px, 32 px, 48 px, 64 px

NEEDS Show Pictures in Results (Display) switched on

Shape on Phones

Choice

The picture shape on phones.

DEFAULT Same as desktop

CHOICES Same as desktop, Square, Circle, Landscape 4:3, Wide 16:9, Panorama 2:1 (whole preview)

NEEDS Show Pictures in Results (Display) switched on

PLACEHOLDERS

Placeholder Style

Choice

Generated: a small tile in your brand color with the type icon (no files needed). Picture files: the images of the plugin's assets folder. A picture file you choose for an element type in Element Types is always used.

DEFAULT Generated tile (brand color)

CHOICES Generated tile (brand color), Picture files (assets folder)

NEEDS Show Pictures in Results (Display) switched on

Brand Color

Color

Color of the generated placeholder tiles.

DEFAULT `#6e85f7`

NEEDS Show Pictures in Results (Display) switched on

HOVER ZOOM

Zoom on Hover (Desktop)

Switch

Zoom the picture while the mouse rests on it.

DEFAULT Off

NEEDS Show Pictures in Results (Display) switched on

Zoom on Touch and Hold (Phone)

Switch

Zoom the picture while a finger holds it. A quick tap still opens the result as usual.

DEFAULT Off

NEEDS Show Pictures in Results (Display) switched on

Zoom Size

Choice

How many times bigger the picture gets.

DEFAULT 3 times bigger

CHOICES 1.5 times bigger, 2 times bigger, 3 times bigger, 4 times bigger

NEEDS Show Pictures in Results (Display) switched on

Delay Before Zooming

Choice

How long the mouse must rest on the picture before it grows. A short delay avoids flicker while moving across the list.

DEFAULT 0.2 second

CHOICES No delay, 0.1 second, 0.2 second, 0.3 second, 0.5 second, 1 second

NEEDS Show Pictures in Results (Display) switched on

Icons

Show a small icon beside results that have no picture and choose how it looks.

You choose the icon of each element type in Element Types. Icon sets load by themselves when an icon needs them: from the plugin's own copy first, from the internet as a backup.

SHOW ICONS

Show Icons in Results

Switch

Show a small icon of the element type beside results that have no picture. Off: results show no icons.

DEFAULT On

ICON SYSTEM

Use Custom Icons

Switch

Use your own icons (Font Awesome, Bootstrap Icons, Ionicons, emojis or pictures) instead of the built-in ones. Off: the built-in icons stay, and their size, color and hover effect can still be set below. You choose each icon in Element Types.

DEFAULT Off

NEEDS Show Icons in Results (Display) switched on

ICON LOOK

Icon Size

Choice

The size of the icons. Icons of 64 px or more can crowd the text, especially on phones.

DEFAULT Small (20px)

CHOICES Extra Small (16px), Small (20px), Medium (24px), Medium Large (28px), Large (32px), Extra Large (48px), Huge (64px)

NEEDS Show Icons in Results (Display) switched on

Icon Color

Color

The color of all icons. The same setting as Icon in Appearance > Results List.

DEFAULT `#6e85f7`

NEEDS Show Icons in Results (Display) switched on

Icon Strength

Slider

How solid the icons are: 0 is invisible, 1 is solid.

DEFAULT `0.9`

RANGE 0 to 1, in steps of 0.1

NEEDS Show Icons in Results (Display) switched on

Icon Side

Choice

Put the icon on the left or on the right of the text.

DEFAULT Left

CHOICES Left, Right

NEEDS Show Icons in Results (Display) switched on

Space Beside the Icon

Number

The empty space between the icon and the text, in pixels.

DEFAULT `12 px`

RANGE 0 to 20 px

NEEDS Show Icons in Results (Display) switched on

Icon Corner Radius

Slider

How round the corners of the icon box are, in pixels. Useful for picture icons.

DEFAULT `6`

RANGE 0 to 24

NEEDS Show Icons in Results (Display) switched on

HOVER EFFECT

Grow on Hover

Switch

Make an icon grow a little when the mouse is over its result.

DEFAULT On

NEEDS Show Icons in Results (Display) switched on

Size on Hover

Slider

How much bigger the icon gets on hover: 1.15 is 15% bigger.

DEFAULT `1.15`

RANGE 1.0 to 2.0, in steps of 0.05

NEEDS Show Icons in Results (Display) switched on

Strength on Hover

Number

How solid the icon is on hover: 0 is invisible, 1 is solid.

DEFAULT `1`

RANGE 0 to 1, in steps of 0.1

NEEDS Show Icons in Results (Display) switched on

Element Types

Choose how each kind of result is named and whether it gets a picture and an icon.

A grayed column belongs to a switch that is off: Show Pictures in Results (Pictures), Show Icons in Results and Use Custom Icons (Icons). Placeholder files must be inside the plugin's assets folder. Names and switches reach an open tour right away.

Name Shown (for each kind of result)

Text per kind

The name visitors see for this kind of result, for example in the group titles.

DEFAULT Different for each kind (see the table below)

LENGTH Up to 60 characters

Picture (for each kind of result)

Switch per kind

Show a picture for this kind of result. Off: it shows an icon instead.

DEFAULT On for every kind

Size (for each kind of result)

Choice per kind

The picture size for this kind of result. Default uses the size chosen in Pictures.

DEFAULT Default for every kind

CHOICES Default, 32 px, 48 px, 64 px, 80 px, 96 px, 128 px

Placeholder File (for each kind of result)

Text per kind

The file in the assets folder that stands in when a result has no picture of its own (.jpg, .jpeg, .png, .gif, .webp, .svg).

DEFAULT Different for each kind (see the table below)

LENGTH Up to 120 characters

Icon (for each kind of result)

Switch per kind

Show an icon for this kind of result when it has no picture.

DEFAULT On for every kind

Custom Icon (for each kind of result)

Icon per kind

Choose your own icon for this kind of result. It needs Use Custom Icons in Icons.

DEFAULT Different for each kind (see the table below)

CHOICES An icon of Font Awesome, Bootstrap Icons or Ionicons, an emoji, or a picture address, chosen in the icon picker

DEFAULTS FOR EACH KIND

KIND	NAME SHOWN	PICTURE	SIZE	PLACEHOLDER FILE	ICON	CUSTOM ICON
Panorama	`Panorama`	On	Default	`default-thumbnail.jpg`	On	`fas fa-home`
360 Video	`360 Video`	On	Default	`360-video-default.jpg`	On	`fas fa-vr-cardboard`
Flat Video	`Flat Video`	On	Default	`flat-video-default.jpg`	On	`fas fa-film`
Photo Album	`Photo Album`	On	Default	`photo-album-default.jpg`	On	`fas fa-images`
Map	`Map`	On	Default	`map-default.jpg`	On	`fas fa-map`
Audio	`Audio`	On	Default	`audio-default.jpg`	On	`fas fa-volume-high`
PDF	`PDF`	On	Default	`pdf-default.jpg`	On	`fas fa-file-pdf`
Hotspot	`Hotspot`	On	Default	`hotspot-default.jpg`	On	`fas fa-laptop`
Polygon	`Polygon`	On	Default	`polygon-default.jpg`	On	`fas fa-diamond`
Video	`Video`	On	Default	`video-default.jpg`	On	`fas fa-video`
Webframe	`Webframe`	On	Default	`webframe-default.jpg`	On	`fas fa-laptop`

KIND	NAME SHOWN	PICTURE	SIZE	PLACEHOLDER FILE	ICON	CUSTOM ICON
Image	`Image`	On	Default	`image-default.jpg`	On	`fas fa-image`
Text	`Text`	On	Default	`text-default.jpg`	On	`fas fa-file-alt`
Projected Image	`Projected Image`	On	Default	`projected-image-default.jpg`	On	`fas fa-desktop`
Element	`Element`	On	Default	`element-default.jpg`	On	`fas fa-circle`
Container	`Container`	On	Default	`container-default.jpg`	On	`fas fa-window-restore`
3D Model	`3D Model`	On	Default	`3d-model-default.jpg`	On	`fas fa-cube`
3D Hotspot	`3D Hotspot`	On	Default	`3d-hotspot-default.jpg`	On	`fas fa-gamepad`
3D Model Object	`3D Model Object`	On	Default	`3d-model-object-default.jpg`	On	`fas fa-wrench`
Other (everything else)		On	Default	`default-thumbnail.jpg`	On	

Unnamed Items

Choose what a result with no name shows. The choices are tried in this order.

Order: its own name, the subtitle, the name of its panorama, the tags, the element type, then the text below.

NAME FOR AN ELEMENT WITHOUT ONE

Use the Subtitle — Switch

An element with no name shows its subtitle instead.

DEFAULT On

Use the Name of Its Panorama — Switch

An unnamed element shows the name of the panorama or 3D model it is in, for example Kitchen.

DEFAULT Off

Add the Element Type — Switch

With the name of its panorama, add the kind of element: Hotspot in Kitchen instead of Kitchen. It needs Use the Name of Its Panorama.

DEFAULT Off

Use the Tags — Switch

An unnamed element shows its tags instead.

DEFAULT On

Use the Element Type — Switch

As a last choice an unnamed element shows its kind and a number, for example Hotspot 3.

DEFAULT Off

Text for Unnamed Items — Text

The text shown for an element that has no name and for which none of the choices above applies.

DEFAULT `[Unnamed Item]`

LENGTH Up to 120 characters

Order of Results

Drag the kinds of result into the order visitors should see them in the search.

Results are listed in groups, one for each kind. Drag a row by its handle to move it, or use the arrow buttons. The group at the top is listed first. Names are the ones set in Element Types. A kind that is switched off in Content never shows.

Order of the Groups

List

Results are listed in groups, one for each kind. Drag a row by its handle to move it, or use the arrow buttons. The group at the top is listed first.

Names are the ones set in Element Types. A kind that is switched off in Content never shows.

DEFAULT Panorama, 360 Video, Flat Video, Hotspot, Polygon, Video, Webframe, Image, Text, Projected Image, 3D Model, 3D Hotspot, Element, Container, Audio, PDF, Photo Album, Map, 3D Model Object

Content

Choose which elements of the tour visitors can find in the search

What Is Searched

Choose which kinds of elements visitors can find. An element of a kind that is off is not in the search at all.

Containers are set up in their own section below. How each kind is named, pictured and shown is set in Display > Element Types; hiding single elements by name or tag is set in Filtering.

In Search (for each kind of result) — Switch per kind

Visitors can find elements of this kind. Off: they are not in the search at all, whatever they are called.

DEFAULT Different for each kind (see the table below)

DEFAULTS FOR EACH KIND

KIND	IN SEARCH
Panorama	On
360 Video	On
Flat Video	On
Hotspot	On
Polygon	On
Video	On
Webframe	On
Text	On
Projected Image	On
Other Elements	On
3D Model	On
3D Hotspot	On

KIND	IN SEARCH
3D Model Object	On
Audio	Off
PDF	Off
Photo Album	Off
Map	Off
Image	On

Unnamed Items

Choose which elements without a title are in the search, and how short a name may be.

An element is unnamed when it has no title in 3DVista. What an unnamed element is called in the results is set in Display > Unnamed Items: its subtitle, the panorama it is in, its tags or the text "[Unnamed Item]".

3DVista names the parts of a 3D file "Object" when the 3D artist did not name them, and a model can hold dozens of them. Visitors cannot tell them apart, so they are left out of the search.

ELEMENTS WITHOUT A TITLE

With a Subtitle — Switch

Include elements that have no title but do have a subtitle. Example: a hotspot with no title and the subtitle Kitchen Door. Off: they are not in the search.

DEFAULT On

With Tags Only — Switch

Include elements that have no title and no subtitle but do have tags. Example: a polygon tagged Exit. Off: they are not in the search.

DEFAULT On

Completely Blank — Switch

Include elements that have no title, no subtitle and no tags, for example a panorama nobody named. They are listed as [Unnamed Item] unless Display > Unnamed Items gives them another name. Off: they are not in the search.

DEFAULT On

3D OBJECTS WITH A DEFAULT NAME

Objects Named Just Object — Switch

On: every 3D object named exactly Object is a result, with the 3D model it belongs to shown as its parent. Off: they are left out. 3D objects with a name of their own are always included (when their kind is switched on above).

DEFAULT Off

SHORT NAMES

Shortest Name Shown

Number

Leave out elements whose name has fewer characters than this, for example single letters or numbers. 0 means no limit.

The name as visitors see it. 0 = no limit.

DEFAULT `0 characters`

RANGE 0 to 100 characters

Containers

Let visitors open and close a container of your tour from the search.

A container is an element of 3DVista that holds other elements, such as a menu, a gallery or a floor plan. You drop it on the tour canvas in 3DVista and give it a name. A container is not found by itself: add its name below, or pick it from the open tour. When a visitor picks it in the search, it opens, or closes if it was already open.

Find Containers

Switch

Visitors can find the containers listed below. Off: containers are not in the search.

DEFAULT On

Container Names

List

The containers visitors can open from the search. Add one row for each container and write its name exactly as it is in 3DVista.

Type the name the container has in 3DVista (its Name property). If the phone version of your tour names the same container differently, type that name in the second box, so the right one opens on each. The third box is only for showing visitors another name.

DEFAULT Empty list

Filtering

Choose which results are left out of the search, by name, tag or number

Names

Show only, or hide, the results whose name matches a value of your list.

Name Filter

Choice

Off: names are not checked. Show Only These: only results whose name matches a value of the list are in the search. Hide These: results whose name matches a value are left out.

DEFAULT	Off
CHOICES	Off, Show Only These, Hide These

How Names Are Compared

Choice

Contains: the value is anywhere in the name. Exactly: the whole name is the value. Starts With: the name begins with the value. Pattern: a regular expression, for advanced users.

DEFAULT	Contains
CHOICES	Contains, Exactly (Whole Name), Starts With, Pattern (Advanced)
APPEARS WHEN	Name Filter is Show Only These

How Names Are Compared

Choice

Contains: the value is anywhere in the name. Exactly: the whole name is the value. Starts With: the name begins with the value. Pattern: a regular expression, for advanced users.

DEFAULT	Contains
CHOICES	Contains, Exactly (Whole Name), Starts With, Pattern (Advanced)
APPEARS WHEN	Name Filter is Hide These

Names to Show

List

Only results whose name matches one of these values are in the search.

One value per line. This includes hotspots and other results, not only panoramas. Capitals and accents do not matter. It compares the name shown in the results as the tour gives it: a title from a Data Sources sheet is not used. No values yet.

DEFAULT	Empty list
LENGTH	Up to 6000 characters
APPEARS WHEN	Name Filter is Show Only These

Names to Hide

List

Results whose name matches one of these values are left out of the search.

One value per line. This includes hotspots and other results, not only panoramas. Capitals and accents do not matter. It compares the name shown in the results as the tour gives it: a title from a Data Sources sheet is not used. No values yet.

DEFAULT	Empty list
LENGTH	Up to 6000 characters
APPEARS WHEN	Name Filter is Hide These

Tags

Show only, or hide, the elements that have certain tags.

Tag Filter

Choice

Off: tags are not checked. Show Only These: only elements that have one of the tags are in the search. Hide These: elements that have one of the tags are left out.

DEFAULT	Off
CHOICES	Off, Show Only These, Hide These

Tags to Show

List

Only elements that have one of these tags are in the search.

One tag per line (commas work too), written as in 3DVista; capitals and accents do not matter. Elements without tags are left out, panoramas and containers too. Tags from a Data Sources sheet are not used. No tags yet.

DEFAULT	Empty list
LENGTH	Up to 6000 characters
APPEARS WHEN	Tag Filter is Show Only These

Tags to Hide

List

Elements that have one of these tags are left out of the search.

One tag per line (commas work too), written as in 3DVista; capitals and accents do not matter. Tags from a Data Sources sheet are not used. No tags yet.

DEFAULT	Empty list
LENGTH	Up to 6000 characters
APPEARS WHEN	Tag Filter is Hide These

Panoramas by Number

Show only, or hide, items of the tour by their place in the tour's list.

Number Filter

Choice

Off: no item is left out by its number. Show Only These: only the listed items are in the search. Hide These: the listed items are left out.

DEFAULT	Off
CHOICES	Off, Show Only These, Hide These

Numbers to Show

List

Only the items with these numbers, and everything inside them, are in the search.

One number per line (commas work too). The number is the place in the tour's list of panoramas, videos and 3D models, counted from 1. Containers are not affected. No numbers yet.

DEFAULT	Empty list
LENGTH	Up to 6000 characters
APPEARS WHEN	Number Filter is Show Only These

Numbers to Hide

List

The items with these numbers, and everything inside them, are left out of the search.

One number per line (commas work too). The number is the place in the tour's list of panoramas, videos and 3D models, counted from 1. Hiding an item also hides its hotspots, polygons and 3D objects. No numbers yet.

DEFAULT	Empty list
LENGTH	Up to 6000 characters
APPEARS WHEN	Number Filter is Hide These

Data Sources

Use a Google Sheet or a CSV file to change how items look in the search results; the tour itself is never changed

Source

Choose where the extra information comes from. Only one source is active at a time.

Google Sheets link

Text

Paste the link from your browser's address bar or from the Share button. The sheet must be shared as 'Anyone with the link: Viewer' (or published to the web).

DEFAULT Empty

CSV file

Text

Where the .csv file is. A path is read from the search-pro-v4 folder of the tour (for example business-data/search-data.csv); a full web address (https://...) also works.

DEFAULT `business-data/search-data.csv`

Source

Choice of three

Choose where the extra information comes from. Only one source is active at a time.

Tour only: search the tour's own titles, descriptions and tags. Google Sheets: read a sheet you share with a link. CSV file: read a .csv file stored with the tour.

CHOICES Tour only, Google Sheets, CSV file

DEFAULT Tour only

Sheet Columns

One row describes one item of the tour. Only what you fill in changes; empty cells keep the tour's own value.

COLUMN	WHAT TO PUT IN IT
`id`	Which tour item this row is about: its Title, Tag, Subtitle or internal id, written exactly (capital letters do not matter).
`tag`	Optional second chance: used only if `id` finds nothing.
`name`	The title shown in the search result.
`description`	The text under the title. It shows while Display > Show Subtitles in Results is on.
`imageUrl`	The picture shown in the result (web address or a path in the assets folder). It shows only while Display > Show Pictures in Results is on, and for a kind whose Picture switch in Display > Element Types is on.
`tags`	The tags shown in the result, separated by commas. They show while Display > Show Tags in Results is on.
`elementType`	Panorama, Video360, FlatVideo, Album, Map, Hotspot, Polygon, Video, Webframe, Image, ProjectedImage, Text, 3DModel, 3DHotspot, 3DModelObject or Audio. Helps pick the right item when names repeat.
`parentId`	The panorama or 3D model the item lives in (same rule as `id`). Use it when a title repeats, and for rows whose item is not in the tour: clicking them jumps to this panorama.

This card has no settings of its own.

Remember the Sheet

Keep a copy of a Google Sheet in the visitor's browser so the tour starts faster. Most tours never need this.

Keep a Copy

Switch

Keeps a copy of a Google Sheet in the visitor's browser so the tour starts faster. Changes you make in the sheet then appear only after this time. Not used for CSV files.

DEFAULT Off

Keep It For

Number

How long the remembered copy is used before the sheet is read again (1 to 1440 minutes).

Minutes, from 1 to 1440.

DEFAULT `60`

RANGE 1 to 1440

Animations

Choose how the search bar, the results and the hover effects move

Preview

See how the search moves with the settings on this page. The colors are only for the preview.

Animations are off, so the search appears at once. Turn on Enable Animations to see the movement.

This card has no settings of its own.

Motion

Turn the animations on, pick a ready-made feel and choose how movement speeds up and slows down.

Enable Animations

Switch

On: the search bar, the results and the hover effects move as set on this page. Off: everything appears at once.

DEFAULT Off

Style

Choice (not saved by itself)

Pick a ready-made feel. It fills in the numbers on this page, and you can still change them one by one (the Style then shows Custom).

Choosing a style fills in the numbers of this page; the style itself is not saved.

DEFAULT Balanced

CHOICES Balanced, Subtle, Lively, Minimal, Custom

Easing

Choice

How the movement speeds up and slows down. Smooth is the default; Overshoot, Spring and Bounce go a little past the end and settle. A part of the search can use its own easing.

DEFAULT Smooth

CHOICES Smooth, Snappy, Gentle, Ease Out, Ease In, Linear, Overshoot, Spring, Bounce

Exact Curve

Text

The exact curve of the Easing above. Type your own, such as cubic-bezier(0.22, 1, 0.36, 1) or ease-out, to use a curve that is not in the list. A curve the browser cannot read is not used.

The same setting as Easing: typing a curve here sets it.

DEFAULT `cubic-bezier(0.22, 1, 0.36, 1)`

Respect Reduced Motion

Switch

On (recommended): visitors whose device is set to reduce motion see only a short fade. Off: everyone sees the same animations.

DEFAULT On

Reduced Motion Fade

Number

How long the short fade lasts for visitors who asked for less motion. 0 shows everything at once.

DEFAULT `100 ms`

RANGE 0 to 1000 ms, in steps of 10

Opening and Closing

Choose how the search bar appears when a visitor opens it and how it leaves when they close it.

Opening Effect

Choice

How the search bar appears. None shows it at once.

DEFAULT Zoom and Slide From Above

CHOICES None, Fade, Slide From Above, Slide From Below, Slide From Left, Slide From Right, Zoom, Zoom and Slide From Above, Zoom and Slide From Below

Opening Duration

Number

How long the search bar takes to appear. 300 is a responsive start, 200 is snappy.

DEFAULT `300 ms`

RANGE 0 to 2000 ms, in steps of 10

Closing Effect

Choice

How the search bar leaves. None hides it at once.

DEFAULT Zoom and Slide From Above

CHOICES None, Fade, Slide From Above, Slide From Below, Slide From Left, Slide From Right, Zoom, Zoom and Slide From Above, Zoom and Slide From Below

Closing Duration

Number

How long the search bar takes to leave. Usually shorter than the opening.

DEFAULT `200 ms`

RANGE 0 to 2000 ms, in steps of 10

Slide Distance

Number

How far the bar travels for the effects that slide. 0 keeps it in place.

DEFAULT `20 px`

RANGE 0 to 200 px

Start Size

Number

The size the bar starts from when it zooms in, and shrinks to when it zooms out. 100% means no zoom.

DEFAULT `95 %`

RANGE 50 to 100 %

Search Bar Easing

Choice

The shape of the opening and closing. Leave it on the default to follow Motion.

DEFAULT Same as Motion

CHOICES Same as Motion, Smooth, Snappy, Gentle, Ease Out, Ease In, Linear, Overshoot, Spring, Bounce

Search Field and Clear Button

Choose how the search field reacts when a visitor clicks into it and how the clear button comes and goes.

Focus Duration

Number

How long the field takes to change when a visitor clicks into it (the focus ring and the text style fade in). 0 changes at once.

DEFAULT `200 ms`

RANGE 0 to 1000 ms, in steps of 10

Grow While Typing

Number

How much larger the field becomes while a visitor types. 100% keeps its size; 103% is a gentle grow.

DEFAULT `100 %`

RANGE 100 to 110 %

Clear Button Fade

Number

How long the clear button and the swap between the search icon and the clear icon take. 0 swaps at once.

DEFAULT `200 ms`

RANGE 0 to 1000 ms, in steps of 10

Results Appearing

Choose how results and their groups appear, and how many of them move one after the other.

EACH RESULT

Effect

Choice

How each result appears. None shows the results at once.

DEFAULT Slide From Left

CHOICES None, Fade, Slide From Above, Slide From Below, Slide From Left, Slide From Right, Zoom, Zoom and Slide From Above, Zoom and Slide From Below

Duration

Number

How long each result takes to appear. 200 feels smooth, 150 quicker.

DEFAULT `200 ms`

RANGE 0 to 2000 ms, in steps of 10

Slide Distance

Number

How far a result travels for the effects that slide. 8 to 12 is a subtle polish; 0 only fades.

DEFAULT `10 px`

RANGE 0 to 100 px

Delay Between Results

Number

How long one result waits for the one before it. 0 shows them together; 40 to 100 gives a smooth cascade.

DEFAULT `50 ms`

RANGE 0 to 200 ms, in steps of 5

Animate Only the First

Number

Only this many results move; the rest appear at once, so a long list is never slow. The last one that moves never waits longer than 0.8 seconds.

DEFAULT `12 results`

RANGE 1 to 50 results

Play

Choice

After Every Change to the Search plays the entrance each time the results change while a visitor types. Only When the List Opens plays it once and then lets the list update quietly.

DEFAULT After Every Change to the Search

CHOICES After Every Change to the Search, Only When the List Opens

GROUPS OF RESULTS

Effect

Choice

How each group (Panorama, Hotspot and so on) appears together with its title.

DEFAULT Slide From Below

CHOICES None, Fade, Slide From Above, Slide From Below, Slide From Left, Slide From Right, Zoom, Zoom and Slide From Above, Zoom and Slide From Below

Duration

Number

How long each group takes to appear.

DEFAULT `200 ms`

RANGE 0 to 2000 ms, in steps of 10

Slide Distance

Number

How far a group travels for the effects that slide.

DEFAULT `10 px`

RANGE 0 to 100 px

ALL RESULT EFFECTS

Start Size

Number

The size results, groups and messages start from for the zoom effects. 100% means no zoom.

DEFAULT `95 %`

RANGE 50 to 100 %

Results Easing

Choice

The shape of the movement of the results, groups and messages. Leave it on the default to follow Motion.

DEFAULT	Same as Motion
CHOICES	Same as Motion, Smooth, Snappy, Gentle, Ease Out, Ease In, Linear, Overshoot, Spring, Bounce

List Box and Messages

Choose how the box around the results appears and how the message for a search without results appears.

LIST BOX

Effect

Choice

How the box around the results appears when the first results come. None keeps it still.

DEFAULT None

CHOICES None, Fade, Slide From Above, Slide From Below, Slide From Left, Slide From Right, Zoom, Zoom and Slide From Above, Zoom and Slide From Below

Duration

Number

How long the box takes to appear.

DEFAULT `200 ms`

RANGE 0 to 2000 ms, in steps of 10

Slide Distance

Number

How far the box travels for the effects that slide.

DEFAULT `8 px`

RANGE 0 to 100 px

NOTHING FOUND MESSAGE

Effect

Choice

How the message appears when a search finds nothing.

DEFAULT Fade

CHOICES None, Fade, Slide From Above, Slide From Below, Slide From Left, Slide From Right, Zoom, Zoom and Slide From Above, Zoom and Slide From Below

Duration

Number

How long the message takes to appear.

DEFAULT `200 ms`

RANGE 0 to 2000 ms, in steps of 10

Slide Distance

Number

How far the message travels for the effects that slide.

DEFAULT `8 px`

RANGE 0 to 100 px

Hover and Press

Choose how a result reacts when the pointer is over it or a visitor presses it.

Hover Lift

Number

How far a result rises while the pointer is over it. 0 keeps it still (the color still changes).

DEFAULT `2 px`

RANGE 0 to 10 px

Hover Duration

Number

How long the hover look takes to change. 0 changes at once.

DEFAULT `200 ms`

RANGE 0 to 1000 ms, in steps of 10

Press Size

Number

The size of a result while it is pressed. 100% means no press effect; 97% shrinks it a little.

DEFAULT `100 %`

RANGE 90 to 100 %

Icon Hover Duration

Number

How long the icon of a result takes to change when the pointer is over the result. Whether the icon grows, and by how much, is set in Display.

Whether the icon grows, and by how much, is set in Display.

DEFAULT `200 ms`

RANGE 0 to 1000 ms, in steps of 10

Advanced

See what the search finds in your tour and tune how it matches what visitors type

What the Search Sees in Your Tour

Count the elements of the open tour and see which of them visitors can find. Nothing is changed.

This card has no settings of its own. It is used to scan the content of your tour's elements.

Search Tuning

Fine-tune when a search starts, which results show and how closely they must match what was typed.

Higher means a match there ranks the result higher.

WHEN SEARCHING STARTS

Start Searching After

Number

How many characters a visitor types before results appear.

DEFAULT `2 chars`

RANGE 1 to 10 chars

Wait After Typing

Number for Desktop and Phone

How long the search waits after the last key press before it runs. Shorter feels faster, longer saves effort on slow devices.

DEFAULT Desktop: `150 ms` · Phone: `300 ms`

RANGE 0 to 2000 ms, in steps of 50

RESULTS

Show at Most

Number

The most results shown for a typed search. 0 shows every match. Typing * always lists everything.

DEFAULT `0 results`

RANGE 0 to 500 results, in steps of 5

Highlight Matches

Switch

On: the letters a visitor typed are highlighted in every result. Off: results show plain text.

DEFAULT On

HOW CLOSELY RESULTS MUST MATCH

Match Tolerance

Slider

Exact only finds names that contain what was typed. Forgiving also finds results with typos or missing letters.

DEFAULT `0.4`

RANGE 0 to 1, in steps of 0.05

Shortest Match

Number

The fewest letters in a row that must match for a result to count. 1 is the most forgiving; 2 or 3 leaves out results that share only a single letter.

DEFAULT `1 chars`

RANGE 1 to 5 chars

Search Operators

Switch

On: visitors can type a space for and, | for or, ! to leave a word out, ^ for names that start with a word and = for an exact name. Off: the text is searched as typed.

DEFAULT On

Match Capital Letters

Switch

On: capital letters count, so Office and office are different words (a forgiving Match Tolerance still finds small differences). Off: capital letters make no difference.

DEFAULT Off

WHAT MATTERS MOST

Name

Slider

How much a match in the name of an element counts.

DEFAULT `1`

RANGE 0.1 to 1, in steps of 0.1

Description

Slider

How much a match in the description counts.

DEFAULT `0.8`

RANGE 0.1 to 1, in steps of 0.1

Tags

Slider

How much a match in a tag counts.

DEFAULT `0.6`

RANGE 0.1 to 1, in steps of 0.1

Panorama Name

Slider

How much a match in the name of the panorama an element lives in counts.

DEFAULT `0.3`

RANGE 0.1 to 1, in steps of 0.1