
## DHCP Project Preparation

2017.05


### 1. DHCP Client的虚拟机




#### 1.1 设置"网卡1"




#### 1.2设置"网卡2"




#### 2. DHCP server的虚拟机






#### 2.1 设置"网卡1"



#### 2.2 检查"网卡2"



#### 3. 修改网络配置

- 启动两个虚拟机,按照以下方式修改网络配置,然后保存配置,重启虚拟机
- Windows
  - 打开Xshell,输入 ssh <u>student@127.0.0.1</u> 2000,进入dhcp client虚拟机
    - sudo vim /etc/network/interfaces,修改eth1的配置为-
  - 新增Xshell选项卡,输入 ssh <u>student@127.0.0.1</u> 2002,进入dhcp server虚拟机
    - sudo vim /etc/network/interfaces,修改eth1的配置为
- Mac
  - 打开Terminal,输入ssh <u>student@127.0.0.1</u> –p 2000,进入dncp client虚拟机
    - sudo vim /etc/network/interfaces,修改eth1的配置为 •
  - 新增Terminal,输入ssh <u>student@127.0.0.1</u> –p 2002,进入dhcp <u>server</u>虚拟机
    - sudo vim /etc/network/interfaces,修改eth1的配置为

auto eth1
iface eth1 inet static
address 0.0.0.0
netmask 0.0.0.0

auto eth1 iface eth1 inet static address 192.168.0.1 netmask 255.255.255.0

### 4. 增加iptables规则


- 在Linux系统中,当数据包的目标地址为255.255.255.255广播地址,源地址必须设置为0.0.0.0,数据包才能被处理
- •由于普通的socket函数不能设置源地址为0.0.0.0,所以需要利用 iptables工具对广播数据包修改源地址
- 请分别在两个虚拟机的终端模拟器内执行:
  - sudo iptables -t nat -A POSTROUTING -d 255.255.255.255 -o eth1 -j SNAT -- to-source 0.0.0.0
  - sudo iptables-save > /etc/network/iptables.rules
  - sudo vim /etc/rc.local, 修改为以下2句

iptables-restore < /etc/network/iptables.rules
exit 0</pre>

sudo sh -c "iptables-save > /etc/network/
iptables.rules"

#### 5. Test

- In xShell or Terminal of DHCP-Server VM
  - sudo wireshark
- In xShell or Terminal of DHCP-Client VM
  - sudo dhclient eth1
- DHCP DISCOVER should display in Wireshark:



#### 6. Hints about broadcast

Set socket: (#include <sys/socket.h>)

int setsockopt (SOCKET s, int level, int optname, const char\* optval, int optlen);

0:success -1:error

s(套接字): 指向 一个打开的套接 口描述字 level:(级别): 指定选项代码 的类型,包含 SOL\_SOCKET和 IPPROTO\_TCP (这里选用基 本套接口 SOL\_SOCKET) optname(选项 名): 选项名称。 指明要设置的 选项,包括 SO\_BROADCAST 允许发送广播 数据等

optval(选项值): 是一个指向变 量的指针类型, 指向存放选项 值的缓冲区 optlen(选项长度):
optval 的大小

• eg: allow socket to broadcast

setsockopt(sock,SOL\_SOCKET,SO\_BROADCAST,&i,len);

• 网络接口信息结构体struct ifreq (#include <net/if.h>)

```
struct ifreq {
         char ifr name[IFNAMSIZ]; /* Interface name */
         union {
                   struct sockaddr ifr addr; /* address */
                   struct sockaddr ifr dstaddr; /* other end of p-p lnk */
                   struct sockaddr ifr broadaddr; /* broadcast address */
                   struct sockaddr ifr netmask; /* interface net mask */
                   struct sockaddr ifr hwaddr; /* MAC address */
                   short ifr flags; /* flags */
                   int ifr ifindex;
                   int ifr metric; /* metric */
                   int ifr mtu; /* mtu
                   struct ifmap ifr map; /* device map
                   char ifr slave[IFNAMSIZ]; /* slave device */
                   char ifr newname[IFNAMSIZ]; /* New name */
                   char *ifr data; /* for use by interface */
         };
};
```

eg: declare an ifreq struct to store eth1 interface information

```
struct ifreq if_eth1;
strcpy(if_eth1.ifr_name, "eth1");
```

• Example: Allow a socket to broadcast and bind the socket to interface eth1

```
#include <sys/socket.h> /* for setsockopt() */
#include <net/if.h> /* for ifreq */
int i=1;
struct ifreq if_eth1;
strcpy(if_eth1.ifr_name, "eth1");
socklen_t len = sizeof(i);
/* Allow socket to broadcast */
setsockopt(sock,SOL_SOCKET,SO_BROADCAST,&i,len);
/* Set socket to interface eth1 */
if (setsockopt(sock, SOL_SOCKET, SO_BINDTODEVICE,(char *)&if_eth1, sizeof(if_eth1)) < 0) {
    printf("bind socket to eth1 error\n");
}</pre>
```

Set address:
 set local address to 0.0.0.0 and broadcast address to 255.255.255.255

• Example:

Server:

Client:

```
/*Zero out structure*/
memset(&servAddr, 0, sizeof(servAddr));
/* Internet addr family */
servAddr.sin_family = AF_INET;
/* Server port */
servAddr.sin_port = htons(serverPort);
/*Server IP address 0.0.0.0*/
servAddr.sin_addr.s_addr = htonl(INADDR_ANY);
if ((bind(sock, (struct sockaddr *)&servAddr,sizeof(servAddr))) < 0){
    printf("bind() failed.\n");
}
/*Client IP address 255.255.255.255*/
clntAddr.sin_addr.s_addr = inet_addr(broadcastIP);</pre>
```

```
/*Zero out structure*/
memset(&clntAddr, 0, sizeof(clntAddr));
/* Internet addr family */
clntAddr.sin_family = AF_INET;
/* Client port */
clntAddr.sin_port = htons(clientPort);
/*Client IP address 0.0.0.0*/
clntAddr.sin_addr.s_addr = htonl(INADDR_ANY);
if ((bind(sock, (struct sockaddr *)&clntAddr,sizeof(clntAddr))) < 0){
    printf("bind() failed.\n");
}
/*Server IP address 255.255.255.255*/
servAddr.sin_addr.s_addr = inet_addr(broadcastIP);</pre>
```

# End