Deform Curves on Surface Node

The *Deform Curves on Surface* node translates and rotates each curve based on the difference in its root position. The root position is defined by UV coordinates stored on each curve and the UV Map selected for the purpose in the Curves surface settings.

The transformation is calculated based on the difference of the original mesh (before shape keys and modifiers are evaluated), and the final mesh.

Unlike other geometry nodes, this node has quite a few implicit inputs:

- The original and evaluated mesh are retrieved from the modifier object's surface property. This means the node only works for curves objects.
- The original and evaluated UV map are also retrieved from the object's surface property.
- A 3D vector attribute named rest_position, used for calculating tangents for rotating curves that are consistent with the tangents calculated of the original mesh (the rotation needs to be calculated from the normal and tangent of the original and evaluated meshes).
- A 2D vector attribute on the curve domain named surface_uv_coordinate to store the location of the root positions on the surface mesh' UV map.

In future development, this node will be generalized so the setup is more flexible.

Parts of the internal operation are similar to the Sample UV Surface Node.

Warning

In order to achieve consistent deformation after the Subdivision Surface Modifier, the *UV Smooth* option of the modifier should be set to *None*. Otherwise the surface UV map will be subdivided in a way that may invalidate the curve UV attachement points stored in the surface_uv_coordinate attribute.

Inputs

Curves

Standard curves input.

Properties

This node has no properties.

Outputs

Curves

Standard curves output.

Previous Curves to Grease Pencil Node Copyright $\$: This page is licensed under a CC-BY-SA 4.0 Int. License Made with Furo Last updated on 2025-05-10

View Source View Translation Report issue on this page Fill Curve No