

Knowledge Base

How can we help?

[Home](#) > [Tutorials](#) > Set Up Your DigiCert Provided eToken

Set Up Your DigiCert Provided eToken

Solution ID : S0260521210823

Last Modified : 04/22/2026



Chat



Learn how to set up your code signing DigiCert-provided hardware token.

Before you begin

Do you have a login password for your token or were you provided with an initialization code?

Or do you have no initialization code nor password?

Important:

The initialization code is **NOT** the token password. This can commonly cause confu

Menu options:

- **Initialization code present or missing**

This option means the eToken is blank, and you must install the certificate on the eToken. See [Install your code signing certificate on your hardware eToken](#) below.

- **Password has been provided**

This option means the certificate comes preinstalled on your eToken. You need to unlock the eToken to access your certificate. See [Initialize your eToken](#) below.

Please make sure you meet these prerequisites:

- DigiCert-provided hardware token: SafeNet 5110 CC, SafeNet 5110 FIPS, or SafeNet 5110+ FIPS.



- Code signing or EV code signing certificate order number.
- Administrator permissions on your computer.
- Secure password manager. [See Passwords 101](#).

Important:

If you incorrectly enter a password too many times, you can permanently disable your eToken. We recommend using a secure password manager to track the passwords used for initializing your eToken.

Install your code signing certificate on your eToken

1. In your CertCentral account, in the left main menu, go to **Certificates > Orders**.
2. On the **Orders** page, select the certificate's order number.


For CertCentral Subscription accounts:

- a. In the left main menu, go to **My Digital Trust Products > Certificates**.
 - b. On the **Certificates** page, select the certificate's order number.
3. On the certificate's **Order details** page, in the **Certificate detail** section, in the **Certificate actions** dropdown, select **Install certificate**.
 4. Use the following link to download and install the DigiCert Hardware Certificate Installer:

[Download the DigiCert Hardware Certificate Installer](#)

2. Learn how to [Install the Safenet Drivers](#).

5. Copy the initialization code for your order.
6. Open the DigiCert Hardware Certificate Installer.
7. In the **DigiCert Hardware Certificate Installer** on the **Initialization Code** page, in the **Initialization Code** box, enter the initialization code from your CertCentral account and then select **Next**.



8. Plug in your eToken.
9. On the **Token Detection** page, check **Re-initialize my token and permanently delete any existing certificates and keys** and then



unchecked.




10. On the **Key information** page, do one of the following tasks and then select **Next**:

- o RSA

1. Under Key Type, select RSA.
2. Under Key Size/Curve Name, select 4096.

- o ECC Key Types

1. Under Key Type, select ECC
2. Under Key Size/Curve Name, select p-256 or p-384.





11. On the **Token Setup** page, do the following tasks:

1. Add a **Token Name**.

The token name is used to identify the eToken. This name is helpful when you have multiple eTokens.

2. Create a **Token Password**.

This password (sometimes called a token PIN) is required to access the certificates saved on the eToken.



12. READ THIS BEFORE YOU CONTINUE

On the **Administrator Password** page, do one of the following tasks:

1. If you have **NOT** changed the Administrator Password since receiving your eToken, leave **Use factory default Administrator password** checked and select **Finish**.
2. If you have set a new Administrator Password (done outside of DigiCert Support using the SafeNet client), uncheck **Use factory default Administrator password**, enter the current



13. On the **Certificate Installation** page, be patient and wait. Some of the steps may take several minutes to complete. Wait to **remove the eToken** until the whole process is completed. Generating an RSA 4096-bit key will take time. Let the process complete.



14. When the process finishes, select **Close**.





15. You can now use the code signing certificate on your eToken to sign code.

Initialize your eToken

1. In your CertCentral account, in the left main menu, go to **Certificates > Orders**.
2. On the **Orders** page, select the certificate's order number.
3. On the certificate's Order details page, in the Certificate detail section, in the Certificate actions dropdown, select Initialize Token.

Important: Do not proceed without your DigiCert-provided hardware token. You need the eToken to complete these steps. Additionally, some information is only shown one time.

4. On the initialization page, confirm you have your eToken.
If you have not received your DigiCert-provided hardware token, **do not** proceed. You can use the link to check your tracking information. However, come back once you have your DigiCert-provided token.
 1. Now that you have your DigiCert-provided hardware token, check **I have received the hardware token**.
 2. When ready, select **Submit**.



store it in a safe place.

Warning: Your preassigned password will only be visible once. Make sure to take note of this password.

You need it to access your certificate on your DigiCert-provided hardware token.

See [Password 101](#).

6. Use the link to download and install the DigiCert Hardware Certificate Installer.
 1. You must install the [SafeNet Authentication Client Tools](#) on any system you plug the eToken in to sign code.
 2. Learn how to [install the SafeNet Drivers](#).
7. **Change the eToken password.**

The eToken password is used to **access the eToken certificate store**.

 1. Open the SafeNet Authentication Client and then connect the eToken to your computer.
 2. In the SafeNet Authentication Client, on the top of the page, click the cog icon (**Advanced View button**).
You should now see the eToken listed in the tree menu on the left side of the page.
 3. Right-click on the eToken name and select **Change Password**.
 4. On the change password page, enter your **Current Token Password** from the **Initialization page** in CertCentral.
 5. Next, create a new password.



7. When ready, select **OK**.

8. You can use the certificate on your eToken to sign code.

Password 101

Warning: The SafeNet eToken uses multiple passwords for authentication. If an **Administrator Password** is entered incorrectly **five times**, the eToken is permanently locked.

The SafeNet eToken uses the following passwords:

- **Administrator Password:**

The default Administrator Password is **"0" 48 times** as provided by the manufacturer. If "this" password is lost, you are permanently locked out of the eToken and must purchase a new one. DigiCert does not set up this password.

- **Token Password:**

This password is used to **access the eToken certificate store**. If lost, you can reset the eToken and reinstall the certificate.

- **Personal Unlocking Key (PUK):** Default PUK is 000000.

DigiCert does not use the PUK in our process.



- Your password should contain at least 8 characters.
- Your password should include both upper-case characters and lower-case characters as well as numerals and special characters (for example: !, \$, %, #).
- The minimum password length and character requirements apply to both the Token password and the Administrator password.

Troubleshooting

1. My token appears as "SafeNet Token JC 0."

Your eToken has been permanently disabled due to incorrect password attempts. Please contact [DigiCert Support](#) to order a new eToken.



2. I lost my Administrator password.

The administrator password is required to reset the device and is unrecoverable. Please contact [DigiCert Support](#) to order a new eToken.

Note: The manufacturer sets this password, **not** DigiCert.

3. I lost my Token password.

The Token Password is used to access the eToken certificate store. Use the Administrator Password to reset the eToken password if lost.



1. Reissue your certificate.
 - [Reissue or re-key a Code Signing certificate](#)
 - [Reissue or re-key an EV Code Signing certificate](#)
 - [Rekeying Your DigiCert Document Signing Certificate](#)
2. Re-initialize your eToken. After DigiCert reissues your certificate, install it on your eToken. See [Install your code signing certificate on your hardware token](#).

Note: Items 4, 5, 6 and 7 refer to troubleshooting errors for the **DigiCert Hardware Certificate Installer**.

4. Error "The Initialization Code was invalid, has already been used, or has expired."

- **Scenario 1:** The user has an existing order in a reissue state.

Solution:

1. Log in to the account > Certificates > Orders > Click on the order number > Certificate Actions > Reissue Certificate > Provisioning options > Use existing token > Submit request.
2. Return to the order > Certificate Actions > Install certificate > Copy the new initialization code.



option in the CertCentral account.

Solution:


Reissue the certificate when the install certificate option is not displayed under certificate actions.

1. Log in to the account > force a reissue using the link below in a new tab on the browser where you are logging in
from: <https://digicert.com/secure/orders/{order-number}/reissue>
 2. Select Provisioning options > Use existing token > Submit request.
 3. Return to the order > Certificate Actions > Install certificate > Copy the new initialization code
- **Scenario 3:** Some time has passed before an install attempt has been made which resulted in the above error.

Solution:

Force reissue the certificate when only the install certificate option is displayed under certificate actions.

1. Log in to the account > force a reissue using the link below in a new tab on the browser where you are logging in from:
<https://digicert.com/secure/orders/{order-number}/reissue>
2. Select Provisioning options > Use existing token > Submit request.
3. Return to the order > Certificate Actions > Install



5. Error: 8-0x00000062

This error is caused by trying to install your certificate on a token that does not support RSA above 2048.

You will need to choose ECC in the DigiCert Hardware Certificate Installer to complete the installation or reissue the order and purchase an additional token that will be compatible. ECC is not always compatible with all signing tools, so this option is only if you need to sign urgently and the signing tool you utilize supports ECC or are unable to purchase a new token at the time. It is recommended that you have a supported token.


6. Error: 5-0x00000030

This error is related to not having the latest Safenet version. To solve this issue please update to the latest Safenet version which you can find [here](#).



This error is related to having too many code signing certificates on the same token. To solve this issue please remove some of the certificates to ensure sufficient space is available for another certificate. Once you have removed the certificates, please reattempt the initialization process.

Did you find this page helpful?



The most-trusted global provider of high-assurance TLS/SSL, PKI, IoT and signing solutions.



8/14/2026

Support

Products



© 2022-2026, DigiCert, Inc. All rights reserved.

[Cookie Settings](#)