

B2W Estimate API Help Guide

How to reach a customer’s Estimate API, sign in, send the right headers, read and update estimate data, and work Estimate API tickets. Every example uses the **B2WTechSupport** environment.

● Example environment

Checked Oct 2, 2026

ENVIRONMENT	B2WTechSupport
ESTIMATE API URL	https://b2w-eus10.b2w.trimble.com/EstAPI_B2WTechSupport
API VERSION	v1
SIGN-IN	Active Directory user name and password
METHODS	GET POST PUT · no DELETE

Understand the basics

What the Estimate API covers, how it differs from the Ops API, and where to find it.

1 What is the B2W Estimate API?

SHORT ANSWER

The Estimate API lets other software read and write B2W Estimate data: estimates and their items and components, plus the resources, organizations, and categories behind them. It is a REST API that speaks JSON, like the Ops API, but it signs in differently and needs a few extra headers.

The B2WTechSupport catalog lists 56 functional areas and 227 operations. It supports **GET**, **POST**, and **PUT**. There is no DELETE.

How it differs from the Ops API

	OPS API	ESTIMATE API
Address prefix	OpsAPI_	EstAPI_
Login	TID UUID + secret, client ID + secret, or user name + password	Active Directory user name + password only
Extra headers	None beyond the token	DatabaseName on every data call; ClientID and ClientSecret when Client ID Security is on
Results	A JSON array	An object with an Items array
Updates	PUT the whole record	PUT the whole record, including its AntiTamperToken

	OPS API	ESTIMATE API
Delete	Supported	Not supported



Not supported by the Estimate API

- DELETE.
- Creating, updating, or modifying the cost structure in an estimate.
- Creating, updating, or modifying container components in an estimate or in resources.
- Creating or updating organizations in an estimate.

2

How do I find a customer's Estimate API URL?

SHORT ANSWER

Use the same formula as the Ops API with the `EstAPI_` prefix:

`https://{cluster}/EstAPI_{environment}` . For B2WTechSupport, that is `https://b2w-eus10.b2w.trimble.com/EstAPI_B2WTechSupport` .

`https://b2w-eus10.b2w.trimble.com/EstAPI_B2WTechSupport`

CLUSTER (HOST) **PREFIX** **ENVIRONMENT**

The path is not case-sensitive, so `estapi_B2WTechSupport` works too. In the Cloud Management Portal, the address is listed as the **Est API URL** under **Estimate API Configuration**:

Estimate API Configuration		
Environment	Est API URL	MR API URL
B2WTechSupport	https://b2w-eus10.b2w.trimble.com/EstAPI_B2WTechSupport ①	https://b2w-eus10.b2w.trimble.com/MRAPI_B2WTechSupport ②

Figure 1. ① The Est API URL. ② The MR API URL sits in the same row. The Est API Secret is further right on that row.

Check a customer's environment

TOOL

Environment checker

Builds all three API addresses and checks each one

Cluster `b2w-eus10.b2w.trimble.com` · Environment `B2WTechSupport` · [Ops site](#)

Ops API

● Not checked

Press Check to test it

`https://b2w-eus10.b2w.trimble.com/OpsAPI_B2WTechSupport`

Estimate API

● Not checked

Press Check to test it

`https://b2w-eus10.b2w.trimble.com/EstAPI_B2WTechSupport`

Management Reporting API

● Not checked

Press Check to test it

`https://b2w-eus10.b2w.trimble.com/MRAPI_B2WTechSupport`

3

Where is the Estimate API documentation?

SHORT ANSWER

Add `/doc/index.html` to the Estimate API URL. It is a standard Swagger page with the setup notes at the top and every functional area below.

`https://b2w-eus10.b2w.trimble.com/EstAPI_B2WTechSupport/doc/index.html`

B2W Estimate API v1 OAS3

General Information (click to expand/collapse)

Post-Installation Step (click to expand/collapse)

Configuration (click to expand/collapse)

Usage Guidelines (click to expand/collapse) ①

Testing Guidelines (click to expand/collapse) ②

Troubleshooting Guidelines (click to expand/collapse)

API Documentation

The following sections provide detailed information regarding every functional area. Click on the section title to expand/collapse that section.

BidAs ③



BidSchedule



Figure 2. Click a heading to expand it. ① Usage Guidelines covers login, Client ID Security, and the AntiTamperToken. ② Testing Guidelines links the official Postman collection and the basic tests. ③ Functional areas expand into their operations.

The machine-readable catalog is at `/doc/v1/EstAPI.json`. The setup sections (Post-Installation Step and Configuration) describe on-premises installs, so for cloud customers the ones to read are Usage, Testing, and Troubleshooting.

Sign in

Get a token, then send it with the headers every Estimate call needs.

4 How do I log in and get a Bearer Token?

SHORT ANSWER

Send `GET {baseUrl}/Login` with `userName` and `password` headers for an Active Directory account that has access to Estimate. The `AccessToken` in the response is your bearer token.

1 Use a Windows account

The `userName` is the Windows account name of an Active Directory user who can access the Estimate data, written as `DOMAIN\user`.

2 Send both headers

Credentials go in headers only. Both `userName` and `password` are required.

3 Copy the AccessToken

Send it as `Authorization: Bearer <AccessToken>` on every other call. The response also has a `RefreshToken`, which the docs say to ignore; it is there for future use.

POSTMAN

GET {{BaseURL}}/Login	
HEADERS	
userName	{{UserName}} (DOMAIN\user)
password	{{Password}}
BODY	
none	Login never takes a body.

POWERSHELL

POWERSHELL

```
$baseUrl = "https://b2w-eus10.b2w.trimble.com/EstAPI_B2WTechSupport"

# Windows (Active Directory) account of an Estimate user, as DOMAIN\user
$login = Invoke-RestMethod -Method Get -Uri "$baseUrl/Login" -Headers @{
    userName = "DOMAIN\jsmith"
    password = "<password>"
}

$token = $login.AccessToken # this is your bearer token
```

CURL

CURL · BASH, MACOS, GIT BASH

```
curl -s 'https://b2w-eus10.b2w.trimble.com/EstAPI_B2WTechSupport/Login' \
-H 'userName: DOMAIN\jsmith' \
-H 'password: <password>'
```

RAW HTTP

HTTP REQUEST

```
GET /EstAPI_B2WTechSupport/Login HTTP/1.1
Host: b2w-eus10.b2w.trimble.com
userName: DOMAIN\jsmith
password: <password>
```

LOGIN

RETURNS

MEANING

200 OK

A JWT with the `AccessToken` (and a `RefreshToken` to ignore).

400

A header is missing or invalid. With no headers, B2WTechSupport answers `{"Error":"Both userName and password must be specified in the request header"}`.

401

The user is not authorized.

500

The server hit an internal error. Capture the details and escalate.



This login uses a real Windows password

Never ask a customer to send their password, and never paste one into a ticket or chat. If you need to test, use an account you are allowed to use.

5 Which headers does every call need?

SHORT ANSWER

Every data call needs `Authorization: Bearer <AccessToken>` and a `DatabaseName` header naming the customer's Estimate database. Add `ClientID` and `ClientSecret` when Client ID Security is on, and `EstimateREF` on the lookups that belong to one estimate.

HEADER	WHEN	VALUE
<code>Authorization</code>	Every data call	<code>Bearer <AccessToken></code> from Login
<code>DatabaseName</code>	Every data call	The customer's Estimate database. The official collection's placeholder is <code>B2WSample</code> .
<code>ClientID</code> · <code>ClientSecret</code>	When Client ID Security is on	The values set in the API
<code>EstimateREF</code>	15 estimate-specific lookups (below)	The <code>ObjectID</code> of the estimate
<code>Content-Type</code>	POST and PUT	<code>application/json</code>

Client ID Security

Client ID Security is optional and set when the API is installed. When it is on, every call must include `ClientID` and `ClientSecret` headers that match the API's values. If they don't match, the call returns `401`, the same code as a bad token.



Cloud environments

The Cloud Management Portal lists each environment's API Client ID and an **Est API Secret**. Confirm with the team which values a customer's Estimate API expects, and treat both as credentials.

Calls that need EstimateREF

These lookups return the values that can be used on one estimate, so they need the estimate's `ObjectID` in an `EstimateREF` header:

- | | |
|---------------------------------------|--|
| ✓ <code>/Estimate/BidAs</code> | ✓ <code>/Estimate/EquipmentRateClass</code> |
| ✓ <code>/Estimate/EstimateType</code> | ✓ <code>/Estimate/EstimateStatus</code> |
| ✓ <code>/Estimate/JobCostID</code> | ✓ <code>/Estimate/LaborRateClass</code> |
| ✓ <code>/Estimate/MinorityType</code> | ✓ <code>/Estimate/UserDefinedField</code> |
| ✓ <code>/Estimate/WorkRule</code> | ✓ <code>.../Organization/{Type}/Category</code> for
Competitor, Customer, EngineerArchitect,
Manufacturer, Subcontractor, and Vendor |



"The user is not authorized for this API."

That is the 401 message B2WTechSupport returns when a data call has no valid credentials. Check the bearer token first, then the ClientID and ClientSecret if Client ID Security is on.

6

How do I set up the Estimate Postman collection?

SHORT ANSWER

Download the official EstAPI collection from the docs, import it into Postman, and fill in six collection variables. Its pre-request script logs in for you before every request, so you never copy a token by hand.

1

Download the collection

Open [EstAPI.postman_collection.json](https://b2w-eus10.b2w.trimble.com/EstAPI_B2WTechSupport/Documentation/EstAPI.postman_collection.json) (https://b2w-eus10.b2w.trimble.com/EstAPI_B2WTechSupport/Documentation/EstAPI.postman_collection.json), or use the link under **Testing Guidelines** in the docs. It has 281 requests.

2 Import it

In Postman, press `Ctrl + O` and drop the file in. The **EstAPI** collection appears.

3 Fill in the variables

Click the collection, open **Variables**, set the values below, and save.

4 Send any request

Start with **Ping**, then any GET. The collection handles login and the extra headers.

VARIABLE	WHAT GOES IN IT	EXAMPLE
BaseUrl	The Estimate API URL (the file ships with <code>http://localhost/EstAPI</code>)	<code>https://b2w-eus10.b2w.trimble.com/EstAPI_B2WTechSupport</code>
DatabaseName	The customer's Estimate database	<code>B2WSample</code> (placeholder)
UserName	Active Directory account, as <code>domain\username</code>	<code>DOMAIN\jsmith</code>
Password	That account's password	Your own value
ClientID · ClientSecret	Only when Client ID Security is on	Leave blank otherwise
Token	Set automatically by the pre-request script	Leave it



What the pre-request script does

Before each request it calls `{{BaseUrl}}/login` with your user name and password, saves the `AccessToken` as the collection's bearer token, and adds your `ClientID` and `ClientSecret` headers. Every request already sends `DatabaseName` .

Make calls

Read and filter estimate data, update records safely, and find the right endpoint.

7 How do I read, filter, and page Estimate data?

SHORT ANSWER

GET returns an object whose `Items` array holds the records, up to 100 per call. Filter, sort, and page with the same OData options as the Ops API: `$filter`, `$select`, `$orderby`, `$top`, and `$skip`.

POSTMAN

GET <code>{{BaseURL}}/Estimate?\$top=5</code>	
HEADERS	
DatabaseName	<code>{{DatabaseName}}</code>
ClientID · ClientSecret	Added by the pre-request script
AUTHORIZATION	
Bearer Token	<code>{{Token}}</code> , set by the pre-request script

POWERSHELL

POWERSHELL · CONTINUES FROM QUESTION 4

```
$headers = @{
    Authorization = "Bearer $token"
    DatabaseName  = "<Estimate database name>"
    # ClientID    = "<client ID>"          # only when Client ID Security is on
    # ClientSecret = "<client secret>"
}

# For GET, -Body becomes the query string: /Estimate?$top=5
$result = Invoke-RestMethod -Uri "$baseUrl/Estimate" -Headers $headers -Body @{
    '$top' = 5 }
$result.Items | Select-Object Number, Name, EstimateStatus
```

CURL

CURL · BASH, MACOS, GIT BASH

```
curl -s -G 'https://b2w-eus10.b2w.trimble.com/EstAPI_B2WTechSupport/Estimate' \  
  --data-urlencode '$top=5' \  
  -H 'Authorization: Bearer <AccessToken>' \  
  -H 'DatabaseName: <Estimate database name>'
```

RAW HTTP

HTTP REQUEST

```
GET /EstAPI_B2WTechSupport/Estimate?$top=5 HTTP/1.1  
Host: b2w-eus10.b2w.trimble.com  
Authorization: Bearer <AccessToken>  
DatabaseName: <Estimate database name>
```

RESPONSE · 200 OK (SHORTENED CATALOG EXAMPLE)

```
{  
  "Items": [  
    {  
      "AntiTamperToken": "string",  
      "ObjectID": "32b66b04-0fdc-409f-8e10-aa6f5cf0fc6e",  
      "Number": "0006",  
      "Name": "Elm Street Bridge Improvements, Manchester",  
      "EstimateStatus": "Signed",  
      "EstimateType": "Public",  
      "BidAs": "General Contractor",  
      "BidDate": "2018-12-28T13:00:00",  
      "PrimaryCustomerName": "City Of Manchester",  
      "EstimatorName": "Paul Smith"  
    }  
  ]  
}
```

Filter examples

POSTMAN URLS

One estimate by number

```
{{BaseURL}}/Estimate?$filter=Number eq '0006'
```

A few fields, sorted

```
{{BaseURL}}/Estimate?$select=ObjectID,Number,Name&$orderby=Number
```

From the official collection: GUIDs go without quotes

```
{{BaseURL}}/Estimate/MinorityParticipationRequirement?$filter=EstimateREF eq  
02E2BD02-B667-4478-A1C6-76DEDFB8958F
```



Exactly 100 records? Ask for the next page.

The page size is 100 by default. Add `$top=100&$skip=100`, then `$skip=200`, until a page has fewer than 100 records.

8

How do I create or update Estimate records?

SHORT ANSWER

POST creates and **PUT** updates. To update, GET the record, change only the fields you need, and PUT the entire record back with its `AntiTamperToken` unchanged.

Why the AntiTamperToken matters

Every GET returns an `AntiTamperToken`. A PUT must send it back with the same value. It protects properties that are returned for information only, such as `ObjectID`, from being changed. The docs also warn that a PUT with missing fields can delete values from the fields you left out, which is why you always send the whole record.

POWERSHELL · GET, CHANGE, PUT

1. GET the record you want to change

```
$result = Invoke-RestMethod -Uri "$baseUrl/Estimate" -Headers $headers -Body @{'$filter' = "Number eq '0006'" }  
$estimate = $result.Items | Select-Object -First 1
```

2. Change only what you need. Leave AntiTamperToken and ObjectID as they are.

```
$estimate.BidLocation = "Manchester, NH"
```

3. PUT the whole record back

```
Invoke-RestMethod -Method Put -Uri "$baseUrl/Estimate" -Headers $headers -Body  
($estimate | ConvertTo-Json -Depth 10) -ContentType "application/json"
```

PUT RETURNS

MEANING

200 OK

The record was updated.

400

The body doesn't contain the record.

403

The operation is not allowed, for example one of the unsupported changes in question 1.

404

The record wasn't found.

422

The body isn't a valid record. Compare it with a fresh GET or with `/schema`.



Practice in B2WTechSupport only

POST and PUT change real estimates. Never test them in a customer's environment unless the customer has asked for the change.

Which endpoints are available?

SHORT ANSWER

The B2WTechSupport catalog lists 227 operations. Most areas support GET, POST, and PUT plus a `/schema` call; some are read-only. Search below, then check Swagger for the fields.

TOOL Endpoint explorer

Showing 80 of 80 endpoint groups · 227 operations in all

/Login

GET

userName + password headers → AccessToken

/Ping/{input}

GET

No login needed

/Estimate

GET

POST

PUT

+ /schema

/BidSchedule

GET

POST

PUT

+ /schema

/Estimate/MinorityParticipationRequirement

GET

POST

PUT

+ /schema

/Estimate/BidAs

GET

EstimateREF

/Estimate/EquipmentRateClass

GET

EstimateREF

/Estimate/EstimateType

GET

EstimateREF

/Estimate/EstimateStatus

GET

EstimateREF

/Estimate/JobCostID

GET

EstimateREF

/Estimate/LaborRateClass

GET

EstimateREF

/Estimate/MinorityType

GET

EstimateREF

/Estimate/UserDefinedField

GET

EstimateREF

/Estimate/WorkRule

GET

EstimateREF

/Estimate/IndirectItem

/Estimate/PayItem

GET

/Estimate/WBSLevel

GET

/Estimate/TaskComponent

GET

/Estimate/LaborComponent

GET

/Estimate/CrewComponent

GET

/Resource/EquipmentBurden

GET POST PUT + /schema

/Resource/EquipmentRateClass

GET + /schema

/Resource/EquipmentType

GET POST PUT + /schema

/Resource/LaborBurden

GET POST PUT + /schema

/Resource/LaborerBurden

GET POST PUT + /schema

/Resource/LaborRateClassBurden

GET + /schema

/Resource/Material

GET POST PUT + /schema

GET

/Estimate/WBSApportioning

GET

/Estimate/MaterialComponent

GET

/Estimate/EquipmentComponent

GET

/Resource/Equipment

GET PUT + /schema

/Resource/EquipmentBurdenInstance

GET POST PUT + /schema

/Resource/EquipmentRateClassBurden

GET + /schema

/Resource/JobCostID

GET POST PUT + /schema

/Resource/Laborer

GET PUT + /schema

/Resource/LaborRateClass

GET + /schema

/Resource/LaborType

GET POST PUT + /schema

/Resource/MinorityType

GET POST PUT + /schema

/Resource/Miscellaneous

GET **POST** **PUT** + /schema

/Resource/Organization/Competitor

GET **POST** **PUT** + /schema

/Resource/Organization/Contact

GET **POST** **PUT** + /schema

/Resource/Organization/Customer/Category

GET EstimateREF

/Resource/Organization/EngineerArchitect/Category

GET EstimateREF

/Resource/Organization/Manufacturer/Category

GET EstimateREF

/Resource/Organization/OrganizationMaterialCategory

GET **POST** + /schema

/Resource/Organization/OrganizationMinerityType

GET **POST** **PUT** + /schema

/Resource/Organization/OrganizationWorkType

GET **POST** + /schema

/Resource/Organization/Subcontractor/Category

GET EstimateREF

/Resource/UserDefinedField

GET **POST** **PUT** + /schema

/Resource/Organization/Competitor/Category

GET EstimateREF

/Resource/Organization/Customer

GET **POST** **PUT** + /schema

/Resource/Organization/EngineerArchitect

GET **POST** **PUT** + /schema

/Resource/Organization/Manufacturer

GET **POST** **PUT** + /schema

/Resource/Organization/ManufacturerMaterial

GET **POST** **PUT** + /schema

/Resource/Organization/OrganizationMaterialSubcategory

GET **POST** + /schema

/Resource/Organization/OrganizationWorkSubtype

GET **POST** + /schema

/Resource/Organization/Subcontractor

GET **POST** **PUT** + /schema

/Resource/Organization/Vendor

GET **POST** **PUT** + /schema

/Resource/Organization/Vendor/Category

GET **EstimateREF**

/Resource/Organization/VendorMaterial

GET **POST** **PUT** + /schema

/Resource/Category/BidAs

GET **POST** **PUT** + /schema

/Resource/Category/CompetitorCategory

GET **POST** **PUT** + /schema

/Resource/Category/CustomerCategory

GET **POST** **PUT** + /schema

/Resource/Category/EngineerArchitectCategory

GET **POST** **PUT** + /schema

/Resource/Category/EquipmentBurdenCategory

GET **POST** **PUT** + /schema

/Resource/Category/EquipmentCategory

GET **POST** **PUT** + /schema

/Resource/Category/EstimateStatus

GET **POST** **PUT** + /schema

/Resource/Category/EstimateType

GET **POST** **PUT** + /schema

/Resource/Category/LaborBurdenCategory

GET **POST** **PUT** + /schema

/Resource/Category/LaborCategory

GET **POST** **PUT** + /schema

/Resource/Category/ManufacturerCategory

GET **POST** **PUT** + /schema

/Resource/Category/MaterialCategory

GET **POST** **PUT** + /schema

/Resource/Category/SubcontractorCategory

GET **POST** **PUT** + /schema

/Resource/Category/Tag

GET **POST** **PUT** + /schema

/Resource/Category/VendorCategory

GET **POST** **PUT** + /schema

/Resource/Category/WorkType

GET **POST** **PUT** + /schema

/Resource/Subcategory/MaterialSubcategory

GET **POST** **PUT** + /schema

/Resource/Subcategory/TagValue

GET **POST** **PUT** + /schema

/Resource/Subcategory/WorkSubtype

/Options/MaterialSettings

GET **POST** **PUT** + /schema

GET **PUT** + /schema

GET read **POST** create **PUT** update /schema field definitions **EstimateREF** needs that header

Each card's **Build** button opens that endpoint in the [request builder](#), which adds the `DatabaseName` and `EstimateREF` headers for you and writes the request for Postman, PowerShell, cURL, or raw HTTP.

Troubleshoot

The basic tests from the Estimate API docs, and fixes for the errors you will see most.

10 What does this error mean?

SHORT ANSWER

Paste the error into the decoder: a status line, a response body, a Postman or PowerShell error, or the request URL. It names the likely cause and links to the fix.

It knows the Estimate API's own messages, such as "The user is not authorized for this API." and "Operation is not allowed". It also reads SQL Server errors like "Login failed for user 'NT AUTHORITY\NETWORK SERVICE'", and checks pasted request headers for a missing `DatabaseName`, `EstimateREF`, or `Bearer`. Decoding runs entirely in your browser.

11 How do I troubleshoot the Estimate API?

SHORT ANSWER

Run the two basic tests in order: an app-up test with `/Ping/hello`, then a login test. Don't go further until both pass. Then check the data call's headers.

01

App-up test

`GET /Ping/hello` should return 200 and `(server) hello`. If it doesn't, check that IIS is running, that the **EstAPI** application pool is running, and that the URL is correct. The environment checker in question 2 runs this test for you.

02

Login test

`GET /Login` with `userName` and `password` headers should return 200 and an `AccessToken`. Any other code points at the account (question 4).

03

Data call headers

Check `Authorization: Bearer`, `DatabaseName`, the ClientID and ClientSecret if Client ID Security is on, and `EstimateREF` for estimate-specific lookups.

Common errors

400 Login: "Both userName and password must be specified in the request header"

LIKELY CAUSE

One or both headers are missing, or they were sent in the URL or body.

FIX

Send both `userName` (DOMAIN\user) and `password` as headers.

401 Login: user is not authorized

LIKELY CAUSE

The domain controller rejected the account, or the account has no access to the Estimate data.

FIX

Confirm the account name format and password, and that the user can access Estimate.

401 Data call: "The user is not authorized for this API."

LIKELY CAUSE

The bearer token is missing, invalid, or expired, or the ClientID or ClientSecret is wrong when Client ID Security is on.

FIX

Log in again for a fresh token and check the Authorization header. Then check the ClientID and ClientSecret headers.

Wrong data **Empty results, or data from the wrong company**

LIKELY CAUSE

The `DatabaseName` header is missing or names the wrong database.

FIX

Confirm the customer's Estimate database name and resend.

SQL **"Login failed for user 'NT AUTHORITY\NETWORK SERVICE'"**

LIKELY CAUSE

The API runs as the Network Service account, which needs db_owner access to the Estimate database (the docs' Post-Installation Step).

FIX

On-premises: grant that access using the ConfigureDB commands. Cloud: escalate to the team that hosts the environment.

403 **PUT: "Operation is not allowed"**

LIKELY CAUSE

The change is one the API doesn't support, such as cost structure, container components, or organizations in an estimate.

FIX

Make that change in Estimate itself. There is no API route for it.

422 **POST or PUT is rejected**

LIKELY CAUSE

The body isn't a valid record, or a PUT left out fields or changed the AntiTamperToken.

FIX

GET the record again and PUT the whole record back with its AntiTamperToken unchanged.



Built for the B2W Support Team. The Ops API guide comes from the Ops API Support Training and its walkthrough notes; the Estimate and Management Reporting guides come from their API documentation and official Postman collections. Endpoint lists, sample responses, and live results come from the B2WTechSupport environment, checked October 2, 2026. Credentials and tokens in screenshots are hidden.



GetBirned on GitHub