

Рис.1. Схема сети.

# Сведения о конфигурации устройств

Устр-во	Интерфейс	IP-адрес	Маска подсети	Шлюз
R1	F0/0	192.168.5.1	255.255.255.0	-
	F0/1	172.16.5.1	255.255.255.0	-
R0	F0/1	172.16.5.2	255.255.255.0	-
	F0/0	172.17.5.1	255.255.255.0	-
	E0/1/0	10.0.1.2	255.255.255.0	-
PC 0	NIC	192.168.5.2	255.255.255.0	192.168.5.1
PC 1	NIC	192.168.5.3	255.255.255.0	192.168.5.1
PC 2	NIC	172.17.5.254	255.255.255.0	172.17.5.1
CorpWeb	NIC	172.17.5.252	255.255.255.0	172.17.5.1
CorpDNS	NIC	172.17.2.253	255.255.255.0	172.17.5.1
InetUsr	NIC	192.168.1.3	255.255.255.0	192.168.1.1
InetSrv	NIC	192.168.1.2	255.255.255.0	192.168.1.1

# Сведения о настроенных NAT

Уст	Инте	Интер	Команды конфигурирования NAT
р-во	p-	-фейс	(включая пул и ACL)
	фейс	outsid	

	inside	e		
R1	F0/0	F0/1	ip dhcp excluded-address 192.168.5.1  ip dhcp pool LAN_A_DHCP  network 192.168.5.0 255.255.255.0  default-router 192.168.5.1  dns-server 172.17.5.253  ip nat pool LAN_A_Translate 172.16.5.100 172.16.5.200 netmask 25:  ip nat inside source list LAN_A_SETUP pool LAN_A_Translate  ip classless  ip route 0.0.0.0 0.0.0:0 FastEthernet0/1  ip access-list extended LAN_A_SETUP  permit ip 192.168.5.0 0.0.0.255 any	5.255.28
R0	F0/1,	Eth0/1		
	F0/0	/0	ip nat inside source list LAN_B_SETUP interface Ethernet0/1/0 over ip nat inside source list corp_nat_setup interface Ethernet0/1/0 ip nat inside source static 172.17.5.252 10.0.1.103 ip nat inside source static 172.17.5.253 10.0.1.104 ip classless ip route 0.0.0.0 0.0.0.0 Ethernet0/1/0  ip access-list extended corp_nat_setup permit ip 172.16.5.0 0.0.0.255 any ip access-list extended LAN_B_SETUP permit ip 172.17.5.0 0.0.0.255 any	

#### Анализ пакетов в режиме симуляции

PC0 - www.corp.com

На устройстве	Source IP	Destination IP	Тип NAT
PC0 - out	192.168.5.2	172.17.5.252	
R1 - in	192.168.5.2	172.17.5.252	динамический
R1 - out	172.16.5.100	172.17.5.252	
R0 - in	172.16.5.100	172.17.5.252	
R0 - out	172.16.5.100	172.17.5.252	
CorpWeb - in	172.16.5.100	172.17.5.252	
CorpWeb - out	172.17.5.252	172.16.2.100	
R0 - in	172.17.5.252	172.16.2.100	
R0 - out	172.17.5.252	172.16.2.100	динамический
R1 - in	172.17.5.252	172.16.2.100	
R1 - out	172.17.5.252	192.168.5.2	
P0 - in	172.17.5.252	192.168.5.2	

## PC0 - internet.com

На устройстве	Source IP	Destination IP	Тип NAT
PC0 - out	192.168.5.2	10.0.2.99	
R1 - in	192.168.5.2	10.0.2.99	динамический
R1 - out	172.16.5.100	10.0.2.99	
R0 - in	172.16.5.100	10.0.2.99	перегруженный
R0 - out	10.0.1.2	10.0.2.99	
ISP - in	10.0.1.2	10.0.2.99	
ISP - out	10.0.1.2	10.0.2.99	
InetSrv - in	10.0.2.99	192.168.1.2	
InetSrv - out	192.168.1.2	10.0.1.2	
ISP - in	10.0.2.99	10.0.1.2	
ISP - out	10.0.2.99	10.0.1.2	
R0 - in	10.0.2.99	10.0.1.2	перегруженный
R0 - out	10.0.2.99	172.16.5.100	
R1 - in	10.0.2.99	172.16.5.100	динамический
R1 - out	10.0.2.99	192.168.5.2	
PC0 - in	10.0.2.99	192.168.5.2	

## PC2 - www.corp.com

На устройстве	Source IP	Destination IP	Тип NAT
PC2 - out	172.17.5.254	172.17.5.252	
CorpWeb - in	172.17.5.254	172.17.5.252	
CorpWeb - out	172.17.5.252	172.17.5.254	
PC2 - in	172.17.5.252	172.17.5.254	

#### PC2 – internet.com

На устройстве	Source IP	Destination IP	Тип NAT
PC2 - out	172.17.5.254	10.0.2.99	
R0 - in	172.17.5.254	10.0.2.99	перегруженный
R0 - out	10.0.1.2	10.0.2.99	
ISP - in	10.0.1.2	10.0.2.99	
ISP - out	10.0.1.2	10.0.2.99	
InetSrv - in	10.0.1.2	192.168.1.2	
InetSrv - out	192.168.1.2	10.0.1.2	
ISP - in	10.0.2.99	10.0.1.2	
ISP - out	10.0.2.99	10.0.1.2	
R0 - in	10.0.2.99	10.0.1.2	перегруженный
R0 - out	10.0.2.99	172.17.5.254	
PC2 - in	10.0.2.99	172.17.5.254	

# $InetUsr-\underline{www.corp.com}$

На устройстве	Source IP	Destination IP	Тип NAT
InetUsr - out	192.168.1.3	10.0.1.103	
ISP - in	10.0.2.2	10.0.1.103	
ISP - out	10.0.2.2	10.0.1.103	
R0 - in	10.0.2.2	10.0.1.103	перегруженный
R0 - out	10.0.2.2	172.17.5.252	
CorpWeb - in	10.0.2.2	172.17.5.252	
CorpWeb - out	172.17.5.252	10.0.2.2	
R0 - in	172.17.5.252	10.0.2.2	перегруженный
R0 - out	10.0.1.103	10.0.2.2	
ISP - in	10.0.1.103	10.0.2.2	
ISP - out	10.0.1.103	10.0.2.2	
InetUsr - in	10.0.1.103	192.168.1.3	

# InetUsr – internet.com

На устройстве	Source IP	Destination IP	Тип NAT
InetUsr - out	192.168.1.3	192.168.1.2	
InetSrv - in	192.168.1.3	192.168.1.2	
InetSrv - out	192.168.1.2	192.168.1.3	
InetUsr - in	192.168.1.2	192.168.1.3	