Discord Setup Guide

Updated for U5 | Installation, authentication, and request/response communication

1. What this integration does

A Discord member sends a message to the bot. The locally or server-hosted Discord Bridge forwards it securely to the selected AI Assistant through the AI Assistant backend. The assistant response returns through the bridge to Discord. This is request/response communication in both directions, not automatic posting of every dashboard chat into Discord.

Discord Integration requires an active AI Assistant Pro entitlement. The bridge process must stay running on an internet-connected computer or server.

2. Before you begin

• Have a Discord account, a server where you can install applications, and access to the Discord Developer Portal.

• Have a Pro account on AI Assistant and an existing assistant to connect.

• Install Python and have a terminal available. The bridge runs separately from the AI Assistant web backend.

3. Create and invite the Discord bot

• At https://discord.com/developers/applications create an application; open Bot and obtain the Bot Token. Keep it private.

• In Bot > Privileged Gateway Intents, enable Message Content Intent and save.

• Use Installation / OAuth2 to add the bot to the correct server. Grant View Channels, Send Messages and Read Message History; for threads, allow Send Messages in Threads.

• Verify the bot appears in your server. Being present does not mean its bridge is running yet.

4. Connect from the AI Assistant dashboard

• Open your selected assistant’s Discord Setup page in AI Assistant (Pro).

• Create or download the Discord integration package using the page’s instructions. If the download accepts your Discord Bot Token, enter it only on the trusted AI Assistant page.

• The integration credential is specific to this Discord connection. Do not replace it with an API Access key or an OpenAI API key.

• Keep the generated integration secret private. If compromised, revoke the integration and issue a new one.

5. Configure the bridge

Keep the downloaded bridge.py, requirements.txt and configuration together. Use the supplied .env file if preconfigured; otherwise create a .env file in the bridge folder with these settings:

DISCORD_TOKEN=<Discord Bot Token>

DJANGO_API_TOKEN=<Discord integration secret starting dsc_>

DJANGO_BOT_ID=<selected AI Assistant bot ID>

DJANGO_BACKEND=https://www.myaiassistantapp.se

Use the actual production backend URL provided by the downloaded package. The backend must be HTTPS. Never use localhost for a public deployment or copy production tokens into GitHub.

The bridge authentication secret and the separate U5 API Access credential serve different purposes. Heroku backend service keys remain in Heroku Config Vars; end users do not need those keys.

6. Install and run

In a terminal opened in the extracted bridge folder:

python -m venv venv

Windows PowerShell: .\venv\Scripts\Activate.ps1

macOS/Linux: source venv/bin/activate

pip install -r requirements.txt

python bridge.py

A successful connection may print: Discord bridge connected. Keep the process running. For 24/7 operation, host it as a persistent service with secure environment variables and process restarts.

7. Send and receive messages

• In a channel the bot can read, type !ping. Expected response: Pong! This only checks Discord connectivity.

• Type !ask What is 2 + 2? to send a question to the selected AI Assistant and receive its response in the same Discord conversation.

• You may also directly mention the bot followed by a question, or send it a DM. Do not expect ordinary unaddressed channel messages to trigger AI responses.

• AI-generated replies depend on the assistant configuration, account access, knowledge base and backend availability.

8. Troubleshooting and security

• No reply to !ping: verify bridge process, bot token, Message Content Intent, bot visibility and send permissions.

• Pong works but !ask fails: verify DJANGO_BACKEND, the assistant ID, active Pro entitlement and the dedicated Discord integration credential.

• 404 from backend: verify the deployed U5 backend and correct endpoint. AI service errors can indicate unavailable backend AI credentials or provider access.

• Do not share .env files, bot tokens, Discord integration secrets, OpenAI keys or Heroku Config Vars.

• Stop bridge with Ctrl+C; revoke compromised integrations from AI Assistant and rotate the Discord Bot Token in Discord if necessary.