Discord Bridge - Commands Guide

AI Assistant | Discord Bridge | U5 release candidate | October 2026

Quick reference

```
!ping
```

Checks that the Discord bot is connected. Replies with Pong. Does not call the AI service.

```
!ask What can you help with?
```

Sends a question to the selected AI Assistant. The question must not be empty.

```
@YourBot Explain this topic
```

Directly mention the bot and add a question. A mention without a question prompts for a question.

```
DM: What can you help with?
```

Send a direct message to the bot. DM text is forwarded to the assistant, except the !ping connectivity command.

Where commands work

!ask and direct mentions work in channels where the bot can view and send messages. Direct messages work when available. In ordinary server messages without !ask or a direct mention, the bridge does not respond.

Grant only View Channels, Send Messages and, where required, Send Messages in Threads. Message Content Intent must be enabled in the Discord Developer Portal. Do not grant Administrator.

Conversation context

A channel or thread keeps its own conversation. Everyone in the same channel shares that conversation and may receive information from the selected assistant Knowledge Base. Each DM has its own context. Context is held by the running bridge process; restarting the process starts fresh conversations.

The bridge uses an assistant-scoped Discord credential, separate from the customer API key. Another integration or private web conversation cannot be reused as a Discord conversation.

Error messages and what to do

Invalid or revoked access (401): ask the owner to revoke/reconnect the integration and download a new bridge ZIP.

Pro or usage restriction (403): check that the account still has active Pro and available usage quota.

Assistant unavailable (404): check the assistant ownership and integration settings.

Too many requests (429): wait before trying again.

Timeout or service unavailable: check backend reachability. The bridge does not automatically retry timed-out AI requests; a timeout does not prove the request was cancelled.

Unable to send Discord reply: check channel permissions, Discord connectivity and whether the bot is still running.

Security and limits

Do not share .env or discord_bridge.zip. Do not paste credentials into chat, screenshots, issues or GitHub. Revoke compromised integrations immediately. Run one bridge process per installation to avoid inconsistent in-memory conversation history.

Long AI replies are automatically split to respect Discord message length. Automatic retries and idempotent chat submissions are not implemented.

Release note

This guide reflects the U5 release-branch implementation reviewed on 14 October 2026. U5 has not yet been deployed to production; real Discord end-to-end tests and release checks are still required.